

Infoprint Manager



# Reference



Infoprint Manager



# Reference

**Note**

Before using this information and the product it supports, be sure to read the general information in "Notices" on page 727.

**Fourth Edition (June 2000)**

This edition of *Infoprint Manager: Reference* applies to Infoprint Manager for AIX, Version 3 Release 2 Modification 0, Infoprint Manager for Windows NT and Windows 2000, Version 1 Release 1 Modification 0, and to all subsequent releases and modifications until otherwise indicated in new editions or technical newsletters. Be sure to use the correct edition for the level of the product. Because this is a minor revision, the revision bars from the previous edition are included for retrievability.

Order publications through your IBM representative or the IBM branch office serving your locality. Publications are not stocked at the address given below.

IBM Printing Systems welcomes your comments. For your convenience, a form for reader's comments is provided at the back of this publication. If the form has been removed, you may send your comments to the following address:

INFORMATION DEVELOPMENT  
IBM PRINTING SYSTEMS  
DEPARTMENT H7FE BUILDING 003G  
PO BOX 1900  
BOULDER CO 80301-9191

If you prefer to send comments electronically, use one of the following methods:

- Internet/Email: [printpub@us.ibm.com](mailto:printpub@us.ibm.com)
- Fax: 1-800-524-1519 within U.S. or 1-303-924-6873 outside U.S.

**Internet**

Visit our home page at <http://www.ibm.com/printers>

When you send information to IBM, you grant IBM a nonexclusive right to use or distribute the information in any way it believes appropriate without incurring any obligation to you.

© Copyright International Business Machines Corporation 1998, 2000. All rights reserved.

US Government Users Restricted Rights – Use, duplication or disclosure restricted by GSA ADP Schedule Contract with IBM Corp.

# Contents

<b>Figures</b> . . . . .	xxvii
<b>Tables</b> . . . . .	xxix
<b>About This Publication.</b> . . . . .	xxxi
Who Should Use This Publication . . . . .	xxxi
About the Documentation for Infoprint . . . . .	xxxi
The Infoprint Publication Library . . . . .	xxxi
Other Publications Related to Infoprint . . . . .	xxxii
Manual (man) Pages for Infoprint Commands, Utilities, and Transforms . . . . .	xxxiii
Manual (man) Pages for Infoprint Attributes. . . . .	xxxv
Infoprint Online Message Catalog . . . . .	xxxv
readme Files. . . . .	xxxvi
The Organization of This Publication . . . . .	xxxvii
Conventions Used in This Publication . . . . .	xxxviii
Highlighting . . . . .	xxxviii
Infoprint Command Notation . . . . .	xxxix
<b>Chapter 1. Introduction.</b> . . . . .	1
Reference Table for Path Names. . . . .	1
Objects . . . . .	3
Object Classes . . . . .	3
Object Name Restrictions . . . . .	4
Object Attributes . . . . .	4
Commands. . . . .	7
Flags, Command Attributes, and Arguments. . . . .	8
Command Output: Headings and Style . . . . .	9
Tips for Using Commands . . . . .	9
Administrative Utilities . . . . .	11
Daemon Utilities for Infoprint Manager for AIX . . . . .	12
Transform Commands . . . . .	12
Environment Variables for Infoprint Manager for AIX . . . . .	12
Windows Services for Infoprint Manager for Windows NT and Windows 2000 . . . . .	12
<b>Chapter 2. Infoprint Commands</b> . . . . .	13
lprfp Command: Submits Remote Jobs in Infoprint Manager for AIX . . . . .	15
Syntax . . . . .	15
Description . . . . .	15
Flags . . . . .	15
Arguments . . . . .	15
Examples . . . . .	16
Files. . . . .	16
mkfntmap Command: Maps PostScript Fonts . . . . .	17
Syntax . . . . .	17
Description . . . . .	17
Arguments . . . . .	17
Examples . . . . .	18
pdaccount Command: Collect Accounting Information for a Specific Time Period . . . . .	19
Syntax . . . . .	19
Description . . . . .	19
Flags . . . . .	19
Argument . . . . .	20
Examples . . . . .	21

pdclean Command: Removes All Jobs from the Specified Object . . . . .	22
Syntax . . . . .	22
Description . . . . .	22
Flags . . . . .	22
Command Attributes . . . . .	23
Arguments . . . . .	23
Examples . . . . .	24
Suggested Reading . . . . .	24
pdcreate Command: Creates Infoprint Objects . . . . .	25
Syntax . . . . .	25
Description . . . . .	25
Flags . . . . .	26
Command Attributes . . . . .	27
Arguments . . . . .	27
Examples . . . . .	28
Suggested Reading in Hardcopy . . . . .	29
Suggested Reading Online . . . . .	29
pddelete Command: Deletes Infoprint Objects . . . . .	30
Syntax . . . . .	30
Description . . . . .	30
Flags . . . . .	30
Command Attributes . . . . .	31
Arguments . . . . .	31
Examples . . . . .	32
Suggested Reading . . . . .	33
pddisable Command: Stops Destinations from Accepting Jobs and Logs from Logging . . . . .	34
Syntax . . . . .	34
Description . . . . .	34
Flags . . . . .	34
Command Attributes . . . . .	35
Arguments . . . . .	35
Examples . . . . .	36
Suggested Reading . . . . .	36
pdenable Command: Enables Destinations to Accept Jobs and Logs to Log	37
Syntax . . . . .	37
Description . . . . .	37
Flags . . . . .	37
Command Attributes . . . . .	38
Arguments . . . . .	38
Examples . . . . .	39
Suggested Reading . . . . .	39
pdls Command: Lists Selected Attribute Values . . . . .	40
Syntax . . . . .	40
Description . . . . .	40
Flags . . . . .	41
Command Attributes . . . . .	42
Arguments . . . . .	45
Examples . . . . .	46
Suggested Reading in Hardcopy . . . . .	49
Suggested Reading Online for Infoprint Manager for AIX . . . . .	49
pdmod Command: Modifies Attributes of Submitted Print Jobs . . . . .	51
Syntax . . . . .	51
Description . . . . .	51
Flags . . . . .	52
Command Attributes . . . . .	53

Arguments . . . . .	54
Examples . . . . .	54
Suggested Reading in Hardcopy . . . . .	54
Suggested Reading Online . . . . .	55
pdpause Command: Pauses Jobs, Actual Destinations, Servers, or Queues	56
Syntax . . . . .	56
Description . . . . .	56
Flags . . . . .	57
Command Attributes . . . . .	58
Arguments . . . . .	60
Examples . . . . .	62
Suggested Reading . . . . .	62
pdpr Command: Submits Jobs . . . . .	63
Syntax . . . . .	63
Description . . . . .	63
Flags . . . . .	64
Command Attributes . . . . .	66
Job and Document Attributes Used with the Command . . . . .	67
Arguments . . . . .	67
Examples for Infoprint Manager for AIX . . . . .	68
Examples for Infoprint Manager for AIX and Infoprint Manager for Windows NT and Windows 2000 . . . . .	70
Suggested Reading in Hardcopy . . . . .	71
Suggested Reading Online for Infoprint Manager for AIX . . . . .	71
pdpromote Command: Advances a Job to the Top of a Queue . . . . .	72
Syntax . . . . .	72
Description . . . . .	72
Flags . . . . .	72
Command Attributes . . . . .	73
Arguments . . . . .	73
Example . . . . .	73
Suggested Reading . . . . .	73
pdq Command: Queries Job Status . . . . .	74
Syntax . . . . .	74
Description . . . . .	74
Flags . . . . .	74
Command Attributes . . . . .	76
Arguments . . . . .	77
Examples . . . . .	77
Suggested Reading in Hardcopy . . . . .	78
Suggested Reading Online . . . . .	78
pdreorder Command: Reassigns Jobs . . . . .	79
Syntax . . . . .	79
Description . . . . .	79
Flags . . . . .	79
Command Attributes . . . . .	80
Arguments . . . . .	80
Examples . . . . .	80
pdresubmit Command: Resubmits Jobs . . . . .	81
Syntax . . . . .	81
Description . . . . .	81
Flags . . . . .	81
Command Attributes . . . . .	82
Arguments . . . . .	83
Examples . . . . .	84
Suggested Reading . . . . .	84

pdresume Command: Enables Paused Objects to Resume Operation. . . . .	85
Syntax . . . . .	85
Description . . . . .	85
Flags . . . . .	85
Command Attributes . . . . .	86
Arguments . . . . .	86
Examples . . . . .	87
Suggested Reading . . . . .	87
pdrm Command: Removes Jobs . . . . .	88
Syntax . . . . .	88
Description . . . . .	88
Flags . . . . .	88
Command Attributes . . . . .	89
Arguments . . . . .	89
Examples . . . . .	89
pdset Command: Defines Attribute Values . . . . .	91
Syntax . . . . .	91
Description . . . . .	91
Flags . . . . .	92
Command Attributes . . . . .	93
Arguments . . . . .	94
Examples . . . . .	94
Suggested Reading in Hardcopy . . . . .	95
Suggested Reading Online for Infoprint Manager for AIX . . . . .	95
pdshutdown Command: Stops Servers or Actual Destinations. . . . .	96
Syntax . . . . .	96
Description . . . . .	96
Flags . . . . .	97
Command Attributes . . . . .	98
Argument . . . . .	99
Examples . . . . .	99
Suggested Reading . . . . .	99
pdspace Command: Backspaces or Forward Spaces a Printer . . . . .	100
Syntax . . . . .	100
Description . . . . .	100
Flags . . . . .	101
Command Attributes . . . . .	101
Arguments . . . . .	102
Examples . . . . .	102
<b>Chapter 3. The -o Flag for AIX Print Commands . . . . .</b>	<b>103</b>
Syntax . . . . .	103
Description . . . . .	103
Limitations . . . . .	103
Flag . . . . .	104
Specifying -o Attribute-Value Pairs . . . . .	104
-o Attribute-Value Pairs . . . . .	105
-o Keywords and Values for Specific Data Types . . . . .	117
Examples . . . . .	123
<b>Chapter 4. Infoprint Administrative Utilities . . . . .</b>	<b>125</b>
adminGUI Utility: Opens the Print Administration Window of the Basic Infoprint Administrator's GUI in Infoprint Manager for AIX . . . . .	128
Syntax . . . . .	128
Description . . . . .	128
Flags . . . . .	128



Arguments . . . . .	128
Examples . . . . .	128
afpsplit Utility: Extracts Pages from a MO:DCA-P File . . . . .	129
Syntax . . . . .	129
Description . . . . .	129
Flags . . . . .	129
Arguments . . . . .	129
Example . . . . .	129
ainupod1 Utility: Generates Accounting Information by User . . . . .	130
Syntax . . . . .	130
Description . . . . .	130
Example . . . . .	130
Suggested Reading. . . . .	130
ainupod2 Utility: Generates Accounting Information by Job . . . . .	131
Syntax . . . . .	131
Description . . . . .	131
Example . . . . .	131
Suggested Reading. . . . .	131
ainupod3 Utility: Generates Accounting Information for a User . . . . .	132
Syntax . . . . .	132
Description . . . . .	132
Example . . . . .	132
Suggested Reading. . . . .	132
ainurpt1 Utility: Generates Accounting Information by Actual Destination . . . . .	134
Syntax . . . . .	134
Description . . . . .	134
Example . . . . .	134
Suggested Reading. . . . .	134
ainurpt2 Utility: Generates Accounting Information by User . . . . .	135
Syntax . . . . .	135
Description . . . . .	135
Example . . . . .	135
Suggested Reading. . . . .	135
ainurpt3 Utility: Generates Accounting Information for a User . . . . .	136
Syntax . . . . .	136
Description . . . . .	136
Example . . . . .	136
Suggested Reading. . . . .	136
ainurpt4 Utility: Generates Audit Information by Destination . . . . .	138
Syntax . . . . .	138
Description . . . . .	138
Example . . . . .	138
Suggested Reading. . . . .	138
ainurpt5 Utility: Generates Audit Information by User . . . . .	139
Syntax . . . . .	139
Description . . . . .	139
Example . . . . .	139
Suggested Reading. . . . .	139
ainurpt6 Utility: Generates Audit Information for a User. . . . .	140
Syntax . . . . .	140
Description . . . . .	140
Example . . . . .	140
Suggested Reading. . . . .	140
cfu Utility: Displays and Builds Coded Fonts in Infoprint Manager for AIX . . . . .	141
Syntax . . . . .	141
Description . . . . .	141

Flags . . . . .	141
Build File Format. . . . .	141
Arguments . . . . .	142
Examples . . . . .	142
Suggested Reading. . . . .	142
cmt Utility: Builds Color Mapping Table Source and Object Files in Infoprint Manager for AIX . . . . .	143
Syntax . . . . .	143
Description . . . . .	143
Flags . . . . .	143
Color Mapping Table Source File . . . . .	143
ipguiadv, ipguibasic, and ipguidist Utilities: Start the Infoprint Manager Operations GUI . . . . .	145
Syntax . . . . .	145
Description . . . . .	145
Example . . . . .	145
ipguiadvadm, ipguibasicadm, and ipguidistadm Utilities: Start the Infoprint Manager Administration GUI. . . . .	146
Syntax . . . . .	146
Description . . . . .	146
Example . . . . .	146
jsmigr Utility: Migrates PSF for AIX Job Scripts in Infoprint Manager for AIX Syntax . . . . .	148
Description . . . . .	148
Arguments . . . . .	149
Examples . . . . .	149
notification client . . . . .	150
opergui Utility: Opens the Print Management Window of the Basic Infoprint Administrator's GUI in Infoprint Manager for AIX . . . . .	151
Syntax . . . . .	151
Description . . . . .	151
Flags . . . . .	151
Arguments . . . . .	151
Examples . . . . .	151
pdadmin Utility: Opens the Servers Window of the Advanced Infoprint Administrator's GUI in Infoprint Manager for AIX . . . . .	152
Syntax . . . . .	152
Description . . . . .	152
Examples . . . . .	152
pdcrcls Utility: Creates Directories for DCE in Infoprint Manager for AIX . . . . .	153
Syntax . . . . .	153
Description . . . . .	153
Example . . . . .	153
pdcrdflt Utility: Creates Default Auxiliary Sheets, Media, and Queue in Infoprint Manager for AIX . . . . .	154
Syntax . . . . .	154
Description . . . . .	154
Flags . . . . .	154
Arguments . . . . .	155
Examples . . . . .	155
pdcrmed Utility: Creates Commonly Used Media in Infoprint Manager for AIX Syntax . . . . .	156
Description . . . . .	156
Arguments . . . . .	156
Example . . . . .	156
pdinitports Utility: Initializes Ports. . . . .	157

Syntax . . . . .	157
Description . . . . .	157
Flags . . . . .	157
Arguments . . . . .	157
Examples . . . . .	158
pdmigpp Utility: Migrates Existing AIX Printers to Infoprint in Infoprint Manager for AIX . . . . .	159
Syntax . . . . .	159
Description . . . . .	159
Arguments . . . . .	159
Example . . . . .	159
pdmincfg Utility: Sets up a Minimum Infoprint Configuration in Infoprint Manager for AIX . . . . .	161
Syntax . . . . .	161
Description . . . . .	161
Flags . . . . .	161
Arguments . . . . .	161
Example . . . . .	161
pdmmsg Utility: Displays Information about a Message in Infoprint Manager for AIX . . . . .	163
Syntax . . . . .	163
Description . . . . .	163
Flags . . . . .	163
Examples . . . . .	163
rc.iprsap Utility: Start SAP Callback Daemons for Infoprint Manager for AIX . . . . .	165
Syntax . . . . .	165
Description . . . . .	165
rc.pd Utility: Restarts Servers in Infoprint Manager for AIX . . . . .	166
Syntax . . . . .	166
Description . . . . .	166
sense Utility: Senses Whether a Channel-Attached Printer is Attached to Infoprint Manager for AIX . . . . .	167
Syntax . . . . .	167
Description . . . . .	167
Arguments . . . . .	167
Messages and Return Codes . . . . .	167
Example . . . . .	168
sense Utility: Senses Whether a Channel-Attached Printer is Attached to Infoprint Manager for Windows NT and Windows 2000 . . . . .	169
Syntax . . . . .	169
Description . . . . .	169
Arguments . . . . .	169
Messages and Return Codes . . . . .	169
Example . . . . .	170
setup Utility: Starts the Infoprint Installer in Infoprint Manager for AIX . . . . .	172
Syntax . . . . .	172
Description . . . . .	172
Flags . . . . .	172
Examples . . . . .	173
startppo Utility: Starts the Infoprint SMIT Production Print Operations Interface in Infoprint Manager for AIX . . . . .	175
Syntax . . . . .	175
Description . . . . .	175
Flags . . . . .	175
Examples . . . . .	175

start_server Utility: Starts a Server for a Basic Infoprint Installation in Infoprint Manager for AIX . . . . .	176
Syntax . . . . .	176
Description . . . . .	176
Flags . . . . .	176
Arguments . . . . .	177
Examples . . . . .	177
startsvr Utility: Starts a Server in Infoprint Manager for AIX . . . . .	178
Syntax . . . . .	178
Description . . . . .	178
Flags . . . . .	178
Arguments . . . . .	179
Examples . . . . .	179
stop_server Utility: Shuts Down a Server in Infoprint Manager for AIX . . . . .	180
Syntax . . . . .	180
Description . . . . .	180
Flags . . . . .	180
Arguments . . . . .	180
Examples . . . . .	180
tdump Utility: Outputs Tape Contents in Human-Readable Format in Infoprint Manager for AIX . . . . .	181
Syntax . . . . .	181
Description . . . . .	181
Flags . . . . .	181
Examples . . . . .	181
tlist Utility: Lists Files on a Tape in Infoprint Manager for AIX . . . . .	183
Syntax . . . . .	183
Description . . . . .	183
Flags . . . . .	183
Examples . . . . .	183
t2file Utility: Reads MVS Partitioned Data Sets from Tape in Infoprint Manager for AIX. . . . .	184
Syntax . . . . .	184
Description . . . . .	184
Flags . . . . .	184
Examples . . . . .	184
<b>Chapter 5. Daemon Utilities for Infoprint Manager for AIX . . . . .</b>	<b>185</b>
mvsprsd Utility: Starts the mvsprsd Daemon . . . . .	186
Syntax . . . . .	186
Description . . . . .	186
Flags . . . . .	186
Examples . . . . .	187
Suggested Reading. . . . .	187
pcl2afpd Utility: Starts the pcl2afpd Daemon . . . . .	188
Syntax . . . . .	188
Description . . . . .	188
Flags . . . . .	188
Configuration File Keywords and Values . . . . .	188
Examples . . . . .	190
Files . . . . .	190
ps2afpd Utility: Starts the ps2afpd Daemon . . . . .	191
Syntax . . . . .	191
Description . . . . .	191
Flags . . . . .	191
Configuration File Keywords and Values . . . . .	191

Examples . . . . .	193
Files . . . . .	193
startnotd Utility: Starts the notifyd Daemon . . . . .	195
Syntax . . . . .	195
Description . . . . .	195
stopnotd Utility: Stops the notifyd Daemon . . . . .	196
Syntax . . . . .	196
Description . . . . .	196
startcbd Utility: Starts the SAP Callback Daemon . . . . .	197
Syntax . . . . .	197
Description . . . . .	197
Arguments . . . . .	197
Examples . . . . .	197
stopcbd Utility: Stops the SAP Callback Daemon . . . . .	199
Syntax . . . . .	199
Description . . . . .	199
Arguments . . . . .	199
Examples . . . . .	199
<b>Chapter 6. Infoprint Transform Commands . . . . .</b>	<b>201</b>
db2afp Command: Transforms DBCS Data to AFP . . . . .	202
Syntax . . . . .	202
Description . . . . .	202
Limitations . . . . .	202
Flags and Values . . . . .	202
Examples . . . . .	204
Files . . . . .	205
d2afp Command: Transforms ditroff Data to AFP in Infoprint Manager for AIX . . . . .	206
Syntax . . . . .	206
Description . . . . .	206
Limitations . . . . .	206
Flags and Values . . . . .	207
Examples . . . . .	207
Files . . . . .	208
gif2afp Command: Transforms GIF Data to AFP in Infoprint Manager for AIX . . . . .	209
Syntax . . . . .	209
Description . . . . .	209
Automatic Invocation . . . . .	209
Input and Output . . . . .	209
Errors and Error Recovery . . . . .	211
Data Transformations . . . . .	212
Parameters . . . . .	213
Resource Search Path . . . . .	214
Limitations . . . . .	214
Acknowledgments . . . . .	214
Options and Values . . . . .	214
jpeg2afp Command: Transforms JPEG Data to AFP in Infoprint Manager for AIX . . . . .	223
Syntax . . . . .	223
Description . . . . .	223
Automatic Invocation . . . . .	223
Input and Output . . . . .	223
Errors and Error Recovery . . . . .	225
Data Transformations . . . . .	226
Parameters . . . . .	227
Resource Search Path . . . . .	228

Limitations . . . . .	228
Acknowledgments . . . . .	228
Options and Values . . . . .	228
line2afp Command: Transforms S/370 Line Data and ASCII Data to AFP . . . . .	236
Syntax . . . . .	236
Description . . . . .	237
Flags and Values . . . . .	239
Examples . . . . .	257
Files . . . . .	259
Messages . . . . .	260
pcl2afp Command: Transforms PCL Data to AFP . . . . .	261
Syntax . . . . .	261
Description . . . . .	261
Limitations . . . . .	262
Flags and Values . . . . .	263
Transforming PCL Image Data. . . . .	270
The pcl2afp and pcl2afpd Configuration Files . . . . .	273
Simple Examples . . . . .	275
More Complex Examples. . . . .	276
Files . . . . .	282
pdf2afp and ps2afp Transforms: Transform PDF or PostScript Data to AFP . . . . .	284
Syntax . . . . .	284
Description . . . . .	284
Limitations . . . . .	285
Flags and Values . . . . .	286
The ps2afp and ps2afpd Configuration Files. . . . .	294
Examples . . . . .	296
Files . . . . .	297
sap2afp Command: Transforms SAP OTF or ABAP Data to AFP in Infoprint Manager for AIX . . . . .	299
Syntax . . . . .	299
Description . . . . .	299
Flags . . . . .	299
The sap2afp Configuration Files . . . . .	299
Examples . . . . .	309
tiff2afp Command: Transforms TIFF Data to AFP in Infoprint Manager for AIX . . . . .	310
Syntax . . . . .	310
Description . . . . .	310
Automatic Invocation . . . . .	310
Input and Output. . . . .	310
Errors and Error Recovery . . . . .	312
Data Transformations . . . . .	313
Parameters. . . . .	314
Resource Search Path . . . . .	316
Limitations . . . . .	316
Acknowledgments . . . . .	316
Options and Values. . . . .	316
<b>Chapter 7. Infoprint Object Attributes . . . . .</b>	<b>325</b>
About Destination Support Systems. . . . .	326
Infoprint Manager for AIX supports the following DSSs: . . . . .	326
Infoprint Manager for Windows NT and Windows 2000 supports the following DSSs: . . . . .	327
Understanding Attachment Types for PSF Actual Destinations . . . . .	327
Attributes Displayed in the Infoprint Manager Administration GUI . . . . .	328
Attributes for Actual Destinations . . . . .	328

Attributes Not Displayed in the Infoprint Administrator's GUI . . . . .	329
Initially Settable Attribute Listing . . . . .	329
Resettable Attribute Listing . . . . .	329
accept-jobs . . . . .	332
accounting-exit . . . . .	332
ack-interval . . . . .	333
add-carriage-returns . . . . .	334
add-line-feeds . . . . .	334
ascii-character-map . . . . .	335
ascii-font-map . . . . .	335
associated-queue . . . . .	336
associated-server . . . . .	337
attachment-type . . . . .	337
attribute-map . . . . .	338
audit-exit . . . . .	339
automatic-postscript-mode-switch . . . . .	339
auxiliary-sheet-selections-supported . . . . .	340
booklet-fold . . . . .	341
cancel-individual-document-supported . . . . .	341
carriage-control-types-supported . . . . .	341
character-mappings-supported . . . . .	342
checkpoint-at-stacker . . . . .	343
checkpoint-formats-supported . . . . .	343
color-mapping-table . . . . .	344
color-rip-servers . . . . .	344
command . . . . .	345
connection-timeout . . . . .	345
content-orientations-supported . . . . .	345
convert-to-ebcdic-supported . . . . .	346
data-fidelity-problem-reported-supported . . . . .	346
default-font-fidelity-action . . . . .	347
default-font-resolution . . . . .	347
default-input-tray . . . . .	348
descriptor . . . . .	348
destination-command . . . . .	349
destination-data-stream . . . . .	350
destination-locations . . . . .	351
destination-model . . . . .	351
destination-name . . . . .	352
destination-needs-attention-time . . . . .	353
destination-needs-key-operator-attention-time . . . . .	353
destination-pass-through . . . . .	353
destination-poll-interval . . . . .	354
destination-realization . . . . .	354
destination-register-threshold . . . . .	355
destination-release-timer . . . . .	355
destination-state . . . . .	356
destination-support-system . . . . .	357
destination-tcpip-internet-address . . . . .	358
destination-tcpip-port-number . . . . .	359
destination-timeout-period . . . . .	359
device-name . . . . .	360
device-support-system . . . . .	361
document-attributes-supported . . . . .	361
document-finishings-supported . . . . .	363
document-formats-ripped-at-destination . . . . .	364

document-formats-supported . . . . .	364
document-types-supported . . . . .	366
dss-job-message-disposition . . . . .	367
dss-job-message-log-size . . . . .	367
dss-job-message-log-wrap . . . . .	368
ebcdic-character-mapping . . . . .	368
enabled . . . . .	369
end-message-supported . . . . .	369
end-sheets-supported . . . . .	370
font-resolutions-supported . . . . .	370
force-destination-setup . . . . .	371
force-printer-setup . . . . .	372
form-definition . . . . .	372
halftones-supported . . . . .	372
image-fit-supported . . . . .	374
image-length . . . . .	374
image-out-formats-supported . . . . .	375
image-width . . . . .	376
input-data-user-exit . . . . .	377
input-trays-medium . . . . .	377
input-trays-supported . . . . .	379
intervention-timer . . . . .	379
job-attributes-supported . . . . .	380
job-batches-ready . . . . .	380
job-finishings-supported . . . . .	381
job-retry-count-limit . . . . .	381
job-retry-interval . . . . .	382
job-rip-actions-supported . . . . .	382
job-size-range-ready . . . . .	383
job-size-range-supported . . . . .	384
job-start-wait-supported . . . . .	385
list-of-managers . . . . .	385
locations . . . . .	386
log-accounting-data . . . . .	386
logical-destinations-assigned . . . . .	387
managers . . . . .	387
maximum-concurrent-jobs . . . . .	387
maximum-copies-supported . . . . .	388
maximum-fonts-to-keep . . . . .	389
maximum-overlays-to-keep . . . . .	389
maximum-segments-to-keep . . . . .	390
media-ready . . . . .	390
media-supported . . . . .	391
message . . . . .	392
message-font-type . . . . .	393
message-form-definition . . . . .	393
model . . . . .	393
non-process-runout-timer . . . . .	394
notification-profile . . . . .	394
notify-operator . . . . .	396
number-up-supported . . . . .	396
object-class . . . . .	397
offset-stacking-available . . . . .	397
operators . . . . .	398
optimize-for-multiple-copies . . . . .	398
orientations-supported . . . . .	399



other-options . . . . .	399
output-appearances-supported. . . . .	399
output-bin . . . . .	399
output-bin-numbers . . . . .	400
output-bins-supported . . . . .	401
output-data-user-exit . . . . .	402
output-format-supported . . . . .	402
overlay . . . . .	403
page-select-supported . . . . .	403
pcl-server-address . . . . .	404
pcl-server-port. . . . .	404
physical-printer . . . . .	405
plex . . . . .	405
plexes-supported. . . . .	405
postscript-server-address. . . . .	406
postscript-server-port . . . . .	407
presentation-fidelity-problem-reported . . . . .	407
print-edge-marks . . . . .	408
print-qualities-supported . . . . .	408
print-queue . . . . .	409
print-queue-name . . . . .	409
printer. . . . .	409
printer-command . . . . .	409
printer-data-stream . . . . .	409
printer-end-sheet. . . . .	409
printer-escape-codes . . . . .	410
printer-memory . . . . .	411
printer-locations . . . . .	412
printer-model . . . . .	412
printer-name . . . . .	412
printer-needs-attention-time . . . . .	412
printer-needs-key-operator-attention-time . . . . .	412
printer-pass-through . . . . .	412
printer-realization . . . . .	412
printer-register-threshold . . . . .	412
printer-release-timer . . . . .	412
printer-resolutions-ready . . . . .	412
printer-resolutions-supported . . . . .	413
printer-separator-sheet . . . . .	414
printer-start-sheet . . . . .	414
printer-state . . . . .	416
printer-s370-channel-device-address . . . . .	416
printer-s370-channel-slot-number. . . . .	416
printer-tcpip-internet-address . . . . .	417
printer-tcpip-port-number . . . . .	417
printer-timeout-period . . . . .	417
problem-message . . . . .	417
protected-attributes . . . . .	417
psf-tray-characteristics. . . . .	418
qualities-supported . . . . .	421
register-threshold . . . . .	421
registered-with-spooler . . . . .	421
remote-queue . . . . .	421
resource-context . . . . .	422
resource-context-font . . . . .	423
resource-context-form-definition . . . . .	424

resource-context-overlay . . . . .	425
resource-context-page-definition . . . . .	426
resource-context-page-segment . . . . .	427
reverse-output. . . . .	428
rip-ini-file. . . . .	428
rip-server . . . . .	429
scanner-corrections-supported . . . . .	429
scheduler-sort-primary-order . . . . .	429
scheduler-sort-secondary-order . . . . .	430
schedulers-supported . . . . .	430
screen-frequencies-supported . . . . .	431
separator-sheets-supported . . . . .	431
shared-printer-name . . . . .	432
sides . . . . .	433
sides-supported . . . . .	433
snmp-active . . . . .	434
snmp-community-name . . . . .	434
snmp-retry-count . . . . .	435
snmp-timeout . . . . .	435
start-message-supported . . . . .	436
start-sheets-supported . . . . .	436
table-reference-characters-supported . . . . .	437
timeout-period . . . . .	438
transform-sequence. . . . .	438
use-snmp . . . . .	438
wait-for-job-completion . . . . .	439
warning-message . . . . .	439
windows-nt-driver-names . . . . .	440
x-image-shift-range-supported . . . . .	440
y-image-shift-range-supported . . . . .	441
Attributes for Auxiliary-Sheet Objects . . . . .	443
Initially Settable Attribute Listing . . . . .	443
Resettable Attribute Listing . . . . .	443
associated-server . . . . .	443
auxiliary-sheet-identifier . . . . .	443
descriptor . . . . .	444
object-class. . . . .	444
psf-exit-form-definition . . . . .	444
psf-exit-page-mark . . . . .	444
psf-exit-program-name . . . . .	445
Attributes for Documents and Default Documents. . . . .	449
Document . . . . .	449
Default Document . . . . .	449
Attributes Not Displayed in the Infoprint Administrator's GUI . . . . .	449
Initially Settable Attribute Listing . . . . .	449
Resettable Attribute Listing . . . . .	449
Per-Document Attribute Listing. . . . .	451
account-text . . . . .	453
address1-text . . . . .	454
address2-text . . . . .	454
address3-text . . . . .	455
address4-text . . . . .	455
associated-server (Default Document Only) . . . . .	456
base-printer . . . . .	456
bits-per-spot . . . . .	457
black-overprint . . . . .	457

building-text . . . . .	458
callback-number . . . . .	458
carriage-control-type . . . . .	458
chars . . . . .	459
cms-proclink . . . . .	460
cms-product . . . . .	460
color-mapping-table . . . . .	461
compressed-output . . . . .	461
content-orientation . . . . .	462
control-strip . . . . .	462
convert-to-ebcdic . . . . .	463
copies . . . . .	463
copy-count . . . . .	463
data-fidelity-problem-reported . . . . .	464
default-character-mapping . . . . .	464
default-input-tray . . . . .	465
default-medium . . . . .	466
default-printer-resolution . . . . .	467
department-text . . . . .	467
descriptor (Default Document Only) . . . . .	468
destination-company-text . . . . .	468
destination-initial-value-document (Document Only) . . . . .	468
destination-pass-through . . . . .	469
document-comment . . . . .	469
document-content (Document Only) . . . . .	469
document-content-list (Document Only) . . . . .	470
document-file-name (Document Only) . . . . .	470
document-finishing . . . . .	470
document-format . . . . .	471
document-number (Document Only) . . . . .	472
document-sequence-number (Document Only) . . . . .	472
document-type (Document Only) . . . . .	472
dot-shape . . . . .	474
email-from-address . . . . .	475
email-to-address . . . . .	475
enable-settrap . . . . .	476
fax-number . . . . .	476
fax-to-name . . . . .	476
file-name (Document Only) . . . . .	477
font-fidelity-action . . . . .	477
font-processing-messages . . . . .	477
font-resolution . . . . .	478
form-definition . . . . .	478
format . . . . .	479
halftone . . . . .	479
image-center-x . . . . .	480
image-center-y . . . . .	481
image-fit . . . . .	481
image-length . . . . .	482
image-out-format . . . . .	483
image-scale . . . . .	483
image-width . . . . .	484
initial-value-document (Document Only) . . . . .	485
initial-value-document-identifier (Default Document Only) . . . . .	485
input-exit . . . . .	486
input-tray-select . . . . .	487

jog-between-job-copies	487
list-of-managers (Default Document Only)	487
logical-destinations-ready (Default Document Only)	488
logical-printers-ready (Default Document Only)	488
managers (Default Document Only)	488
maximum-messages-printed	488
maximum-transform-pages-ahead	489
message (Default Document Only)	489
mvs-class	489
mvs-destination	490
mvs-forms	490
mvs-segment-id	491
name-text	491
new-line-option	492
node-id-text	492
number-up	493
object-class	493
octet-count (Document Only)	494
offset-stacking-between-job-copies	494
orientation	494
originating-company-text	494
other-options	495
other-transform-options	495
output-appearance	495
output-bin	495
output-face-up	496
output-format	497
overlay	498
overlay-back	499
overlay-front	499
overprint	500
page-clip	500
page-count (Document Only)	501
page-definition	501
page-media-select	502
page-select (Document Only)	502
plex	503
print-quality	504
printer-initial-value-document (Document Only)	504
printer-pass-through	504
programmer-text	504
resource-context	505
resource-context-font	506
resource-context-form-definition	507
resource-context-overlay	508
resource-context-page-definition	509
resource-context-page-segment	509
resource-context-user	510
resource-exit	511
room-text	512
scanner-correction	512
screen-frequency	513
segment-file-size	513
sequence-number (Document Only)	514
shared-formdef	514
shift-out-shift-in	514

sides	515
start-on-new-sheet	516
subject-text	516
table-reference-characters	516
title-text	517
transfer-method (Document Only)	518
transform-message-file-name	518
transform-output-file-name	518
type (Document Only)	519
user-id-text	519
x-image-shift	519
x-image-shift-back	520
y-image-shift	521
y-image-shift-back	521
Attributes for Jobs and Default Jobs	523
Default Job	523
Job	523
Attributes Not Displayed in the Infoprint Administrator's GUI	523
Initially Settable Attribute Listing	523
Resettable Attribute Listing	523
actual-destinations-requested	524
associated-server (Default Job Only)	525
auxiliary-sheet-selection	525
comment	525
completion-time (Job Only)	526
current-job-state (Job Only)	526
current-page-printing (Job Only)	527
d-s-s-requested	528
deadline-in-jeopardy (Job Only)	528
delete-segment-list	528
descriptor (Default Job Only)	529
destination-initial-value-job (Job Only)	529
destination-locations-requested	530
destination-models-requested	530
destination-name-requested (Job Only)	531
destinations-assigned (Job Only)	531
destinations-used (Job Only)	532
device-support-system-requested	532
discard-time (Job Only)	532
dss-requested	532
end-message	533
estimated-completion-time (Job Only)	533
estimated-processing-time (Job Only)	534
formatted-job-ticket-content (Job Only)	534
global-id (Job Only)	534
hold	534
initial-value-job (Job Only)	535
initial-value-job-identifier (Default Job Only)	535
intervening-jobs (Job Only)	535
job-batch	536
job-client-id (Job Only)	536
job-comment	536
job-complexity	537
job-copies-completed (Job Only)	537
job-deadline-time (Job Only)	538
job-discard-time (Job Only)	538

job-end-message . . . . .	539
job-finishing . . . . .	539
job-hold . . . . .	540
job-identifier (Job Only) . . . . .	541
job-log (Job Only) . . . . .	541
job-media-sheet-count (Job Only) . . . . .	542
job-message-from-administrator (Job Only) . . . . .	542
job-message-to-operator . . . . .	543
job-name . . . . .	543
job-originator (Job Only) . . . . .	544
job-owner (Job Only) . . . . .	544
job-page-count (Job Only) . . . . .	545
job-print-after (Job Only) . . . . .	545
job-priority . . . . .	546
job-retain-until (Job Only) . . . . .	546
job-retention-period . . . . .	547
job-rip-action . . . . .	547
job-ripped-by-server . . . . .	548
job-size (Job Only) . . . . .	551
job-start-message . . . . .	551
job-start-wait . . . . .	552
job-state (Job Only). . . . .	552
job-state-reasons (Job Only) . . . . .	552
job-submission-complete (Job Only). . . . .	554
job-ticket-content. . . . .	554
last-accessor (Job Only) . . . . .	554
last-modifier (Job Only) . . . . .	554
list-of-managers (Default Job Only) . . . . .	554
locations-requested . . . . .	555
logical-destinations-ready (Default Job Only) . . . . .	555
logical-printer-requested . . . . .	555
logical-printers-ready (Default Job Only) . . . . .	555
managers (Default Job Only) . . . . .	555
media-sheet-count (Job Only) . . . . .	556
media-sheets-completed (Job Only). . . . .	556
message (Default Job Only) . . . . .	556
message-from-administrator (Job Only) . . . . .	556
message-to-operator . . . . .	556
models-requested . . . . .	557
modification-time (Job Only) . . . . .	557
name . . . . .	557
name-of-last-accessor (Job Only). . . . .	557
new-job-identifier (Job Only) . . . . .	557
notification-profile . . . . .	558
number-of-documents (Job Only). . . . .	560
object-class. . . . .	560
octets-completed (Job Only) . . . . .	561
optimize-for-multiple-copies . . . . .	561
originator (Job Only) . . . . .	562
owner (Job Only) . . . . .	562
pages-completed (Job Only) . . . . .	562
physical-printers-requested . . . . .	563
position-in-queue (Job Only) . . . . .	563
previous-job-state (Job Only) . . . . .	563
previous-state (Job Only). . . . .	564
print-after (Job Only) . . . . .	564

printer-initial-value-job (Job Only)	564
printer-locations-requested	564
printer-models-requested	564
printer-name-requested	564
printer-requested	564
printers-assigned (Job Only)	564
printers-used (Job Only)	564
processing-time (Job Only)	564
queue-assigned (Job Only)	565
queue-position (Job Only)	565
reasons (Job Only)	565
required-resources-not-ready (Job Only)	565
required-resources-not-supported (Job Only)	566
results-profile	566
retained-time (Job Only)	568
retention-period	568
start-message	568
started-printing-time (Job Only)	568
state-reasons (Job Only)	568
submission-time (Job Only)	568
tape-exit (Job Only)	569
tape-format (Job Only)	569
tape-labeled (Job Only)	570
tape-max-block-size (Job Only)	570
tape-rewind-before (Job Only)	570
tape-rewind-unload (Job Only)	571
ticket-content (Job Only)	571
total-job-octets (Job Only)	571
user-locale (Job Only)	572
user-name (Job Only)	572
Attributes for Logs	573
Initially Settable Attribute Listing	573
Resettable Attribute Listing	573
associated-server	573
descriptor	573
enabled	574
log-address	574
log-identifier	574
log-messages	575
log-severity	575
log-size	576
log-trace-groups	576
log-type	576
log-wrap	577
object-class	577
Attributes for Logical Destinations	578
Attributes Not Displayed in the Infoprint Administrator's GUI	578
Initially Settable Attribute Listing	578
Resettable Attribute Listing	578
associated-queue	579
associated-server	579
authorize-jobs	580
auxiliary-sheet-selections-supported	580
carriage-control-types-supported	581
character-mappings-supported	581
content-orientations-supported	581

convert-to-ebcdic-supported . . . . .	582
data-fidelity-problem-reported-supported . . . . .	583
descriptor . . . . .	583
destination-associated-destinations . . . . .	584
destination-initial-value-document . . . . .	584
destination-initial-value-job . . . . .	584
destination-locations . . . . .	585
destination-model . . . . .	585
destination-name . . . . .	585
destination-realization . . . . .	586
destination-support-system . . . . .	586
destinations-ready . . . . .	587
device-support-system . . . . .	587
document-formats-supported . . . . .	587
document-types-supported . . . . .	588
enabled . . . . .	588
end-message-supported . . . . .	589
image-out-formats-supported . . . . .	589
input-trays-supported . . . . .	590
job-size-range-supported . . . . .	590
list-of-managers . . . . .	591
locations . . . . .	592
logical-printer . . . . .	592
managers . . . . .	592
maximum-copies-supported . . . . .	592
media-supported . . . . .	592
message . . . . .	593
model . . . . .	593
notification-profile . . . . .	593
nt-drivers . . . . .	594
object-class . . . . .	595
orientations-supported . . . . .	595
os2-driver-names . . . . .	595
os2-drivers . . . . .	596
page-select-supported . . . . .	596
plexes-supported . . . . .	597
print-qualities-supported . . . . .	597
printer . . . . .	597
printer-associated-printers . . . . .	597
printer-initial-value-document . . . . .	597
printer-initial-value-job . . . . .	598
printer-locations . . . . .	598
printer-model . . . . .	598
printer-name . . . . .	598
printer-realization . . . . .	598
printers-ready . . . . .	598
protected-attributes . . . . .	598
qualities-supported . . . . .	598
sides-supported . . . . .	598
start-message-supported . . . . .	599
table-reference-characters-supported . . . . .	599
windows-driver-names . . . . .	600
windows-drivers . . . . .	601
windows-nt-driver-names . . . . .	601
windows-nt-drivers . . . . .	601
x-image-shift-range-supported . . . . .	601



y-image-shift-range-supported . . . . .	602
Attributes for Media . . . . .	604
Attributes Not Displayed in the Infoprint Administrator's GUI . . . . .	604
Initially Settable Attribute Listing . . . . .	604
Resettable Attribute Listing . . . . .	604
associated-server . . . . .	604
descriptor . . . . .	605
medium-color . . . . .	605
medium-dimensions . . . . .	605
medium-form-parts . . . . .	606
medium-holes-count . . . . .	606
medium-identifier. . . . .	607
medium-sides . . . . .	607
medium-size . . . . .	608
medium-type . . . . .	608
medium-weight . . . . .	609
message. . . . .	609
object-class. . . . .	609
Attributes for Queues . . . . .	610
Initially Settable Attribute Listing . . . . .	610
Resettable Attribute Listing . . . . .	610
actual-destinations-assigned . . . . .	610
actual-destinations-ready . . . . .	610
assign-to-destination . . . . .	611
associated-server . . . . .	611
backlog . . . . .	612
backlog-lower-bound . . . . .	612
backlog-update-interval . . . . .	612
backlog-upper-bound . . . . .	613
backlogged . . . . .	613
current-backlog . . . . .	613
descriptor . . . . .	613
list-of-managers . . . . .	614
logical-destinations-assigned . . . . .	614
logical-destinations-ready . . . . .	614
logical-printers-assigned . . . . .	615
logical-printers-ready . . . . .	615
managers . . . . .	615
message. . . . .	615
notification-profile . . . . .	615
notify-operator. . . . .	616
object-class. . . . .	617
operators . . . . .	617
physical-printers-assigned . . . . .	617
physical-printers-ready . . . . .	617
protected-attributes . . . . .	618
queue-backlog . . . . .	618
queue-name . . . . .	618
queue-state. . . . .	618
requeue-failed-jobs . . . . .	619
Attributes for Resource Contexts . . . . .	620
Initially Settable Attribute Listing . . . . .	620
Resettable Attribute Listing . . . . .	620
associated-server . . . . .	620
context-address . . . . .	621
descriptor . . . . .	621

object-class . . . . .	621
resource-context-identifier . . . . .	622
Attributes for Servers . . . . .	623
Initially Settable Attribute Listing . . . . .	623
Resettable Attribute Listing . . . . .	623
accept-unsupported-jobs . . . . .	623
actual-destinations-ready . . . . .	624
actual-destinations-supported . . . . .	624
auto-create-shared-printers (Windows NT and Windows 2000 Only) . . . . .	625
cancel-individual-document-supported . . . . .	625
descriptor . . . . .	625
destination-states-supported . . . . .	626
destination-support-systems-supported . . . . .	626
document-attributes-supported . . . . .	627
events-supported . . . . .	627
hostname . . . . .	629
i-p-address . . . . .	629
ip-address . . . . .	629
job-attributes-supported . . . . .	629
job-state-reasons-supported . . . . .	629
job-states-supported . . . . .	630
job-submission-timer . . . . .	630
list-of-managers . . . . .	630
locale . . . . .	631
log-accounting-data . . . . .	631
logical-destinations-ready . . . . .	632
logical-destinations-supported . . . . .	632
logical-printers-ready . . . . .	632
logical-printers-supported . . . . .	632
managers . . . . .	633
maximum-barco-rips . . . . .	633
maximum-non-raster-rips . . . . .	633
maximum-raster-rips . . . . .	633
message . . . . .	634
modify-individual-document-supported . . . . .	634
multiple-documents-supported . . . . .	634
notification-delivery-methods-supported . . . . .	634
notification-profile . . . . .	635
npm-server-ip-address . . . . .	636
npm-server-port-number . . . . .	637
object-class . . . . .	637
object-classes-supported . . . . .	637
physical-printers-ready . . . . .	638
physical-printers-supported . . . . .	638
printer-states-supported . . . . .	638
problem-child . . . . .	638
protected-attributes . . . . .	638
queues-supported . . . . .	639
save-rip-files . . . . .	639
security-level . . . . .	639
server-hostname . . . . .	640
server-ip-address . . . . .	640
server-name . . . . .	641
server-state . . . . .	641
smtp-server-host (Windows NT and Windows 2000 Only) . . . . .	641
smtp-server-port-number (Windows NT and Windows 2000 Only) . . . . .	642

snmp-aix-printer-models . . . . .	642
snmp-discovery-during-startup . . . . .	642
snmp-normal-poll-interval . . . . .	643
snmp-problem-poll-interval . . . . .	643
transfer-methods-supported . . . . .	644
windows-drivers . . . . .	644
windows-nt-driver-names . . . . .	644
windows-nt-drivers . . . . .	645
Attributes for Transforms (Windows NT or Window 2000 only) . . . . .	645
Initially Settable Attribute Listing . . . . .	645
Resettable Attribute Listing . . . . .	645
associated-server . . . . .	645
descriptor . . . . .	645
document-formats-supported . . . . .	646
object-class . . . . .	646
other-transform-options . . . . .	647
output-document-format . . . . .	648
terminating-transform . . . . .	649
transform-identifier . . . . .	649
transform-library . . . . .	650
<b>Chapter 8. Infoprint Environment Variables . . . . .</b>	<b>651</b>
Querying Environment Variables . . . . .	655
Setting Environment Variables . . . . .	655
In a File . . . . .	656
On the Command Line . . . . .	656
<b>Chapter 9. Notification Events and Event Classes . . . . .</b>	<b>657</b>
<b>Appendix A. Attribute-to-Object Listing . . . . .</b>	<b>673</b>
<b>Appendix B. Migrating PSF for AIX Job Script Keywords to Infoprint     Equivalents . . . . .</b>	<b>691</b>
<b>Appendix C. Job Validation and Scheduling . . . . .</b>	<b>695</b>
<b>Appendix D. Form Definitions and Page Definitions Supplied with     Infoprint . . . . .</b>	<b>699</b>
Default Form Definitions . . . . .	699
General-Purpose Form Definitions . . . . .	699
Form Definitions for Printing Envelopes . . . . .	701
Form Definitions for 17 by 11 Inch Paper . . . . .	701
Form Definitions Specifying a 0, 0 Offset . . . . .	702
Form Definitions Specifying N_UP Page Positioning . . . . .	703
Form Definitions for Printing on Prepunched Paper . . . . .	704
Form Definitions for Specific Models of IBM Printers. . . . .	705
Page Definitions Supplied with Infoprint . . . . .	706
Page Definitions for Letter-Sized Paper . . . . .	706
Page Definitions for A4-Sized Paper . . . . .	706
Page Definitions for Letter- and A4-Sized Paper with Multiple-Up of 2 and 4 . . . . .	707
Page Definitions for Legal-Sized Paper . . . . .	707
Page Definitions for B4-Sized Paper . . . . .	708
<b>Glossary . . . . .</b>	<b>709</b>
<b>Sources and References . . . . .</b>	<b>709</b>

<b>Notices</b> . . . . .	727
Licenses . . . . .	727
Trademarks. . . . .	727
<b>Index</b> . . . . .	729

---

## Figures

1. A PCL Image . . . . .	271
2. A Cropped PCL Image . . . . .	271
3. A PCL Image Offset from the Top-Left Corner . . . . .	272
4. Sample pcl2afp Configuration File . . . . .	274
5. Sample ps2afp Configuration File . . . . .	295
6. Sample barcode.tab Configuration File . . . . .	301
7. Sample defcp.tab Configuration File . . . . .	302
8. Header and Courier Portions of a Sample fonts.tab Configuration File . . . . .	305
9. Heisei Gothic Portion of a Sample fonts.tab Configuration File. . . . .	305
10. Sample image.tab Configuration File . . . . .	306
11. Sample pagedef.tab Configuration File . . . . .	307
12. Sample printer.tab Configuration File . . . . .	308
13. Sample xxxyyyyy.tab Configuration File (Single-Byte Code Pages) . . . . .	309
14. Sample xxxyyyyy.tab Configuration File (Double-Byte Code Pages). . . . .	309



---

## Tables

1. Infoprint Objects . . . . .	3
2. Attribute Operators for Filters . . . . .	42
3. Filter Syntax . . . . .	44
4. pdmod Operators. . . . .	51
5. Results of the pdq Command . . . . .	74
6. pdset Operators . . . . .	91
7. line2afp Resource Options and Corresponding Options and Attributes . . . . .	236
8. File Extensions for Resources . . . . .	238
9. PCL Printing and Processing Options . . . . .	274
10. PostScript and PDF Printing and Processing Options . . . . .	295
11. SAP Code Page Configuration Files . . . . .	308
12. Input Tray Names, Job Bin Numbers, and Tray Numbers on AFP Printer Devices . . . . .	420
13. Staple Position for PSF DSS . . . . .	540
14. Infoprint Environment Variables Defaulted or Set for Infoprint Manager for AIX and Infoprint Manager for Windows NT and Windows 2000. . . . .	651
15. Infoprint Environment Variables Defaulted or Set in the /etc/environment File in Infoprint Manager for AIX . . . . .	652
16. Infoprint Environment Variables Set in the Infoprint SMIT Production Print Operations Interface Environment File for Infoprint Manager for AIX . . . . .	653
17. AIX Environment Variables. . . . .	654
18. Notification Events . . . . .	657
19. Notification Event Classes . . . . .	668
20. PSF for AIX Keywords Used in Job Script Files and Infoprint Equivalents . . . . .	691
21. PSF for AIX Keywords Used in parmdd Files . . . . .	693
22. Document and Destination Attributes Used for Validation and Scheduling. . . . .	696
23. Job and Destination Attributes Used for Validation and Scheduling . . . . .	697
24. Default Form Definition Characteristics . . . . .	699
25. General-Purpose Form Definitions . . . . .	699
26. Form Definitions Supplied with Infoprint for Printing Envelopes . . . . .	701
27. Form Definitions Supplied for 17 by 11 Paper . . . . .	701
28. Form Definitions Supplied with Infoprint Specifying a 0, 0 Offset . . . . .	702
29. Form Definitions for N_UP Page Positioning . . . . .	703
30. Form Definitions for Prepunched Paper . . . . .	704
31. Form Definitions Supplied for IBM 3831, 3835, and 3900 Printers . . . . .	705
32. Form Definition Supplied for IBM 3935 and 3160 Printers . . . . .	705
33. Page Definitions for Letter-Sized Paper . . . . .	706
34. Page Definitions for A4-Sized Paper . . . . .	706
35. Page Definitions for Letter- and A4-Sized Paper with Multiple-Up of 2 and 4 . . . . .	707
36. Page Definitions for Legal-Sized Paper . . . . .	707
37. Page Definitions for B4-Sized Paper . . . . .	708





---

## About This Publication

This publication describes the Infoprint Manager (Infoprint):

- Commands
- Flags used with AIX print commands
- Administrative utilities
- Daemon utilities
- Transform commands
- Object attributes
- Environment variables
- Notification events and event classes

---

## Who Should Use This Publication

This publication is intended for the person responsible for installing, customizing, operating, or administrating Infoprint.

---

## About the Documentation for Infoprint

Infoprint provides the following types of documentation:

- Infoprint library in portable document format (PDF) or hard copy
- Infoprint documentation on the World Wide Web
- Online help for Infoprint Submit, Infoprint Scan, the Infoprint Administration GUI, the Infoprint Operations GUI, the Infoprint administrator's GUI, the Infoprint SMIT production printing system interface, and the Infoprint SMIT production print operations interface
- Manual (man) pages
- Infoprint online message catalog
- **readme** files

## The Infoprint Publication Library

For the most current information, please go to the IBM Printing System site at <http://www.ibm.com/printers>.

### Infoprint Manager for AIX Publication Library

Infoprint provides the following publications in PDF format on a CD-ROM supplied with the product:

- *Infoprint Manager for AIX: Administrator's Guide*, S544-5595. This publication describes the primary administrator tasks necessary for setting up an Infoprint environment.
- *Infoprint Manager for AIX: User's and Operator's Guide*, S544-5596. This publication describes submitting print jobs from Infoprint Submit, Infoprint Scan, Infoprint Select, and the Infoprint AIX client, scheduling jobs, and managing the print environment.
- *Infoprint Manager: Reference*, S544-5475. For print administrators, operators, and application programmers with the need to perform command-line functions, this publication describes the commands, utilities, transforms, attributes, and attribute values associated with Infoprint.
- *PSF Direct Network Configuration Guide for System/370*, S544-5486. For system administrators or network specialists responsible for configuring a system for Print Services Facility (PSF) Direct. PSF Direct is a function of Infoprint Manager that allows another PSF program (PSF/VM, PSF/MVS, or PSF/VSE) to print

remotely, using the SNA LU 6.2 protocol, on printers supported by Infoprint. The PSF program sends the print data stream directly to the Infoprint printer.

- *IBM PSF for AIX: AFP Upload Configuration Guide Using SNA Server/6000*, S544-5422. For system administrators, this publication describes how to configure AFP Upload on both AIX (client) and MVS (server) to send files to the JES spool on the MVS server, using a SNA Server/6000 protocol.
- *IBM PSF for AIX: AFP Upload Configuration Guide Using TCP/IP*, S544-5423. For system administrators, this publication describes how to configure AFP Upload on both AIX (client) and MVS (server) to send files to the JES spool on the MVS server, using a TCP/IP protocol.

## **Infoprint Manager for Windows NT and Windows 2000 Publication Library**

Infoprint provides the following publications in PDF format on a CD-ROM supplied with the product:

- *Infoprint Manager for Windows NT and Windows 2000: Planning Guide*, G544-5716. This publication helps you prepare to use Infoprint Manager for Windows NT and Windows 2000. It describes features of this product and compares its functions to those of IBM Print Services Facility for OS/2 (PSF for OS/2). It addresses migration from PSF for OS/2 at a high level. Finally, this publication explains the differences between the AIX and Windows version of Infoprint. You can order a printed copy of this publication from IBM by requesting the form number.
- *Infoprint Manager for Windows NT and Windows 2000: Getting Started*, G544-5717. This publication helps you install and configure Infoprint Manager for Windows NT and Windows 2000. It focuses primarily on server and client system software configuration, but it also includes information for the IBM 4159 Model 001 S/390 Parallel Channel Emulator Card. You can order a printed copy of this publication from IBM by requesting the form number.
- *Infoprint Manager: Reference*, S544-5475. For print administrators, operators, and application programmers with the need to perform command-line functions, this publication describes the commands, utilities, transforms, attributes, and attribute values associated with Infoprint.

**Note:** This publication is available only in PDF format.

- *PSF Direct Network Configuration Guide for System/370*, S544-5486. For system administrators or network specialists responsible for configuring a system for Print Services Facility (PSF) Direct. PSF Direct is a function of Infoprint Manager that allows another PSF program (PSF/VM, PSF/MVS, or PSF/VSE) to print remotely, using the SNA LU 6.2 protocol, on printers supported by Infoprint. The PSF program sends the print data stream directly to the Infoprint printer.
- *IBM PSF for AIX: AFP Upload Configuration Guide Using SNA Server/6000*, S544-5422. For system administrators, this publication describes how to configure AFP Upload on both AIX (client) and MVS (server) to send files to the JES spool on the MVS server, using a SNA Server/6000 protocol.
- *IBM PSF for AIX: AFP Upload Configuration Guide Using TCP/IP*, S544-5423. For system administrators, this publication describes how to configure AFP Upload on both AIX (client) and MVS (server) to send files to the JES spool on the MVS server, using a TCP/IP protocol.

## **Other Publications Related to Infoprint**

The following publications contain information you might find useful while installing, administrating, and using Infoprint:

- *AIX Version 4 Release 1 Commands Reference*, SBOF-1851, or *AIX Version 4 Release 3 Commands Reference*, SBOF-1877. For administrators, operators, and end users, these publications provide complete information about AIX commands.

**Note:** Infoprint requires AIX Version 4.2.1 or 4.3. Users of AIX Version 4.2.1 should refer to *AIX Version 4 Release 1 Commands Reference*.

- *PSF/MVS MVS Download Guide*, G544-5294. For administrators and job submitters, this publication provides instructions for setting up the MVS Download support on PSF/MVS so that data can be transmitted from the Job Entry Subsystem (JES) spool on MVS for printing on an Infoprint system.
- *Printing for Fun and Profit under AIX*, GG24-3570. For administrators and system engineers, this publication provides instructions for installing printer devices and configuring AIX print queues.
- *IBM Page Printer Formatting Aid: User's Guide*, S544-5284. For administrators and job submitters, this publication provides instructions for creating form definitions and page definitions with Page Printer Formatting Aid for AIX (PPFA).

**Note:** This is an optional feature of Infoprint.

- *Advanced Function Presentation: Font Summary*, G544-3810. For administrators and job submitters, this publication provides information on IBM fonts.
- *Advanced Function Presentation: Printer Information*, G544-3290. For administrators and job submitters, this publication provides information on IBM printer devices.
- *IBM Data Stream and Object Architectures: Bar Code Object Content Architecture Reference*, S544-3766. For administrators, this publication provides information on bar codes.
- *IBM Data Stream and Object Architectures: Font Object Content Architecture Reference*, S544-3285. For administrators, this publication provides information on coded fonts.
- *IBM Data Stream and Object Architectures: Graphics Object Content Architecture Reference*, S544-5498. For administrators, this publication provides information on printing graphics.
- *IBM Data Stream and Object Architectures: Image Object Content Architecture Reference*, SC31-6805. For administrators and job submitters, this publication provides information on the IOCA data stream.
- *IBM Data Stream and Object Architectures: Mixed Object Document Content Architecture Reference*, SC31-6802. For administrators and job submitters, this publication provides information on the MOD:CA data stream.
- *TCP/IP Tutorial and Technical Overview*, GG24-3376. For networking specialists, this publication provides an overview of the Transmission Control Protocol/Internet Protocol (TCP/IP) and its uses in heterogeneous networks.

## Manual (man) Pages for Infoprint Commands, Utilities, and Transforms

Online information, in manual (man) page format, is available for all Infoprint commands and utilities. You can use the AIX **man** command to view man pages for the following Infoprint commands:

lprafp  
mkfntmap  
pdaccount  
pdclean  
pdcreate  
pddelete  
pddisable  
pdenable  
pdls  
pdmod  
pdpause

pdpr  
pdpromote  
pdq  
pdreorder  
pdresubmit  
pdresume  
pdrm  
pdset  
pdshutdown  
pdspace  
psfstat

For example, to view online information for the **pdpr** command, enter:

```
man pdpr
```

You can use the AIX **man** command to view the following man page for the **-o** flag, which is used to pass information to Infoprint on AIX print commands:

**oflag**

You can use the AIX **man** command to view man pages for the following Infoprint utilities:

admingui  
afpsplit  
ainupod1  
ainupod2  
ainupod3  
ainurpt1  
ainurpt2  
ainurpt3  
ainurpt4  
ainurpt5  
ainurpt6  
cfu  
ipguiadv  
ipguibasic  
ipguidist  
jsmigr  
opergui  
pdadmin  
pdcrcls  
pdcrflt  
pdcrmed

pdinitports  
pdmigpp  
pdmincfg  
pdmsg  
pdnetifspri  
rc.ipsap  
rc.pd  
sense  
setup  
startcbd  
startnotd  
startppo  
start\_server  
startsrv  
stopcbd  
stopnotd  
stop\_server  
tdump  
tlist  
t2file

You can use the AIX **man** command to view man pages for the following Infoprint daemon utilities:

mvsprsd  
pcl2afpd

ps2afpd

You can use the AIX **man** command to view man pages for the following Infoprint transform commands:

db2afp  
d2afp  
gif2afp  
jpeg2afp  
line2afp

pcl2afp  
pdf2afp  
ps2afp  
sap2afp  
tiff2afp

For information about the flags that you can use with the **man** command, refer to the **man** man page or to the AIX Version 4.2 *Commands Reference*.

## Manual (man) Pages for Infoprint Attributes

Infoprint also provides you with online information about the attributes that each object supports. To view the various attributes, enter the following command:

```
man pd_att
```

A list displays containing file names of attribute man pages. You can then display the desired file and view the information about specific attributes.

Use the AIX **man** command to view the following Infoprint man pages for attributes:

pd_att_act_dest	pd_att_medium
pd_att_aux_sheet	pd_att_queue
pd_att_document	pd_att_res_context
pd_att_job	pd_att_server
pd_att_log	pd_att_transform
pd_att_log_dest	

## Infoprint Online Message Catalog

Infoprint supplies a message catalog for the messages that are issued during its operation. For each message, the message catalog includes the text of the message, an explanation, a system action, and a response. You can view all information for a specific Infoprint error message by issuing the Infoprint **pdmsg** utility followed by the message number.

For example, from the command line enter:

```
pdmsg 5010-096
```

Messages issued by Infoprint have the following prefixes:

0420	0424
0421	0425
0422	5010
0423	

See the Infoprint **pdmsg** man page for a complete description of the **pdmsg** utility.

To view information about an AIX message, issue the AIX **info** command with the **-h** flag, followed by the message number. For example, from the command line enter:

```
info -h MessageNumber
```

where *MessageNumber* is the number of the AIX message.

## readme Files

The **readme** files on the Infoprint CD-ROM contain last-minute information about Infoprint that the hardcopy publications or the online information do not contain. You can use the AIX **more** command or a text editor, such as **dtpad** or **vi** on AIX, EPM on OS/2, or Notepad on Windows, to view the contents of the **readme** files.

### Viewing PDF Publications

Infoprint provides software publications in PDF files on the publications CD-ROM. To view or print these publications:

1. Log in to AIX as **root** or as a member of the **system** group.
2. Insert the Infoprint publications CD-ROM into the drive.
3. To determine the identifier of your CD-ROM drive, enter on the AIX command line:

```
lsdev -C -c cdrom
```

4. Then enter:

```
mount -v cdrfs -r /dev/cdn /cdrom
```

where *cdn* is the identifier of your CD-ROM drive, and */cdrom* is the file system that was created to install Infoprint.

5. Read the **readme.txt** file in the **/cdrom** directory.
6. If your AIX server or Windows system has an internet browser, such as Netscape or Internet Explorer, select the **aixindex.html** file in the appropriate language directory and click on the descriptions to view the appropriate PDF file.

For example, if you use English, access the **/cdrom/english/aixindex.html** file.

If your AIX server or Windows system does not have an internet browser, move to the appropriate language directory and select the appropriate PDF file from the following choices:

### Installing Infoprint Manager

Title	PDF file name
Getting up and running in no time with IBM installation services	inscf798.pdf
Installing and Configuring Infoprint Library	library.pdf
Installing Infoprint Manager Control on your AIX Server	aixinsr32.pdf
Installing Optional Features	insoptf32.pdf

### Using Infoprint Manager

Title	PDF file name
IPDS Printer Operator Commands	refip798232.pdf
IPDS Error Recovery	ipdserrecov32.pdf
Performing Optional Configuration	optcfg32.pdf
Printing Variable Data	VariData.pdf
Submitting a Job to a DocuTech 135 Printer	prdocu39932.pdf
Using Enhanced Grab and Move to Shift Page Images	prnpgoff39932.pdf
Using Infoprint Scan	g5445722.pdf

## Infoprint Publications

Title	PDF file name
Administrator's Guide	iprf1mst.pdf
User's and Operator's Guide	ipro1mst.pdf
Infoprint Manager Reference	iprr2mst.pdf
IBM PSF for AIX: AFP Upload Configuration Guide Using SNA Server/6000	S5445422.pdf
IBM PSF for AIX: AFP Upload Configuration Guide Using TCP/IP	S5445423.pdf
SAP R/3 Support: Configuration and Printing Tasks	sapr332.pdf.pdf

7. To use the Adobe Acrobat Viewer, enter:

```
cd /usr/lpp/Acrobat3/bin
./acroexch
```

Click on the **Help** button to learn how to view or print a publication.

8. If you have installed Infoprint Submit or the Adobe Acrobat Viewer on Windows, you can print or view the Infoprint PDF publications from your Windows system. On Windows, the publications directory is called *d:\cdrom\books\language*, where *d:* is the identifier of your CD-ROM drive and *language* is the appropriate language for the books.

---

## The Organization of This Publication

This publication contains the following chapters and appendixes:

### Chapter 1. Introduction

This chapter describes the Infoprint object classes and gives some general information about invoking Infoprint commands, utilities, and transforms.

### Chapter 2. Infoprint Commands

This chapter describes the syntax, use, flags, attributes, and arguments of the Infoprint commands and shows examples of each command.

### Chapter 3. The -o Flag for AIX Print Commands

This chapter describes the **-o** flag, which is used with AIX print commands to pass information to Infoprint.

### Chapter 4. Infoprint Administrative Utilities

This chapter describes the syntax, use, flags, and arguments of the Infoprint administrative utilities and shows examples of each utility.

### Chapter 5. Daemon Utilities for Infoprint Manager for AIX

This chapter describes the utilities that start Infoprint daemons.

### Chapter 6. Infoprint Transform Commands

This chapter describes the transforms used for converting data for printing with Infoprint.

### Chapter 7. Infoprint Object Attributes

This chapter describes the use and values of the attributes associated with each Infoprint object class.

### **Chapter 8. Infoprint Environment Variables**

This chapter describes the Infoprint and AIX environment variables that affect the processing of Infoprint commands.

### **Chapter 9. Notification Events and Event Classes**

This chapter describes the Infoprint events for which you can request notification.

### **Appendix A. Attribute-to-Object Listing**

This appendix contains a table listing all the Infoprint attributes in alphabetical order and naming the objects that support each attribute.

### **Appendix B. Migrating PSF for AIX Job Script Keywords to Infoprint Equivalents**

This appendix contains a table showing the attribute, or the flag or argument of the **pdpr** command, that replaces each PSF job script keyword when the job script is migrated to Infoprint.

### **Appendix C. Job Validation and Scheduling**

This appendix describes how Infoprint validates and schedules jobs. It contains tables showing the attributes used for validation and scheduling.

### **Appendix D. Form Definitions and Page Definitions Supplied with Infoprint**

This appendix lists the form definitions and page definitions supplied with Infoprint.

This publication also contains a glossary and an index.

---

## **Conventions Used in This Publication**

This publication uses conventions for the following:

- Highlighting
- Infoprint command notation

### **Highlighting**

This publication uses four different types of highlighting:

**Bold** In this publication, bold highlighting identifies commands, attributes, files, directories, and other items whose names the system predefines, such as **pdpr** and **notification-profile**.

*Italic* When used in running text, italic highlighting identifies a variable item whose actual name or value you supply, such as *AttributesFileName* or *Notification*. Italics also identify publication titles.

**Bold Italic**

When enclosed in double quotation marks, combined bold and italic highlighting identifies a specific attribute name that you enter exactly as shown and a variable value that you supply with the attribute. For example: **"copy-count=number"**



## Monospace

When used in command examples, information in a monospaced font identifies the exact wording of the command.

## Infoprint Command Notation

Command syntax notation uses symbols to show specific conditions. Do not enter the following symbols, unless specifically instructed to do so, when actually issuing a Infoprint command:

**Bar** |

**Braces**

{ }

**Note:** There are some situations in which you will actually type the brace characters. See “Special Characters That Are Included in Commands” on page xl.

**Brackets**

[ ]

**Underlining**

—

**Ellipsis**

...

These symbols have the following meanings when used in the publications and in the online information:

- A vertical bar, |, between values means that you can only enter one of the values with the command. For example:

**job-hold:= {true | false}**

means that when you set the **job-hold** attribute, you can specify either **true** or **false**, but not both.

- Braces, { }, around values identify required items that you must supply with the command. For example:

**job-hold:= {true | false}**

means that you must enter either **true** or **false**.

- Brackets, [ ], around values indicate that they are optional. For example:

**resource-context=directory[:directory...]**

means that you do not have to enter more than one directory, but that you can have two or more directories, each separated by a colon, : .

- An ellipsis, ... , means that you can supply more than one occurrence of a keyword or value with the command. For example:

**resource-context=directory[:directory...]**

means that you can enter more than directory name.

- Underlined text identifies the default fixed value that Infoprint uses if you do not specify a value. For example:

**default-printer-resolution={240 | 300 | 480 | 600}**

means that **240** is the default value.

## Special Characters That Are Included in Commands

When colons, dashes, the equals sign, double quotation marks, single quotation marks, and braces are shown in command syntax notation, you will include them when you issue the command in most cases. These special characters have the following meanings:

- A colon, `:`, separates related values. For example:

```
pdpr -f file1 -x "page-select=3:6" file2
```

means that only pages 3 through 6 of `file2` are to print.

- A dash, `-`, always precedes a flag, for example, `-x`.
- The equals sign, `=`, separates attribute and value pairs. For example:

```
pdmod -x "sides=2" DivSpool12:1011230045
```

means that **2** is the value assigned to the **sides** attribute.

- Double quotation marks, `" "`, surround multiple attribute and value pairs, such as:

```
-x "sides=2 print-quality=draft"
```

For consistency, this publication also shows double quotation marks around single attribute and value pairs in all command examples, although they are not required. For example:

```
-x "document-format=ascii"
```

- Double quotation marks, `" "`, surround text strings that contain spaces, such as:

```
-m "Down for maintenance"
```

- Single quotation marks, `' '`, surround a text string that contains spaces inside another string that is enclosed in double quotation marks. An example is:

```
-x "sides=2 job-print-after='08:00:00 10/09/98'"
```

- Braces, `{ }`, surround a value in a notification profile. An example is:

```
-x "notification-profile={delivery-method=electronic-mail}"
```

### Global Character Used in Examples and Shell Information

The examples using a global character and other examples shown within the Infoprint publications relate to the Korn shell. Depending on the shell you are using, the examples shown may or may not work. The examples may also show control characters that other shells do not require. Adjust the examples as necessary for the shell you are using.

### Examples of Commands and Attributes

- This publication shows examples of commands in a format designed for ease of reading. When entering the command, allow the command to wrap characters from one line to the next.
- Many examples in this publication use spacing of attributes and values for ease of reading and formatting considerations. When entering the attributes and their values on the command line or in attributes files, use the correct syntax.

# Chapter 1. Introduction

Infoprint Manager for AIX allows you to send a file, as an electronic document, for printing on a printer device or for transmission by fax or electronic mail; and Infoprint Manager for Windows NT and Windows 2000 allows you to send a file, as an electronic document, for printing on a printer device.

This book was originally written for Infoprint Manager for AIX. Because of the commonality between Infoprint Manager for AIX and Infoprint Manager for Windows NT and Windows 2000, this book now documents both products with an admitted slant on the AIX side for such things as examples and path names. (See “Reference Table for Path Names” for a table that lists the NT and 2000 paths with the AIX paths used in this book.) An effort has been made to indicate significant differences between the two platforms, especially in “Chapter 7. Infoprint Object Attributes” on page 325. For example, Infoprint Manager for Windows NT and Windows 2000 does not support tape.

## Reference Table for Path Names

AIX Path	NT or 2000 Path
<code>/usr/lpp/psf/ps/psfonts.map</code>	<code>install_path\ps\fonts.map</code>
<code>/usr/lpp/psf/psf/bin/db2afp</code>	<code>install_path\bin\db2afp.exe</code>
<code>/usr/lpp/psf/db2afp/afpdfont.rc</code>	<code>install_path\bin\afpdfont.rc</code>
<code>/usr/lib/nls/loc/iconv/ConverterName</code>	<code>install_path</code>
<code>/usr/lpp/psf/jpeg2afp/jpeg2afp.cfg</code>	<code>install_path\</code>
<code>/usr/lpp/psf/reslib</code>	<code>install_path\reslib</code>
<code>/usr/lpp/afpfonts</code>	<code>install_path\fontlib</code>
<code>/usr/lpp/psf/fontlib</code>	<code>install_path\fontlib</code>
<code>inpexit=/usr/lpp/psf/bin/apka2e</code>	<code>inpexit=c:\Program Files\IBM Printing Systems\bin\apka2e</code> , which assumes you installed in the default path
<code>inpexit=/usr/lpp/psf/bin/asciinpe</code>	<code>inpexit=c:\Program Files\IBM Printing Systems\bin\asciinpe</code> , which assumes you installed in the default path
<code>inpexit=/usr/lpp/psf/bin/asciinp</code>	<code>inpexit=c:\Program Files\IBM Printing Systems\bin\asciinp</code> , which assumes you installed in the default path
<code>formdef=memo userlib=/usr/afp/resources</code>	<code>formdef=memo userlib=d:\afp\resources</code>
<code>formdef=memo fdeflib=/usr/lib/formdefns</code>	<code>formdef=memo fdeflib=d:\lib\formdefns</code>
<code>pagedef=memo userlib=/usr/afp/resources</code>	<code>pagedef=memo userlib=d:\afp\resources</code>
<code>pagedef=memo pdeflib=/usr/lib/pagedefns</code>	<code>pagedef=memo pdeflib=d:\lib\pagedefns</code>
<code>/usr/lpp/psf/bin/line2afp</code>	<code>install_path\bin\line2afp.exe</code>
<code>/usr/lpp/psf/bin/acif</code>	<code>install_path\bin\acif.exe</code>
<code>/usr/lpp/psf/acif/apkinp.c, apkind.c, apkres.c, apkout.c, apka2e.c, ascinnp.c</code>	<code>install_path\exits\acif\apkinp.c, apkind.c, apkres.c, apkout.c, apka2e.c, ascinnp.c</code>
<code>/usr/lpp/psf/bin/apka2e, apkin, apkind, apkres, apkout, apka2e, ascinp, ascinpe</code>	<code>install_path\bin\apka2e.dll, apkin.dll, apkind.dll, apkres.dll, apkout.dll, apka2e.dll, ascinp.dll, ascinpe.dll</code>

## Introduction

/usr/lpp/psf/acif/apkexits.h	install_path\exits\acif\apkexits.h
/usr/lpp/psf/bin/Makefile	No NT or 2000 equivalent
No AIX equivalent	install_path\exits\acif\apka2e.dsw, apkinp.dsw, apkind.dsw, apkres.dsw, apkout.dsw, apka2e.dsw, asciinp.dsw, ascinnpe.dsw (Microsoft Visual C++ 6.0 Workspaces for the user exits)
No AIX equivalent	install_path\exits\acif\apka2e.dsp apkinp.dsp apkind.dsp apkres.dsp apkout.dsp apka2e.dsp asciinp.dsp ascinnpe.dsp (microsoft Visual C++ 6.0 Project files for the user exits)
/usr/lpp/psf/pcl2afp	install_path\pcl2afp
/usr/lpp/psf/pcl2afp/pcl2afp.cfg	install_path\pcl2afp\pcl2afp.cfg
/usr/lpp/psf/pcl2afp/custom.cfg	install_path\pcl2afp\custom.cfg
/usr/lpp/psf/pcl2afp/custom.cfg	install_path\pcl2afp\custom.cfg
/usr/lpp/psf/pcl2afp/pcl2afpd.cfg	install_path\pcl2afp\pcl2afpd.cfg
/usr/lpp/psf/pcl2afp/myfile.cfg	d:\pcl\myfile.cfg
/usr/lpp/psf/pcl2afp/gl_before.pcl myfile.g1 /usr/lpp/psf/pcl2afp/gl_after.pcl	install_path\pcl2afp\gl_before.pcl myfile.g1 install_path\pcl2afp\gl_after.pcl
/usr/lpp/psf/pcl2afp/sample.pcl	install_path\pcl2afp\sample.pcl
/usr/lpp/psf/bin/pcl2afp	install_path\bin\pcl2afpd.exe
/usr/lpp/psf/bin/pcl2afpd	install_path\bin\pcl2afpd.exe
/usr/lpp/psf/bin/ppxpcli	install_path\bin\ppxpcli.exe
/usr/lpp/psf/bin/ppxpclis	No equivalent on NT
/usr/lpp/psf/pcl2afp/pcl2afp.cfg	install_path\pcl2afp\pcl2afp.cfg
/usr/lpp/psf/pcl2afp/pcl2afpd.cfg	install_path\pcl2afp\pcl2afpd.cfg
/var/psf/pcl2afp	install_path\var\psf\pcl2afp
/usr/lpp/psf/ps2afp/ps2afp.cfg	install_path\ps2afp\ps2afp.cfg
/usr/lpp/psf/ps2afp/ps2afpd.cfg	install_path\ps2afp\ps2afpd.cfg
/usr/lpp/psf/bin/ps2afp	install_path\bin\ps2afp
/usr/lpp/psf/bin/ps2afpd	install_path\bin\ps2afpd
/usr/lpp/psf/bin/pdf2afp	install_path\bin\pdf2afp
/usr/lpp/psf/bin/ppxps2i	install_path\bin\ppxps2i
/usr/lpp/psf/bin/ps2afpi	install_path\bin\ps2afpi.vm
/usr/lpp/psf/bin/ps2afpi.vm	install_path\bin\ps2afpi
/usr/lpp/psf/bin/ppxps2	install_path\bin\ppxps2
/usr/lpp/psf/bin/ps2afp.ps	install_path\bin\ps2afp.ps
/usr/lpp/psf/bin/ps2afpe.ps	install_path\bin\ps2afpe.ps
/usr/lpp/psf/bin/fontsave	install_path\bin\fontsave
/usr/lpp/psf/psfonts.map	install_path\bin\psfonts.map
/var/psf/psfonts	install_path\var\psfonts
/usr/lpp/psf/tiff2afp/tiff2afp.cfg	install_path\tiff2afp\tiff2afp.cfg
/var/psf/podaccount.log	install_path\var\psf\podaccount.log

`/var/psf/audit.log``install_path\var\psf\audit.log`

## Objects

Infoprint performs the management and printing or transmission of jobs by using **Infoprint objects**.

## Object Classes

Table 1 lists the object classes that Infoprint supports. The destination class is subdivided into logical and actual destinations.

Table 1. Infoprint Objects

Object Name	Purpose
Auxiliary sheet	Represents a sheet of paper, blank or otherwise, that precedes a job, separates copies within a job, or follows a job; or a user exit program that produces output that can be printed on an auxiliary sheet or logged.
Default document	Represents default attribute values for a document within a job. Also called <i>initial value document</i> .
Default job	Represents default attribute values for a job. Also called <i>initial value job</i> .
Destination (actual)	Represents the output device that Infoprint uses to print or transmit the job. It is not the actual output device. It is a software representation of the features and capabilities of the printer or fax hardware device, or of an electronic mailing system.  <i>A physical printer</i> is an actual destination that represents a printer device. <i>A fax destination</i> represents a fax device. An <i>email destination</i> represents an electronic mailing system.
Destination (logical)	Represents an abstract entity to which users submit jobs for printing or transmission. The logical destination provides restrictions and defaults for the job. It also verifies that associated actual destinations capable of handling the jobs exist. Once the logical destination verifies the job, Infoprint sends it to an associated queue, from which it is routed to an actual destination.  The term <i>logical printer</i> is used for logical destinations that route jobs to physical printers.
Document	Represents a grouping of data within a job: either a printable file or a resource that is not printable by itself, for example, a font.
Job	Represents one or more documents submitted together in one request.
Log	Represents a collection of messages or message segments added to a file for data collection purposes. Infoprint uses two types of logs: error and trace.
Medium	Represents the physical material on which a job prints.

## Introduction

Table 1. Infoprint Objects (continued)

Object Name	Purpose
Queue	Manages a collection of jobs that are waiting to be printed or transmitted and jobs that have been retained after processing. A queue receives jobs from one or more logical destinations and schedules and sends the jobs to actual destinations.
Resource context	Contains directory path information that is used to locate resources needed for processing a job. Resources include fonts, overlays, form definitions, page segments, and page definitions.
Server	Manages and controls the validation, routing, notification, logging, scheduling, and printing or transmission of jobs. The server applies specified defaults to jobs, validates that the destinations on the network can process the jobs, schedules jobs from queues to actual destinations, directs jobs to the actual destination, reports errors, and reports job status.
Transform	Indicates how specific document formats sent to an associated actual destination are to be transformed before printing or storing.

## Object Name Restrictions

The following restrictions apply to naming Infoprint objects:

- You can specify object names up to 255 characters in length, except for the names of PSF physical printers, fax destinations, and email destinations, which you must limit to eight characters or less.
- Characters allowed in object names include uppercase A through Z, lowercase a through z, digits 0 through 9, and the special characters hyphen or dash, -, period, ., and underscore, \_ . Do not start an object name with a hyphen.
- Names for servers used with SAP systems should restrict their server names to nine characters.

## Object Attributes

All Infoprint objects have associated attributes. Attributes provide information about the objects and determine what you can do with objects.

### Attribute Disclaimer

There are attributes and attribute values identified in the ISO 10175-1 *Information Technology Text and Office Systems - Document Printing Application (DPA) - Part 1: Abstract-Service Definition and Procedures* standard that Infoprint does not support. If you use any of these non-supported attributes or values, Infoprint may accept them. However, the results may be different than you expect. At times you may receive a message stating that Infoprint does not support the attribute or value.

## Initially Settable, Resettable Attributes, and Non-Settable

Infoprint attributes fall into three categories:

**Initially settable**

For some attributes, you can set a value when you create the object with the **pdcreate** or the **pdpr** command. You cannot change these attributes afterwards.

For example, the following command:

```
pdpr -x "job-originator='Anne Brown'" -d Sevv1-ld bigbook
```

creates a job containing a file called bigbook and identifies the person who submitted the job by name. The attribute **job-originator** is *initially settable* and you cannot change it.

**Resettable**

For some attributes, you can set or modify the value using the **pdmod** command (for jobs and documents) or the **pdset** command (for all objects, including jobs and documents), after you create the object.

For example, this command:

```
pdmod -x "job-end-message='Please call 5-9999 for pickup'" 37
```

sets a new value for the **job-end-message** attribute for the existing job whose local ID is 37.

**Non-settable**

You cannot set a value for some attributes at any time.

For example, in the following command:

```
pdcreate -c queue Serv1:Queue3
```

Infoprint uses the command arguments to assign the queue attribute **queue-name** the value Queue3, and the **associated-server** attribute the value Serv1. You cannot set different values for these arguments using the **-x** flag of the **pdcreate** command and you cannot change them later.

**Resetting Attributes to the Default Value**

“Chapter 7. Infoprint Object Attributes” on page 325 shows default values for all attributes. For some attributes, the default value is “no value”.

- When you create an object, Infoprint assigns a default value (or values, for some multi-valued attributes) to each attribute. You can override these default values by specifying a different value using the **-x** and **-X** flags of the **pdmod** or **pdset** commands.
- You can change values back to their default values by using the **pdmod** or **pdset** commands and specifying the attribute name followed by two equals signs, **==**, without any attribute value.

For example, the following command:

```
pdset -x "printer-end-sheet==" Serv3-pp
```

sets the value assigned to **printer-end-sheet** for the actual destination Serv3-pp back to its default value.

- Deleting all the values from a multi-valued attribute or deleting the value of a single-valued attribute sets the attribute value to the default values.

**Attribute Syntax**

This section describes the syntax to use when you set values for three types of attributes on the command line or in an attributes file. Most attributes are either **single-valued** (they can have only one value at a time) or **multi-valued** (they can have multiple values). Infoprint also has some **complex attributes**.

## Introduction

Examples of these types of attributes follow.

**Single-Valued Attributes:** For single-valued attributes, the syntax is:

```
"attribute=value"  
"attribute='value with spaces'"
```

Enclose the value in single quotation marks if it includes spaces, for example:

```
-x "message='Down for maintenance until 7AM'"
```

**Note:** The Infoprint administrator's GUI does not require quotation marks.

**Multi-Valued Attributes:** For multi-valued attributes, the syntax is:

```
"attribute=value1 value2 value3"
```

where *value1 value2 value3* are multiple values of the attribute. Separate the values with spaces and enclose the attribute name and values in double quotation marks. For example:

```
-x "content-orientations-supported=portrait landscape"
```

assigns two values, **portrait** and **landscape**, to the **content-orientations-supported** attribute.

**Note:** In the Infoprint administrator's GUI, most multi-valued attributes require you to specify each value on a separate line of a list box. When you must enter multiple values in a single field, separate the values by commas. For example, enter multiple values for the **chars** attribute like this:

Fonts

**Complex Attributes:** Complex attributes can have multiple values, but each value itself has multiple components. Each component of a value has its own values. Two types of complex attributes are those that require braces, { }, enclosing each value, and those that have the components of each value separated by a colon, : .

**Note:** In the Infoprint administrator's GUI, you enter each component in a separate field. No braces or colons are required.

**Complex Attributes that Require Braces:** The only complex attribute that requires braces is **notification-profile**

- Each value for this complex attribute begins and ends with braces, { } .
- Each value has several components
- Each component has a name and associated values
- The sequence in which you enter the components is not important
- The component **event-identifiers** is the only component that can have multiple values

An example of creating a **notification profile** with one value for a queue follows:

```
pdset -c queue  
-x "notification-profile={event-identifiers=job-modified  
queue-state-changed delivery-method=message  
event-comment='This is a job modification or status event'  
delivery-address=dave@cowboy locale=En_US.IBM-850}" Queue1
```



If you change one component within the notification profile, Infoprint sets all the rest of the components of that value to their default values. For example, the following command sets the **delivery-address**, but Infoprint sets the other components to their defaults:

```
pdset -c queue
-x "notification-profile={delivery-address=tom@hope}" Queue1
```

If you want to maintain the existing values, you must specify them. You cannot use the add, +=, or delete, -=, operators of the **pdset** or **pdmod** commands when changing the component values within a **notification-profile** value. However, you can add or delete all components of a value from the **notification-profile** by using the add, +=, or delete, -=, operators. For example, the following command:

```
pdset -c queue
-x "notification-profile+={delivery-address=mary@cowboy} Queue1
```

adds another value to the previous one. Now the **notification-profile** has two values.

```
notification-profile=
{event-identifiers=job-modified queue-state-changed delivery-method=message
event-comment='This is a job modification or status event'
delivery-address=dave@cowboy locale=En_US.IBM-850}

{event-identifiers=object-deleted object-cleaned queue-backlogged
delivery-method=message delivery-address=mary@cowboy
locale=En_US.IBM-850}
```

The second value contains default values for each component except the delivery address. If you want values other than defaults, you must specify them.

*Complex Attributes that Require Colons:* All other complex attributes require colons between components.

- Do not enter the component name.
- Separate the values for the components with a colon, :, and no spaces
- Enter a colon even if you do not enter a value for a given component. Infoprint sets the default value or no value for that component.
- If you use the default value for the last value, Infoprint does not require the colon for that component.
- Separate each attribute value within a multi-valued attribute with spaces (see the following example)

An example of setting the **notify-operator** attribute for a queue is:

```
pdset -c queue -x "notify-operator=
message:White@Caddy.xyz.com email:Jones@Chevy.xyz.com"
Queue2
```

Examples of setting the **results-profile** attribute for a job are:

```
pdset -c job -x "results-profile='dave@cowboy:pickup:2:Please staple'" 2
pdset -c job -x "results-profile='dave@cowboy::2:Please staple'" 2
```

The result of these two commands is the same because the default for the second component is **pickup**.

---

## Commands

Infoprint commands act on objects. They create, modify, and delete objects, and may also return status and other information about the Infoprint objects.

## Introduction

# Flags, Command Attributes, and Arguments

The basic Infoprint command syntax is:

```
command [-flag ...] [argument ...]
```

The *argument* targets the specific object on which the Infoprint command operates. Most commands must include an *argument*. All commands can include one or more of the following:

**Flags** Flags consist of a dash, - , followed by a single character. Flags either substitute for command or object attributes or modify the way Infoprint processes a command. For example, you can use the **-c** flag instead of the **class** command attribute. Some flags have values associated with them.

Use the **-x** and the **-X** flags to enter command attributes or object attributes on the command line or to read in a file containing those attributes at a specific point in the command.

### Command attributes

Use command attributes to modify the action of the command and to define the object class on which the command operates. Most of the command attributes have an associated command flag that causes the same action. You cannot use a command flag in an attributes file. You can use the command attribute in an attributes file or on the command line using the **-X** flag or the **-x** flag respectively.

When you enter an attribute and value pair, you must specify the attribute followed by the equals sign, = , followed by the value; do not include spaces between these three items unless you enclose the items in quotation marks. For example, Infoprint accepts both the *class=destination* and "*class = destination*" formats.

You must begin and end a string of multiple attribute-value pairs with double quotation marks, for example:

```
pdls -x "class=job requested-attributes=current-job-state" 10
```

### Object attributes

Use object attributes to apply attribute values to the specified argument. You can use the object attribute in an attributes file or on the command line using the **-X** flag or the **-x** flag respectively.

When you enter an attribute and value pair, you must specify the attribute followed by the equals sign, = , followed by the value.

You must begin and end a string of multiple attribute-value pairs with double quotation marks, for example:

```
pdpr -x "document-format=ascii sides=2 plex=simplex" File1
```

### Arguments

The argument specified in a command is the name of the object the command acts on. For servers, the argument is the name of the server. Servers contain all other objects. For some objects, you must specify the name of its server in the form *ServerName:ObjectName*. For other objects, the server name is optional. You must look at each command to determine the exact format allowed.

If you specify multiple arguments in one command, they must belong to the same object class.

## Command Output: Headings and Style

Some commands allow you to specify whether you want the output displayed in line style, column style, or document column style, and whether you want the output displayed with or without headings. Document column (**doccol**) style is a variant of column style used only for jobs. It is like column style except that the attributes for the first document in the job are displayed on the same line as the job attributes, rather than on a separate line as in column style.

The following examples show the same information (the **current-job-state** and **destination-name-requested** attributes for a job, plus the **document-format** and **copy-count** attributes for the first document in the job) in the six possible combinations of headings and style:

- Line style, with headings:

```
jw-srv:0524600000: current-job-state           = held
jw-srv:0524600000: destination-name-requested = jw-lp1
jw-srv:0524600000.1: document-format         = ascii
jw-srv:0524600000.1: copy-count              = 1
```

- Line style, without headings:

```
current-job-state           = held
destination-name-requested = jw-lp1
document-format            = ascii
copy-count                 = 1
```

- Column style, with headings:

```
Current  Destination
State    Requested
-----  -
held     jw-lp1
```

```
Format  Copies
-----  -
ascii   1
```

- Column style, without headings:

```
held jw-lp1
```

```
ascii 1
```

- Document column style, with headings:

```
Current  Destination
State    Requested  Format  Copies
-----  -
held     jw-lp1     ascii  1
```

- Document column style, without headings:

```
held jw-lp1 ascii 1
```

## Tips for Using Commands

Understanding the following topics can make your use of, and entry of, commands easier.

### Wildcards

You can use the global character, an asterisk, `*`, to simplify broadcasting commands to all servers. For example, `STU*` sends the command to all servers whose names begin with the letters STU. When the global character is present in the *ServerName*, Infoprint sends the command to each of the servers that match the specified criterion.

## Introduction

Depending on the shell you are using, you may need to enter control characters to keep the shell from interpreting the asterisk, \*, before Infoprint has a chance to operate on it.

### Abbreviations

This publication shows attribute names and values in their complete form. Often, you can abbreviate attribute names and values by using the first letter of each word in the name or value. For example, you can use the abbreviation **s-m-s** for the **start-message-supported** attribute, **t** for the **true** value, and specify the attribute and value pair as **s-m-s=t**.

However, sometimes specifying only the first letter in each word is ambiguous, as for the attributes **job-owner** and **job-originator**. Here, specify enough of the name so that it is unique, as in **j-ow** and **j-or**. If the values are ambiguous, Infoprint rejects the command and issues an error message. Use abbreviated attribute names and values as appropriate.

### Attributes File

You may want to predefine specific attribute and value pairs in permanent files and access them when you need those specific values within a command. These files can contain command attributes, object attributes, or both.

#### *Creating an Attributes File:*

- You can list command attributes and any initially settable or resettable object attributes in an attributes file, including the command attribute **attributes**. Thus, an attributes file can invoke other attributes files.

**Note:** If an attributes file calls itself, Infoprint issues an error.

- You can only use a file that contains initially settable attributes with the **pdcreate** or **pdpr** commands. If you include an initially settable attribute in an attributes file and use the file with the **pdset** or **pdmod** commands, Infoprint rejects the attribute and issues an error message.
- Attributes files must not contain any attributes without values.
- When creating an attributes file, consider spelling out the complete attribute names and attribute values rather than using abbreviations.
- You can use spaces between the attribute name and the equals sign to align the equals sign and values. This makes your files easier to read and maintain.
- You can use comment lines in attributes files. The comment starts with a number sign, #, and ends at the end of line.

For example, an attributes file used to set two-sided printing and to request a specific printer model contains these lines:

```
# These are my document attributes
sides = 2
destination-models-requested = 4019 # 4019 printer only
```

**Note:** You can include a number sign, #, as part of an attribute value if you precede it immediately with a backslash, \#.

**Using an Attributes File:** Infoprint provides both a command attribute and a flag to read an attributes file into a command.

*Command Attribute:* **-x "attributes=AttributesFileName"**

You use the **-x** flag to specify the command attribute **attributes**. This attribute designates and causes Infoprint to read and use an attributes file, which contains

attribute and value pairs (one or more per line), at the current point in the command. Specifying this attribute is equivalent to using the **-X** flag.

*Flag: -X AttributesFileName*

This causes Infoprint to read and use the designated attributes file containing attribute and value pairs at the current point in the command.

The following two examples are equivalent:

```
pdset -X AttrFileAD1.X Serv2-pp
pdset -x "attributes=AttrFileAD1.X" Serv2-pp
```

Using the command attribute **attributes** or the **-X** flag to designate and read an attributes file has the same effect as specifying multiple attribute and value pairs using the **-x** flag. These attributes require the same syntax as those used with the **-x** flag. For example, both of the previous examples reference the following attributes file:

```
# Actual Destination Attributes File
# AttrFileAD1.X
document-formats-supported =ascii ditroff modca-p
maximum-copies-supported   =3
document-types-supported   =printable overlay page-segment
printer-memory              =32
```

It is equivalent to the following command:

```
pdset -x "document-formats-supported=ascii ditroff modca-p
maximum-copies-supported=3 document-types-supported=printable
overlay page-segment printer-memory=32" Serv2-pp
```

The **-X** and **-x** flags are additive so that Infoprint uses all attributes and values. If you specify the same object attribute more than once in a command with multiple uses of the **-x** and **-X** command flags or the **attributes** command attribute, or a combination of them, the value read last takes precedence.

**Locating an Attributes File for Infoprint Manager for AIX:** If you do not specify a full path name for the attributes file, Infoprint uses the path name from the environment variable **PDPATH** to locate the attributes file. If you do not define **PDPATH** or it contains a null string, Infoprint looks in your current working directory for the attributes file.

For example, if **PDPATH** contained **/usr/user/smith/** the following command:

```
pdpr -X my_attributes.X File1
```

would read the file **/usr/smith/my\_attributes.X** to obtain the attribute and values.

**Note:** For Infoprint Manager for Windows NT and Windows 2000, you must specify the full path.

---

## Administrative Utilities

Infoprint administrative utilities perform such tasks as setting up a minimum Infoprint configuration, starting servers, and displaying information about Infoprint messages.

### Daemon Utilities for Infoprint Manager for AIX

Infoprint has some special utilities for starting daemons. Daemons are often called by the same name as the utility that starts them. For example, the daemon that receives data from MVS Download is called the **mvsprsd** daemon, or simply **mvsprsd**.

---

### Transform Commands

Infoprint transform commands convert another data stream to the AFP data stream. You can allow Infoprint to invoke these transforms automatically, or you can invoke them yourself.

Some transforms use options instead of flags. Like flags, options begin with a dash, - , and modify the way Infoprint processes the transform. Unlike flags, options may have more than one character following the dash.

---

### Environment Variables for Infoprint Manager for AIX

Infoprint and AIX environment variables affect the way that Infoprint processes commands and utilities. These environment variables are summarized in “Chapter 8. Infoprint Environment Variables” on page 651.

---

### Windows Services for Infoprint Manager for Windows NT and Windows 2000

Infoprint Manager for Windows NT and Windows 2000 uses Windows Services for many functions, including the Infoprint server, Notification, IPP, and MVS download.

## Chapter 2. Infoprint Commands

This chapter describes the following Infoprint commands:

Command Name	AIX	NT and 2000
"lprafp Command: Submits Remote Jobs in Infoprint Manager for AIX" on page 15	AIX	N/A
"mkfntmap Command: Maps PostScript Fonts" on page 17	AIX	NT and 2000
"pdaccount Command: Collect Accounting Information for a Specific Time Period" on page 19	AIX	N/A
"pdclean Command: Removes All Jobs from the Specified Object" on page 22	AIX	NT and 2000
"pdcreate Command: Creates Infoprint Objects" on page 25	AIX	NT and 2000
"pddelete Command: Deletes Infoprint Objects" on page 30	AIX	NT and 2000
"pddisable Command: Stops Destinations from Accepting Jobs and Logs from Logging" on page 34	AIX	NT and 2000
"pdenable Command: Enables Destinations to Accept Jobs and Logs to Log" on page 37	AIX	NT and 2000
"pdl Command: Lists Selected Attribute Values" on page 40	AIX	NT and 2000
"pdmod Command: Modifies Attributes of Submitted Print Jobs" on page 51	AIX	NT and 2000
"pdpause Command: Pauses Jobs, Actual Destinations, Servers, or Queues" on page 56	AIX	NT and 2000
"pdpr Command: Submits Jobs" on page 63	AIX	NT and 2000
"pdpromote Command: Advances a Job to the Top of a Queue" on page 72	AIX	NT and 2000
"pdq Command: Queries Job Status" on page 74	AIX	NT and 2000
"pdreorder Command: Reassigns Jobs" on page 79	AIX	NT and 2000
"pdresubmit Command: Resubmits Jobs" on page 81	AIX	NT and 2000

## Commands

"pdresume Command: Enables Paused Objects to Resume Operation" on page 85	AIX	NT and 2000
"pdrm Command: Removes Jobs" on page 88	AIX	NT and 2000
"pdset Command: Defines Attribute Values" on page 91	AIX	NT and 2000
"pdshutdown Command: Stops Servers or Actual Destinations" on page 96	AIX	NT and 2000
"pdspace Command: Backspaces or Forward Spaces a Printer" on page 100	AIX	NT and 2000

**Note:** The **psfstat** command for displaying information about Infoprint destinations and PSF Direct receivers is documented in *PSF Direct Network Configuration Guide for System/370* and the **psfstat** man page.



## lprafp Command: Submits Remote Jobs in Infoprint Manager for AIX

### Syntax

```
lprafp [-n] [-o option] [-r retries] [-q delay] [-p destination]
      [-s server] FileName ...
```

### Description

The **lprafp** command, when compiled on a UNIX client system, allows UNIX users operating on AIX 3.2.5 or higher, non-AIX systems, or non-RS/6000 systems to pass **-o** flag keywords to Infoprint for use in printing or transmitting remote jobs. The **-o** flags that are interpreted by Infoprint can be sent with the remote job.

You can submit a job using a shell script called **LPR**. When you invoke **LPR** with the **-A** flag, **LPR** invokes the **lprafp** command. **lprafp** passes **-o** keywords to Infoprint. If you invoke the **LPR** shell script without the **-A** flag, **LPR** invokes the operating system's standard print command.

### Flags

- n** Indicates that only error messages display when the output is processed. If you do not specify this flag, you receive status information on the job sent to the destination system.
- o option**  
Indicates Infoprint options, for example:  
-oformdef=F1SAMPLE  
  
See "Chapter 3. The -o Flag for AIX Print Commands" on page 103 for descriptions of the **-o** options.
- r {3 | retries}**  
Indicates how many times the **lprafp** program attempts to connect with the TCP/IP line printer daemon (**lpd**) on the destination system. This flag defaults to three retries.
- q {10 | delay}**  
Indicates the retry delay in seconds. This flag defaults to ten seconds.
- p destination**  
Indicates the destination name on the server. This flag defaults to the value of the **LPR\_PRINTER** environment variable.
- s server**  
Specifies the destination server. This flag defaults to the value of the **LPR\_SERVER** environment variable.

### Arguments

Use the argument value to identify the specific files you want to submit for printing or transmission. If you specify multiple objects, separate the object names with spaces.

You can use the following arguments with the **lprafp** command:

*FileName ...*

Indicates the files that are to be printed or transmitted. You can specify global file characters in this argument.

## lprfp

### Examples

#### Submitting a Remote Print Job

To submit two copies of `/etc/motd` to the logical printer named `laser` on server `alexandria`, for printing without an end sheet, enter:

```
LPR -A -ocopies=2 -otrailer=no -s alexandria -p laser /etc/motd
```

#### Submitting a Remote Email Job

To send the file `memo1` to the logical destination mailbox on server `alexandria`, enter:

```
LPR -A -s alexandria -p mailbox memo1
```

**Note:** The default document associated with mailbox must specify the **email-to-address** attribute.

#### Setting Environment Variables

To set up the environment so that subsequent print requests are sent to the logical destination named `alexe-lp` on server `alexandria`, enter:

```
export LPR_PRINTER=alexe-lp
export LPR_SERVER=alexandria
```

(Note that *server* can be in dotted address format; for example 9.99.9.99)

To test that your environment variables have been set correctly, enter:

```
LPR -A /etc/motd
```

### Files

<b>/usr/lpp/psf/utils/lpr/Makefile</b>	Generates the executable program
<b>/usr/lpp/psf/utils/lpr/getopts.c</b>	Source code
<b>/usr/lpp/psf/utils/lpr/getopts.h</b>	Source code header file
<b>/usr/lpp/psf/utils/lpr/LPR</b>	Shell script for print command
<b>/usr/lpp/psf/utils/lpr/lprfp.c</b>	Source code
<b>/usr/lpp/psf/utils/lpr/lprfp.h</b>	Source code header file

## mkfntmap Command: Maps PostScript Fonts

### Syntax

```
mkfntmap inputfile ... [> outputfile]
```

### Description

The **mkfntmap** command creates a font mapping file that contains a list of the PostScript Type 1 fonts specified in the *inputfiles* parameter of the command and their locations.

Infoprint Manager for AIX includes the **/usr/lpp/psf/ps/psfonts.map** file.

Infoprint Manager for Windows NT and Windows 2000 includes the **install\_path\ps\fonts.map** file.

The font map file maps the AFP outline fonts to the directory in which they were installed. If you have additional PostScript fonts or you add new PostScript fonts, use the **mkfntmap** command to create a font mapping file for the new fonts after they are installed.

If you will be using the additional fonts frequently, you should add the fonts to the **preload.ps** file in the **/usr/lpp/psf/ps** directory for Infoprint Manager for AIX.

If you will be using the additional fonts frequently, you should add the fonts to the **preload.ps** file in the **install\_path\ps** directory for Infoprint Manager for Windows NT and Windows 2000.

The fonts you specify in the **preload.ps** file load before transform processing begins, improving the performance of the PostScript transform.

**Note:** With Infoprint Manager for AIX, the Courier font must exist in at least one of your font mapping files. It is included in the font mapping file, **/usr/lpp/psf/ps/psfonts.map** for Infoprint Manager for AIX and the **install\_path\ps\fonts.map** for Infoprint Manager for Windows NT and Windows 2000.

### Arguments

The argument value identifies the specific object to which the command applies.

The valid argument values for the **mkfntmap** command are:

*inputfile* ...

Specifies the name of the file or files that contain PostScript Type 1 fonts. At least one input file is required, although you can list more than one.

*outputfile*

Specifies the name of the font mapping file that contains the font mapping for the PostScript Type 1 fonts that were specified in the *inputfiles*. When the output file is created, it can be specified in the **ps2afpd** daemon and **ps2afp** command configuration files. You also can specify the *outputfile* name from the command line with the **-F** flag of the **ps2afp** command. If you do not specify an *outputfile* name, Infoprint writes the results to standard output.

## mkfntmap

### Examples

- To create a font mapping file of all binary fonts named atm\*, which have the extension .pfb, and call it atmfonts.map, enter:  

```
mkfntmap atm*.pfb > atmfonts.map
```
- To create a font mapping file of all fonts named cou\*, and call it courier.map, enter:  

```
mkfntmap cou* > courier.map
```

## pdaccount Command: Collect Accounting Information for a Specific Time Period

### Syntax

```
pdaccount [-c server]
           {-t destination | user | all}
           [ -s StartTime] [-e EndTime]
           [ -f] ServerName...
```

### Description

Use the **pdaccount** administrative command to collect summary accounting information for a specified time period in a comma delimited format about jobs processed by actual destinations on one or more servers. This information can be filed and imported into a spread sheet to calculate the cost of consumables, the usage rate of printers, the cost for each user, and so forth. You can request summary information or all available information. The summary information includes the following:

- Total pages printed by a destination or a user for a specified time period
- Total octets printed by a destination or a user for a specified time period

You can also request complete records for a specified time period.

When the **log-accounting-data** actual destination or server attributes are set to **true**, Infoprint Manager creates an accounting log for each destination and stores the information in the server's `accounting.logs` subdirectory. When the accounting logs are active, Infoprint Manager records the following information:

- actual destination name** (up to 255 characters)
- job owner** (up to 255 characters)
- global job-id** without *ServerName*
- submission-time** (GMT format)
- submission-time** (date in server's displayable locale and time zone)
- submission-time** (time in server's displayable locale and time zone)
- completion-time** (GMT format)
- completion-time** (date in server's displayable locale and time zone)
- completion-time** (time in server's displayable locale and time zone)
- pages-completed**
- octets-completed**
- data stream** (first document only)
- job name** (up to 255 characters)

For actual destinations that are unable to get pages completed from the printer, the information is obtained from the **job-page-count** attribute (which can be set by the user), or in some cases, Infoprint Manager determines the information by analyzing the datastream.

**Note:** Because of the way that Infoprint Manager pauses and cancels jobs, the totals for the pages completed could be inaccurate.

### Flags

You can use the following flags with the **pdaccount** command:

## pdaccount

### **-c server**

Specifies the object class for the **pdaccount** command. Server is the only class supported for the **pdaccount** command.

### **-t** Specifies the type of account information that you want collected:

**destination** Summary information by destination

**user** Summary information by job owner

**all** All records as logged

**Attention:** Requesting information for **all** accounting records can consume a lot of the server's memory since all the data is read into memory to be sent to you. If you have a lot of data to retrieve, you should consider requesting it for smaller time periods and concatenating the returned data.

For example, if you want to retrieve all the accounting records for a one month period, you could issue four **pdaccount** commands like this:

```
pdaccount -t all -s '00:00:00 03/01/00' -e '00:00:00 03/08/00'  
Server A >March1.accting.data  
pdaccount -t all -s '00:00:00 03/08/00' -e '00:00:00 03/15/00'  
Server A >March2.accting.data  
pdaccount -t all -s '00:00:00 03/15/00' -e '00:00:00 03/22/00'  
Server A >March3.accting.data  
pdaccount -t all -s '00:00:00 03/22/00' -e '00:00:00 03/31/00'  
Server A >March4.accting.data
```

### **-s StartTime**

Specifies the oldest job-completion time for records to include. If this flag is not specified, defaults to the first record in the accounting log.

### **-e EndTime**

Specifies the latest job-completion time for records to include. If this flag is not specified, defaults to the last record in the accounting log.

### **-f**

Places the results in a file in the server's directory. If specified, the results of the **pdaccount** command are filed in the server's directory where the command is processed. The file is named **accounting.summary.timestamp**, where timestamp is the time the request was performed. If **-f** is not specified, the results are returned to standard out or can be redirected by the user.

## Argument

Use the argument value to identify the specific server or servers that you want to collect accounting information for.

You can use the following argument values with the **pdaccount** command:

### *ServerName*

Specifies the server that you want to collect accounting information for.

## Examples

### Summary Information for Destinations on Server A

To request summary accounting information for the destinations on server A for the period starting at 8 AM on 12/20/99 and ending at 8 AM on 12/24/99, enter the following command:

```
pdaccount -t destination -s '08:00:00 12/20/99' -e '08:00:00 12/24/99' A
```

The information returned is similar to:

```
Destination, Pages Completed, Octets Completed
Printer1,12997,1989787763
Printer2,2455,17676836
Printer3,86673,189808083
```

### Summary Information for Users on All the Servers

To request summary accounting information for users on all the servers for the period starting at 8 AM on 12/20/99 and ending at 8 AM on 12/24/99, enter the following command:

```
pdaccount -t user -s '08:00:00 12/20/99' -e '08:00:00 12/24/99' *:
```

The information returned is similar to:

```
Owner, Pages Completed, Octets Completed
gnelson@info1.penn.boulder.ibm.com,1347,1987763
hlava@ips1.penn.boulder.ibm.com,2455,12237676836
root@pumbaa.penn.boulder.ibm.com,86673,189808083
```

### All Accounting Information for Destinations on Servers B and C

To request all the data (or raw data) for the destinations on servers B and C for the period starting at 8 AM on 12/20/99 and ending at 8 AM on 12/24/99, enter the following command:

```
pdaccount -t all -s '08:00:00 12/20/99' -e '08:00:00 12/24/99' B C
```

The command returns the complete accounting log records for the time period collected from all the accounting logs on the requested servers in no particular sorted order.

**Attention:** Requesting information for **all** accounting records can consume a lot of the server's memory since all the data is read into memory to be sent to you. If you have a lot of data to retrieve, you should consider requesting it for smaller time periods and concatenating the returned data.

For example, if you want to retrieve all the accounting records for a one month period, you could issue four **pdaccount** commands like this:

```
pdaccount -t all -s '00:00:00 03/01/00' -e '00:00:00 03/08/00' Server A
>March1.accting.data
pdaccount -t all -s '00:00:00 03/08/00' -e '00:00:00 03/15/00' Server A
>March2.accting.data
pdaccount -t all -s '00:00:00 03/15/00' -e '00:00:00 03/22/00' Server A
>March3.accting.data
pdaccount -t all -s '00:00:00 03/22/00' -e '00:00:00 03/31/00' Server A
>March4.accting.data
```

---

## pdclean Command: Removes All Jobs from the Specified Object

### Syntax

```
pdclean [-c ObjectClass] [-m "MessageText"]
        [-x "attribute=value ..."] [-X AttributesFileName]
        {ServerName ... | [ServerName:]DestinationName ... |
        [ServerName:]QueueName ...}
```

```
pdclean -h
```

### Description

Use the **pdclean** administrative command to remove all jobs from the specified servers, logical destinations, queues, or actual destinations. If you are removing jobs from a server, Infoprint ignores any **job-retention-period** or **job-retain-until** attribute values. For all other conditions, Infoprint honors the **job-retention-period** or **job-retain-until** value. If you are removing jobs from a logical destination, Infoprint removes all jobs from the queue to which the logical destination submitted the jobs. If you are removing jobs from a queue, Infoprint removes all jobs that the queue contains, regardless of which logical destination or destinations submitted the jobs to the queue.

Infoprint removes processing jobs, if the actual destination supports this.

Infoprint Manager for AIX issues a confirmation message prior to cleaning the object, unless your **PD\_CONFIRM\_DELETE** environment variable has a value of **no**.

Infoprint Manager for Windows NT and Windows 2000 issues a confirmation message prior to cleaning the object, unless the **Confirm Object Delete** checkbox is unchecked (which is accessed through the Infoprint Manager Management Console with **Edit→Service Configuration**).

### Flags

You can use the following flags with the **pdclean** command:

**-c {destination | queue | server}**

Specifies the object class you want for this command. Within the valid classes, **destination** is a logical or actual destination.

Using this flag is equivalent to specifying the command attribute **class**.

**-h** Displays a command-specific help message containing information about command syntax and flags. If you use this flag with any other flag or attribute, Infoprint recognizes only the **-h** flag.

**-m "*MessageText*"**

Specifies the message you want associated with the specified destination, queue, or server. You can use this message to indicate the reason why you are cleaning the destination, queue, or server, or any other appropriate comments.

Using this flag is equivalent to specifying the command attribute **message**.

You can list this message by specifying **requested-attributes=message** with the **pdls** command.



**-x** *"attribute=value ..."*

A single attribute string, consisting of one or more attribute-value pairs.

**-X** *AttributesFileName*

Specifies the name of a file containing attribute and value pairs you want Infoprint to insert at the current point in the command.

Using this flag is equivalent to specifying the command attribute **attributes**.

## Command Attributes

You may specify these attributes in a **-x** *"attribute=value ..."* string or in an attributes file designated with the **-X** *AttributesFileName* flag.

**attributes=AttributesFileName**

Specifies the designated attributes file that Infoprint reads and inserts at the current point in the command. This file contains attribute and value pairs that Infoprint uses to expand the command.

**class={destination | queue | server}**

Specifies the destination, queue, or server you want for this command. Within the valid classes, **destination** is a logical or actual destination.

**message="MessageText"**

Specifies the message you want associated with the destination, queue, or server. You can use this message to indicate the reason why you are cleaning the destination, queue, or server, or any other appropriate comments.

You can list this message by specifying **requested-attributes=message** with the **pdls** command.

## Arguments

Use the argument value to specify the destination, queue, or server that you want Infoprint to clean. If you specify multiple objects, all must be of the same object class and you must separate the object names with spaces.

You can use the following arguments with the **pdclean** command:

*[ServerName:]DestinationName*

Specifies which destinations you want cleaned of jobs.

Cleaning an actual destination removes only those jobs that Infoprint has assigned to that actual destination.

Cleaning a logical destination removes all jobs submitted through that logical destination that Infoprint has not yet completed. Infoprint removes those jobs from the queue associated with that logical destination. Infoprint removes any jobs currently processing if the actual destination supports this.

*[ServerName:]QueueName*

Specifies which queues you want cleaned of jobs.

Cleaning a queue deletes all jobs that reside in that queue. Infoprint removes any jobs currently processing if the actual destination supports this.

*ServerName*

Specifies which servers you want cleaned of jobs.

## **pdclean**

Cleaning a server deletes all jobs submitted to any of the logical destinations, or assigned to the actual destinations, residing in that server, including any retained jobs. Infoprint removes any jobs currently processing if the actual destination supports this.

## **Examples**

### **Clean a Logical Destination**

To clean logical destination Mserv-1p of all jobs, enter the command:

```
pdclean Myserv-1p
```

### **Clean a Server**

To clean server DServ1, enter the command:

```
pdclean -c server DServ1
```

### **Clean an Actual Destination**

To clean destination Mserv-pp of all jobs and to leave a message, enter the command:

```
pdclean -m "Destination Mserv-pp is down for repairs" Super1:PhysPrt2
```

## **Suggested Reading**

For more information about:

- Attributes file, see "Attributes File" on page 10

## pdcreate Command: Creates Infoprint Objects

### Syntax

```
pdcreate [-c ObjectClass] [-g] [-m "MessageText"]
         [-r "attribute ..."] [-s StyleName]
         [-x "attribute=value ..."] [-X AttributesFileName]
         {ServerName:AuxiliarySheetName ... |
          ServerName:DefaultDocumentName ... |
          ServerName:DefaultJobName ... |
          ServerName:DestinationName ... |
          ServerName:MediumName ... |
          ServerName:QueueName ... |
          ServerName:ResourceContextName ...}
          ServerName:TransformName ...}
```

```
pdcreate -h
```

### Description

Use the **pdcreate** administrative command to create Infoprint objects (except servers, logs, documents and jobs) and to set their attributes to specific values.

You can specify any initially settable or resettable attribute for an object with the **pdcreate** command. You can specify an initially settable attribute only when you create an object.

“Appendix A. Attribute-to-Object Listing” on page 673, provides a listing of all attributes by object class and “Chapter 7. Infoprint Object Attributes” on page 325, contains descriptions for each attribute by object.

**Note:** Infoprint creates servers and logs when the server starts. Infoprint creates documents and jobs when users submit files for printing or transmission with the **pdpr** command.

You can use the **pdcreate** command to create objects for the following object classes:

- **destination** (logical and actual)
- **queue**
- **initial-value-job**
- **initial-value-document**
- **medium**
- **auxiliary-sheet**
- **resource-context**
- **transform**

When you create a destination, it remains in the disabled state and Infoprint cannot accept any jobs for it until you enable the destination. You must issue the **pdenable** command to enable the destinations.

An object you create with the **pdcreate** command still exists even if the server that contains it terminates normally (shutdown) or abnormally. A logical destination or queue returns to its previous state when its server restarts; an actual destination attempts to return to its previous state when its server restarts.

## Flags

You can use the following flags with the **pdcreate** command:

**-c {destination | queue | medium | initial-value-job | initial-value-document | auxiliary-sheet | resource-context | transform}**

Specifies the object class you want for this command. You can only specify one class per command invocation. Using this flag is equivalent to specifying the command attribute **class**.

**-g** Turns off headings. Using this flag is equivalent to specifying the command attribute **headings=false**.

**-h** Displays a command-specific help message containing information about command syntax and flags. If you use this flag with any other flag or attribute, Infoprint recognizes only the **-h** flag.

**-m "MessageText"**

Specifies the message that you want associated with the object you are creating. You may indicate the reason for creating the object or to provide any other comments.

You can list this message by specifying **requested-attributes=message** with the **pdl**s command. Using this flag is equivalent to specifying the command attribute **message**.

**-r {none | brief | verbose}**

Specifies the attribute values you want Infoprint to display for the specified object.

**none** Displays no attributes.

**brief** Displays a small subset of important attributes for each object.

**verbose**

Displays a larger subset of important attributes for each object.

Using this flag is equivalent to specifying the command attribute **requested-attributes**.

**-s {column | docol | line}**

When combined with the **-r** flag or the **requested-attributes** command attribute, specifies the format in which you want Infoprint to display attribute information.

**column**

Attribute values are displayed in tabular format, so that values of the same attribute for multiple objects line up in columns.

**docol**

For jobs only, job attribute values and the document attribute values for the first document in the job are displayed in column format on the same line.

**line** Each attribute is displayed on a separate line.

Using this flag is equivalent to specifying the command attribute **style**.

**-x "attribute=value ..."**

A single attribute string, consisting of one or more attribute-value pairs.

**-X AttributesFileName**

Specifies the name of a file containing attribute and value pairs Infoprint

inserts at the current point in the command. Using this flag is equivalent to specifying the command attribute **attributes**.

## Command Attributes

You can specify these attributes in a **-x** *"attribute=value ..."* string or in an attributes file designated with the **-X** *AttributesFileName* flag.

**attributes=AttributesFileName**

Specifies the designated attributes file that Infoprint reads and inserts at the current point in the command. This file contains attribute and value pairs that Infoprint uses to expand the command.

**class={destination | queue | medium | initial-value-job | initial-value-document | auxiliary-sheet | resource-context | transform}**

Specifies the object class you want for this command. You can only specify one class per command invocation.

**headings={true | false}**

Specifies whether you want headings displayed in the output.

**message="MessageText"**

Specifies the message that you want associated with the object you are creating. You may indicate the reason for creating the object or provide other comments.

You can list this message by specifying **requested-attributes=message** with the **pdls** command.

**requested-attributes={none | brief | verbose}**

Specifies which output attributes you want Infoprint to display.

**none** Displays no attributes.

**brief** Displays a small subset of important attributes for each object.

**verbose**

Displays a larger subset of important attributes for each object.

**style={column | doccol | line}**

Specifies the presentation format you want for the displayed output.

**column**

Attribute values are displayed in tabular format, so that values of the same attribute for multiple objects line up in columns.

**doccol**

For jobs only, job attribute values and the document attribute values for the first document in the job are displayed in column format on the same line.

**line** Each attribute is displayed on a separate line.

## Arguments

Use the argument values to identify the specific object you are creating. If you specify multiple objects, separate the object names with spaces.

**Note:** Regardless of which object you create, you must use *ServerName:* with the **pdcreate** command.

You can use the following arguments with the **pdcreate** command:

*ServerName:DestinationName*

## pdcreate

```
ServerName:QueueName
ServerName:DefaultJobName
ServerName:DefaultDocumentName
ServerName:MediumName
ServerName:AuxiliarySheet
ServerName:ResourceContextName
ServerName:TransformName
```

## Examples

### Create a Queue

To create the queue Serv1-p3-queue, on the server Serv1, enter the command:

```
pdcreate -c queue Serv1:Serv1-p3-queue
```

### Create a Logical Destination

To create the logical destination Destination3-Serv1 in the server Serv1 and specify the queue you want associated with that destination, enter the command:

```
pdcreate -x "associated-queue=Serv1-p3-queue" Serv1:Destination3-Serv1
```

### Create an Actual Destination

To create the PSF TCP/IP-attached actual destination Destination3 in the server Serv1 and specify the queue you want associated with that destination, enter the command:

```
pdcreate -x "destination-realization=actual
associated-queue=Serv1-p3-queue attachment-type=tcPIP
destination-model=Infoprint4000
destination-tcPIP-internet-address=martha.boulder.ibm.com
destination-tcPIP-port-number=5001" Serv1:Destination3
```

### Create a Default Document

To create the default document LP3ivd, enter the command:

For Infoprint Manager for AIX:

```
pdcreate -c initial-value-document -m "Created 04/01/1997"
-x "copy-count=1 document-format=line-data page-definition=MyPageDef
resource-context-page-definition=/usr/lpp/psf/mypdlib sides=1
descriptor='IVD for LogPrt3'" Serv1:LP3ivd
```

For Infoprint Manager for Windows NT and Windows 2000:

```
pdcreate -c initial-value-document -m "Created 04/01/1997"
-x "copy-count=1 document-format=line-data page-definition=MyPageDef
resource-context-page-definition=\install_path\psf\mypdlib sides=1
descriptor='IVD for LogPrt3'" Serv1:LP3ivd
```

### Create a Default Job

To create the default job MyJobTemplate using the attributes specified in the attributes file named MyJobAttributes.X, enter the command:

```
pdcreate -c initial-value-job -X MyJobAttributes.X
server3:MyJobTemplate
```

### Create a Medium

To create a medium representing a transparency with the identifier my-clear-medium in the server Serv1, enter the command:

```
pdcreate -c medium -x "descriptor='letter size, common transparency'
medium-type=transparency medium-color=transparent medium-size=letter
medium-sides=1 medium-dimensions=215.9:355.6" Serv1:my-clear-medium
```

### Create a Medium in All Active Servers

To create the medium A4-blue in all active servers, enter the command:

```
pdcreate -c medium \*:A4-blue
```

## Create a Queue and its Notification Profile

To create a notification profile for Serv1-p3-queue in server Serv1, enter the command:

```
pdcreate -c queue -x "notification-profile={event-identifiers=job-modified
queue-state-changed delivery-method=message
event-comment='This is a modification of job or status event'
delivery-address=dave@cowboy locale=En_US}" Serv1:Serv1-p3-queue
```

## Suggested Reading in Hardcopy

For information about:

- Attributes file, see “Attributes File” on page 10
- Headings and style, see “Command Output: Headings and Style” on page 9
- Attributes for Infoprint objects, see “Chapter 7. Infoprint Object Attributes” on page 325.
- Non-settable, initially settable, and resettable attributes, see “Initially Settable, Resettable Attributes, and Non-Settable” on page 4

## Suggested Reading Online

For Infoprint Manager for AIX, to view information about all supported attributes for Infoprint, enter the command:

```
man pd_att
```

This displays a list of files by object from which you can select the attribute listing you want.

## pddelete Command: Deletes Infoprint Objects

### Syntax

```
pddelete [-c ObjectClass] [-m "MessageText"]
          [-x "attribute=value ..."] [-X AttributesFileName]
          {ServerName ... | ServerName:AuxiliarySheetName ... |
           ServerName:DefaultDocumentName ... |
           ServerName:DefaultJobName ... |
           [ServerName:]DestinationName ... |
           ServerName:MediumName ... |
           [ServerName:]QueueName ... |
           ServerName:ResourceContextName ... |
           ServerName:TransformName ... |
           LocalJobID ... | GlobalJobID ...}
```

```
pddelete -c job [-m "MessageText"] -r JobRetentionPeriod
          [-x "attribute=value ..."] [-X AttributesFileName]
          {LocalJobID ... | GlobalJobID ...}
```

```
pddelete -h
```

### Description

Use the **pddelete** administrative command to delete Infoprint objects.

Infoprint Manager for AIX issues a confirmation message before deleting objects, unless your **PD\_CONFIRM\_DELETE** environment variable is set to **no**.

Infoprint Manager for Windows NT and Windows 2000 issues a confirmation message prior to cleaning the object, unless the **Confirm Object Delete** checkbox is unchecked (which is accessed through the Infoprint Manager Management Console with **Edit→Service Configuration**).

Infoprint does not delete jobs with a non-zero value for the **job-retain-until** or **job-retention-period** attribute (either previously set or set with this command) until the retention deadline arrives or the retention period expires.

### Flags

You can use the following flags with the **pddelete** command:

**-c** {*destination* | *job* | *queue* | *medium* | *initial-value-job* | *initial-value-document* | *auxiliary-sheet* | *resource-context* | *transform* | *server*}

Specifies the object class you want for this command. Using this flag is equivalent to specifying the command attribute **class**.

**-h** Displays a command-specific help message containing information about command syntax and flags. If you use this flag with any other flag or attribute, Infoprint recognizes only the **-h** flag.

**-m** "*MessageText*"

Specifies the message you want to associate with the object that you want to delete. You can use this message to indicate the reason for deleting the object or to provide any other comments.

If the command operates on a job with a non-zero value for the **job-retention-period** or **job-retain-until** attribute (either previously set or



set with this command), you can list this message by specifying **requested-attributes=job-message-from-administrator** with the **pdls** command. Otherwise, Infoprint deletes this message with the object and you cannot retrieve it. If you do not specify **-m**, the message already stored with the object remains unchanged and Infoprint deletes it as previously described.

Using this flag is equivalent to specifying the command attribute **message**.

#### **-r** *JobRetentionPeriod*

You can only use this flag if the object class is **job**. Infoprint rejects the command if you use this flag with any other class.

If the job has a retention period or retention deadline, you must specify this flag with a zero (0) value to delete the job. If not specified, Infoprint uses the present retention period or retention deadline for the job.

Using this flag is equivalent to specifying the object attribute **job-retention-period**.

#### **-x** *"attribute=value ..."*

A single attribute string, consisting of one or more attribute-value pairs.

#### **-X** *AttributesFileName*

Specifies the name of a file containing attribute and value pairs you want Infoprint to insert at the current point in the command.

Using this flag is equivalent to specifying the command attribute **attributes**.

## Command Attributes

You may specify these attributes in a **-x "attribute=value ..."** string or in an attributes file designated with the **-X AttributesFileName** flag.

#### **attributes=AttributesFileName**

Specifies the designated attributes file that Infoprint reads and inserts at the current point in the command. This file contains attribute and value pairs that Infoprint uses to expand the command.

#### **class={destination | job | queue | medium | initial-value-job | initial-value-document | auxiliary-sheet | resource-context | transform | server}**

Specifies the object class you want for this command.

#### **message="MessageText"**

Specifies the message you want to associate with the object you want to delete. You can use this message to indicate the reason for deleting the object or to provide any other comments.

If the command operates on a job with a non-zero value for the **job-retention-period** or **job-retain-until** attribute (either previously set or set with this command), you can list this message by specifying **requested-attributes=job-message-from-administrator** with the **pdls** command. Otherwise, Infoprint deletes this message with the object and you cannot retrieve it.

If you do not specify the **message** attribute, the message stored with the object remains unchanged and Infoprint deletes it as previously described.

## Arguments

Use the argument value to identify the specific object you want to delete. If you specify multiple objects, separate the object names with spaces.

## pddelete

You can use the following arguments with the **pddelete** command:

*ServerName*

You must remove all jobs contained within this server before you can delete it.

*ServerName:AuxiliarySheetName*

You cannot delete this auxiliary sheet if any of the actual destinations that reference it are enabled.

*ServerName:DefaultDocumentName*

You cannot delete this default document if any of the logical destinations that reference it are enabled.

*ServerName:DefaultJobName*

You cannot delete this default job if any of the logical destinations that reference it are enabled.

*LocalJobID or GlobalJobID*

Infoprint deletes a job based on the specified value in its **job-retention-period** or **job-retain-until** attribute.

**Notes:**

1. You can identify your own jobs by either the local job ID or the global job ID. You must identify other users' jobs by the global job ID.
2. In DCE installations, you do not need permission to delete your own jobs. You must have **write** permission for the server in order to delete other users' jobs. By default, only operators and administrators have this permission.
3. In installations without DCE, by default, end users do not have permission to use the **pddelete** command. They cannot delete even their own jobs.

*ServerName:MediumName*

You cannot delete this medium if any of the actual destinations that reference it are enabled.

*[ServerName:]DestinationName*

You must remove all the jobs from an actual destination before you can delete it.

*[ServerName:]QueueName*

You must disable all logical destinations associated with the queue before you can delete the queue. You must remove all jobs (including paused jobs) from the queue before you can delete the queue.

*ServerName:ResourceContextName*

You cannot delete this resource context if any of the actual destinations that reference it are enabled.

*ServerName:TransformName*

There is no restriction.

## Examples

### Delete a Job Using a Local ID

To delete job 5, enter the command:

```
pddelete -c job 5
```

**Delete Logical Destinations**

To delete logical destinations srA-lp11 and srA-lp15, enter the command:

```
pdelete srA-lp11 srA-lp15
```

**Delete a Default Job**

To delete the default IVJ\_2 from the server DivServ2, enter the command:

```
pdelete -c initial-value-job DivServ2:IVJ_2
```

**Delete a Server**

To delete the server Serv1, enter the command:

```
pdelete -c server Serv1
```

**Suggested Reading**

For information about:

- Attributes file, see “Attributes File” on page 10

## pddisable Command: Stops Destinations from Accepting Jobs and Logs from Logging

### Syntax

```
pddisable [-c ObjectClass] [-m "MessageText"]
          [-x "attribute=value ..." ] [-X AttributesFileName]
          {ServerName ... | ServerName:LogName ... |
          [ServerName:]DestinationName ... |
          [ServerName:]QueueName ...}
```

```
pddisable -h
```

### Description

Use the **pddisable** administrative command to stop actual destinations or logical destinations from accepting jobs, or to stop logs from logging data.

When you disable a destination, it does not accept jobs submitted with **pdpr** or **pdresubmit** commands. The destination still accepts other commands. All previously submitted jobs and currently processing jobs continue unaffected.

#### Notes:

1. Use the **pdenable** command to enable a destination to accept jobs again and to enable the logging function of a log again.
2. Use the **pddisable** and **pdenable** commands to prevent or allow input to the object. Use the **pdpause** and **pdresume** commands to prevent or allow output from the object.

### Flags

You can use the following flags with the **pddisable** command:

#### **-c** {destination | log | queue | server}

Specifies the object class you want for this command. Within the valid classes, **queue** disables all associated logical destinations, **destination** is for a logical or actual destination, and **server** disables all destinations in the server.

Using this flag is equivalent to specifying the command attribute **class**.

**-h** Displays a command-specific help message containing information about command syntax and flags. If you use this flag with any other flag or attribute, Infoprint recognizes only the **-h** flag.

#### **-m** "*MessageText*"

Specifies the message you want associated with the destination, log, queue, or server. You can use this message to indicate the reason for disabling the object or to provide any other comments.

If you do not specify the **-m** flag, the message already stored with the object remains unchanged.

When you issue a command against a server, Infoprint propagates the message to the **message** attribute of the destinations residing in the server. Infoprint does not change the server **message** attribute. When you issue a command against a queue, Infoprint propagates the message to the **message** attribute of the logical destinations associated with the queue. Infoprint does not change the queue **message** attribute.

You can list this message by specifying **requested-attributes=message** with the **pdlis** command. Using this flag is equivalent to specifying the command attribute **message**.

**-x** *"attribute=value ..."*

A single attribute string, consisting of one or more attribute-value pairs.

**-X** *attributes file name*

Specifies the name of a file containing attribute and value pairs you want inserted at the current point in the command.

Using this flag is equivalent to specifying the command attribute **attributes**.

## Command Attributes

You may specify these attributes in a **-x** *"attribute=value ..."* string or in an attributes file designated with the **-X** *AttributesFileName* flag.

**attributes=AttributesFileName**

Specifies the designated attributes file that Infoprint reads and inserts at the current point in the command. This file contains attribute and value pairs that Infoprint uses to expand the command.

**class={destination | log | queue | server}**

Specifies the object class you want for this command. Within the valid classes, **queue** disables all associated logical destinations, **destination** is for a logical or actual destination, and **server** disables all destinations in the server.

**message="MessageText"**

Specifies the message you want to associate with the destination, log, queue, or server. You can use this message to indicate the reason for disabling the object or to provide any other comments.

If you do not specify this attribute, the message already stored with the object remains unchanged.

When you issue a command against a server, Infoprint propagates the message to the **message** attribute of the destinations residing in the server. Infoprint does not change the server **message** attribute.

When you issue a command against a queue, Infoprint propagates the message to the **message** attribute of the logical destinations associated with the queue. Infoprint does not change the queue **message** attribute.

You can list this message by specifying **requested-attributes=message** with the **pdlis** command.

## Arguments

Use the argument value to identify the specific object you want to disable. If you specify multiple objects, separate the object names with spaces.

You can use the following arguments with the **pddisable** command:

*ServerName:LogName*

Specifies the log you want to disable. Disabling a log stops it from logging data.

*[ServerName:]DestinationName*

Specifies the destination you want to disable. Disabling a destination stops it from accepting print or transmission requests. Any jobs currently assigned to an actual destination continue processing.

## pddisable

*[ServerName:]QueueName*

Specifies the queue you want to disable. Disabling a queue disables all of the logical destinations associated with that queue.

*ServerName*

Specifies the server you want to disable. Disabling a server disables all destinations residing in the server.

## Examples

### Disable a Logical Destination

To disable logical destination Serv1-lp on server Serv1, enter:

```
pddisable Serv1-lp
```

Infoprint does not require the server name.

### Disable an Actual Destination

To disable actual destination Serv1-pp on server Serv1, enter:

```
pddisable Serv1-pp
```

Infoprint does not require the server name.

### Disable All Destinations in a Server

To disable the logical and actual destinations contained in the server ServG1 and assign a message to the destinations, enter:

```
pddisable -c server -m "Unavailable due to testing" ServG1
```

### Disable All Logical Destinations Associated with a Queue

To disable the logical destinations associated with the queue production-q1 on server servera, enter:

```
pddisable -c queue production-q1
```

Infoprint does not require the server name.

## Suggested Reading

For information about:

- Attributes file, see “Attributes File” on page 10

## pdenable Command: Enables Destinations to Accept Jobs and Logs to Log

### Syntax

```
pdenable [-c ObjectClass] [-m "MessageText"]
          [-x "attribute=value ..."] [-X AttributesFileName]
          {ServerName ... | ServerName:LogName ... |
          [ServerName:]DestinationName ... |
          [ServerName:]QueueName ...}
```

```
pdenable -h
```

### Description

Use the **pdenable** administrative command to enable the logging function of logs or to enable logical destinations or actual destinations to accept jobs.

#### Notes:

1. Use the **pdenable** and **pddisable** commands to allow or prevent input to an object. Use the **pdresume** and **pdpause** commands to allow or prevent output from the object.
2. To stop destinations from accepting jobs, use the **pddisable** command.
3. To stop logs from logging data, use the **pddisable** command.

### Flags

You can use the following flags with the **pdenable** command:

#### **-c** {destination | log | queue | server}

Specifies the object class you want for this command. Within the valid classes, **queue** enables all associated logical destinations, **destination** is for a logical or actual destination, and **server** enables all destinations in that server.

Using this flag is equivalent to specifying the command attribute **class**.

**-h** Displays a command-specific help message containing information about command syntax and flags. If you use this flag with any other flag or attribute, Infoprint recognizes only the **-h** flag.

#### **-m** "*MessageText*"

Specifies the message you want to associate with the destination, log, queue, or server you want to enable. You can use this message to indicate the reason for enabling the object or to provide any other comments. If you do not specify the **-m** flag, the message already stored with the destination, log, queue, or server remains unchanged.

When you issue the command against a server, Infoprint propagates the message to the **message** attribute of the destinations residing in that server. Infoprint does not change the server **message** attribute.

When you issue the command against a queue, Infoprint propagates the message to the **message** attribute of the logical destinations associated with the queue. Infoprint does not change the queue **message** attribute.

You can list this message by specifying **requested-attributes=message** with the **pdls** command.

## pdenable

Using this flag is equivalent to specifying the command attribute **message**.

**-x** *"attribute=value ..."*

A single attribute string, consisting of one more attribute-value pairs.

**-X** *attributes file name*

Specifies the name of a file containing attribute and value pairs you want Infoprint to insert at the current point in the command.

Using this flag is equivalent to specifying the command attribute **attributes**.

## Command Attributes

You can specify these attributes in a **-x** *"attribute=value ..."* string or in an attributes file designated with the **-X** *AttributesFileName* flag.

**attributes=AttributesFileName**

Specifies the designated attributes file that Infoprint reads and inserts at the current point in the command. This file contains attribute and value pairs that Infoprint uses to expand the command.

**class={destination | log | queue | server}**

Specifies the object class you want for this command. Within the valid classes, **queue** enables all associated logical destinations; **destination** is for a logical or actual destination; and **server** enables all destinations in that server.

**message="MessageText"**

Specifies the message you want to associate with the destination, log, queue, or server that you want to enable. You can use this message to indicate the reason for enabling the object or to provide any other comments. If you do not specify the **message** attribute, the message already stored with the destination, log, queue, or server remains unchanged.

When you issue the command against a server, Infoprint propagates the message to the **message** attribute of the destinations residing in that server. Infoprint does not change the server **message** attribute.

When you issue the command against a queue, Infoprint propagates the message to the **message** attribute of the logical destinations associated with the queue. Infoprint does not change the queue **message** attribute.

You can list this message by specifying **requested-attributes=message** with the **pdls** command.

## Arguments

Use the argument value to identify the specific object you want to enable. If you specify multiple objects, separate the object names with spaces.

You can use the following arguments with the **pdenable** command:

*ServerName:LogName*

Specifies the log you want to enable. Enabling a log allows it to begin accepting input (logging).

*[ServerName:]DestinationName*

Specifies the destination you want to enable. When first created, destinations are in the disabled state. You cannot enable destinations unless you associate them with an existing queue. Any other objects referenced by the destination must also exist. These are:



- For logical destinations
  - Default jobs
  - Default documents
- For actual destinations
  - Media
  - Auxiliary-sheets
  - Resource-contexts

*[ServerName:]QueueName*

Specifies the queue you want to enable. When you issue the **pdenable** command against a queue, Infoprint attempts to enable all of its associated logical destinations.

*ServerName*

Specifies the server you want to enable. When you issue the **pdenable** command against a server, Infoprint attempts to enable all of its destinations.

When a server initializes again after being shut down, whether the destinations are either enabled or disabled depends on:

- The state of the destination when the system was shut down
- The ability of the server to communicate with its associated queue

## Examples

### Enable Logical Destinations

To enable logical destinations `Serv1-lp` and `draft-lp` on server `Serv1`, enter:

```
pdenable Serv1-lp draft-lp
```

### Enable All Destinations in a Server

To enable all logical and actual destinations contained in the server `ServG1`, enter the command:

```
pdenable -c server ServG1
```

## Suggested Reading

For information about:

- Attributes file, see “Attributes File” on page 10

## pdls Command: Lists Selected Attribute Values

### Syntax

```
pdls [-c ObjectClass] [-f "FilterCriteria"] [-F] [-g] [-j]
      [-r RequestedAttribute ...] [-s StyleName] [-U]
      [-x "attribute=value ..."] [-X AttributesFileName]
      [ServerName ... | ServerName:AuxiliarySheetName ... |
      ServerName:DefaultDocumentName ... |
      ServerName:DefaultJobName ... |
      ServerName:LogName ... | ServerName:MediumName ... |
      [ServerName:]DestinationName ... |
      [ServerName:]QueueName ... |
      ServerName:ResourceContextName ... |
      ServerName:TransformName ... | LocalJobID[.DocNumber] ... | GlobalJobId[.DocNumber] ...]
```

**pdls -h**

### Description

Use the **pdls** command to request that Infoprint display selected attribute values for one or more jobs or other Infoprint objects.

- By default, Infoprint creates a filter when listing jobs that only allows you to see your jobs. The jobs have a predefined value for the filter that is equal to the job attribute **user-name**; this value is your login identity when you submit a job. You can add to this filter to further restrict the jobs for which Infoprint returns information.
- You must suppress the default filter by using the **-U** flag or turn off all filtering with the **-F** flag to see more than your own jobs.
- If you only specify the *ServerName* as the command argument, Infoprint displays the attribute values for all objects belonging to the object class you specify.
- In general, you can only list the attributes of the object class you are requesting. However, you can view attributes of initial-value-jobs (IVJs) and initial-value-documents (IVDs) associated with a logical destination through the logical destination.
- You can list the attribute values for specific jobs by using the local ID or the global ID. You must have submitted the job to use the local ID.

#### Notes:

1. There is a situation when you must use the global ID. If the Infoprint communications daemon responsible for the mapping of local ID-to-global ID values is not available, this can prevent Infoprint from tying the local ID to the global ID. If this situation exists, you must use the global ID, the name of the server, or an argument specification using global characters.
2. There is a possible situation that can occur if your administrator has set the **PDIDTABLE** environment variable to a low value, for example 10. You submit a series of jobs during a short time span such that the number of jobs you have in process is larger than the value set, say 14. You will have two jobs with the local IDs of 1, 2, 3, and 4. However, Infoprint no longer associates the first four jobs with a local ID because those local IDs now belong to the 11th, 12th, 13th, and 14th jobs. Therefore, you must use the global ID to take action on any of the first four jobs.

## Flags

You can use the following flags with the **pdls** command:

**-c {job | auxiliary-sheet | document | initial-value-document | initial-value-job | log | medium | destination | queue | resource-context | transform | server}**

Specifies the object class of the object whose attributes you want to list. All object classes are valid.

Using this flag is equivalent to specifying the command attribute **class**.

**-f "FilterCriteria"**

Specifies the filter criteria you want to use in selecting from the candidate objects. Among the candidate objects, Infoprint returns only those matching the filter expression. See the command attribute **filter**, for filter expression details.

Using this flag is equivalent to specifying the command attribute **filter**.

**-F** Turns off all filtering, both specified and default. See the **-U** flag for suppressing only the default.

**-g** Turns off headings.

Using this flag is equivalent to specifying the command attribute **headings=false**.

**-h** Displays a command-specific help message containing information about command syntax and flags. If you use this flag with any other flag or attribute, Infoprint recognizes only the **-h** flag.

**-j** Use this flag to display only job attributes.

**-r {brief | verbose | archive | "*attribute ...*" | all | none}**

Specifies the group of attributes that you want to display for the specified job, auxiliary sheet, document, default document, default job, log, medium, destination, queue, resource-context, or server.

**brief** Displays a small subset of important attributes for each object.

**verbose**

Displays a larger subset of important attributes for each object.

**archive**

Writes only initially settable and resettable attributes to an archive file (see "Create an Archive File" on page 49).

*attributes ...*

Displays the attributes you specify.

**all** Displays all attributes.

**none** Displays no attributes.

If you specify more than one of these values, Infoprint displays all the attributes requested.

Using this flag is equivalent to specifying the command attribute **requested-attributes**.

**-s {column | doccol | line}**

Specifies the format in which you want Infoprint to display the attributes.

**column**

Attribute values are displayed in tabular format, so that values of

the same attribute for multiple objects line up in columns. This is the default for **-r brief** and **-r verbose**.

**docol**

For jobs only, job attribute values and the document attribute values for the first document in the job are displayed in column format on the same line.

**line** Each attribute is displayed on a separate line. This is the default for **-r all**, **-r "attribute ...:"**, and **-r archive**.

Using this flag is equivalent to specifying the command attribute **style**.

**-U** Suppresses the default user-name filter.

**-x "attribute=value ..."**  
Consists of a single attribute string, containing of one or more attribute-value pairs.

**-X AttributesFileName**  
Specifies the name of the file containing attribute and value pairs you want Infoprint to insert at the current point in the command.

Using this flag is equivalent to specifying the command attribute **attributes**.

## Command Attributes

You can specify these attributes in a **-x "attribute=value ..."** string or in an attributes file designated with the **-X AttributesFileName** flag.

**attributes=AttributesFileName**  
Specifies the designated attributes file that Infoprint reads and inserts at the current point in the command. This file contains attribute and value pairs that Infoprint uses to expand the command.

**class={job | auxiliary-sheet | document | initial-value-document | initial-value-job | log | medium | destination | queue | resource-context | transform | server}**  
Specifies the object class of the object whose attributes you want listed. All object classes are valid.

**filter="FilterCriteria"**  
Specifies the selection criteria you want Infoprint to use in order to select a subset from the candidate objects (if you request attribute values for multiple objects). A filter is a logical expression consisting of relations of attributes to attribute values. Among the objects you specify, Infoprint returns only objects whose attribute values match the filter expression.

You can only use attributes for the object class (**job**, **auxiliary-sheet**, **document**, **initial-value-document**, **initial-value-job**, **log**, **medium**, **destination**, **queue**, **resource-context**, **transform**, or **server**) that you specify in the command. The filter may contain an attribute other than one of those you are requesting.

Table 2. Attribute Operators for Filters

Operation	Operator	Strings	Integers	Time Format
Equal	==	Yes	Yes	Yes
Match first part of a value	=*	Yes	Yes	Yes

Table 2. Attribute Operators for Filters (continued)

Operation	Operator	Strings	Integers	Time Format
Match last part of a value	*=	Yes	Yes	Yes
Match any part of a value; such as a sub-string	*=*	Yes	Yes	Yes
Attribute present (any value)	==*	Yes	Yes	Yes
<b>Note:</b> When you test for attribute presence, Infoprint evaluates the filter item as true when the attribute has a <b>value</b> , not just when the attribute exists. You may need a false value to satisfy the requirement, as long as the false value conforms to the general syntax.				
Match approximately; for case-insensitive sub-string	~=	Yes	No	No
<b>Notes:</b> 1. An approximate match occurs when at least half of the target string, regardless of starting position, matches the filter value. 2. A case-insensitive match occurs when the target string may have a mix of upper- and lower-case characters, but the characters do match.				
Match a value greater than that specified	>	No	Yes	Yes
Match a value less than that specified	<	No	Yes	Yes

This list shows the filter syntax:

1. A filter item consisting of an attribute name, operator, and value. Table 2 on page 42 shows the operators and the data formats you can use to separate the attribute and value.
2. In Table 2 on page 42, the attribute-present operation consists of an attribute name followed by the equality operator followed by an \* in place of an attribute value. For example:

```
-f "media-ready=="
```

If the attribute has no value, Infoprint evaluates the filter item as false. Infoprint evaluates the filter item as true if the attribute has any assigned value.

3. Infoprint can compare each attribute in a filter item to only one attribute value. To compare an attribute to more than one value, or to filter more than one attribute, separate the filter items with one of the following operators:

#### The AND operator ("&&")

*FilterItem && FilterItem*

The expression evaluates to true only if both filter items evaluate to true.

#### The OR operator ("||")

*FilterItem || FilterItem*

The expression evaluates to true if either of the filter items evaluate to true.

- To evaluate a filter item as false, use the NOT operator before the filter item and enclose the filter item in parentheses.

**Note:** With Infoprint Manager for AIX, depending on the shell you are using, you may need to place quotation marks before and after the parentheses.

**The NOT operator !**

*!(FilterItem)*

If the filter item evaluates to true, the expression is false.

If the filter item evaluates to false, the expression is true.

- When you use multiple logical operators in a filter, Infoprint evaluates them in an order of precedence. You can override the order of precedence by using parentheses, ( ).

**Note:** Depending on the shell you are using, you may need to place quotation marks before and after the parentheses. See Table 3 for the order of precedence.

Table 3 summarizes the filter syntax. The table lists the operators in the order of precedence from highest to lowest.

Table 3. Filter Syntax

Operators	Placement
Parentheses: ( )	Around filter items
Relational operators: > <	Between attribute and value
Equality operators: ==	Between attribute and value
String matching: =* *= *=* ~=	Between attribute and value
NOT Operator: !	Before (filter-item) only
AND operator: &&	Between two filter items
OR operator:	Between two filter items

**headings= {true | false}**

Specifies whether you want the output displayed with or without headings.

**message-count=number**

When you request the **log-messages** log attribute, this specifies the number of previous messages you want to see starting from the last message logged. The value you can specify for *number* can be an integer from 1 through 2147483647.

Use this command attribute in conjunction with the **log-messages** log attribute to query for error log information. For example:

```
pdls -c log -r log-messages -x "message-count=4" Serv1:
```

displays the last four messages contained in the error log for server Serv1.

**requested-attributes={brief | verbose | archive | "attribute ...:" all | none}**

Specifies the group of attributes you want to display for the specified job, auxiliary-sheet, document, default document, default job, log, medium, destination, queue, resource-context, or server object.

**brief** Displays a small subset of important attributes for each object.

**verbose**

Displays a larger subset of important attributes for each object.

**archive**

Writes only initially settable and resettable attributes to an archive file (see “Create an Archive File” on page 49).

*attribute ...*

Displays the attributes you specify.

**all** Displays all attributes.

**none** Displays no attributes.

If you specify more than one of these values, Infoprint displays all the attributes requested.

**style={column | doccol | line}**

The format in which you want the attributes displayed.

**column**

Attribute values are displayed in tabular format, so that values of the same attribute for multiple objects line up in columns. This is the default for **requested-attributes=brief** and **requested-attributes=verbose**.

**doccol**

For jobs only, job attribute values and the document attribute values for the first document in the job are displayed in column format on the same line.

**line**

Each attribute is displayed on a separate line. This is the default for **requested-attributes=all**, **requested-attributes="attribute ...:"**, and **requested-attributes=archive**.

**when=now**

When you specify **when=now** with object class destination, the Infoprint Server returns its current information regarding the destinations instead of performing SNMP queries to get any updates. If you have many SNMP destinations, the use of this command attribute improves the performance of your **pdls** request.

For example, to list the brief attributes of all the destinations in Server1 and request that Server1 does not make SNMP queries to get the latest information but just returns its most current information, use the following command:

```
pdls -c dest -xwhen=now Server1:
```

## Arguments

Use the argument value to identify the specific object whose attributes you want to display. If you specify multiple objects, separate the object names with spaces.

You can use the following arguments with the **pdls** command:

```
LocalJobID[.DocNumber]
GlobalJobID[.DocNumber]
ServerName:AuxiliarySheetName
ServerName:DefaultDocumentName
ServerName:DefaultJobName
ServerName:LogName
ServerName:MediumName
```

## pdls

```
[ServerName:]DestinationName  
[ServerName:]QueueName  
ServerName:ResourceContextName  
ServerName:TransformName  
ServerName:
```

**Note:** When you only specify *ServerName:* as the argument of the command (without an object name), Infoprint returns the attribute values for all of the objects within the object class that you specify for that server and that meet the filter criteria.

## Examples

### List Full Attribute Information for a Document

To display attribute information for the first document in a job with a local ID of 13, enter the command:

```
pdls -c document -r all 13.1
```

### List Minimum Information for a Document

To find the minimum information (document number, format, and file name) about the second document in a job with a local ID of 13, enter the command:

```
pdls -c document 13.2
```

### List Selected Attributes for a Queue

To list the values of the brief attributes and the **backlogged** attribute for the queue Charlie-q, enter the command:

```
pdls -c queue -r "brief backlogged" Charlie-q
```

Infoprint displays information similar to the following:

```
Charlie-q: queue-name      = Charlie-q  
Charlie-q: queue-state    = ready  
Charlie-q: associated-server = Charlie  
Charlie-q: backlogged     = false
```

### List Document Formats Supported by Destinations

To display the document formats supported by the logical and actual destinations in Serv1, enter the command:

```
pdls -c destination -r document-formats-supported -s line Serv1:
```

Infoprint displays information similar to the following:

```
Serv1-lp: document-formats-supported =  
Serv1-pp: document-formats-supported = ascii  
                                             dbc-ascii  
                                             ditroff  
                                             line-data  
                                             modca-p  
                                             pdf  
                                             postscript  
                                             tiff  
Srv1-pp2: document-formats-supported = ascii  
                                             dbc-ascii  
                                             ditroff  
                                             line-data
```

### List the retention-period Defaulted by a Logical Destination and the Name of the initial-value-job Being Used

To list the retention-period defaulted by a logical destination and the name of the initial value job being used, enter the command:



```
pdls -c destination -r retention-period,destination-initial-value-job Dserv-1p
```

Infoprint displays information similar to the following:

```
Dserv-1p:job-retention-period=1:00
Dserv-1p:destination-initial-value-job=retain
```

### Filter Destinations by Attribute with Infoprint Manager for AIX

To determine the logical destinations and actual destinations that support the selected attributes on any server, enter the command:

```
pdls -c destination -f "content-orientation-supported==landscape &&
plexes-supported==tumble && sides-supported==2"
-r "destination-realization associated-queue" \*:
```

**Note:** Including the backslash before the global character prevents the Korn shell from interpreting the \* as a filename wildcard. Infoprint displays information similar to the following:

```
Serv3-1p: destination-realization = logical
Serv3-1p: associated-queue       = Serv3-q
Serv4-1p: destination-realization = logical
Serv4-1p: associated-queue       = Serv4-q
Serv3-pp: destination-realization = actual
Serv3-pp: associated-queue       = Serv3-q
Serv4-pp: destination-realization = actual
Serv4-pp: associated-queue       = Serv4-q
```

### Filter Jobs by Attribute with Infoprint Manager for AIX

To list all jobs that have requested more than one copy and that Infoprint has assigned to actual destination mysrv-pp, enter the command:

```
pdls -U -f "copy-count>1 && destination-assigned==mysrv-pp" "\*:"
```

**Note:** Placing the quotation marks before the global character and after the colon prevents the Korn shell from interpreting the \* as a filename wildcard.

### Filter Jobs by User Name (Include a User)

To list all jobs owned by the user named Smith, enter this command:

```
pdls -f "job-owner==Smith" -U Serv1:
```

### Filter Jobs by User Name (Exclude a User)

To list all jobs not owned by the user named Smith, enter the command:

```
pdls -f "!(job-owner==Smith)" -U Serv1:
```

### Filter Jobs by User Name (Substring) with Infoprint Manager for AIX

To list jobs owned by users with a given substring in their names (substring matching) use one of the following filters with the **pdls** command:

- Initial string match:

```
pdls -U -f "job-owner=*Jones" Serv1:
```
- Any substring match:

```
pdls -U -f "job-owner**one" Serv1:
```
- Final string match:

```
pdls -U -f "job-owner*=nes" Serv1:
```

All of these commands return jobs owned by Jones.

**Note:** These examples use the Korn shell.

### Filter Jobs by User Name (Approximate Match) with Infoprint Manager for AIX

To list jobs owned by all users with a name close to Jones (an approximate match), enter the command:

```
pdls -U -f "job-owner~=jones" Serv1:
```

**Note:** This example uses the Korn shell.

### Display the Server Associated with a Destination

To query for the name of the server containing logical destination draft-1p, enter the command:

```
pdls -c destination -r associated-server draft-1p
```

Infoprint displays information similar to the following:

```
draft-1p: associated-server=Serv1
```

### List the Attributes Specified in a Default Document

To query for the attributes specified in the default document sp17ivd contained in Serv7, enter the command:

```
pdls -c initial-value-document -r all Serv7:sp17ivd
```

Infoprint displays information similar to the following:

```
sp17ivd: carriage-control-type      =
sp17ivd: chars                      =
sp17ivd: content-orientation        =
sp17ivd: initial-value-document-identifier = sp17ivd
sp17ivd: associated-server          = Serv7
sp17ivd: logical-destination-ready  = Serv7-1p
sp17ivd: copy-count                 = 2
sp17ivd: sides                      = 2
sp17ivd: document-format            = line-data
```

**Note:** The list that Infoprint returns contains all possible attributes for a default document (those without values and those with values).

### List All Job Attributes

To list all attributes of jobs 10 and 12, enter the command:

```
pdls -r all 10 12
```

### List Brief Job Attributes

To list just the brief job attributes of jobs 10 and 12, enter the command:

```
pdls -j 10 12
```

### Display Status of All Jobs

To list the status of all jobs you have submitted to the default logical destination, Dserv-1p, enter the command:

```
pdls -f "destination-name-requested==Dserv-1p" Serv1:
```

Infoprint displays information similar to the following:

Job ID	Name	Current State	Intervening Jobs	Destination Requested	Destinations Assigned
4	Sp1X:1099222204 Wkly-report	processing	0	Dserv-1p	Dserv-pp
5	Sp1X:1114222205 Test-report	processing	0	Dserv-1p	Laser-pp
6	Sp1X:1224222206 Trip-report	pending	2	Dserv-1p	
1	Sp1X:0988222201 Dept-memo12	retained		Dserv-1p	

## Display Status of All Pending Jobs

To list the job status of all pending jobs submitted to the default logical destination, Dserv-lp, enter the command:

```
pdls -f "destination-name-requested==Dserv-lp &&
      current-job-state==pending" Serv1:
```

Infoprint displays information similar to the following:

Job ID	Name	Current State	Intervening Jobs	Destination Requested	Destinations Assigned
6	Sp1X:1224222206 Trip-report	pending	2	Dserv-lp	

## List the Brief Attributes of a Logical Destination

To list the **brief** attributes of logical destination Dserv-lp, enter the command:

```
pdls -c destination Dserv-lp
```

Infoprint displays information similar to the following:

Destination	Realization	Enabled	Queue
Dserv-lp	logical	true	Dserv-q

With Infoprint Manager for AIX, if you do not specify a destination name, Infoprint displays the brief attributes of all the destinations that share the same server with your default logical destination (as defined by your **PDPRINTER** environment variable).

## List Document Formats Supported by a Destination

To list the document formats supported by the actual destination srv37-pp in the line style with headings, which is the default style for an attribute list, enter the command:

```
pdls -c destination -r document-formats-supported srv37-pp
```

Infoprint displays information similar to the following:

```
srv37-pp: document-formats-supported = modca-p
                                           pdf
                                           postscript
```

## Create an Archive File

To create an archive file for a server and store it in a file, enter the command:

```
pdls -c server -r archive Serv1 > Serv1.archive
```

## Suggested Reading in Hardcopy

For information about:

- Global character support for server names, see “Wildcards” on page 9
- Attributes file, see “Attributes File” on page 10
- Headings and style, see “Command Output: Headings and Style” on page 9
- Attributes for Infoprint objects, see “Chapter 7. Infoprint Object Attributes” on page 325
- Non-settable, initially settable, and resettable attributes, see “Initially Settable, Resettable Attributes, and Non-Settable” on page 4

## Suggested Reading Online for Infoprint Manager for AIX

To view information about all supported attributes for Infoprint, enter the command:

```
man pd_att
```

## **pdl**

This displays a list of files by object from which you can select the attribute listing you want.

## pdmod Command: Modifies Attributes of Submitted Print Jobs

### Syntax

```
pdmod [-g] [-m "MessageText"] [-n CopyCount]
      [-r attribute ...] [-s StyleName] [-t JobName]
      [-x "attribute=value ..."] [-X AttributesFileName]
      {LocalJobID ... | GlobalJobID ...}
```

```
pdmod -h
```

### Description

Use the **pdmod** command to modify the values of job and document attributes of previously submitted jobs.

You may specify any resettable job and document attributes. See “Attributes for Documents and Default Documents” on page 449 and “Attributes for Jobs and Default Jobs” on page 523 for descriptions of all job and document attributes.

You can only modify preprocessing, pending, held, paused, or retained jobs. In general, you cannot modify processing or printing jobs. The only exception is if you modify only **job-hold=true**, the job will be paused, modified, and resumed.

Modifying an existing job may affect the scheduling of the job.

Table 4 lists the four modification operators.

Table 4. *pdmod* Operators

Operator	Syntax	Description
Replace	<i>attribute=value</i>	Replaces the entire value of the attribute <i>attribute</i> with <i>value</i> or, if not already present, adds the attribute-value pair to the job.
Add values	<i>attribute+=value</i>	Adds the value <i>value</i> to the attribute <i>attribute</i> . You cannot add values to single-valued attributes. An add request that duplicates values on a multi-valued attribute has no effect on the job.
Remove values	<i>attribute-=value</i>	Removes the value <i>value</i> from the attribute <i>attribute</i> . A remove request for a nonexistent value has no effect on the object. A remove request for the last or only value of an attribute is equivalent to a reset-to-default request.
Reset to default	<i>attribute==</i>	Sets the attribute <i>attribute</i> to the default values according to the job-defaulting hierarchy. If you supply values with a reset request, Infoprint ignores them.

If you do not specify a value with a replace, add, or remove request, Infoprint issues an error and rejects the request to change the attribute value for the object.

**Note:** If Infoprint does not accept a modification, Infoprint rejects the whole request and the job continues as before.

## pdmod

Use the global job identifier to identify jobs belonging to another person. If you use DCE, you must have **write** permission for the server to modify other people's jobs.

## Flags

You can use the following flags with the **pdmod** command:

**-g** Turns off headings.

Using this flag is equivalent to specifying the command attribute **headings=false**.

**-h** Displays a command-specific help message containing information about command syntax and flags. If you use this flag with any other flag or attribute, Infoprint recognizes only the **-h** flag.

**-m** "*MessageText*"

Specifies the message you want to store in the **job-message-from-administrator** attribute. You can use the message to give the reason why you are modifying the job or to provide any other comments. If you do not specify the **-m** flag, the message already stored with the job remains unchanged.

You can list this message by specifying **requested-attributes=job-message-from-administrator** with the **pdls** command.

Using this flag is equivalent to specifying the command attribute **message**.

**-n** *CopyCount*

Specifies the number of document copies.

Using this flag is equivalent to specifying the object attribute **copy-count**.

**-r** {**none** | **brief** | **verbose**}

Specifies the attribute values you want to display for the specified object.

**none** Displays no attributes.

**brief** Displays a small subset of important attributes for each object.

**verbose**

Displays a larger subset of important attributes for each object.

Using this flag is equivalent to specifying the command attribute **requested-attributes**.

**-s** {**column** | **docol** | **line**}

When combined with the **-r** flag or the **requested-attributes** command attribute, specifies the format in which you want Infoprint to display the attributes.

**column**

Attribute values are displayed in tabular format, so that values of the same attribute for multiple objects line up in columns.

**docol**

For jobs only, job attribute values and the document attribute values for the first document in the job are displayed in column format on the same line.

**line** Each attribute is displayed on a separate line.

Using this flag is equivalent to specifying the command attribute **style**.

**-t JobName**

Specifies the new name you want for the job.

Using this flag is equivalent to specifying the object attribute **job-name**.

**-x "attribute=value ..."**

Consists of an attribute string, containing one or more attribute-value pairs. Prefix the attribute value with the replace operator, =, to replace a value, with the add-values operator, +=, to add a value, or the remove-values operator, -=, to remove a value. Use the reset-to-default operator, ==, with no attribute value to set the attribute to its default value.

**-X AttributesFileName**

Specifies the name of a file containing attribute and value pairs you want Infoprint to insert at the current point in the command.

Using this flag is equivalent to specifying the command attribute **attributes**.

## Command Attributes

You can specify these attributes in a **-x "attribute=value ..."** string or in an attributes file designated with the **-X AttributesFileName** flag.

**attributes=AttributesFileName**

Specifies the designated attributes file that Infoprint reads and inserts at the current point in the command. This file contains attribute and value pairs that Infoprint uses to expand the command.

**headings={true | false}**

Specifies if you want Infoprint to display headings on the output.

**message="MessageText"**

Specifies the message you want to store in the **job-message-from-administrator** attribute. You can use the message to give the reason why you are modifying the job or to provide any other comments. If you do not specify the **message** attribute, the message already stored with the job remains unchanged.

You can list this message by specifying **requested-attributes=job-message-from-administrator** with the **pdlis** command.

**requested-attributes={none | brief | verbose}**

Specifies which attributes you want displayed.

**none** Displays no attributes.

**brief** Displays a small subset of important attributes for each object.

**verbose**

Displays a larger subset of important attributes for each object.

**style={column | doccol | line}**

Specifies the presentation format that you want for the displayed output.

**column**

Attribute values are displayed in tabular format, so that values of the same attribute for multiple objects line up in columns.

**doccol**

For jobs only, job attribute values and the document attribute values for the first document in the job are displayed in column format on the same line.

**line** Each attribute is displayed on a separate line.

## pdmod

### Arguments

Use the argument value to identify the specific object that you want to modify. If you specify multiple objects, separate the object names with spaces.

*LocalJobID or GlobalJobID*

Specifies the local or global job identifier.

### Examples

#### Modify Content Orientation

To modify the job with a local ID of 10 and change the orientation to landscape, enter the command:

```
pdmod -x "content-orientation=landscape" 10
```

#### Modify Job Hold Condition

To modify the job attribute **job-hold** to **false** for job 10 so that Infoprint can schedule the job (previously submitted with **job-hold** set to **true**), enter the command:

```
pdmod -x "job-hold=false" 10
```

#### Modify Job Comment

To modify the job attribute **job-comment** to Test Results 100 for job 10, enter the command:

```
pdmod -x "job-comment='Test Results 100'" 10
```

#### Modify the Number of Sides that Print

To modify the document attribute **sides** to specify that all documents in the job with global identifier DivSpool2:1011222243 should print on both sides, enter the command:

```
pdmod -x "sides=2" DivSpool2:1011222243
```

#### Add a Destination Location Request

To add a destination location request to job 10, enter the command:

```
pdmod -x "destination-locations-requested+='bldg.10 room 1-15'" 10
```

#### Remove a Destination Location Request

To remove a destination location request from job 10, enter the command:

```
pdmod -x "destination-locations-requested-='bldg.25 room 3-22'" 10
```

#### Remove All Destination Location Requests

To remove all destination locations requested from job 10, enter the command:

```
pdmod -x "destination-locations-requested==" 10
```

#### Combining Modifications

To modify job 17, by changing the content-orientation and removing the hold on the job, enter the command:

```
pdmod -x "content-orientation=landscape job-hold=false" 17
```

### Suggested Reading in Hardcopy

For information about:

- Attributes files, see “Attributes File” on page 10
- Headings and style, see “Command Output: Headings and Style” on page 9
- Job defaulting-hierarchy, see “pdpr Command: Submits Jobs” on page 63
- Job attributes, see “Attributes for Jobs and Default Jobs” on page 523
- Document attributes, see “Attributes for Documents and Default Documents” on page 449



- Non-settable, initially settable, and resettable attributes, see “Initially Settable, Resettable Attributes, and Non-Settable” on page 4

## **Suggested Reading Online**

To view information about job attributes, enter the command:

```
man pd_att_job
```

To view information about document attributes, enter the command:

```
man pd_att_document
```

## pdpause Command: Pauses Jobs, Actual Destinations, Servers, or Queues

### Syntax

```
pdpause [-c destination] [-m "MessageText"] [-n]
        [-x "attribute=value ..."] [-X AttributesFileName]
        [-w {now | after-current-copy | after-current-job}]
        [ServerName:]DestinationName ...
```

```
pdpause -j [-m "MessageText"]
        [-x "attribute=value ..."] [-X AttributesFileName]
        [-w {now | after-current-copy}] [ServerName:]DestinationName ...
```

```
pdpause -c job [-m "MessageText"] [-x "attribute=value ..."]
        [-X AttributesFileName] [-w {now | after-current-copy}]
        {LocalJobID ... | GlobalJobID ...}
```

```
pdpause -c queue [-m "MessageText"] [-x "attribute=value ..."]
        [-X AttributesFileName] [ServerName:]QueueName ...
```

```
pdpause -c server [-m "MessageText"] [-n]
        [-x "attribute=value ..."] [-X AttributesFileName]
        [-w {now | after-current-copy | after-current-job}]
        ServerName ...
```

```
pdpause -h
```

### Description

Use the **pdpause** administrative command to pause an object that holds jobs or to pause a job.

You can pause these objects:

- Jobs that are
  - **pending**
  - **held**
  - **ripping**
  - **imposing**
  - **processing**
  - **printing**
- Actual destinations
  - Note:** You cannot pause PSF upload-TCP/IP-attached physical printers or PSF upload-SNA-attached physical printers.
- Queues
- Servers (pauses all of the queues and actual destinations contained in a server)

To resume a paused object, use the **pdresume** command.

**Note:** Use the **pdpause** and **pdresume** commands to prevent or allow output from the object. Use the **pddisable** and **pdenable** commands to prevent or allow input to the object.

## Flags

You can use the following flags with the **pdpause** command:

**-c {destination | queue | job | server}**

Specifies the object class you want to pause. Within the valid classes, **destination** is an actual destination.

Using this flag is equivalent to specifying the command attribute **class**.

**-h** Displays a command-specific help message containing information about command syntax and flags. This flag and any other flag are mutually exclusive (if you use it with any other flag or attribute, Infoprint recognizes only the **-h** flag).

**-j** This flag is only valid when you use it with object-class **destination**. Use this flag to pause the currently printing job on the specified actual destination. The actual destination must be a physical printer, not a fax destination or an email destination.

**-m "MessageText"**

Specifies the message you want to associate with the specified destination, queue, job, or server that you are pausing. You can use this message to indicate the reason that you are pausing the object or to provide any other comments.

When pausing a server, Infoprint propagates the message to the **message** attribute of the actual destinations and queues residing in the server.

If the command operates on a destination or a queue, you can list this message by specifying **requested-attributes=message** with the **pdls** command.

When the command operates on a job, the specified text becomes the value of the **job-message-from-administrator** attribute. You can list this message by specifying **requested-attributes=job-message-from-administrator** with the **pdls** command.

If you do not specify the **-m** flag, the message already stored with the destination, queue, job, or server remains unchanged.

Using this flag is equivalent to specifying the command attribute **message**.

**-n** Causes the destination to perform an NPRO (move the last printed page to the stacker). Using this flag is equivalent to specifying the command attribute **non-process-runout=true**.

This flag is valid only with object class **destination** or **server**. It is not valid with the **-j** flag. It is valid only for PSF physical printers and for servers containing them.

**-w {now | after-current-copy | after-current-job}**

Specifies when to pause the destination, job, or server. If you specify:

**now** and the paused object is a:

**destination**

The destination pauses as soon as possible. How long this takes depends on the output device.

**job**

The job pauses as soon as possible. If the job is processing or printing, how long this takes depends on the output device.

## pdpause

**server** The server pauses as soon as possible. How long this takes depends on the output devices represented by the destinations in the server.

### after-current-copy

and the paused object is a:

#### destination

The destination pauses after the current copy of the current job finishes printing.

**job** The job pauses after the current copy finishes printing.

**server** The server pauses after the current copy of the current job on each actual destination in the server finishes printing.

This value is valid only for PSF physical printers, for jobs printing on PSF physical printers, and for servers containing PSF physical printers.

### after-current-job

and the paused object is a:

#### destination

The destination pauses after the current job finishes printing.

**server** The server pauses after the current job on each actual destination in the server finishes printing.

This value is not valid for jobs, including jobs paused with the **-j** flag. It is valid only for PSF physical printers and for servers containing PSF physical printers.

Specifying this flag is equivalent to specifying the command attribute **when**.

**-x** *"attribute=value ..."*

A single attribute string, consisting of one or more attribute-value pairs.

**-X** *AttributesFileName*

Specifies the name of a file containing attribute and value pairs you want inserted at the current point in the command.

Using this flag is equivalent to specifying the command attribute **attributes**.

## Command Attributes

You can specify these attributes in a **-x** *"attribute=value ..."* string or in an attributes file designated with the **-X** *AttributesFileName* flag.

**attributes=AttributesFileName**

Specifies the designated attributes file that Infoprint reads and inserts at the current point in the command. This file contains attribute and value pairs that Infoprint uses to expand the command.

**class={destination | queue | job | server}**

Specifies the object class that you want to pause. Within the valid classes, **destination** is an actual destination.

**message="MessageText"**

Specifies the message that you want to associate with the specified

destination, queue, job, or server that you are pausing. You can use this message to indicate the reason you are pausing the object or to provide any other comments.

When pausing a server, Infoprint propagates the message to the **message** attribute of the actual destinations and queues residing in the server. Infoprint does not change the server **message** attribute.

If the command operates on a destination or a queue, you can list this message by specifying **requested-attributes=message** with the **pdls** command.

When the command operates on a job, the specified text becomes the value of the **job-message-from-administrator** attribute. You can list this message by specifying **requested-attributes=job-message-from-administrator** with the **pdls** command.

If you do not specify the **message** attribute, the message already stored with the destination, queue, job, or server remains unchanged.

**non-process-runout={true | false}**

Specifies whether the destination should perform an NPRO (move the last printed page to the stacker). This attribute is valid only with object class **destination** or **server**. It is not valid with the **-j** flag. It is valid only for PSF physical printers and for servers containing them.

**when={now | after-current-copy | after-current-job}**

Specifies when to pause the destination, job, or server. If you specify:

**now** and the paused object is a:

**destination**

The destination pauses as soon as possible. How long this takes depends on the output device.

**job**

The job pauses as soon as possible. If the job is processing or printing, how long this takes depends on the output device.

**server**

The server pauses as soon as possible. How long this takes depends on the output devices represented by the destinations in the server.

**after-current-copy**

and the paused object is a:

**destination**

The destination pauses after the current copy of the current job finishes printing.

**job**

The job pauses after the current copy finishes printing.

**server**

The server pauses after the current copy of the current job on each actual destination in the server finishes printing.

This value is valid only for PSF physical printers, for jobs printing on PSF physical printers, and for servers containing PSF physical printers.

**after-current-job**

and the paused object is a:

## pdpause

### **destination**

The destination pauses after the current job finishes printing.

**server** The server pauses after the current job on each actual destination in the server finishes printing.

This value is not valid for jobs, including jobs paused with the **-j** flag. It is valid only for PSF physical printers and for servers containing PSF physical printers.

## Arguments

Use the argument value to identify the specific object that you want to pause. If you specify multiple objects, all of the objects must belong to the same class and you must separate the object names with spaces.

You can use the following arguments with the **pdpause** command:

### *LocalJobID... or GlobalJobID...*

Specifies the jobs that you want to pause as determined by a local job identifier or global job identifier. If you use DCE, by default, only administrators have the authority to pause jobs. If you do not use DCE, by default, administrators and operators have the authority to pause jobs but end users do not. Therefore, in most cases someone other than the job submitter will pause a job and must identify it by the global job ID. Job submitters who do have authority to pause jobs can identify their own jobs by the local job ID.

The following actions take place when you cause Infoprint to pause:

#### **A ripping or imposing job:**

- The job stops. If the first pages of the job have started to print or transmit while the last pages are ripping or imposing, the job is treated like a printing job.
- The job state changes to paused.
- The destination remains available to accept work.
- Infoprint can assign other jobs to the destination.

#### **A processing or printing job:**

- The job stops.
  - If you specify **-w=after-current-copy**, the job stops after the current copy finishes printing.
  - Otherwise, the job stops as soon as possible. How long this takes depends on the type of output device printing or transmitting the job.
- The job state changes to paused.
- The destination remains available to accept work.
- Infoprint can assign other jobs to the destination.

#### **A pending job:**

Infoprint prevents scheduling of the job but does not affect any destination.

#### **A held job:**

Infoprint prevents the job from becoming pending, even if you or Infoprint removes the reason for the job hold. For example, the specified **job-print-after** time expires.

Paused jobs remain in the queue until someone resumes or cancels them. Infoprint allows modification of a paused job, but you cannot resubmit the job until you issue a **pdresume** command for the job.

**Note:** If you modify a paused job, it resumes at the beginning, not at the point where it paused.

*[ServerName:]DestinationName*

Specifies the destinations you want to pause. The action taken depends on whether you include the **-j** flag in the command.

**Without the -j flag:**

- The destination stops.
  - If you specify **-w=after-current-job**, the destination stops after the current job finishes printing.
  - If you specify **-w=after-current-copy**, the destination stops after the current copy finishes printing.
  - Otherwise, the destination stops as soon as possible. How long this takes depends on the type of output device.
- Infoprint changes the destination state to paused.
- Infoprint leaves the job state unchanged; the job is still assigned to the destination.

The actual destination still accepts jobs from its associated queue up to the maximum-concurrent-jobs limit, but does not print them.

**With the -j flag:**

- The job now printing on the destination stops.

**Note:** The actual destination must be a physical printer, not a fax destination or an email destination.

- If you specify **-w=after-current-copy**, the job stops after the current copy finishes printing.
- Otherwise, the job stops as soon as possible. How long this takes depends on the type of printer device.
- Infoprint changes the job state to paused.
- The destination remains available to accept work.
- Infoprint can assign other jobs to the destination.

The actual destination may still accept jobs from its associated queue and process them.

**Note:** You cannot pause logical destinations because they do not hold jobs.

*[ServerName:]QueueName*

Specifies the queues you want to pause.

Pausing a queue halts the distribution of jobs from the queue to the actual destinations associated with the queue. Pausing a queue does not prevent it from accepting jobs from its associated logical destinations.

*ServerName*

Specifies the server on which you want the command to operate. A server does not have a paused state. Issuing the command against a server pauses all queues and actual destinations contained within the server.

## pdpause

### Examples

#### **Pause an Actual Destination**

To pause actual destination molly-pp and include a message as to why you are pausing the destination, enter the command:

```
pdpause -m "Toner is low, refilling" molly-pp
```

#### **Pause a Currently Printing Job**

To pause the currently printing job on destination molly-pp, enter the command:

```
pdpause -j molly-pp
```

#### **Pause a Queue**

To pause the queue Div1Q2, enter the command:

```
pdpause -c queue Div1Q2
```

#### **Pause All Queues in a Server**

To pause all of the queues in server DivServ1, enter the command:

```
pdpause -c server DivServ1
```

#### **Pause an Actual Destination after the Current Copy with NPRO**

To pause actual destination molly-pp after the current copy and move the last printed sheet to the stacker, enter the command:

```
pdpause -w after-current-copy -n molly-pp
```

### Suggested Reading

For information about:

- Attributes file, see "Attributes File" on page 10



## pdpr Command: Submits Jobs

### Syntax

```
pdpr [{-d | -p} LogicalDestinationName]
[-f FileName ...] [-g]
      [-l] [-n CopyCount] [-N NotificationMethod]
      [-r attribute ...] [-s StyleName] [-t JobName]
      [-x "attribute=value ..."] [-X AttributesFileName]
      [-Z InputFileName] {- | FileName ...}

pdpr -T TapeDevice [{ -d | -p} TargetDestinationName] [-g] [-l]
      [-n CopyCount] [-N NotificationMethod] [-r attribute ...]
      [-s StyleName] [-t JobName]
      [-x "attribute=value ..."] [-X AttributesFileName]
      [-Z InputFileName]
{FileName ... | [N]#FileNumber...}
```

```
pdpr -h
```

### Description

Use the **pdpr** command to submit jobs to logical destinations. Each job can contain multiple printable documents and, for jobs sent to PSF physical printers, fax destinations, or email destinations, any number of resources.

With Infoprint Manager for AIX, the target destination name defaults to the value of the **PDPRINTER** environment variable. You can override the default by specifying the name of another logical destination using the **-d** or **-p** flag or the job attribute **destination-name-requested**.

When the server accepts the job request, Infoprint assigns a unique global ID (job identifier) and a local ID to it. Only the job submitter can use the local ID. The job submitter can use either the global ID or the local ID in subsequent commands, such as **pdmod**, **pdrm**, or **pdls**. Anyone else who accesses the job, such as an administrator, must use the global ID.

Infoprint sets the values for job and document attributes from these possibilities:

1. Values specified in the **pdpr** command using the **-x "attribute=value ..."** flag or the **-X AttributesFile** flag.

**Note:** If multiple values for the same attribute are specified in the **pdpr** command, Infoprint uses the last value read, except for those attributes that can have different values for different documents in the same job.

2. The values of a default job specified by the job attribute **initial-value-job** or the values for a default document specified by the document attribute **initial-value-document**.
3. The values of a default job specified by the **destination-initial-value-job** attribute or the values of a default document specified by the **destination-initial-value-document** attribute of the logical destination to which the user submitted the job.
4. Server defaults for required attribute values not specified through the previous methods.

## pdpr

You must be authorized to submit jobs to the specified destination if the logical destination is protected (the value of its **authorize-jobs** attribute is **true**).

If the server cannot locate an actual destination (associated with the requested logical destination) supporting the job and document attributes, Infoprint rejects the job.

## Flags

You can use the following flags with the **pdpr** command:

### **-d** *TargetDestinationName*

The target destination can be either the actual destination name if **logical-destination-assigned** is set on the actual destination or the logical destination name to which you want to submit the job.

With Infoprint Manager for AIX, if you do not specify this flag (or the equivalent **-p** flag), Infoprint uses the **PDPRINTER** environment variable to determine the destination.

Using this flag is equivalent to specifying the **destination-name-requested** attribute.

### **-f** *FileName*

Specifies files you want included in the job. Use this flag only with file identifiers that are not placed at the end of the command. For example, to print all pages of `file1` and pages 3 through 6 of `file2`, enter:

```
pdpr -f file1 -x page-select=3:6 file2
```

This flag is not valid for tape input.

### **-g**

Turns off headings.

Using this flag is equivalent to specifying the command attribute **headings=false**.

### **-h**

Displays a command-specific help message containing information about command syntax and flags. If you use this flag with any other flag or attribute, Infoprint recognizes only the **-h** flag).

### **-l**

Creates symbolic links to the job files rather than making temporary copies when used with Infoprint Manager for AIX. When Infoprint assigns the job to an actual destination, the server uses the links to the job files to locate the original files and copies them (if needed) at that time. This can be useful when printing large files or jobs.

#### **Notes:**

1. Use this flag only for jobs submitted from AIX to an AIX server; you cannot use it when submitting jobs from a workstation client or to a Windows server.
2. You must use caution when using this flag because:
  - a. Depending on when you make changes to the files and when the server prints them, the printed output may or may not reflect the changes.
  - b. If you delete the file before the job prints or while the job is printing, the printed output may fail or be incomplete.
  - c. When you are using an AIX client and sending a **pdpr** command with **PDHOST** or **PD\_SOCKET**, you cannot specify the **-l** flag.

### **-n** *{1 | CopyCount}*

Specifies the number of document copies that you want to print.

If you do not specify the **-n** flag, the copy count defaults to one (1).

Using this flag is equivalent to specifying the document attribute **copy-count=CopyCount**.

**Note:** You cannot use the **-n** flag or the document attribute **copy-count** if the job contains inline resources. Use the job attribute **results-profile** instead.

**-N {message | email | job-log| none}**

Specifies the delivery method that you want to use for notification of job events for this job.

**Note:** Using this flag and its value causes Infoprint to generate a **notification-profile** attribute value for this job.

**-p TargetDestinationName**

The target destination can be either the actual destination name if **logical-destination-assigned** is set on the actual destination or the logical destination name to which you want to submit the job.

With Infoprint Manager for AIX, if you do not specify this flag (or the equivalent **-d** flag), Infoprint uses the **PDPRINTER** environment variable to determine the destination.

Using this flag is equivalent to specifying the **destination-name-requested** attribute.

**-r {none | brief | verbose}**

Identifies the job attribute values that you want to display for the job just created.

**none** Displays no attributes.

**brief** Displays a small subset of important attributes for the job.

**verbose**

Displays a larger subset of important attributes for the job.

Using this flag is equivalent to specifying the command attribute **requested-attributes**.

**-s {column | doccol | line}**

When combined with the **-r** flag or the **requested-attributes** command attribute, specifies the format in which you want the attributes displayed.

**column**

Attribute values are displayed in tabular format, so that values of the same attribute for multiple objects line up in columns.

**doccol**

For jobs only, job attribute values and the document attribute values for the first document in the job are displayed in column format on the same line.

**line** Each attribute is displayed on a separate line.

Using this flag is equivalent to specifying the command attribute **style**.

**-T TapeDevice**

With Infoprint Manager for AIX, specifies the name of the tape device from which **pdpr** reads the input file. Specify the name without prefixing **/dev**, for example, **-T rmt0**.

**-t** *JobName*

Specifies the name you want to assign to the job.

Using this flag is equivalent to specifying the job attribute **job-name**.

**-x** "*attribute=value ...*"

Consists of a single attribute string containing one or more attribute-value pairs.

Any document attribute defined with the **-x** flag affects all files whose names follow that **-x** flag on the command line, unless you reset that attribute.

To reset an attribute to the default value, specify *AttributeName==*. For example, to reset the **document-type** attribute to its default value, **printable**, specify

```
document-type==
```

**-X** *AttributesFileName*

Specifies the name of a file containing attribute and value pairs that you want Infoprint to insert at the current point in the command.

Any document attribute in the file defined with the **-X** flag affects all files whose names follow that **-X** flag on the command line, unless you reset that attribute.

To reset an attribute to the default value, specify *AttributeName==*. For example, to reset the **document-type** attribute to its default value, **printable**, specify

```
document-type==
```

Using this flag is equivalent to specifying the command attribute **attributes**.

**-Z** *InputFileName*

Specifies the name of a file containing command flags, command attributes, or the names of files to be printed, that you want Infoprint to insert at the current point in the command. Use this flag when the command is too long to fit on the command line.

- Entering a dash (hyphen) causes the command to read from standard input (STDIN). If you use this flag, it must occur at the end of the command after any other flags or command attributes.

## Command Attributes

You can specify these attributes in a **-x** "*attribute=value ...*" string or in an attributes file designated with the **-X** *AttributesFileName* flag.

**attributes=AttributesFileName**

Specifies the designated attributes file that Infoprint reads and inserts at the current point in the command. This file contains attribute and value pairs that Infoprint uses to expand the command.

Any document attribute in the attributes file affects all files whose names follow that **attributes** command attribute on the command line, unless you reset that attribute.

To reset an attribute to the default value, specify *AttributeName==*. For example, to reset the **document-type** attribute to its default value, **printable**, specify

```
document-type==
```

**headings={true | false}**

Specifies whether you want Infoprint to display headings with the attributes.

**requested-attributes={none | brief | verbose}**

Specifies which job attributes you want Infoprint to display.

**none** Displays no attributes.

**brief** Displays a small subset of important attributes for each object.

**verbose**

Displays a larger subset of important attributes for each object.

**style={column | doccol | line}**

Specifies the presentation format in which you want Infoprint to display the output.

**column**

Attribute values are displayed in tabular format, so that values of the same attribute for multiple objects line up in columns.

**doccol**

For jobs only, job attribute values and the document attribute values for the first document in the job are displayed in column format on the same line.

**line** Each attribute is displayed on a separate line.

## Job and Document Attributes Used with the Command

There are two types of object attributes used with the **pdpr** command, per-job and per-document. You can specify these attributes in a **-x "attribute=value ..."** string or in an attributes file designated with the **-X AttributesFileName** flag. You can specify any initially settable or resettable job or document attribute with the **pdpr** command. See "Attributes for Documents and Default Documents" on page 449 and "Attributes for Jobs and Default Jobs" on page 523 for descriptions of job and document attributes.

### Per-Job Attributes

Per-job attributes apply to the job as a whole and may occur anywhere in the **pdpr** command.

### Per-Document Attributes

If you specify some document attributes before the first document (file) on the command line, those attributes apply to all documents (files) you specify for this job. If you specify a different document attribute between the first and second document (files), that attribute applies to the second document and any following document you specify for this job. This progression of attributes to files continues until the last document (file) specified.

The value for a given attribute must be the same for all the documents in the job except for those listed in "Per-Document Attribute Listing" on page 451. Even for those attributes, the value must be the same for all documents in the job if

- The job is submitted from tape
- The documents are in ASCII format

## Arguments

Use the argument value to identify the name or tape position of a file that you want to print. If you specify multiple file identifiers, separate the file identifiers with spaces. Each file becomes a document within the job. Unless you end the

## pdpr

command with the **-** flag, indicating that **pdpr** is to read from standard input, you must place at least one file identifier without the **-f** flag at the end of the command.

### *FileName ...*

Specifies the document that you want to print. Precede the file name by any per-document attributes.

### **[N]#FileName ...**

With Infoprint Manager for AIX, when you submit a file from tape, instead of the file name you can specify the position of the file on the tape. The number sign (**#**) indicates a file number and the backslash (**\**) escapes the number sign. If your shell does not have a special meaning for the number sign, you can omit the backslash.

If you specify a multi-document job, and if Infoprint cannot support one or more of the documents within the job, Infoprint rejects the job and issues an error message.

## Examples for Infoprint Manager for AIX

### Print a Job on the Default Logical Destination

To submit the file `File1` to your default logical destination, enter the commands:

```
pdpr File1
```

### Print a Multi-Document Job

To submit the files `File1` and `File2` to the default logical destination, enter the command:

```
pdpr File1 File2
```

### Fax a Job

To submit the cover sheet `faxcover` and the file `Memo1` to the logical destination `Serv1-faxout` for faxing to fax number 1-709-123-4567, enter the command:

```
pdpr -d Serv1-faxout -x "fax-number=17091234567
document-type=cover-sheet" -f faxcover
-x "document-type=printable" Memo1
```

### Email a Job

To submit the file `report.ps` to the logical destination mailbox for electronic mailing to `julia@kingston`, enter the command:

```
pdpr -d mailbox -x "email-to-address=julia@kingston
subject-text='Status Report'" report.ps
```

### Print Multiple Copies of Each Document in a Job

To submit a job to the default logical destination and to specify two copies of each file in the job, enter one of these commands:

```
pdpr -n 2 Title Contents Body1 Body2 Append
```

```
pdpr -x "copy-count=2" Title Contents Body1 Body2 Append
```

Infoprint prints two copies of `Title`, followed by two of `Contents`, and so forth for each file in the job.

**Note:** You cannot use the **-n** flag or the document attribute **copy-count** if the job contains inline resources. Use the job attribute **results-profile** instead.

### Print Multiple Copies of a Job

To submit the job to the default logical destination and to specify two copies of the complete job, enter the command:

```
pdpr -x "results-profile=:2" Title Contents Body1 Body2 Append
```

Infoprint prints a single copy of each file in the job, and then prints a second set in the same manner.

### Print Multiple Copies of Documents and Jobs

To submit a job to the default logical destination and to specify two copies of the complete job with each copy of the job containing three copies of each file, enter the command:

```
pdpr -n 3 -x "results-profile=:2" Title Contents Body1 Body2 Append
```

Infoprint prints three copies of Title, followed by three copies of Contents and so until the first copy of the job completes. Then Infoprint prints a second set in the same manner.

### Specify Job Name

To submit the file File1 to your default logical destination and to specify the job name, enter the command:

```
pdpr -t CmdRef File1
```

### Print a Duplexed Job

To submit the file File1 to the default logical destination and to specify normal-duplexed printing, enter the command:

```
pdpr -x "sides=2 plex=simplex" File1
```

### Specify Document Format

To submit the file PSFile2 to the default logical destination and to specify a document format of ASCII, enter the command:

```
pdpr -x "document-format=ascii" PSFile2
```

### Request Status

To submit the file File1 to the default logical destination and to receive brief status information, enter the command:

```
pdpr -r brief File1
```

Infoprint displays information similar to the following:

Job	ID	Name	Current State	Destination Requested	Destinations Assigned
8	sp15:0754100002	File1	pending	LogPrt1	

### Delay Printing

To submit the file BigJob to the default logical destination and to delay printing until after 6:30 p.m. on May 2, 1997, enter the command:

```
pdpr -x "job-print-after='18:30:00 05/02/97'" BigJob
```

### Specify a Symbolic Link

To submit the file BigJob to a logical destination LogPrt4 without copying the file, enter the command:

```
pdpr -p LogPrt4 -l BigJob
```

### Specify Job Discard Time

To submit the file BigJob to the default logical destination and to specify that Infoprint is to discard the job if it has not printed by 5:00 p.m., enter the command:

```
pdpr -x "job-discard-time=17:00:00" BigJob
```

### Retain a Job

To submit the file `File1` to the default logical destination requesting feedback of job attributes (brief group), and to specifying a retention period of 90 minutes so you can print more copies after you have looked at the first copy, enter the command:

```
pdpr -r brief -x "job-retention-period=90" File1
```

Note the job number (local ID) so you can use that number when you want to print more copies within the time allotted.

### Specify Default Job and Document

To submit the file `File1` to the default logical destination and use the job attribute values specified in the default job `ivj23` and the document attribute values specified in the default document `ivd44`, enter the command:

```
pdpr -x "initial-value-document=ivd44 initial-value-job=ivj23" File1
```

### Specify Attributes Files for a Job

To submit the file `File5` to the default logical destination and to specify the two attributes files `default.att` and `special.att`, enter the command:

```
pdpr -X default.att -X special.att File5
```

### Specify Different Attribute Values for Different Documents

To submit the files `File5`, `File6`, and `File7` to the default logical destination and to specify that:

- Each document starts on a new sheet of paper
- You want to print pages 11 through 20 of `File5`, all pages of `File6`, and all pages of `File7`
- Each document has a different estimated page count

enter the command:

```
pdpr -x "start-on-new-sheet=true page-select=11:20 page-count=10"  
-f File5 -x "page-select== page-count=3" -f File6  
-x "page-count=19" File7
```

### Override an Attribute Value in an Attributes File

To submit the file `File1` to the default logical destination and override the value of 2 for the **sides** attribute specified in a given attributes file, enter the command:

```
pdpr -X default.att -x "sides=1" File1
```

### Request Feedback Concerning the Job as Each Event Happens

To submit the file `File1` to the default logical destination and to have all possible event notifications sent to you by electronic mail, enter the command:

```
pdpr -x "notification-profile={event-identifiers=job-modified  
class-job-problem class-job-attention delivery-method=electronic-mail}" File1
```

### Print Files from Tape

To print the second and third files on the tape mounted on tape device `rmt0`, enter:

```
pdpr -T rmt0 \#2 \#3
```

## Examples for Infoprint Manager for AIX and Infoprint Manager for Windows NT and Windows 2000

### Print a Job on a Specified Logical Destination

To submit the file `File1` to the logical destination `fred-lp`, enter the command:

```
pdpr -d fred-lp File1
```



**Print a Job on a Specified Actual Destination**

To submit the file `File5` for printing on actual destination `draft-pp`, enter the command:

```
pdpr -p fred-lp -x "actual-destinations-requested=draft-pp" File5
```

**Specify Destination Location**

To submit the file `File5` for printing on one of the printer devices located in Building 20, Room 17, enter the command:

```
pdpr -d LogPrt20 -x "destination-locations-requested=bld20.rm17" File5
```

**Specify a Medium**

To submit the file `MyAddress` to logical destination `MServ-lp` and to specify a default medium of `number-10-envelope` for the job, enter the command:

```
pdpr -p MServ-lp -x "default-medium=number-10-envelope" MyAddress
```

**Specify a Command Input File**

To submit a job and read the command flags, command attributes, and names of files to be printed from the file `pdinput` instead of from the command line, enter the command:

```
pdpr -Z pdinput
```

**Specify a Code Page for ASCII Jobs**

To print the files `File1` and `File2` and to specify the code page `IBM-863`, enter the commands:

```
pdpr -d LogPrtPSF -x "default-character-mapping=IBM-863" File1 File2
```

**Print a Range of Pages**

To print pages 1 through 10 of the file `report.ps`, enter the command:

```
pdpr -p LogPrtPSF -x "document-format=postscript  
destination-pass-through=-o-p 1-10" report.ps
```

**Suggested Reading in Hardcopy**

For information about:

- Attributes file, see “Attributes File” on page 10
- Headings and style, see “Command Output: Headings and Style” on page 9
- Document attributes, see “Attributes for Documents and Default Documents” on page 449
- Document attributes that can have different values for each document in a job, see “Per-Document Attribute Listing” on page 451
- Job attributes, see “Attributes for Jobs and Default Jobs” on page 523

**Suggested Reading Online for Infoprint Manager for AIX**

To view information about document attributes, enter the command:

```
man pd_att_document
```

To view information about job attributes, enter the command:

```
man pd_att_job
```

---

## pdpromote Command: Advances a Job to the Top of a Queue

### Syntax

```
pdpromote [-m "MessageText"] [-x "attribute=value ..."]
          [-X AttributesFileName] {LocalJobID | GlobalJobID}
```

```
pdpromote -h
```

### Description

Use the **pdpromote** administrative command to move a pending job before any currently-queued jobs. The job becomes the first job in the queue. If you then promote another job, it becomes the first job in the queue ahead of the job previously promoted.

A move to the beginning of the queue does not necessarily guarantee that the job is the next job to be printed or transmitted. The jobs currently printing on each of the actual destinations associated with the queue continue printing. The server assigns the promoted job to the first actual destination that:

- Becomes available
- Uses the **job-priority** scheduler
- Is capable of handling the promoted job

If you use DCE, you must have at least **read** and **write** authority for the queue to promote your own jobs as well as the jobs belonging to other people.

You can change the priority level of a job by setting the **job-priority** attribute with the **pdmod** or the **pdset** command. However, Infoprint promotes a job regardless of its priority to the top of the queue when you use the **pdpromote** command.

### Flags

You can use the following flags with the **pdpromote** command:

**-h** Displays a command-specific help message containing information about command syntax and flags. If you use this flag with any other flag or attribute, Infoprint recognizes only the **-h** flag.

**-m "MessageText"**

Specifies the message you want to store in the **job-message-from-administrator** attribute. You can use this message to indicate why you want to promote the job or to provide any other comments. If you do not specify the **-m** flag, the message already stored with the job remains unchanged.

You can list this message by specifying **requested-attributes=job-message-from-administrator** with the **pdlis** command.

Using this flag is equivalent to specifying the command attribute **message**.

**-x "attribute=value ..."**

A single attribute string, consisting of one or more attribute and value pairs.

**-X AttributesFileName**

Specifies the name of a file containing attribute and value pairs that you want Infoprint to insert at the current point in the command.

Using this flag is equivalent to specifying the command attribute **attributes**.

## Command Attributes

You may specify these attributes in a **-x** *"attribute=value ..."* string or in an attributes file designated with the **-X** *AttributesFileName* flag.

### **attributes=AttributesFileName**

Specifies the designated attributes file that Infoprint reads and inserts at the current point in the command. This file contains attribute and value pairs that Infoprint uses to expand the command.

### **message="MessageText"**

Specifies a message you want to store in the **job-message-from-administrator** attribute. You can use this message to indicate why you want to promote this job or to provide any other comments. If you do not specify the **message** attribute, the message already stored with the job remains unchanged.

You can list this message by specifying **requested-attributes=job-message-from-administrator** with the **pdlis** command.

## Arguments

Use the argument value to identify the specific object that you want Infoprint to promote. You can use the following arguments with the **pdpromote** command:

### *LocalJobID or GlobalJobID*

Specifies the job you want to promote. By default, end users do not have permission to promote jobs. Therefore, in most cases someone other than the job submitter will promote a job and must identify it by the global job ID. Job submitters who do have permission to promote jobs can identify their own jobs by the local job ID.

When you specify a job with the **pdpromote** command, it becomes the first job in the queue. If a another job is then promoted, it becomes the first job in the queue (ahead of the job previously promoted).

## Example

To promote job Serv1:1099600001 and add a job message from the administrator, enter the command:

```
pdpromote -m "This job must be printed in 10 minutes" Serv1:1099600001
```

## Suggested Reading

For information about:

- Attributes file, see "Attributes File" on page 10

## pdq Command: Queries Job Status

### Syntax

```
pdq [-f "FilterCriteria"] [{-d | -p} DestinationName] [-F] [-g] [-j]
    [-r attribute ...] [-s StyleName] [-U]
    [-x "attribute=value ..."] [-X AttributesFileName]
    [LocalJobID[.DocNumber] ... | GlobalJobID[.DocNumber] ...]
```

```
pdq -h
```

### Description

Use the **pdq** command to list the status of some or all jobs submitted to a logical destination or assigned to an actual destination.

With Infoprint Manager for AIX, if you omit both the *LocalJobID* and the *GlobalJobID* and do not name a destination, Infoprint lists all the jobs in the queue associated with the default logical destination, as defined by the **PDPRINTER** environment variable.

If you do not specify a value for the **-r** flag or the command attribute **requested-attributes**, the **pdq** command defaults to the value **brief**. By default, you can list the attribute values only for the jobs you submit.

Infoprint lists the jobs in the order in which the queue considers them for printing.

You can use the filtering option so that Infoprint returns status only for some jobs. The jobs have a predefined value for the filter that is equal to the job attribute **user-name**; Infoprint sets this value to your login identity when you submit a job.

### Flags

You can use the following flags with the **pdq** command:

#### **-d** *DestinationName*

Queries all jobs in the queue associated with this destination, or all jobs assigned to this actual destination. The results depend on the destination realization and the value of the queue attribute **assign-to-destination**, as shown in Table 5.

Table 5. Results of the *pdq* Command

Destination Realization	assign-to-destination	pdq Returns
Logical	<b>true</b> or <b>false</b>	All jobs in the queue associated with the logical destination
Actual	<b>true</b>	All jobs assigned to the actual destination
Actual	<b>false</b>	All jobs in the queue associated with the actual destination

#### **-f** *"FilterCriteria"*

Specifies the filter selection criteria that you want to use for the jobs. Among the jobs, Infoprint returns only those matching the filter expression.

Using this flag is equivalent to specifying the command attribute **filter**.

- F Turns off all filtering, both specified and default. See the **-U** flag for only turning the default filter off.
- g Turns off headings.  
Using this flag is equivalent to specifying the command attribute **headings=false**.
- h Displays a command-specific help message containing information about command syntax and flags. If you use this flag with any other flag or attribute, Infoprint recognizes only the **-h** flag.
- j Returns only the job attributes.
- p *DestinationName*  
Same as **-d DestinationName**.
- r **{brief | verbose | archive | "attribute ..." | all | none}**  
Specifies the group of attributes you want to display.
  - brief** Displays a small subset of important attributes for each object.
  - verbose** Displays a larger subset of important attributes for each object.
  - archive** Writes only initially settable and resettable attributes to an archive file.
  - attribute ...* Displays the attributes you specify.
  - all** Displays all attributes.
  - none** Displays no attributes.

If you specify more than one of these values, Infoprint displays all the attributes requested.

Using this flag is equivalent to specifying the command attribute **requested-attributes**.
- s **{column | doccol | line}**  
Specifies the format in which you want Infoprint to display the attributes.
  - column** Attribute values are displayed in tabular format, so that values of the same attribute for multiple objects line up in columns.
  - doccol** For jobs only, job attribute values and the document attribute values for the first document in the job are displayed in column format on the same line.
  - line** Each attribute is displayed on a separate line.

Using this flag is equivalent to specifying the command attribute **style**.
- U Suppresses the default user-name filter.
- x *"attribute=value ..."*  
Consists of a single attribute string, containing one or more attribute and value pairs.

## pdq

### **-X AttributesFileName**

Specifies the name of a file containing attribute and value pairs that you want Infoprint to insert at the current point in the command.

Using this flag is equivalent to specifying the command attribute **attributes**.

## Command Attributes

You can specify these attributes in a **-x "attribute=value ..."** string or in an attributes file designated with the **-X AttributesFileName** flag.

### **attributes=AttributesFileName**

Specifies the designated attributes file that Infoprint reads and inserts at the current point in the command. This file contains attribute and value pairs that Infoprint uses to expand the command.

### **filter="FilterCriteria"**

Specifies the filter selection criteria you want used if you request attribute values for multiple objects. Infoprint selects only some of the candidate jobs based on the filtering criteria. A filter is a logical expression consisting of relationships between attributes and attribute values. Among the specified jobs, Infoprint only returns those whose attribute values match the filter expression.

The **filter** command attribute functions the same way for the **pdq** command as for the **pdlis** command.

### **headings={true | false}**

Specifies whether you want Infoprint to display headings for the requested attributes.

### **requested-attributes={brief | verbose | archive | "attribute ..." | all | none}**

Specifies the group of attributes you want to display.

**brief** Displays a small subset of important attributes for each object.

#### **verbose**

Displays a larger subset of important attributes for each object.

#### **archive**

Writes only initially settable and resettable attributes to an archive file.

#### **attribute ...**

Displays the attributes you specify.

**all** Displays all attributes.

**none** Displays no attributes.

If you specify more than one of these values, Infoprint displays all the attributes requested.

### **style={column | doccol | line}**

Specifies the presentation format in which you want Infoprint to display the attributes.

#### **column**

Attribute values are displayed in tabular format, so that values of the same attribute for multiple objects line up in columns.

**doccol**

For jobs only, job attribute values and the document attribute values for the first document in the job are displayed in column format on the same line.

**line** Each attribute is displayed on a separate line.

## Arguments

Use the argument value to identify the specific object for which you want the status. If you specify multiple objects, separate the object names with spaces.

You can use the following arguments with the **pdq** command:

*LocalJobID[.DocNumber]*

Specifies the job or documents you want Infoprint to list as determined by a local ID or a local ID and document number. If you specify multiple arguments on the command line, separate the arguments with spaces.

*GlobalJobID[.DocNumber]*

Specifies the job or documents you want Infoprint to list as determined by a global ID or a global ID and document number. If you specify multiple arguments on the command line, separate the arguments with spaces.

With Infoprint Manager for AIX, if you omit the **-d DestinationName** or **-p DestinationName** flag and the *LocalJobID* or *GlobalJobID* argument, Infoprint lists all of the jobs in the queue associated with your default logical destination, defined by your **PDPRINTER** environment variable.

## Examples

### Query All Jobs on the Default Logical Destination with Infoprint Manager for AIX

To list all your jobs sent to your default logical destination `Dsrv-1p`, enter the command:

```
pdq
```

Infoprint displays information similar to the following:

Job	ID	Name	State	Intervening Jobs	Destination Requested	Destinations Assigned
13	sp14:1104221000	File1	processing	0	Dsrv-1p	Dsrv-pp
14	sp14:1105226030	JobA	pending	7	Dsrv-1p	
15	sp14:1133000058	MyJob	pending	8	Dsrv-1p	

**Note:** If you issue the command:

```
pdq -U
```

Infoprint displays status information for all jobs in the queue associated with your default logical destination.

### Query All Your Jobs on a Logical Destination

To list all jobs that you sent to logical destination `dizzy-1p`, enter the command:

```
pdq -d dizzy-1p
```

### Query All Users' Jobs on a Logical Destination

To list all jobs that any user sent to logical destination `dizzy-1p`, enter the command:

## pdq

```
pdq -U -d dizzy
```

### Query All Your Jobs Assigned to an Actual Destination

To list all jobs that you submitted and that Infoprint assigned to actual destination proof-pp, enter the command:

```
pdq -p proof-pp
```

**Note:** If the value of **assign-to-destination** is **false** for the queue associated with proof-pp, Infoprint lists all your jobs in the queue.

## Suggested Reading in Hardcopy

For information about:

- Filters, see the **pdls** command attribute **filter**.
- Attributes file, see “Attributes File” on page 10.
- Headings and style, see “Command Output: Headings and Style” on page 9
- Job attributes, see “Attributes for Jobs and Default Jobs” on page 523
- Document attributes, see “Attributes for Documents and Default Documents” on page 449

## Suggested Reading Online

To view information about job attributes, enter the command:

```
man pd_att_job
```

To view information about document attributes, enter the command:

```
man pd_att_document
```



## pdreorder Command: Reassigns Jobs

### Syntax

```
pdreorder {-a [TargetServerName.:]TargetJobID |
           -b [TargetServerName.:]TargetJobID |
           -p [TargetServerName.:]TargetDestinationName |
           -s TargetServerName | -u TargetServerName}
           [-m "MessageText"] [-x "attribute=value ..."]
           [-X AttributesFileName] [ServerName.:]GlobalJobID ...
```

```
pdreorder -h
```

### Description

Enter the **pdreorder** command to request Infoprint to reassign a job to a actual destination or to the unassigned jobs area in the same server or another server. You can assign the job to the actual destination where another job is assigned and specify that it should be printed or transmitted before or after the other job. You can reassign the job to a specified actual destination, request the server to reschedule the job, or request the server to make the job an unassigned job.

If a job is reordered to an actual destination that does not support the job's attribute values, the job is held and the **required-resources-not-supported** attribute lists the unsupported values.

### Flags

You can use the following flags with the **pdreorder** command:

- a [*TargetServerName*.:]*TargetJobId*  
Specifies that the reordered job should be assigned to print or transmit after the target job on the same actual destination.
- b [*TargetServerName*.:]*TargetJobId*  
Specifies that the reordered job should be assigned to print or transmit before the target job on the same actual destination.
- h Displays a command-specific help message containing information about command syntax and flags. If you use this flag with any other flag or attribute, Infoprint recognizes only the **-h** flag.
- m "*MessageText*"  
Specifies the message you want associated with the reordered job. You can use this message to indicate the reason why the job is being reordered or other comments. Using this flag is equivalent to specifying the command attribute **message**.  
  
You can list this message by specifying **requested-attributes=job-message-from-administrator** with the **pdlis** command.
- p [*TargetServerName*.:]*TargetDestinationName*  
Specifies that the job should be reassigned to the target actual destination.
- s *TargetServerName*  
Specifies that the job should be moved to the target server and that the target server should assign it to an actual destination.

## pdreorder

- u** *TargetServerName*  
Specifies that the job should be moved to the target server as an unassigned job.
- x** "*attribute=value ...*"  
Consists of a single attribute string, containing one or more attribute-value pairs.
- X** *AttributesFileName*  
Specifies the name of a file containing attribute and value pairs that you want Infoprint to insert at the current point in the command line. Using this flag is equivalent to specifying the command attribute **attributes**.

## Command Attributes

You can specify these attributes in a **-x** "*attribute=value ...*" string or in an attributes file designated with the **-X** *AttributesFileName* flag.

### **attributes=***AttributesFileName*

Specifies the designated attributes file that Infoprint reads and inserts at the current point in the command. This file contains attribute and value pairs that Infoprint uses to expand the command.

### **message=**"*MessageText*"

Specifies the message you want associated with the reordered job. You can use this message to indicate the reason why the job is being reordered or other comments.

You can list this message by specifying **requested-attributes=job-message-from-administrator** with the **pdlis** command.

## Arguments

Use the argument value to identify the specific object for which you want the status. If you specify multiple objects, separate the object names with spaces.

You can use the following arguments with the **pdreorder** command:

*[ServerName:]GlobalJobID*

The global ID of the job to be reassigned.

## Examples

- To reorder job 1099600001 so that it prints after job 1099500047, enter the command:  

```
pdreorder -a 1099500047 1099600001
```
- To reassign job 2000004341 from server molly to server david and have david assign it to an actual destination, enter the command:  

```
pdreorder -s david molly:2000004341
```

## pdresubmit Command: Resubmits Jobs

### Syntax

```
pdresubmit [-c ObjectClass] [-g] [-r "RequestedAttribute ..."]
           [-s StyleName]
           [-x "attribute=value ..."] [-X AttributesFileName]
           [ServerName:]TargetLogicalDestinationName
           {LocalJobID ... | GlobalJobID ... |
           [ServerName:]QueueName ... |
           [ServerName:]DestinationName ...}
```

```
pdresubmit -h
```

### Description

Use the **pdresubmit** command to resubmit an existing job to a specific logical destination. The logical destination can be in the same server as the logical destination to which the job was first submitted or a different server. You can only resubmit jobs that have the current job state of **held**, **pending**, **retained**, or **unknown**.

If the logical destination specified is in a different server, the old server resubmits the job with all of its current attributes to the new server. Infoprint includes any default attributes associated with the old server so that the new job remains as similar as possible to the old job. If the new server accepts the job, it assigns a new global job identifier and the old global job identifier becomes invalid.

Logical destinations and queues can also be arguments for this command. If a logical destination is the argument, Infoprint resubmits all of the jobs submitted to the old logical destination to the specified new logical destination. If a queue is the argument, Infoprint resubmits all of the jobs in the old queue to the specified logical destination. Infoprint validates all of the resubmitted jobs again. If the newly specified logical destination does not support them, they remain in the queue that they were in originally.

If the new logical destination cannot accept the job for some reason, Infoprint issues an error message and the job stays where it was.

#### Notes:

1. Infoprint does not change the global job identifier for the job if you resubmit the job to a logical destination on the same server.
2. Infoprint changes the global job identifier for the job if you resubmit the job to a logical destination on a different server. However, if you are the job-owner, you can still use the same local job identifier.

### Flags

You can use the following flags with the **pdresubmit** command:

**-c** {job | **queue** | **destination**}

Specifies the object class that you want for this command. Within the valid classes, **destination** only applies to logical destinations.

Using this flag is equivalent to specifying the command attribute **class**.

**-g** Turns off headings.

## pdresubmit

Using this flag is equivalent to specifying the command attribute **headings=false**.

**-h** Displays a command-specific help message containing information about command syntax and flags. If you use this flag with any other flag or attribute, Infoprint recognizes only the **-h** flag.

**-r {none | brief | verbose}**

Specifies the group of attributes you want Infoprint to display for the specified job, queue, or destination.

**none** Displays no attributes.

**brief** Displays a small subset of important attributes for each object.

**verbose**

Displays a larger subset of important attributes for each object.

Using this flag is equivalent to specifying the command attribute **requested-attributes**.

**-s {column | doccol | line}**

When combined with the **-r** flag or the **requested-attributes** command attribute, this flag specifies the format in which you want the attributes displayed.

**column**

Attribute values are displayed in tabular format, so that values of the same attribute for multiple objects line up in columns.

**doccol**

For jobs only, job attribute values and the document attribute values for the first document in the job are displayed in column format on the same line.

**line** Each attribute is displayed on a separate line.

Using this flag is equivalent to specifying the command attribute **style**.

**-x "attribute=value ..."**

Consists of a single attribute string, containing one or more attribute-value pairs.

**-X AttributesFileName**

Specifies the name of a file containing attribute and value pairs that you want Infoprint to insert at the current point in the command.

Using this flag is equivalent to specifying the command attribute **attributes**.

## Command Attributes

You may specify these attributes in a **-x "attribute=value ..."** or in an attributes file designated with the **-X AttributesFileName** flag.

**attributes=AttributesFileName**

Specifies the designated attributes file that Infoprint reads and inserts at the current point in the command. This file contains attribute and value pairs that Infoprint uses to expand the command.

**class={job | queue | destination}**

Specifies the object class you want for this command. Within the valid classes, **destination** only applies to logical destinations.

**headings={true | false}**

Specifies whether you want Infoprint to display headings for the requested attributes.

**requested-attributes={none | brief | verbose}**

Specifies the group of attributes you want Infoprint to display for the specified job, queue, or destination.

**none** Displays no attributes.

**brief** Displays a small subset of important attributes for each object.

**verbose**

Displays a larger subset of important attributes for each object.

**style={column | doccol | line}**

Specifies the format in which you want Infoprint to display the attributes.

**column**

Attribute values are displayed in tabular format, so that values of the same attribute for multiple objects line up in columns.

**doccol**

For jobs only, job attribute values and the document attribute values for the first document in the job are displayed in column format on the same line.

**line** Each attribute is displayed on a separate line.

## Arguments

Use the argument value to identify the specific object you want to resubmit. If you specify multiple objects, all must belong to the same class and you must separate the object names with spaces.

You must use the following argument:

*[ServerName:]TargetLogicalDestinationName*

Specifies the name of the new logical destination.

You must use one of the following arguments with the **pdresubmit** command:

*LocalJobID or GlobalJobID*

Specifies the job you want resubmitted as determined by a local or global job identifier. If you do not use DCE, by default, end users do not have permission to use the **pdresubmit** command. Therefore, in most cases someone other than the job submitter will resubmit a job and must identify it by the global job ID. Job submitters who do have permission to use **pdresubmit**, either because they belong to the **printq** group or because the file permissions have been changed, can identify their own jobs by the local job ID.

If you use DCE, you must have **write** permission for the server to resubmit a job belonging to another user.

*[ServerName:]DestinationName*

Causes Infoprint to resubmit to the target logical destination all jobs currently submitted to the specified logical destination.

*[ServerName:]QueueName*

Causes Infoprint to resubmit to the target logical destination all jobs that are currently in the specified queue.

**pdresubmit**

## **Examples**

### **Resubmit Jobs**

To resubmit jobs 3828:1098223002 and 3828PP:1099223003 to logical destination local-lp, enter the command:

```
pdresubmit local-lp 3828PP:1098223002 3828PP:1099223003
```

### **Resubmit All Jobs from One Logical Destination to Another**

To resubmit all jobs submitted to logical destination dept1-lp to logical destination local-lp, enter the command:

```
pdresubmit local-lp -c destination dept1-lp
```

## **Suggested Reading**

For information about:

- Attributes file, see “Attributes File” on page 10

---

## pdresume Command: Enables Paused Objects to Resume Operation

### Syntax

```
pdresume [-c ObjectClass] [-m "MessageText"]
          [-x "attribute=value ..."] [-X AttributesFileName]
          {LocalJobID ... | GlobalJobID ... |
           ServerName ... | [ServerName:]DestinationName ... |
           [ServerName:]QueueName ...}
```

```
pdresume -h
```

### Description

Use the **pdresume** administrative command to cause Infoprint to restart paused jobs, actual destinations, queues, or servers.

**Note:** Use the **pdresume** and **pdpause** commands to allow or prevent output from the object, whereas you use the **pdenable** and **pddisable** commands to allow or prevent input to the object.

### Flags

You can use the following flags with the **pdresume** command:

**-c** {destination | queue | job | server}

Specifies the object class you want for this command. Within the valid classes, **destination** is an actual destination.

**Note:** You cannot resume PSF upload-TCP/IP-attached physical printers or PSF upload-SNA-attached physical printers.

Using this flag is equivalent to specifying the command attribute **class**.

**-h** Displays a command-specific help message containing information about command syntax and flags. If you use this flag with any other flag or attribute, Infoprint recognizes only the **-h** flag.

**-m** "*MessageText*"

Specifies the message you want associated with the specified destination, queue, job, or server. You can use this message to indicate the reason for resumption or to provide any other comments.

When resuming a server, Infoprint propagates the message to the **message** attribute of the actual destinations and queues residing in the server. Infoprint does not change the server **message** attribute.

If the command operates on a job, you can list this message by specifying **requested-attributes=job-message-from-administrator** with the **pdls** command. If the command operates on a destination, queue, or server you can list this message by specifying **requested-attributes=message** with the **pdls** command.

If you do not specify the **-m** flag, the message already stored with the object remains unchanged.

Using this flag is equivalent to specifying the command attribute **message**.

**-x** "*attribute=value ...*"

A single attribute string, consisting of one or more attribute-value pairs.

## pdresume

### **-X AttributesFileName**

Specifies the name of a file containing attribute and value pairs that you want Infoprint to insert at the current point in the command.

Using this flag is equivalent to specifying the command attribute **attributes**.

## Command Attributes

You can specify these attributes in a **-x "attribute=value ..."** string or in an attributes file designated with the **-X AttributesFileName** flag.

### **attributes=AttributesFileName**

Specifies the designated attributes file that Infoprint reads and inserts at the current point in the command. This file contains attribute and value pairs that Infoprint uses to expand the command.

### **class={destination | queue | job | server}**

Specifies the object class you want for this command. Within the valid classes, **destination** is an actual destination.

**Note:** You cannot resume PSF upload-TCP/IP-attached physical printers or PSF upload-SNA-attached physical printers.

### **message="MessageText"**

Specifies the message you want to associate with the specified destination, queue, job, or server. You can use this message to indicate the reason for resumption or to provide any other comments.

When resuming a server, Infoprint propagates the message to the **message** attribute of the actual destinations and queues residing in the server. Infoprint does not change the server **message** attribute.

If the command operates on a job, you can list this message by specifying **requested-attributes=job-message-from-administrator** with the **pdls** command. If the command operates on a destination, queue, or server, you can list this message by specifying **requested-attributes=message** with the **pdls** command.

If you do not specify the **message** attribute, the message already stored with the object remains unchanged.

## Arguments

Use the argument value to identify the specific destination, queue, job, or server you want to start processing again (resume operating). If you specify multiple objects, all of the objects must belong to the same class and you must separate the object names with spaces.

You can use the following arguments with the **pdresume** command:

### **LocalJobID... or GlobalJobID...**

Specifies the job you want to resume as determined by a local job identifier or global job identifier. If you use DCE, by default, only an administrator has the authority to resume jobs. If you do not use DCE, by default, administrators and operators have the authority to resume jobs, but end users do not. Therefore, in most cases someone other than the job submitter will resume a job and must identify it by the global job ID. Job submitters who do have authority to resume jobs can identify their own jobs by the local job ID.



A resumed job does not automatically return to its previous state. For example, if the **job-hold** or **print-after** attributes of a paused job were modified, returning to its previous state would cause Infoprint to hold the job even after it was resumed.

Resuming a job that was not previously assigned to an actual destination allows Infoprint to schedule it.

Resuming a job that was processing when it was paused causes Infoprint to restore it to the **pending** state and attempt to schedule it on the original actual destination. If the original destination is not available, Infoprint schedules the job on another actual destination that can support the job checkpoint format and begins processing the job where it stopped. If Infoprint cannot find another actual destination that supports the checkpoint format, Infoprint places the job in the **held** state. You can resubmit the job, which means that Infoprint will start the job from the beginning.

Resuming a job that had any attributes modified while it was paused causes it to restart from the beginning.

*[ServerName:]DestinationName*

Specifies the destination you want to resume operation.

Resuming an actual destination allows it to start processing jobs that Infoprint has assigned to it.

*[ServerName:]Queue*

Specifies the queue you want to resume operating.

Resuming a queue resumes the distribution of jobs to actual destinations associated with that queue.

*ServerName*

Specifies the server on which you want the command to operate. A server does not have a **paused** state. Issuing the command to a server resumes all of the paused queues and actual destinations that reside in that server. The queues can then continue to distribute jobs to actual destinations; and the actual destinations can start processing jobs.

## Examples

### Resume an Actual Destination

To resume actual destination Csrv-pp and issue a message, enter the command:  
 pdresume -m "Toner refilled" Csrv-pp

### Resume a Queue

To resume the queue Div1-q, enter the command:  
 pdresume -c queue Div1-q

### Resume All Queues and Actual Destinations in a Server

To resume all of the queues and actual destination in the server Mrk-server3, enter the command:  
 pdresume -c server Mrk-server3

## Suggested Reading

For information about:

- Attributes file, see “Attributes File” on page 10

## pdrm Command: Removes Jobs

### Syntax

```
pdrm [-m "MessageText"] [-r JobRetentionPeriod]
      [-x "attribute=value ..."] [-X AttributesFileName]
      {LocalJobID ... | GlobalJobID ...}
```

```
pdrm -h
```

### Description

Use the **pdrm** command to remove (delete) previously submitted jobs.

#### Notes:

1. If the job you specify is currently printing or transmitting, Infoprint can only remove it at a pausable point in the job. The pausable point at which the Infoprint can remove the job depends on the type of output device. A pausable point may be immediate or it may be the next page, sheet, document, or job boundary. If there is no such point before the end of job, Infoprint does not remove the job.
2. When you request Infoprint to remove a job with a non-zero value for the **job-retention-period** or **job-retain-until** attribute, Infoprint retains the job until the **job-retain-until** deadline or until the **job-retention-period** runs out, then deletes the job.
3. You can remove your own jobs by specifying either the local ID or the global ID for the job. You can remove jobs belonging to another person by specifying the global ID for the job.

**Note:** If you use DCE, you must have **write** permission for the server to remove jobs belonging to another person.

Infoprint Manager for AIX issues a confirmation message prior to deleting jobs, unless the environment variable **PD\_CONFIRM\_DELETE** for the person requesting the job removal has a value of **no**.

Infoprint Manager for Windows NT and Windows 2000 issues a confirmation message prior to cleaning the object, unless the **Confirm Object Delete** checkbox is unchecked (which is accessed through the Infoprint Manager Management Console with **Edit→Service Configuration**).

### Flags

You can use the following flags with the **pdrm** command:

- h** Displays a command-specific help message containing information about command syntax and flags. If you use this flag with any other flag or attribute, Infoprint recognizes only the **-h** flag.
- m "MessageText"** Specifies the message you that want to associate with the specified job. The specified text becomes the value of the **job-message-from-administrator** attribute. You can use it to provide the reason you are removing the job or to provide any other comments. If you do not specify the **-m** flag, the message already stored with the job remains unchanged.

You can list this message by specifying **requested-attributes=job-message-from-administrator** with the **pdlis** command.

Using this flag is equivalent to specifying the command attribute **message**.

**-r** *JobRetentionPeriod*

Specifies the period of time you want the server to retain the job before Infoprint deletes the job. If specified, this retention period takes precedence over the previous job-retention period set for the job.

Using this flag is equivalent to specifying the job object attribute **job-retention-period**.

**-x** *"attribute=value ..."*

Consists of a single attribute string, containing one or more attribute-value pairs.

**-X** *AttributesFileName*

Specifies the name of a file containing attribute and value pairs that you want Infoprint to insert at the current point in the command.

Using this flag is equivalent to specifying the command attribute **attributes**.

## Command Attributes

You can define these attributes in a **-x** *"attribute=value ..."* string or in an attributes file designated in the **-X** *AttributesFileName* flag.

**attributes=AttributesFileName**

Specifies the designated attributes file that Infoprint reads and inserts at the current point in the command. This file contains attribute and value pairs that Infoprint uses to expand the command.

**message="MessageText"**

Specifies the message that you want Infoprint to store in the **job-message-from-administrator** attribute. You can use it to provide the reason you are removing the job or to provide any other comments. If you do not specify the **message** attribute, the message already stored with the job remains unchanged.

You can list this message by specifying **requested-attributes=job-message-from-administrator** with the **pdlis** command.

## Arguments

Use the argument value to identify the specific job you want to remove. You must use one of the following arguments for the **pdrm** command:

*LocalJobID* or *GlobalJobID*

Specifies the local ID or global ID of the job that you want Infoprint to remove.

This argument must appear last in the command. If you want to remove more than one job, separate the job identifiers with spaces.

## Examples

### Remove Your Own Job

To remove your job with the local ID of 15, enter the command:

```
pdrm 15
```

## pdrm

### **Remove Another User's Job**

To remove the job with global ID Server1:1011223002 on server Server1, enter the command:

```
pdrm Server1:1011223002
```

### **Remove Job Regardless of Retention Time**

To remove your job with the local ID of 10 as soon as possible, regardless of any previously specified **job-retention-period** attribute value, enter the command:

```
pdrm -r 0 10
```

## pdset Command: Defines Attribute Values

### Syntax

```
pdset [-c ObjectClass] [-g] [-m "MessageText"]
      [-r "attribute ..."] [-s StyleName]
      [-x "attribute=value ..."] [-X AttributesFileName]
      {ServerName ... | ServerName:AuxiliarySheetName ... |
       ServerName:DefaultDocumentName ... |
       ServerName:DefaultJobName ... |
       [ServerName:]DestinationName ... | ServerName:LogName ... |
       ServerName:MediumName ... |[ServerName:]QueueName ... |
       ServerName:ResourceContextName ... |
       ServerName:TransformName ... |
       LocalJobID ... |
       GlobalJobID ...}
```

```
pdset -h
```

### Description

Use the **pdset** administrative command to define or modify the values of object attributes. You must disable a destination before you can modify its attributes.

Table 6 lists the four modification operators.

Table 6. *pdset* Operators

Operator	Syntax	Description
Replace	<i>attribute=value</i>	Replaces the entire value of the attribute <i>attribute</i> with <i>value</i> or adds the attribute to the object, if not already present.
Add values	<i>attribute+=value</i>	Adds the value <i>value</i> to the attribute <i>attribute</i> . You cannot add values to single-valued attributes. Infoprint honors an add request that duplicates values on a multi-valued attribute without warning.
Remove values	<i>attribute-=value</i>	Removes the value <i>value</i> from the attribute <i>attribute</i> . Infoprint ignores a remove request for a nonexistent value, without warning or error. A remove request for the last or only value of an attribute is equivalent to a reset-to-default request.
Reset to default	<i>attribute==</i>	Sets the attribute value <i>attribute</i> to the default. If you supply values with a <b>reset-to-default</b> request, Infoprint ignores them.

If you do not specify a value with a replace, add, or remove request, Infoprint issues an error and rejects the request to change the object.

You can only change values for resettable attributes using the **pdset** command. Using this command for non-settable or initially settable attributes results in an error.

See “Chapter 7. Infoprint Object Attributes” on page 325 for lists of all resettable attributes by object and a description of each attribute.

## pdset

Changes made to objects are permanent and remain changed even if you shut down and then restart the system (except for logs).

## Flags

You can use the following flags with the **pdset** command:

**-c {destination | **job** | **server** | **queue** | **auxiliary-sheet** | **document** | **initial-value-job** | **initial-value-document** | **medium** | **resource-context** | **transform** | **log**}**

Specifies the object class that you want for this command. Within the valid classes, **destination** is for a logical destination or actual destination.

Using this flag is equivalent to specifying the command attribute **class**.

**-g** Turns off headings.

Using this flag is equivalent to specifying the command attribute **headings=false**.

**-h** Displays a command-specific help message containing information about command syntax and flags. If you use this flag with any other flag or attribute, Infoprint recognizes only the **-h** flag.

**-m** "*MessageText*"

Specifies the message that you want to associate with the object that you want to modify. You can use this message to indicate the reason why you are modifying or setting object attributes or to provide any other comments.

If the command operates on a job, you can list this message by specifying **requested-attributes=job-message-from-administrator** with the **pdls** command. Otherwise, you can list this message by specifying **requested-attributes=message** with the **pdls** command.

If you do not specify the **-m** flag, the message already stored with the object remains unchanged.

Using this flag is equivalent to specifying the command attribute **message**.

**-r {none | **brief** | **verbose**}**

Specifies the attribute values you want to display for the specified object.

**none** Displays no attributes.

**brief** Displays a small subset of important attributes for each object.

**verbose**

Displays a larger subset of important attributes for each object.

Using this flag is equivalent to specifying the command attribute **requested-attributes**.

**-s {column | **doccol** | **line**}**

Specifies the format in which you want Infoprint to display the attributes.

**column**

Attribute values are displayed in tabular format, so that values of the same attribute for multiple objects line up in columns.

**doccol**

For jobs only, job attribute values and the document attribute values for the first document in the job are displayed in column format on the same line.

**line** Each attribute is displayed on a separate line.

Using this flag is equivalent to specifying the command attribute **style**.

**-x** *"attribute=value ..."*

A single attribute string, consisting of one or more attribute-value pairs. Prefix the attribute value with the replace operator, = , to replace a value, the add-value operator, += , to add a value or the remove-value operator, -= , to remove a value. Use the reset-to-default operator, == , with no attribute value to set the value to its default.

**-X** *AttributesFileName*

Specifies the name of a file containing attribute and value pairs that you want Infoprint to insert at the current point in the command.

Using this flag is equivalent to specifying the command attribute **attributes**.

## Command Attributes

You can specify these attributes in a **-x** *"attribute=value ..."* string or in an attributes file designated with the **-X** *AttributesFileName* flag.

**attributes=AttributesFileName**

Specifies the designated attributes file that Infoprint reads and inserts at the current point in the command. This file contains attribute and value pairs that Infoprint uses to expand the command.

**class={destination | job | server | queue | auxiliary-sheet | document | initial-value-job | initial-value-document | medium | resource-context | transform | log}**

Specifies the object class you want for this command. Within the valid classes, **destination** is for a logical destination or actual destination.

**headings={true | false}**

Specifies if you want Infoprint to display headings on the output.

**message="MessageText"**

Specifies the message that you want to associate with the object you are modifying. You can use this message to indicate the reason that you are modifying the object attributes or to provide any other comments.

If the command operates on a job, you can list this message by specifying **requested-attributes=job-message-from-administrator** with the **pdls** command. Otherwise, you can list this message by specifying **requested-attributes=message** with the **pdls** command.

If you do not specify the **message** attribute, the message already stored with the object remains unchanged.

**requested-attributes={none | verbose | brief}**

Specifies the attribute values you want to display for the specified object.

**none** Displays no attributes.

**brief** Displays a small subset of important attributes for each object.

**verbose**

Displays a larger subset of important attributes for each object.

**style={column | doccol | line}**

Specifies the presentation format in which you want the output displayed.

**column**

Attribute values are displayed in tabular format, so that values of the same attribute for multiple objects line up in columns.

## pdset

### doccol

For jobs only, job attribute values and the document attribute values for the first document in the job are displayed in column format on the same line.

**line** Each attribute is displayed on a separate line.

## Arguments

Use the argument value to identify the specific object for which you want to set or modify attributes. If you specify multiple objects, separate the object names with spaces.

You can use the following arguments with the **pdset** command:

*ServerName:AuxiliarySheetName*  
*ServerName:DefaultJobName*  
*ServerName:DefaultDocumentName*  
*ServerName:MediumName*  
*ServerName:LogName*  
*[ServerName:]DestinationName*  
*[ServerName:]QueueName*  
*ServerName:ResourceContextName*  
*ServerName:TransformName*  
*ServerName*  
*LocalJobID*  
*GlobalJobID*

By default, end users do not have permission to modify jobs. Therefore, in most cases someone other than the job submitter will modify a job and must identify the job by the global job ID. Job submitters who do have permission to modify jobs can identify their own jobs by the local job ID.

## Examples

### Specify a Descriptor for a Server

To set a description for the server `Server1` and identify the processor name containing it and the TCP/IP address for the processor, enter the command:

```
pdset -c server -x "descriptor='Server Server1 is installed on  
cowboy. The TCP/IP address for cowboy is 9.99.9.143.'" Server1
```

### Change the Operator to Receive Messages

To identify a new person to receive start and stop messages for actual destination `Serv4-pp`, enter the command:

```
pdset -c destination -x "notify-operator=electronic-mail:ro@cowboy"  
Serv4-pp
```

### Set the Job Size Range

To set the size of jobs that users can submit to actual destination `small-pp`, enter the command:

```
pdset -x "job-size-range-supported=0:10000  
job-size-range-ready=0:10000" small-pp
```

### Specify Media Supported by an Actual Destination

To specify the media supported by a given actual destination and the media currently loaded in the printer device, enter the command:



```
pdset -x "media-supported=letter na-letter-colored  
legal na-legal-colored A4 A4-colored  
psf-tray-characteristics=top:letter  
bottom:A4" Serv4-pp
```

### **Set a Message**

To set the message for server Serv2, enter the command:

```
pdset -c server -m "printing system now ok" Serv2
```

## **Suggested Reading in Hardcopy**

For information about:

- Attributes for Infoprint objects, see “Chapter 7. Infoprint Object Attributes” on page 325
- Attributes file, see “Attributes File” on page 10
- Headings and style, see “Command Output: Headings and Style” on page 9
- Non-settable, initially settable, and resettable attributes, see “Initially Settable, Resettable Attributes, and Non-Settable” on page 4

## **Suggested Reading Online for Infoprint Manager for AIX**

To view information about all supported attributes for Infoprint, enter the command:

```
man pd_att
```

This displays a list of files by object from which you can select the attribute listing you want.

---

## pdshutdown Command: Stops Servers or Actual Destinations

### Syntax

```
pdshutdown [-c server] [-m "MessageText"] [-w time]  
           [-x "attribute=value ..."] [-X AttributesFileName]  
           ServerName
```

```
pdshutdown [-c destination] [-m "MessageText"]  
           [-x "attribute=value ..."] [-X AttributesFileName]  
           [-s [-n]] [ServerName:]DestinationName
```

```
pdshutdown -h
```

### Description

Use the **pdshutdown** administrative command to terminate a server process or shut down a PSF physical printer, fax destination, or email destination.

You can shut down a server either immediately or after it finishes processing some or all of its current jobs.

Infoprint prevents the server from accepting new jobs while the server is shutting down and after it has shut down. Destinations in the server that were enabled at shutdown time are enabled when the server restarts. Destinations in the server that were disabled at shutdown time are disabled when the server restarts.

**Note:** To restart a server after shutdown, use the **startsrv** or **start\_server** utility. See “startsrv Utility: Starts a Server in Infoprint Manager for AIX” on page 178 or “start\_server Utility: Starts a Server for a Basic Infoprint Installation in Infoprint Manager for AIX” on page 176.

Shutting down an actual destination:

- Terminates all communication with the output device
- Pauses the job printing or transmitting on the actual destination
- Terminates all jobs processing on the actual destination and puts these jobs in the **pending** state
- Releases jobs assigned to the actual destination so that you can reschedule them on another actual destination
- Disables the actual destination

You can shut down a PSF physical printer either immediately or after synchronizing the current job’s checkpoint data with the pages that have actually printed.

**Notes:**

1. To restart an actual destination after shutdown, use the **pdenable** command. See “pdenable Command: Enables Destinations to Accept Jobs and Logs to Log” on page 37.
2. Synchronize the checkpoint data for a controlled shutdown, for example, when you want to perform maintenance that will take some time.
3. If Infoprint cannot communicate with the output device, shut down the actual destination so that you can reschedule the jobs assigned to it. Do not synchronize the checkpoint data. If you try, the command will hang, waiting for the output device to respond.

If you shut down without synchronization, the shutdown will take effect and allow any previously hung commands to complete.

4. A job paused by a destination shutdown without synchronization may reprint some pages when printing is resumed.
5. If you want to interrupt the actual destination for only a short time, consider pausing it rather than shutting it down. When you pause an actual destination, scheduled jobs remain scheduled. When you shut down an actual destination, scheduled jobs are requeued.

## Flags

You can use the following flags with the **pdshutdown** command:

### **-c** {server | destination}

Specifies the object class you want to shut down. Within the valid classes, **destination** is a PSF physical printer, fax destination, or email destination.

Using this flag is equivalent to specifying the command attribute **class**.

- h** Displays a command-specific help message containing information about command syntax and flags. If you use this flag with any other flag or attribute, Infoprint recognizes only the **-h** flag.

### **-m** "*MessageText*"

Specifies the message that you want to associate with the server or actual destination being shut down. You can use this message to indicate the reason for the shutdown or to provide any other comments.

You can list this message by specifying **requested-attributes=message** with the **pdls** command. If you do not specify the **-m** flag, the message already stored with the object remains unchanged.

Using this flag is equivalent to specifying the command attribute **message**.

- n** Causes the PSF physical printer to perform an NPRO (move the last printed page to the stacker). Using this flag is equivalent to specifying the command attribute **non-process-runout=true**.

This flag is valid only with object class **destination**, and only if you also specify **-s**. It is not valid for fax destinations or email destinations.

- s** Synchronizes the checkpoint data for the current job with the pages that have actually printed. This permits the job to resume at the point of synchronization. Using this flag is equivalent to specifying the command attribute **synchronize=true**. Do not use this flag if Infoprint cannot communicate with the printer device.

This flag is valid only with object class **destination**. It is not valid for fax destinations or email destinations.

### **-w** {after-current | now | after-all}

Specifies when you want a server to shut down. When the value is:

**now** Infoprint cancels and requeues any currently printing jobs, then shuts down the server. You must resubmit the jobs using the **pdresubmit** command when the server restarts.

#### after-current

The server continues to accept requests other than print requests until the currently-printing jobs finish printing, then the server shuts down.

## pdshutdown

### after-all

The server continues to accept all requests except print requests until all scheduled jobs finish printing, then the server shuts down.

Using this flag is equivalent to specifying the command attribute **when**.

This flag is valid only with object class **server**.

### -x "attribute=value ..."

A single attribute string, consisting of one or more attribute-value pairs.

### -X AttributesFileName

Specifies the name of a file containing attribute and value pairs that you want Infoprint to insert at the current point in the command.

Using this flag is equivalent to specifying the command attribute **attributes**.

## Command Attributes

You may specify these attributes in a **-x "attribute=value ..."** string or in an attributes file designated with the **-X AttributesFileName** flag.

### attributes=AttributesFileName

Specifies the designated attributes file that Infoprint reads and inserts at the current point in the command. This file contains attribute and value pairs that Infoprint uses to expand the command.

### class={server | destination}

Specifies the object class you want to shut down. Within the valid classes, **destination** is a PSF physical printer, fax destination, or email destination.

### message="MessageText"

Specifies the message you want associated with the server or actual destination being shut down. You can use this message to indicate the reason for the shutdown or to provide any other comments.

You can list this message by specifying **requested-attributes=message** with the **pdls** command. If you do not specify the **message** attribute, the message already stored with the object remains unchanged.

### non-process-runout={true | false}

Specifies whether the PSF physical printer should perform an NPRO (move the last printed page to the stacker).

This attribute is valid only with object class **destination**, and only if you also specify **synchronize=true**. It is not valid for fax destinations or email destinations.

### synchronize={true | false}

Specifies whether to synchronize the checkpoint data for the current job with the pages that have actually printed. A value of **true** permits the job to resume at the point of synchronization. Do not specify **synchronize=true** if Infoprint cannot communicate with the printer device.

This attribute is valid only with object class **destination**. It is not valid for fax destinations or email destinations.

### when={after-current | now | after-all}

Specifies when you want a server to shut down. When the value is:

**now** Infoprint cancels and requeues any currently printing jobs, then shuts down the server. You must resubmit the jobs using the **pdresubmit** command when the server restarts.

**after-current**

The server continues to accept requests other than print requests until the currently-printing jobs finish printing, then the server shuts down.

**after-all**

The server continues to accept all requests except print requests until all scheduled jobs finish printing, then the server shuts down.

This attribute is valid only with object class **server**.

## Argument

Use the argument value to identify the specific server or actual destination that you want to shut down.

You can use the following argument values with the **pdshutdown** command:

*ServerName*

Specifies the server that you want to shut down.

*[ServerName:]DestinationName*

Specifies the actual destination that you want to shut down.

## Examples

### Shut Down a Server

To shut down server `Server1`, to abort all jobs that are currently printing, and to set a message, `Down for maintenance`, enter the command:

```
pdshutdown -w now -m "Down for maintenance" Server1
```

### Shut Down an Actual Destination

To shut down actual destination `Serv9-fax`, enter the command:

```
pdshutdown -c destination Serv9-fax
```

### Shut Down a PSF Physical Printer and Update Job Checkpoint Data

To shut down PSF physical printer `Serv9-pp` after synchronizing the printer with the currently printing job's checkpoint data, enter the command:

```
pdshutdown -c printer -s Serv9-pp
```

**Note:** The PSF physical printer must be able to communicate with the printer device to perform the synchronize function.

### Shut Down a PSF Physical Printer, Update Job Checkpoint Data, and Perform NPRO

To shut down PSF physical printer `Serv9-pp` after synchronizing the currently printing job's checkpoint data and perform an NPRO, enter the command:

```
pdshutdown -c destination -s -n Serv9-pp
```

## Suggested Reading

For information about:

- Attributes file, see "Attributes File" on page 10.

---

## pdspace Command: Backspaces or Forward Spaces a Printer

### Syntax

```
pdspace [-c destination] {-b SideCount | -f SideCount} [-n]
        [-x "attribute=value ..."] [-X AttributesFileName]
        [ServerName:]DestinationName ...
```

```
pdspace -h
```

### Description

Use the **pdspace** command to backspace or forward space the currently printing job on the specified PSF physical printer a given number of sides. If the job is printing on one side of the medium, one side is equivalent to one sheet. If the job is printing on two sides of the medium (duplex), two sides are equivalent to one sheet.

#### Notes:

1. The functions of this command only apply to PSF physical printers. They do not apply to PSF upload-TCP/IP-attached physical printers or PSF upload-SNA-attached physical printers.
2. To guarantee accurate backspacing or forward spacing to a specific side, you must install the level of microcode supporting **pdspace** on the printer device.
3. You cannot backspace or forward space ASCII print jobs.

You can issue the **pdspace** command while the printer is stopped, paused, or running.

- If the printer has been stopped by pressing the **STOP** button on the printer device, the printer operator must press the **START** or **READY** button before the printer can restart printing. You cannot force a stopped printer to perform an NPRO by specifying the **-n** flag; but the operator can force an NPRO by pressing the **NPRO** button.
- If the printer has been paused with the **pdpause** command, you must issue the **pdresume** command before the printer can restart printing.
- If the printer is running, the **pdspace** command takes effect as soon as possible.

The printer backspaces or forward spaces the number of sides you specify, except that:

- The printer will not backspace or forward space to the back side of a duplexed sheet. If a backspace or forward calculation points to the back side of a duplexed sheet, the printer backspaces or forward spaces to the front side of that sheet.
- When backspacing, if you specify a side count of -1, the job restarts printing on page 1 with a new header sheet.
- When backspacing, if you specify more sides than have already printed, the job restarts printing on page 1 without a header sheet.
- When forward spacing, if you specify more sides than there are sides left to print, the job terminates.

**Note:** Infoprint backspaces or forward spaces from the last printed sheet: any count is one less than you would normally expect. For example, if you backspace ten sides starting at page 39, the job resumes on page 30 because page 39 is counted as one of the pages backspaced.

## Flags

You can use the following flags with the **pdspace** command:

- b *SideCount*  
Specifies the number of sides to backspace before continuing to print. Using this flag is equivalent to specifying the command attribute **back-space**.
- c destination  
Specifies the object class of **destination**, which represents a PSF physical printer. This is the only allowed class. Using this flag is equivalent to specifying the command attribute **class**.
- f *SideCount*  
Specifies the number of sides to forward space before continuing to print. Using this flag is equivalent to specifying the command attribute **forward-space**.
- h  
Displays a command-specific help message containing information about command syntax and flags. If you use this flag with any other flag or attribute, Infoprint recognizes only the **-h** flag.
- n  
Causes the printer to perform an NPRO (move the last printed page to the stacker) before restarting printing. An NPRO makes it easier to see exactly where the spacing took place. Using this flag is equivalent to specifying the command attribute **non-process-runout=true**.
- x "*attribute=value ...*"  
Consists of a single attribute string, containing one or more attribute-value pairs.
- X *AttributesFileName*  
Specifies the name of a file containing attribute and value pairs that you want Infoprint to insert at the current point in the command. Using this flag is equivalent to specifying the command attribute **attributes**.

## Command Attributes

You can define these attributes in a **-x** "*attribute=value ...*" string or in an attributes file designated in the **-X** *AttributesFileName* flag.

### **attributes=AttributesFileName**

Specifies the designated attributes file that Infoprint reads and inserts at the current point in the command. This file contains attribute and value pairs that Infoprint uses to expand the command.

### **back-space=SideCount**

Specifies the number of sides to backspace before continuing to print.

### **class=destination**

Specifies the object class of **destination**, which represents a PSF physical printer. This is the only allowed class.

### **forward-space=SideCount**

Specifies the number of sides to forward space before continuing to print.

### **non-process-runout={true | false}**

Specifies whether the printer should perform an NPRO (move the last printed sheet to the stacker) before restarting printing. An NPRO makes it easier to see exactly where the spacing took place.

## pdspace

### Arguments

Use the argument value to identify the specific physical printer on which the job backsplaces.

*[ServerName:]DestinationName*

### Examples

#### Backspacing 22 Sides

To backspace the currently printing job on physical printer jrSrv-pp by 22 sides, enter the command:

```
pdspace -b22 jrSrv-pp
```

#### Forward Spacing 22 Sides

To forward space the currently printing job on physical printer mySrv-pp by 22 sides, enter the command:

```
pdspace -f22 mySrv-pp
```

#### Forward Spacing a Paused Printer 10 Sides with NPRO

To pause physical printer carlo-pp, forward space the job that was printing by 10 sides, move the last printed sheet to the stacker, and resume printing, enter the commands:

```
pdpause carlo-pp  
pdspace -f10 -n carlo-pp  
pdresume carlo-pp
```

#### Backspacing to a Specific Side

To backspace exactly to page 62 in the job printing on physical printer mySrv-pp:

1. Use *one* of these methods to interrupt printing:
  - Press the **STOP** button to stop the printer device.
  - Enter this command to pause the physical printer:  

```
pdpause mySrv-pp
```
2. At the operator viewing point, check to see what page was printing when the job stopped.
3. Calculate the number of sides to backspace. For example, if the job stopped at page 97:  
$$97 - 62 + 1 = 36$$

You must add one because page 97 is counted as the first side to backspace.

4. Enter the command:  

```
pdspace -b36 mySrv-pp
```
5. Use *one* of these methods to resume printing:
  - If you pressed **STOP**, press **START** to restart the printer device.
  - If you paused the physical printer, enter this command to resume it:  

```
pdresume mySrv-pp
```



---

## Chapter 3. The -o Flag for AIX Print Commands

As well as the Infoprint **pdpr** and **lprafp** commands, you can use the AIX print commands, **enq**, **lp**, and **qprt**, to print jobs.

AIX uses the **-o** flag on the AIX print commands and on the Infoprint **lprafp** command to pass information to the backend program. This program handles the details of printing or transmitting your job.

### **-o flag not valid on pdpr command**

You cannot use the **-o** flag on the Infoprint **pdpr** command, nor can you use it to specify Infoprint object attributes. Use the **-o** keywords only on the AIX print commands **enq**, **lp**, and **qprt** and on the Infoprint **lprafp** command.

Similar or equivalent Infoprint object attributes are listed for each **-o** flag keyword. Use these attributes only on the **pdpr** command.

To pass flags or options to a transform command when you submit DBCS ASCII, EUC, GIF, JPEG, line-data, PCL, PDF, PostScript, or TIFF files with the **pdpr** command, use the Infoprint **other-transform-options** document attribute instead of the **-o** flag.

---

## Syntax

You can use any one of the following AIX commands to submit an Infoprint job:

```
enq [-P DestinationName] [-okeyword=value ...] FileName ...  
lp [-d DestinationName] [-okeyword=value ...] FileName ...  
qprt [-P DestinationName] [-okeyword=value ...] FileName ...
```

---

## Description

The AIX print commands (**enq**, **lp**, and **qprt**) enqueue requests to a shared system resource. For Infoprint, this resource is a printer device, fax device, or electronic mailing system.

---

## Limitations

If you specify a data type value that causes an Infoprint transform program to be run before the file is printed on a PSF physical printer, the transform program writes the MO:DCA-P output to a temporary file in the directory specified by the **PDBASE** environment variable or in one of its subdirectories. No single user can create a MO:DCA-P file larger than the amount of free space in the file system containing this directory. If many users are submitting jobs that invoke transform programs, the directory may fill up and prevent all users from successfully running the transform programs.

### Flag

The AIX print commands use the following flag to pass information to Infoprint:

**-okeyword=value**

Is the information to be passed to Infoprint. You can specify as many keyword-value pairs in the AIX print command as you like, provided that each of them starts with the **-o** flag.

**Note:** You can specify other flags associated with the AIX print commands or with the **lprafp** command, for example, the **-N** flag (number of copies) of the **enq** and **qprt** commands. Some of these flags are equivalent to the **-o** values you can specify with the AIX print commands.

For information about the other flags for the **enq**, **lp**, and **qprt** commands, refer to the appropriate man page or to *AIX for RS/6000 Commands Reference*.

For information about the other flags for the **lprafp** command, refer to "lprafp Command: Submits Remote Jobs in Infoprint Manager for AIX" on page 15.

### Specifying -o Attribute-Value Pairs

In Infoprint, options appear as strings after the **-o** flag in the format *keyword=value*. For example,

```
enq -P DestinationName -obin=2 -oduplex=no FileName
```

Consider the following when using **-o** with an AIX print command or with the **lprafp** command:

- The **-o** flag is not valid on the **pdpr** command. Use the similar or equivalent Infoprint attributes listed for each **-o** keyword.
- Do not specify Infoprint attributes with the **-o** flag.
- All **-o** keywords override the equivalent flags specified with the print commands (such as the **-N** flag of the **enq** and **qprt** commands).
- If you specify the same keyword with the **-o** flag multiple times, Infoprint uses only the value of the last occurrence.
- When using keywords with the **-o** flag, you can use blanks between the keyword and the **-o** flag (for example **-o bin=1**). You cannot, however, use blanks between the keyword and the value (for example, **-o bin = 1** is not). Values that have blanks must be enclosed with single quotes or double quotes (for example, **-odocname="Tim Memo"**).
- When using another flag with the **-o** flag, you cannot use blanks between the second flag and its value. For example, **-o-w6i** is valid; **-o-w 6i** is not.
- The keywords used with the **-o** flag *are not* case-sensitive. For example, **-o BIN=1** and **-o bin=1** are both valid.
- Values for some keywords (such as path names or form definition names), *are* case-sensitive; for example:

```
enq -P3900A -oformdef=F100S /usr/lpp/psf/README
```

and

```
enq -P3900A -oformdef=F100S /usr/lpp/psf/readme
```

specify two different files to submit, just as:

```
enq -P3900A -osfo=/usr/lpp/psf/VMfonts myfile
```

and

```
enq -P3900A -osfo=/usr/lpp/psf/vmfonts myfile
```

specify two different directories to search for fonts.

In addition, the first example below is valid and the second one is not because the **-F** keyword used with the **ps2afp** command must be uppercase.

```
enq -P3900A -odatatype=postscript -o-FFontMapFile
enq -P3900A -odatatype=postscript -o-fFontMapFile
```

- The following flags show the minimum version of the keyword, as well as the complete keyword. For example, you can abbreviate the **-obin** keyword to two letters: **-obi**.

## **-o Attribute-Value Pairs**

You can use the following keyword-value pairs with the AIX print commands **enq**, **lp**, or **qprt**, or with the **lprafp** command, to pass information to Infoprint.

**{-oac | -oaccount}=account**

Specifies the account information that Infoprint prints on start, end, and separator sheets. The account information can also be used for audit and accounting purposes.

This command keyword is equivalent to the Infoprint document attribute **account-text**.

You must specify a value of **full** for one of the Infoprint actual destination auxiliary sheet attributes (**accounting-exit**, **audit-exit**, **printer-start-sheet**, **printer-end-sheet**, or **printer-separator-sheet**) for Infoprint to use this information.

The value is:  
*account*

Any 1 to 20 characters of account information.

**-oaddress1=address1**

Specifies the first line of address information that Infoprint prints on start, end, and separator sheets. The address information can also be used for audit and accounting purposes.

This command keyword is equivalent to the Infoprint document attribute **address1-text**.

You must specify a value of **full** for one of the Infoprint actual destination auxiliary sheet attributes (**accounting-exit**, **audit-exit**, **printer-start-sheet**, **printer-end-sheet**, or **printer-separator-sheet**) for Infoprint to use this information.

The value is:  
*address1*

Any 1 to 90 characters of address information.

**-oaddress2=address2**

Specifies the second line of address information that Infoprint prints on start, end, and separator sheets. Other information is the same as for **-oaddress1**.

This command keyword is equivalent to the Infoprint document attribute **address2-text**.

## -o Flag

### **-oaddress3=address3**

Specifies the third line of address information that Infoprint prints on start, end, and separator sheets. Other information is the same as for **-oaddress1**.

This command keyword is equivalent to the Infoprint document attribute **address3-text**.

### **-oaddress4=address4**

Specifies the fourth line of address information that Infoprint prints on start, end, and separator sheets. Other information is the same as for **-oaddress1**.

This command keyword is equivalent to the Infoprint document attribute **address4-text**.

### **{-obi | -obin}={1 | 2 to 255 | 65 | 100}**

Determines the input bin used for the job. This keyword overrides the value specified in the form definition. If you do not specify the **-obin** keyword, Infoprint uses the bin value specified in the form definition you provide for printing the job. If you do not specify the **-obin** keyword and the default form definition is used to print your job, the input bin value in the printer profile or in that form definition is used.

This command keyword is similar to the Infoprint document attribute **default-input-tray**.

Values are:

**1** Selects the primary bin for the printer device. This is the default.

**2 to 255**

You can specify bin 2 to bin 255. Refer to your printer documentation for more information about the bins available on the printer device.

**65** Selects the envelope bin on certain IBM printer devices.

**100** Selects manual feed on certain IBM printer devices.

### **{-obu | -obuilding}=building**

Specifies the building information that Infoprint prints on start, end, and separator sheets. The building information can also be used for audit and accounting purposes.

This command attribute is equivalent to the Infoprint document attribute **building-text**.

You must specify a value of **full** for one of the Infoprint actual destination auxiliary sheet attributes (**accounting-exit**, **audit-exit**, **printer-start-sheet**, **printer-end-sheet**, or **printer-separator-sheet**) for Infoprint to use this information.

The value is:

*building*

Any 1 to 90 characters of building information.

### **{-ocd | -ocdp | -ocod | -ocodepage}={850 | 437 | 860 | 863 | 865}**

Specifies the ASCII input code page used for the job; that is, the "keyboard" code that Infoprint uses to translate the ASCII code points it finds in the job.

This command attribute is similar to the Infoprint document attribute **default-character-mapping**.

Values are:

**850** Defaults to the IBM code page 850.

*nnn* Other possible input code page values are 437 (a subset of the IBM code page 850), 860 (Portuguese), 863 (French Canadian), or 865 (Nordic); however, none of these IBM code pages are directly supported by AIX. If you are using a different ASCII code page as your keyboard code page, you can select 437, 860, 863, or 865, depending on which code page is the closest match to the one you are currently using.

**Notes:**

1. This parameter is used only for ASCII jobs. If you specify **-odatatype=dbcsascii**, Infoprint ignores the value you specify for the **-ocodepage** keyword and value.
2. The Infoprint ASCII data type does not support the non-U.S. code pages supported by AIX (for example, IBM 932 and the variations of ISO8859). Infoprint supports code pages 437, 860, 863, and 865 so that you can select the code page that most closely matches the one you are currently using, if you are located outside the United States and using the ASCII data type.
3. If you are printing single-byte ASCII code points that are part of code page 932 (Japan), 938 (Traditional Chinese), or an Extended UNIX Code (EUC) code set for Japan, China, or Korea, you must use the **db2afp** command to print the file, even though the entire file is single-byte ASCII.

**{-ocop | -ocopies}={1 to 255}**

Specifies the number of copies of the job. If you also specify one of the copy flags for the AIX print command (the **-N** flag of the **enq** and **qprt** commands, or the **-n** flag of the **lp** command), the value you specify with the **-ocopies** keyword overrides the value specified with the **-N** or **-n** flag.

This command keyword is equivalent to the Infoprint document attribute **copy-count**.

Values are:

- |            |                                                    |
|------------|----------------------------------------------------|
| <b>1</b>   | The minimum number of copies. This is the default. |
| <b>255</b> | The maximum number of copies.                      |

**{-odatac | -odatack}={block | blkchar | blkpos | unblock}**

Determines what type of errors in the job cause Infoprint to issue error messages. The value you assign to this keyword can significantly affect IPDS printer performance as described in the following list.

This command keyword is similar to the Infoprint document attribute **data-fidelity-problem-reported**.

Values are:

**block** Block print-positioning errors and invalid-character errors; that is, do not report these errors or issue error messages for these types of errors. This value produces the best printer performance.

Print-positioning errors occur when the printer device tries to print outside the valid printable area of the form. Invalid-character errors include attempts to use a code point that is not assigned to a character in an AFP font.

**block** is the default.

## -o Flag

### **blkchar**

Block invalid-character errors; that is, do not report these errors. However, Infoprint reports print-positioning errors and issues error messages for them.

### **blkpos**

Block print-positioning errors; that is, do not report these errors. However, Infoprint reports invalid-character errors and issues error messages for them.

### **unblock**

Report all print-positioning errors and invalid-character errors. If the job has many errors, selecting **unblock** could decrease your IPDS printer device's performance because of the constant communication between the printer device and Infoprint, and because of the repositioning that must occur to continue printing the next page after the page containing the error. You might use this value when diagnosing problems with Infoprint.

**{-odatat | -odatatype}={ascii | afpds | dbcsascii | ditroff | gif | jpeg | line | modcap | pcl | pdf | postscript | sap | tiff}**

Specifies the type of the input data stream. If you do not specify the **-odatatype** keyword, Infoprint reads the first few lines of the file to determine if the file is an AFP data stream. If Infoprint does not find AFP data stream commands in the file, it assumes a data type of ASCII.

If you are printing PostScript, ditroff, S/370 line data, PCL, double-byte character set (DBCS) ASCII, Extended UNIX Code (EUC) on a PSF physical printer, or if you are printing ASCII data that you want to format with a page definition on a PSF physical printer, specifying the particular data type alerts Infoprint to execute the appropriate transform command (**ps2afp**, **d2afp**, **line2afp**, **pcl2afp**, or **db2afp**) before printing the file. In this way, you can specify transform-specific options with the **-o** flag. See “-o Keywords and Values for Specific Data Types” on page 117 for more information.

This command keyword is equivalent to the Infoprint document attribute **document-format**.

Values are:

### **{as | ascii}**

The type of data is an ASCII data stream with embedded controls for an IBM 4201-2 Proprinter or 5202 printer. You can also specify **ascii** to print “flat” ASCII (no embedded formatting controls except for newline characters) without using a page definition.

**ascii** is the default.

### **{af | afpds}**

The type of data is an Advanced Function Presentation data stream.

**gif** The type of data is Graphical Interchange Format.

**jpeg** The type of data is Joint Photographic Experts Group.

### **{db | dbcsascii}**

The type of data is double-byte character set (DBCS) ASCII for Japanese or Traditional Chinese, or Extended UNIX Code (EUC) for Japanese, Traditional Chinese, or Korean. DBCS ASCII may contain controls for an IBM 5577 or 5587 printer. When you specify

## -o Flag

this value, Infoprint automatically runs the **db2afp** command to transform the DBCS ASCII or EUC into printable AFP data. Infoprint ignores any values specified with the **-ocodepage** flag and keyword.

If you are printing EUC data, you must also specify **-o-e** (the **db2afp -e** flag) along with **-odatatype=dbcsascii**.

### {d | ditroff}

The type of data is ditroff, which is a device-independent data stream (troff files that have been formatted for Infoprint using the **troff -Tafp** command). When you specify this value, Infoprint automatically runs **d2afp** to transform the ditroff into printable AFP data.

### {l | line}

The type of data is S/370 line data or is ASCII data that you want to format with a page definition. When you specify this value, Infoprint automatically runs **line2afp** to transform the ASCII or line data into printable AFP data.

**Note:** If the input file is ASCII, but you want to use fonts that have EBCDIC code points, you must also specify a **line2afp** input exit program to convert the ASCII file to EBCDIC. Infoprint supplies two input exit programs that perform this function:

- **/usr/lpp/psf/bin/apka2e**, which is appropriate for ASCII files that only contain line feed controls (not carriage returns and form feeds)
- **/usr/lpp/psf/bin/asciinpe**, which is appropriate for ASCII files that contain line feed, carriage returns, and form feeds.

You specify an exit program using the **-oinpexit** keyword-value pair on the AIX print command.

### {mo | modcap}

The type of data is a Mixed Object: Document Content Architecture for Presentation data stream.

### {pc | pcl}

The type of data is PCL. When you specify this value, Infoprint automatically runs **pcl2afp** to transform the PCL into printable AFP data.

### pdf

The type of data is PDF. When you specify this value, Infoprint automatically runs **pdf2afp** to transform the PDF into printable AFP data.

### {ps | postscript}

The type of data is PostScript. When you specify this value, Infoprint automatically runs **ps2afp** to transform the PostScript into printable AFP data.

### sap

The type of data is an OTF data stream.

You cannot submit ABAP List Format files with the **-odatatype=sap** flag and keyword-value pair. If you submit an ABAP List Format file, Infoprint will convert it to line data, try to print it, and fail. You must first use **sap2afp** to convert the ABAP List Format file to line data, then submit it with the **-odatatype=line** flag and keyword-value pair.

## -o Flag

**tiff** The type of data is Tag Image File Format.

**{-ode | -odepartment}=*department***

Specifies the department information that Infoprint prints on start, end, and separator sheets. The department information can also be used for audit and accounting purposes.

This command keyword is equivalent to the Infoprint document attribute **department-text**.

You must specify a value of **full** for one of the Infoprint actual destination auxiliary sheet attributes (**accounting-exit**, **audit-exit**, **printer-start-sheet**, **printer-end-sheet**, or **printer-separator-sheet**) for Infoprint to use this information.

The value is:

*department*

Any 1 to 90 characters of department information.

**{-odi | -odistribution}=*distribution***

Specifies the distribution information that Infoprint prints on start, end, and separator sheets.

If you do not specify the **-odistribution** keyword for local jobs, no distribution information prints. For remote jobs, the value defaults to the information provided by AIX (usually the user ID and the name of the host from which the job was submitted; for example, **bob@sys1**).

The value is:

*distribution*

Any 1 to 90 characters of distribution information. Whether all of these characters print depends on the user exit program.

**{-odo | -odocname | -ojobn | -ojobname}=*JobName***

Identifies the document name or job name associated with this job. If you do not specify the **-odocname** or **-ojobname** keyword for ASCII or AFP data stream jobs, Infoprint uses the file name of the first file in the job.

If you do not specify the **-odocname** keyword for other types of data, Infoprint creates a temporary file for the transform output and uses that temporary file name for the job name. If you want to retain the original name of the input file for these types of data, you can specify a job name with this keyword.

The **-odocname** command keyword is equivalent to the Infoprint document attribute **document-file-name**. The **-ojob** command keyword is equivalent to the Infoprint job attribute **job-name**.

The value is:

*JobName*

You can enter a job name of up to 255 characters in length. Note that the user-exit programs supplied with the start, end, and separator sheets assume a maximum of 50 characters for the job name. If you want to display more than 50 characters, change the user-exit programs to use the number of characters you need. Use single quotes (') or double quotes (") if the document name or job name contains spaces (blanks).

**{-odu | -oduplex}={no | yes | tumble}**

Specifies whether the job prints on one or both sides of the paper and how



successive pages are oriented. This keyword overrides the value specified in the form definition. If you do not specify the **-oduplex** keyword, Infoprint uses the duplex printing value specified in the form definition you provide for printing the job. If you do not specify the **-oduplex** keyword and the default form definition is used to print your job, the duplex printing value in the printer profile or in that form definition is used.

This command keyword is similar to the Infoprint document attributes **plex** and **sides**.

Values are:

**{n | no}**

The job prints on one side of the sheet. This is the default.

**{y | yes}**

The job prints on both sides of the sheet, top edge to top edge.

**{t | tumble}**

The job prints on both sides of the sheet. The top edge of one side is the bottom edge of the other side.

**{-of | -oforndef}=FormDefinitionName**

Specifies the name of the form definition Infoprint uses for the job. The form definition defines the placement of the page of data on the form, the input and output bins to use, duplex printing, and so on.

If you do not specify the **-oforndef** keyword, Infoprint looks in the input file for an inline form definition. If the input file doesn't contain a form definition, Infoprint uses the default form definition for that Infoprint actual destination.

This command keyword is equivalent to the Infoprint document attribute **form-definition**.

The value is:

*FormDefinitionName*

Any form definition located in one of the directories defined in the search path.

You can specify a form definition name between 1 and 8 characters in length.

**{-oh | -oheader}={yes | no}**

Specifies whether Infoprint prints a start sheet before the job.

This command keyword is similar to the Infoprint job attribute **auxiliary-sheet-selection**.

Values are:

**{y | yes}**

Print the start sheet specified by the actual destination attribute **printer-start-sheet** before the job. If there are multiple files in a single job, a start sheet is printed before the first file only. This is the default.

**{n | no}**

Do not print a start sheet.

**{-omsgc | -omsgcount}={9999 | 1 to 9998 | 0}**

Specifies the number of messages or groups of related messages that Infoprint prints with the job. A message group consists of one error or warning message, followed by one or more secondary messages.

## -o Flag

This command keyword is similar to the Infoprint document attribute **maximum-messages-printed**.

Values are:

**9999** All messages print. This is the default.

**1 to 9998**

A specified number of messages print.

**0** No messages print.

**Note:** When Infoprint reaches the message count value, Infoprint processing continues; however, Infoprint prints no additional messages.

**{-ona | -oname}=name**

Specifies the name information that Infoprint prints on start, end, and separator sheets. The name information can also be used for audit and accounting purposes.

This command keyword is equivalent to the Infoprint document attribute **name-text**.

You must specify a value of **full** for one of the Infoprint actual destination auxiliary sheet attributes (**accounting-exit**, **audit-exit**, **printer-start-sheet**, **printer-end-sheet**, or **printer-separator-sheet**) for Infoprint to use this information.

The value is:

*name* Any 1 to 90 characters of name information.

**{-ono | -onodeid}=NodeID**

Specifies the node ID information that Infoprint prints on start, end, and separator sheets. The node ID information can also be used for audit and accounting purposes.

This command keyword is equivalent to the Infoprint document attribute **node-id-text**.

You must specify a value of **full** for one of the Infoprint actual destination auxiliary sheet attributes (**accounting-exit**, **audit-exit**, **printer-start-sheet**, **printer-end-sheet**, or **printer-separator-sheet**) for Infoprint to use this information.

The value is:

*NodeID*

Any 1 to 20 characters of nodeid information.

**{-oou | -ooutbin}={ 1 | 2 to 65535}**

Determines the output bin used for the job. If you do not specify the **-ooutbin** keyword, the output bin value in the printer profile is used.

This command keyword is similar to the Infoprint document attribute **output-bin** and the Infoprint actual destination attribute **output-bin-numbers**.

Values are:

**1** Selects the primary output bin for the printer device. This is the default.

**2 to 65535**

You can specify bin 2 to bin 65535. Refer to your printer documentation for more information about the bins available on the printer device.

**{-oov | -ooverlay}=OverlayName**

Specifies the name of an overlay to be printed on every page of the job. An overlay contains predefined data, such as lines, shading, text, boxes, or logos that can be merged with variable data on a printed page. Overlays can also be specified in a form definition. Any overlay you name here is printed in addition to overlays named in the form definition.

This command keyword is equivalent to the Infoprint document attribute **overlay**.

The value is:

*OverlayName*

Any overlay located in one of the directories defined in the search path.

You can specify an overlay name between 1 and 8 characters in length.

**{-opa | -opassthru}=PassthruFlags**

Identifies any other information provided when the job is submitted.

You specify this information in the following format:

**-opassthru**={*PassthruFlag=value*, [*PassthruFlag=value*,]...}

The following flags are supported by the user-exit program supplied with Infoprint:

**class** Identifies the 1-character class keyword provided by TCP/IP for MVS for those jobs submitted to Infoprint from MVS hosts through the Network Print Facility (NPF), PSF Direct, or MVS Download.

**destination**

Identifies the 1-to 8-character destination keyword provided for those jobs submitted to Infoprint from MVS hosts through the Network Print Facility (NPF), PSF Direct, or MVS Download.

**forms** Identifies the 1-to 8-character forms keyword provided for those jobs submitted to Infoprint from MVS hosts through the Network Print Facility (NPF), PSF Direct, or MVS Download.

**segmentid**

Identifies the 1-to 10-character segmentation identifier provided by TCP/IP for MVS for those jobs submitted to Infoprint from MVS hosts through the Network Print Facility (NPF), PSF Direct, or MVS Download.

This command keyword is equivalent to the Infoprint document attributes **mvs-class**, **mvs-destination**, **mvs-forms**, and **mvs-segment-id**.

**{-opr | -oprogrammer}=programmer**

Specifies the programmer information that Infoprint prints on start, end, and separator sheets. The programmer information can also be used for audit and accounting purposes.

This command keyword is equivalent to the Infoprint document attribute **programmer-text**.

## -o Flag

You must specify a value of **full** for one of the Infoprint actual destination auxiliary sheet attributes (**accounting-exit**, **audit-exit**, **printer-start-sheet**, **printer-end-sheet**, or **printer-separator-sheet**) for Infoprint to use this information.

The value is:

*programmer*

Any 1 to 40 characters of programmer information.

**{-oresp | -orespath}=PathList**

Specifies the search order that Infoprint uses for all Advanced Function Printing (AFP) resources.

This command keyword is equivalent to the Infoprint document attribute **resource-context-user**.

If you do not specify this keyword, Infoprint uses these search orders:

- For fonts:
  1. The paths named in the **-osrchfontlib** keyword
  2. The paths named in the Infoprint default document attribute **resource-context-user**
  3. The paths named in the Infoprint default document attribute **resource-context-font**
  4. The paths named in the Infoprint default document attribute **resource-context**
  5. The paths named in the **PSFPATH** environment variable
  6. The paths named in the Infoprint actual destination attribute **resource-context-font**
  7. The directory **/usr/lpp/psf/reslib**
  8. The directory **/usr/lpp/afpfonts**
  9. The directory **/usr/lpp/psf/fontlib**
- For other resources:
  1. The paths named in the Infoprint default document attribute **resource-context-user**
  2. The paths named in the Infoprint default document attributes **resource-context-form-definition**, **resource-context-overlay**, **resource-context-page-definition**, or **resource-context-page-segment**,
  3. The paths named in the Infoprint default document attribute **resource-context**
  4. The paths named in the **PSFPATH** environment variable
  5. The paths named in the Infoprint actual destination attributes **resource-context-form-definition**, **resource-context-overlay**, **resource-context-page-definition**, or **resource-context-page-segment**,
  6. The directory **/usr/lpp/psf/reslib**

The value is:

*PathList*

Any valid search path on the system where the job prints. You must use a colon (:) to separate multiple paths.

**{-oro | -oroom}=room**

Specifies the room information that Infoprint prints on start, end, and separator sheets. The room information can also be used for audit and accounting purposes.

This command keyword is equivalent to the Infoprint document attribute **room-text**.

You must specify a value of **full** for one of the Infoprint actual destination auxiliary sheet attributes (**accounting-exit**, **audit-exit**, **printer-start-sheet**, **printer-end-sheet**, or **printer-separator-sheet**) for Infoprint to use this information.

The value is:

*room* Any 1 to 90 characters of room information.

**{-osep | -oseparator}={ yes | no}**

Specifies whether Infoprint prints separator sheets between copies of the job.

This command keyword is similar to the Infoprint job attribute **auxiliary-sheet-selection**.

Values are:

**{y | yes}**

Print the separator sheet specified by the actual destination attribute **printer-separator-sheet** between copies of the job. This is the default.

**{n | no}**

Do not print separator sheets.

**{-osfo | -osrchfo | -osrchfontlib}=PathList**

Specifies one or more paths Infoprint searches for the fonts required by the job.

This command keyword is equivalent to the Infoprint document attribute **resource-context-font**.

If you do not specify this keyword, Infoprint uses this search order:

1. The paths named in the **-orespath** keyword
2. The paths named in the Infoprint default document attribute **resource-context-user**
3. The paths named in the Infoprint default document attribute **resource-context-font**
4. The paths named in the Infoprint default document attribute **resource-context**
5. The paths named in the **PSFPATH** environment variable
6. The paths named in the Infoprint actual destination attribute **resource-context-font**
7. The directory **/usr/lpp/psf/reslib**
8. The directory **/usr/lpp/afpfonts**
9. The directory **/usr/lpp/psf/fontlib**

The value is:

## -o Flag

### *PathList*

Any valid search path on the system where the job prints. You must use a colon (:) to separate multiple paths.

### **{-oti | -otitle}=title**

Specifies the title information that Infoprint prints on start, end, and separator sheets. The title information can also be used for audit and accounting purposes.

This command keyword is equivalent to the Infoprint document attribute **title-text**.

You must specify a value of **full** for one of the Infoprint actual destination auxiliary sheet attributes (**accounting-exit**, **audit-exit**, **printer-start-sheet**, **printer-end-sheet**, or **printer-separator-sheet**) for Infoprint to use this information.

The value is:

*title* Any 1 to 90 characters of title information.

### **{-otr | -otrailer}={yes | no}**

Specifies whether an end sheet prints after the job.

This command keyword is similar to the Infoprint job attribute **auxiliary-sheet-selection**.

Values are:

#### **{y | yes}**

Print the end sheet specified by the actual destination attribute **printer-end-sheet** after the job. This is the default.

#### **{n | no}**

Do not print an end sheet.

### **{-ous | -ouserid}=UserID**

Specifies the user ID information that Infoprint prints on start, end, and separator sheets. The user ID information can also be used for audit and accounting purposes.

This command keyword is equivalent to the Infoprint document attribute **user-id-text**.

You must specify a value of **full** for one of the Infoprint actual destination auxiliary sheet attributes (**accounting-exit**, **audit-exit**, **printer-start-sheet**, **printer-end-sheet**, or **printer-separator-sheet**) for Infoprint to use this information.

The value is:

*UserID*

Any 1 to 20 characters of userid information.

### **{-oxo | -oxoffset}=nnnn.nnnu**

Specifies the X offset of the logical page origin from the physical page origin. This keyword overrides any X offset value in the form definition. If you do not specify the **-oxoffset** keyword, Infoprint uses the X offset value specified in the form definition you provide for printing the job.

This command keyword is equivalent to the Infoprint document attribute **x-image-shift**.

The value is:

*nnnn.nnnu*

A numeric value that establishes the X (across) coordinate of the logical page origin, as shown in the figure below. *nnnn.nnn* is a number that can optionally contain a decimal point, and *u* is the units in inches (*i*) or millimeters (*m*).

If you do not specify a unit (*i* or *m*), then Infoprint uses pels as the unit type. You cannot specify fractional values (that is, you cannot use a decimal point) for pels.

**Note:** If you specify a value that is outside of the printable area, you will get a print-positioning error. To determine the printable area of IBM printer devices, see *Advanced Function Presentation: Printer Information*.

**{-oyo | -oyoffset}=nnnn.nnnu**

Specifies the Y offset of the logical page origin from the physical page origin. This keyword overrides any Y offset value in the form definition. If you do not specify the **-oyoffset** keyword, Infoprint uses the Y offset value specified in the form definition you provide for printing the job.

This command keyword is equivalent to the Infoprint document attribute **y-image-shift**.

The value is:

*nnnn.nnnu*

Any numeric value that establishes the Y (down) coordinate of the logical page origin. *nnnn.nnn* is a number that can optionally contain a decimal point, and *u* is the units in inches (*i*) or millimeters (*m*).

If you do not specify a unit (*i* or *m*), then Infoprint uses pels as the unit type. You cannot specify fractional values (that is, you cannot use a decimal point) for pels.

**Note:** If you specify a value that is outside of the printable area, you will get a print-positioning error. To determine the printable area of IBM printer devices, see *Advanced Function Presentation: Printer Information*.

## **-o Keywords and Values for Specific Data Types**

You can also use **-o** to specify keywords (transform command flags or options) that apply to the following specific data types:

- Double-byte character set (DBCS) ASCII data
- Extended UNIX code (EUC) data
- Graphical Interchange Format (GIF) data
- Joint Photographic Experts Group (JPEG) data
- Line data
- PCL data
- Portable Document Format (PDF) data
- PostScript data
- Tag Image Format File (TIFF) data

For example, to specify that the finished width of a PostScript image is 6 inches, enter:

```
enq -P3825C -odatatype=ps -o-w6i memo1.ps
```

## -o Flag

### DBCS ASCII Data and EUC Data

If you are printing DBCS (double-byte) ASCII or Extended UNIX Code (EUC) data:

- Specify **-odatatype=dbcsascii** for DBCS ASCII or **-odatatype=dbcsascii -o-e** for EUC with the **enq**, **lp**, **qprt**, or **lprafp** command; or allow Infoprint to identify the data type.
- Infoprint automatically runs the **db2afp** transform command.
- You can use the following **db2afp** flags on the command line with **enq**, **lp**, **qprt** or **lprafp**:
  - o-e**
  - o-lja**
  - o-lch**
  - o-lko** (EUC only)

For information about these flags, see “db2afp Command: Transforms DBCS Data to AFP” on page 202.

You cannot use the **db2afp -o** flag to specify an output file.

**Note:** The **db2afp** transform must be installed on the workstation where Infoprint is installed.

### GIF Data

If you are printing GIF data:

- Specify **-odatatype=gif** with the **enq**, **lp**, **qprt**, or **lprafp** command; or allow Infoprint to identify the data type.
- Infoprint automatically runs the **gif2afp** transform command.
- You can use the following **gif2afp** options on the command line with **enq**, **lp**, **qprt**, or **lprafp**. For those options that accept a value, do not put a blank between the option and the value.
  - o-a***ImageType*
  - o-alg***ProcessingAlgorithms*
  - o-calib***calibration*
  - o-C***ConfigurationFile*
  - o-clean***cleanup*
  - o-cmp***compression*
  - o-crop***CropFactors*
  - o-fit**{*trim* | *scale*}
  - o-gcorr***GrayscaleMappingTable*
  - o-ink***color*
  - o-inv**
  - o-j***ScanOffsetFileName*
  - o-l***ImageLength*
  - o-M***MemoryBound*
  - o-ms***space*
  - o-msf***SpaceFraction*
  - o-nosniff**
  - o-noterm**
  - o-nov**
  - o-outbits***NumberOfOutputBits*
  - o-outcolor***OutputColorModel*
  - o-p***PageRange*
  - o-pagetype***PageType*
  - o-paper***PaperSize*
  - o-r***resolution*
  - o-respath***ResourceSearchPath*



**-o-rot***rotation*  
**-o-scale***ImageSize*  
**-o-sgcorr***ScannerCorrection*  
**-o-sniff**  
**-o-term**  
**-o-thresh***HalftoneFile*  
**-o-v**  
**-o-w***ImageWidth*  
**-o-x***LeftMargin*  
**-o-y***TopMargin*

For information about these options, see “gif2afp Command: Transforms GIF Data to AFP in Infoprint Manager for AIX” on page 209.

You cannot use the print command **-o** flag to pass the **gif2afp -o** option to specify an output file, or the **@**, **-f**, and **-z** options to specify input files.

**Note:** The **gif2afp** transform must be installed on the workstation where Infoprint is installed.

### JPEG Data

If you are printing JPEG data:

- Specify **-odatatype=jpeg** with the **enq**, **lp**, **qprt**, or **lprafp** command; or allow Infoprint to identify the data type.
- Infoprint automatically runs the **jpeg2afp** transform command.
- You can use the following **jpeg2afp** options on the command line with **enq**, **lp**, **qprt**, or **lprafp**. For those options that accept a value, do not put a blank between the option and the value.

**-o-a***ImageType*  
**-o-alg***ProcessingAlgorithms*  
**-o-calib***calibration*  
**-o-C***ConfigurationFile*  
**-o-cmp***compression*  
**-o-crop***CropFactors*  
**-o-fit**{*trim* | *scale*}  
**-o-force**  
**-o-gcorr***GrayscaleMappingTable*  
**-o-j***ScanOffsetFileName*  
**-o-l***ImageLength*  
**-o-M***MemoryBound*  
**-o-ms***space*  
**-o-msf***SpaceFraction*  
**-o-noterm**  
**-o-nov**  
**-o-outbits***NumberOfOutputBits*  
**-o-outcolor***OutputColorModel*  
**-o-p***PageRange*  
**-o-pagetype***PageType*  
**-o-paper***PaperSize*  
**-o-r***resolution*  
**-o-respath***ResourceSearchPath*  
**-o-rot***rotation*  
**-o-scale***ImageSize*  
**-o-sgcorr***ScannerCorrection*  
**-o-term**

## -o Flag

**-o-thresh***HalftoneFile*  
**-o-v**  
**-o-w***ImageWidth*  
**-o-wrkdir***WorkDirectory*  
**-o-x***LeftMargin*  
**-o-y***TopMargin*

For information about these options, see “jpeg2afp Command: Transforms JPEG Data to AFP in Infoprint Manager for AIX” on page 223.

You cannot use the print command **-o** flag to pass the **jpeg2afp -o** option to specify an output file, or the **@**, **-f**, and **-z** options to specify input files.

**Note:** The **jpeg2afp** transform must be installed on the workstation where Infoprint is installed.

## Line Data

If you are printing S/370 line data, or you are printing ASCII data that you want to format with a page definition:

- Specify **-odatatype=line** with the **enq**, **lp**, **qprt**, or **lprafp** command; or allow Infoprint to identify the data type.
- Infoprint automatically runs the **line2afp** transform command.
- You can use the following **line2afp** flags on the command line with **enq**, **lp**, **qprt**, or **lprafp**:

**-occ=***value*  
**-occtype=***value*  
**-ochars=***FontName[, ...]*  
**-ofileformat=***value*  
**-oformdef=***FormDefinitionName*  
**-oimageout=***value*  
**-oinpexit=***ProgramName*  
**-ormsgdd=***FileName*  
**-ooutexit=***ProgramName*  
**-opagedef=***PageDefinitionName*  
**-oparmdd=***FileName*  
**-opdeflib=***PathList*  
**-oprmode=***value*  
**-oresexit=***ProgramName*  
**-otrc=***value*  
**-ouserlib=***PathList*

For information about these flags, see “line2afp Command: Transforms S/370 Line Data and ASCII Data to AFP” on page 236.

You cannot use **line2afp** flags for the input file (**inputdd**) or the output file (**outputdd**).

When you are using **line2afp** flags with an AIX print command, you should not use **line2afp** flags that do the same thing as Infoprint-specific **-o** flags. Use the Infoprint-specific **-o** flags instead:

- Use **enq -odatatype=line -orespath=** instead of **enq -odatatype=line -ofdeflib=**
- Use **enq -odatatype=line -osrchfontlib=** instead of **enq -odatatype=line -ofontlib=**

- Use **enq -odatatype=line -orespath=** instead of **enq -odatatype=line -oovlylib=**
- Use **enq -odatatype=line -orespath=** instead of **enq -odatatype=line -opseglib=**
- Use **enq -odatatype=line -orespath=** instead of **enq -odatatype=line -oreslib=**

**Note:** The **line2afp** transform and **acif** command must be installed on the workstation where Infoprint is installed.

### PCL Data

If you are printing PCL data:

- Specify **-odatatype=pcl** with the **enq**, **lp**, **qprt**, or **lprafp** command; or allow Infoprint to identify the data type.
- Infoprint automatically runs the **pcl2afp** transform command.
- You can use the following **pcl2afp** flags on the command line with **enq**, **lp**, **qprt**, or **lprafp**. For those flags that accept a value, do not put a blank between the flag and the value.

**-o-a***OutputType*

**-o-c**

**-o-C***ConfigurationFile* (the configuration file must be specified as a full path name)

**-o-j***nnnn*

**-o-l***nnnn.nnnu*

**-o-M***nnnnn*

**-o-p***PageRange*

**-o-P***nnnnn*

**-o-q**

**-o-r***nnn*

**-o-S***ServerName*

**-o-s***nnnn*

**-o-w***nnnn.nnnu*

**-o-x***nnnn.nnnu*

**-o-y***nnnn.nnnu*

For information about these flags, see “pcl2afp Command: Transforms PCL Data to AFP” on page 261.

You cannot use the **pcl2afp -o** flag to specify an output file.

**Note:** The **pcl2afp** transform must be installed on the workstation where Infoprint is installed.

### PostScript and PDF Data

If you are printing PostScript or PDF data:

- Specify **-odatatype=ps** or **-odatatype=pdf** with the **enq**, **lp**, **qprt**, or **lprafp** command; or allow Infoprint to identify the data type.
- Infoprint automatically runs the **ps2afp** transform command. (The **pdf2afp** command is another name for **ps2afp**.)
- You can use the following **ps2afp** flags on the command line with **enq**, **lp**, **qprt**, or **lprafp**. For those flags that accept a value, do not put a blank between the flag and the value.

**-o-a***OutputType*

**-o-c**

## **-o Flag**

**-o-C***ConfigurationFile* (the configuration file must be specified as a full path name)  
**-o-F***FontMapFile[:...]* (the font map files must be specified as full path names)  
**-o-g***PageRange*  
**-o-j***nnnn*  
**-o-l***nnnn.nnnu*  
**-o-M***nnnnn*  
**-o-p***PageRange*  
**-o-P***nnnnn*  
**-o-q**  
**-o-r***nnn*  
**-o-S***ServerName*  
**-o-s***nnnn*  
**-o-w***nnnn.nnnu*  
**-o-x***nnnn.nnnu*  
**-o-y***nnnn.nnnu*

For information about these flags, see “pdf2afp and ps2afp Transforms: Transform PDF or PostScript Data to AFP” on page 284.

You cannot use the **ps2afp -o** flag to specify an output file.

**Note:** The **ps2afp** transform must be installed on the workstation where Infoprint is installed.

## **TIFF Data**

If you are printing TIFF data:

- Specify **-odatatype=tiff** with the **enq**, **lp**, **qpvt**, or **lprafp** command; or allow Infoprint to identify the data type.
- Infoprint automatically runs the **tiff2afp** transform command.
- You can use the following **tiff2afp** options on the command line with **enq**, **lp**, **qpvt**, or **lprafp**. For those options that accept a value, do not put a blank between the option and the value.

**-o-a***ImageType*  
**-o-alg***ProcessingAlgorithms*  
**-o-calib***calibration*  
**-o-choice***ImageChoice*  
**-o-C***ConfigurationFile*  
**-o-clean***cleanup*  
**-o-cmp***compression*  
**-o-crop***CropFactors*  
**-o-fit**{*trim* | *scale*}  
**-o-force**  
**-o-gcorr***GrayscaleMappingTable*  
**-o-ink***color*  
**-o-inv**  
**-o-j***ScanOffsetFileName*  
**-o-l***ImageLength*  
**-o-M***MemoryBound*  
**-o-mp**  
**-o-ms***space*  
**-o-msf***SpaceFraction*  
**-o-nomp**  
**-o-nosniff**  
**-o-noterm**

**-o-nov**  
**-o-outbits** *NumberOfOutputBits*  
**-o-outcolor** *OutputColorModel*  
**-o-p** *PageRange*  
**-o-pagetype** *PageType*  
**-o-paper** *PaperSize*  
**-o-r** *resolution*  
**-o-respath** *ResourceSearchPath*  
**-o-rot** *rotation*  
**-o-scale** *ImageSize*  
**-o-sgcorr** *ScannerCorrection*  
**-o-sniff**  
**-o-term**  
**-o-thresh** *HalftoneFile*  
**-o-v**  
**-o-w** *ImageWidth*  
**-o-wrkdir** *WorkDirectory*  
**-o-x** *LeftMargin*  
**-o-y** *TopMargin*

For information about these options, see “tiff2afp Command: Transforms TIFF Data to AFP in Infoprint Manager for AIX” on page 310.

You cannot use the print command **-o** flag to pass the **tiff2afp -o** option to specify an output file, or the **@**, **-f**, and **-z** options to specify input files.

**Note:** The **tiff2afp** transform must be installed on the workstation where Infoprint is installed.

---

## Examples

- To submit the ASCII file `myfile` to the Infoprint logical destination called `Xserv-lp` with four copies printed on one side of hole-punched paper, which is stored in the secondary bin of the printer device, enter:

```
enq -P Xserv-lp -obin=2 -ocopies=4 -oduplex=n myfile
```

Infoprint includes a form definition that specifies single-sided printouts of hole-punched paper from bin 2. If this form definition (**F1H10120**) is installed in the default directory, you could alternatively type:

```
enq -P Xserv-lp -ocopies=4 -oformdef=F1H10120 myfile
```

- To submit AFP data stream files `file1` and `file2` to the Infoprint logical destination called `dtsrv-lp`, with a search path for fonts of `/home/afpfonts`, enter:

```
lp -d dtsrv-lp -osrchfontlib=/home/afpfonts file1 file2
```

- To submit the PostScript file `myfile` to the Infoprint logical destination called `servB-lp` (which has a resolution of 300 pels), with a form definition of `F1PP0120`, with no reported invalid-character errors, and with a maximum of 100 printed messages, enter:

```
qprt -P servB-lp -o-r300 -odatac=blkchar -odatat=ps -of=F1PP0120  
-omsgc=100 myfile
```

**-o Flag**

## Chapter 4. Infoprint Administrative Utilities

This chapter describes the following Infoprint administrative utilities:

Utility Name	AIX	NT and 2000
“admingui Utility: Opens the Print Administration Window of the Basic Infoprint Administrator’s GUI in Infoprint Manager for AIX” on page 128	AIX	N/A
“afpsplit Utility: Extracts Pages from a MO:DCA-P File” on page 129	AIX	NT and 2000
“ainupod1 Utility: Generates Accounting Information by User” on page 130	AIX	NT and 2000: must be issued from the <i>install_path\bin</i> directory
“ainupod2 Utility: Generates Accounting Information by Job” on page 131	AIX	NT and 2000: must be issued from the <i>install_path\bin</i> directory
“ainupod3 Utility: Generates Accounting Information for a User” on page 132	AIX	NT and 2000: must be issued from the <i>install_path\bin</i> directory
“ainurpt1 Utility: Generates Accounting Information by Actual Destination” on page 134	AIX	NT and 2000: must be issued from the <i>install_path\bin</i> directory
“ainurpt2 Utility: Generates Accounting Information by User” on page 135	AIX	NT and 2000: must be issued from the <i>install_path\bin</i> directory
“ainurpt3 Utility: Generates Accounting Information for a User” on page 136	AIX	NT and 2000: must be issued from the <i>install_path\bin</i> directory
“ainurpt4 Utility: Generates Audit Information by Destination” on page 138	AIX	NT and 2000: must be issued from the <i>install_path\bin</i> directory
“ainurpt5 Utility: Generates Audit Information by User” on page 139	AIX	NT and 2000: must be issued from the <i>install_path\bin</i> directory
“ainurpt6 Utility: Generates Audit Information for a User” on page 140	AIX	NT and 2000: must be issued from the <i>install_path\bin</i> directory
“cfu Utility: Displays and Builds Coded Fonts in Infoprint Manager for AIX” on page 141	AIX	N/A
“cmt Utility: Builds Color Mapping Table Source and Object Files in Infoprint Manager for AIX” on page 143	AIX	N/A

## Administrative Utilities

“ipguiadv, ipguibasic, and ipguidist Utilities: Start the Infoprint Manager Operations GUI” on page 145	AIX	NT and 2000: add .bat to command name
“ipguiadvadm, ipguibasicadm, and ipguidistadm Utilities: Start the Infoprint Manager Administration GUI” on page 146	AIX	NT and 2000: add .bat to command name
“jsmigr Utility: Migrates PSF for AIX Job Scripts in Infoprint Manager for AIX” on page 148	AIX	N/A
“notification client” on page 150	AIX	NT and 2000
“opergui Utility: Opens the Print Management Window of the Basic Infoprint Administrator’s GUI in Infoprint Manager for AIX” on page 151	AIX	N/A
“pdadmin Utility: Opens the Servers Window of the Advanced Infoprint Administrator’s GUI in Infoprint Manager for AIX” on page 152	AIX	N/A
“pdcrcds Utility: Creates Directories for DCE in Infoprint Manager for AIX” on page 153	AIX	N/A
“pdcrdflt Utility: Creates Default Auxiliary Sheets, Media, and Queue in Infoprint Manager for AIX” on page 154	AIX	N/A
“pdcrrmed Utility: Creates Commonly Used Media in Infoprint Manager for AIX” on page 156	AIX	N/A
“pdinitports Utility: Initializes Ports” on page 157	AIX	NT and 2000
“pdmigpp Utility: Migrates Existing AIX Printers to Infoprint in Infoprint Manager for AIX” on page 159	AIX	N/A
“pdmincfg Utility: Sets up a Minimum Infoprint Configuration in Infoprint Manager for AIX” on page 161	AIX	N/A
“pdmsg Utility: Displays Information about a Message in Infoprint Manager for AIX” on page 163	AIX	N/A



## Administrative Utilities

“rc.ipsap Utility: Start SAP Callback Daemons for Infoprint Manager for AIX” on page 165	AIX	N/A
“rc.pd Utility: Restarts Servers in Infoprint Manager for AIX” on page 166	AIX	N/A
“sense Utility: Senses Whether a Channel-Attached Printer is Attached to Infoprint Manager for AIX” on page 167	AIX	N/A
“sense Utility: Senses Whether a Channel-Attached Printer is Attached to Infoprint Manager for Windows NT and Windows 2000” on page 169	N/A	NT and 2000
“setup Utility: Starts the Infoprint Installer in Infoprint Manager for AIX” on page 172	AIX	NT and 2000
“startppo Utility: Starts the Infoprint SMIT Production Print Operations Interface in Infoprint Manager for AIX” on page 175	AIX	N/A
“start_server Utility: Starts a Server for a Basic Infoprint Installation in Infoprint Manager for AIX” on page 176	AIX	N/A
“startsrv Utility: Starts a Server in Infoprint Manager for AIX” on page 178	AIX	NT and 2000
“stop_server Utility: Shuts Down a Server in Infoprint Manager for AIX” on page 180	AIX	NT and 2000
“tdump Utility: Outputs Tape Contents in Human-Readable Format in Infoprint Manager for AIX” on page 181	AIX	N/A
“tlist Utility: Lists Files on a Tape in Infoprint Manager for AIX” on page 183	AIX	NT and 2000
“t2file Utility: Reads MVS Partitioned Data Sets from Tape in Infoprint Manager for AIX” on page 184	AIX	NT and 2000

---

## admingui Utility: Opens the Print Administration Window of the Basic Infoprint Administrator's GUI in Infoprint Manager for AIX

### Syntax

```
admingui [-n | ServerName ...]
```

```
admingui -?
```

### Description

Use the **admingui** utility to open the Print Administration window of the basic Infoprint administrator's GUI. The Print Administration window displays the logical destinations, actual destinations, default jobs, default documents, and media that reside in all servers in the namespace.

### Flags

The **admingui** utility uses the following flags:

- n** Prevents Infoprint from starting any server. If you do not specify this flag, Infoprint checks to see if any server is running. If it is not running, Infoprint invokes the **start\_server** utility to start an existing server or create a new one.  
  
When you specify **-n**, you cannot specify a *ServerName*.
- ?** Displays help for the **admingui** utility.

### Arguments

The argument value identifies the server to which the utility applies.

Valid argument values for the **admingui** utility are:

*ServerName*

Specifies which server to start if no other servers are currently running. *ServerName* defaults to the hostname. If a server is already running, Infoprint ignores this argument.

When you specify *ServerName*, you cannot specify the **-n** flag.

### Examples

- To open the Print Administration window of the basic Infoprint administrator's GUI and ensure that the **default** server is started if no other server is running, enter:  
admingui
- To open the Print Administration window of the basic Infoprint administrator's GUI and ensure that the **charlie** server is started if no other server is running, enter:  
admingui charlie
- To open the Print Administration window of the basic Infoprint administrator's GUI without starting any servers, enter:  
admingui -n

---

## afpsplit Utility: Extracts Pages from a MO:DCA-P File

### Syntax

```
afpsplit [-f page] [-p page] [-o OutputFile] [InputFile]
```

### Description

Issue the **afpsplit** command to extract a page or a range of pages from an AFP MO:DCA-P document and create MO:DCA-P output.

You might use the **afpsplit** command to create a separate file starting at the 25th page and ending at the 50th page of a 200-page document. After you use the **afpsplit** command to create a file, you can view, store, print, or transmit that file.

#### Notes:

1. **afpsplit** removes structured index fields from MO:DCA-P files. This does not affect the appearance of printed files, but index entries are no longer available for viewing.
2. **afpsplit** writes error messages to STDERR.

### Flags

#### **-f** *page*

Specifies the forward space function, where *page* indicates the number of pages (0-999999999) that you can forward space from the beginning of the input file to start extracting the page or range of pages. To start extracting on page *n*, forward space *n-1* pages.

If you do not specify the **-f** flag, the extraction starts at the beginning of the file. If you specify more than one **-f** flag, the last one you specify is used.

#### **-p** *page*

Specifies the page end function, where *page* indicates the number of pages (0-999999999) to be extracted.

If you do not specify the **-p** flag, all pages from the forward space point to the end of the input file are included in the output file. If you specify more than one **-p** flag, the last one you specify is used.

#### **-o** *OutputFile*

Specifies the name of the file for the page or range of pages produced by **afpsplit**.

If you do not specify this flag, **afpsplit** uses standard output (STDOUT).

### Arguments

The valid argument value for the **afpsplit** utility is:

#### *InputFile*

Specifies the input file.

If you do not specify an input file, **afpsplit** uses standard input (STDIN).

### Example

To extract pages 21-30 from a MO:DCA-P input file called `input.afp` and use the **pdpr** command to print those 10 pages on printer `serv1-1p`, enter:

```
afpsplit -f 20 -p 10 input.afp | pdpr -p serv1-1p
```

---

## ainupod1 Utility: Generates Accounting Information by User

### Syntax

```
ainupod1
```

### Description

For Infoprint Manager for AIX, use the **ainupod1** utility to generate a report of accounting information for all jobs printed or transmitted on all defined PSF, fax, or email actual destinations, sorted by user ID. This information is derived from the **/var/psf/podaccount.log** file. By default, basic Infoprint installations set the value of the **accounting-exit** actual destination attribute to **job-ticket**, which invokes a user exit program that writes accounting information to this file.

For Infoprint Manager for Windows NT and Windows 2000, use the **ainupod1** utility to generate a report of accounting information for all jobs printed or transmitted on all defined PSF actual destinations, sorted by user ID. This information is derived from the **\install\_path\var\psf\podaccount.log** file. By default, basic Infoprint installations set the value of the **accounting-exit** actual destination attribute to **job-ticket**, which invokes a user exit program that writes accounting information to this file.

**Note:** On Windows NT or Window 2000, this command must be run from the **install\_path\bin** directory.

### Example

To generate accounting information for all users, enter:

```
ainupod1
```

**ainupod1** returns information similar to the following:

```
Accounting Report by Customer ID

Customer  Jobs  Pages  Bin1  Bin2
-----  -
apple      6     8     8     0
donald    18    2297  1511  0
```

### Suggested Reading

For information about:

- Auxiliary sheets, see “Attributes for Auxiliary-Sheet Objects” on page 443
- Other utilities that generate accounting reports from the **podaccount.log** file, see “ainupod2 Utility: Generates Accounting Information by Job” on page 131 and “ainupod3 Utility: Generates Accounting Information for a User” on page 132
- Utilities that generate accounting reports from the **accounting.log** file, see “ainurpt1 Utility: Generates Accounting Information by Actual Destination” on page 134, “ainurpt2 Utility: Generates Accounting Information by User” on page 135, and “ainurpt3 Utility: Generates Accounting Information for a User” on page 136
- Utilities that generate audit reports, see “ainurpt4 Utility: Generates Audit Information by Destination” on page 138, “ainurpt5 Utility: Generates Audit Information by User” on page 139, and “ainurpt6 Utility: Generates Audit Information for a User” on page 140

## ainupod2 Utility: Generates Accounting Information by Job

### Syntax

```
ainupod2
```

### Description

For Infoprint Manager for AIX, use the **ainupod2** utility to generate a report of accounting information for all jobs printed or transmitted on all defined PSF, fax, and email actual destinations, sorted by job ID. This information is derived from the **/var/psf/podaccount.log** file. By default, basic Infoprint installations set the value of the **accounting-exit** actual destination attribute to **job-ticket**, which invokes a user exit program that writes accounting information to this file.

For Infoprint Manager for Windows NT and Windows 2000, use the **ainupod2** utility to generate a report of accounting information for all jobs printed or transmitted on all defined PSF actual destinations, sorted by job ID. This information is derived from the **install\_path\var\psf\podaccount.log** file. By default, basic Infoprint installations set the value of the **accounting-exit** actual destination attribute to **job-ticket**, which invokes a user exit program that writes accounting information to this file.

**Note:** On Windows NT or Window 2000, this command must be run from the **install\_path\bin** directory.

### Example

To generate accounting information for all jobs, enter:

```
ainupod2
```

**ainupod2** returns information similar to the following:

Accounting Report by Job ID

Job ID	Jobs	Pages	Bin1	Bin2
E1A0540F.3F8	7	48	48	0
E1B0440B.B0B	10	196	175	0
NONE	53	94	94	0

### Suggested Reading

For information about:

- Auxiliary sheets, see “Attributes for Auxiliary-Sheet Objects” on page 443
- Other utilities that generate accounting reports from the **podaccount.log** file, see “ainupod1 Utility: Generates Accounting Information by User” on page 130 and “ainupod3 Utility: Generates Accounting Information for a User” on page 132
- Utilities that generate accounting reports from the **accounting.log** file, see “ainurpt1 Utility: Generates Accounting Information by Actual Destination” on page 134, “ainurpt2 Utility: Generates Accounting Information by User” on page 135, and “ainurpt3 Utility: Generates Accounting Information for a User” on page 136
- Utilities that generate audit reports, see “ainurpt4 Utility: Generates Audit Information by Destination” on page 138, “ainurpt5 Utility: Generates Audit Information by User” on page 139, and “ainurpt6 Utility: Generates Audit Information for a User” on page 140

## ainupod3 Utility: Generates Accounting Information for a User

### Syntax

```
ainupod3
```

### Description

For Infoprint Manager for AIX, use the **ainupod3** utility to generate a report of accounting information for all jobs printed or transmitted on all defined PSF, fax, and email actual destinations by a given user. This information is derived from the **/var/psf/podaccount.log** file. By default, basic Infoprint installations set the value of the **accounting-exit** actual destination attribute to **job-ticket**, which invokes a user exit program that writes accounting information to this file.

For Infoprint Manager for Windows NT and Windows 2000, use the **ainupod3** utility to generate a report of accounting information for all jobs printed or transmitted on all defined PSF actual destinations by a given user. This information is derived from the **install\_path\var\psf\podaccount.log** file. By default, basic Infoprint installations set the value of the **accounting-exit** actual destination attribute to **job-ticket**, which invokes a user exit program that writes accounting information to this file.

**Note:** On Windows NT or Window 2000, this command must be run from the **install\_path\bin** directory.

### Example

To generate accounting information for user donald, enter:

```
ainupod3
```

When **ainupod3** prompts you for a user ID, enter:

```
donald
```

**ainupod3** returns information similar to the following:

```
Print Activity Report for donald
```

Start Date	Start Time	Destination ID	Pages Printed	Copies Requested	Job Identification
07/26/1997	15:36:32	e1	45	1	E1B0440B.B0B
07/31/1997	08:24:24	3900-p4	15	1	ila11908.54d
08/01/1997	08:28:48	e1	131	1	e1a1050c.431

### Suggested Reading

For information about:

- Auxiliary sheets, see “Attributes for Auxiliary-Sheet Objects” on page 443
- Other utilities that generate accounting reports from the **podaccount.log** file, see “ainupod1 Utility: Generates Accounting Information by User” on page 130 and “ainupod2 Utility: Generates Accounting Information by Job” on page 131
- Utilities that generate accounting reports from the **accounting.log** file, see “ainurpt1 Utility: Generates Accounting Information by Actual Destination” on page 134, “ainurpt2 Utility: Generates Accounting Information by User” on page 135, and “ainurpt3 Utility: Generates Accounting Information for a User” on page 136

- Utilities that generate audit reports, see “ainurpt4 Utility: Generates Audit Information by Destination” on page 138, “ainurpt5 Utility: Generates Audit Information by User” on page 139, and “ainurpt6 Utility: Generates Audit Information for a User” on page 140

## ainurpt1 Utility: Generates Accounting Information by Actual Destination

### Syntax

```
ainurpt1
```

### Description

For Infoprint Manager for AIX, use the **ainurpt1** utility to generate a report of accounting information for all jobs printed or transmitted on all defined PSF, fax, and email actual destinations, sorted by actual destination. This information is derived from the */var/psf/accounting.log* file. By default, advanced Infoprint installations set the value of the the **accounting-exit** actual destination attribute to **accounting-log**, which invokes a user exit program that writes accounting information to this file.

For Infoprint Manager for Windows NT and Windows 2000, use the **ainurpt1** utility to generate a report of accounting information for all jobs printed or transmitted on all defined PSF actual destinations, sorted by actual destination. This information is derived from the *install\_path\var\psf\accounting.log* file. By default, advanced Infoprint installations set the value of the the **accounting-exit** actual destination attribute to **accounting-log**, which invokes a user exit program that writes accounting information to this file.

**Note:** On Windows NT or Window 2000, this command must be run from the *install\_path\bin* directory.

### Example

To generate accounting information for all PSF, fax, and email actual destinations, enter:

```
ainurpt1
```

**ainurpt1** returns information similar to the following:

Destination	Jobs	Pages	Bin1	Bin2	Fonts	Resident	Overlays	Hard	Soft
ksrv-p1	120	1200	88	32	10	0	0	0	0
ksrv-p2	72	981	72	0	4	0	0	0	0

### Suggested Reading

For information about:

- Auxiliary sheets, see “Attributes for Auxiliary-Sheet Objects” on page 443
- Other utilities that generate accounting reports from the **accounting.log** file, see “ainurpt2 Utility: Generates Accounting Information by User” on page 135 and “ainurpt3 Utility: Generates Accounting Information for a User” on page 136
- Utilities that generate accounting reports from the **podaccount.log** file, see “ainupod1 Utility: Generates Accounting Information by User” on page 130, “ainupod2 Utility: Generates Accounting Information by Job” on page 131, and “ainupod3 Utility: Generates Accounting Information for a User” on page 132
- Utilities that generate audit reports, see “ainurpt4 Utility: Generates Audit Information by Destination” on page 138, “ainurpt5 Utility: Generates Audit Information by User” on page 139, and “ainurpt6 Utility: Generates Audit Information for a User” on page 140



## ainurpt2 Utility: Generates Accounting Information by User

### Syntax

```
ainurpt2
```

### Description

For Infoprint Manager for AIX, use the **ainurpt2** utility to generate a report of accounting information for all jobs printed or transmitted on all defined PSF, fax, and email actual destinations, sorted by user. This information is derived from the **/var/psf/accounting.log** file. By default, advanced Infoprint installations set the value of the the **accounting-exit** actual destination attribute to **accounting-log**, which invokes a user exit program that writes accounting information to this file.

For Infoprint Manager for Windows NT and Windows 2000, use the **ainurpt2** utility to generate a report of accounting information for all jobs printed or transmitted on all defined PSF actual destinations, sorted by user. This information is derived from the **install\_path\var\psf\accounting.log** file. By default, advanced Infoprint installations set the value of the the **accounting-exit** actual destination attribute to **accounting-log**, which invokes a user exit program that writes accounting information to this file.

**Note:** On Windows NT or Window 2000, this command must be run from the **install\_path\bin** directory.

### Example

To generate accounting information for all users, enter:

```
ainurpt2
```

**ainurpt2** returns information similar to the following:

Userids	Jobs	Pages	Bin1	Bin2	Fonts	Resident	Overlays	Hard	Soft
billing	120	1200	88	32	10	0	0	0	0
reppen	72	981	72	0	4	0	0	0	0

### Suggested Reading

For information about:

- Auxiliary sheets, see “Attributes for Auxiliary-Sheet Objects” on page 443
- Other utilities that generate accounting reports from the **accounting.log** file, see “ainurpt1 Utility: Generates Accounting Information by Actual Destination” on page 134 and “ainurpt3 Utility: Generates Accounting Information for a User” on page 136
- Utilities that generate accounting reports from the **podaccount.log** file, see “ainupod1 Utility: Generates Accounting Information by User” on page 130, “ainupod2 Utility: Generates Accounting Information by Job” on page 131, and “ainupod3 Utility: Generates Accounting Information for a User” on page 132
- Utilities that generate audit reports, see “ainurpt4 Utility: Generates Audit Information by Destination” on page 138, “ainurpt5 Utility: Generates Audit Information by User” on page 139, and “ainurpt6 Utility: Generates Audit Information for a User” on page 140

## ainurpt3 Utility: Generates Accounting Information for a User

### Syntax

```
ainurpt3
```

### Description

For Infoprint Manager for AIX, use the **ainurpt3** utility to generate a report of accounting information for all jobs printed or transmitted on all defined PSF, fax, and email actual destinations by a given user. This information is derived from the **/var/psf/accounting.log** file. By default, advanced Infoprint installations set the value of the the **accounting-exit** actual destination attribute to **accounting-log**, which invokes a user exit program that writes accounting information to this file.

For Infoprint Manager for Windows NT and Windows 2000, use the **ainurpt3** utility to generate a report of accounting information for all jobs printed or transmitted on all defined PSF actual destinations by a given user. This information is derived from the **install\_path\var\psf\accounting.log** file. By default, advanced Infoprint installations set the value of the the **accounting-exit** actual destination attribute to **accounting-log**, which invokes a user exit program that writes accounting information to this file.

**Note:** On Windows NT or Window 2000, this command must be run from the **install\_path\bin** directory.

### Example

To generate accounting information for user kathy, enter:

```
ainurpt3
```

When **ainurpt3** prompts you for a user ID, enter:

```
kathy
```

**ainurpt3** returns information similar to the following:

Report for kathy

Start Date	Start Time	Destination ID	Pages Printed	Job Name
06/02/1997	12:53:47	ksrv-p1	1190	/net/home/kathy/May.billing
06/03/1997	15:42:31	hsrv-p1	944	/net/home/kathy/May.reports

### Suggested Reading

For information about:

- Auxiliary sheets, see “Attributes for Auxiliary-Sheet Objects” on page 443
- Other utilities that generate accounting reports from the **accounting.log** file, see “ainurpt1 Utility: Generates Accounting Information by Actual Destination” on page 134 and “ainurpt2 Utility: Generates Accounting Information by User” on page 135
- Utilities that generate accounting reports from the **podaccount.log** file, see “ainupod1 Utility: Generates Accounting Information by User” on page 130, “ainupod2 Utility: Generates Accounting Information by Job” on page 131, and “ainupod3 Utility: Generates Accounting Information for a User” on page 132

- Utilities that generate audit reports, see “ainurpt4 Utility: Generates Audit Information by Destination” on page 138, “ainurpt5 Utility: Generates Audit Information by User” on page 139, and “ainurpt6 Utility: Generates Audit Information for a User” on page 140

## ainurpt4 Utility: Generates Audit Information by Destination

### Syntax

```
ainurpt4
```

### Description

For Infoprint Manager for AIX, use the **ainurpt4** utility to generate a report of audit information for all jobs printed or transmitted on all defined PSF, fax, and email actual destinations, sorted by actual destination. This information is derived from the **/var/psf/audit.log** file. To write information to this file, specify **accounting-log** as the value of the **audit-exit** actual destination attribute.

For Infoprint Manager for Windows NT and Windows 2000, use the **ainurpt4** utility to generate a report of audit information for all jobs printed or transmitted on all defined PSF actual destinations, sorted by actual destination. This information is derived from the *install\_path\var\psf\audit.log* file. To write information to this file, specify **accounting-log** as the value of the **audit-exit** actual destination attribute.

**Note:** On Windows NT or Window 2000, this command must be run from the *install\_path\bin* directory.

### Example

To generate audit information for all PSF, fax, and email actual destinations, enter:

```
ainurpt4
```

**ainurpt4** returns information similar to the following:

Destination	Jobs	Pages	Bin1	Bin2	Fonts	Resident	Overlays	Hard	Soft
ksrv-p1	120	1200	88	32	10	0	0	0	0
ksrv-p2	72	981	72	0	4	0	0	0	0

### Suggested Reading

For information about:

- Auxiliary sheets, see “Attributes for Auxiliary-Sheet Objects” on page 443
- Other utilities that generate audit reports, see “ainurpt5 Utility: Generates Audit Information by User” on page 139 and “ainurpt6 Utility: Generates Audit Information for a User” on page 140
- Utilities that generate accounting reports from the **accounting.log** file, see “ainurpt1 Utility: Generates Accounting Information by Actual Destination” on page 134, “ainurpt2 Utility: Generates Accounting Information by User” on page 135, and “ainurpt3 Utility: Generates Accounting Information for a User” on page 136
- Utilities that generate accounting reports from the **podaccount.log** file, see “ainupod1 Utility: Generates Accounting Information by User” on page 130, “ainupod2 Utility: Generates Accounting Information by Job” on page 131, and “ainupod3 Utility: Generates Accounting Information for a User” on page 132

## ainurpt5 Utility: Generates Audit Information by User

### Syntax

```
ainurpt5
```

### Description

For Infoprint Manager for AIX, use the **ainurpt5** utility to generate a report of audit information for all jobs printed or transmitted on all defined PSF, fax, and email actual destinations, sorted by user. This information is derived from the **/var/psf/audit.log** file. To write information to this file, specify **accounting-log** as the value of the **audit-exit** actual destination attribute.

For Infoprint Manager for Windows NT and Windows 2000, use the **ainurpt5** utility to generate a report of audit information for all jobs printed or transmitted on all defined PSF actual destinations, sorted by user. This information is derived from the **install\_path\var\psf\audit.log** file. To write information to this file, specify **accounting-log** as the value of the **audit-exit** actual destination attribute.

**Note:** On Windows NT or Window 2000, this command must be run from the **install\_path\bin** directory.

### Example

To generate audit information for all users, enter:

```
ainurpt5
```

**ainurpt5** returns information similar to the following:

Userids	Jobs	Pages	Bin1	Bin2	Fonts	Resident	Overlays	Hard	Soft
billing	120	1200	88	32	10	0	0	0	0
reppen	72	981	72	0	4	0	0	0	0

### Suggested Reading

For information about:

- Auxiliary sheets, see “Attributes for Auxiliary-Sheet Objects” on page 443
- Other utilities that generate audit reports, see “ainurpt4 Utility: Generates Audit Information by Destination” on page 138 and “ainurpt6 Utility: Generates Audit Information for a User” on page 140
- Utilities that generate accounting reports from the **accounting.log** file, see “ainurpt1 Utility: Generates Accounting Information by Actual Destination” on page 134, “ainurpt2 Utility: Generates Accounting Information by User” on page 135, and “ainurpt3 Utility: Generates Accounting Information for a User” on page 136
- Utilities that generate accounting reports from the **podaccount.log** file, see “ainupod1 Utility: Generates Accounting Information by User” on page 130, “ainupod2 Utility: Generates Accounting Information by Job” on page 131, and “ainupod3 Utility: Generates Accounting Information for a User” on page 132

## ainurpt6 Utility: Generates Audit Information for a User

### Syntax

```
ainurpt6
```

### Description

For Infoprint Manager for AIX, use the **ainurpt6** utility to generate a report of audit information for all jobs printed or transmitted on all defined PSF, fax, and email actual destinations by a given user. This information is derived from the **/var/psf/audit.log** file. To write information to this file, specify **accounting-log** as the value of the **audit-exit** actual destination attribute.

For Infoprint Manager for Windows NT and Windows 2000, use the **ainurpt6** utility to generate a report of audit information for all jobs printed or transmitted on all defined PSF actual destinations by a given user. This information is derived from the **install\_path\var\psf\audit.log** file. To write information to this file, specify **accounting-log** as the value of the **audit-exit** actual destination attribute.

**Note:** For Windows NT or Window 2000, this command must be run from the **install\_path\bin** directory.

### Example

To generate audit information for user kathy, enter:

```
ainurpt6
```

When **ainurpt6** prompts you for a user ID, enter:

```
kathy
```

**ainurpt6** returns information similar to the following:

Report for kathy

Start Date	Start Time	Destination ID	Pages Printed	Job Name
06/02/1997	12:53:47	ksrv-p1	1190	/net/home/kathy/May.billing
06/03/1997	15:42:31	hsrv-p1	944	/net/home/kathy/May.reports

### Suggested Reading

For information about:

- Auxiliary sheets, see “Attributes for Auxiliary-Sheet Objects” on page 443
- Other utilities that generate audit reports, see “ainurpt4 Utility: Generates Audit Information by Destination” on page 138 and “ainurpt5 Utility: Generates Audit Information by User” on page 139
- Utilities that generate accounting reports from the **accounting.log** file, see “ainurpt1 Utility: Generates Accounting Information by Actual Destination” on page 134, “ainurpt2 Utility: Generates Accounting Information by User” on page 135, and “ainurpt3 Utility: Generates Accounting Information for a User” on page 136
- Utilities that generate accounting reports from the **podaccount.log** file, see “ainupod1 Utility: Generates Accounting Information by User” on page 130, “ainupod2 Utility: Generates Accounting Information by Job” on page 131, and “ainupod3 Utility: Generates Accounting Information for a User” on page 132

---

## cfu Utility: Displays and Builds Coded Fonts in Infoprint Manager for AIX

### Syntax

```
cfu [-d | -b] CodedFontName [BuildFileName]
```

### Description

**cfu**, the Coded Font Utility, displays and builds coded fonts for use with IBM Infoprint Control. The main purpose of the **cfu** utility is to allow users of double-byte raster fonts to indicate which font sections in the coded font should be downloaded to the printer and which font sections can be found resident in the printer. This is useful when:

- You have added user-defined characters to a font section
- The printer-resident version of a font differs from the system-resident version of a font, and you want to ensure that IBM Infoprint Control downloads the system version.

You can also add and delete sections from the coded font and change which character sets and code pages are referenced in the coded font.

You can also use the **cfu** utility to build single-byte coded fonts by specifying a font character set name and a code page name.

You can use the **cfu** utility in two ways:

- In the display mode of the **cfu** utility, you provide a coded font name as input. The **cfu** utility generates a build file that can be used as input to the build mode of the **cfu** utility.
- In the build mode of the **cfu** utility, you provide a build file name as input. The **cfu** utility generates a coded font.

### Flags

The **cfu** utility uses the following flags:

- d Display mode displays the contents of a coded font. Output is written to standard output. This is the default mode if no flag is entered.
- b Build mode builds a new coded font using the *build file name*, or standard input if the *build file name* is omitted.

### Build File Format

Each non-commented line in the build file defines one repeating group within the Coded Font Index structured field. Repeating group definitions may not span more than one line and fields within each line must be delimited with blanks. A pound sign (#) at the beginning of a line indicates a comment.

A repeating group definition has the following format:

- Field 1 is the section identifier of the repeating group. The format is **X'hh'**, where *hh* is the hexadecimal section identifier. Both the **X** character and the single quotation marks are required.
- Field 2 is the character set name. Only the first 8 characters are used.
- Field 3 is the code page name. Only the first 8 characters are used.
- Field 4 is the section resident indicator:

## cfu

- 1 Use the printer-resident section if possible.
- 0 Download the section.

**Note:** This field is only meaningful for double-byte raster fonts.

This is an example of a repeating group:

```
# SectId CharSet CodePage Resident
# -----
X'41' C0Z24F41 T1Z24F41 0
```

## Arguments

The valid argument values for the **cfu** utility are:

### *CodedFontName*

The name of the coded font for display mode or the new coded font name in build mode. **cfu** will not overwrite existing coded fonts in build mode.

**Note:** In build mode, the *coded font name* is also the internal coded font name in the Begin Coded Font structured field.

### *BuildFileName*

The input file used to build a new coded font. If *build file name* is omitted, **cfu** reads from standard input.

## Examples

- To display the contents of the coded font X0Z24F, enter either of the following commands:

```
cfu X0Z24F
cfu -d X0Z24F
```

- To build a new coded font with the name X0Z24F using build file X0Z24F.bld, enter:

```
cfu -b X0Z24F X0Z24F.bld
```

## Suggested Reading

Refer to *Data Stream and Object Architectures: Font Object Content Architecture Reference* for more information on coded font structured fields.



## cmt Utility: Builds Color Mapping Table Source and Object Files in Infoprint Manager for AIX

### Syntax

```
cmt -i input file [-o output file] [-n internal CMT name] [-t]
```

### Description

**cmt**, the Color Mapping Table Utility, generates color mapping table source and object files. If the input file is an object color mapping table, **cmt** generates a source output file; and if the input file is a source file, **cmt** generates an object file. Object color mapping tables are used to map OCA (Object Content Architecture) colors and fills to printer specific colors.

### Flags

The **cmt** utility uses the following flags:

- i The file name of the input file. The input file can be a source or object file. When you use the **cmt** utility, you must specify this flag.
- o The file name of the output file. If this flag is not specified, **stdout** is used. This is a optional flag.
- n The name that appears on the MO:DCA Begin Object Container (BOC) structured field. This is a optional flag.
- t Use this flag to turn on trace. This is a optional flag.

### Color Mapping Table Source File

The source file describes the contents of the color mapping table object file.

Each mapping definition of one source color or fill to a target color is bracketed by the keywords **BeginMappingDef:** and **EndMappingDef:**. The **cmt** utility requires one mapping definition for each source target mapping.

Each source definition within a mapping definition is bracketed by the keywords **BeginSourceDef:** and **EndSourceDef:**. The **cmt** utility requires one source definition for each mapping definition.

Valid keywords and values for a source definition follow:

#### ColorSpace

You must specify **OCA**, **Highlight**, or **GOCA**.

#### ColorValue

You must specify a value that depends upon the value specified for **ColorSpace:**

- When **ColorSpace=OCA**, **ColorValue** is a one string component of the following:

**Default**  
**Blue**  
**Red**  
**Pink**  
**Green**  
**Cyan**  
**Yellow**

**Black**  
**Brown**  
**Medium**

**Note:** The binary representation for all **OCA** colors are supported by the **cmt** utility.

- When **ColorSpace=Highlight**, the **ColorValue** has one component, integer 0 through 3, for example:

ColorValue: 2

- When **ColorSpace=GOCA**, the **ColorValue** has one component, integer 0 through 16 or 64, for example:

ColorValue: 13

Each target definition within a mapping definition is bracketed by the keywords **BeginTargetDef** and **EndTargetDef**. The **cmt** utility requires one target definition within each mapping definition. Valid keywords and values for a target definition follow:

**ColorSpace**

You must specify **RGB**, **CMYK**, **Highlight**, or **CIELAB**.

**ColorValue**

You must specify a value determined by the value specified by **ColorSpace** as follows:

- When **ColorSpace=RGB**, the **ColorValue** has three components from 0 through 255. For example, 33 167 247.
- When **ColorSpace=CMYK**, the **ColorValue** has four components from 0 through 255. For example, 135 26 37 255.
- When **ColorSpace=CIELAB**, the **ColorValue** has three components with the first integer from 0 through 100, and the second and third integers from -127 through 127. For example 65 -120 111.

**PercentShading**

Valid values are integers 0 through 100. This optional value defaults to 100.

**PercentCoverage**

Value values are integers 0 through 100. This optional value defaults to 100.

## ipguiadv, ipguibasic, and ipguidist Utilities: Start the Infoprint Manager Operations GUI

### Syntax

For Infoprint Manager for AIX:

**ipguiadv**

**ipguibasic**

**ipguidist**

For Infoprint Manager for Windows NT and Windows 2000:

**ipguiadv.bat**

### Description

Issue the **ipguiadv**, **ipguibasic**, or **ipguidist** utility to start the Infoprint Manager Operations GUI on Infoprint Manager for AIX.

Issue the **ipguiadv** utility to start the Infoprint Manager Operations GUI on Infoprint Manager for Windows NT and Windows 2000.

Each view is designed to be most useful in a specific environment, but you can open any view in any environment.

For Infoprint Manager for AIX:

**ipguiadv**

Starts the view for an advanced Infoprint Manager Operations GUI.

**ipguibasic**

Starts the view for a basic Infoprint Manager Operations GUI.

**ipguidist**

Starts the view for a distributed Infoprint Manager Operations GUI.

For Infoprint Manager for Windows NT and Windows 2000:

**ipguiadv**

Starts the view for an advanced Infoprint Manager Operations GUI.

**Note:** On Windows NT or Windows 2000, **ipguiadv** is installed into *install\_path\ipqui*, which is not the PATH.

### Example

With Infoprint Manager for AIX, to start the Infoprint Manager Operations GUI, displaying the view for a basic Infoprint installation, enter:

```
ipguibasic
```

With Infoprint Manager for Windows NT and Windows 2000, to start the Infoprint Manager Operations GUI, displaying the view for an advanced Infoprint installation, enter:

```
ipguiadv.bat
```

## ipguiadvadm, ipguibasicadm, and ipguidistadm Utilities: Start the Infoprint Manager Administration GUI

### Syntax

For Infoprint Manager for AIX:

**ipguiadvadm**

**ipguibasicadm**

**ipguidistadm**

For Infoprint Manager for Windows NT and Windows 2000:

**ipguiadvadm.bat**

**ipguibasicadm.bat**

**ipguidistadm.bat**

### Description

Issue the **ipguiadvadm**, **ipguibasicadm**, or **ipguidistadm** utility to start the Infoprint Manager Administration GUI on Infoprint Manager for AIX.

Issue the **ipguiadvadm** utility to start the Infoprint Manager Administration GUI on Infoprint Manager for Windows NT and Windows 2000.

For Infoprint Manager for AIX:

**ipguiadvadm**

Starts the view for an advanced Infoprint Manager Administration GUI.

**ipguibasicadm**

Starts the view for a basic Infoprint Manager Administration GUI.

**ipguidistadm**

Starts the view for a distributed Infoprint Manager Administration GUI.

For Infoprint Manager for Windows NT and Windows 2000:

**ipguiadvadm**

Starts the view for an advanced Infoprint Manager Administration GUI.

**Note:** On Windows NT or Window 2000, **ipquiadvadm.bat** is installed into *install\_path\ipquiadm*, which is not the PATH.

Each view is designed to be most useful in a specific environment, but you can open any view in any environment.

### Example

With Infoprint Manager for AIX, to start the Infoprint Manager Administration GUI, displaying the view for a basic Infoprint installation, enter:

```
ipguibasicadm
```

## **ipguiadvadm, ipguibasicadm, and ipguidistadm**

| With Infoprint Manager for Windows NT and Windows 2000, to start the Infoprint  
| Manager Administration GUI, displaying the view for an advanced Infoprint  
| installation, enter:

| `ipguiadvadm.bat`  
|

---

## jsmigr Utility: Migrates PSF for AIX Job Scripts in Infoprint Manager for AIX

### Syntax

```
jsmigr JobScript ...
```

### Description

Issue the **jsmigr** utility to migrate PSF for AIX job scripts to Infoprint command scripts and attributes files. The **jsmigr** utility creates the following files:

#### *JobScript.ksh*

Infoprint command script containing

- The **pdpr** command
- One or more **-X** flags invoking attributes files
- If the job script includes the corresponding keywords, other flags and arguments of the **pdpr** command (for example, the **-T** flag for tape input or the names of files to be printed)

This file is created in the same directory as the migrated job script and has the same file name with **.ksh** appended.

#### *JobScript.X*

Attributes file used by *JobScript.ksh*, containing attributes migrated from the job script keywords. This file is created in the same directory as the migrated job script and has the same file name with **.X** appended.

#### *FileName.X*

Attributes files used by *JobScript.ksh*. These files are migrated from job scripts named as values for the **a\_Parmdd**, **i\_FileNames**, **p\_Config**, and **e\_Filemsg** keywords. Each file is created in the same directory as the original file and has the same file name with **.X** appended.

#### Notes:

1. This utility normally executes as part of the Infoprint installation.
2. "Appendix B. Migrating PSF for AIX Job Script Keywords to Infoprint Equivalents" on page 691 shows the attributes to which job script keywords are migrated.
3. If multiple job scripts refer to the same file, **jsmigr** migrates the file only once.
4. Job scripts named as values for the **a\_Parmdd**, **p\_Config**, and **e\_Filemsg** keywords must be specified with absolute path names.
5. Infoprint searches for job scripts named as values for the **i\_FileNames** keyword in these directories:
  - a. Current directory
  - b. **\$HOME/js**
  - c. **/var/psf/js**
6. If a data type is specified with the **JsFileType** keyword, keywords that are not valid for that data type are commented out in the attributes file resulting from conversion. For example, if **JsFileType** has any value other than **line**, all **a\_** keywords are commented out. If you edit the attributes file and change the value of the **document-format** attribute to **line-data**, you must remove the comment characters before using the attributes file to submit line-data jobs.

7. If the input device is not **rmtx**, tape-related job script keywords are commented out in the attributes file resulting from conversion. You must edit the attributes file and remove the comment characters before using it to submit jobs read from tape.
8. Job scripts containing both **a\_** and **p\_** keywords may convert to an attributes file that causes transforms to fail, especially if any of the keywords convert to the **other-transform-options** attribute. This happens because PSF for AIX ignores job script keywords that do not apply to the job, but Infoprint processes all attributes.
9. If **jsmigr** encounters a job script keyword that it cannot map to an Infoprint attribute, it issues an error message, erases the attributes file it is writing, ends migrating the job script, and continues with the next job script.
10. If **jsmigr** encounters a job script keyword that it can map to an Infoprint attribute, with a value that has no Infoprint equivalent, it converts the keyword and continues writing the attributes file. When you use the attributes file to submit a job, Infoprint issues an error message and does not print or transmit the job.

## Arguments

The argument value identifies the job script to be migrated.

Valid argument values for the **jsmigr** utility are:

### *JobScript*

Specifies the job script to be migrated. The job script file must have a **.js** extension, which you do not have to specify.

You can specify multiple job script names. You can use an asterisk (\*) to specify all job scripts in a directory.

## Examples

- To migrate the job scripts `bigjob.js` and `smalljob.js`, enter:  

```
jsmigr bigjob smalljob
```
- To migrate all the job scripts in the directory `/var/psf/js`, enter:  

```
jsmigr /var/psf/js/*
```

notification client

---

## notification client

Used to start a notification window to retrieve notifications delivered by *message* from the notification server.



---

## opergui Utility: Opens the Print Management Window of the Basic Infoprint Administrator's GUI in Infoprint Manager for AIX

### Syntax

```
opergui [-n|ServerName]
```

### Description

Use the **opergui** utility to open the Print Management window of the basic Infoprint administrator's GUI. The Print Management window displays the actual destinations, unassigned jobs, and retained jobs that reside in all servers in the namespace.

### Flags

The **opergui** utility uses the following flag:

- n** Prevents Infoprint from starting any servers. If you do not specify this flag, Infoprint checks to see if any servers are running. If no servers are running, Infoprint invokes the **start\_server** utility to start the specified server if it exists or create it if it does not.  
If you specify the **-n** flag, you cannot specify a server name.
- ?** Displays help for the **opergui** utility.

### Arguments

The argument value identifies the server to which the utility applies.

Valid argument values for the **opergui** utility are:

*ServerName*

Specifies the name of the server you want to start if no other servers are currently running. *ServerName* defaults to the hostname. If any servers are running, Infoprint ignores this argument.

If you specify a server name, you cannot specify the **-n** flag.

### Examples

- To open the Print Management window of the basic Infoprint administrator's GUI, starting the default server if no other servers are running, enter:  
opergui
- To open the Print Management window of the basic Infoprint administrator's GUI, starting the server `charlie` if no other servers are running, enter:  
opergui charlie
- To open the Print Management window of the basic Infoprint administrator's GUI, without starting any servers, enter:  
opergui -n

---

## pdadmin Utility: Opens the Servers Window of the Advanced Infoprint Administrator's GUI in Infoprint Manager for AIX

### Syntax

```
pdadmin
```

### Description

Use the **pdadmin** utility to open the Servers window of the advanced Infoprint administrator's GUI. The Servers window displays the queues and actual destinations default jobs, default documents, and media that reside in the servers you select in a dialog.

### Examples

- To monitor all the servers in the namespace:
  1. Enter:

```
pdadmin
```
  2. In the Select Servers dialog, click **OK**.
- To monitor the servers `julia` and `henry`:
  1. Enter:

```
pdadmin
```
  2. In the Select Servers dialog, select `julia`.
  3. Hold down the **CTRL** key and select `henry`.
  4. Click **OK**.

---

## pdcr cds Utility: Creates Directories for DCE in Infoprint Manager for AIX

### Syntax

```
pdcr cds
```

### Description

Issue the **pdcr cds** utility to create the directories and soft links needed for Infoprint within the DCE namespace. You should only run the **pdcr cds** utility once in each DCE cell in which Infoprint servers will run regardless of the number of servers. This utility also establishes the initial ACL structure used by the Infoprint security service.

**Note:** This utility normally executes as part of the Infoprint installation.

### Example

To create directories needed for Infoprint in the DCE namespace, enter:

```
pdcr cds
```

Infoprint displays the following:

```
Creating Infoprint directories in the DCE namespace...
```

---

## pdcrdflt Utility: Creates Default Auxiliary Sheets, Media, and Queue in Infoprint Manager for AIX

### Syntax

```
pdcrdflt [-c] ServerName
```

### Description

Issue the **pdcrdflt** utility to perform the following server configuration tasks:

- Create the default auxiliary sheets and media in a server.
- For a basic installation only, create the default queue.
- For a basic installation only, set server and queue attributes.

The default auxiliary sheets that this utility creates are:

**accounting-log**  
**blank**  
**brief**  
**full**  
**job-ticket**  
**none**  
**64xx**

The default media that this utility creates are:

**A3**  
**A4**  
**B4**  
**B5**  
**ledger**  
**legal**  
**letter**  
**tabloid**

You only need to run the **pdcrdflt** utility if the **startsrv** utility failed to create all the default objects.

If you specify the **-c** flag, **pdcrdflt**

- Sets the following server attributes to **true**:  
**accept-unsupported-jobs**  
**save-rip-files**
- Creates the default queue
- Sets the following queue attributes to **true**:  
**assign-to-printer**  
**requeue-failed-jobs**

If you have a server that has been configured for an advanced Infoprint installation and want to reconfigure it for a basic installation, do not use **pdcrdflt**. You must create the default queue and reset the attributes manually.

### Flags

The **pdcrdflt** utility uses the following flags:

- c** Configures the server for a basic installation. If you do not specify this flag, Infoprint configures the server for an advanced installation.

## Arguments

The argument value identifies the server to which the utility applies.

Valid argument values for the **pdcrdflt** utility are:

*ServerName*

Specifies the name of the server to configure. You must specify the name.

## Examples

- To create the default objects for a server with the name `srv1` in an advanced installation, enter:

```
pdcrdflt srv1
```

- To configure the server `charlie` for a basic installation and create the default objects, enter:

```
pdcrdflt -c charlie
```

## pdcrmed Utility: Creates Commonly Used Media in Infoprint Manager for AIX

### Syntax

**pdcrmed** *ServerName*

### Description

Issue the **pdcrmed** utility to create the large number of predefined medium objects. Use this utility after starting the server.

The utility creates these predefined medium objects:

A0	B7	jis-b6-white
A1	B8	jis-b7-white
A2	B9	jis-b8-white
A3-colored	B10	jis-b9-white
A4-colored	C4-envelope	jis-b10-white
A4-transparent	C5-envelope	letter-tab
A4-tab	a	manual
A5	b	monarch-envelope
A5-colored	c	na-legal-colored
A6	d	na-letter-colored
A7	designated-long-envelope	na-letter-transparent
A8	e	na-number-9-envelope
A9	executive	na-number-10-envelope
A10	folio	na-6x9-envelope
B0	invoice	na-7x9-envelope
B1	jis-b0-white	na-9x11-envelope
B2	jis-b1-white	na-9x12-envelope
B3	jis-b2-white	na-10x13-envelope
B4-colored	jis-b3-white	na-10x14-envelope
B4-envelope	jis-b4-colored	na-10x15-envelope
B5-colored	jis-b4-white	quarto
B5-envelope	jis-b5-colored	8x10.5
B6	jis-b5-white	

### Arguments

The argument value identifies the server to which the utility applies.

Valid argument values for the **pdcrmed** utility are:

*ServerName*

Specifies the name of the server on which to create the medium objects. You must specify the name.

### Example

To create the commonly used medium objects on a server with the name `srv1`, enter:

```
pdcrmed srv1
```

## pdinitports Utility: Initializes Ports

### Syntax

```
pdinitports [-n NumberOfPorts] MinimumPortNumber MaximumPortNumber]
```

```
pdinitports {-h | -?}
```

### Description

For Infoprint Manager for AIX, use the **pdinitports** utility to set up Infoprint to use a specific range or number of port numbers on this system for interprocess communication. By initializing a specific range of port numbers, you can avoid using port numbers that are used by or reserved for other programs.

#### Notes:

1. See the **/etc/services** file for reserved port numbers. Because Infoprint does not use the port numbers in **/etc/services**, you do not have to run this utility if all reserved port numbers are listed there.
2. Because Infoprint automatically initializes port numbers when it is started, you should not normally have to run this utility.
3. Before using this utility, you must shut down all the servers on this system.

For Infoprint Manager for Windows NT and Windows 2000, use the **pdinitports** utility to set up Infoprint to use a specific range or number of port numbers on this system for interprocess communication. By initializing a specific range of port numbers, you can avoid using port numbers that are used by or reserved for other programs.

#### Notes:

1. See the **/etc/services** file for reserved port numbers. Because Infoprint does not use the port numbers in **/etc/services**, you do not have to run this utility if all reserved port numbers are listed there.
2. Because Infoprint automatically initializes port numbers when it is started, you should not normally have to run this utility.
3. Before using this utility, you must shut down all the servers on this system.

### Flags

The **pdinitports** utility uses the following flags:

**-n** *NumberOfPorts*

Specifies that Infoprint is to find the first available block of *num-ports* port numbers and use them. If you do not specify either this flag or a range of port numbers, **pdinitports** finds and uses the first available block of 10 port numbers.

**-h** Displays help for the **pdinitports** utility.

**-?** Displays help for the **pdinitports** utility.

### Arguments

Valid argument values for the **pdinitports** utility are:

*MinimumPortNumber*

The minimum port number that the Infoprint will use on this system.

## pdinitports

### *MaximumPortNumber*

The maximum port number that the Infoprint will use on this system.

If you do not specify either a range of port numbers or the **-n** flag, **pdinitports** finds and uses the first available block of 10 port numbers.

## Examples

- To initialize Infoprint to use the first available range of 12 ports, enter:  
`pdinitports -n 12`
- To initialize Infoprint to use ports 6001 through 6010, enter:  
`pdinitports 6001 6010`



## pdmigpp Utility: Migrates Existing AIX Printers to Infoprint in Infoprint Manager for AIX

### Syntax

```
pdmigpp AIXPrintQueue ServerName DestinationName QueueName
```

### Description

Issue the **pdmigpp** utility to migrate an existing AIX print queue to an actual destination within Infoprint.

You can migrate printer devices currently configured for the AIX print system, for PSF for AIX, and for AIX remote queues that send jobs to another AIX processor or to any remote host connected to the network with TCP/IP.

This utility automatically selects the appropriate DSS, which the **device-support-system** actual destination attribute reflects. If the AIX print queue is a remote queue, Infoprint selects the BSD DSS. For PSF physical printers, the utility selects the appropriate attachment type, reflected by the **attachment-type** actual destination attribute. The corresponding Infoprint actual destination attributes, if they exist, reflect any values for the existing printer device.

After this utility has run successfully, an Infoprint actual destination that is equivalent to the AIX print queue exists in the specified server.

To run this utility ensure that:

- If you use DCE, you are logged into DCE with administrator authority
- You are logged onto the AIX processor on which the AIX print queue resides
- The Infoprint server whose name you specify is up and running

### Arguments

The argument value identifies the existing AIX virtual printer that the utility migrates to Infoprint as an actual destination within the specified server and its associated queue.

Valid argument values for the **pdmigpp** utility are:

*AIXPrintQueue*

The name of an existing AIX print queue that the utility migrates to Infoprint.

*ServerName*

Specifies the name of the server that will contain the actual destination the utility creates.

*DestinationName*

The name of the Infoprint actual destination that the utility creates.

*QueueName*

The name of the Infoprint queue that will provide jobs to the created actual destination.

### Example

To migrate the PSF for AIX print queue 1pd8 to actual destination PhyPtr3 on server Server2 with an associated queue of queue1, enter:

**pdmigpp**

pdmigpp 1pd8 Server2 PhyPtr3 queue1

---

## pdmincfg Utility: Sets up a Minimum Infoprint Configuration in Infoprint Manager for AIX

### Syntax

```
pdmincfg [-s] [ServerName]
```

### Description

Issue the **pdmincfg** utility to create a minimum Infoprint configuration.

This minimum configuration consists of one server, one logical destination, one queue, and one actual destination. You can use this minimum configuration to verify that Infoprint is properly installed and is operational. The **pdmincfg** utility creates a minimal configuration appropriate for a small Infoprint installation.

### Flags

The **pdmincfg** utility uses the following flag:

- s** Causes **pdmincfg** to start the specified server. If you do not specify this flag, but do specify the *ServerName*, Infoprint does not start the server. If you do not request Infoprint to start the server, Infoprint assumes it is already up and running.

### Arguments

The argument value identifies the specific object to which the utility applies.

Valid argument values for the **pdmincfg** utility are:

*ServerName*

Specifies the name of the server that runs in the minimum configuration. *ServerName* defaults to the hostname.

### Example

To set up a minimum configuration on a system with the server name of *serv1*, follow these steps:

1. Enter:

```
pdmincfg -s serv1
```

Infoprint displays the following:

```
Your server print database will be stored in /var/pd/serv1.  
Press enter to continue or press CTRL-C to cancel the request.
```

**Note:** Your **PDBASE** environment variable setting determines the directories where Infoprint stores your server print database.

2. Press Enter and the following displays:

**Note:** If the server does not exist, Infoprint prompts you after message 5010-467. Type **y** and press Enter to create the server.

```
5010-467 Starting server serv1.  
5010-406 Creating default objects. Please wait.  
5010-405 Successfully started server serv1.  
5010-470 Creating logical destination serv1-lp.  
5010-471 Creating queue serv1-q.  
5010-472 Enabling logical destination serv1-lp.
```

## pdmincfg

Enter 1 or 2 for the type of actual destination to be created:

- 1 = Test actual destination that does not actually print to a printer device
- 2 = Actual destination that uses your attributes file

3. You now have a choice of responses:

- To create a test actual destination to verify that Infoprint is properly installed, enter **1**.
- To create an actual destination that represents a real printer device, follow these steps:

a. Enter **2**.

Infoprint displays the following:

Enter the name of your destination attributes file:

- b. Enter the name of a file containing attributes that describe the destination you want to create. For example:

```
/usr/fred/attfiles/pp_tcpip.X
```

This example shows the full pathname of the file. If `/usr/fred/attfiles` is defined in your **PDPATH** environment variable, you can specify just the file name.

The file `pp_tcpip.X` contains information like this:

```
# TCP/IP-attached actual destination
destination-realization      =actual
attachment-type              =tcpip
destination-model            =Infoprint4000
destination-tcpip-internet-address=martha.boulder.ibm.com
destination-tcpip-port-number =5001
```

4. Infoprint displays the following:

```
5010-476 Creating actual destination serv1-pp.
5010-477 Enabling actual destination serv1-pp.
5010-462 Your minimum configuration is now active:
  Logical Destination: serv1-lp
      |
      v
  Queue: serv1-q
      |
      v
  Actual Destination: serv1-pp
```

5. To print a file named `test` on the actual destination you just created, enter:

```
pdpr -p serv1-lp test
```

## pdmsg Utility: Displays Information about a Message in Infoprint Manager for AIX

### Syntax

```
pdmsg [-d] [-t] MessageNumber
```

### Description

The **pdmsg** utility displays the text and description of an Infoprint message at the command line. The **pdmsg** utility extracts the text and description from the appropriate message catalogs. If you do not specify the **-d** or **-t** flag with the utility, Infoprint displays both the text and the message description.

### Flags

The **pdmsg** utility uses the following flags:

- d** Displays only the description of a message, which consists of a 7-digit message number, an explanation of the message, the system action, and the response.
- t** Displays only the text of a message, which consists of a 7-digit message number along with the actual words of the message itself. Underlined blanks in the text identify variable fields in the message text (also called message inserts). When Infoprint actually issues messages, Infoprint replaces the blanks with the appropriate variable information.

#### *MessageNumber*

The number of the Infoprint message you want displayed. Valid message numbers range from 0420-001 through 0423-999 and 5010-001 through 5010-999; however, not every number in these ranges has an associated message.

### Examples

- To view the text and description for Infoprint message 5010-096, enter:

```
pdmsg 5010-096
```

Infoprint displays the following:

```
5010-096 The value ____ is not supported for attribute ____.  
5010-096
```

```
EXPLANATION: The server or destination does not support this value.
```

```
SYSTEM ACTION: Infoprint could not process the request.
```

```
RESPONSE: Enter the command again and specify a value that is supported  
by the server and destination, or specify a destination that supports (by  
association) the value.
```

- To view only the text for Infoprint message 5010-096, enter:

```
pdmsg -t 5010-096
```

Infoprint displays the following:

```
5010-096 The value ____ is not valid not supported for attribute ____.
```

- To view only the description for Infoprint message 5010-096, enter:

```
pdmsg -d 5010-096
```

Infoprint displays the following:

## pdmsg

5010-096

EXPLANATION: The server or destination does not support this value.

SYSTEM ACTION: Infoprint could not process the request.

RESPONSE: Enter the command again and specify a value that is supported by the server and destination, or specify a destination that supports (by association) the value.

---

## rc.ipsap Utility: Start SAP Callback Daemons for Infoprint Manager for AIX

### Syntax

rc.ipsap

### Description

Use this utility to start the Infoprint Manager SAP callback daemons for each SAP system defined to use Infoprint Manager as an OMS (Output Management System). **/etc/inittab** invokes the **rc.ipsap** utility to automatically restart the Infoprint Manager SAP callback daemons listed in this file during reboot if you activate it through SMIT as follows:

```
Infoprint Printing System
  Utilities
    SAP Callback Daemon
```

**Note:** For specific information about a menu choice, press the **F1** key for help.

| As the administrator, you can edit the **/etc/rc.ipsap** file using a text editor, such as  
| vi. Edit this file to include a startcbd line for each SAP System setup to receive  
| callback notifications. See “startcbd Utility: Starts the SAP Callback Daemon” on  
| page 197 for more information.

---

## rc.pd Utility: Restarts Servers in Infoprint Manager for AIX

### Syntax

**rc.pd**

### Description

**/etc/inittab** (or a program called from **/etc/inittab**) invokes the **rc.pd** utility to automatically restart the Infoprint servers listed in **/etc/rc.pd.servers** during a reboot. As the administrator, you can edit the **rc.pd.servers** file using a text editor, such as **vi**. Edit this file to include a **startsrv** line for each server you want to start automatically.



## sense Utility: Senses Whether a Channel-Attached Printer is Attached to Infoprint Manager for AIX

### Syntax

```
sense SlotControlUnitAddress
```

### Description

The **sense** command senses whether a channel-attached printer device is attached to the RS/6000. If it is, the command returns a code of 81 in the sense bytes information, indicating that a connection exists.

**Note:** You must shut down the actual destination representing the printer device before issuing the **sense** command. If the actual destination is enabled, the results of the **sense** command will not be accurate.

### Arguments

*SlotControlUnitAddress*

The slot number (first one or two digits) and control unit address (last two digits, in hexadecimal) of the printer device you want to check. Enter any alphabetic hexadecimal characters in lowercase only.

### Messages and Return Codes

The **sense** utility returns the following messages and return codes:

- If you receive this message and return code:

```
printer connected at address 3af
00 00 00 81 00 00 00 00 00 00 00 00 00 00 00 00 00 00 00 00 00 00
```

the printer device is ready and correctly attached. You can print jobs on it.

- If you receive this message and return code:

```
printer connected at address 3AF
40 00 03 01 00 04 00 00 00 00 00 00 00 00 00 00 00 00 00 00 00 00
```

the printer device is correctly attached, but it is not ready to receive print jobs. Follow the instructions in the printer documentation to make the printer device ready at the printer's operator panel or console.

- If you receive this message:

```
printer not connected at address 3AF
```

the printer device is not attached correctly; or the printer device is not powered on. Check the printer and ensure that it is powered on and ready to accept print jobs. Verify that you entered the correct slot number and control unit address with the **sense** command. If the printer is powered on and you entered the correct information with the command, contact your IBM Printing Systems Company service representative.

- If you receive this message:

```
printer not defined at address 3AF
```

any of these things may be wrong:

- The printer is either not configured or not configured correctly.

## sense for AIX

- You did not shut down the actual destination before entering the **sense** command.
- The device driver for the printer at this address is missing or has not been loaded onto the S/370 Channel Emulator/A adapter. To load the driver, use the SMIT Miscellaneous Configuration panel.

## Example

To check the connection on a channel-attached printer attached to an S/370 Channel Emulator/A adapter in slot 3, with a hexadecimal control unit address of af, enter:

```
sense 3af
```

## sense Utility: Senses Whether a Channel-Attached Printer is Attached to Infoprint Manager for Windows NT and Windows 2000

### Syntax

```
sense [-f] [-s] slot_number control_unit_address
```

### Description

The **sense** command queries a channel-attached printer attached to the PC through the IBM 4159 S/390 Parallel Channel Emulator Card. The sense byte information is displayed.

**Note:** You must shut down the actual destination representing the printer device before issuing the **sense** command. If the actual destination is enabled, the results of the **sense** command will not be accurate.

### Arguments

**-f** All forms of channel sense data should be retrieved. The printer must be made ready for this to complete successfully.

**-s** Only basic channel sense data should be retrieved.

*slot\_number*

The PC slot that the channel card is installed in. The number is a value between 1 and 8. If you only have one channel card installed, the channel slot number is always 1.

*control\_unit\_address*

The channel control unit address as it is configured on the target channel-attached printer. The address is a hexadecimal value between 00 and FF.

**Note:** The **sense** command can only be issued using eight unique control unit addresses per channel card installed in the PC. Subsequent invocations of the **sense** command or activation of channel attached actual destinations with control unit addresses beyond the eighth unique address will result in an error. The system must be re-booted to allow a new set of eight control unit addresses. For example, if the one actual destination is active to a printer at channel address 34, then the **sense** command is issued seven times to control unit addresses 11 through 17. If the **sense** command is then issued to control unit address B1 or an actual destination is enabled to a printer at channel address B1, it will fail since the eight unique control unit addresses have been exhausted.

### Messages and Return Codes

The **sense** utility returns the following messages and return codes:

- If you receive this message:

The device type is: 3835-02

The sense response is: 0000008100000000000000000000000000000000000000000000000000000000

the printer device is ready and correctly attached. You can print jobs on it.

- If you receive this message and return code:

The device type is 3835-02

The sense response is: 4000030100040000000000000000000000000000000000000000000000000000

## sense for NT/2000

the printer device is correctly attached, but it is not ready to receive print jobs. Follow the instructions in the printer documentation to make the printer device ready at the printer's operator panel or console.

- If you receive this message:

There is no channel card in the specified slot

there is no S/390 Parallel channel card installed in the slot specified.

- If you receive this message:

No device is responding at Control Unit address 91

the channel cabling and termination are correctly attached, but no device is responding at the specified control unit address. Any of the following things may be wrong:

- The specified control unit address does not match the control unit address specified in the printer's configuration. Consult your printer documentation to identify the control unit address configured in your printer.
  - The channel attachment has not been enabled on the printer or the wrong channel attachment has been enabled on the printer.
  - If multiple channel cards are present in the Windows PC, the slot number does not match the channel card containing the printer at the specified control unit address.
- If you receive this message:  
The specified control unit is being used by another program

the actual destination for this printer was not shutdown before entering the **sense** command.

- If you receive this message:

A Channel Program Check occurred while issuing the *senseid*

or

An Interface Control Check occurred while issuing the *senseid*

it is likely that there is a channel cabling problem between the 4159 S/390 Parallel Channel Emulator Card and the printer.

**Note:** The term *senseid* in this message may be one of several nouns indicating that any of the following things may be wrong:

- The channel cable connectors have bent or broken pins.
- The channel cables are not properly terminated.
- The channel cables are not properly seated in the printer tailgate.
- The channel cables are oriented backwards.
- The channel cable configuration exceeds specifications.

## Example

To check the connection on a channel-attached printer attached to the 4159 S/390 Parallel Channel Emulator Card in slot 1, with a hexadecimal control unit address of af, enter:

```
c:\>sense 1 af
```

The message you receive is:



---

## setup Utility: Starts the Infoprint Installer in Infoprint Manager for AIX

### Syntax

```
setup -c [-e] [-R] [-s FileSystem]
```

```
setup -C [-e] [-L locale] -n ServerName -p PortNumber  
[-P DestinationName] [-R] [-s FileSystem]
```

```
setup -m [-a ResponseFile] [-e] [-q] [-R] [-s Filesystem]
```

```
setup -M [-a ResponseFile] [-e] [-q] [-R] [-s Filesystem] [-S]
```

### Description

Issue the **setup** utility to start the Infoprint Installer. The Infoprint Installer installs either the entire Infoprint Control component of Infoprint Manager, including an Infoprint server and an Infoprint AIX client, or the Infoprint AIX client alone.

The AIX client allows users to enter Infoprint commands on the command line for transmission to the Infoprint server, which may be on another AIX system. The AIX client has no graphical user interface.

#### Notes:

1. You can install the Infoprint server or Infoprint AIX client in any of the following languages:
  - English
  - French
  - German
  - Italian
  - Japanese
  - Spanish

If the Infoprint AIX client and server do not use the same language, the Infoprint server must run in English.

2. If you use Infoprint Manager DCE, and if the Infoprint AIX client and server are not in the same DCE namespace, the client can issue only the **pdpr**, **pdls**, and **pdq** commands.

### Flags

The **setup** utility uses the following flags:

**-a** Specifies a response file for use with an unattended installation. By default, unattended installations do not display any Installer screens. Further, when the **-a** flag is used, the default mount point is `/ip_remote`. All unattended installations must be performed using an Infoprint Manager Software Server, not the Infoprint Manager CD-ROMs.

**-c** Invokes the Infoprint Installer graphical user interface (GUI) to install only the Infoprint AIX client.

**Note:** The **-L**, **-n**, **-p**, and **-P** flags are not valid with this flag. The Infoprint Installer GUI will prompt you to specify the locale, server name, port number, and optional default logical destination.

**-C** Invokes the Infoprint Installer to install only the Infoprint AIX client using the command line, without invoking the Installer GUI.

**Note:** If you use this flag, you must specify the **-n** and **-p** flags.

**-e** Echoes the Installer log updates to **stdout** as they occur.

**-L** *locale*

Specifies the locale of the AIX client. The default is **en\_US** (U.S. English).

**Note:** This flag is not valid with the **-c** flag. It is optional with the **-C** flag.

**-m** Performs unattended installations on one or more remote systems. Before you can use this flag, you must create an Infoprint Manager Software Server on the local machine. After the software server is in place, you must copy response files to its `/ip_remote/auto` subdirectory to specify the which installations to complete. The default mount point for unattended installation is `/ip_remote`. The **-m** flag performs the specified installations concurrently.

**-M** Performs unattended installations like the **-m** flag, but the installations are performed serially. That is, an installation on the first system will complete before the installation on the second system begins.

**-n** *ServerName*

Specifies the name of the Infoprint server.

**Note:** This flag is not valid with the **-c** flag. It is required with the **-C** flag.

**-p** *PortNumber*

Specifies the port number that the remote Infoprint server is using for communications.

**Note:** This flag is not valid with the **-c** flag. It is required with the **-C** flag.

**-P** *DestinationName*

Specifies the default logical destination to which the Infoprint AIX client submits jobs.

**Note:** This flag is not valid with the **-c** flag. It is optional with the **-C** flag.

**-q** Displays the Installer screens during an unattended install.

**-R** Replaces any currently installed version of the Infoprint Installer on your AIX system with the Installer code from the Infoprint CD-ROMs.

**-s** *FileSystem*

Specifies the file system where the installable software images may be accessed. For example, you could specify the file system that you defined for installing Infoprint, or the drive where you mounted the Infoprint server CD-ROM. The default mount point for all installations that use the Installer GUI is `/cdrom`. The default mount point for all unattended installations is `/ip_remote`.

**Note:** The `/cdrom` file system may be predefined.

**-S** Saves the `.wlog` files from any prior installation. This flag is usually used with the **-M** flag to maintain a record of all installations performed on a machine as part of a serial sequence of unattended remote installations.

**-h** Displays help for the **setup** utility.

## Examples

- To install Infoprint in the file system `/cdrom`, follow these steps:
  1. Log onto AIX as **root**.

## setup

2. If available, insert the latest Infoprint Manager server APAR Service CD-ROM into the drive. Otherwise, insert the gold Infoprint Manager Server 1 CD-ROM into the drive.

3. If this is the first time you are running the Infoprint Installer on this system, create the **/cdrom** file system. Enter:

```
smit cdrfs
```

4. Select **Add a CDROM File System**.

5. Complete the **Add a CDROM File System** panel.

a. In the **DEVICE Name** field, enter the identifier of your CD-ROM drive. If you do not know the identifier, select **List** in the AIXwindows version of SMIT, or press **PF4** in the ASCII version of SMIT, to see a list of CD-ROM drives. Select one.

b. In the **MOUNT POINT** field, enter **/cdrom**.

c. Select **OK** (AIXwindows version) or press **Enter** (ASCII version).

d. Press **F10** to exit from SMIT.

6. To mount the CD-ROM, enter the following command on the AIX command line:

```
mount /cdrom
```

7. To read the **/readme.txt** file, enter:

```
dtpad /cdrom/readme.txt
```

8. Enter:

```
/cdrom/setup
```

- You want to install only a German-language Infoprint AIX client in the previously defined file system **/cdrom**, and to replace the previous version of the Infoprint Installer. The client will communicate with the English-language server **martha**, running on port number 6874. Because your AIX console does not support graphics, you cannot invoke the Infoprint Installer GUI. Follow these steps:

1. Log onto AIX as **root**.

2. Insert the gold Infoprint Manager Server 1 CD-ROM into the drive.

3. To mount the CD-ROM, enter:

```
mount /cdrom
```

4. Enter:

```
/cdrom/setup -C -L de_DE -n martha -p 6874 -R
```



---

## startppo Utility: Starts the Infoprint SMIT Production Print Operations Interface in Infoprint Manager for AIX

### Syntax

```
startppo [-t | -g width×depth+XOffset+YOffset]
```

```
startppo {-h | -?}
```

### Description

Issue the **startppo** utility to start the Infoprint SMIT production print operations interface.

### Flags

The **startppo** utility uses the following flags:

**-t** Starts the ASCII (**tt**) version of the Infoprint SMIT production print operations interface. The ASCII version of the Infoprint SMIT production print operations interface has no graphics and is controlled with the keyboard.

If you do not specify the **-t** flag, **startppo** starts the AIXWindows version of the Infoprint SMIT production print operations interface. The AIXWindows version displays a graphic of a running man to indicate task progress and can be controlled either with the mouse or with the keyboard.

**-g width×depth+XOffset+YOffset**  
Overrides the default size and position of the window for the AIXWindows version of the Infoprint SMIT production print operations interface.

**-h** Displays help for the **startppo** utility.

**-?** Displays help for the **startppo** utility.

### Examples

- To start the ASCII version of the Infoprint SMIT production print operations interface, enter:  
startppo -t
- To start the AIXWindows version of the Infoprint SMIT production print operations interface in an 800 by 500 window, enter:  
startppo -g 800×500+100+100

---

## start\_server Utility: Starts a Server for a Basic Infoprint Installation in Infoprint Manager for AIX

### Syntax

```
start_server [-l] locale [-p] port [ServerName]
```

```
start_server -?
```

### Description

Issue the **start\_server** utility to create or restart a server configured for a basic Infoprint installation. A server:

- Manages the validation, routing, and scheduling of jobs
- Manages the printing or transmission process
- Contains logical destinations, queues, and actual destinations

Three possible conditions can exist when you issue this utility:

- If the server name you specify with the utility (or the default server name) does not exist, Infoprint creates the server on the AIX processor from which you issue the utility and then starts the new server.
- If the server name does exist but is not currently running, Infoprint displays status information and issues a message when it has successfully restarted the server.
- If the server name does exist and it is currently running, Infoprint displays a message that shows the server is already operational.

**Note:** Use **start\_server** instead of **startsrv** when both these conditions are true:

- You want to configure the server for a basic Infoprint installation. **start\_server** always configures a new server for a basic installation, while **startsrv** defaults to an advanced installation.
- You do not want to be prompted for confirmation if the server does not already exist. **start\_server** never prompts, while **startsrv** prompts by default.

### Flags

The **start\_server** utility uses the following flags:

**-l** *locale*

Allows you to specify the locale for Infoprint messages in a specific language. If you do not specify this flag, the default is your current locale.

**-p** *port* Allows you to specify the port number when starting a server in a locale other than the default locale. The port number you assign must not conflict with port numbers in use by other processes. The file **/etc/services** lists the port numbers reserved by other processes.

If you do not specify this flag, the port defaults to the value of the **PD\_SOCKET** environment variable, if any, then to 6874.

**Note:** When selecting your own port number, always increment the choice by two because the Infoprint server uses two numbers: the one you specify and the next one, for example, 6874 and 6875.

**-?** Displays help for the **start\_server** utility.

## Arguments

The argument value identifies the specific object to which the utility applies.

The valid argument value for the **start\_server** utility is:

*ServerName*

Assigns a name to a new server or specifies the name of the server to restart. *ServerName* defaults to the hostname.

## Examples

- To create a server with the same name as the host and configure it for a basic installation, enter:

```
start_server
```

- To restart serv1, enter:

```
start_server serv1
```

---

## startsrv Utility: Starts a Server in Infoprint Manager for AIX

### Syntax

```
startsrv [-c] [-F] [-I] locale [-p] port [ServerName]
```

```
startsrv -?
```

### Description

Issue the **startsrv** utility to create or restart a server. A server:

- Manages the validation, routing, and scheduling of jobs
- Manages the printing or transmission process
- Contains logical destinations, queues, and actual destinations

The following conditions can exist when you issue this utility:

- If the server name you specify with the utility (or the default server name), does not exist, and if you do not specify the **-F** flag, Infoprint displays a confirmation message asking if you want to create a new server. If your response is yes, Infoprint creates the server on the AIX processor from which you issue the utility and then starts the new server.
- If the server name does not exist, and if you specify the **-F** flag, Infoprint creates the server on the AIX processor from which you issue the utility without asking for confirmation and then starts the new server.
- If the server name does exist but is not currently running, Infoprint displays status information and issues a message when it has successfully restarted the server.
- If the server name does exist and it is currently running, Infoprint displays a message that shows the server is already operational.

**Note:** Use **startsrv** instead of **start\_server** when either of these conditions is true:

- You want to configure the server for an advanced Infoprint installation. **startsrv** configures a new server for an advanced installation by default, while **start\_server** always configures a new server for a basic installation.
- You want to be prompted for confirmation if the server does not already exist. **startsrv** prompts by default, while **start\_server** never prompts.

### Flags

The **startsrv** utility uses the following flags:

- c** Configures a new server for a basic Infoprint installation. If you do not specify this flag, Infoprint configures the server for an advanced installation. This flag has no effect on an existing server.
- F** Forces creation of the server if it does not already exist. Infoprint does not display confirmation prompts (if any).  
  
If you do not specify this flag and if the server does not already exist, Infoprint prompts you to confirm whether to create the server.
- I *locale*** Allows you to specify the locale for Infoprint messages in a specific language. If you do not specify this flag, the default is your current locale.
- p *port*** Allows you to specify the port number when starting a server in a locale other than the default locale. The port number you assign must not conflict

with port numbers in use by other processes. The file **/etc/services** lists the port numbers reserved by other processes.

If you do not specify this flag, the port defaults to the value of the **PD\_SOCKET** environment variable, if any, then to 6874.

**Note:** When selecting your own port number, always increment the choice by two because the Infoprint server uses two numbers: the one you specify and the next one, for example, 6874 and 6875.

-? Displays help for the **startsrv** utility.

## Arguments

The argument value identifies the specific object to which the utility applies.

The valid argument value for the **startsrv** utility is:

*ServerName*

Assigns a name to a new server or specifies the name of the server to restart. *ServerName* defaults to the hostname.

## Examples

- To create a server with the name `serv1` and configure it for an advanced installation, enter:  
`startsrv -F serv1`
- To create a server with the same name as the host and configure it for a basic installation, enter:  
`startsrv -c -F`
- To restart `serv1`, enter:  
`startsrv serv1`

---

## stop\_server Utility: Shuts Down a Server in Infoprint Manager for AIX

### Syntax

```
stop_server [-F] [ServerName]
```

```
stop_server -?
```

### Description

Issue the **stop\_server** utility to shut down a server.

### Flags

The **stop\_server** utility uses the following flags:

- F Forces the server to shut down as soon as possible. If you do not specify this flag, the server shuts down when all currently printing jobs have finished printing.
- ? Displays help for the **stop\_server** utility.

### Arguments

The argument value identifies the specific object to which the utility applies.

The valid argument value for the **stop\_server** utility is:

*ServerName*

Specifies the name of the server to shut down. *ServerName* defaults to the hostname.

### Examples

- To shut down a server with the same name as the host as soon as possible, enter:  

```
stop_server -F
```
- To shut down serv1 after all currently printing jobs have finished printing, enter:  

```
stop_server serv1
```
- To shut down the server DeServ, which is running in the locale De\_DE, enter:  

```
export LC_ALL=De_DE  
stop_server DeServ  
export LC_ALL=
```

## tdump Utility: Outputs Tape Contents in Human-Readable Format in Infoprint Manager for AIX

### Syntax

```
tdump [-a] [-b] [-c] [-n number] [-o OutputFile] [-s {b | f}]
      -t {rmtm | rmtm.n}
```

### Description

Use the **tdump** utility to output the contents of a tape in a human-readable format. You can format the output to display in hexadecimal or octal (with a readable character above each byte), dump by file or block, determine the size of a file on tape, or determine the largest block in a file.

You can examine the output from this utility to determine such information as:

- The format of the tape
- What type of data is on the tape
- The maximum block size
- Label information for IBM standard labeled and nonstandard labeled tapes
- Error diagnosis for damaged or incorrectly created tapes

**tdump** works from the place where the tape is positioned. If you need to dump the third file on a tape, you must position the tape with the AIX **tctl** command or the Infoprint SMIT production printing system interface Position A Tape panel to the beginning of the third file and then invoke **tdump**.

### Flags

The **tdump** utility uses the following flags:

- a      Input is in ASCII. If this flag is not specified, EBCDIC is used.
- b      Dump by block. If this flag is not specified, file is used.
- c      Dump bytes in octal format. If this flag is not specified, hexadecimal is used.
- n *number*  
      Number of files or blocks to dump. If this flag is not specified, 1 is used.
- o *OutputFile*  
      Output file. If this flag is not specified, **stdout** is used.
- s {**b** | **f**}  
      Reports largest block size in the file (**b**) or the number of bytes in the file (**f**). Suppresses dump.
- t *tdrive*  
      Name of the tape drive containing the tape, of the form **rmtm** or **rmtm.n**, where *m* is a non-negative integer and *n* is from 1 to 7, inclusive

### Examples

- To dump two files in hexadecimal to **stdout** from the current position of the tape in drive rmt0, enter:  
tdump -t rmt0 -n 2
- To display the largest block in the file from the current position of the tape in drive rmt2, enter:

## **tdump**

```
tdump -s b -t rmt2
```

- To instruct **tdump** to interpret the tape as ASCII and write the bytes in octal for the next three blocks on the tape in drive rmt0 into outfile, enter:

```
tdump -t rmt0 -n 3 -b -a -c -o outfile
```



---

## tlist Utility: Lists Files on a Tape in Infoprint Manager for AIX

### Syntax

```
tlist -t {rmtm | rmtm.n}
```

### Description

For IBM standard labeled tapes, use the **tlist** utility to display the name and file characteristics (record format, record length, and block size) of each file on a tape. For nonstandard or unlabeled tapes, the **tlist** utility displays the number of files on a tape.

You can use the **tlist** utility to create a list of file names to use as arguments for the **pdpr** command.

### Flags

The **tlist** utility uses the following flags:

**-t** *tdrive*

Name of the tape drive containing the tape, of the form **rmtm** or **rmtm.n**, where *m* is a non-negative integer and *n* is from 1 to 7, inclusive

### Examples

- To display the names of all files on an IBM standard labeled tape for the tape in tape drive rmt2, enter:  

```
tlist -t rmt2
```
- To count the number of files on a non-standard or unlabeled tape for the tape in tape drive rmt0, enter:  

```
tlist -t rmt0
```

## t2file Utility: Reads MVS Partitioned Data Sets from Tape in Infoprint Manager for AIX

### Syntax

```
t2file [-d directory] [-m member ...] -t {rmtm | rmtm.n} [-s]
```

### Description

Use the **t2file** utility to read MVS partitioned data sets from IBM standard labeled tapes created with the MVS **IEBCOPY** program and to break them apart into individual files on AIX.

The typical application for this program is to break apart host resource libraries that have been dumped to tape into individual files, as IBM Infoprint Control requires.

### Flags

The **t2file** utility uses the following flags:

**-d** *directory*

Directory where files should be written. If this flag is not specified, the files are written to the current directory.

**-m** *member ...*

Specific members to read from the MVS partitioned data set. If this flag is not specified, all members are read.

**Note:** You must specify all the file names with one use of the **-m** option. To specify one name, use **t2file -m *memname***. To specify multiple names, use **t2file -m '*mem1 mem2 mem3*'**. If you have multiple **-m** options, **t2file** does not concatenate them together. It uses the last occurrence of **-m** on the command line.

**-t** *tdrive*

Name of the tape drive containing the tape, of the form **rmt*m*** or **rmt*m.n***, where *m* is a non-negative integer and *n* is from 1 to 7, inclusive.

**-s** Unload only one MVS partitioned data set. If this flag is not specified, all partitioned data sets are read.

### Examples

- To designate specific members to read from the MVS partitioned data set, enter:  

```
t2file -m 'mem1 mem2 mem3' -t rmt3
```
- To unload only one MVS partitioned data set from tape drive rmt2 into the current directory and then end the program, position the tape at the beginning of the header label before the partitioned data set with the AIX **tctl** command on the Infoprint SMIT production printing system interface Position A Tape panel and enter:  

```
t2file -t rmt2 -s
```
- To unload all the members from all the partitioned data sets on the tape in the drive rmt0 into /home/custom/resources, enter:  

```
t2file -t rmt0 -d /home/custom/resources
```

---

## Chapter 5. Daemon Utilities for Infoprint Manager for AIX

This chapter describes the following Infoprint daemon utilities:

- “mvsprsd Utility: Starts the mvsprsd Daemon” on page 186
- “pcl2afpd Utility: Starts the pcl2afpd Daemon” on page 188
- “ps2afpd Utility: Starts the ps2afpd Daemon” on page 191
- “startnotd Utility: Starts the notifyd Daemon” on page 195
- “stopnotd Utility: Stops the notifyd Daemon” on page 196
- “startcbd Utility: Starts the SAP Callback Daemon” on page 197
- “stopcbd Utility: Stops the SAP Callback Daemon” on page 199

---

## mvsprsd Utility: Starts the mvsprsd Daemon

### Syntax

```
mvsprsd -pPortNumber -d FileSystem [-d FileSystem ...] [-x ShellScript]
      [-q destination] [-k]
```

### Description

Use the **mvsprsd** daemon to start the **mvsprsd** daemon. This daemon receives the data that MVS Download transmits from the Job Entry Subsystem (JES) spool on an MVS system for printing.

You can specify that the **mvsprsd** daemon starts whenever the system starts by including the **mvsprsd** command in one of the files that are executed when the AIX operating system is initialized. The two types of files that are read during AIX initialization are **/etc/rc** files and the **/etc/inittab** file.

If the **mvsprsd** daemon stops running for some reason, you can restart it by issuing the following command:

```
/usr/lpp/psf/bin/mvsprsd -p PortNumber -d FileSystem -x ShellScript
      -q destination -k
```

If your job does not print on IBM Infoprint Control, you might be able to restart the shell script process with the downloaded file and downloaded print-options string. If you specified the **-k** flag on the print command, you can use the following command to restart the shell script with its required parameter list:

```
/usr/lpp/pd/bin/mvsprpsm.sh FileName.PRD "$(cat string.JCL)" destination
```

where **FileName.PRD** represents the file successfully downloaded to IBM Infoprint Control as

**MVS\_system\_name.jobname.dataset\_name.forms\_name.yyyyddd.hhmmsstABCD.PRD**;

and where **string.JCL** represents the MVS print options string that is saved to a file named in the following format:

**MVS\_system\_name.jobname.dataset\_name.forms\_name.yyyyddd.hhmmsstABCD.JCL**.

Note that the string **/usr/lpp/pd/bin/mvsprpsm.sh...** refers to the shell script that is provided with this command. Check to see that your installation has not modified this shell script or added another shell script before specifying this value.

### Flags

The **mvsprsd** daemon utility uses the following flags:

**-p** *PortNumber*

Specifies the socket port number for the daemon in the valid range (5001-64000). Do not use 8251 and 8253, which are used by Infoprint for the PCL and PostScript data transforms. The port number must be the same as the port number specified in the routing-control data set used by MVS Download.

**-d** *FileSystem*

Specifies a file system where Infoprint stores the received file until the shell script you specify in the **-x** flag processes and deletes the file. The **mvsprsd** daemon must have write permission for the file system.

You must specify at least one file system. You can specify up to ten file systems. If you specify more than one file system, the file system having the most available space is used. To specify more than one file system, specify the entire flag again:

```
-d FileSystem1 -d FileSystem2 ...
```

**-x ShellScript**

Specifies the complete path name and file name for the shell script that the daemon executes to process the files sent by MVS Download. You can specify the file name of the shell script without the path name and it will default to the **/usr/lpp/pd/bin** path.

The daemon forks a child process to execute the shell script after each successfully received file. If you do not specify the path name of a shell script, the received files are not printed and remain on the file system.

Infoprint provides a shell script, **mvsprpsm.sh**, which submits a file to the **pdpr** command for printing and deletes the file if the file prints successfully. This shell script is installed in the **/usr/lpp/pd/bin** directory.

**-q destinationname**

Specifies the name of the logical destination to which the shell script can submit the file. If you specify a logical destination, you should also specify the name of a shell script on the **-x** flag that the program uses to submit files to the logical destination.

If you specify this shell script on the **-x** flag, you must specify the **-q** flag or **mvsprsd** displays its command syntax and exits.

If you do not specify a logical destination name, the received files are not printed and remain on the file system.

**-k** Specifies that the MVS print-options string is kept on the file system and can be used later for error recovery. If a file is transferred from MVS to AIX successfully, but does not print because of a problem, IBM recommends that you specify this option so that the job can be resubmitted for printing from the AIX operating system.

## Examples

1. To start an MVS Download daemon that stores files received from the JES spool on the **/files1** or **/files2** file system and executes the **mvsprpsm.sh** shell script, which submits the files to the **serv2-lp** logical destination, enter:

```
mvsprsd -p 5400 -d /files1 -d /files2 -x mvsprpsm.sh -q serv2-lp
```

2. To have the same MVS Download daemon keep the MVS print-options string file(s), enter:

```
mvsprsd -p5400 -d/files1 -d/files2 -qserv2-lp -k
```

**Note:** Anyone can start the **mvsprsd** daemon, but only someone with **root** authority can stop it.

## Suggested Reading

- *PSF/MVS: MVS Download Guide*
- The man pages for the **rc** command and the **inittab** file

---

## pcl2afpd Utility: Starts the pcl2afpd Daemon

### Syntax

**pcl2afpd** [-C *ConfigurationFile*]

### Description

Use the **pcl2afpd** utility to start the **pcl2afpd** daemon. The **pcl2afpd** daemon manages the PCL interpreter portion of the Infoprint PCL transform program. You must start the **pcl2afpd** daemon somewhere on the network before you can use the **pcl2afp** transform command to transform PCL data streams for printing or transmission with Infoprint.

The **startsrv** or **start\_server** utility automatically starts the **pcl2afpd** daemon if it is installed and not running.

If the **pcl2afpd** daemon stops running, you can restart it by issuing the following command:

```
/usr/lpp/psf/bin/pcl2afpd
```

Infoprint uses the **pcl2afpd** daemon configuration file to determine the default parameters of the **pcl2afpd** daemon. The **/usr/lpp/psf/pcl2afp/pcl2afpd.cfg** file is installed with Infoprint, and Infoprint uses it as the default configuration file. You can, however, copy the configuration file, use an AIX editor to edit the copy of the file, and rename it so that you can customize the **pcl2afpd** daemon for your applications. After you make the modifications, you specify the new configuration file with the **-C** flag of the **pcl2afpd** daemon utility.

**Note:** If you create your own configuration file, you must specify it with the **-C** flag of the **pcl2afp** transform command when you transform PCL files.

### Flags

The **pcl2afpd** daemon utility uses the following flag:

**-C** *ConfigurationFile*

Specifies the configuration file Infoprint uses with the transform. The value is:

*ConfigurationFile*

A valid PCL configuration file name. If you do not specify a file, Infoprint uses the file **/usr/lpp/psf/pcl2afp/pcl2afpd.cfg**.

### Configuration File Keywords and Values

The **pcl2afpd.cfg** file contains the same keywords as the **pcl2afp.cfg** file except that the transform daemon configuration file does not have the **server** keyword. The **pcl2afpd.cfg** contains several additional keywords.

For the keywords common to both configuration files, see “The pcl2afp and pcl2afpd Configuration Files” on page 273.

The PCL transform daemon configuration file can also contain the following keywords:

**log\_file**={*WorkDirectory*/**pcl2afpd.log** | *PathName*}

Specifies the file in which the transform daemon logs errors and messages when it converts a data stream from PCL to an AFP data stream.

Valid keyword values are:

**WorkDirectory/pcl2afpd.log**

This is the default log file, where *WorkDirectory* is the value of the **work\_directory** keyword. The default work directory is **/var/psf/pcl2afp**.

*PathName*

The full path name of a log file

**mail\_command**={**/usr/bin/mail** | *PathName*}

Specifies the executable file that the **pcl2afp** command uses to send transform status notifications.

Valid keyword values are:

**/usr/bin/mail**

The AIX **mail** command

*PathName*

The full path name of a communication program

**notify**={**root** | *UserID*}

Identifies the user to receive notification about problems encountered during transformation of the PCL file into an AFP data stream file. If a particular user runs most of the PCL transform jobs, you might want to send notifications to that person using this keyword.

Valid keyword values are:

**root** The user at the server console

*UserID*

An AIX user ID

**pcl\_program**={**/usr/lpp/psf/bin/ppxpcli** | *PathName*}

Specifies which PCL-to-AFP transform program (the PCL interpreter) to run. Generally, you will not change this value.

Valid keyword values are:

**/usr/lpp/psf/bin/ppxpcli**

The default PCL interpreter

*PathName*

The full path name of a PCL interpreter file

**pcl\_support\_prog**={**/usr/lpp/psf/bin/ppxpclis** | *PathName*}

Specifies which PCL-to-AFP transform support program to run. Generally, you will not change this value. Values are:

**/usr/lpp/psf/bin/ppxpclis**

The default PCL support program

*PathName*

The full path name of a PCL support program

**work\_directory**={**/var/psf/pcl2afp** | *PathName*}

Specifies the path to the directory where the transform daemon puts its work files. The transform daemon must have read, write, and execute

## pcl2afpd

permissions to this directory. The transform daemon is owned by the **root** user, but runs as **daemon**, and is in the **printq** group.

Values are:

### /var/psf/pcl2afp

The default work directory

### *PathName*

A directory path

## Examples

- To restart the **pcl2afpd** daemon with the default configuration file, enter:

```
pcl2afpd
```

### **Notes:**

1. If you have not set the **PATH** environment variable to include **/usr/lpp/psf/bin**, you must enter the path name with the **pcl2afpd** daemon.
  2. Anyone can start the **pcl2afpd** daemon, but only a person with **root** user authority can stop it.
- To restart the **pcl2afpd** daemon with the configuration file `myfile.cfg`, which resides in the directory `/usr/lpp/psf/pcl2afp`, enter:  

```
pcl2afpd -C /usr/lpp/psf/pcl2afp/myfile.cfg
```

## Files

### **/usr/lpp/psf/bin/pcl2afpd**

Transform daemon

### **/usr/lpp/psf/pcl2afp/pcl2afpd.cfg**

**pcl2afpd** daemon configuration file

### **/usr/lpp/psf/bin/ppxpcli**

PCL interpreter program

### **/usr/lpp/psf/bin/ppxpclis**

PCL interpreter support program



## ps2afpd Utility: Starts the ps2afpd Daemon

### Syntax

```
ps2afpd [-C ConfigurationFile]
```

### Description

Use the **ps2afpd** utility to start the **ps2afpd** daemon. The **ps2afpd** daemon manages the interpreter portion of the Infoprint PostScript and PDF transform programs. You must start the **ps2afpd** daemon somewhere on the network before you can use the **ps2afp** or **pdf2afp** transform command to transform PostScript or PDF data streams for printing with Infoprint on IPDS printers.

The **startsrv** or **start\_server** utility automatically starts the **ps2afpd** daemon if it is installed and not running.

If the **ps2afpd** daemon stops running, you can restart it by issuing the following command:

```
/usr/lpp/psf/bin/ps2afpd
```

Infoprint uses the **ps2afpd** daemon configuration file to determine the default parameters of the **ps2afpd** daemon. The **/usr/lpp/psf/ps2afp/ps2afpd.cfg** file is installed with Infoprint, and Infoprint uses it as the default configuration file. You can, however, copy the configuration file, use an AIX editor to edit the copy of the file, and rename it so that you can customize the **ps2afpd** daemon for your applications. After you make the modifications, you specify the new configuration file with the **-C:** flag of the **ps2afpd** daemon utility.

**Note:** If you create your own configuration file, you must specify it with the **-C** flag of the **ps2afp** transform command when you transform PostScript or PDF files.

### Flags

The **ps2afpd** daemon utility uses the following flag:

**-C** *ConfigurationFile*

Specifies the configuration file Infoprint uses with the transform. The value is:

*ConfigurationFile*

A valid PostScript configuration file name. If you do not specify a file, Infoprint uses the file **/usr/lpp/psf/ps2afp/ps2afpd.cfg**.

### Configuration File Keywords and Values

The **ps2afpd.cfg** file contains the same keywords as the **ps2afp.cfg** file except that the transform daemon configuration file does not have the **server** keyword. The **ps2afpd.cfg** contains several additional keywords.

For the keywords common to both configuration files, see “The ps2afp and ps2afpd Configuration Files” on page 294.

The PostScript transform daemon configuration file can also contain the following keywords:

## ps2afpd

**log\_file**={*WorkDirectory*/**pcl2afpd.log** | *PathName*}

Specifies the file in which the transform daemon logs errors and messages when it converts a data stream from PostScript or PDF to an AFP data stream.

Valid keyword values are:

*WorkDirectory*/**ps2afpd.log**

This is the default log file, where *WorkDirectory* is the value of the **work\_directory** keyword. The default work directory is **/var/psf/ps2afp**.

*PathName*

The full path name of a log file

**mail\_command**={*/usr/bin/mail* | *PathName*}

Specifies the executable file that the **pcl2afp** command uses to send transform status notifications.

Valid keyword values are:

**/usr/bin/mail**

The AIX **mail** command

*PathName*

The full path name of a communication program

**notify**={**root** | *UserID*}

Identifies the user to receive notification about problems encountered during transformation of the PostScript or PDF file into an AFP data stream file. If a particular user runs most of the PostScript and PDF transform jobs, you might want to send notifications to that person using this keyword.

Valid keyword values are:

**root** The user at the server console

*UserID*

An AIX user ID

**ps\_program**={*/usr/lpp/psf/bin/ppxps2i* | *PathName*}

Specifies which Postscript-or-PDF-to-AFP transform program (the PostScript interpreter) to run. Generally, you will not change this value. If you do change it, you must change the value of the **ps\_init\_file** keyword to specify an initialization file at the same level.

Valid keyword values are:

**/usr/lpp/psf/bin/ppxps2i**

The PostScript Level 2 transform

*PathName*

The full path name of a PostScript interpreter file

**ps\_init\_file**={*/usr/lpp/psf/ps2afp/ppxps2.ps* | *PathName*}

Specifies the PostScript initialization program to use with the PostScript interpreter. This file specifies the types of messages that the PostScript interpreter reports. Generally, you will not change this value. If you do change it, you must change the value of the **ps\_program** keyword to specify a PostScript interpreter at the same level.

Valid keyword values are:

**/usr/lpp/psf/ps2afp/ppxps2.ps**

The PostScript Level 2 initialization file

*PathName*

The full path name of an initialization file

**work\_directory={/var/psf/ps2afp | *PathName*}**

Specifies the path to the directory where the transform daemon puts its work files. The transform daemon must have read, write, and execute permissions to this directory. The transform daemon is owned by the **root** user, but runs as **daemon**, and is in the **printq** group.

Values are:

**/var/psf/ps2afp**

The default work directory

*PathName*

A directory path

## Examples

- To restart the **ps2afpd** daemon with the default configuration file, enter:

```
ps2afpd
```

**Notes:**

- If you have not set the **PATH** environment variable to include **/usr/lpp/psf/bin**, you must enter the path name with the **ps2afpd** daemon.
  - Anyone can start the **ps2afpd** daemon, but only a person with **root** user authority can stop it.
- To restart the **ps2afpd** daemon with the configuration file `myfile.cfg`, which resides in the directory `/usr/lpp/psf/ps2afp`, enter:

```
ps2afpd -C /usr/lpp/psf/ps2afp/myfile.cfg
```

## Files

**/usr/lpp/psf/bin/ps2afpd**

PostScript daemon

**/usr/lpp/psf/bin/ps2afp**

PostScript transform executable

**/usr/lpp/psf/bin/pdf2afp**

PDF transform executable (linked to **/usr/lpp/psf/bin/ps2afp**)

**/usr/lpp/psf/ps2afp/ps2afpd.cfg**

**ps2afpd** daemon configuration file

**/usr/lpp/psf/ps2afp/ps2afp.cfg**

**ps2afp** command configuration file

**/usr/lpp/psf/bin/ppxps2i**

PostScript level 2 interpreter program

**/usr/lpp/psf/bin/ps2afpi**

PostScript Level 1 interpreter program

**/usr/lpp/psf/bin/ps2afpi.vm**

PostScript interpreter program initial virtual memory

**/usr/lpp/psf/ps2afp/ppxps2.ps**

PostScript level 2 initialization file

**/usr/lpp/psf/ps2afp/ps2afp.ps**

PostScript Level 1 initialization file

**/usr/lpp/psf/ps2afp/ps2afpe.ps**

PostScript Level 1 initialization file for extended error reporting

**/usr/lpp/psf/bin/fontsave**

PostScript executable for saving fonts

## **ps2afpd**

**/usr/lpp/psf/ps2afp/psfonts.map**  
Default PostScript font mapping file

**/var/psf/psfonts**  
User-defined PostScript fonts file

---

## startnotd Utility: Starts the notifyd Daemon

### Syntax

**startnotd**

### Description

Use the **startnotd** utility to start the **notifyd** daemon. The **notifyd** daemon receives and stores notification messages for all users requesting notification by deliver-method message. Only one notification daemon needs to be running for each Infoprint Manager cell or domain; one notification daemon receives notifications from and services all Infoprint Manager servers sharing the same name space.

With Infoprint Manager for AIX, you can specify that the **notifyd** daemon starts whenever the system starts or is rebooted by using the Infoprint Manager SMIT panels on AIX.

The **notifyd** daemon has a monitor that will restart it if it ever stops running. If you want to stop it, to move it to another machine for example, use the “stopnotd Utility: Stops the notifyd Daemon” on page 196.

**stopnotd**

---

## **stopnotd Utility: Stops the notifyd Daemon**

### **Syntax**

**stopnotd**

### **Description**

Use the **stopnotd** utility to stop the **notifyd** daemon and its monitor.

If you want to start the **notifyd**, see “startnotd Utility: Starts the notifyd Daemon” on page 195.

## startcbd Utility: Starts the SAP Callback Daemon

### Syntax

```
startcbd SystemName HostName InstanceID User Client Password Language[31h ]
```

### Description

Use the **startcbd** utility to start a **sapcbd** daemon. The **sapcbd** or SAP Callback daemon logs onto an SAP system and delivers notifications from Infoprint Manager servers to the SAP system. You should start only one **sapcbd** for each SAP system for which you have configured Infoprint Manager as an Output Management System (OMS). All SAP instances sharing the same database form one SAP system.

See “rc.ipsap Utility: Start SAP Callback Daemons for Infoprint Manager for AIX” on page 165 for information on having SAP Callback daemons start on system reboot.

Each **sapcbd** daemon has a monitor that will restart if it stops for some reason. If you want to stop it, to move it to another machine for example, use the “stopcbd Utility: Stops the SAP Callback Daemon” on page 199.

### Arguments

The **startcbd** utility uses the following arguments:

*SystemName*

Specifies the three character SAP system name.

*HostName*

Specifies the name of the host where you want the SAP Callback daemon to log onto the SAP system.

*InstanceID*

Specifies the SAP Instance ID you want the SAP Callback daemon to log onto.

*User*

Specifies the userid defined for the SAP Callback daemon to log on with. This needs to be a userid of CPIC type with XOMI permissions.

*Client*

Specifies the SAP client for the SAP Callback daemon to log onto.

*Password*

Specifies the password for the SAP Callback daemon to log on with.

*Language*

Specifies the language for the SAP Callback daemon to log on with.

*31h*

An extra argument to specify that the SAP Callback daemon is for a 3.1h or 3.1i system.

### Examples

- To start the **startcbd** daemon to support SAP Release 4 System TST after you have:
  - Configured Infoprint Manager as an OMS in TST
  - Created a CPIC user for the **sapcbd** daemon
  - Identified which instance and client you want the **startcbd** to log onto

Then you would enter:

```
startcbd TST ibmbtt15 15 ibm 030 ipmpass EN
```

## **startcbd**

- To start the **startcbd** daemon to support SAP Release 3.1 System TST after you have:
  - Configured Infoprint Manager as an OMS in TST
  - Created a CPIC user for the **sapcbd** daemon
  - Identified which instance and client you want the **startcbd** to log onto

Then you would enter:

```
startcbd TST ibmbtt15 15 ibm 030 ipmpass EN 31h
```



---

## stopcbd Utility: Stops the SAP Callback Daemon

### Syntax

```
stopcbd SAPSystemName
```

### Description

Use the **stopcbd** utility to stop the **sapcbd** daemon or SAP Callback daemon for an SAP system and stop its monitor.

### Arguments

The **stopcbd** utility uses the following argument:

*SAPSystemName*

Specifies the three character ID of the SAP system that the **sapcbd** daemon is supporting. This is the specific **sapcbd** daemon to stop.

### Examples

To stop or shutdown the **sapcbd** daemon for SAP System PRD, enter:

```
stopcbd PRD
```

**stopcbd**

## Chapter 6. Infoprint Transform Commands

This chapter describes the following Infoprint transform commands:

Transform Name	AIX	NT and 2000
"db2afp Command: Transforms DBCS Data to AFP" on page 202	AIX	NT and 2000
"d2afp Command: Transforms ditroff Data to AFP in Infoprint Manager for AIX" on page 206	AIX	N/A
"gif2afp Command: Transforms GIF Data to AFP in Infoprint Manager for AIX" on page 209	AIX	N/A
"jpeg2afp Command: Transforms JPEG Data to AFP in Infoprint Manager for AIX" on page 223	AIX	N/A
"line2afp Command: Transforms S/370 Line Data and ASCII Data to AFP" on page 236	AIX	NT and 2000
"pcl2afp Command: Transforms PCL Data to AFP" on page 261	AIX	NT and 2000
"pdf2afp and ps2afp Transforms: Transform PDF or PostScript Data to AFP" on page 284	AIX	NT and 2000
"sap2afp Command: Transforms SAP OTF or ABAP Data to AFP in Infoprint Manager for AIX" on page 299	AIX	N/A
"tiff2afp Command: Transforms TIFF Data to AFP in Infoprint Manager for AIX" on page 310	AIX	N/A

**Note:** Infoprint invokes the appropriate transform automatically whenever you print a DBCS ASCII, DBCS EUC, ditroff, GIF, JPEG, line data, PCL, PDF, PostScript, SAP, or TIFF job on a PSF physical printer. You can pass options to these transforms using the **other-transform-options** document attribute on the Infoprint **pdpr** command or the **-o** flag of the AIX print commands (**enq**, **lp**, and **qprt**) and the Infoprint **lprafp** command.

For more information, see "Attributes for Documents and Default Documents" on page 449, "pdpr Command: Submits Jobs" on page 63, "lprafp Command: Submits Remote Jobs in Infoprint Manager for AIX" on page 15, or "Chapter 3. The -o Flag for AIX Print Commands" on page 103.

## db2afp Command: Transforms DBCS Data to AFP

### Syntax

```
db2afp [-o -OutputFile] [-l {ja | ch | ko}] [-e] [InputFile]
```

### Description

Use the **db2afp** command to transform either a DBCS ASCII or an EUC file into an AFP data stream file so that you can print the file on an Infoprint printer.

The **db2afp** command can transform input files that use the following code pages:

- Japanese PC (code page number 932)
- Japanese EUC
- Traditional Chinese PC (code page number 938 and 950 for AIX)
- Traditional Chinese PC (code page number 950 for NT)
- Traditional Chinese EUC
- Korean EUC

You can run **db2afp** manually if you want to transform a DBCS ASCII or EUC file into an AFP data stream file without printing it immediately.

The PSF DSS automatically runs the **db2afp** command whenever:

- Infoprint identifies the format of a document in a print job as DBCS ASCII or EUC.
- You specify **document-format=dbcs-ascii** with the **-x** flag or in an attributes file on the **pdpr** command.

**Note:** For EUC format, specify **document-format=dbcs-ascii** and an EUC code page as the value of the **default-character-mapping** attribute.

- You submit a DBCS ASCII or EUC print job and request **-odatatype=dbcsascii** with one of the AIX print commands (**enq**, **lp**, and **qprt**) or with the **lprafp** command
- You select an attributes file that shows **dbcs-ascii** in the Type of Data in the Print File field, using the Infoprint SMIT panels.

If you do not specify an input file, the **db2afp** command defaults to standard input. If no output file is specified, the **db2afp** command defaults to standard output.

### Limitations

The **db2afp** command generates an AFP data stream file with double-byte character set (DBCS) font references. These DBCS fonts (for Japanese, Traditional Chinese, and Korean) are not part of Infoprint and are sold separately.

### Flags and Values

You can specify these flags and values

- With the **db2afp** command
- With the **enq -o**, **lp -o**, **qprt -o**, or **lprafp** commands
- With the **pdpr** command, using the **other-transform-options** attribute or equivalent attributes on the command line or in an attributes file

**Note:** If you are migrating from PSF for AIX, see “Appendix B. Migrating PSF for AIX Job Script Keywords to Infoprint Equivalents” on page 691 for a table of

attributes equivalent to the job script keywords that you used to use to specify flags and values for transforms.

**-o** *OutputFile*

Specifies the name of the AFP data stream output file generated by the transform. If you do not specify the **-o** flag, Infoprint writes the result to standard output.

You cannot use **-o***OutputFile* on the command line with the **enq**, **lp**, **qpri**, or **lprafp** commands. You can only use **-o***OutputFile* with the **db2afp** command, or with the **other-transform-options** attribute on the **pdpr** command.

This flag is equivalent to the **transform-output-file-name** document attribute on the **pdpr** command.

**-l** {**japanese** | **chinese** | **korean**}

Specifies the language to be used for the transform. The values are:

**ja** | **japanese**

The input file is in Japanese.

**ch** | **chinese**

The input file is in Traditional Chinese for AIX (code page 938).

**c2** The input file is in Traditional Chinese for NT/2000 (code page 950).

**ko** | **korean**

The input file is in Korean.

**Note:** If you specify **-l ko**, you must also specify the **-e** flag. The **db2afp** command supports only Korean EUC, not Korean DBCS ASCII.

If you do not specify **-l** or **-e** on the command line, the **db2afp** command uses the value that has previously been set and exported with the **PSFDBLANG** environment variable. The **PSFDBLANG** environment variable can be set to one of the following:

**j** Japanese (code page 932)  
**je** Japanese EUC  
**c** Traditional Chinese (code page 938)  
**t** Traditional Chinese (code page 950)  
**ce** Traditional Chinese EUC  
**ke** Korean EUC

With Infoprint Manager for AIX, if you are unsure about the value to use with the **PSFDBLANG** environment variable, enter the following command:

```
echo $LANG
```

The command displays one of the following output values:

**Ja\_JP** Japanese DBCS ASCII  
**ja\_JP** Japanese EUC  
**zh\_TW**  
 Traditional Chinese EUC  
**ko\_KR**  
 Korean EUC

With Infoprint Manager for Windows NT and Windows 2000, if you are unsure about the value to use with the **PSFDBLANG** environment variable, enter the following at a Windows command prompt:

```
chcp
```

## db2afp

The command displays the following information:

Active code page: nnn

where *nnn* is the code page number 932, 938, 950.

### Notes:

1. A Traditional Chinese DBCS ASCII locale does not exist.  
If you specify either **-l** or **-e** on the command line, the **db2afp** command ignores the value set in the **PSFDBLANG** environment variable. If the **PSFDBLANG** value has not been set and you do not specify **-l** (and **-e** for EUC files), the transform will not work.
2. The value set in the **PSFDBLANG** environment variable is used when you submit a DBCS ASCII or EUC print job with the AIX print commands (**enq**, **lp**, or **qpri**), with the **pdpr** or **lprafp** command, or in the SMIT Submit an Infoprint Job panel.
3. This flag and the **-e** flag, used together, are equivalent to the **default-character-mapping** document attribute on the **pdpr** command.

**-e** Tells the **db2afp** command to use the EUC code page when converting the input file into an AFP data stream. If the input file is in the Korean language, you should always use **-e**. If the input file is in Traditional Chinese or Japanese, you should use **-e** if your input data is in EUC format.

This flag and the **-l** flag, used together, are equivalent to the **default-character-mapping** document attribute on the **pdpr** command.

### InputFile

Specifies the DBCS ASCII or EUC file that will be transformed into AFP. If you do not specify an input file, the **db2afp** command uses standard input.

## Examples

- To transform the Japanese DBCS ASCII file *dbfile* into an AFP data stream file called *dbfile.afp*, enter:

```
db2afp -o dbfile.afp -l ja dbfile
```

The file is transformed, but not printed.

**Note:** You could also use the following command to perform a similar task, except that the output is sent to the printer:

```
pdpr -p servC-lp -x "default-character-mapping=ibm-932" dbfile
```

- To transform the Korean EUC file *korefile* into an AFP data stream file called *korefile.afp*, enter:

```
db2afp -o korefile.afp -l ko -e korefile
```

The file is transformed, but not printed.

**Note:** You could also use the following command to transform the file, then print it:

```
pdpr -p servC-lp -x "other-transform-options='-e -l ko'" korefile
```

or

```
pdpr -p servC-lp -x "default-character-mapping=ibm-euckr" korefile
```

- With Infoprint Manager for AIX, to transform a Traditional Chinese DBCS ASCII file named *memo.tc* into an AFP file and print it on an Infoprint printer named *servC-lp*, enter:

```
pdpr -X chinese.X -p servC-1p memo.tc
```

In this example, the attributes file named `chinese.X` contains the following settings:

```
document-format=dbcs-ascii
default-character-mapping=ibm-938
```

With Infoprint Manager for AIX, to set the `db2afp` command to default to Korean EUC, enter the following lines in the `.profile` file (Bourne shell or Korn shell) or the `.cshrc` file (C shell) in your home directory:

```
export PSFDBLANG=ke
```

The `db2afp` command now uses Korean EUC as long as the `PSFDBLANG` environment variable is set and exported, and `-I` or `-e` are not specified on the command line. So, to transform the Korean EUC file `korefile` into an AFP data stream file called `korefile.afp`, you now can enter:

```
db2afp -o korefile.afp korefile
```

Similarly, you could now use the following command to transform the Korean EUC file, then print it:

```
enq -PservC-1p -o datatype=dbcsascii korefile
```

## Files

For Infoprint Manager for AIX, use the following locations:

**`/usr/lpp/psf/bin/db2afp`**

Transform program

**`/usr/lpp/psf/db2afp/afpdfont.rc`**

AFP font mapping file used by the `db2afp` command

**`/usr/lib/nls/loc/iconv/ConverterName`**

Code page translation files (which contains mappings from the input code page to the output code page)

For Infoprint Manager for Windows NT and Windows 2000, use the following locations:

**`install_path\bin\db2afp.exe`**

Transform program

**`install_path\bin\afpdfont.rc`**

AFP font mapping file used by the `db2afp` command

**`install_path\iconv\ConverterName`**

Code page translation files (which contains mappings from the input code page to the output code page)

## d2afp Command: Transforms ditroff Data to AFP in Infoprint Manager for AIX

### Syntax

```
d2afp [-o OutputFile] [InputFile]
```

### Description

The **d2afp** command transforms a ditroff data stream file preformatted for an AFP device into an AFP data stream file so that you can print the file on an Infoprint printer.

The process to transform troff files into AFP data stream files has two steps:

1. The troff file is first formatted by specifying the **troff -Tafp** command. This formatting step produces a device-independent troff (ditroff) file.

#### Notes:

- a. Use the **-Tafp** flag and value; otherwise, you cannot transform the ditroff file with the **d2afp** command. If you do not want to specify the **-Tafp** flag and value each time you use the **troff** command, you can set the **TYPESETTER** environment variable to **afp**. To do this, enter the following at the AIX command-line prompt or add this line to your **.profile** file (Bourne shell or Korn shell) or the **.cshrc** file (C shell) in your home directory:
 

```
export TYPESETTER=afp
```
  - b. Although you cannot use the **d2afp** command to transform ditroff files formatted with **troff -Tpsc** or **troff -Thplj**, you can print them. Use the **psc** or **hplj** command to convert the file to PostScript or PCL format. Then use **ps2afp** or **pcl2afp** to transform it.
2. The ditroff file is then transformed into an AFP data stream file with the **d2afp** command.

The PSF DSS automatically runs the **d2afp** command whenever:

- Infoprint identifies the format of a document in a print job as ditroff.
- You specify **document-format=ditroff** with the **-x** flag or in an attributes file submitted with the **pdpr** command.
- You submit a ditroff print job and include the **-odatatype=ditroff** flag and keyword-value pair with one of the AIX print commands (**enq**, **lp**, and **qprt**) or with the **lprafp** command.
- You select an attributes file that has **ditroff** in the Type of Data in Print File field when using the Infoprint SMIT panels to submit a print job.

### Limitations

The **d2afp** command limits the number of fonts that a ditroff file can load, change, or map. The following shows the maximum number of fonts for specific conditions:

#### ditroff Fonts

	Condition
40	Loaded at one time
127	Point size or font changes on one page
200	ditroff fonts mapped to AFP fonts

If your troff file has graphics, you might use a different method to print ditroff files. If one of the following conditions applies:



- Your PPDS or PCL printer does not support the PCL5 or PCL5C data streams.
- Your channel-attached printer does not have the Advanced Function Image and Graphics feature installed.

**Note:** TCP/IP-attached IPDS printers print troff files with graphics; therefore, you do not need to use other procedures.

use this procedure to print troff files containing graphics:

1. Convert the troff file to ditroff format using the **troff -Thplj** command.
2. Convert the ditroff file to PCL format using the **hplj** command.
3. Submit the PCL file to print. Infoprint automatically invokes the **pcl2afp** command to convert the PCL file to AFP format.

## Flags and Values

You can specify the *InputFile* and the **-o** *OutputFile* values in any order.

### *InputFile*

Specifies the name of the input file to transform. This input file must be a ditroff file; that is, a troff file formatted for an AFP printer device using the **troff -Tafp** command.

If you do not specify an input file, the command uses standard input. The value for the input file is any valid AIX file name.

### **-o** *OutputFile*

Specifies the name of the AFP data stream output file generated by the transform. If you do not specify the **-o** flag, the output generated goes to standard output. The value for the output file is any valid AIX file name.

## Examples

- To transform the ditroff file `myfile` into an AFP data stream file called `myfile.afp`, enter:

```
d2afp myfile -o myfile.afp
```

- To create an AFP data stream output file from the troff file `doc.trf` and print the output file using the Infoprint logical printer `servC-1p`, enter:

```
troff -Tafp doc.trf | d2afp | pdpr -p servC-1p
```

In this example, the `troff` command searches the `/usr/lib/font/devafp` directory for the troff font and printer description files. The **d2afp** command also uses files in this directory.

In the preceding example, the **d2afp** transform runs on the local AIX system whether the printer, `servC-1p` is a local or remote printer.

**Note:** You could also use the following command to perform the same function:

```
troff -Tafp doc.trf | pdpr -p servC-1p -odatatype=ditroff
```

In this case, if the printer, `servC-1p`, is local, the **d2afp** transform runs on the local AIX system; however, if the printer is remote, the **d2afp** transform runs on the remote AIX system.

- To print the ditroff file report on an Infoprint printer named `servD-1p`, enter:

```
pdpr -X ditroff.X report
```

In this example, the attributes file named `ditroff.X` contains the following settings:

## d2afp

```
document-format=ditroff  
printer-name-requested=servD-1p
```

## Files

### **/usr/lpp/psf/bin/d2afp**

Transform program

### **/usr/lib/font/devafp/devafp.fontmap**

AFP font mapping file used by the **d2afp** command to map troff fonts to AFP code pages and AFP character sets

### **/usr/lib/font/devafp/\*.d2afp**

Binary versions of the troff font and description files used by the **d2afp** command

### **/usr/lpp/psf/fontlib**

AFP font resource directory, which includes AFP character sets and AFP code pages for ditroff

### **/usr/lib/font/devafp/README.d2afp**

File that has useful information about AFP characters for troff and ditroff files

Other files associated with the **troff** command are described in *AIX for RS/6000 Commands Reference*.

## gif2afp Command: Transforms GIF Data to AFP in Infoprint Manager for AIX

### Syntax

```
gif2afp [-a ImageType] [-alg ProcessingAlgorithms]
        [-calib calibration] [-C ConfigurationFile]
        [-clean cleanup] [-cmp compression]
        [-crop CropFactors] [-fit {trim | scale}]
        [-gcorr GrayscaleMappingTable] [-ink color] [-inv]
        [-j ScanOffsetFileName] [-l ImageLength ]
        [-M MemoryBound] [-ms space] [-msf SpaceFraction]
        [-o OutputFile] [-outbits NumberOfOutputBits]
        [-outcolor OutputColorMode] [-p PageRange]
        [-pagetype PageType] [-paper PaperSize]
        [-r resolution] [-respath ResourceSearchPath]
        [-rot rotation] [-scale ImageSize]
        [-sgcorr ScannerCorrection]
        [-sniff | -nosniff] [-term | -noterm]
        [-thresh HalftoneFile] [-v | -nov] [-w ImageWidth]
        [-x LeftMargin] [-y TopMargin] [-z]
        [[file | directory | -f FileList | @FileList]...]
```

### Description

The **gif2afp** command transforms a GIF (Graphical Interchange Format) data stream into an AFP (MO:DCA-P) or PostScript Level 2 data stream file.

The transform can process GIF images, including bilevel, grayscale and color images. The output can be bilevel (IM1 or IOCA FS10), 4-bit or 8-bit grayscale, or 24-bit YCbCr color (IOCA FS11). The transform automatically uses halftoning to convert the grayscale and color images to bilevel.

### Automatic Invocation

The PSF DSS automatically invokes the **gif2afp** transform command whenever you submit a GIF file for printing. You can pass options to **gif2afp** using the **other-transform-options** attribute on the **pdpr** command or the **-o** flag of the AIX print commands and the **lprafp** command.

### Input and Output

**gif2afp** can process either standard input, or multiple files specified on the command line. If no input file is specified, **stdin** is assumed. Only a single GIF file should be submitted via **stdin**. If multiple GIF files are concatenated via standard input, all except the first one are ignored.

If an input file is specified on the command line, it can be either a GIF file, a directory, or a file list (**-f** and **@** prefixes). Multiple input file specifications are allowed. The transform processes each file in the order in which it was specified on the command line. If the **-z** option is specified, a list of file names to be processed is also submitted via standard input. The files on the list are processed as if the list were given via the **-f** option on the same place on the command line as **-z**.

## gif2afp

If the file name points to a directory, **gif2afp** processes every file in that directory. The files are processed in the order they would be shown using the **ls -a** command. Directory search is not recursive, that is, the subdirectories are not searched.

If the file name is preceded by the **-f** option or the at sign (**@**), **gif2afp** assumes that the file contains the list of GIF files to be processed. Each of the files in the list is processed in the order it was listed.

If a GIF file has the extension **.gif** or **.GIF**, this extension need not be given explicitly. **gif2afp** first tries to open the file as specified and, if unsuccessful, tries to append the extensions **.gif** and **.GIF** in turn.

For example, suppose that:

- The directory `tFiles` contains the files `file1.gif`, `file2.gif`, `file3.gif`, and `file4.gif` and nothing else.
- The file `flist` in the current directory contains the two file names `tFiles/file2.gif` and `tFiles/file3.gif`. The names listed in the file list may have their extensions omitted.
- The file `flist2` contains the file name `tFiles/file4`. Again, the names listed in the file list may have their extensions omitted.

In order to process files `file1.gif`, `file2.gif`, `file3.gif`, and `file4.gif`, any of the following invocations of **gif2afp** would work:

```
gif2afp tFiles/file1.gif tFiles/file2.gif tFiles/file3.gif tFiles/file4.gif
gif2afp tFiles/file1 tFiles/file2 tFiles/file3 tFiles/file4
gif2afp tFiles/file*.gif
gif2afp tFiles
gif2afp tFiles/file1 -fflist tFiles/file4
gif2afp tFiles/file1 -f flist tFiles/file4
gif2afp tFiles/file1 -f flist -f flist2
gif2afp tFiles/file1 @flist @flist2
```

The file list files allow the display text to be added for each file. A display text is any text starting with the pound character (**#**) and extending to the end of the line. The display text should follow the file name, and can extend over several lines, up to 2048 characters long. The initial **#** character on each line is discarded. If a display text is present for a file name, that text is displayed in the status and error messages instead of the file name. This is useful if the **gif2afp** is invoked using temporary files whose names are meaningless to the user. Any display text before the first file name is treated as comment and discarded. Display text is allowed also if the **-z** option is used to submit the file list via standard input.

GIF files may contain multiple images. The **gif2afp** transform can process and output all the images in the file, subject to the values given in the **-p** option.

The output file name can be either specified explicitly via the **-o** option, or derived from the input file name. If multiple input files have been specified, the default output file is standard output. If a single input file is given and the output file is not specified explicitly, the transform strips the **.gif** or **.GIF** extension from the input file name (if one is present), and appends the **.afp** extension for AFP output, or the **.ps** extension for PostScript output, to get the output file name.

To disable automatic output file name generation and force the default output stream to be the standard output in all cases, set the environment variable

**GIF2AFP\_o** to **-** or **stdout**, or, alternatively, put the line **o=-** or **o=stdout** into the configuration file and invoke that configuration file using the **-C** option or the **GIF2AFP\_C** environment variable.

For example, all the following commands:

```
gif2afp myfile
gif2afp myfile.gif
gif2afp myfile -o myfile.afp
```

have `myfile.afp` as the output file. Note that there is no requirement for the explicitly specified input and output files to have **.gif** and **.afp** extensions. To process GIF file `foo.bar` into an AFP file `foo.bar2`, invoke the transform using `gif2afp foo.bar -o foo.bar2`

The output data stream is MODCA-P IS/1, MODCAP-P IS/2, or PostScript Level 2. IS/1 images are bilevel and are encoded as IOCA Function Set 10 or IM1. IM1 images are uncompressed. IOCA FS10 output images can be either uncompressed, or compressed via one of the four available compression algorithms (see the **-cmp** option). The default is ITU-T T.6 Group 4 compression. IM1 images are always uncompressed. IS/2 images can be either bilevel, 4-bit or 8-bit grayscale, or 24 bit YCbCr color. Multibit images are encoded as IOCA Function Set 11. Be aware that the only product that supports IOCA FS11 images is the AFP Workbench, that is, grayscale and color AFP images are not currently supported by any printer.

PostScript Level 2 images can be uncompressed or ITU-T T.6 Group 4 bilevel, uncompressed 8-bit grayscale or uncompressed 24-bit RGB color. By default, the transform leaves scaling and halftoning to the printer (that is, color GIF images are output as 24-bit RGB color images).

## Errors and Error Recovery

**gif2afp** divides errors into fatal and non-fatal. The fatal error categories are the following:

- Errors in the user-specified parameters, either in the environment variables, the configuration file, or the command line arguments. These errors include unrecognized options, invalid values for parameters, or inability to open the configuration file or the output file.
- Out of memory errors. The requested memory is larger than the memory specified using the **-M** option or the dynamic memory allocation has failed.
- Disk space errors. The transform guards against trying to write to a full file system. See the **-ms** and **-msf** options for setting the minimum free disk space requirements. If the file system is full, the transform deletes the partial output file before terminating.
- Internal errors.

In the case of a fatal error, the last output page might not be complete.

Errors encountered in the GIF files are non-fatal and **gif2afp** attempts to recover from them. These errors include not being able to open an input file, an input file not being a GIF file, or an input file containing features that cannot be processed. If the transform fails to open 15 or more input files, it assumes an error in the parameter list (for example, **-f** was used with a file that does not contain a file list) and terminates.

## gif2afp

If an error is encountered in a file, the transform attempts to recover with the next image in the file. If such recovery is not possible, **gif2afp** attempts to recover with the next input file. In both cases, a warning message is issued. Errors and warnings are output to standard error.

For example, let a directory `tFiles` contain files `file1.gif`, `file1.txt`, `file2.gif` and `file3.gif`, where `file1.txt` is an ASCII file. Invoking the transform via `gif2afp tFiles`

processes the bilevel images in all three GIF files correctly. A warning is issued that `file1.txt` is not a GIF file.

Non-fatal errors can be made fatal by using the option **-term**, or the corresponding environment variable or configuration file entry. If **-term** is set, the transform terminates in error if it encounters an error in the GIF data stream.

## Data Transformations

If the input image is grayscale or color, and the output image type is bilevel (IOCA FS10 or IM1), the transform internally scales the image to the desired size, then uses a halftoning algorithm (ordered dither, the default, or Floyd-Steinberg) to convert it to bilevel. In converting the image to bilevel, the characteristics of the output device such as dot shape and dot gain must be taken into consideration. The internal grayscale mapping table has been optimized for the 600-pel IBM Infoprint 4000 laser printer. The **-gcorr** option can be used to specify a different mapping of gray levels.

For very light or very dark images, the halftoning algorithms can be automatically recalibrated to preserve details that would be lost using the default calibration. See the **-alg** option for more information.

To maintain the image quality, scaling must be done prior to halftoning. Halftoning algorithm is very computation-intensive. Unless the images are small, **gif2afp** cannot process the color images fast enough to feed even a slow printer.

The size and position of the output image depend on several factors:

- The size specified to the transform
- The form map specified at print time
- The forms and options loaded in the printer

If the image is too large to fit on the page, it is trimmed to size by default. Use the **-fit scale** option to instruct the printer to scale the image to the paper size. If the paper size is not specified explicitly via the **-paper** option, the paper size defaults to US letter size (8.5 by 11 inches). If the image is larger than this, the paper dimensions are increased as necessary. If the paper size is been specified explicitly, it is not increased if the image does not fit on paper. The options **-l** and **-w** have the same effect as **-paper**.

The size of the actual image (as opposed to the paper size) is controlled by the **-scale** option. You can either specify a value of **orig** for the **-scale** option or give an actual size. If you specify **orig**, the output image is the same size as the input image. If you specify **-scale** with an actual size, the output image is scaled to the desired size. You can also specify a percentage for enlargement or reduction.

Even if you specify **-scale orig**, the image may still have to be scaled if the input file specifies non-square pixels. By default, the transform leaves scaling to the printer. The exceptions are:

- Images that are being halftoned, which are always scaled in the transform,
- Images that have different resolutions in X and Y directions (non-square pixels)

**Note:** Because GIF files do not specify resolutions, the image is assumed to have the resolution of the output device.

You can use the **-alg** option to instruct the transform to perform internal image scaling. Options **-alg**, **-clean**, and **-ink** choose and configure various scaling algorithms.

GIF images are compressed using the LZW algorithm. Because LZW compression is not part of any current IOCA function set, **gif2afp** always reads and decompresses the image.

## Parameters

**gif2afp** behavior is governed by many parameters. The parameters are set by the following hierarchy (least significant first):

- Internal defaults
- Environment variables
- Configuration file
- Command-line arguments

### Command Line Arguments

Note the following points regarding the command line arguments for the **gif2afp** transform:

- Options and input file names can appear on the command line in any order.
- When you run **gif2afp** as a standalone transform, the blank between option and value is optional (for example, both **-inkblack** and **-ink black** are valid).
- When you use the **-o** flag of the **enq**, **lp**, **qprt**, or **lprafp** commands to pass options to **gif2afp**, no blank is permitted between option and value is optional (for example, **-o-inkblack** is valid, but **-o -ink black** is not).
- When you use the **other-transform-options** attribute on the **pdpr** command to pass options to **gif2afp**, any string containing a blank must be surrounded by single quotes (for example, both **other-transform-options=-inkblack** and **other-transform-options='-ink black'** are valid).
- All values except file names are case-insensitive.
- If an option is specified multiple times, the last specification remains in force.
- If multiple configuration file names are given, they are processed in order.

### Configuration File

The configuration file has entries of the form *option=value*, where each pair must reside on a separate line. Options and other syntax are the same as for the command line arguments and the option names are the same. Input files and configuration files cannot be specified in the configuration file (that is, nested configuration files are not supported). In the case of options without values (for example, **-inv**), the equals sign must be present.

Some command line options, for example, **-calib**, cannot be used in the configuration file or as environment variables. Options available only on the command line are noted as such in their descriptions.

## gif2afp

If you do not specify a configuration file on the command line with the **-C** option, the transform checks for the existence of the default configuration file, **/usr/lpp/psf/gif2afp/gif2afp.cfg**. If this file exists, the transform uses it as the configuration file.

The following is an example of a valid configuration file:

```
scale = letter
r= 300
o = -
inv=
alg=afp
```

Note that the spaces around the equals sign (=) are optional. In this example, the option-value pair **o = -** means that the default output file is the standard output. Output file name computation has been disabled.

### Environment Variables

Environment variables have the form **GIF2AFP\_option**, where *option* is the same as on the command line and the configuration file.

Some command line options, for example, **-calib**, cannot be used in the configuration file or as environment variables. Options available only on the command line are noted as such in their descriptions.

For example, to achieve the same effect as the configuration file in the last example, the following statements have to be executed in the calling shell:

```
export GIF2AFP_scale=letter
export GIF2AFP_r=300
export GIF2AFP_o=-
export GIF2AFP_inv=" "
export GIF2AFP_alg=afp
```

There must be some value set for each desired option. For options that do not take a value, specify a blank surrounded by double quotes, for example:

```
export GIF2AFP_inv=" "    correct
export GIF2AFP_inv=      has no effect
```

## Resource Search Path

For resource files, such as scan offset files and grayscale correction files, the transform searches the current directory by default. You can use the **-respath** option to specify a list of directories to be searched for such files. This resource path does not apply to the configuration file.

## Limitations

- Timing data from GIF animation sequences is ignored.
- Animation sequences are processed as unrelated images.

## Acknowledgments

This software is partially based on the Independent JPEG Group's JPEG compression and decompression code.

## Options and Values

### @FileList

Specifies a name of a file that contains a list of files to be processed by the transform. If the **@** option is present, the output file defaults to standard



output, even if the list of files contains only a single entry. Multiple @ options are allowed. Also see the **-f** and **-z** options. The @ is not preceded by the dash, and is implemented to maintain compatibility with the **ps2afp** transform.

**-a {ioca | ioca10 | ioca11 | im1 | PS.2}**

**-a {IO1\_G4 | IM1 | IO1 | IO1\_MMR | PSEG\_IO1\_G4 | PSEG\_IM1 | PSEG\_IO1 | PSEG\_IO1\_MMR | OVLY\_IO1\_G4 | OVLY\_IM1 | OVLY\_IO1 | OVLY\_IO1\_MMR}**

Choice of the output image type. The first syntax chooses between the IOCA FS 10 (**ioca**, **ioca10**), IOCA FS11 (**ioca11**), IM1, and PostScript Level 2 (**PS.2**) output. IOCA FS10 and IM1 yield bilevel images, while IOCA FS11 results in 4-bit or 8-bit gray or 24-bit color output (see option **-outbits**). Note that presently the only product that supports IOCA FS11 is the AFP Workbench. The output compression algorithm is set via the option **-cmp**. To set the page type (page, overlay, page segment or object), use the **-pagetype** option.

The second syntax is to maintain compatibility with the **ps2afp** transform, and sets the image type (**IO1** for IOCA FS10 or **IM1** for IM1 output), compression (**G4** for Group 4 or **MMR** for Group 3), and page type (**PSEG** for page segment or **OVLY** for overlay). If **PSEG** or **OVLY** is not specified, the output is a printable page. If no compression algorithm is specified, the output is not compressed. The second syntax cannot be used for IOCA FS11 output.

Some older printers do not support IOCA images. In such cases, the IM1 output type should be chosen. IM1 images are uncompressed and thus use more space. The processing might also take longer since the IM1 image cannot be scaled by the printer and so internal scaling algorithms must be used. See option **-alg**.

The default is **ioca** for IOCA FS10 output compressed via Group 4 algorithm.

This option is similar to the **image-out-format** document attribute on the **pdpr** command.

**-alg {afp | alg1 | alg2 | alg3}**

**-alg {htod1 | htfs}**

**-alg htcal1**

Choice of the scaling and halftoning algorithms. You can specify multiple choices, separated by commas, for one **-alg** option. The effect is the same as specifying multiple **-alg** options. For example, **-alg htfs,htcal1** is equivalent to **-alg htfs -alg htcal1**.

The scaling algorithms are:

- If **afp** is chosen, the scaling is done using the default algorithm in the printer. This makes the transform much faster. If the image must be reduced, however, this algorithm may drop some information from the image, such as thin lines.
- **alg1** activates the internal scaling algorithm to scale the image explicitly to the specified size. This algorithm is guaranteed not to discard any ink. "White space" in the image, however, may be lost (that is, features close to one another might merge). This algorithm makes the transform run

## gif2afp

longer, and might occasionally make for a “dirty” image, since the occasional “noise pixels” in the scanned images tend to be amplified.

- **alg2** activates the more flexible version of **alg1**. If this algorithm is selected, option **-clean** can be used to specify the amount of ink “cleanup” to be performed. Option **-clean 0.0** makes the algorithm **alg2** perform like **alg1** (albeit more slowly). Increasing the value specified in **-clean** discards more and more ink, until **-clean 1.0** results in a blank page.
- **alg3** activates a scaling algorithm that works by deleting or duplicating rows and columns in the image. This is a fast general-purpose algorithm.

For bilevel images, the default is **afp** if the output image type is IOCA and **alg3** if the output image type is IM1. For color images with bilevel output, the scaling is always done prior to the halftoning algorithm. If a grayscale or color output is chosen (**-a ioca11**), this option is ignored and the algorithm is set to **afp**.

The halftoning algorithms are:

- **htod1** uses an ordered dither with a screen derived from the value of the **-thresh** option. The default is an 85 line per inch screen.
- **htfs** uses the Floyd-Steinberg algorithm.
- **htcal1** recalibrates the halftoning algorithm for each image. **htcal1** forces the transform to read the whole image into memory and requires an additional pass through the image. It should be used only for very light or very dark images.

The default is **htod1**. Each halftoning algorithm uses a different internal default calibration curve. If the automatic calibration is turned on, a still different set of calibration curves are used.

See options **-clean**, **-gcorr**, **-ink**, **-paper**, **-scale**, **-thresh**, **-l**, **-w**, **-x**, and **-y**.

### **-calib scanner**

#### **-calib {scanner | printer | patch | patchr},name1...**

Transform calibration for the scanner or printer. If **scanner** is specified, **-sgcorr** must be present. If **printer** is specified, **-sgcorr** may or may not be present. If **patch** or **patchr** is specified, **-sgcorr** (if present) is ignored. Detailed explanation of the calibration process is beyond the scope of this entry.

You cannot specify **-calib** in the configuration file or as an environment variable.

#### **-C ConfigurationFileName**

The name of a configuration file containing option-value pairs. If multiple **-C** options are given on the command line, they are processed in order. Specifying the configuration file on the command line overrides any specification done via the **GIF2AFP\_C** environment variable.

The default configuration file is **/usr/lpp/psf/gif2afp/gif2afp.cfg**.

#### **-clean {0.5 | x.xxx}**

The internal scaling algorithm **alg2** allows for variable thresholding. The scaled pixel is declared painted if the fraction of its area greater than the threshold is painted in the original image. The value **x.xxx** is a real number between zero and 1 inclusive and gives this threshold.

If the option **-clean 0.0** is issued, **alg2** behaves like **alg1** and turns on a pixel as long as any part of the pixel has been painted in the original image. **-clean 1.0** results in a blank image because the output pixels are never painted.

Note that setting **-clean 0.95** and **0.9999999** turns on the pixels that had essentially all the area painted in the original picture. Depending on the data, most of the image will probably be preserved. Increasing **-clean** by a small amount to **1.0** erases the image. If the scaling algorithm is not **alg2**, this option is ignored. The default is **-clean 0.5**.

**-cmp {none | mh | mmr | g3 | g4 | jpeg}**

Choice of the output image compression algorithm:

- none** Uncompressed output
- mh** ITU-T T.4 G3 Modified Huffman
- mmr** IBM Modified Modified Read
- g3** ITU-T T.4 G3 Modified Read
- g4** ITU-T T.6 G4
- jpeg** JPEG non-differential Huffman coding with baseline DCT. The output image data should be compressed to reduce the file sizes and increase the printing speed.

The default compression is ITU-T T.6 Group 4 for bilevel images and no compression for grayscale or color images. Note that some printers may not support Group 4 compression algorithm and require using the **-cmp** option to choose a different one. The JPEG algorithm can compress only 8-bit grayscale and 24-bit color images. 4-bit grayscale images cannot be compressed.

**-crop *t,b,l,r*[*i* | *m* | *p* | *d*]**

Image cropping. *t,b,l,r* specify how much should be cropped from the image top, bottom, left edge, and right edge. The numbers are floating point and can be either positive or negative. Negative numbers indicate that a blank space should be inserted. The units are inches, millimeters, points, and dots (pels), with the default being dots. The cropping is specified in the context of the output page, so that "top" means the top of the output page and so on, regardless of the **-rot** option. To crop, the transform will enlarge the image by the amount to be cropped, then crop the specified amount by manipulating the actual bitmap. The resulting image has the size as specified by the explicit (or implicit) **-scale** option. See also option **-j**.

If **-fit trim** is specified, the right and the bottom edge of the image are not cropped. Instead, the image grows as necessary. Because **-fit trim** causes the output data stream to contain the "position and trim" specification, the printer discards any extra image.

**-f *FileList***

Specifies the name of a file that contains a list of files to be processed by the transform. If the **-f** option is present, the output file defaults to standard output, even if the list of files contains only a single entry. Multiple **-f** options are allowed. See also options **@** and **-z**.

**-fit {trim | scale}**

Determines whether the printer behavior will be position-and-trim or scale-to-fit if the image is too large to fit on the paper. The default is **trim**.

This option is equivalent to the **image-fit** document attribute on the **pdpr** command.

**-gcorr** *FileName*

Specifies a file with grayscale mapping table for halftoning of the grayscale and color images to bilevel for output. The mapping table must be provided to compensate for the printing characteristics of the particular output device and paper type, such as dot gain. This file must contain either:

- 256 real numbers, one for each level of gray in the 8-bit grayscale image
- The PostScript **settransfer** operator

The algorithm converts every image to 8-bit grayscale before applying the halftoning algorithm. The default internal mapping table has been optimized for the 600-peI IBM Infoprint 4000 laser printer. You shouldn't change this unless you know what you are doing. See also options **-alg** and **-thresh**. PostScript code submitted via the **-thresh** option can have the same effect as **-gcorr**.

**-ink {black | white}**

This option is used only with scaling algorithm **alg1** or **alg2**. The GIF images can be either black on white or white on black. The internal scaling algorithm must know which, because "ink" is preserved at the expense of "non-ink" The default value, "black", indicates that the image is black on white.

If the option **-inv** is used to print the reversed image, the inversion is done as the data is read by the transform, before any processing is done. The black or white must thus be specified in the terms of the printed image, not in the terms of the input GIF image.

- inv** Reverses the image. Areas that are black in the original image become white and vice versa. Note that the reversed image may be either black on white or white on black, depending on the original image.

**-j** *ScanOffsetFileName*

Sometimes input images must be shifted to get the desired positioning on the page. The scan offset file contains the directions for shifting. The file has the format of

```
[attribute]
values
:
values
[attribute]
values
:
values
```

Currently, the recognized attributes are **[Units]** (values **millimeters**, **mm**, **inches**, **in**, **points**, **dots**, **pels**) **[Page\_Offset\_Type]** (values **crop** or **grow**) and **[Page\_Offsets]**. The values for page offsets are in the format *FileName,Hhoriz,Vvert* Each entry refers to a file. The file names must be specified (or at least the leading comma must), but are currently ignored and the offset factors are applied to each file in turn. Note that the same factors are applied to each image in the file. The *horiz* and *vert* values are the amount that the image is to be shifted, in the horizontal and vertical direction. The positive directions are down and right (that is, the origin is in the left upper corner of the page). The default units are millimeters. Like the values for the **-crop** option, the shifts are specified in the output space context.

Extra spaces and blank lines are allowed. Unrecognized attributes and their values are ignored. See the sample file **shift.sample**.

If the image is moved left or up, part of the bitmap is removed. If the image is moved down or right, removal is governed by the value of the **[Page\_Offset\_Type]** attribute. If **crop** is chosen, the transform removes the requisite amount from the right and bottom edges of the bitmap. If **grow** is chosen, the transform does not remove any space. The bitmap grows and the trimming, if any, is left to the printer. If the **-fit trim** option (the default) is specified, **[Page\_Offset\_Type]** defaults to **grow**. For **-fit scale**, **[Page\_Offset\_Type]** defaults to **crop**.

**-l {11i | yyy.yy[d | m | i | p]}**

Specifies the paper length. The optional units are **dots** (pels), **millimeters**, **inches**, or **points**. The default unit is dots. If the unit is dots, decimals (if any) are ignored. The default paper length is 11 inches. See options **-w** to set the paper width or **-paper** to set both dimensions at the same time.

**-M {0 | nnn}**

Limits the amount of memory available to **gif2afp**. *nnn* is the maximum amount of memory in kilobytes. A value of **0** means there is no memory limit. *nnn* can be set from **0** to the maximum value that AIX allows. The default is **0**.

**-ms {10 | nnn}**

Requires that at least *nnn* kilobytes of disk space be available on the file system that contains the output file. This limit is enforced every time data is written to the output file. If the output is standard output, this option is ignored. The default is **10**. See option **-msf**.

**-msf {0.1 | x.xxx}**

The number *x.xxx* is a real number between 0 and 1. It denotes the minimum space that must be left unused on the file system containing the output file. The space is given as a fraction of the total space in the file system. This limit is enforced every time data is written to the output file. If the output is standard output, this option is ignored. The default is **0.1**. See option **-ms**.

**-nosniff**

See **[-sniff | -nosniff]**.

**-noterm**

See **[-term | -noterm]**.

**-nov** See **[-v | -nov]**.

**-o FileName**

Optional output file name. Specify **-** for standard output.

**-outbits NumberOfOutputBits**

Sets the number of bits per pel in output. This value must be **1**, **4**, **8**, or **24**. If the output image type is IOCA FS10 or IM1, the number of output bits is set to **1** and this option is ignored. For IOCA FS11 output, the default is **24**. Note that this number represents the maximum number of bits used per pel. Thus, even if the number of bits is set to **24**, a 4-bit grayscale image is still displayed in 4-bit format.

**-outcolor {rgb | ycbcr | ycrCb}**

Sets the output color model to RGB, YCbCr, or YCrCb if the image type is IOCA FS11 and the number of output bits is 24. Otherwise, this option is ignored. The default is **ycbcr**.

**-p {even | odd | nn | nn-mm | nn-}**

Specifies that the output should only contain the specified pages. If no **-p** option is given, all the pages are output. Multiple **-p** options may be specified. Their effect is cumulative. Regardless of the order in which the pages are specified, they are always printed in ascending order. The recognized values are:

**even** Print all even pages

**odd** Print all odd pages

*nn* Print page *nn*

*nn-mm*

Print pages *nn* to *mm*, inclusive.

*nn-* Print all pages starting with page *nn*

Pages are numbered starting with 1.

**-pagetype {page | overlay | ovly | pseg | object}**

Sets the output page type to be page, overlay, page segment or object. The same page type is set for every page in the output. Thus, unless option **-p** is used to select a single page, multiple overlays, page segments or overlays are stored in the output file. The default is **page**. See option **-a**.

**-paper {a5 | a4 | a3 | letter | folio | legal | ledger | xxx.xx,yyy.yy[d | m | i | p]}**

Specifies the output paper size. The supported values are:

**a3** A3 format (297 by 420 mm or 11.69 by 16.54 inches)

**a4** A4 format (210 by 297 mm or 8.27 by 11.69 inches)

**a5** A5 format (148 by 210 mm or 5.83 by 8.27 inches)

**letter** 8.5 by 11 inches (216 by 279 mm)

**folio** 8.5 by 13.0 inches (216 by 330 mm)

**legal** 8.5 by 14.0 inches (216 by 356 mm)

**ledger** 11.0 by 17.0 inches (279 by 432 mm)

*xx.xx,yy.yy*[**d | m | i | p**]

Horizontal and vertical page dimensions. The optional units are **dots** (pels), **millimeters**, **inches**, or **points**.

The default paper size is letter. If **-paper** is not used, the paper size is increased, if necessary, to contain the output image.

See options **-l**, **-w**, and **-scale**.

**-r {300 | nnn}**

The output device resolution, specified in dots per inch. The default is **300**.

This option is equivalent to the **default-printer-resolution** document attribute on the **pdpr** command.

**-respath directory[:directory...]**

Sets the search path for resource files, such as the scan offset files and grayscale calibration curve files. If a resource file name is specified as a relative name (does not start with a */*), the transform searches every directory in the path, in the order specified in the path, until it finds the file (or fails). See options **-j** and **-gcorr** for scan offsets and grayscale calibration curve. The default is the current directory.

**-rot** {0 | 90 | 180 | 270[p | i]}

The image is rotated in the clockwise direction by the amount specified. The default is zero, that is, no rotation.

If **p** is specified, the transform sets the output datastream in such a way that the printer performs the actual image rotation. If **i** is specified, the transform rotates the output bitmap. When **i** is chosen, the transform takes much longer to run and uses much more memory. If no letter is specified, the default or any previous value (such as the value specified in the configuration file) remains in force. The default is **p**.

**-scale** {orig | a5 | a4 | a3 | letter | folio | legal | ledger | *xxx.xx,yy.yy*[d | m | i | p] | *xxx%*}

Specifies the output image size. The image is scaled to this size and centered in the area defined by the paper size and margin options. The supported values are:

**orig** Preserve the input image size, regardless of the printable paper area.

**a3** A3 format (297 by 420 mm or 11.69 by 16.54 inches)

**a4** A4 format (210 by 297 mm or 8.27 by 11.69 inches)

**a5** A5 format (148 by 210 mm or 5.83 by 8.27 inches)

**letter** 8.5 by 11 inches (216 by 279 mm)

**folio** 8.5 by 13.0 inches (216 by 330 mm)

**legal** 8.5 by 14.0 inches (216 by 356 mm)

**ledger** 11.0 by 17.0 inches (279 by 432 mm)

*xx.xx,yy.yy*[d | m | i | p]

Horizontal and vertical image dimensions. The optional units are **dots** (pels), **millimeters**, **inches**, or **points**.

*xxx%* Magnification relative to the original image size. Numbers below 100% mean reduction, while Numbers above 100% mean enlargement. For example, **-scale 200%** causes the output image to be twice as long and twice as wide as the input image.

The default image size is **orig**.

**-sgcorr** *FileName*

Specifies the name of the scanner-related calibration file. If **-calib** is absent, this option is ignored.

A detailed discussion of **-sgcorr** is beyond the scope of this document.

**[-sniff | -nosniff]**

Turns automatic conversion to black on white for bilevel images on (**-sniff**) or off (**-nosniff**). The automatic conversion algorithm counts the number of 0 and 1 bits in the image. If there are fewer zeros, it assumes the printed features are represented by zeros (white on black), and inverts the image to be black on white. The detection and conversion are done after the conversion specified by the Photometric Interpretation tag is applied (if any).

This option is ignored if the image is not bilevel. The default is **-nosniff**.

**[-term | -noterm]**

Disables (**-term**) or enables (**-noterm**) error recovery.

## gif2afp

- When error recovery is disabled, on encountering an error in a GIF file, the transform terminates with an error message and a nonzero return code.
- When error recovery is enabled, the errors in GIF files are treated as non-fatal. The transform attempts to recover with the next image in the file, or with the next file. The return code is zero.

The default is **-noterm**.

### **-thresh** *FileName*

Specifies a file that contains a PostScript Type 1 or Type 3 halftone dictionary. Alternatively, the PostScript code can specify the **setscreen** operator instead of a Type 1 dictionary. The halftone cell in the dictionary is used to overwrite the default ordered dither clustered dot halftone cell. If the PostScript code contains a transfer function, either in the halftone dictionary or specified by the **settransfer** operator, the current grayscale correction curve is overwritten as if **-gcorr** were used.

### **[-v | -nov]**

Turns verbose mode on (**-v**) or off (**-nov**).

- When verbose mode is on, the transform prints a message as it opens each resource file, then echoes the command line, then prints a message for each file name as it is processed.
- When verbose mode is off, the transform prints only error messages.

The default is **-nov**.

### **-w** {**8.5i** | *yyy.yy*[**d** | **m** | **i** | **p**]}

Specifies the paper width. The optional units are **dots** (pels), **millimeters**, **inches**, or **points**. The default unit is dots. The default page width is 8.5 inches. See options **-l** to set the paper length or **-paper** to set both dimensions at the same time.

### **-x** {**0** | *nnn.nn*[**d** | **m** | **i** | **p**]}

Specifies the left margin. The optional units are **dots** (pels), **millimeters**, **inches**, or **points**. The default unit is dots. The default is zero (no margin).

### **-y** {**0** | *nnn.nn*[**d** | **m** | **i** | **p**]}

Specifies the top margin. The optional units are **dots** (pels), **millimeters**, **inches**, or **points**. The default unit is dots. The default is zero (no margin).

**-z** Signifies that a list of files to be processed is submitted from standard input. See also options **-f** and **@**.



## jpeg2afp Command: Transforms JPEG Data to AFP in Infoprint Manager for AIX

### Syntax

```
jpeg2afp [-a ImageType] [-alg ProcessingAlgorithms]
          [-calib calibration] [-C ConfigurationFile]
          [-cmp compression] [-crop CropFactors]
          [-fit {trim | scale}] [-force]
          [-gcorr GrayscaleMappingTable]
          [-j ScanOffsetFileName] [-l ImageLength ]
          [-M MemoryBound] [-ms space] [-msf SpaceFraction]
          [-o OutputFile] [-outbits NumberOfOutputBits]
          [-outcolor OutputColorMode] [-p PageRange]
          [-pagetype PageType] [-paper PaperSize]
          [-r resolution] [-respath ResourceSearchPath]
          [-rot rotation] [-scale ImageSize]
          [-sgcorr ScannerCorrection] [-term | -noterm]
          [-thresh HalftoneFile] [-v | -nov]
          [-w ImageWidth] [-wrkdir WorkDirectory]
          [-x LeftMargin] [-y TopMargin] [-z]
          [[file | directory | -f FileList | @FileList]...]
```

### Description

The **jpeg2afp** command transforms a JPEG (Joint Photographic Experts Group) data stream into an AFP (MO:DCA-P) or PostScript Level 2 data stream file.

The transform can process images compressed using baseline lossy JPEG compression. Only 8 bits per channel and Huffman coding are supported. The output can be bilevel (IM1 or IOCA FS10), 4-bit or 8-bit grayscale, or 24-bit YCbCr color (IOCA FS11). The transform automatically uses halftoning to convert the grayscale and color images to bilevel.

### Automatic Invocation

The PSF DSS automatically invokes the **jpeg2afp** transform command whenever you submit a JPEG file for printing. You can pass options to **jpeg2afp** using the **other-transform-options** attribute on the **pdpr** command or the **-o** flag of the AIX print commands and the **lprafp** command.

### Input and Output

**jpeg2afp** can process either standard input, or multiple files specified on the command line. If no input file is specified, **stdin** is assumed. Standard input is cached to a file (see the **-wrkdir** option) and then processed. Only a single JPEG file should be submitted via **stdin**. If multiple JPEG files are concatenated via standard input, all except the first one are ignored.

If an input file is specified on the command line, it can be either a JPEG file, a directory, or a file list (**-f** and **@** prefixes). Multiple input file specifications are allowed. The transform processes each file in the order in which it was specified on the command line. If the **-z** option is specified, a list of file names to be processed is also submitted via standard input. The files on the list are processed as if the list were given via the **-f** option on the same place on the command line as **-z**.

## jpeg2afp

If the file name points to a directory, **jpeg2afp** processes every file in that directory. The files are processed in the order they would be shown using the **ls -a** command. Directory search is not recursive, that is, the subdirectories are not searched.

If the file name is preceded by the **-f** option or the at sign (**@**), **jpeg2afp** assumes that the file contains the list of JPEG files to be processed. Each of the files in the list is processed in the order it was listed.

If a JPEG file has the extension **.jpg**, **.jpeg**, **.JPG**, or **.JPEG**, this extension need not be given explicitly. **jpeg2afp** first tries to open the file as specified and, if unsuccessful, tries to append the extensions **.jpg**, **.jpeg**, **.JPG**, and **.JPEG** in turn.

For example, suppose that:

- The directory `tFiles` contains the files `file1.jpg`, `file2.jpg`, `file3.jpg`, and `file4.jpg` and nothing else.
- The file `flist` in the current directory contains the two file names `tFiles/file2.jpg` and `tFiles/file3.jpg`. The names listed in the file list may have their extensions omitted.
- The file `flist2` contains the file name `tFiles/file4`. Again, the names listed in the file list may have their extensions omitted.

In order to process files `file1.jpg`, `file2.jpg`, `file3.jpg`, and `file4.jpg`, any of the following invocations of **jpeg2afp** would work:

```
jpeg2afp tFiles/file1.jpg tFiles/file2.jpg tFiles/file3.jpg tFiles/file4.jpg
jpeg2afp tFiles/file1 tFiles/file2 tFiles/file3 tFiles/file4
jpeg2afp tFiles/file*.jpg
jpeg2afp tFiles
jpeg2afp tFiles/file1 -fflist tFiles/file4
jpeg2afp tFiles/file1 -f flist tFiles/file4
jpeg2afp tFiles/file1 -f flist -f flist2
jpeg2afp tFiles/file1 @flist @flist2
```

The file list files allow the display text to be added for each file. A display text is any text starting with the pound character (**#**) and extending to the end of the line. The display text should follow the file name, and can extend over several lines, up to 2048 characters long. The initial **#** character on each line is discarded. If a display text is present for a file name, that text is displayed in the status and error messages instead of the file name. This is useful if the **jpeg2afp** is invoked using temporary files whose names are meaningless to the user. Any display text before the first file name is treated as comment and discarded. Display text is allowed also if the **-z** option is used to submit the file list via standard input.

The output file name can be either specified explicitly via the **-o** option, or derived from the input file name. If multiple input files have been specified, the default output file is standard output. If a single input file is given and the output file is not specified explicitly, the transform strips the **.jpg** or **.jpeg** extension from the input file name (if one is present), and appends the **.afp** extension for AFP output, or the **.ps** extension for PostScript output, to get the output file name.

To disable automatic output file name generation and force the default output stream to be the standard output in all cases, set the environment variable **JPEG2AFP\_o** to **-** or **stdout**, or, alternatively, put the line **o=-** or **o=stdout** into the configuration file and invoke that configuration file using the **-C** option or the **JPEG2AFP\_C** environment variable.

For example, all the following commands:

```
jpeg2afp myfile
jpeg2afp myfile.jpg
jpeg2afp myfile -o myfile.afp
```

have `myfile.afp` as the output file. Note that there is no requirement for the explicitly specified input and output files to have `.jpg` and `.afp` extensions. To process JPEG file `foo.bar` into an AFP file `foo.bar2`, invoke the transform using `jpeg2afp foo.bar -o foo.bar2`

The output data stream is MODCA-P IS/1, MODCAP-P IS/2, or PostScript Level 2. IS/1 images are bilevel and are encoded as IOCA Function Set 10 or IM1. IM1 images are uncompressed. IOCA FS10 output images can be either uncompressed, or compressed via one of the four available compression algorithms (see the `-cmp` option). The default is ITU-T T.6 Group 4 compression. IM1 images are always uncompressed. IS/2 images can be either bilevel, 4-bit or 8-bit grayscale, or 24 bit YCbCr color. Multibit images are encoded as IOCA Function Set 11. Be aware that the only product that supports IOCA FS11 images is the AFP Workbench, that is, grayscale and color AFP images are not currently supported by any printer.

PostScript Level 2 images can be uncompressed or ITU-T T.6 Group 4 bilevel, uncompressed 8-bit grayscale or uncompressed 24-bit RGB color. By default, the transform leaves scaling and halftoning to the printer (that is, color JPEG images are output as 24-bit RGB color images).

## Errors and Error Recovery

`jpeg2afp` divides errors into fatal and non-fatal. The fatal error categories are the following:

- Errors in the user-specified parameters, either in the environment variables, the configuration file, or the command line arguments. These errors include unrecognized options, invalid values for parameters, or inability to open the configuration file or the output file.
- Out of memory errors. The requested memory is larger than the memory specified using the `-M` option or the dynamic memory allocation has failed.
- Disk space errors. The transform guards against trying to write to a full file system. See the `-ms` and `-msf` options for setting the minimum free disk space requirements. If the file system is full, the transform deletes the partial output file before terminating.
- Internal errors.

In the case of a fatal error, the last output page might not be complete.

Errors encountered in the JPEG files are non-fatal and `jpeg2afp` attempts to recover from them. These errors include not being able to open an input file, an input file not being a JPEG file, or an input file containing features that cannot be processed. If the transform fails to open 15 or more input files, it assumes an error in the parameter list (for example, `-f` was used with a file that does not contain a file list) and terminates.

If an error is encountered in a file, the transform attempts to recover with the next input file. A warning message is issued. Errors and warnings are output to standard error.

For example, let a directory `tFiles` contain files `file1.jpg`, `file1.txt`, `file2.jpg` and `file3.jpg`, where `file1.txt` is an ASCII file. Invoking the transform via `jpeg2afp tFiles`

## jpeg2afp

processes the bilevel images in all three JPEG files correctly. A warning is issued that file1.txt is not a JPEG file.

Non-fatal errors can be made fatal by using the option **-term**, or the corresponding environment variable or configuration file entry. If **-term** is set, the transform terminates in error if it encounters an error in the JPEG data stream.

## Data Transformations

If the input image is grayscale or color, and the output image type is bilevel (IOCA FS10 or IM1), the transform internally scales the image to the desired size, then uses a halftoning algorithm (ordered dither, the default, or Floyd-Steinberg) to convert it to bilevel. In converting the image to bilevel, the characteristics of the output device such as dot shape and dot gain must be taken into consideration. The internal grayscale mapping table has been optimized for the 600-pel IBM Infoprint 4000 laser printer. The **-gcorr** option can be used to specify a different mapping of gray levels.

For very light or very dark images, the halftoning algorithms can be automatically recalibrated to preserve details that would be lost using the default calibration. See the **-alg** option for more information.

To maintain the image quality, scaling must be done prior to halftoning. Halftoning algorithm is very computation-intensive. Unless the images are small, **jpeg2afp** cannot process the color images fast enough to feed even a slow printer.

The size and position of the output image depend on several factors:

- The size specified to the transform
- The form map specified at print time
- The forms and options loaded in the printer

If the image is too large to fit on the page, it is trimmed to size by default. Use the **-fit scale** option to instruct the printer to scale the image to the paper size. If the paper size is not specified explicitly via the **-paper** option, the paper size defaults to US letter size (8.5 by 11 inches). If the image is larger than this, the paper dimensions are increased as necessary. If the paper size is been specified explicitly, it is not increased if the image does not fit on paper. The options **-l** and **-w** have the same effect as **-paper**.

The size of the actual image (as opposed to the paper size) is controlled by the **-scale** option. You can either specify a value of **orig** for the **-scale** option or give an actual size. If you specify **orig**, the output image is the same size as the input image. If you specify **-scale** with an actual size, the output image is scaled to the desired size. You can also specify a percentage for enlargement or reduction.

By default, the transform leaves scaling to the printer. The exceptions are images that are being halftoned, which are always scaled in the transform.

**Note:** Because JPEG files do not specify resolutions, the image is assumed to have the resolution of the output device.

If possible, **jpeg2afp** rewraps the JPEG raster data in MODCA-P headers.

For 8-bit grayscale and 24-bit color images, both JPEG and IOCA FS11 support JPEG compression algorithms. However, the JPEG standard has different

subsampling defaults than IOCA FS11. Thus, most 24-bit color images are not suitable for rewrapping, even if they use a JPEG compression algorithm and a color model supported by IOCA FS11.

Note also that JPEG is a lossy compression algorithm. Decompressing a JPEG image and then recompressing it for output might result in reduced image quality. For that reason, the default is to use no compression for the gray or color output.

Be aware that not all the printers support all the recognized IOCA compression standards. If the output image is IM1, the image is always decompressed and scaled in the transform.

## Parameters

**jpeg2afp** behavior is governed by many parameters. The parameters are set by the following hierarchy (least significant first):

- Internal defaults
- Environment variables
- Configuration file
- Command-line arguments

### Command Line Arguments

Note the following points regarding the command line arguments for the **jpeg2afp** transform:

- Options and input file names can appear on the command line in any order.
- When you run **jpeg2afp** as a standalone transform, the blank between option and value is optional (for example, both `-fittrim` and `-fit trim` are valid).
- When you use the **-o** flag of the **enq**, **lp**, **qprt**, or **lprafp** commands to pass options to **jpeg2afp**, no blank is permitted between option and value is optional (for example, `-o-fittrim` is valid, but `-o -fit trim` is not).
- When you use the **other-transform-options** attribute on the **pdpr** command to pass options to **jpeg2afp**, any string containing a blank must be surrounded by single quotes (for example, both `other-transform-options=-fittrim` and `other-transform-options='-fit trim'` are valid).
- All values except file names are case-insensitive.
- If an option is specified multiple times, the last specification remains in force.
- If multiple configuration file names are given, they are processed in order.

### Configuration File

The configuration file has entries of the form *option=value*, where each pair must reside on a separate line. Options and other syntax are the same as for the command line arguments and the option names are the same. Input files and configuration files cannot be specified in the configuration file (that is, nested configuration files are not supported). In the case of options without values (for example, **-v**), the equals sign must be present.

Some command line options, for example, **-calib**, cannot be used in the configuration file or as environment variables. Options available only on the command line are noted as such in their descriptions.

If you do not specify a configuration file on the command line with the **-C** option, the transform checks for the existence of the default configuration file, **/usr/lpp/psf/jpeg2afp/jpeg2afp.cfg**. If this file exists, the transform uses it as the configuration file.

## jpeg2afp

The following is an example of a valid configuration file:

```
scale = letter
r= 300
o = -
v=
```

Note that the spaces around the equals sign (=) are optional. In this example, the option-value pair `o = -` means that the default output file is the standard output. Output file name computation has been disabled.

### Environment Variables

Environment variables have the form `JPEG2AFP_option`, where *option* is the same as on the command line and the configuration file.

Some command line options, for example, `-calib`, cannot be used in the configuration file or as environment variables. Options available only on the command line are noted as such in their descriptions.

For example, to achieve the same effect as the configuration file in the last example, the following statements have to be executed in the calling shell:

```
export JPEG2AFP_scale=letter
export JPEG2AFP_r=300
export JPEG2AFP_o=-
export JPEG2AFP_v=" "
```

There must be some value set for each desired option. For options that do not take a value, specify a blank surrounded by double quotes, for example:

```
export JPEG2AFP_v=" "    correct
export JPEG2AFP_v=      has no effect
```

## Resource Search Path

For resource files, such as scan offset files and grayscale correction files, the transform searches the current directory by default. You can use the `-respath` option to specify a list of directories to be searched for such files. This resource path does not apply to the configuration file.

## Limitations

- Only Huffman coding with baseline DCT JPEG algorithm is supported.
- At most 8-bit grayscale and 24-bit color are supported.

## Acknowledgments

This software is partially based on the Independent JPEG Group's JPEG compression and decompression code.

## Options and Values

### @FileList

Specifies a name of a file that contains a list of files to be processed by the transform. If the `@` option is present, the output file defaults to standard output, even if the list of files contains only a single entry. Multiple `@` options are allowed. Also see the `-f` and `-z` options. The `@` is not preceded by the dash, and is implemented to maintain compatibility with the `ps2afp` transform.

`-a {ioca | ioca10 | ioca11 | im1 | PS.2}`

**-a {IO1\_G4 | IM1 | IO1 | IO1\_MMR | PSEG\_IO1\_G4 | PSEG\_IM1 | PSEG\_IO1 | PSEG\_IO1\_MMR | OVLY\_IO1\_G4 | OVLY\_IM1 | OVLY\_IO1 | OVLY\_IO1\_MMR}**

Choice of the output image type. The first syntax chooses between the IOCA FS 10 (**ioca**, **ioca10**), IOCA FS11 (**ioca11**), IM1, and PostScript Level 2 (**PS.2**) output. IOCA FS10 and IM1 yield bilevel images, while IOCA FS11 results in 4-bit or 8-bit gray or 24-bit color output (see option **-outbits**). Note that presently the only product that supports IOCA FS11 is the AFP Workbench. The output compression algorithm is set via the option **-cmp**. To set the page type (page, overlay, page segment or object), use the **-pagetype** option.

The second syntax is to maintain compatibility with the **ps2afp** transform, and sets the image type (**IO1** for IOCA FS10 or **IM1** for IM1 output), compression (**G4** for Group 4 or **MMR** for Group 3), and page type (**PSEG** for page segment or **OVLY** for overlay). If **PSEG** or **OVLY** is not specified, the output is a printable page. If no compression algorithm is specified, the output is not compressed. The second syntax cannot be used for IOCA FS11 output.

Some older printers do not support IOCA images. In such cases, the IM1 output type should be chosen. IM1 images are uncompressed and thus use more space. The processing might also take longer since the IM1 image cannot be scaled by the printer and so internal scaling algorithms must be used. See option **-alg**.

The default is **ioca** for IOCA FS10 output compressed via Group 4 algorithm.

This option is similar to the **image-out-format** document attribute on the **pdpr** command.

**-alg afp**

**-alg {htod1 | htfs}**

**-alg htcal1**

Choice of the scaling and halftoning algorithms. You can specify multiple choices, separated by commas, for one **-alg** option. The effect is the same as specifying multiple **-alg** options. For example, **-alg htfs,htcal1** is equivalent to **-alg htfs -alg htcal1**.

The scaling algorithms are:

- If **afp** is chosen, the scaling is done using the default algorithm in the printer. This makes the transform much faster. If the image must be reduced, however, this algorithm may drop some information from the image, such as thin lines.

For color images with bilevel output, the scaling is always done prior to the halftoning algorithm. If a grayscale or color output is chosen (**-a ioca11**), this option is ignored and the algorithm is set to **afp**.

The halftoning algorithms are:

- **htod1** uses an ordered dither with a screen derived from the value of the **-thresh** option. The default is an 85 line per inch screen.
- **htfs** uses the Floyd-Steinberg algorithm.

## jpeg2afp

- **htcal1** recalibrates the halftoning algorithm for each image. **htcal1** forces the transform to read the whole image into memory and requires an additional pass through the image. It should be used only for very light or very dark images.

The default is **htod1**. Each halftoning algorithm uses a different internal default calibration curve. If the automatic calibration is turned on, a still different set of calibration curves are used.

See options **-gcorr**, **-paper**, **-scale**, **-thresh**, **-l**, **-w**, **-x**, and **-y**.

### **-calib scanner**

#### **-calib {scanner | printer | patch | patchr},name1...**

Transform calibration for the scanner or printer. If **scanner** is specified, **-sgcorr** must be present. If **printer** is specified, **-sgcorr** may or may not be present. If **patch** or **patchr** is specified, **-sgcorr** (if present) is ignored. Detailed explanation of the calibration process is beyond the scope of this entry.

You cannot specify **-calib** in the configuration file or as an environment variable.

#### **-C ConfigurationFileName**

The name of a configuration file containing option-value pairs. If multiple **-C** options are given on the command line, they are processed in order. Specifying the configuration file on the command line overrides any specification done via the **JPEG2AFP\_C** environment variable.

The default configuration file is **/usr/lpp/psf/jpeg2afp/jpeg2afp.cfg**.

#### **-cmp {none | mh | mmr | g3 | g4 | jpeg}**

Choice of the output image compression algorithm:

- none** Uncompressed output
- mh** ITU-T T.4 G3 Modified Huffman
- mmr** IBM Modified Modified Read
- g3** ITU-T T.4 G3 Modified Read
- g4** ITU-T T.6 G4
- jpeg** JPEG non-differential Huffman coding with baseline DCT. The output image data should be compressed to reduce the file sizes and increase the printing speed.

The default compression is ITU-T T.6 Group 4 for bilevel images and no compression for grayscale or color images. Note that some printers may not support Group 4 compression algorithm and require using the **-cmp** option to choose a different one. The JPEG algorithm can compress only 8-bit grayscale and 24-bit color images. 4-bit grayscale images cannot be compressed.

#### **-crop t,b,l,r[i | m | p | d]**

Image cropping. *t,b,l,r* specify how much should be cropped from the image top, bottom, left edge, and right edge. The numbers are floating point and can be either positive or negative. Negative numbers indicate that a blank space should be inserted. The units are inches, millimeters, points, and dots (pels), with the default being dots. The cropping is specified in the context



of the output page, to that “top” means the top of the output page and so on, regardless of the **-rot** option. To crop, the transform will enlarge the image by the amount to be cropped, then crop the specified amount by manipulating the actual bitmap. The resulting image has the size as specified by the explicit (or implicit) **-scale** option. See also option **-j**.

If **-fit trim** is specified, the right and the bottom edge of the image are not cropped. Instead, the image grows as necessary. Because **-fit trim** causes the output data stream to contain the “position and trim” specification, the printer discards any extra image.

**-f** *FileList*

Specifies the name of a file that contains a list of files to be processed by the transform. If the **-f** option is present, the output file defaults to standard output, even if the list of files contains only a single entry. Multiple **-f** options are allowed. See also options **@** and **-z**.

**-fit {trim | scale}**

Determines whether the printer behavior will be position-and-trim or scale-to-fit if the image is too large to fit on the paper. The default is **trim**.

This option is equivalent to the **image-fit** document attribute on the **pdpr** command.

**-force** If present, this option forces **jpeg2afp** to decompress and recompress the image, regardless of other factors.

**-gcorr** *FileName*

Specifies a file with grayscale mapping table for halftoning of the grayscale and color images to bilevel for output. The mapping table must be provided to compensate for the printing characteristics of the particular output device and paper type, such as dot gain. This file must contain either:

- 256 real numbers, one for each level of gray in the 8-bit grayscale image
- The PostScript **settransfer** operator

The algorithm converts every image to 8-bit grayscale before applying the halftoning algorithm. The default internal mapping table has been optimized for the 600-peI IBM Infoprint 4000 laser printer. You shouldn't change this unless you know what you are doing. See also options **-alg** and **-thresh**. PostScript code submitted via the **-thresh** option can have the same effect as **-gcorr**.

**-j** *ScanOffsetFileName*

Sometimes input images must be shifted to get the desired positioning on the page. The scan offset file contains the directions for shifting. The file has the format of

```
[attribute]
values
:
values
[attribute]
values
:
values
```

Currently, the recognized attributes are **[Units]** (values **millimeters**, **mm**, **inches**, **in**, **points**, **dots**, **pels**) **[Page\_Offset\_Type]** (values **crop** or **grow**) and **[Page\_Offsets]**. The values for page offsets are in the format *FileName,Hhoriz,Vvert* Each entry refers to a file. The file names must be specified (or at least the leading comma must), but are currently ignored

## jpeg2afp

and the offset factors are applied to each file in turn. The *horiz* and *vert* values are the amount that the image is to be shifted, in the horizontal and vertical direction. The positive directions are down and right (that is, the origin is in the left upper corner of the page). The default units are millimeters. Like the values for the **-crop** option, the shifts are specified in the output space context.

Extra spaces and blank lines are allowed. Unrecognized attributes and their values are ignored. See the sample file **shift.sample**.

If the image is moved left or up, part of the bitmap is removed. If the image is moved down or right, removal is governed by the value of the **[Page\_Offset\_Type]** attribute. If **crop** is chosen, the transform removes the requisite amount from the right and bottom edges of the bitmap. If **grow** is chosen, the transform does not remove any space. The bitmap grows and the trimming, if any, is left to the printer. If the **-fit trim** option (the default) is specified, **[Page\_Offset\_Type]** defaults to **grow**. For **-fit scale**, **[Page\_Offset\_Type]** defaults to **crop**.

**-l {11i | yyy.yy[d | m | i | p]}**

Specifies the paper length. The optional units are **dots** (pels), **millimeters**, **inches**, or **points**. The default unit is dots. If the unit is dots, decimals (if any) are ignored. The default paper length is 11 inches. See options **-w** to set the paper width or **-paper** to set both dimensions at the same time.

**-M {0 | nnn}**

Limits the amount of memory available to **jpeg2afp**. *nnn* is the maximum amount of memory in kilobytes. A value of **0** means there is no memory limit. *nnn* can be set from **0** to the maximum value that AIX allows. The default is **0**.

**-ms {10 | nnn}**

Requires that at least *nnn* kilobytes of disk space be available on the file system that contains the output file. This limit is enforced every time data is written to the output file. If the output is standard output, this option is ignored. The default is **10**. See option **-msf**.

**-msf {0.1 | x.xxx}**

The number *x.xxx* is a real number between 0 and 1. It denotes the minimum space that must be left unused on the file system containing the output file. The space is given as a fraction of the total space in the file system. This limit is enforced every time data is written to the output file. If the output is standard output, this option is ignored. The default is **0.1**. See option **-ms**.

**-noterm**

See **[-term | -noterm]**.

**-nov** See **[-v | -nov]**.

**-o FileName**

Optional output file name. Specify **-** for standard output.

**-outbits NumberOfOutputBits**

Sets the number of bits per pel in output. This value must be **1**, **4**, **8**, or **24**. If the output image type is IOCA FS10 or IM1, the number of output bits is set to **1** and this option is ignored. For IOCA FS11 output, the default is **24**. Note that this number represents the maximum number of bits used per pel. Thus, even if the number of bits is set to **24**, a 4-bit grayscale image is still displayed in 4-bit format.

**-outcolor {rgb | ycbcr | ycrcb}**

Sets the output color model to RGB, YCbCr, or YCrCb if the image type is IOCA FS11 and the number of output bits is 24. Otherwise, this option is ignored. The default is **ycbcr**.

**-p {even | odd | nn | nn-mm | nn-}**

Specifies that the output should only contain the specified pages. If no **-p** option is given, all the pages are output. Multiple **-p** options may be specified. Their effect is cumulative. Regardless of the order in which the pages are specified, they are always printed in ascending order. The recognized values are:

**even** Print all even pages

**odd** Print all odd pages

*nn* Print page *nn*

*nn-mm*

Print pages *nn* to *mm*, inclusive.

*nn-* Print all pages starting with page *nn*

Pages are numbered starting with 1.

**-pagetype {page | overlay | ovly | pseg | object}**

Sets the output page type to be page, overlay, page segment or object. The same page type is set for every page in the output. Thus, unless option **-p** is used to select a single page, multiple overlays, page segments or overlays are stored in the output file. The default is **page**. See option **-a**.

**-paper {a5 | a4 | a3 | letter | folio | legal | ledger | xxx.xx,yyy.yy[d | m | i | p]}**

Specifies the output paper size. The supported values are:

**a3** A3 format (297 by 420 mm or 11.69 by 16.54 inches)

**a4** A4 format (210 by 297 mm or 8.27 by 11.69 inches)

**a5** A5 format (148 by 210 mm or 5.83 by 8.27 inches)

**letter** 8.5 by 11 inches (216 by 279 mm)

**folio** 8.5 by 13.0 inches (216 by 330 mm)

**legal** 8.5 by 14.0 inches (216 by 356 mm)

**ledger** 11.0 by 17.0 inches (279 by 432 mm)

*xx.xx,yy.yy*[**d | m | i | p**]

Horizontal and vertical page dimensions. The optional units are **dots** (pels), **millimeters**, **inches**, or **points**.

The default paper size is letter. If **-paper** is not used, the paper size is increased, if necessary, to contain the output image.

See options **-l**, **-w**, and **-scale**.

**-r {300 | nnn}**

The output device resolution, specified in dots per inch. The default is **300**.

This option is equivalent to the **default-printer-resolution** document attribute on the **pdpr** command.

**-respath directory[:directory...]**

Sets the search path for resource files, such as the scan offset files and grayscale calibration curve files. If a resource file name is specified as a relative name (does not start with a */*), the transform searches every directory in the path, in the order specified in the path, until it finds the file

## jpeg2afp

(or fails). See options **-j** and **-gcorr** for scan offsets and grayscale calibration curve. The default is the current directory.

**-rot** {**0** | **90** | **180** | **270**[**p** | **i**]}

The image is rotated in the clockwise direction by the amount specified. The default is zero, that is, no rotation.

If **p** is specified, the transform sets the output datastream in such a way that the printer performs the actual image rotation. If **i** is specified, the transform rotates the output bitmap. When **i** is chosen, the transform takes much longer to run and uses much more memory. If no letter is specified, the default or any previous value (such as the value specified in the configuration file) remains in force. The default is **p**.

**-scale** {**orig** | **a5** | **a4** | **a3** | **letter** | **folio** | **legal** | **ledger** | *xxx.xx,yy.yy*[**d** | **m** | **i** | **p**] | *xxx%*}

Specifies the output image size. The image is scaled to this size and centered in the area defined by the paper size and margin options. The supported values are:

**orig** Preserve the input image size, regardless of the printable paper area.

**a3** A3 format (297 by 420 mm or 11.69 by 16.54 inches)

**a4** A4 format (210 by 297 mm or 8.27 by 11.69 inches)

**a5** A5 format (148 by 210 mm or 5.83 by 8.27 inches)

**letter** 8.5 by 11 inches (216 by 279 mm)

**folio** 8.5 by 13.0 inches (216 by 330 mm)

**legal** 8.5 by 14.0 inches (216 by 356 mm)

**ledger** 11.0 by 17.0 inches (279 by 432 mm)

*xx.xx,yy.yy*[**d** | **m** | **i** | **p**]

Horizontal and vertical image dimensions. The optional units are **dots** (pels), **millimeters**, **inches**, or **points**.

*xxx%* Magnification relative to the original image size. Numbers below 100% mean reduction, while Numbers above 100% mean enlargement. For example, **-scale 200%** causes the output image to be twice as long and twice as wide as the input image.

The default image size is **orig**.

**-sgcorr** *FileName*

Specifies the name of the scanner-related calibration file. To use this option in the calibration process (with the option **-calib**) you must specify a single file name. If **-calib** is absent, this option is ignored.

A detailed discussion of **-sgcorr** is beyond the scope of this document.

**[-term | -noterm]**

Disables (**-term**) or enables (**-noterm**) error recovery.

- When error recovery is disabled, on encountering an error in a JPEG file, the transform terminates with an error message and a nonzero return code.
- When error recovery is enabled, the errors in JPEG files are treated as non-fatal. The transform attempts to recover with the next file. The return code is zero.

The default is **-noterm**.

**-thresh** *FileName*

Specifies a file that contains a PostScript Type 1 or Type 3 halftone dictionary. Alternatively, the PostScript code can specify the **setscreen** operator instead of a Type 1 dictionary. The halftone cell in the dictionary is used to overwrite the default ordered dither clustered dot halftone cell. If the PostScript code contains a transfer function, either in the halftone dictionary or specified by the **settransfer** operator, the current grayscale correction curve is overwritten as if **-gcorr** were used.

**[-v | -nov]**

Turns verbose mode on (**-v**) or off (**-nov**).

- When verbose mode is on, the transform prints a message as it opens each resource file, then echoes the command line, then prints a message for each file name as it is processed.
- When verbose mode is off, the transform prints only error messages.

The default is **-nov**.

**-w {8.5i | yyy.yy[d | m | i | p]}**

Specifies the paper width. The optional units are **dots** (pels), **millimeters**, **inches**, or **points**. The default unit is dots. The default page width is 8.5 inches. See options **-l** to set the paper length or **-paper** to set both dimensions at the same time.

**-wrkdir** *WorkDirectoryName*

Input to **jpeg2afp** from **stdin** must be cached on disk before it can be processed. This option specifies which directory to use for the caching of the standard input. If this option is absent or the directory cannot be opened, the transform first tries to use **/var/psf/jpeg2afp** as the working directory and, if **/var/psf/jpeg2afp** is absent, uses **/tmp**.

The **stdin** cache file is never visible to the user because it is immediately unlinked after creation. Thus, the cache file is always deleted when **jpeg2afp** finishes execution, even if **jpeg2afp** is killed or otherwise terminates in error.

**-x {0 | nnn.nn[d | m | i | p]}**

Specifies the left margin. The optional units are **dots** (pels), **millimeters**, **inches**, or **points**. The default unit is dots. The default is zero (no margin).

**-y {0 | nnn.nn[d | m | i | p]}**

Specifies the top margin. The optional units are **dots** (pels), **millimeters**, **inches**, or **points**. The default unit is dots. The default is zero (no margin).

**-z** Signifies that a list of files to be processed is submitted from standard input. See also options **-f** and **@**.

## line2afp Command: Transforms S/370 Line Data and ASCII Data to AFP

### Syntax

```
line2afp [cc=value] [cctype=value]
         [chars=FontName[, ...]] [fdeflib=PathList] [fileformat=value]
         [fontlib=PathList] formdef=FormDefinitionName [imageout=value]
         [inpxit=ProgramName] [inputdd=FileName] [msgdd=FileName]
         [outexit=ProgramName] [outputdd=FileName]
         [ovlylib=PathList] pagedef=PageDefinitionName
         [parmdd=FileName] [pdeflib=PathList]
         [prmode=value] [pseglib=PathList] [resexit=ProgramName]
         [reslib=PathList] [trc=value] [userlib=PathList]
```

With Infoprint Manager for AIX, if you need guidance in passing the **line2afp** command option syntax through the shell, refer to the documentation for the shell you are using in the *AIX for RS/6000 Commands Reference*.

Table 7 shows the **line2afp** command options that specify resource names or resource directories, and the corresponding AIX print command options and Infoprint attributes:

Table 7. *line2afp* Resource Options and Corresponding Options and Attributes

line2afp option	AIX -o flag option	Document attribute	Physical printer attribute
chars	-ochars	chars	
fdeflib	-orespath	resource-context-form-definition	resource-context-form-definition
fontlib	-osrchfontlib	resource-context-font	resource-context-font
formdef	-oformdef	form-definition	form-definition
ovlylib	-orespath	resource-context-overlay	resource-context-overlay
pagedef	-opagedef	page-definition	
pdeflib	-opdeflib	resource-context-page-definition	resource-context-page-definition
pseglib	-orespath	resource-context-page-segment	resource-context-page-segment
reslib	-orespath	resource-context	
userlib	-ouserlib	resource-context-user	

For these options, you should specify the same value with the **line2afp** command as you specify to Infoprint when you submit the print job or predefine for the physical printer where the job prints. In this way, the search paths and resources used at transform time are identical to the search paths and resources used at print time.

In addition to the usual command notational conventions, the **line2afp** command follows these additional rules. These rules apply to options you type at the command line. See also the **parmdd** option for the syntax of options contained in the **line2afp** option file.

- When the **line2afp** command processes any unrecognized or unsupported option, **line2afp** issues a message, ignores the option, and continues processing any remaining options. The **line2afp** command then stops processing.

- With Infoprint Manager for AIX, though the options themselves are not case-sensitive, associated values, such as file names, attribute names, and directory names *are* case-sensitive. For example,

```
formdef=F1MINE
```

is *not* the same as

```
formdef=f1mine
```

Be sure to specify these values in the case in which they exist in the file system (for external resources) or in the print file (for inline resources).

- If the same option is specified more than one time, the **line2afp** command uses the last value specified. For example, if you specify the following:

```
pagedef=P1MINE
```

```
pagedef=P1YOURS
```

the **line2afp** command uses page definition **P1YOURS** only.

## Description

The **line2afp** command transforms S/370 line data, mixed-mode data, and ASCII files into the AFP (MO:DCA-P) data stream, so that you can print the file on an Infoprint printer.

When you use the **line2afp** command to convert S/370 line data or ASCII data, you must specify a page definition (**pagedef** option). If the page definition names fonts, Infoprint uses those fonts. If the page definition does not name any fonts, and if you want the file to print with more than one font, then the input file must contain table reference characters (TRCs), and you must:

- Specify **trc=yes**.
- Use **chars** to indicate the fonts to be associated with each TRC.

If the page definition does not specify fonts, and you have not specified any TRCs, your job will print, although the output may not be formatted correctly.

If the page definition does not name any fonts, and you want the whole file to print with one font, then you must:

- Specify **trc=no**.
- Use **chars** to indicate the single fonts in which the file should be printed.

If the page definition does not specify fonts, and you have not specified any TRCs, your job will print, although the output may not be formatted correctly.

If the page definition does not name any fonts, and you want the whole file to print with one font, then you must:

The **line2afp** command searches for resources in the following order:

1. Paths specified by the **userlib** option for miscellaneous user resources. If **line2afp** is invoked as part of submitting a print job, the paths you specified with the **resource-context-user** attribute on the **pdpr** command, in an attributes file, or in a default document, are also searched.
2. Paths specified by the **fdeflib**, **fontlib**, **ovlylib**, **pdeflib**, and **pseglib** options for specific types of resources.
3. Paths specified by the **reslib** option. If **line2afp** is invoked as part of submitting a print job, the paths you specified with the **-orespath** flag on an AIX print

## line2afp

command, or with the **resource-context** attribute on the **pdpr** command, in an attributes file, or in a default document, are also searched.

4. Paths specified by the **PSFPATH** environment variable.
5. If **line2afp** is invoked as part of submitting a print job, the paths specified with the **resource-context-font**, **resource-context-form-definition**, **resource-context-overlay**, **resource-context-page-definition**, and **resource-context-page-segment** physical printer attributes for specific types of resources.
6. With AIX:
  - a. **/usr/lpp/psf/reslib**
  - b. **/usr/lpp/afpfonts**
  - c. **/usr/lpp/psf/fontlib**
7. With Windows NT or Window 2000, where *install\_path* indicates the path where you installed Infoprint Manager:
  - a. **\install\_path\reslib**
  - b. **\install\_path\afpfonts**
  - c. **\install\_path\fontlib**

When the **line2afp** command finds more than one resource with the same name in the same directory, it selects the resource to be used depending on the file extension. Table 8 shows the order in which resources with the same name but different file extensions are used by **line2afp**.

**Note:** If a file name includes a period (.), the file extension is that part of the file name that follows the period. For example, the file extension of the file name **ARTWORK.PSEG3820** is **PSEG3820**.

Table 8. File Extensions for Resources

<b>Type of Resource</b>	<b>File Extensions Searched (see note)</b>
BCOCA (bar code) objects	1. No file extension
Code pages	1. No file extension 2. <b>FONT3820</b> 3. <b>FONT38PP</b> 4. <b>CDP</b>
Coded fonts	1. No file extension 2. <b>FONT3820</b> 3. <b>FONT38PP</b> 4. <b>CFT</b>
Font character sets, 240-pel resolution	1. No file extension 2. <b>240</b> 3. <b>FONT3820</b> 4. <b>FONT38PP</b>
Font character sets, 300-pel resolution	1. <b>300</b> 2. <b>FONT300</b> 3. No file extension
Fonts, outline	1. <b>OLN</b> 2. <b>FONTOLN</b>
Form definitions	1. No file extension 2. <b>FDEF3820</b> 3. <b>FDEF38PP</b> 4. <b>FDE</b>
GOCA (graphics) objects	1. No file extension



Table 8. File Extensions for Resources (continued)

Type of Resource	File Extensions Searched (see note)
IOCA (IO image) objects	1. No file extension
Overlays	1. No file extension 2. <b>OVLY3820</b> 3. <b>OVLY38PP</b> 4. <b>OVL</b>
Page definitions	1. No file extension 2. <b>PDEF3820</b> 3. <b>PDEF38PP</b> 4. <b>PDE</b>
Page segments	1. No file extension 2. <b>PSEG3820</b> 3. <b>PSEG38PP</b> 4. <b>PSG</b> 5. <b>PSE</b>
Setup data	1. No file extension 2. <b>SETUP</b> 3. <b>SET</b> 4. <b>COMSETUP</b>
<b>Note:</b> All file extensions must be in upper case.	

The PSF DSS automatically invokes **line2afp** whenever you submit a line-data or unformatted ASCII job. You can specify **document-format=line-data** or **document-format=ascii** on the **pdpr** command, or **-odatatype=line** or **-odatatype=ascii** on an AIX print command or the **lprafp** command, or you can allow Infoprint to identify the data type.

## Flags and Values

You can specify many of these flags and values with the **other-transform-options** attribute on the **pdpr** command or with the **enq -o**, **lp -o**, **qprt -o**, or **lprafp -o** command.

See “pdpr Command: Submits Jobs” on page 63 and “Attributes for Documents and Default Documents” on page 449 or “Chapter 3. The -o Flag for AIX Print Commands” on page 103 for more information.

### **cc={yes | no}**

Specifies whether the input file has carriage-control characters.

Values are:

- yes** The file contains carriage-control characters. **yes** is the default.
- no** The file does not contain carriage-control characters.

Carriage-control characters, if present, are located in the first byte (column) of each line in a document. They are used to control how the line will be formatted (single space, double space, triple space, and so forth). In addition, other carriage-controls can be used to position the line anywhere on the page. If there are no carriage-controls, single spacing is assumed.

This option and the **cctype** option, used together, are equivalent to the document attribute **carriage-control-type** on the **pdpr** command.

### **cctype={z | a | m}**

Specifies the type of carriage-control characters in the input file. The

## line2afp

**line2afp** command supports ANSI carriage-control characters in either ASCII or EBCDIC encoding, as well as machine carriage-control characters. The **line2afp** command does not allow a mixture of ANSI and machine carriage-control characters within a file. Values are:

**z** The file contains ANSI carriage-control characters that are encoded in ASCII. **z** is the default.

The carriage-control characters are the ASCII hexadecimal values that directly relate to ANSI carriage-controls, which cause the action of the carriage-control character to occur *before* the line is printed. For example, if the carriage-control character is zero (X'30'), which represents double spacing, double spacing will occur *before* the line is printed.

**a** The file contains ANSI carriage-control characters that are encoded in EBCDIC.

The use of ANSI carriage-control characters cause the action of the carriage-control character to occur *before* the line of data is printed. For example, if the carriage-control character is a zero (X'F0'), which represents double spacing, the double spacing will occur *before* the line is printed.

**m** The file contains machine code carriage-control characters that are encoded in hexadecimal format.

The use of machine code carriage-control characters cause the action of the carriage-control character to occur *after* the line of data is printed. For example, if the carriage-control character is a X'11', which represents double spacing, the line will be printed and the double spacing will occur *after* the line is printed. In addition, machine code carriage-control has a set of carriage-control characters that perform the action, but do not print the associated line.

If you specify **cc=yes** but you do not specify **cctype**, the **line2afp** command assumes that the file contains ANSI carriage-control characters encoded in ASCII.

If you are not sure which type of carriage-control characters are in your input file, consult your system support group.

This option and the **cc** option, used together, are equivalent to the document attribute **carriage-control-type** on the **pdpr** command.

**chars=***FontName1, FontName2, FontName3, FontName4*

Specifies the file name of from one to four coded fonts to be used in processing the print file. A coded font specifies a character set and code page pair.

The value is:

*FontName*

The name of the desired coded font. The font name is limited to 4 alphanumeric or national characters, and should not include the 2-character prefix of the coded-font name (**X0** through **XG**). With Infoprint Manager for AIX, the font name is case-sensitive.

With Infoprint Manager for AIX, if you use the ASCII fonts that are supplied with Infoprint, use the 4-character names. If you use your own coded font that has a file name with more than 6 characters (including the *Xn* prefix), then do one of the following:

- Rename the font file to a shorter name. For example,  

```
mv X0423002 X04202
```
- Copy the font file to a file that has a shorter name. For example,  

```
cp X0423002 X04202
```
- Link the original font file to a shorter name. For example,  

```
ln -s X0423002 X04202
```

With Infoprint Manager for Windows NT and Windows 2000, if you use the ASCII fonts that are supplied with Infoprint, use the 4-character names. If you use your own coded font that has a file name with more than 6 characters (including the *Xn* prefix), then do one of the following:

- Rename the font file to a shorter name. For example,  

```
rename X0423002 X04202
```
- Copy the font file to a file that has a shorter name. For example,  

```
copy X0423002 X04202
```

When you use the **line2afp** command to convert S/370 line-mode data or unformatted ASCII data, you must specify a page definition (**pagedef** option). If the page definition names some fonts, the **line2afp** command uses those fonts, and ignores the **chars** option. If the page definition does not name any fonts (like the sample page definitions supplied with Infoprint), and if you want the file to print with more than one font, then the input file must contain table reference characters, and you must:

- Specify **trc=yes**.
- Use **chars** to indicate the fonts to be associated with each table reference character (TRC). *Fontname1* is associated with TRC 0, *FontName2* is associated with TRC 1, and so on.

If the page definition does not name any fonts, and you want the whole file to print with only one font, then the input file must not contain table reference characters and you must:

- Specify **trc=no**.
- Use **chars** to indicate the single font in which the file should be printed.

Consider the following when specifying fonts with the **chars** option:

- If your input file is unformatted ASCII, you can do one of the following:
  - Specify a font that has the appropriate ASCII code points. To specify a font search path, either use the **fontlib** option to specify it explicitly, or set the **PSFPATH** environment variable to search the appropriate directories. See “IBM AFP Fonts for ASCII Data” in *AFP Conversion and Indexing Facility: User’s Guide* for a list of suggested ASCII fonts.
  - Use the **apka2e** or **asciinpe** input record exit programs to convert the ASCII code points in the input file into EBCDIC, and use EBCDIC fonts. To do this, use the **inpexit** option, specifying:

**For AIX**

```
inpexit=/usr/lpp/psf/bin/apka2e
```

## line2afp

### For NT/2000

inpexit=c:\Program Files\IBM Printing Systems\bin\apka2e  
where this path assumes you installed into the default path.

If the ASCII input file contains form feeds or carriage returns, specify:

### For AIX

inpexit=/usr/lpp/psf/bin/asciinp

### For NT/2000

inpexit=c:\Program Files\IBM Printing  
Systems\bin\asciinp where this path assumes you installed  
into the default path.

- You can specify fonts with the **chars** option only if you want the entire file printed in a single printing direction. The **line2afp** command uses the fonts that have 0-degree character rotation for the specified direction. When a file requires fonts with more than one print direction or character rotation, you must specify the fonts in the page definition.
- You can specify from one to four fonts with the **chars** option. If you specify more than one font with the **chars** option, then the input file must contain table reference characters, and you must specify **trc=yes**.
- If you use **chars** to specify fonts, but you also use the **pagedef** option to specify a page definition that names fonts, the **chars** option is ignored. Therefore, if your page definition names fonts, you should not use **chars**.
- If you do not specify a **chars** option, and if no fonts are contained in the page definition you specified, the **line2afp** command uses the default font that is set in the printer's hardware.

This option is equivalent to the document attribute **chars** on the **pdpr** command.

### **fdeflib**=*PathList*

Specifies the directories in which form definitions are stored. The value is:

#### *PathList*

Any valid search path. The **line2afp** command searches the paths in the order in which they are specified.

With AIX, you must use a colon (:) to separate multiple paths.

With NT/2000, you must use a semi-colon (;) to separate multiple paths.

The **line2afp** command searches for the form definition in the following order:

1. The paths you specified with **userlib**, if any. If **line2afp** is invoked as part of submitting a print job, the paths you specified with the **resource-context-user** attribute on the **pdpr** command, in an attributes file, or in a default document, are also searched.
2. The paths you specified with **fdeflib**, if any. If **line2afp** is invoked as part of submitting a print job, the paths you specified with the **resource-form-definition** attribute on the **pdpr** command, in an attributes file, or in a default document, are also searched.
3. The paths you specified with **reslib**, if any. If **line2afp** is invoked as part of submitting a print job, the paths you specified with the **-orespath** flag

on an AIX print command, or with the **resource-context** attribute on the **pdpr** command, in an attributes file, or in a default document, are also searched.

4. The paths specified by the **PSFPATH** environment variable.
5. If **line2afp** is invoked as part of submitting a print job, the paths specified with the **resource-context-form-definition** physical printer attribute.
6. With AIX:
  - a. **/usr/lpp/psf/reslib**
  - b. **/usr/lpp/afpfonts**
  - c. **/usr/lpp/psf/fontlib**
7. With Windows NT or Window 2000, where *install\_path* indicates the path where you installed Infoprint Manager:
  - a. **\install\_path\reslib**
  - b. **\install\_path\afpfonts**
  - c. **\install\_path\fontlib**

For S/370 line data and for ASCII data that you want to format with a page definition, if you are transforming and printing a file by piping **line2afp**'s output to an AIX print command or the **pdpr** command, you should specify the same form definition search path on both sides of the pipe, unless you are sure that the same form definition will be found by **line2afp** and Infoprint using each program's default search path.

With Infoprint Manager for AIX, for S/370 line data and for ASCII data that you want to format with a page definition, if you are transforming and printing a file by specifying **-odatatype=line** with an AIX print command, you must specify the form definition search path with **-orespath** instead of **fdeflib**. For example:

```
enq -odatatype=line -oformdef=myfd -opagedef=mypdef
    -orespath=/home/greg/resources -Pprinter myfile
```

This option is equivalent to the document attribute **resource-context-form-definition** on the **pdpr** command.

**fileformat={record | record,*n* | stream | stream,(newline=**X'***nn'*)}**

Specifies the format of the input file. If you do not specify **fileformat**, the **line2afp** command uses **stream** as the default.

The **fileformat** option does not apply to input files that are resources. Resource files are in MO:DCA-P or AFP data stream format, and the **line2afp** command automatically determines that the file is a resource.

Values are:

#### **record**

The input file is formatted in S/370 record format, where the first two bytes of each line specify the length of the line. Files with **record** format typically are MVS or VM files that have a variable record format and are downloaded to AIX or Windows.

#### **record,*n***

The input file is formatted in such a way that each record (including AFP data stream and MO:DCA-P records) is a fixed length, *n* bytes long. The value of *n* is a number from 1 to 32767. The encapsulated size of the AFP structured field must be less than the

## line2afp

size of *n*. Files with **record,*n*** format typically are MVS or VM files that have a fixed record format and are downloaded to AIX or Windows.

### stream

The input file has no length information; it is a stream of data separated by a newline character. The AFP portion (if any) of the input file has its length information encapsulated in the structured field. Files with **stream** format typically come from a workstation operating system like AIX, Windows, OS/2, or DOS.

The **line2afp** command examines the first six bytes of the first line data record of the input file, to determine whether the input file is ASCII or EBCDIC. If **line2afp** determines that the input file is ASCII, **line2afp** looks for ASCII newline characters (X'0A') to delimit the end of a record. If **line2afp** determines that the input file is EBCDIC, **line2afp** looks for EBCDIC newline characters (X'25') to delimit the end of a record. The **line2afp** command does not include newline characters in the MO:DCA-P data stream that **line2afp** produces.

**stream** is the default.

### **stream,(newline=X'*nn*')**

Use **newline** to specify a hexadecimal value for the newline character in the input data file.

You can use **newline** when **line2afp**'s algorithm cannot determine the correct newline character (if blanks are at the beginning of the file, for instance). Or you can use **newline** if you want to specify a newline character that is not the standard default. For example, you could use **newline** as follows:

```
fileformat=stream,(newline=X'0D')
```

If **newline** is not specified, **line2afp** uses the algorithm specified under **fileformat=stream**.

This option is equivalent to the document attribute **new-line-options** on the **pdpr** command.

### **fontlib=PathList**

Specifies the directories in which fonts are stored.

The value is:

#### *PathList*

Any valid search path. The **line2afp** command searches the paths in the order in which they are specified.

With AIX, you must use a colon (:) to separate multiple paths.

With NT/2000, you must use a semi-colon (;) to separate multiple paths.

The **line2afp** command searches for the fonts in the following order:

1. The paths you specified with **userlib**, if any. If **line2afp** is invoked as part of submitting a print job, the paths you specified with the **resource-context-user** attribute on the **pdpr** command, in an attributes file, or in a default document, are also searched.

2. The paths you specified with **fontlib**, if any. If **line2afp** is invoked as part of submitting a print job, the paths you specified with the **-osrchfontlib** flag on an AIX print command, or with the **resource-context-font** attribute on the **pdpr** command, in an attributes file, or in a default document, are also searched.
3. The paths you specified with **reslib**, if any. If **line2afp** is invoked as part of submitting a print job, the paths you specified with the **resource-context** attribute on the **pdpr** command, in an attributes file, or in a default document, are also searched.
4. If **line2afp** is invoked as part of submitting a print job, the paths specified with the **resource-context-font** physical printer attribute.
5. The paths specified by the **PSFPATH** environment variable.
6. With AIX:
  - a. **/usr/lpp/psf/reslib**
  - b. **/usr/lpp/afpfonts**
  - c. **/usr/lpp/psf/fontlib**
7. With Windows NT or Window 2000, where *install\_path* indicates the path where you installed Infoprint Manager:
  - a. **\install\_path\reslib**
  - b. **\install\_path\afpfonts**
  - c. **\install\_path\fontlib**

For S/370 line data and for ASCII data that you want to format with a page definition, if you are transforming and printing a file by piping **line2afp**'s output to an AIX print command or the **pdpr** command, you should specify the same font search path on both sides of the pipe, unless you are sure that the same fonts will be found by **line2afp** and Infoprint using each program's default search path.

With Infoprint Manager for AIX, for S/370 line data and for ASCII data that you want to format with a page definition, if you are transforming and printing a file by specifying **-odatatype=line** with an AIX print command, you must specify the font search path (if any) with **-osrchfontlib** instead of **fontlib**, as shown in the following example:

```
enq -odatatype=line -osrchfontlib=/home/greg/resources
    -oformdef=myfdef -opagedef=mypdef -Pprinter myfile
```

**Note:** If the input file is ASCII data that you want to format with a page definition, you can do one of the following:

- Specify a font that has the appropriate ASCII code points. To specify a font search path, either use the **fontlib** option to specify it explicitly, or set the **PSFPATH** environment variable to search the appropriate directories.
- Use the **apka2e** or **asciinpe** input record exit to convert the ASCII code points in the input file into EBCDIC, and use EBCDIC fonts. To do this, use the **inpexit** option, specifying:

**For AIX**

```
inpexit=/usr/lpp/psf/bin/apka2e
```

**For NT/2000**

```
inpexit=c:\Program Files\IBM Printing
Systems\bin\apka2e where this path assumes you
installed into the default path.
```

## line2afp

or

### For AIX

```
inpxit=/usr/lpp/psf/bin/asciipe
```

### For NT/2000

```
inpxit=c:\Program Files\IBM Printing  
Systems\bin\asciipe where this path assumes you  
installed into the default path.
```

This option is equivalent to the document attribute **resource-context-font** on the **pdpr** command.

### **formdef=***FormDefinitionName*

Specifies the file name of the form definition. A form definition defines how a page of data is placed on a form, the number of copies of a page, any modifications to that group of copies, the paper source, and duplexing. The form definition is actually used at print time, not at transform time.

The value is:

#### *FormDefinitionName*

Any valid form definition file name. The *FormDefinitionName* can be 1 to 8 alphanumeric or national characters, including the two-character prefix, if there is one. For AIX, the *FormDefinitionName* is case-sensitive.

**Note:** If the file name of the form definition includes a file extension, do not use the file extension when specifying the form definition. For example, to use a form definition named **memo.FDEF38PP**, specify **formdef=memo**.

The **line2afp** command requires a form definition in order to process the input file (even though the form definition actually gets used at print time). If you do not specify **formdef=**, or if you specify **formdef=** without a form definition file name, the **line2afp** command will not work.

For S/370 line data and for ASCII data that you want to format with a page definition, if you are transforming and printing a file by piping **line2afp**'s output to an AIX print command or the **pdpr** command, you should specify the same form definition on both sides of the pipe. If you are using the default form definition for the target printer, you do not need to specify a form definition with the AIX print command or **pdpr** command.

The form definition you use may be located:

- In a directory
- Inline in the file (that is, within the file itself)

If the form definition file is in a directory, use the **userlib** option or **fdeflib** option to specify the path to the file. For example:

### For AIX

```
formdef=memo userlib=/usr/afp/resources
```

### For NT/2000

```
formdef=memo userlib=d:\afp\resources
```

or



**For AIX**

```
formdef=memo fdeflib=/usr/lib/formdefns
```

**For NT/2000**

```
formdef=memo fdeflib=d:\lib\formdefns
```

If the form definition is an inline resource, you must do the following:

- Specify **cc=yes** to indicate that the file contains carriage-control characters.
- Specify **formdef=FormDefinitionName**, where *FormDefinitionName* is the name of the inline form definition; or specify **formdef=dummy**.

If you specify **formdef=dummy** but the file does not include an inline form definition, the **line2afp** command looks for the form definition named **dummy**.

If you use **formdef** to specify an inline form definition that is different than the actual form definition used inline, the **line2afp** command looks for the **formdef** value instead of the inline form definition.

An input file can contain multiple form definitions, but only one form definition can be used for printing. If a file contains more than one inline form definition, and you specify **formdef=FormDefinitionName**, **line2afp** uses the first inline form definition named *FormDefinitionName*. If a file contains more than one inline form definition, and you specify **formdef=dummy**, **line2afp** uses the first inline form definition in the input file.

This option is equivalent to the document attribute **form-definition** on the **pdpr** command.

**imageout={asis | ioca}**

Specifies the format of the image data produced by the **line2afp** command in the output document.

Values are:

- asis** The **line2afp** command produces all image data in the same format that it was in the input file.
- ioca** The **line2afp** command produces all image data in the Image Object Content Architecture uncompressed format. **ioca** is the default.

This option is similar to the document attribute **image-out-format** on the **pdpr** command.

**inpexit=ProgramName**

Specifies the name or the full path name of the input record exit program. The **line2afp** command calls this program for every record (every line) it reads from the input file (**inputdd**). If you specify the file name without a path, the **line2afp** command searches for the exit program in the paths specified by the **PATH** environment variable. If you do not specify this option, the **line2afp** command will not use an input record exit program.

The value is:

*ProgramName*

Any valid input record exit program name. With Infoprint Manager for AIX, the exit program name is case-sensitive.

## line2afp

If the input file is unformatted ASCII, but the fonts you are using contain EBCDIC, not ASCII, code points (for example, you specify **chars=GT15**), you can specify:

With AIX:

### **/usr/lpp/psf/bin/apka2e**

Converts ASCII stream data to EBCDIC stream data.

### **/usr/lpp/psf/bin/asciinpe**

Converts unformatted ASCII data into a record format that contains an American National Standards Institute (ANSI) carriage control character in byte 0 of every record, and then converts the ASCII stream data to EBCDIC stream data.

With NT/2000:

### **c:\Program Files\IBM Printing Systems\bin\apka2e**

Converts ASCII stream data to EBCDIC stream data. This path assumes you installed into the default directory.

### **c:\Program Files\IBM Printing Systems\bin\asciinpe**

Converts unformatted ASCII data into a record format that contains an American National Standards Institute (ANSI) carriage control character in byte 0 of every record, and then converts the ASCII stream data to EBCDIC stream data. This path assumes you installed into the default directory.

If your input file uses fonts that have ASCII code points (for example, you specify **chars=H292**, or any of the fonts listed in "IBM AFP Fonts for ASCII Data" in *AFP Conversion and Indexing Facility: User's Guide*) you should *not* use the **apka2e** or **asciinpe** exit programs. However, if your unformatted ASCII file contains carriage returns and form feeds, you may want to specify the following exit program supplied with Infoprint:

### **For AIX: /usr/lpp/psf/bin/asciinp**

Converts unformatted ASCII data that contains carriage returns and form feeds into a record format that contains an American National Standards Institute (ANSI) carriage control character. This exit encodes the ANSI carriage control character in byte 0 of every record.

### **For NT/2000: c:\Program Files\IBM Printing Systems\bin\asciinp**

Converts unformatted ASCII data that contains carriage returns and form feeds into a record format that contains an American National Standards Institute (ANSI) carriage control character. This exit encodes the ANSI carriage control character in byte 0 of every record.

This option is equivalent to the document attribute **input-exit** on the **pdpr** command.

### **inputdd=FileName**

Specifies the full path name of the input file that the **line2afp** command will process. If you do not specify **inputdd**, the **line2afp** command uses standard input.

You cannot use **inputdd=FileName** on the command line with the **enq**, **lp**, **qprt**, or **lprafp** commands, or with the **other-transform-options** attribute on the **pdpr** command. You can only use **inputdd=FileName** with the **line2afp** command.

**msgdd=FileName**

Specifies the name or the full path name of the file where the **line2afp** command writes error messages. If you specify the file name without a path, the **line2afp** command puts the error file into your current directory. If you do not specify **msgdd**, the **line2afp** command uses standard error for its message output.

This option is equivalent to the document attribute **transform-message-file-name** on the **pdpr** command.

**outexit=ProgramName**

Specifies the name or the full path name of the output record exit program. The **line2afp** command calls this program for every output record (every line) it writes to the output document file (**outputdd**). If you specify the file name without a path, the **line2afp** command searches for the file name in the paths specified by the PATH environment variable. If you do not specify this option, the **line2afp** command will not use an output record exit program.

The value is:

*ProgramName*

Any valid output record exit program name. With Infoprint Manager for AIX, the exit program name is case-sensitive.

This option is equivalent to the document attribute **output-exit** on the **pdpr** command.

**outputdd=FileName**

Specifies the name or the full path name of the output document file. If you specify the file name without a path, the **line2afp** command puts the output file into your current directory. If you do not specify **outputdd**, the **line2afp** command writes the output to standard output.

You cannot use **outputdd=FileName** on the command line with the **enq**, **lp**, or **qprt** commands, or with the **other-transform-options** attribute on the **pdpr** command. You can only use **outputdd=FileName** with the **line2afp** command.

This option is equivalent to the document attribute **transform-output-file-name** on the **pdpr** command.

**ovlylib=PathList**

Specifies the directories in which overlays are stored. The value is:

*PathList*

Any valid search path. The **line2afp** command searches the paths in the order in which they are specified.

With AIX, you must use a colon (:) to separate multiple paths.

With NT/2000, you must use a semi-colon (;) to separate multiple paths.

The **line2afp** command searches for an overlay in the following order:

1. The paths you specified with **userlib**, if any. If **line2afp** is invoked as part of submitting a print job, the paths you specified with the

## line2afp

**resource-context-user** attribute on the **pdpr** command, in an attributes file, or in a default document, are also searched.

2. The paths you specified with **ovlylib**, if any. If **line2afp** is invoked as part of submitting a print job, the paths you specified with the **resource-context-overlay** attribute on the **pdpr** command, in an attributes file, or in a default document, are also searched.
3. The paths specified in **reslib**, if any. If **line2afp** is invoked as part of submitting a print job, the paths you specified with the **-orespath** flag on an AIX print command, or with the **resource-context** attribute on the **pdpr** command, in an attributes file, or in a default document, are also searched.
4. If **line2afp** is invoked as part of submitting a print job, the paths specified with the **resource-context-overlay** physical printer attribute.
5. The paths specified by the **PSFPATH** environment variable.
6. With AIX:
  - a. **/usr/lpp/psf/reslib**
  - b. **/usr/lpp/afpfonts**
  - c. **/usr/lpp/psf/fontlib**
7. With Windows NT or Window 2000, where *install\_path* indicates the path where you installed Infoprint Manager:
  - a. **\install\_path\reslib**
  - b. **\install\_path\afpfonts**
  - c. **\install\_path\fontlib**

For S/370 line data and for ASCII data that you want to format with a page definition, if you are transforming and printing a file by piping **line2afp**'s output to an AIX print command or the **pdpr** command, you should specify the same overlay search path on both sides of the pipe, unless you are sure that the same overlays will be found by **line2afp** and Infoprint using each program's default search path.

Infoprint Manager for AIX, for S/370 line data and for ASCII data that you want to format with a page definition, if you are transforming and printing a file by specifying **-odatatype=line** with an AIX print command, you must specify the overlay search path with **-orespath** instead of **ovlylib**. For example:

```
enq -odatatype=line -oformdef=myfd -opagedef=mypd  
-orespath=/home/greg/resources -Pprinter myfile
```

This option is equivalent to the document attribute **resource-context-overlay** on the **pdpr** command.

### **pagedef=PageDefinitionName**

Specifies the file name of the page definition. A page definition defines the page format that the **line2afp** command uses to compose the input file into pages. The page definition is actually used at transform time, not at print time.

The value is:

*PageDefinitionName*

Any valid page definition file name. The *PageDefinitionName* can

be 1 to 8 alphanumeric or national characters, including the two-character prefix, if there is one. With AIX, the **pdefname** is case-sensitive.

**Note:** If the file name of the page definition includes a file extension, do not use the file extension when specifying the page definition. For example, to use a page definition named **memo.PDEF38PP**, specify **pagedef=memo**.

The **line2afp** command requires a page definition in order to process the input file. If you do not specify **pagedef=**, or if you specify **pagedef=** without a page definition file name, the **line2afp** command will not work.

The page definition you use may be located:

- In a directory
- Inline in the file (that is, within the file itself)

If the page definition file is in a directory, use the **userlib** option or **pdeflib** option to specify the path to the file. For example:

**For AIX**

```
pagedef=memo userlib=/usr/afp/resource
```

**For NT/2000**

```
pagedef=memo userlib=d:\afp\resource
```

or

**For AIX**

```
pagedef=memo pdeflib=/usr/lib/pagedefns
```

**For NT/2000**

```
pagedef=memo pdeflib=d:\lib\pagedefns
```

If the page definition is an inline resource, you must do the following:

- Specify **cc=yes** to indicate that the file contains carriage-control characters.
- Specify **pagedef=PageDefinitionName**, where *PageDefinitionName* is the name of the inline page definition; or specify **pagedef=dummy**.

If you specify **pagedef=dummy** but the file does not include an inline page definition, the **line2afp** command looks for the page definition named **dummy**.

If you use **pagedef** to specify an inline page definition that is different than the actual page definition used inline, the **line2afp** command looks for the **pagedef** value instead of the inline page definition.

An input file can contain multiple page definitions, but only one page definition can be used by the **line2afp** command. If a file contains more than one inline page definition, and you specify **pagedef=PageDefinitionName**, **line2afp** uses the first inline page definition named *PageDefinitionName*. If a file contains more than one inline page definition, and you specify **pagedef=dummy**, the **line2afp** command uses the first inline page definition in the input file.

This option is equivalent to the document attribute **page-definition** on the **pdpr** command.

## line2afp

### **parmdd=FileName**

Specifies the name or the full path name of a file that contains the **line2afp** options and their values. If you specify the file name without a path, the **line2afp** command searches for the file name in your current directory.

You may find it convenient to put the **line2afp** options and values into a file, so that you do not have to type all of them on the command line whenever you use **line2afp**.

Values are:

#### *FileName*

The name of the file containing **line2afp** command options and values.

#### **Notes:**

1. The beginning delimiter for comments is `/*`. For example:

```
formdef=F1TEMP /* Temporary formdef
formdef=F1PROD /* Production-level formdef
```

Comments can appear anywhere, but the **line2afp** command ignores all information in the line following the `/*` character string.

2. Each option must be on a separate line. For example:

```
chars=GT10 cctype=a /* This is NOT allowed.
```

3. If the option file contains the name of the input file (**inputdd=FileName**), you cannot specify the option file with an AIX print command's **-o** flag or with the **other-transform-options** attribute on the **pdpr** command. For example, these commands are not valid:

```
enq -odatatype=line -oparmdd=myparms
pdpr -x "document-format=line-data
      other-transform-options='parmdd=myparms '"
```

However, these are valid:

```
line2afp parmdd=myparms | enq
line2afp parmdd=myparms | pdpr -d my-printer
```

### **pdeflib=PathList**

Specifies the directories in which page definitions are stored.

The value is:

#### *PathList*

Any valid search path. The **line2afp** command searches the paths in the order in which they are specified.

With AIX, you must use a colon (:) to separate multiple paths.

With NT/2000, you must use a semi-colon (;) to separate multiple paths.

The **line2afp** command searches for a page definition in the following order:

1. The paths you specified with **userlib**, if any. If **line2afp** is invoked as part of submitting a print job, the paths you specified with the **resource-context-user** attribute on the **pdpr** command, in an attributes file, or in a default document, are also searched.
2. The paths you specified with **pdeflib**, if any. If **line2afp** is invoked as part of submitting a print job, the paths you specified with the

**resource-context-page-definition** attribute on the **pdpr** command, in an attributes file, or in a default document, are also searched.

3. The paths specified in **reslib**, if any. If **line2afp** is invoked as part of submitting a print job, the paths you specified with the **-orespath** flag on an AIX print command, or with the **resource-context** attribute on the **pdpr** command, in an attributes file, or in a default document, are also searched.
4. If **line2afp** is invoked as part of submitting a print job, the paths specified with the **resource-context-page-definition** physical printer attribute.
5. The paths specified by the **PSFPATH** environment variable.
6. With AIX:
  - a. **/usr/lpp/psf/reslib**
  - b. **/usr/lpp/afpfonts**
  - c. **/usr/lpp/psf/fontlib**
7. With Windows NT or Window 2000, where *install\_path* indicates the path where you installed Infoprint Manager:
  - a. *install\_path*\reslib
  - b. *install\_path*\afpfonts
  - c. *install\_path*\fontlib

This option is equivalent to the document attribute **resource-context-page-definition** on the **pdpr** command.

**prmode={SOSI1 | SOSI2 | aaaaaaaaa}**

Specifies the type of data in the input file and whether the **line2afp** command must perform optional processing of that data.

Values are:

**SOSI1** Specifies that each shift-out, shift-in code be converted to a blank and a Set Coded Font Local text control.

**SOSI2** Specifies that each shift-out, shift-in code be converted to a Set Coded Font Local text control.

*aaaaaaaa*

Any 8-byte alphanumeric string. This value is supplied to all of the ACIF user exits. (Refer to *AFP Conversion and Indexing Facility: User's Guide* for information about ACIF user exits.)

For the **SOSI** process modes to work correctly, the first font specified in the **chars** option (or in a font list in a page definition) must be a single-byte font, and the second font must be a double-byte font.

This option is equivalent to the document attribute **shift-out-shift-in** on the **pdpr** command.

**pseglib=PathList**

Specifies the directories in which page segments and BCOCA, GOCA, and IOCA objects are stored.

The value is:

*PathList*

Any valid search path. The **line2afp** command searches the paths in the order in which they are specified.

## line2afp

With AIX, you must use a colon (:) to separate multiple paths.

With NT/2000, you must use a semi-colon (;) to separate multiple paths.

The **line2afp** command searches for page segments in the following order:

1. The paths you specified with **userlib**, if any. If **line2afp** is invoked as part of submitting a print job, the paths you specified with the **resource-context-user** attribute on the **pdpr** command, in an attributes file, or in a default document, are also searched.
2. The paths you specified with **pseglib**, if any. If **line2afp** is invoked as part of submitting a print job, the paths you specified with the **resource-context-page-segment** attribute on the **pdpr** command, in an attributes file, or in a default document, are also searched.
3. The paths specified in **reslib**, if any. If the **line2afp** command is invoked as part of submitting a print job, the paths you specified with the **-orespath** flag on an AIX print command, or with the **resource-context** attribute on the **pdpr** command, in an attributes file, or in a default document, are also searched.
4. If **line2afp** is invoked as part of submitting a print job, the paths specified with the **resource-context-page-segment** physical printer attribute.
5. The paths specified by the **PSFPATH** environment variable.
6. With AIX:
  - a. **/usr/lpp/psf/reslib**
  - b. **/usr/lpp/afpfonts**
  - c. **/usr/lpp/psf/fontlib**
7. With Windows NT or Window 2000, where *install\_path* indicates the path where you installed Infoprint Manager:
  - a. **\install\_path\reslib**
  - b. **\install\_path\afpfonts**
  - c. **\install\_path\fontlib**

For S/370 line data and for ASCII data that you want to format with a page definition, if you are transforming and printing a file by piping **line2afp**'s output to an AIX print command or the **pdpr** command, you should specify the same page segment search path on both sides of the pipe, unless you are sure that the same page segments will be found by **line2afp** and Infoprint using each program's default search path.

For S/370 line data and for ASCII data that you want to format with a page definition, if you are transforming and printing a file by specifying **-odatatype=line** with an AIX print command, you must specify the page segment search path with **-orespath** instead of **pseglib**. For example:

```
enq -odatatype=line -oformdef=myfd -opagedef=mypd  
-orespath=/home/greg/resources -Pprinter myfile
```

This option is equivalent to the document attribute **resource-context-page-segment** on the **pdpr** command.

### **resexit=ProgramName**

Specifies the name or the full path name of the resource exit program. This is the program the **line2afp** command calls each time it attempts to retrieve a requested resource from a directory. If you specify the file name without a



path, the **line2afp** command searches for the file name in the paths specified by the **PATH** environment variable. If you do not specify this option, the **line2afp** command does not use a resource exit program. The exit program name is case-sensitive.

The value is:

*ProgramName*

Any valid resource exit program name.

This option is equivalent to the document attribute **resource-exit** on the **pdpr** command.

**reslib=PathList**

Specifies the paths for the system resource directories. System resource directories typically contain resources that are shared by many users. The directories can contain any AFP resources (fonts, page segments, overlays, page definitions, or form definitions).

For S/370 line data and for ASCII data that you want to format with a page definition, if you are transforming and printing a file by piping **line2afp**'s output to an AIX print command or the **pdpr** command, you should specify the same resource search path on both sides of the pipe, unless you are sure that the same resources will be found by **line2afp** and Infoprint using each program's default search path.

For S/370 line data and for ASCII data that you want to format with a page definition, if you are transforming and printing a file by specifying **-odatatype=line** with an AIX print command, you must specify the search path for AFP resources with **-orespath** instead of **reslib**. For example:

```
enq -odatatype=line -oformdef=myfd -opagedef=mypd
    -orespath=/home/greg/resources -Pprinter myfile
```

The value is:

*PathList*

Any valid search path. The **line2afp** command searches the paths in the order in which they are specified.

With AIX, you must use a colon (:) to separate multiple paths.

With NT/2000, you must use a semi-colon (;) to separate multiple paths.

The **line2afp** command searches for resources in the following order:

1. Paths specified by the **userlib** option for miscellaneous user resources, or the **resource-context-user** attribute on the **pdpr** command if **line2afp** was invoked as part of submitting a print job.
2. Paths specified by the **fdeflib**, **fontlib**, **ovlylib**, **pdeflib**, and **pseglib** options for specific types of resources or the equivalent options of an AIX print command or equivalent document attributes on the **pdpr** command if **line2afp** was invoked as part of submitting a print job.
3. Paths specified by the **reslib** option, or the **-orespath** flag of an AIX print command or the **resource-context** attribute on the **pdpr** command if **line2afp** was invoked as part of submitting a print job.
4. Paths specified by the **PSFPATH** environment variable.
5. If **line2afp** is invoked as part of submitting a print job, the paths specified with the **resource-context-font**, **resource-context-form-definition**, **resource-context-overlay**, **resource-context-page-**

## line2afp

**definition**, and **resource-context-page-segment** physical printer attributes for specific types of resources.

6. With AIX:
  - a. **/usr/lpp/psf/reslib**
  - b. **/usr/lpp/afpfonts**
  - c. **/usr/lpp/psf/fontlib**
7. With Windows NT or Window 2000, where *install\_path* indicates the path where you installed Infoprint Manager:
  - a. **\install\_path\reslib**
  - b. **\install\_path\afpfonts**
  - c. **\install\_path\fontlib**

This option is equivalent to the document attribute **resource-context** on the **pdpr** command.

### **trc={yes | no}**

Specifies whether the input file contains table reference characters (TRCs). Some applications may produce output that uses different fonts on different lines of a file by specifying TRCs at the beginning of each line after the carriage-control character, if one is present.

Values are:

- yes** The input file contains table reference characters.
- no** The input file does not contain table reference characters. **no** is the default.

Consider the following when you use TRCs:

- The order in which the fonts are specified in the **chars** option establishes which number is assigned to each associated TRC. For example, the first font specified is assigned 0, the second font 1, and so on.
- If you specify **trc=yes** but TRCs are not contained in the file, the **line2afp** command interprets the first character (or second, if carriage-control characters are used) of each line as the font identifier. Consequently, the font used to process each line of the file may not be the one you expect, and one byte of data will be lost from each line.
- If you specify **trc=no** or you do not specify **trc** at all, but your data contains a TRC as the first character (or second if carriage-control characters are used) of each line, the **line2afp** command interprets the TRC as a text character in the processed output, rather than using it as a font identifier.

This option is equivalent to the document attribute **table-reference-characters** on the **pdpr** command.

### **userlib=PathList**

Specifies the names of user directories containing AFP resources for processing the input file. The directories can contain any AFP resources (fonts, page segments, overlays, page definitions, or form definitions).

By convention, these resources are typically used by one user, as opposed to the system resources (specified with the **reslib** option) that are shared by many users. Therefore, you should use the **userlib** option to specify resources that are not retrieved with the **fdeflib**, **fontlib**, **ovlylib**, **pdeflib**, or **pseglib** options.

The value is:

#### *PathList*

Any valid search path. The **line2afp** command searches the paths in the order in which they are specified.

With AIX, you must use a colon (:) to separate multiple paths.

With NT/2000, you must use a semi-colon (;) to separate multiple paths.

The **line2afp** command searches for resources in the following order:

1. Paths specified by the **userlib** option, or the **resource-context-user** attribute on the **pdpr** command if **line2afp** was invoked as part of submitting a print job.
2. Paths specified by the **fdeflib**, **fontlib**, **pdeflib**, **pseglib**, **ovlylib**, options for specific types of resources or the equivalent options of an AIX print command or equivalent document attributes on the **pdpr** command if **line2afp** was invoked as part of submitting a print job.
3. Paths specified by the **reslib** option, or the **-orespath** flag of an AIX print command or the **resource-context** attribute on the **pdpr** command if **line2afp** was invoked as part of submitting a print job.
4. Paths specified by the **PSFPATH** environment variable.
5. If **line2afp** is invoked as part of submitting a print job, the paths specified with the **resource-context-font**, **resource-context-form-definition**, **resource-context-overlay**, **resource-context-page-definition**, and **resource-context-page-segment** physical printer attributes for specific types of resources.
6. With AIX:
  - a. **/usr/lpp/psf/reslib**
  - b. **/usr/lpp/afpfonts**
  - c. **/usr/lpp/psf/fontlib**
7. With Windows NT or Window 2000, where *install\_path* indicates the path where you installed Infoprint Manager:
  - a. **\install\_path\reslib**
  - b. **\install\_path\afpfonts**
  - c. **\install\_path\fontlib**

## Examples

- To print a “flat” ASCII file called `timesheet` that does not contain carriage controls, on the Infoprint printer named `servC-1p`, enter:

```
pdpr -p servC-1p -x "document-format=line-data
form-definition=FDEF1 page-definition=PDEF3 input-exit=apka2e
carriage-control-type=none" timesheet
```

Because you specified `document-format=line data`, Infoprint invokes the **line2afp** command. Because you specified `form-definition=FDEF1`, the **line2afp** command uses the FDEF1 form definition. Because you specified `page-definition=PDEF3`, the **line2afp** command uses the PDEF3 page definition.

If the PDEF3 page definition specifies 2-up printing, then the `timesheet` file prints 2-up — that is, with two “pages” printed side by side on the same physical page.

- On AIX, assume that you want to print a S/370 line data file called `statements`. Assume that the file contains ANSI carriage-control characters.

## line2afp

To print this file on the Infoprint printer named servA-1p; use form definition FDEF6 in your current directory (/usr/liz/fdefs) and use page definition P1USER10 which might be in the directory /usr/res/pdefs1 or in the directory /usr/res/pdefs2, enter:

```
pdpr -p servA-1p -x "document-format=line-data form-definition=FDEF6
resource-context=/usr/liz/fdefs page-definition=P1USER10
resource-context-page-definition=/usr/res/pdefs1:/usr/res/pdefs2
carriage-control-type=ansi-ebcdic new-line-options=record"
/usr/370/statements
```

- Because you specified document-format=line data, Infoprint invokes the **line2afp** command.
- Because you specified page-definition=P1USER10, the **pdpr** command tells the **line2afp** command to use the page definition named P1USER10.
- Because you specified resource-context-page-definition, the **pdpr** command tells the **line2afp** command to search the two directories you specified for the page definition.
- Because you specified form-definition=FDEF6, the **pdpr** command tells the **line2afp** command to use the form definition named FDEF6.
- Because you specified carriage-control-type=ansi-ebcdic, and new-line-options=record, the **pdpr** command gives **line2afp** information about the data stream format of statements.

- Suppose you downloaded a file called myfile from a S/370 host to the Windows NT/2000 PC. The file transfer process converted the file's EBCDIC encoding to ASCII; the file still retains table reference characters and carriage controls. The file also retains the line length it had on the host (100 characters long). Also suppose that your current directory is d:\Host.Files.

To print this file on the Infoprint printer BServ-1p; use the coded fonts Courier 12-pitch (**X042B2**) and Times New Roman 14-pitch (**X0N2D2**) for the output; use the form definition called F1USER10 in your current directory; and use the page definition called MYP1 (which does not name any fonts) in your current directory, enter:

```
pdpr -X 370files.X myfile
```

where the attributes file named 370files.X contains the following settings:

```
document-format=line-data
chars=42B2,N202
form-definition=F1USER10
resource-context=d:\Host.Files
page-definition=MYP1
resource-context-page-definition=d:\Host.Files
new-line-options=record,100
table-reference-characters=yes
carriage-control-type=ansi-ascii
printer-name-requested=BServ-1p
```

- Because you specified document-format=line-data, Infoprint invokes the **line2afp** command.
- The page definition you specified with page-definition does not name any fonts, but the input file contained table reference characters that indicate when fonts should be changed. You specified table-reference-characters=yes and chars=42B2,N2D2, and **pdpr** passes these values to **line2afp**.

You had to use resource-context-page-definition to specify the path to the page definition; **line2afp** does not automatically look in your current directory.

- Because you specified chars=42B2,N2D2, **pdpr** tells **line2afp** to associate font 42B2 with the first table reference character, and font N2D2 with the second table reference character. Any lines in the input file that begin with table

reference character 0 will now print using font 42B2; lines beginning with table reference character 1 will print using font N2D2.

- Because you specified `form-definition=F1USER10`, **pdpr** tells **line2afp** to use form definition F1USER10. You had to use **resource-context** to specify the path to the form definition; **pdpr** and **line2afp** do not automatically look in your current directory.
- Suppose you downloaded a file called `myfile` from a S/370 host to the RS/6000. The file transfer process converted the file's EBCDIC encoding to ASCII; the file still retains table reference characters, plus ANSI carriage controls. You want to print this file on the Infoprint printer `servC-1p`, but you do not have any ASCII fonts; you only have the EBCDIC coded fonts Gothic 10-pitch (**X0GT10**) and Gothic 12-pitch (**X0GT12**).

To print this file using the form definition called F1USER10 and the page definition called MYPDEF2, which does not name any fonts, enter:

```
pdpr -p servC-1p -x "document-format=line-data
chars=GT10,GT12 input-exit=apka2e
form-definition=F1USER10 page-definition=MYPDEF2
table-reference-characters=yes
carriage-control-type=ansi-ebcdic
resource-context=/usr/mydir" myfile
```

- Because you specified `document-format=line-data`, Infoprint invokes the **line2afp** command.
- The page definition you specified with **page-definition** does not name any fonts, but the input file contains table reference characters that specify when fonts are to be changed. You specified `table-reference-characters=yes` and `chars=GT10,GT12`, and **pdpr** passes these values to **line2afp**.
- Because you specified `chars=GT10,GT12`, **pdpr** tells **line2afp** to associate font GT10 with the first table reference character, and font GT12 with the second table reference character. Any lines in the input file that begin with table reference character 0 will now print using font GT10; lines beginning with table reference character 1 will print using font GT12.
- Because you specified `input-exit=apka2e`, **pdpr** tells **line2afp** to convert the ASCII input file into EBCDIC so you can use your EBCDIC coded fonts (GT10 and GT12). Your carriage controls are also in EBCDIC now, so you have to specify `carriage-control-type=ansi-ebcdic`. This example assumes you have `/usr/lpp/psf/bin` in your **PATH** environment variable.
- Because you specified `form-definition=F1USER10`, **pdpr** tells **line2afp** to use form definition F1USER10. You had to use **resource-context** to specify the path to the form definition; **pdpr** and **line2afp** do not automatically look in your current directory.

## Files

For AIX:

**/usr/lpp/psf/bin/line2afp**

Symbolic link to the **acif** command

**/usr/lpp/psf/bin/acif**

The **acif** command

**/usr/lpp/psf/acif/apkinp.c, apkind.c, apkres.c, apkout.c, apka2e.c, asciinp.c, asciinpe.c**

**acif** user exits (see *AFP Conversion and Indexing Facility: User's Guide* for more information)

## line2afp

**/usr/lpp/psf/bin/apka2e, apkinp, apkind, apkres, apkout, apka2e, asciinp, asciinpe**

User exit executables (see *AFP Conversion and Indexing Facility: User's Guide* for more information)

**/usr/lpp/psf/bin/Makefile**

The build rules for the ACIF user exits

**/usr/lpp/psf/acif/apkexits.h**

C language header file for the ACIF user exits

For NT/2000:

**install\_path\bin\line2afp.exe**

The **acif** executable

**install\_path\bin\acif.exe**

The **acif** command

**install\_path\exits\acif\apkinp.c, apkind.c, apkres.c, apkout.c, apka2e.c, asciinp.c, asciinpe.c**

**acif** user exits (see *AFP Conversion and Indexing Facility: User's Guide* for more information)

**install\_path\bin\apka2e.dll, apkinp.dll, apkind.dll, apkres.dll, apkout.dll, apka2e.dll, asciinp.dll, asciinpe.dll**

User exit executables (see *AFP Conversion and Indexing Facility: User's Guide* for more information)

**install\_path\exits\acif\apkexits.h**

C language header file for the ACIF user exits

**install\_path\exits\acif\apka2e.dsw, apkinp.dsw, apkind.dsw, apkres.dsw, apkout.dsw, apka2e.dsw, asciinp.dsw, asciinpe.dsw**

Microsoft Visual C++ 6.0 Workspaces for the user exists

**install\_path\exits\acif\apka2e.dsp, apkinp.dsp, apkind.dsp, apkres.dsp, apkout.dsp, apka2e.dsp, asciinp.dsp, asciinpe.dsp**

Microsoft Visual C++ 6.0 Project files for the user exists.

## Messages

For AIX, message files for the **line2afp** transform can be found in **/usr/lib/nls/msg/LANG/acif.cat**, where *LANG* is the name of a locale, for example, en\_US.

## pcl2afp Command: Transforms PCL Data to AFP

### Syntax

```
pcl2afp [-aOutputType] [-CConfigurationFile] [-c] [-j nnnn]
        [-Innnn.nnnu] [-Mnnnnn] [-oOutputFile] [-P nnnnn]
        [-pPageRange] [-q] [-rnnn] [-S ServerName] [-snnnn]
        [-wnnnn.nnnu] [-xnnnn.nnnu] [-y nnnn.nnnu] [InputFile ...]
```

### Description

The **pcl2afp** command transforms a PCL data stream file into an AFP data stream file.

The PSF DSS runs the **pcl2afp** command automatically whenever:

- Infoprint identifies the format of a document in a print job as PCL.
- You use the **pdpr** command to specify **document-format=pcl** with the **-x** flag or in an attributes file.
- You specify a data type of **-odatatype=pcl** with an AIX print command (**enq**, **lp**, or **qprt**) or with the **lprafp** command.

If you specify multiple values of the same flag, **pcl2afp** uses the last value specified, with the exception of the **-p** flag. Multiple values of the **-p** flag are accumulated and the pages identified for printing are printed in normal numerical sequence, regardless of the order you specify.

When using the **pcl2afp** command, you can specify an optional input file name. If you do not specify an input file name, **pcl2afp** uses standard input. The output file name is also optional; if you do not specify one, the **pcl2afp** command writes the results to standard output.

Note the following about the flags you can specify with the **pcl2afp** command:

1. You can pass flags to **pcl2afp** using the **other-transform-options** document attribute on the Infoprint **pdpr** command or the **-o** flag of the AIX print commands (**enq**, **lp**, and **qprt**) and the Infoprint **lprafp** command.
2. When you run **pcl2afp** as a standalone transform, flags can appear anywhere on the command line with or without a blank in the flag and value pair.
 

When you specify **pcl2afp** transform flags with the **other-transform-options** attribute, any string containing a blank must be surrounded by single quotes.

Do not use a blank between the flag and the value when you specify **pcl2afp** transform flags with an AIX print command or with the **lprafp** command.
3. When you specify flags with the **pcl2afp** command, **pcl2afp** echoes them back to your display along with the settings for the flags. To suppress the command echoing, enter the **-q** (quiet) flag along with the **pcl2afp** command.
4. The order in which Infoprint uses PCL options is as follows:
  - a. Any options you specify on the command line with the **pcl2afp** command (for example, **-r300**), including values contained in the customized configuration file you specify with the **pcl2afp -C** command. If you specify the same option more than once, Infoprint uses the last value.
  - b. Values contained in the configuration file, **pcl2afp.cfg**, in the current directory, if you invoked **pcl2afp** directly. If you invoked **pcl2afp** indirectly by

## pcl2afp

- submitting a print job with a data type of PCL, **pcl2afp** ignores any configuration files in the current directory, and proceeds to step 4c.
- c. Values contained in the **pcl2afp.cfg** file in the user's home directory.
  - d. Values contained in the default **pcl2afp** command configuration file:

**For AIX**

**/usr/lpp/psf/pcl2afp/pcl2afp.cfg**

**For NT/2000**

*install\_path*\pcl2afp\pcl2afp.cfg

- e. Values contained in the customized configuration file you specify with the **pcl2afpd -C** command.
- f. Values contained in the default **pcl2afpd** daemon configuration file:

**For AIX**

**/usr/lpp/psf/pcl2afp/pcl2afpd.cfg**

**For NT/2000**

*install\_path*\pcl2afp\pcl2afpd.cfg

- g. Values contained in the **pcl2afpd.cfg** file when **pcl2afpd** was started.
  - h. The defaults that are built into **pcl2afpd**. These defaults are the same as the defaults for the **pcl2afp** flags.
5. The position of PCL data on the page depends on the interaction of the **-l** and **-w** flags, the **-x** and **-y** flags, and the form definition you use. In general, to position data on the page:
- Use **-l** and **-w** to set the physical page dimensions.
  - Use a form definition that specifies zero vertical offset and zero horizontal offset (for example, F100S, F100D, or F100T) or specify X and Y offsets of 0 when you submit the print job. For more information, see page 272.
  - Use **-x** and **-y** to avoid any areas that your printer cannot print.
6. You can specify the **pcl2afp** flags and values with the **pcl2afp** command, with the **pdpr -x "other-transform-options"** command, or with **enq -o**, **lp -o**, **qprt -o**, or **lprafp -o** command. You can also specify equivalent attributes with the **-x** flag or in an attributes file with the **pdpr** command.

**Note:** If you are migrating from PSF for AIX, see "Appendix B. Migrating PSF for AIX Job Script Keywords to Infoprint Equivalents" on page 691 for a table of attributes equivalent to the job script keywords that you used to use to specify flags and values for transforms.

## Limitations

- The **pcl2afp** transform must be installed, and the **pcl2afpd** daemon must be running.
- PCL data can contain device commands (for example, to begin or end duplexing or to change the input bin). Because the AFP architecture defines those device functions in a form definition resource instead of the print data, the **pcl2afp** transform ignores the device commands in the print data. To access those device functions (such as duplexing and bin selection), you must specify them in the form definition or attributes file, or on a print command, when you print the job.
- Resolution conversion algorithms may yield degraded appearance when used to reduce the resolution of a data stream. For this reason, **pcl2afp** may degrade the appearance of higher-resolution data streams when used with 240-pel printers. You should verify that print fidelity is satisfactory.



- There are subtle differences between PCL4 and PCL5e when it comes to handling fonts. While many PCL4 files will work with **pcl2afp**, some may not produce the expected output.

## Flags and Values

**-a {IO1\_G4 | IM1 | IO1 | IO1\_MMR | PSEG\_IO1\_G4 | PSEG\_IM1 | PSEG\_IO1 | PSEG\_IO1\_MMR | OVLY\_IO1\_G4 | OVLY\_IM1 | OVLY\_IO1 | OVLY\_IO1\_MMR}**

Determines the type of AFP data stream image to generate for each page in the PCL file.

Values are:

### **IO1\_G4**

Compressed Image Object Content Architecture (IOCA) image in Modified TSS (formerly CCITT) T.6 G4 Facsimile Coding Scheme (G4 MMR) format. This is the recommended output type because it takes up less space on the fixed disk, and it prints faster. It is the default specified in the **pcl2afpd** daemon and **pcl2afp** command configuration files.

**Note:** The IBM 3812 and 3816 printers do not support printing with an image type of **IO1\_G4**. For these printers, specify an image type of **IO1\_MMR** because it is the compressed image type supported by these printers, and it will result in faster printing than uncompressed image types.

PPDS, PCL, and TCP/IP-attached IPDS printers can print IOCA images; however, only channel-attached printers that have the Advanced Function Image and Graphics (AFIG) feature installed can print IOCA images. Therefore, if you are printing images on channel-attached printers without the AFIG feature, select the **IM1** value.

**IM1** IM1 image. This type of image is not compressed.

**IO1** IOCA image. This type of image is not compressed.

### **IO1\_MMR**

Compressed IOCA image in Modified Modified Read (MMR) format.

**PSEG\_IO1\_G4 | PSEG\_IM1 | PSEG\_IO1 | PSEG\_IO1\_MMR**

Page segment of the specified image type.

**Note:** When generating page segments from multiple-page documents, you may want to use the **-p** flag to select which page is to be made into a page segment; otherwise, multiple page segments will be created, one for each page of PCL.

**OVLY\_IO1\_G4 | OVLY\_IM1 | OVLY\_IO1 | OVLY\_IO1\_MMR**

Overlay of the specified image type.

**Note:** When generating overlays from multiple-page documents, you may want to use the **-p** flag to select which page is to be made into an overlay; otherwise, multiple overlays will be created, one for each page of PCL.

This flag is similar to the **image-out-format** document attribute on the **pdpr** command.

## pcl2afp

### **-C** *ConfigurationFile*

Specifies the path and file name of the customized configuration file **pcl2afp** uses with the transform. If you specify the **-C** flag with an AIX print command (**enq**, **lp**, or **qprt**), or with the **lprafp** command, specify the fully qualified name of the file, including its path; for example:

#### **For AIX**

**/usr/lpp/psf/pcl2afp/myfile.cfg**

#### **For NT/2000**

**d:\pcl\myfile.cfg**

- c** Concatenates multiple input files without putting a Esc-E (end of job) characters between the files. The **pcl2afp** command interprets the input files as a continuous data stream, and processes them as if they were one PCL job. This flag can be useful when processing PCL files with inline resources.

**Note:** Do not use this flag when you perform the PCL-to-AFP data stream transform by submitting a print job with the **pdpr** command.

### *InputFile ...*

Specifies one or more input files to be transformed. If you specify more than one input file name, the **pcl2afp** command concatenates the files and separates them with the Esc-E (end of job) characters. The results of the transform are written to a single output file (if one is specified) or to standard output.

In addition, you can specify PCL inline resource files as input files to the **pcl2afp** command. The file name of the inline resource file must precede the file name of the PCL print file so that **pcl2afp** concatenates the files in the correct order. The **pcl2afp** command concatenates the resources in front of the print file when the **-c** flag is specified.

If you do not specify an input file, **pcl2afp** uses standard input. If the **pcl2afp** command cannot read from standard input, the command issues a message.

### **-j** {20 | 1 to 9998 | 9999}

Specifies the maximum amount of time, in minutes, to spend processing the job.

Values are:

**20** 20 minutes, the default

**1 to 9998**  
The timer ranges from 1 to 9998 minutes, in one-minute increments

**9999** No time limit

### **-l** *nnnn.nnnu*

Specifies the length of the generated image; *nnnn.nnn* is a number that can optionally contain a decimal point, and *u* is the units in inches (**i**) or millimeters (**m**). If you do not specify a unit (**i** or **m**), then **pcl2afp** uses pels as the unit type. You cannot specify fractional values (that is, you cannot use a decimal point) for pels.

**Note:** If a text margin is already built into the file, try **-l11i** to set the length to 11 inches.

For 240-pel resolution printers, values are:

**11i** 11 inches, the default

**16 to 5280**

The length can be from 16 pels to 5280 pels, 0.067i to 22.002i, or 1.701m to 558.852m. For example, the following are all valid:

```
-l 40m
-l 200.5m
-l 13i
-l 4000
```

For 300-pel resolution printers, values are:

**11i** 11 inches, the default

**16 to 6600**

The length can be from 16 pels to 6600 pels, 0.053i to 22.001i, or 1.346m to 558.842m. For example, the following are all valid:

```
-l 40m
-l 200.5m
-l 13i
-l 5000
```

For 480-pel resolution printers, values are:

**11i** 11 inches, the default

**16 to 10560**

The length can be from 16 pels to 10560 pels, 0.033i to 22.002i, or 0.838m to 558.852m. For example, the following are all valid:

```
-l 40m
-l 200.5m
-l 13i
-l 8000
```

For 600-pel resolution printers, values are:

**11i** 11 inches, the default

**16 to 20400**

The length can be from 16 pels to 20400 pels, 0.0267i to 34.001i, or 0.678m to 863m. For example, the following are all valid:

```
-l 40m
-l 200.5m
-l 13i
-l 10000
```

This flag is equivalent to the **image-length** document attribute on the **pdpr** command.

**-M {6000 | 2000 to *nnnnn*}**

Determines the maximum amount of memory, in KB, that the transform can use. This flag may be useful if you are processing large PCL jobs that require a lot of memory.

Values are:

**6000** 6000KB (6MB), the default

**2000** to *nnnnn*

The maximum memory ranges from 2000 to *nnnnn* (where *nnnnn* is the maximum upper limit allowed by AIX or Windows) up to 64MB.

## pcl2afp

### **-o** *OutputFile*

Specifies the output path and file into which the transformed PCL files are to be written. If more than one output file is specified, the last specified file name and path is the one used. If no output file is specified, the result is written to standard output.

You cannot use **-o** *OutputFile* on the command line with the **enq**, **lp**, **qprt**, or **lprafp** commands. You can only use **-o** *OutputFile* with the **pcl2afp** command, or with the **other-transform-options** attribute on the **pdpr** command.

This option is equivalent to the **transform-output-file-name** document attribute on the **pdpr** command.

### **-P** {**8253** | **924** to *nnnnn*}

Specifies the TCP/IP port number **pcl2afp** uses to make a connection with the workstation on which the **pcl2afpd** daemon is running (set by the **-S** flag). If your Infoprint installation uses more than one PCL daemon, use this flag to select the daemon.

This port should not be the same port used by the TCP/IP-attached IPDS printer or by the PostScript transform. On AIX, to find out which ports are already being used on your system (although they may or may not be active), look in the **/etc/services** file.

Values are:

**8253** The default port number.

**924** to *nnnnn*

Any valid port number greater than or equal to 924. With AIX, the maximum value, *nnnnn*, depends on AIX, but it must be equal to or less than 65535.

**Note:** You can only access secure ports, 924 to 1023, with **root** user authority.

### **-p** *PageRange*

Specifies that the output should only contain selected pages. When you specify multiple **-p** flags, the **pcl2afp** command accumulates them and prints the identified pages in normal numerical order, regardless of the order you specify. Examples of values include:

**-p even**

Output even pages.

**-p odd**

Output odd pages.

**-p 1-10**

Output pages 1 through 10.

**-p 10-** Output pages from page 10 until the end of the job.

**-p 1 -p 3 -p 6**

Output pages 1, 3, and 6, in that order.

**-p1 -p6 -p3**

Output pages 1, 3, and 6, in that order.

This flag is equivalent to the **page-select** document attribute on the **pdpr** command.

**-q** Quiets (suppresses) the echoing of the **pcl2afp** command to the display.

**-r {240 | 300 | 480 | 600}**

Specifies the resolution of the output image. Select the resolution based on the printer on which you will be printing the image.

Values are:

- 240** 240 pels-per-inch (for example, IBM 3812, 3825, 3827, 3835, and 3900 printers), the default
- 300** 300 pels-per-inch (for example, IBM 3112, 3116, 4019, 4028, 4029, and 4039 printers and Hewlett-Packard printers)
- 480** 480 pels-per-inch
- 600** 600 pels-per-inch (for example, IBM 3900 printers)

**Note:** If you specify a resolution that the printer does not support, Infoprint will print the image under most conditions, but with degraded results. Specify the correct resolution for the printer on which you will print the PCL job.

This flag is equivalent to the **default-printer-resolution** document attribute on the **pdpr** command.

**-S ServerName**

Specifies the name of the AIX system on which the **pcl2afpd** daemon is running. If you do not specify this flag, the *ServerName* defaults to the effective name of the workstation on which you issued the **pcl2afp** command. The value is:

*ServerName*

Any valid AIX workstation name on which the **pcl2afpd** daemon is installed and running. The name is defined in the **/etc/hosts** file or by a name server, and may be a nickname like **molly**, or a dotted decimal address like **9.99.9.23**.

**-s {20 | 1 to 9998 | 9999}**

Specifies the maximum amount of time, in minutes, that the PCL interpreter remains idle between jobs before it goes down. When the PCL interpreter is running, it uses some of the workstation memory. If the PCL interpreter goes down, you do not need to bring it back up; the interpreter automatically starts when you submit another PCL job as long as the **pcl2afpd** daemon is running.

Values are:

- 20** The default time is 20 minutes.
- 1 to 9998** The time is the number of minutes specified in one-minute increments.
- 9999** There is no time limit.

**-w nnnn.nnnu**

Specifies the width of the generated image; *nnnn.nnn* is a number that can optionally contain a decimal point, and *u* is the units in inches (**i**) or millimeters (**m**). If you do not specify a unit (**i** or **m**), then **pcl2afp** uses pels as the unit type. You cannot specify fractional values (that is, you cannot use a decimal point) for pels.

**Note:** If a text margin is already built into the file, try **-w8.5i** to set the width to 8.5 inches.

## pcl2afp

For 240-pel resolution printers, values are:

**8.5i** 8.5 inches, the default

### 16 to 4080

The width can be from 16 pels to 4080 pels, 0.065i to 17.002i, or 1.641m to 431.852m. For example, the following are all valid:

```
-w 40m
-w 200.5m
-w 13i
-w 3300
```

For 300-pel resolution printers, values are:

**8.5i** 8.5 inches, the default

### 16 to 5100

The width can be from 16 pels to 5100 pels, 0.052i to 17.001i, or 1.313m to 431.842m. For example, the following are all valid:

```
-w 40m
-w 200.5m
-w 13i
-w 5000
```

For 480-pel resolution printers, values are:

**8.5i** 8.5 inches, the default

### 16 to 8160

The width can be from 16 pels to 8160 pels, 0.065i to 17.002i, or 1.641m to 431.852m. For example, the following are all valid:

```
-w 40m
-w 200.5m
-w 13i
-w 6600
```

For 600-pel resolution printers, values are:

**8.5i** 8.5 inches, the default

### 16 to 10200

The width can be from 16 pels to 10200 pels, 0.052i to 17.001i, or 1.313m to 431.842m. For example, the following are all valid:

```
-w 40m
-w 200.5m
-w 13i
-w 10000
```

This flag is equivalent to the **image-width** document attribute on the **pdpr** command.

### -x *nnnn.nnnu*

Specifies an X offset (horizontal offset) of the generated image; *nnnn.nnn* is a number that can optionally contain a decimal point, and *u* is the units in inches (**i**) or millimeters (**m**). If you do not specify a unit (**i** or **m**), then **pcl2afp** uses pels as the unit type. You cannot specify fractional values (that is, you cannot use a decimal point) for pels.

An offset value specifies a border or margin around the generated image to avoid the non-printable areas of some printers. An X-offset value specifies the left and right margins of the generated image.

For all printers, values are:

**0.167i** 0.167 inches, the default

**0 to 8.5i**

The X offset can be no more than half of the width (**-w**) of the generated image. For example, if you specify a width of 13i, then the X offset can be no larger than 6.5i.

This flag is equivalent to the **x-image-shift** document attribute on the **pdpr** command.

**Notes:**

1. The X offset specified with **-x** must be less than the width specified with **-w**. If the **-x** value is greater than or equal to the **-w** value, a blank page is printed.
2. The X-offset value specifies margins on *both* the left and right sides of the page. If you have a width of 8.5 inches and specify an X offset of 5 inches, a blank page will also result because the margins on the left and right sides of the paper exceed the width of the paper.
3. PCL processing is slower when you use the **-x** flag, because the **pcl2afpd** daemon must stop and re-start the PCL interpreter. You may improve performance by changing the **pcl\_x\_offset** value in the **pcl2afpd** daemon configuration file rather than using **-x** on a regular basis.

**-y** *nnnn.nnnu*

Specifies a Y offset (vertical offset) of the generated image; *nnnn.nnn* is a number that can optionally contain a decimal point, and *u* is the units in inches (**i**) or millimeters (**m**). If you do not specify a unit (**i** or **m**), then **pcl2afp** uses pels as the unit type. You cannot specify fractional values (that is, you cannot use a decimal point) for pels.

An offset value specifies a border or margin around the generated image to avoid the non-printable areas of some printers. A Y-offset value specifies the top and bottom margins of the generated image.

For all printers, values are:

**0.167i** 0.167 inches, the default

**0 to 8.5i**

The Y offset can be no more than half of the width (**-w**) of the generated image. For example, if you specify a width of 14i, then the X offset can be no larger than 7.0i.

This flag is equivalent to the **y-image-shift** document attribute on the **pdpr** command.

**Notes:**

1. The Y offset specified with **-y** must be less than the length specified with **-l**. If the **-y** value is greater than or equal to the **-l** value, a blank page is printed.
2. The Y-offset value specifies margins on *both* the top and bottom edges of the page. If you have a length of 11 inches and specify an Y offset of 6 inches, a blank page will also result because the margins on the top and bottom of the paper exceed the length of the paper.
3. PCL processing is slower when you use the **-y** flag, because the **pcl2afpd** daemon must stop and re-start the PCL interpreter. You may

## pcl2afp

improve performance by changing the **pcl\_y\_offset** value in the **pcl2afpd** daemon configuration file rather than using **-y** on a regular basis.

## Transforming PCL Image Data

The output of the PCL transform (the **pcl2afp** command) is AFP image data for any type of PCL input, whether it be text or images. The image that the **pcl2afp** command creates minimizes white space within an image block by defining the image block size to be exactly the right size to contain all of the black pels of the image. A PCL image may not print if any part of the image lies outside of the valid printable area. In addition, be aware that using form definitions that specify a non-zero logical page origin may move a valid PCL image out of the printable area; thus, the image won't print.

The **pcl2afp** command, the **pcl2afp.cfg** configuration file, and the **pcl2afpd.cfg** configuration file all let you specify the length and the width of PCL images. Before you use the **-l** and **-w** flags of the **pcl2afp** command or modify the **pcl\_length** and **pcl\_width** options in the configuration file, it's helpful to understand how Infoprint places PCL images on the page.

Figure 1 on page 271 shows an example of a PCL image. This image is 8.5 inches high and 11 inches wide, measured from the lower-left corner of the image.

If you want to print the entire image, specify a length of 11i and a width of 8.5i. When Infoprint prints the image, the upper-left corner of the image is placed at the point on the page called the logical page origin, which is specified in the form definition. The logical page origin is the point on the form where the page of data is positioned, and it is specified as an offset from the top-left corner of the sheet. Therefore, if the form definition has a logical page origin of 0.165 inches from both the left and top sides of the sheet, then the top-left corner of the image is placed 0.165 inches down and to the left of the upper left corner of the sheet.






Figure 1. A PCL Image

All this gets more complicated if you don't specify the entire image. For example, if you want to crop the image so that you only use the lower left corner, you would specify a width of 7i and a length of 7i with the **pcl2afp** command. The upper left corner of the resulting image is then placed at the logical page origin (Figure 2).




Figure 2. A Cropped PCL Image

## pcl2afp

In this final example, specify a PCL image that is 8.5 inches wide and 11 inches high. Again, the upper-left corner of the transformed image is placed at the logical page origin. Unless you specify a form definition with the print job that has a zero logical page origin (for example, **F100S**, **F100D**, or **F100T**), the page will not print because part of the image is outside the valid printable area (Figure 3).




Figure 3. A PCL Image Offset from the Top-Left Corner

As you can see from Figure 3, specifying the correct form definition is extremely important, particularly when you are printing a full-page image.

The default length and width values specified in the PCL configuration files, **pcl2afp.cfg** and **pcl2afpd.cfg** work with the default form definitions that Infoprint provides for each type of Infoprint printers.

However, if you want to specify exact placement of your PostScript output on the page using a zero vertical and horizontal offset from the top-left corner of the page, do one of the following:

- Specify one of the following form definitions:
  - F100S**
  - F100D**
  - F100T**
- Specify an X- and Y-offset value of **0** to override the values set in the form definition, using one of the following:
  - The **-oxoffset** and **-oyoffset** flags on the AIX print commands
  - The X offset and Y offset fields on the SMIT Submit an Infoprint Job panel
  - The **x-image-shift** and **y-image-shift** attributes with the **-x** flag or in an attributes submitted with the **pdpr** command

If you specify a 0 horizontal and vertical offset in the form definition, with an AIX print command, or in an attributes file, the image produced by the **pcl2afp** transform might be printed in the unprintable area of the printer. To avoid printing in the unprintable area, you can specify the **-x** (X offset) and **-y** (Y offset) flags on the **pcl2afp** command. These flags add white space to the top and left side of the image produced by the transform, ensuring that no data will print in the unprintable area. For more information about the unprintable area of your printer, refer to *Advanced Function Presentation: Printer Information*.

## The **pcl2afp** and **pcl2afpd** Configuration Files

Instead of typing flags on the command line with the **pcl2afp** command, you can use the **-C** flag to specify a configuration file that contains the flags. In this way, you can simply specify a configuration file name, rather than typing many flags. You may find it convenient to use a configuration file if you repeatedly use the same flags with the **pcl2afp** command, or if you are using different PCL processing values than the defaults defined by your system support group.

When your system support group installed the **pcl2afp** transform, a default **pcl2afp** command configuration file, **pcl2afp.cfg**, was installed as follows:

**For AIX**

`/usr/lpp/psf/pcl2afp`

**For NT/2000**

`install_path\pcl2afp`

If you want to create your own files, copy the **pcl2afp.cfg** file and then use a system editor to modify the options in this ASCII file to suit your needs.

A default **pcl2afpd** daemon configuration file, **pcl2afpd.cfg**, was also installed as follows:

**For AIX**

`/usr/lpp/psf/pcl2afp`

**For NT/2000**

`install_path\pcl2afp`

The **pcl2afpd** daemon configuration file can contain most of the same keywords as the **pcl2afp** command configuration file, plus some keywords that control the operation of the **pcl2afpd** daemon. Values in the command configuration file override values in the daemon configuration file.

Figure 4 on page 274 shows an example of a configuration file.

## pcl2afp

```
# pcl2afp configuration file

# KEYWORD                EQUIVALENT                PURPOSE
#                          pcl2afp FLAG
#####

port = 8253                # -P                which TCP/IP port to use
server = 127.0.0.1        # -S                which server to connect with

pcl_max_memory = 6000K    # -M                maximum amount of memory that
                        #                    PCL uses; the 'K' is ignored

pcl_job_timeout = 20      # -j                maximum number of minutes
                        #                    to process PCL job
pcl_server_timeout = 20  # -s                maximum number of minutes
                        #                    server waits between jobs

pcl_width = 8.5i          # -w                width of generated image
pcl_length = 11i         # -l                length of generated image
pcl_x_offset = 0.167i    # -x                left and right margins
pcl_y_offset = 0.167i    # -y                top and bottom margins
pcl_resolution = 240      # -r                resolution of printer
pcl_output_type = I01_G4 # -a                type of AFP image to generate
```

Figure 4. Sample *pcl2afp* Configuration File

Table 9 shows the **pcl2afp** flags and their equivalent configuration file keywords. To override the values in the default configuration file, **pcl2afp.cfg**, you can do one of the following:

- Specify flags with the **pcl2afp** command at transform time.
- Specify a configuration file with **pcl2afp -C** at transform time.
- Specify **pcl2afp** flags with **-o** flags on an AIX print command, or with equivalent attributes with the **-x** flag or in an attributes file on the **pdpr** command, to transform a file and print it at the same time.

**Note:** If you are migrating from PSF for AIX, see “Appendix B. Migrating PSF for AIX Job Script Keywords to Infoprint Equivalents” on page 691 for a table of attributes equivalent to the job script keywords that you used to use to specify flags and values for transforms.

Table 9. PCL Printing and Processing Options

<i>pcl2afp</i> Flag	Keyword in <i>pcl2afp</i> Configuration File	Keyword in <i>pcl2afpd</i> Configuration File
<b>Note:</b> The valid values for configuration file keywords are the same as for the corresponding <b>pcl2afp</b> command flag. For keywords used only in the <b>pcl2afpd</b> daemon configuration file, which have no corresponding command flag, see “ <i>pcl2afpd</i> Utility: Starts the <i>pcl2afpd</i> Daemon” on page 188.		
<b>-a</b> <i>OutputType</i>	<b>pcl_output_type=</b> <i>value</i>	<b>pcl_output_type=</b> <i>value</i>
<b>-C</b> <i>ConfigurationFile</i>	None	None
<b>-c</b>	None	None
<i>InputFile ...</i>	None	None
<b>-j</b> <i>nnnn</i>	<b>pcl_job_timeout=</b> <i>nnnn</i>	<b>pcl_job_timeout=</b> <i>nnnn</i>
<b>-l</b> <i>nnnn.nnnu</i>	<b>pcl_length=</b> <i>nnnn.nnnu</i>	<b>pcl_length=</b> <i>nnnn.nnnu</i>
<b>-M</b> <i>nnnnn</i>	<b>pcl_max_memory=</b> <i>nnnnn</i>	<b>pcl_max_memory=</b> <i>nnnnn</i>

Table 9. PCL Printing and Processing Options (continued)

<i>pcl2afp</i> Flag	Keyword in <i>pcl2afp</i> Configuration File	Keyword in <i>pcl2afpd</i> Configuration File
<b>-o</b> <i>OutputFile</i>	None	None
<b>-P</b> <i>nnnnn</i>	<b>port=PortNumber</b>	<b>port=PortNumber</b>
<b>-p</b> <i>PageRange</i>	None	None
<b>-q</b>	None	None
<b>-r</b> <i>nnn</i>	<b>pcl_resolution=nnn</b>	<b>pcl_resolution=nnn</b>
<b>-S</b> <i>ServerName</i>	<b>server=ServerName</b>	None
<b>-s</b> <i>nnnn</i>	<b>pcl_server_timeout=nnnn</b>	<b>pcl_server_timeout=nnnn</b>
<b>-w</b> <i>nnnn.nnnu</i>	<b>pcl_width=nnnn.nnnu</b>	<b>pcl_width=nnnn.nnnu</b>
<b>-x</b> <i>nnnn.nnnu</i>	<b>pcl_x_offset=nnnn.nnnu</b>	<b>pcl_x_offset=nnnn.nnnu</b>
<b>-y</b> <i>nnnn.nnnu</i>	<b>pcl_y_offset=nnnn.nnnu</b>	<b>pcl_y_offset=nnnn.nnnu</b>
None	None	<b>log_file=PathName</b>
None	None	<b>mail_command=PathName</b>
None	None	<b>notify=UserID</b>
None	None	<b>pcl_program=PathName</b>
None	None	<b>pcl_support_program=PathName</b>
None	None	<b>work_directory=PathName</b>

## Simple Examples

This section shows some simple examples of using **pcl2afp**. For more detailed examples, see “More Complex Examples” on page 276.

- To submit the sample PCL file `sample.pcl` supplied with Infoprint Manager for AIX to the logical printer named `Pserv-lp`, enter:

```
enq -PPserv-lp -odatat=pcl /usr/lpp/psf/pcl2afp/sample.pcl
```

- To transform the PCL file `myfile` into an AFP data stream, and then submit it to the Infoprint logical printer called `Pserv-lp`, enter:

```
pdpr -p Pserv-lp -x "default-printer-resolution=300" myfile
```

or

```
pcl2afp -r300 myfile | pdpr -p Pserv-lp
```

**Note:** You need to specify a resolution of 300 pels (**default-printer-resolution=300**) because the `Pserv-lp` printer routes jobs to a 4019 printer device. The 4019 is a 300-pel resolution printer and the default resolution for the **pcl2afp** command is 240 pels.

- To transform the PCL file `myfile` into an AFP data stream, with an image that is 8 inches high and 5 inches wide, and write the result to a file called `myfile.afp`, enter:

```
pcl2afp -l 8i -w 5i -o myfile.afp myfile
```

or

```
pcl2afp -l 8i -w 5i myfile > myfile.afp
```

- To transform the PCL `myfile` file into an AFP data stream in 300-pel resolution, as an `IO1_MMR` image, and send the result to the printer with the **pdpr** command, enter:

## pcl2afp

```
pcl2afp -aIO1_MMR -r300 myfile | pdpr -X myafp.X -p lserv-1p
```

or

```
pdpr -X mypcl.X myfile -p Pserv-1p
```

where the attributes file named myafp.X contains the following settings:

```
document-format=modca-p  
printer-name-requested=robin-1p
```

and the attributes file named mypcl.X contains the following settings:

```
document-format=pcl  
printer-name-requested=robin-1p  
image-output-format=io1_mmr  
default-printer-resolution=300
```

- Assume that the PCL file myfile uses the BarKode.pcl font that is a PCL resource on a system named molly. Also assume that the **pcl2afpd** daemon is running on robin, but you are logged in to the AIX system named molly. To transform myfile into an AFP data stream, but not print it:

```
pcl2afp -S robin -c -o myfile.afp BarKode.pcl myfile
```

The **-c** flag concatenates the two input files, with the file BarKode.pcl first, so that the two files are processed together. In this way, myfile uses BarKode.pcl as an inline resource.

- Because the **pcl2afp** transform does not accept HP-GL/2 directly as input, you can use the **-c** flag to concatenate some sample PCL files that allow the HP-GL/2 file to be processed. To transform the HP-GL/2 file myfile.gl into a MO:DCA-P data stream file myfile.afp, enter:

### For AIX

```
pcl2afp -o myfile.afp -c /usr/lpp/psf/pcl2afp/gl_before.pcl  
myfile.gl /usr/lpp/psf/pcl2afp/gl_after.pcl
```

### For NT/2000

```
pcl2afp -o myfile.afp -c install_path\pcl2afp\gl_before.pcl  
myfile.gl install_path\pcl2afp\gl_after.pcl
```

The **-c** flag concatenates the three input files, making myfile.gl appear as a PCL file that includes HP-GL/2 commands.

## More Complex Examples

This section shows the following examples of transforming and printing PCL files:

- “Printing a PCL File”
- “Printing a PCL File with a Defined Image Size” on page 277
- “Printing a PCL File at 300-Pel Resolution” on page 278
- “Printing a PCL File with a Custom Configuration File” on page 280
- “Transforming Three PCL Files at the Same Time” on page 281
- “Transforming an HP-GL/2 File” on page 282

### Printing a PCL File

In this example, you will submit a PCL file called PCLfile1 for printing on an Infoprint printer called molly-1p.

**Configuration Assumptions:** This example assumes the following tasks have been performed by your system support group:

- Infoprint, including the **pcl2afp** transform, has been installed on the workstation on which the **pcl2afp** command is executed.

- The **pcl2afpd** daemon has been started on the workstation on which the **pcl2afp** command is executed.
- A 3825 printer device has been installed and defined to Infoprint. A logical printer called `molly-1p` routes jobs to the physical printer representing that device.

**Using the AIX SMIT Submit an Infoprint Job Panel:** To print this example, do the following steps:

1. On the AIX command line, enter:

```
smit ipsub
```

SMIT displays a list of attributes files to select from.

**Note:** The attributes file must contain the **document-format** attribute. Although Infoprint can determine the document format without being told, SMIT cannot.

2. Select `template_PCL.X`.  
SMIT displays the Submit an Infoprint Job panel.
3. Enter `PCLFile1` in the NAMES of files to be submitted in the job field.
4. Select `molly-1p` from the list for the Logical PRINTER field.
5. Press Enter (ASCII interface) or select **Do** (AIXwindows interface).

**Using the Command Line Options:** To print this example, enter the following on the command line: or

```
pdpr -p molly-1p PCLFile1
```

or on AIX

```
enq -P molly-1p PCLFile1
```

**Using an Attributes File with the pdpr Command:** To print this example, enter the following on the command line:

```
pdpr -X pcllex1.X -p molly-1p PCLFile1
```

where the attributes file named `pcllex1.X` contains the following settings:

```
document-format=pcl
    A data type of PCL
```

### Printing a PCL File with a Defined Image Size

In this example, you will submit a PCL file called `PCLFile2.pcl` for printing on an Infoprint printer called `Dserv-1p`. In addition, you will specify the form definition `F100S` and an image size of 9 inches in length and 6 inches in width, measured from the upper-left corner of the image.

**Configuration Assumptions:** This example assumes the following tasks have been performed by your system support group:

- Infoprint, including the **pcl2afp** transform, has been installed on the workstation on which the **pcl2afp** command is executed.
- The **pcl2afpd** daemon has been started on the workstation on which the **pcl2afp** command is executed.
- A 3900 printer device has been installed and defined to Infoprint. A logical printer called `Dserv-1p` routes jobs to the physical printer representing that device.

**Using the AIX SMIT Submit an Infoprint Job Panel:** To print this example, do the following steps:

## pcl2afp

1. On the AIX command line, enter:

```
smit ipsub
```

SMIT displays a list of attributes files to select from.

**Note:** The attributes file must contain the **document-format** attribute. Although Infoprint can determine the document format without being told, SMIT cannot.

2. Select template\_PCL.X.  
SMIT displays the Submit an Infoprint Job panel.
3. Enter PCLFile2.pcl in the NAMES of files to be submitted in the job field.
4. Select Dserv-1p from the list for the Logical PRINTER field.
5. Enter F100S in the FORM DEFINITION name field.
6. Enter 9i in the Image LENGTH field.
7. Enter 6i in the Image WIDTH field.
8. Press Enter (ASCII interface) or select Do (AIXwindows interface).

**Using the Command Line Options:** To print this example, enter the following on the command line:

```
pdpr -p Dserv-1p -x "form-definition=F100S  
image-length=19i image-width=6i" PCLFile2.pcl
```

or on AIX

```
enq -P Dserv-1p -oformdef=F100S -o-19i -o-w6i PCLFile2.pcl
```

Infoprint identifies the input data type as PCL without being told. Infoprint automatically runs **pcl2afp**, and passes **-19i** and **-w6i** from the **enq** command to **pcl2afp**.

You can get the same result by piping the output of the **pcl2afp** command to the input of the **enq** command:

```
pcl2afp PCLFile2.pcl -19i -w 6i | enq -P Dserv-1p -oformdef=F100S
```

**Using an Attributes File with the pdpr Command:** To print this example, enter the following on the command line:

```
pdpr -X pcl2.X -p Dserv-1p PCLFile2.pcl
```

where the attributes file named `pcl2.X` contains the following settings:

**image-length=9i**

Image length is nine inches

**image-width=6i**

Image width is six inches

**form-definition=F100S**

Use the F100S formdef for printing the job

### Printing a PCL File at 300-Pel Resolution

In this example, you will submit a PCL file called `PCLFile3.pcl` for printing on an Infoprint printer called `G4019-Serv1`. In addition, you will specify a resolution of 300 pels.

**Configuration Assumptions:** This example assumes the following tasks have been performed by your system support group:



- Infoprint, including the **pcl2afp** transform, has been installed on the workstation on which the **pcl2afp** command is executed.
- The **pcl2afpd** daemon has been started on the workstation on which the **pcl2afp** command is executed.
- The 4019 printer has been installed and defined to AIX. A logical printer, named G4019-Serv1, has been configured to route jobs to the physical printer representing the 4019.

**Using the AIX SMIT Submit an Infoprint Job Panel:** To print this example, do the following steps:

1. On the AIX command line, enter:

```
smit ipsub
```

SMIT displays a list of attributes files to select from.

**Note:** The attributes file must contain the **document-format** attribute. Although Infoprint can determine the document format without being told, SMIT cannot.

2. Select `template_PCL.X`.  
SMIT displays the Submit an Infoprint Job panel.
3. Enter `PCLFile3.pcl` in the NAMES of files to be submitted in the job field.
4. Select `G4019-Serv1` from the list for the Logical PRINTER field.
5. Select `300` from the list for the Printer RESOLUTION field.
6. Press Enter (ASCII interface) or select Do (AIXwindows interface).

**Using the Command Line Options:** To print this example, enter the following on the command line:

```
pdpr -o G4019-Serv1 -x "default-printer-resolution=300" PCLFile3.pcl
```

or on AIX

```
enq -P G4019-Serv1 -o-r300 PCLFile3.pcl
```

Infoprint determines that the input data type is PCL and automatically runs **pcl2afp**, passing `-r300` from the **enq** command to **pcl2afp**.

You can get the same result by piping the output of the **pcl2afp** command to the input of the **enq** command:

```
pc12afp PCLFile3.pcl -r 300 | enq -P G4019-Serv1
```

**Using an Attributes File with the pdpr Command:** To print this example, enter the following on the command line:

```
pdpr -X pcl3.X PCLFile3.pcl
```

where the attributes file named `pcl3.X` contains the following settings:

**document-format=pcl**

A data type of PCL

**default-printer-resolution=300**

Image resolution is 300 pels

**printer-name-requested=G4019-Serv1**

Submit the job to the G4019-Serv1 logical printer

## pcl2afp

### Printing a PCL File with a Custom Configuration File

In this example, you will submit a PCL file called PCLFile4.pcl for printing on an Infoprint printer called molly-lp. In addition, you will specify the form definition F100D, as well as a customized PCL configuration file called custom.cfg, which is located in the directory

#### For AIX

```
/usr/lpp/psf/pcl2afp
```

#### For NT/2000

```
install_path\pcl2afp
```

The output file name is PCLFile4.afp.

**Configuration Assumptions:** This example assumes the following items have been done by your system support group:

- Infoprint, including the **pcl2afp** transform, has been installed on the workstation on which the **pcl2afp** command is executed.
- The **pcl2afpd** daemon has been started on the workstation on which the **pcl2afp** command is executed.
- A 3825 printer device has been installed and defined to Infoprint. A logical printer called molly-lp routes jobs to the physical printer representing that device.
- The customized configuration file is custom.cfg, located in the **pcl2afp** directory; and you have permission to read this file.

**Using the AIX SMIT Submit an Infoprint Job Panel:** To print this example, do the following steps:

1. On the AIX command line, enter:

```
smit ipsub
```

SMIT displays a list of attributes files to select from.

**Note:** The attributes file must contain the **document-format** attribute. Although Infoprint can determine the document format without being told, SMIT cannot.

2. Select template\_PCL.X.  
SMIT displays the Submit an Infoprint Job.
3. Enter PCLFile4.pcl in the NAMES of files to be submitted in the job field.
4. Select molly-lp from the list for the Logical PRINTER field.
5. Enter F100D in the FORM DEFINITION name field.
6. Enter /usr/lpp/psf/pcl2afp/custom.cfg in the PCL transform OPTIONS file field.
7. Press Enter (ASCII interface) or select Do (AIXwindows interface).

**Using the Command Line Options:** To print this example, enter the following on the command line:

#### For AIX

```
pdpr -p molly-lp -x "form-definition=F100D  
other-transform-options='-o-C/usr/lpp/psf/pcl2afp/custom.cfg'"  
PCLFile4.pcl
```

or

```
enq -P molly-lp -oformdef=F100D  
-o-C/usr/lpp/psf/pcl2afp/custom.cfg PCLFile4.pcl
```

**For NT/2000**

```
install_path\pcl2afp\custom.cfg
```

Infoprint determines the data type, automatically runs **pcl2afp**, and passes:

**For AIX**

`-C /usr/lpp/psf/pcl2afp/custom.cfg` to **pcl2afp** (When you use the **-C** flag with an AIX print command, no spaces are allowed between the **-C** flag and the configuration file name, and the configuration file name must be fully qualified).

**For NT/2000**

```
-C install_path\custom.cfg
```

(

On AIX, you can get the same result by invoking **pcl2afp** first, then using **enq** to process the output of **pcl2afp**:

```
pcl2afp PCLFile4.pcl -o PCLFile4.afp -C /usr/lpp/psf/pcl2afp/custom.cfg
enq -P molly-1p -ofordef=F100D PCLFile4.afp
```

**Using an Attributes File with the pdpr Command:** To print this example, enter the following on the command line:

```
pdpr -X pcl4.X PCLFile4.pcl
```

where the attributes file named `pcl4.X` contains the following settings:

For AIX:

**document-format=pcl**

A data type of PCL

**other-transform-options='-C /usr/lpp/psf/pcl2afp/custom.cfg'**

Use the `/usr/lpp/psf/pcl2afp/custom.cfg` **pcl2afp** configuration file

**form-definition=F100D**

Use the F100D form definition for printing the job

**printer-name-requested=molly-1p**

Submit the job to the `molly-1p` logical printer

For NT/2000:

**document-format=pcl**

A data type of PCL

**other-transform-options='-C install\_path\pcl2afp\custom.cfg'**

Use the `install_path\pcl2afp\custom.cfg` configuration file

**form-definition=F100D**

Use the F100D form definition for printing the job

**printer-name-requested=molly-1p**

Submit the job to the `molly-1p` logical printer

**Transforming Three PCL Files at the Same Time**

In this example, you will transform three PCL files to create one AFP data stream file. The PCL files are called `PCLFile5.pcl`, `PCLFile6.pcl`, and `PCLFile7.pcl`. You write the output of the transform to the file called `PCLFile0.afp`. Other options you want to specify are an image type of **IM1**.

## pcl2afp

**Configuration Assumptions:** This example assumes the following tasks have been performed by your system support group:

- Infoprint, including the **pcl2afp** transform, has been installed on the workstation on which the **pcl2afp** command is executed.
- The **pcl2afpd** daemon has been started on the workstation on which the **pcl2afp** command is executed.

**Using the AIX SMIT Submit an Infoprint Job Panel:** You cannot perform the PCL to AFP data stream transform using the Submit an Infoprint Job panel without also submitting the output file as a print job.

**Using the Command Line Options:** To transform this example, enter the following on the command line:

```
pcl2afp -aim1 PCLFile5.pcl PCLFile6.pcl PCLFile7.pcl -oPCLFile0.afp
```

### Transforming an HP-GL/2 File

Because the **pcl2afp** transform does not accept HP-GL/2 directly as input, you can use the **-c** flag to concatenate some sample PCL files that allow the HP-GL/2 file to be processed. To transform the HP-GL/2 file `myfile.gl` into a MO:DCA-P data stream file `myfile.afp`, enter:

#### For AIX

```
pcl2afp -o myfile.afp -c /usr/lpp/psf/pcl2afp/gl_before.pcl  
myfile.gl /usr/lpp/psf/pcl2afp/gl_after.pcl
```

#### For NT/2000

```
pcl2afp -o myfile.afp -c install_path\pcl2afp\gl_before.pcl  
myfile.gl install_path\pcl2afp\gl_after.pcl
```

The **-c** flag concatenates the three input files, making `myfile.gl` appear as a PCL file that includes HP-GL/2 commands.

## Files

For AIX:

```
/usr/lpp/psf/pcl2afp/sample.pcl  
PCL sample program  
/usr/lpp/psf/bin/pcl2afp  
Transform program  
/usr/lpp/psf/bin/pcl2afpd  
PCL daemon  
/usr/lpp/psf/bin/ppxpcli  
PCL interpreter program  
/usr/lpp/psf/bin/ppxpclis  
PCL interpreter support program  
/usr/lpp/psf/pcl2afp/pcl2afp.cfg  
PCL pcl2afp command configuration file  
/usr/lpp/psf/pcl2afp/pcl2afpd.cfg  
PCL pcl2afpd daemon configuration file  
/var/psf/pcl2afp  
Work directory for PCL transform
```

For NT/2000:

```
install_path\pcl2afp\sample.pcl  
PCL sample program  
install_path\bin\pcl2afp.exe  
Transform program
```

*install\_path*\bin\pcl2afpd.exe  
PCL daemon  
*install\_path*\bin\ppxpcli.exe  
PCL interpreter program  
**/usr/lpp/psf/pcl2afp/pcl2afp.cfg**  
PCL **pcl2afp** command configuration file  
*install\_path*\pcl2afp\pcl2afpd.cfg  
PCL **pcl2afpd** daemon configuration file  
*install\_path*\var\psf\pcl2afp  
Work directory for PCL transform

## pdf2afp and ps2afp Transforms: Transform PDF or PostScript Data to AFP

### Syntax

```
{pdf2afp | ps2afp}
  [-aOutputType] [-CConfigurationFile] [-c]
  [-FFontMapFile[:FontMapFile...]] [-g PageRange] [-jnnnn]
  [-Innnn.nnnu] [-Mnnnnn] [-oOutputFile]
  [-Pnnnnn] [-pPageRange] [-q] [-rnnn]
  [-SServerName] [-snnnn] [-wnnnn.nnnu]
  [-xnnnn.nnnu] [-ynnnn.nnnu] [InputFile ...]
```

### Description

The **ps2afp** command and its alias, the **pd2afp** command, transform a PostScript or Portable Document Format (PDF) data stream file into an AFP data stream file.

The PSF DSS runs the **ps2afp** command automatically whenever:

- Infoprint identifies the format of a document in a print job as PostScript or PDF.
- You use the **pdpr** command to specify **document-format=postscript** or **document-format=pdf** with the **-x** flag or in an attributes file.
- You specify a data type of **-odatatype=ps** or **-odatatype=pdf** with an AIX print command (**enq**, **lp**, or **qprt**) or with the **lprafp** command.

If you specify multiple values of the same flag, **ps2afp** uses the last value specified, with the exception of the **-F**, **-g**, and **-p** flags. **ps2afp** concatenates multiple values of the **-F** flag from left-to-right (first entered to last entered). Multiple values of the **-g** and **-p** flags are accumulated and the pages identified for printing are printed in normal numerical sequence, regardless of the order you specify.

When using the **ps2afp** or **pdf2afp** command, you can specify an optional input file name. If you do not specify an input file name, **ps2afp** reads standard input. The output file name is also optional; if you do not specify one, the **ps2afp** command writes the results to standard output.

Note the following about the flags you can specify with the **ps2afp** or **pdf2afp** command:

1. When you run **ps2afp** or **pdf2afp** as a standalone transform, flags can appear anywhere on the command line with or without a blank in the flag and value pair.  
When you specify **ps2afp** transform flags with the **other-transform-options** attribute, any string containing a blank must be surrounded by single quotes.  
Do not use a blank between the flag and the value when you specify **ps2afp** transform flags with an AIX print command or with the **lprafp** command.
2. When you specify flags with the **ps2afp** or **pdf2afp** command, the command echoes them back to your display along with the settings for the flags. To suppress the command echoing, enter the **-q** (quiet) flag along with the **ps2afp** or **pdf2afp** command.
3. Finally, be aware that the PostScript or PDF file may contain the commands **letter** and **legal**. If these commands are present in the PostScript or PDF file, you may not get what you expect due to the interaction of the **letter** and **legal**

commands with the **-l** and **-w** flags of the **ps2afp** or **pdf2afp** command. The order in which **ps2afp** uses PostScript and PDF options is as follows:

- a. The PostScript program commands **letter** and **legal**, if they are present.
- b. Any options you specify on the command line with the **ps2afp** or **pdf2afp** command (for example, **-r300**), including values contained in the customized configuration file you specify with the **ps2afp -C** or **pdf2afp** command. If you specify the same option more than once, Infoprint uses the last value.
- c. Values contained in the configuration file, **ps2afp.cfg**, in the current directory, if you invoked **ps2afp** or **pdf2afp** directly. If you invoked **ps2afp** indirectly by requesting **enq -odatatype=ps**, or **enq -odatatype=pdf**, **ps2afp** ignores any configuration files in the current directory, and proceeds to step 3d.
- d. Values contained in the **ps2afp.cfg** file in the user's home directory.
- e. Values contained in the default **ps2afp** command configuration file:

**For AIX**

**/usr/lpp/psf/ps2afp/ps2afp.cfg**

**For NT/2000**

*install\_path*\ps2afp\ps2afpd.cfg

- f. Values contained in the customized configuration file you specify with the **ps2afpd -C** command.
- g. Values contained in the default **ps2afpd** daemon configuration file:

**For AIX**

**/usr/lpp/psf/ps2afp/ps2afpd.cfg**

**For NT/2000**

*install\_path*\ps2afp\ps2afpd.cfg

- h. Values contained in the **ps2afpd.cfg** file when **ps2afpd** was started.
  - i. The defaults that are built into **ps2afpd**. These defaults are the same as the defaults for the **ps2afp** flags, except that the default output type (**-a** flag) is an IM1 uncompressed image.
4. The position of PostScript or PDF data on the page depends on the interaction of the **-l** and **-w** flags, the **-x** and **-y** flags, and the form definition you use. In general, to position data on the page,
    - Use **-l** and **-w** to set the physical page dimensions.
    - Use a form definition that specifies zero vertical offset and zero horizontal offset (for example, **F100S**, **F100D**, or **F100T**) or specify X and Y offsets of 0 when you submit the print job.
    - Use **-x** and **-y** to avoid any areas that your printer cannot print.
  5. You can specify the **ps2afp** flags and values with the **ps2afp** or **pdf2afp** command, or with **enq -o**, **lp -o**, **qprt -o**, or **lprafp**. You can also specify equivalent attribute values with the **-x** flag or in an attributes file with the **pdpr** command.

**Note:** If you are migrating from PSF for AIX, see “Appendix B. Migrating PSF for AIX Job Script Keywords to Infoprint Equivalents” on page 691 for a table of attributes equivalent to the job script keywords that you used to use to specify flags and values for transforms.

## Limitations

- Infoprint, including the **ps2afp** transform, must be installed, and the **ps2afpd** daemon must be running.

## pdf2afp and ps2afp

- PostScript data can contain device commands (for example, to begin or end duplexing or to change the input bin). Because the AFP architecture defines those device functions in a form definition resource instead of the print data, the **ps2afp** transform ignores the device commands in the print data. To access those device functions (such as duplexing and bin selection), you must specify them in the form definition or attributes file, or on a print command, when you print the job.
- Resolution conversion algorithms may yield degraded appearance when used to reduce the resolution of a datastream. For this reason, **ps2afp** may degrade the appearance of higher-resolution datastreams when used with 240-pel printers. You should verify that print fidelity is satisfactory.

## Flags and Values

**-a {IO1\_G4 | IM1 | IO1 | IO1\_MMR | PSEG\_IO1\_G4 | PSEG\_IM1 | PSEG\_IO1 | PSEG\_IO1\_MMR | OVLY\_IO1\_G4 | OVLY\_IM1 | OVLY\_IO1 | OVLY\_IO1\_MMR}**

Determines the type of AFP data stream image to generate for each page in the PostScript or PDF file.

Values are:

### **IO1\_G4**

Compressed Image Object Content Architecture (IOCA) image in Modified TSS (formerly CCITT) T.6 G4 Facsimile Coding Scheme (G4 MMR) format. This is the recommended output type because it takes up less space on the fixed disk, and it prints faster. It is the default specified in the **ps2afpd** daemon and **ps2afp** command configuration files.

**Note:** The IBM 3812 and 3816 printers do not support printing with an image type of **IO1\_G4**. For these printers, specify an image type of **IO1\_MMR** because it is the compressed image type supported by these printers. This will result in faster printing than uncompressed image types.

PPDS, PCL, and TCP/IP-attached IPDS printers can print IOCA images; however, only channel-attached printers that have the Advanced Function Image and Graphics (AFIG) feature installed can print IOCA images. Therefore, if you are printing images on channel-attached printers without the AFIG feature, select the **IM1** value.

**IM1** IM1 image. This type of image is not compressed.

**IO1** IOCA image. This type of image is not compressed.

### **IO1\_MMR**

Compressed IOCA image in Modified Modified Read (MMR) format.

**PSEG\_IO1\_G4 | PSEG\_IM1 | PSEG\_IO1 | PSEG\_IO1\_MMR**

Page segment of the specified image type.

**Note:** When generating page segments from multiple-page documents, you may want to use the **-p** flag to select which page is to be made into a page segment; otherwise, multiple page segments will be created, one for each page of PostScript or PDF.



**OVLY\_IO1\_G4 | OVLY\_IM1 | OVLY\_IO1 | OVLY\_IO1\_MMR**

Overlay of the specified image type.

**Note:** When generating overlays from multiple-page documents, you may want to use the **-p** flag to select which page is to be made into an overlay; otherwise, multiple overlays will be created, one for each page of PostScript or PDF.

This flag is similar to the **image-out-format** document attribute on the **pdpr** command.

**-C ConfigurationFile**

Specifies the path and file name of the customized configuration file Infoprint uses with the transform. If you specify the **-C** flag with an AIX print command (**enq**, **lp**, or **qprt**), or with the **lprafp** command, specify the fully qualified name of the file, including its path; for example:

**With AIX**

**/usr/lpp/ps2afp/myfile.cfg**

**With NT/2000**

**install\_path\ps2afp\myfile.cfg**

- c** Concatenates multiple input files without putting a Ctrl-D (end of job) character between the files. The **ps2afp** command interprets the input files as a continuous data stream, and processes them as if they were one PostScript or PDF job. This flag can be useful when processing PostScript or PDF files with inline resources. (See “Examples” on page 296).

**Note:** Do not use this flag when you perform the data stream transform by submitting a print job with the **pdpr** command.

**-F FontMapFile[:FontMapFile...]**

Specifies the path and file name **ps2afp** uses for the font mapping file. This file correlates PostScript font names with their file locations. A font mapping file must exist on the AIX system where the **ps2afpd** daemon is running (specified by the **-S** flag).

You can include multiple values in the **-F** flag by separating each value with a colon (:). The files will be concatenated. When you specify multiple **-F** flags, **ps2afp** concatenates them from left-to-right (first entered to last entered) in that order.

The **-F** value overrides the **ps\_font\_map\_files** value in the **ps2afp** configuration file and the **ps2afpd** configuration file. If you do not specify **-F**, **ps2afp** uses the font mapping file specified in the **ps2afp** command or **ps2afpd** daemon configuration file. (By default, the **ps2afpd** daemon configuration file specifies the font mapping file as follows:

**For AIX**

**/usr/lpp/psf/ps/psfonts.map**

**For NT/2000**

**install\_path\ps\fonts.map**

If you specify **-F** without a file name, or if the file does not exist, the **ps2afp** command does not work.

**Notes:**

1. PostScript or PDF processing is slower when you use the **-F** flag, because the **ps2afpd** daemon must stop and re-start the PostScript

## pdf2afp and ps2afp

interpreter. You may improve performance by changing the **ps\_font\_map\_files** value in the **ps2afpd** daemon configuration file rather than using **-F** on a regular basis.

2. Specify the fully qualified name of the file if you specify the **-F** flag with an AIX print command.

### **-g** *PageRange*

Specifies that the output should only contain selected pages. When you specify multiple **-g** flags, the **ps2afp** command transforms only the specified pages in the PostScript or PDF input data stream, then prints the transformed pages in normal numerical order, regardless of the order you specify. Examples of values include:

#### **-g even**

Output even pages.

#### **-g odd**

Output odd pages.

#### **-g 1-10**

Output pages 1 through 10.

**-g 10-** Output pages from page 10 until the end of the job.

#### **-g 1 -g 3 -g 6**

Output pages 1, 3, and 6, in that order.

#### **-g1 -g6 -g3**

Output pages 1, 3, and 6, in that order.

This flag is equivalent to the **page-select** document attribute on the **pdpr** command.

**Note:** You should only specify the **-g** flag when the input data conforms to Adobe Document Structuring Conventions (DSC). If you have any doubt about the input data, use the **-p** flag.

You cannot specify both the **-g** flag and the **-p** flag.

### *InputFile ...*

Specifies one or more input files to be transformed. If you specify more than one input file name, the **ps2afp** command concatenates the files and separates them with the Ctrl-D (end of job) character. The results of the transform are written to a single output file (if one is specified) or to standard output.

In addition, you can specify PostScript inline resource files as input files to the **ps2afp** command. The file name of the inline resource file must precede the file name of the PostScript or PDF print file so that **ps2afp** concatenates the files in the correct order.

If you do not specify an input file, **ps2afp** uses standard input. If the **ps2afp** command cannot read from standard input, **ps2afp** issues a message.

### **-j** {20 | 1 to 9998 | 9999}

Specifies the maximum amount of time, in minutes, to spend processing the job.

Values are:

**20** 20 minutes, the default

**1 to 9998**

The timer ranges from 1 to 9998 minutes, in one-minute increments

**9999** No time limit

**-l nnnn.nnnu**

Specifies the length of the generated image; *nnnn.nnn* is a number that can optionally contain a decimal point, and *u* is the units in inches (**i**) or millimeters (**m**). If you do not specify a unit (**i** or **m**), then **ps2afp** uses pels as the unit type. You cannot specify fractional values (that is, you cannot use a decimal point) for pels.

**Note:** If a text margin is already built into the file, try **-l11i** to set the length to 11 inches.

For 240-pel resolution printers, values are:

**11i** 11 inches, the default

**16 to 8160**

The length can be from 16 pels to 8160 pels, 0.065i to 34i, or 1.641m to 863.628m. For example, the following are all valid:

```
-l 40m
-l 200.5m
-l 13i
-l 4000
```

For 300-pel resolution printers, values are:

**11i** 11 inches, the default

**16 to 10200**

The length can be from 16 pels to 10200 pels, 0.052i to 34i, or 1.313m to 863.628m. For example, the following are all valid:

```
-l 40m
-l 200.5m
-l 13i
-l 5000
```

For 480-pel resolution printers, values are:

**11i** 11 inches, the default

**16 to 16320**

The length can be from 16 pels to 16320 pels, 0.065i to 34i, or 1.641m to 863.628m. For example, the following are all valid:

```
-l 40m
-l 200.5m
-l 13i
-l 8000
```

For 600-pel resolution printers, values are:

**11i** 11 inches, the default

**16 to 20400**

The length can be from 16 pels to 20400 pels, 0.052i to 34i, or 1.313m to 863.628m. For example, the following are all valid:

```
-l 40m
-l 200.5m
-l 13i
-l 10000
```

This flag is equivalent to the **image-length** document attribute on the **pdpr** command.

## pdf2afp and ps2afp

### **-M** {**15000** | **11000** to *nnnnn*}

Determines the maximum amount of memory, in KB, that the transform can use. This flag may be useful if you are processing large PostScript or PDF jobs that require a lot of memory.

Values are:

**15000** 15000KB (15MB)

**11000** to *nnnnn*

The maximum memory ranges from 11000 to *nnnnn* (where *nnnnn* is the maximum upper limit allowed by AIX) up to 64MB. 15000 is the default.

### **-o** *OutputFile*

Specifies the output path and file into which the transformed files are to be written. If more than one output file is specified, the last specified file name and path is the one used. If no output file is specified, the result is written to standard output.

You cannot use **-o** *OutputFile* on the command line with the **enq**, **lp**, **qpri**, or **lprafp** commands. You can only use **-o** *OutputFile* with the **ps2afp** command. You can also specify the **transform-output-file-name** document attribute on the **pdpr** command.

### **-P** {**8251** | **924** to *nnnnn*}

Specifies the TCP/IP port number **ps2afp** uses to make a connection with the workstation on which the **ps2afpd** daemon is running (set by the **-S** flag). If your Infoprint installation uses more than one PostScript daemon, use this flag to select the daemon.

This port should not be the same port used by the TCP/IP-attached IPDS printer or the PCL transform. To find out which ports are already being used on your system (although they may or may not be active), look in the **/etc/services** file.

Values are:

**8251** The default port number.

**924** to *nnnnn*

Any valid port number greater than or equal to 924. The maximum value, *nnnnn*, depends on AIX, but it must be equal to or less than 65535.

**Note:** You can only access secure ports, 924 to 1023, with **root** user authority.

### **-p** *PageRange*

Specifies that the output should only contain selected pages. When you specify multiple **-p** flags, the **ps2afp** command transforms all the pages in the input, then extracts the specified MO:DCA-P pages and prints them in normal numerical order, regardless of the order you specify.

You cannot specify both the **-g** flag and the **-p** flag.

Examples of values include:

**-p even**

Output even pages.

**-p odd**

Output odd pages.

**-p 1-10**

Output pages 1 through 10.

**-p 10-** Output pages from page 10 until the end of the job.

**-p 1 -p 3 -p 6**

Output pages 1, 3, and 6, in that order.

**-p1 -p6 -p3**

Output pages 1, 3, and 6, in that order.

This flag is equivalent to the **page-select** document attribute on the **pdpr** command.

**-q** Quiets (suppresses) the echoing of the **ps2afp** command to the display.

**-r {240 | 300 | 480 | 600}**

Specifies the resolution of the output image. Select the resolution based on the printer on which you will be printing the image.

Values are:

**240** 240 pels-per-inch (for example, IBM 3812, 3825, 3827, 3835, and 3900 printers).

**300** 300 pels-per-inch (for example, IBM 4019, 4028, 4029, and 4039 printers and Hewlett-Packard printers)

**480** 480 pels-per-inch

**600** 600 pels-per-inch (for example, IBM 3900 printers), the default

This flag is equivalent to the **default-printer-resolution** document attribute on the **pdpr** command.

**Note:** If you specify a resolution that the printer does not support, Infoprint will print the image under most conditions, but with degraded results. Specify the correct resolution for the printer on which you will print the job.

**-S ServerName**

Specifies the name of the AIX system on which the **ps2afpd** daemon is running. If you do not specify this flag, the *ServerName* defaults to the effective name of the workstation on which you issued the **ps2afp** command. The value is:

*ServerName*

Any valid AIX workstation name on which the **ps2afpd** daemon is installed and running. The name is defined in the **/etc/hosts** file or by a name server, and may be a nickname like **molly**, or a dotted decimal address like **9.99.9.23**.

**-s {20 | 1 to 9998 | 9999}**

Specifies the maximum amount of time, in minutes, that the PostScript interpreter remains idle between jobs before it goes down. When the PostScript interpreter is running, it uses some of the workstation memory. If the PostScript interpreter goes down, you do not need to bring it back up; the interpreter automatically starts when you submit another PostScript or PDF job as long as the **ps2afpd** daemon is running.

Values are:

**20** The default time is 20 minutes.

## pdf2afp and ps2afp

### 1 to 9998

The time is the number of minutes specified in one-minute increments.

**9999** There is no time limit.

### **-w** *nnnn.nnnu*

Specifies the width of the generated image; *nnnn.nnn* is a number that can optionally contain a decimal point, and *u* is the units in inches (**i**) or millimeters (**m**). If you do not specify a unit (**i** or **m**), then **ps2afp** uses pels as the unit type. You cannot specify fractional values (that is, you cannot use a decimal point) for pels.

**Note:** If a text margin is already built into the file, try **-w8.5i** to set the width to 8.5 inches.

For 240-pel resolution printers, values are:

**8.5i** 8.5 inches, the default

### **16 to 8160**

The width can be from 16 pels to 8160 pels, 0.065i to 34i, or 1.641m to 863.628m. For example, the following are all valid:

```
-w 40m
-w 200.5m
-w 13i
-w 3300
```

For 300-pel resolution printers, values are:

**8.5i** 8.5 inches, the default

### **16 to 10200**

The width can be from 16 pels to 10200 pels, 0.052i to 34i, or 1.313m to 863.628m. For example, the following are all valid:

```
-w 40m
-w 200.5m
-w 13i
-w 5000
```

For 600-pel resolution printers, values are:

**8.5i** 8.5 inches, the default

### **16 to 20400**

The width can be from 16 pels to 20400 pels, 0.052i to 34i, or 1.313m to 863.628m. For example, the following are all valid:

```
-w 40m
-w 200.5m
-w 13i
-w 5000
```

This flag is equivalent to the **image-width** document attribute on the **pdpr** command.

### **-x** *nnnn.nnnu*

Specifies an X offset (horizontal offset) of the generated image; *nnnn.nnn* is a number that can optionally contain a decimal point, and *u* is the units in inches (**i**) or millimeters (**m**). If you do not specify a unit (**i** or **m**), then **ps2afp** uses pels as the unit type. You cannot specify fractional values (that is, you cannot use a decimal point) for pels.

An offset value specifies a border or margin around the generated image to avoid the non-printable areas of some printers. An X-offset value specifies the left and right margins of the generated image.

Values are:

**0** No border is specified. This is the default.

**0 to 17i**

The value specified here can be no greater than half of the value specified on the **-w** flag. For example, if you specified **-w=12i**, this value can be no greater than 6i.

This flag is equivalent to the **x-image-shift** document attribute on the **pdpr** command.

**Notes:**

1. The X offset specified with **-x** must be less than the width specified with **-w**. If the **-x** value is greater than or equal to the **-w** value, a blank page is printed.
2. The X-offset value specifies margins on both the left and right sides of the page. If you have a width of 8.5 inches and specify an X offset of 5 inches, a blank page will also result because the margins on the left and right sides of the paper exceed the width of the paper.
3. PostScript or PDF processing is slower when you use the **-x** flag, because the **ps2afpd** daemon must stop and re-start the PostScript interpreter. You may improve performance by changing the **ps\_x\_offset** value in the **ps2afpd** daemon configuration file rather than using **-x** on a regular basis.

**-y nnnn.nnnu**

Specifies a Y offset (vertical offset) of the generated image; *nnnn.nnn* is a number that can optionally contain a decimal point, and *u* is the units in inches (**i**) or millimeters (**m**). If you do not specify a unit (**i** or **m**), then **ps2afp** uses pels as the unit type. You cannot specify fractional values (that is, you cannot use a decimal point) for pels.

An offset value specifies a border or margin around the generated image to avoid the non-printable areas of some printers. A Y-offset value specifies the top and bottom margins of the generated image.

Values are:

**0** No border is specified. This is the default.

**0 to 17i**

The value specified here can be no greater than half of the value specified on the **-l** flag. For example, if you specified **-l=16i**, this value can be no greater than 8i.

This flag is equivalent to the **y-image-shift** document attribute on the **pdpr** command.

**Notes:**

1. The Y offset specified with **-y** must be less than the length specified with **-l**. If the **-y** value is greater than or equal to the **-l** value, a blank page is printed.
2. The Y offset value specifies margins on *both* the top and bottom edges of the page. If you have a length of 11 inches and specify an Y offset of

## pdf2afp and ps2afp

6 inches, a blank page will also result because the margins on the top and bottom of the paper exceed the length of the paper.

3. PostScript or PDF processing is slower when you use the **-y** flag, because the **ps2afpd** daemon must stop and re-start the PostScript interpreter. You may improve performance by changing the **ps\_y\_offset** value in the **ps2afpd** daemon configuration file rather than using **-y** on a regular basis.

## The ps2afp and ps2afpd Configuration Files

Instead of typing flags on the command line with the **ps2afp** or **pdf2afp** command, you can use the **-C** flag to specify a configuration file that contains the flags. In this way, you can simply specify a configuration file name, rather than typing many flags. You may find it convenient to use a configuration file if you repeatedly use the same flags with the **ps2afp** or **pdf2afp** command, or if you are using different PostScript or PDF processing values than the defaults defined by your system support group.

When your system support group installed the **ps2afp** transform and its alias, **pdf2afp**, a default **ps2afp** command configuration file, **ps2afp.cfg**, was installed in the following directory:

### With AIX

`/usr/lpp/psf/ps2afp`

### With NT/2000

`install_path\ps2afp`

If you want to create your own files, copy the **ps2afp.cfg** file and then use a system editor to modify the options in this ASCII file to suit your needs.

A default **ps2afpd** daemon configuration file, **ps2afpd.cfg**, was also installed in the following directory:

### With AIX

`/usr/lpp/psf/ps2afp`

### With NT/2000

`install_path\ps2afp`

The **ps2afpd** daemon configuration file can contain most of the same keywords as the **ps2afp** command configuration file, plus some keywords that control the operation of the **ps2afpd** daemon. Values in the command configuration file override values in the daemon configuration file.

Figure 5 on page 295 shows an example of a configuration file.



```

# ps2afp configuration file

# KEYWORD          EQUIVALENT ps2afp FLAG          PURPOSE
#####

port = 8251         # -P          which TCP/IP port to use
server = 127.0.0.1 # -S          which server to connect with

ps_max_memory = 14000K # -M          maximum amount of memory that
#                  #                  PostScript uses; the 'K' is ignored

ps_job_timeout = 20 # -j          maximum number of minutes
#                  #                  to process PostScript job

ps_server_timeout = 20 # -s          maximum number of minutes
#                  #                  server waits between jobs

ps_width = 8.5i    # -w          width of generated image
ps_length = 11i    # -l          length of generated image
ps_x_offset = 0i   # -x          left and right margins
ps_y_offset = 0i   # -y          top and bottom margins
ps_resolution = 600 # -r          resolution of printer
ps_output_type = I01_G4 # -a          type of AFP image to generate

```

Figure 5. Sample ps2afp Configuration File

Table 10 shows the **ps2afp** flags and their equivalent configuration file keywords. To override the values in the default configuration file, **ps2afp.cfg**, you can do one of the following:

- Specify flags with the **ps2afp** or **pdf2afp** command at transform time.
- Specify a configuration file with **ps2afp -C** at transform time.
- Specify **ps2afp** flags with **-o** flags on an AIX print command, or with equivalent attributes with the **-x** flag or in an attributes file on the **pdpr** command, to transform a file and print it at the same time.

**Note:** If you are migrating from PSF for AIX, see “Appendix B. Migrating PSF for AIX Job Script Keywords to Infoprint Equivalents” on page 691 for a table of attributes equivalent to the job script keywords that you used to use to specify flags and values for transforms.

Table 10. PostScript and PDF Printing and Processing Options

<b>ps2afp or pdf2afp Flag</b>	<b>Keyword in ps2afp Configuration File</b>	<b>Keyword in ps2afpd Configuration File</b>
<b>Note:</b> The valid values for configuration file keywords are the same as for the corresponding <b>ps2afp</b> or <b>pdf2afp</b> command flag. For keywords used only in the <b>ps2afpd</b> daemon configuration file, which have no corresponding command flag, see “ps2afpd Utility: Starts the ps2afpd Daemon” on page 191.		
<b>-a</b> <i>OutputType</i>	<b>ps_output_type=value</b>	<b>ps_output_type=value</b>
<b>-C</b> <i>ConfigurationFile</i>	None	None
<b>-c</b>	None	None
<b>-F</b> <i>FontMapFile[: ...]</i>	<b>ps_font_map_file=PathName</b>	<b>ps_font_map_file=PathName</b>
<b>-g</b> <i>PageRange</i>	None	None
<i>InputFile ...</i>	None	None
<b>-j</b> <i>nnnn</i>	<b>ps_job_timeout=nnnn</b>	<b>ps_job_timeout=nnnn</b>
<b>-l</b> <i>nnnn.nnnu</i>	<b>ps_length=nnnn.nnnu</b>	<b>ps_length=nnnn.nnnu</b>

## pdf2afp and ps2afp

Table 10. PostScript and PDF Printing and Processing Options (continued)

<i>ps2afp or pdf2afp Flag</i>	<i>Keyword in ps2afp Configuration File</i>	<i>Keyword in ps2afpd Configuration File</i>
<b>-M</b> <i>nnnnn</i>	<b>ps_max_memory</b> = <i>nnnnn</i>	<b>ps_max_memory</b> = <i>nnnnn</i>
<b>-o</b> <i>OutputFile</i>	None	None
<b>-P</b> <i>nnnnn</i>	<b>port</b> = <i>PortNumber</i>	<b>port</b> = <i>PortNumber</i>
<b>-p</b> <i>PageRange</i>	None	None
<b>-q</b>	None	None
<b>-r</b> <i>nnn</i>	<b>ps_resolution</b> = <i>nnn</i>	<b>ps_resolution</b> = <i>nnn</i>
<b>-S</b> <i>ServerName</i>	<b>server</b> = <i>ServerName</i>	None
<b>-s</b> <i>nnnn</i>	<b>ps_server_timeout</b> = <i>nnnn</i>	<b>ps_server_timeout</b> = <i>nnnn</i>
<b>-w</b> <i>nnnn.nnnu</i>	<b>ps_width</b> = <i>nnnn.nnnu</i>	<b>ps_width</b> = <i>nnnn.nnnu</i>
<b>-x</b> <i>nnnn.nnnu</i>	<b>ps_x_offset</b> = <i>nnnn.nnnu</i>	<b>ps_x_offset</b> = <i>nnnn.nnnu</i>
<b>-y</b> <i>nnnn.nnnu</i>	<b>ps_y_offset</b> = <i>nnnn.nnnu</i>	<b>ps_y_offset</b> = <i>nnnn.nnnu</i>
None	None	<b>log_file</b> = <i>PathName</i>
None	None	<b>mail_command</b> = <i>PathName</i>
None	None	<b>notify</b> = <i>UserID</i>
None	None	<b>ps_init_file</b> = <i>PathName</i>
None	None	<b>ps_program</b> = <i>PathName</i>
None	None	<b>ps_support_program</b> = <i>PathName</i>
None	None	<b>work_directory</b> = <i>PathName</i>

## Examples

- To submit the PostScript file `sample.ps` to the logical printer named `molly-lp`, enter the following:

### For AIX

```
enq -Pmolly-lp -odatat=ps /usr/lpp/psf/ps2afp/sample.ps
```

### For NT/2000

```
pdpr -pmolly-lp install_path\ps\sample.ps
```

- To transform the PDF file `myfile1` into an AFP data stream, and then submit it to the Infoprint logical printer called `robin-lp`, enter:

or

```
pdpr -p robin-lp -x "default-printer-resolution=300" myfile1
```

or

```
pdf2afp -r300 myfile1 | pdpr -p robin-lp
```

**Note:** You need to specify a resolution of 300 pels (`default-printer-resolution=300` or `-r300`) because `robin-lp` routes jobs to a 4019 printer device. The 4019 printer is a 300-pel resolution printer and the default resolution for the **pdf2afp** command is 600 pels.

- To transform the PostScript file `myfile2` into an AFP data stream, with an image that is 8 inches high and 5 inches wide, and write the result to a file called `myfile2.afp`, enter:

```
ps2afp -l 8i -w 5i -o myfile2.afp myfile2
```

or

```
ps2afp -l 8i -w 5i myfile2 > myfile2.afp
```

- To transform the PostScript file `myfile2` into an AFP data stream, creating a compressed IO (IOCA) image (the default image type for the **ps2afp** command), and piping the result to the **pdpr** command to submit the file to the Infoprint logical printer called `molly-lp`, enter:

```
ps2afp myfile2 | pdpr -p molly-lp
```

You can get the same result without piping (that is, using **pdpr** directly) by entering:

```
pdpr -p molly-lp myfile2
```

- To transform the PDF `myfile1` file into an AFP data stream in 300-pel resolution, as an IO1\_MMR image, and send the result to the printer with the **pdpr** command, enter:

```
pdf2afp -aIO1_MMR -r300 myfile1 | pdpr -X myafp.X
```

or

```
pdpr -X myps.X myfile1
```

where the attributes file named `myafp.X` contains the following settings:

```
document-format=modca-p
printer-name-requested=david-lp
```

and the attributes file named `myps.X` contains the following settings:

```
document-format=pdf
printer-name-requested=david-lp
image-out-format=io1_mmr
default-printer-resolution=300
```

- Assume that the PostScript file `myfile2` uses the **BarKode.pfa** font that is a PostScript resource not installed for use by the **ps2afpd** on an AIX system named `robin`. Also assume that the **ps2afpd** daemon is running on `robin`, but you are logged into the AIX system named `molly`. To transform `myfile2` into an AFP data stream, but not print it:

```
ps2afp -S robin -c -o myfile2.afp BarKode.pfa myfile2
```

The **-c** flag concatenates the two input files, with the file `BarKode.pfa` first, so that the two files are processed together. In this way, `myfile2` uses `BarKode.pfa` as an inline resource.

## Files

For AIX:

**/usr/lpp/psf/bin/ps2afpd**

PostScript daemon

**/usr/lpp/psf/bin/ps2afp**

PostScript transform executable

**/usr/lpp/psf/bin/pdf2afp**

PDF transform executable (linked to **/usr/lpp/psf/bin/ps2afp**)

**/usr/lpp/psf/ps2afp/ps2afpd.cfg**

**ps2afpd** daemon configuration file

**/usr/lpp/psf/ps2afp/ps2afp.cfg**

**ps2afp** command configuration file

**/usr/lpp/psf/bin/ppxps2i**

PostScript level 2 interpreter program

## pdf2afp and ps2afp

**/usr/lpp/psf/bin/ps2afpi**  
PostScript Level 1 interpreter program

**/usr/lpp/psf/bin/ps2afpi.vm**  
PostScript interpreter program initial virtual memory

**/usr/lpp/psf/ps2afp/ppxps2.ps**  
PostScript level 2 initialization file

**/usr/lpp/psf/ps2afp/ps2afp.ps**  
PostScript Level 1 initialization file

**/usr/lpp/psf/ps2afp/ps2afpe.ps**  
PostScript Level 1 initialization file for extended error reporting

**/usr/lpp/psf/bin/fontsave**  
PostScript executable for saving fonts

**/usr/lpp/psf/psfonts.map**  
Default PostScript font mapping file

**/var/psf/psfonts**  
User-defined PostScript fonts file

For NT/2000:

**install\_path\bin\ps2afpd.exe**  
PostScript daemon

**install\_path\bin\ps2afp.exe**  
PostScript transform executable

**install\_path\bin\pdf2afp.exe**  
PDF transform executable

**install\_path\ps2afp\ps2afpd.cfg**  
**ps2afpd** daemon configuration file

**install\_path\ps2afp\ps2afp.cfg**  
**ps2afp** command configuration file

**install\_path\bin\ps2afpi.exe**  
PostScript Level 1 interpreter program

**install\_path\bin\ps2afpi.vm**  
PostScript interpreter program initial virtual memory

**install\_path\ps2afp\ps2afp.ps**  
PostScript Level 1 initialization file

**install\_path\psfonts.map**  
Default PostScript font mapping file

**install\_path\var\psf\psfonts**  
User-defined PostScript fonts file

## sap2afp Command: Transforms SAP OTF or ABAP Data to AFP in Infoprint Manager for AIX

### Syntax

```
sap2afp -d DeviceName {-f FileName | -i | -q} [-g ]
          [-r { 240 | 300 | 480 | 600}] [-t]
```

### Description

Use the **sap2afp** command to transform an SAP Output Text Format (OTF) or Advanced Business Application Programming (ABAP) file into an AFP data stream file and to submit it to an Infoprint destination.

### Flags

- d *DeviceName*  
Specifies the name of the R/3 output device. This name is converted to the name of an Infoprint logical destination as specified in the **printer.tab** configuration file.
- f *FileName*  
Specifies the input file to be converted. This file is erased after successful conversion.
- g  
Invokes the Graphics Object Content Architecture (GOCA) feature of the printer device. The GOCA feature allows you to print boxes with four different levels of shading, as well as clear and solid boxes.
- i  
Specifies that input comes from standard input (**stdin**). A temporary file (**sap2afp.tmp**) is created, processed as with the **-f** parameter, then erased.
- q  
Invokes the **lpq** command to display the queue.
- r { 240 | 300 | 480 | 600}  
Specifies the printer resolution used to print image data in the job. If you do not specify the **-r** flag, the **DEFRES** value in the **image.tab** file is used. In the **image.tab** file shipped with Infoprint, the **DEFRES** value is **600**.
- t  
Traces program execution.

### The sap2afp Configuration Files

This section consists of examples for the following configuration files that are required for the **sap2afp** transform:

```
barcode.tab
defcp.tab
fonts.tab
image.tab
pagedef.tab
printer.tab
xxxxyyyy.tab
```

#### Notes:

1. All tables can contain comments (starting with **//** in column 1) and empty lines. These lines are ignored by the **sap2afp** transform.
2. All table entries are case-sensitive.

## barcode.tab Configuration File

This table describes the bar code mappings. SAP calls bar codes by names that must be mapped into the matching bar codes available with Bar Code Object Content Architecture (BCOCA).

**barcode.tab** uses the following keyword-value pairs:

### BarCode

Specifies the OTF bar code names (**SAPBARCODE** parameter of the **BC** OTF command). The maximum length of this field is 8 bytes. It can contain any value.

**Type** Specifies the AFP bar code type as defined in *IBM Data Stream and Object Architectures: Bar Code Object Content Architecture Reference* for the **Barcode Type** parameter of the **Barcode Data Descriptor** Structured Field. The content can be any decimal value between 0 and 999. The **sap2afp** transform does not verify that this value maps to a valid hexadecimal barcode type.

**Mode** Specifies the modifier byte within the **Barcode Modifier** parameter of the **Barcode Data Descriptor** Structured Field. Any numeric value between 0 and 999 is accepted and not verified.

**Flag** Controls the printing of the Human Readable Interface (**HRI**) character. Specify one of the following values:

**0** Causes the **HRI** character to be printed

**128** Causes the **HRI** character not to be printed

### ModWidth=*n*

This optional keyword specifies the width of the smallest defined bar code element, using mils (thousandths of an inch). For bar code types that explicitly specify the module width, such as POSTNET or RM4SCC, this field is ignored. The range of values allowed is 1–254. If **ModWidth** is not specified, the printer default ModWidth is used.

*n* specifies the width of each module, using thousandths of an inch (1/1000) as the unit of measurement.

### Ratio=*n*

This optional keyword specifies the ratio between the width of the wide and the narrow bar code elements. The range of values allowed is 100–500, but you must specify a value appropriate for your printer and bar code type. If the values you specify are not appropriate for your printer, error messages are issued at printing time. If **Ratio** is not specified, the printer default Ratio is used.

*n* specifies the **Ratio** as a percent value. The ratio value should be between 200 and 300 in the form *mnn*. For example, 200 represents a ratio of 2 to 1; 250 represents a ratio of 2.5 to 1. For bar code types that explicitly specify the module width (for example, POSTNET and RM4SCC, this field is ignored. If **RATIO** is not specified, the default ratio for the bar code symbol is used.

**Note:** Many barcode types do not support Ratio values or if they do, the Ratio values are within certain ranges that are type-specific.

The following example uses both the **Ratio** and **ModWidth** optional keywords:

```
BarCode=BC_CD39 Type=001 Mode=001 Flag=128 Ratio=200 ModWidth=10
```

#### Notes:

1. The system administrator is responsible for the values entered in the table. Invalid values are not verified and may result in errors.
2. The second group of bar codes in the **barcode.tab** file (following the blank line) is supported from R/3 Release 3.0A only.

Figure 6 shows a sample **barcode.tab** configuration file.

```
// Barcode table

// Format : Barcode=ARTNR Type=017 Mode=002

//BarCode = 30F9      Type = 001 Mode = 001 Flag = 000
//BarCode = 30F91    Type = 001 Mode = 002 Flag = 000
//BarCode = MSI      Type = 002 Mode = 002 Flag = 000
//BarCode = UPCA     Type = 003 Mode = 000 Flag = 000
//BarCode = UPCE     Type = 005 Mode = 000 Flag = 000
//BarCode = UPC2     Type = 006 Mode = 000 Flag = 000
//BarCode = UPC5     Type = 007 Mode = 000 Flag = 000
//BarCode = EAN8     Type = 008 Mode = 000 Flag = 000
//BarCode = EAN13    Type = 009 Mode = 000 Flag = 000
//BarCode = IND25    Type = 010 Mode = 002 Flag = 000
//BarCode = MAT25    Type = 011 Mode = 002 Flag = 000
//BarCode = INTER    Type = 012 Mode = 002 Flag = 000
//BarCode = CODA     Type = 013 Mode = 002 Flag = 000
//BarCode = C128     Type = 017 Mode = 002 Flag = 000
//BarCode = EAN2     Type = 022 Mode = 000 Flag = 000
//BarCode = EAN5     Type = 023 Mode = 000 Flag = 000
//BarCode = POST     Type = 024 Mode = 002 Flag = 000
//BarCode = AUFNR    Type = 001 Mode = 001 Flag = 128

BarCode = ARTNR      Type = 017 Mode = 002 Flag = 000
BarCode = AUFNR      Type = 017 Mode = 002 Flag = 000
BarCode = BARCLVS    Type = 001 Mode = 001 Flag = 000

BarCode = BC_C128B   Type = 017 Mode = 002 Flag = 128
BarCode = BC_CD39    Type = 001 Mode = 001 Flag = 128
BarCode = BC_CD39C   Type = 001 Mode = 002 Flag = 128
BarCode = BC_EAN13   Type = 009 Mode = 000 Flag = 128
BarCode = BC_EAN8    Type = 008 Mode = 000 Flag = 128
BarCode = BC_I25     Type = 012 Mode = 001 Flag = 128
BarCode = BC_I25C    Type = 012 Mode = 002 Flag = 128
BarCode = BC_MSI     Type = 002 Mode = 001 Flag = 128
BarCode = BC_MSIC    Type = 002 Mode = 002 Flag = 128
BarCode = BC_MSIC1   Type = 002 Mode = 003 Flag = 128
BarCode = BC_MSIC2   Type = 002 Mode = 005 Flag = 128

BarCode = KUNAUNR    Type = 017 Mode = 002 Flag = 000
BarCode = KUNAUPS    Type = 017 Mode = 002 Flag = 000
BarCode = MBBARC     Type = 017 Mode = 002 Flag = 000
BarCode = MBBARC1    Type = 008 Mode = 000 Flag = 000
BarCode = RSNUM      Type = 017 Mode = 002 Flag = 000
BarCode = RSPOS      Type = 017 Mode = 002 Flag = 000
BarCode = RUECKNR    Type = 017 Mode = 002 Flag = 000
```

Figure 6. Sample barcode.tab Configuration File

### defcp.tab Configuration File

Figure 7 shows the default conversion table for the conversion of ASCII characters into EBCDIC. The **sap2afp** transform uses this table for ABAP data conversion.

The left column consists of the ASCII code, while the right column contains the corresponding EBCDIC value. The values are checked for a numeric value between 0 and 255.

```
// Linedata CodePage
//-----
// This file is used internally by sap2afp, as well as
// to convert ABAP data to linedata.

// Format : Ascii=Ebcdic

// T1000819 + box characters -> T1DATABASE

000 = 064
001 = 064
002 = 064
  :
253 = 064
254 = 062
255 = 223
```

Figure 7. Sample *defcp.tab* Configuration File

### fonts.tab Configuration File

This table maps the fonts used in the OTF data stream to AFP fonts.

The following font families are predefined with R/3:

<b>FONTFAMILY</b>	<b>Font</b>
<b>COURIER</b>	Courier
<b>HELVE</b>	Helvetica
<b>LETGOTH</b>	Letter Gothic
<b>LNPRINT</b>	Line Print
<b>TIMES</b>	Times New Roman
<b>OCRA</b>	Optical Character Recognition A
<b>OCRB</b>	Optical Character Recognition B
<b>JPMINCHO</b>	Heisei Mincho
<b>DBMINCHO</b>	Heisei Mincho
<b>DBGOTHIC</b>	Heisei Gothic

**Note:** **JPMINCHO** and **DBMINCHO** are different names for the same font.

A font named **BARCODE** must be defined for the **HRI** character of a bar code.

The following parameters in the **fonts.tab** configuration file set the format of the fonts you use to print with R/3:

#### **DefCodePage**

Specifies the default SBCS code page used if no **FC** OTF command is given or if the requested font is not found in the **fonts.tab** table.

#### **DefCharSet**

Specifies the default SBCS character set used if no **FC** OTF command is given or if the requested font is not found in the **fonts.tab** table.



**DBDefCodePage**

Specifies the default DBCS code page used if no **FC** OTF command is given or if the requested font is not found in the **fonts.tab** table.

**DBDefCharSet**

Specifies the default DBCS character set used if no **FC** OTF command is given or if the requested font is not found in the **fonts.tab** table.

**SBDefCodePage**

Specifies the default SBCS code page used for half-width characters in DBCS fonts if no **FC** OTF command is given or if the requested font is not found in the **fonts.tab** table.

**SBDefCharSet**

Specifies the default SBCS character set used for half-width characters in DBCS fonts if no **FC** OTF command is given or if the requested font is not found in the **fonts.tab** table.

**Font** Describes the font family (**FONTFAMILY** parameter of the **FC** OTF command). The maximum size is 8 bytes and content is not verified.

**Size** Specifies the font size in 1/10 of a point (**FONT SIZE** parameter of the **FC** OTF command). The value must be numeric and is not verified.

**Type** Defines the font type (**BOLD** and **ITALIC** parameter of the **FC** OTF command). **Type=0** is normal, **Type=1** is italic, **Type=2** is bold, and **Type=3** is italic bold. Any other value is invalid.

**CodePage**

Specifies the code page and requires a valid AFP code page name (8 bytes). The value is not verified. An invalid name can result in an error message.

**CharSet**

Specifies the AFP font character set. The content is not verified.

**CodedFont**

Specifies the AFP coded font. The content is not verified.

**DB** Specifies whether the font is an SBCS font (**DB=0**) or a DBCS font (**DB=1**).

**SBCodePage**

Specifies the single-byte code page used for half-width characters in DBCS fonts. The value is not verified. An invalid name can result in an error message.

**SBCharSet**

Specifies the AFP single-byte font character set used for half-width characters in DBCS fonts. The content is not verified.

**SBCodedFont**

Specifies the AFP single-byte coded font used for half-width characters in DBCS fonts. The content is not verified.

If an SBCS font that matches the **Font**, **Size** and **Type** values is not found, the code page and font character set from the **DefCodePage** and **DefCharSet** keywords are used and a warning message is displayed. If a DBCS font that matches the **Font**, **Size** and **Type** values is not found, the code pages and font character sets from the **DBDefCodePage**, **SBDefCodePage**, **DBDefCharSet**, and **SBDefCharSet** keywords are used and a warning message is displayed.

## sap2afp

The device types **IBMAFP** and **IBMAFP3** support the predefined font families. These font families are also supported as IBM Expanded Core Fonts, or IBM Chinese, Japanese, and Korean (CJK) Fonts.

ISO 8859-1 (Latin-1) is the default code page that maps to the **1148** code page in the **fonts.tab** configuration table. This ISO code page maps to the German **T1V10273** code page and must be modified for non-Latin-1 R/3 installations. You can make this change on the **xxxxyyyy.tab** configuration file that is used to convert data from ASCII data to EBCDIC data so that these characters are mapped correctly. If you have installed a SAP R/3 Release 2.2 or earlier, use the **S9148.CPA** file to determine the modifications you need to make.

Use the font Letter Gothic Latin1 of the coordinated font family for ABAP listings. If you do not want to install the coordinated font family and plan to use the traditional Gothic text fonts found within the IBM Compatibility Fonts, you can adjust the font names in the **pagedef.tab** configuration file.

If you wish to use fonts that are not supported, take the following steps:

1. Obtain the font as Adobe Type 1.
2. Convert the font into a raster using the Type Transformer in the IBM AFP Font Collection (program number 5648-113).
3. Contact your IBM representative for further details.

Figure 8 on page 305 and Figure 9 on page 305 show examples of sections of the **fonts.tab** configuration file.

```

// Fonts table
// Format : Font=COURIER Size=070 Type=0 CodePage=T1V10273 CharSet=C0420070 DB=0
//          or
//          Font=COURIER Size=090 Type=0 CodedFont=X0GT2A DB=0
//          or
//          Font=JPMINCHO Size=060 Type=0 CodePage=T10300 CharSet=CZJHMN DB=1 SBCodePage=T1H01027 SBCharSet=CZJHMN
//          or
//          Font=JPMINCHO Size=060 Type=0 CodedFont=XZJHMN DB=1 SBCodedFont=XZN16J
DefCodePage = T1V10273
DefCharSet   = C0420000
DBDefCodePage = T10300
DBDefCharSet  = CZJHMN
SBDefCodePage = T1H01027
SBDefCharSet  = CZJHMN

// Courier
Font=COURIER  Size=070 Type=0 CodePage=T1V10273 CharSet=C0420070 DB=0
Font=COURIER  Size=070 Type=1 CodePage=T1V10273 CharSet=C0430070 DB=0
Font=COURIER  Size=070 Type=2 CodePage=T1V10273 CharSet=C0440070 DB=0
Font=COURIER  Size=070 Type=3 CodePage=T1V10273 CharSet=C0450070 DB=0
Font=COURIER  Size=080 Type=0 CodePage=T1V10273 CharSet=C0420080 DB=0
Font=COURIER  Size=080 Type=1 CodePage=T1V10273 CharSet=C0430080 DB=0
Font=COURIER  Size=080 Type=2 CodePage=T1V10273 CharSet=C0440080 DB=0
Font=COURIER  Size=080 Type=3 CodePage=T1V10273 CharSet=C0450080 DB=0
Font=COURIER  Size=100 Type=0 CodePage=T1V10273 CharSet=C0420000 DB=0
Font=COURIER  Size=100 Type=1 CodePage=T1V10273 CharSet=C0430000 DB=0
Font=COURIER  Size=100 Type=2 CodePage=T1V10273 CharSet=C0440000 DB=0
Font=COURIER  Size=100 Type=3 CodePage=T1V10273 CharSet=C0450000 DB=0
Font=COURIER  Size=120 Type=0 CodePage=T1V10273 CharSet=C04200B0 DB=0
Font=COURIER  Size=120 Type=1 CodePage=T1V10273 CharSet=C04300B0 DB=0
Font=COURIER  Size=120 Type=2 CodePage=T1V10273 CharSet=C04400B0 DB=0
Font=COURIER  Size=120 Type=3 CodePage=T1V10273 CharSet=C04500B0 DB=0
Font=COURIER  Size=140 Type=0 CodePage=T1V10273 CharSet=C04200D0 DB=0
Font=COURIER  Size=140 Type=1 CodePage=T1V10273 CharSet=C04300D0 DB=0
Font=COURIER  Size=140 Type=2 CodePage=T1V10273 CharSet=C04400D0 DB=0
Font=COURIER  Size=140 Type=3 CodePage=T1V10273 CharSet=C04500D0 DB=0
Font=COURIER  Size=200 Type=0 CodePage=T1V10273 CharSet=C04200J0 DB=0
Font=COURIER  Size=200 Type=1 CodePage=T1V10273 CharSet=C04300J0 DB=0
Font=COURIER  Size=200 Type=2 CodePage=T1V10273 CharSet=C04400J0 DB=0
Font=COURIER  Size=200 Type=3 CodePage=T1V10273 CharSet=C04500J0 DB=0

```

Figure 8. Header and Courier Portions of a Sample fonts.tab Configuration File

```

// Japanese Gothic
Font=DBGOTHIC Size=060 Type=0 CodePage=T10300 CharSet=CZJHKG DB=1 SBCodePage=T1H01027 SBCharSet=CZJHKG
Font=DBGOTHIC Size=080 Type=0 CodePage=T10300 CharSet=CZJHKG DB=1 SBCodePage=T1H01027 SBCharSet=CZJHKG
Font=DBGOTHIC Size=100 Type=0 CodePage=T10300 CharSet=CZJHKG DB=1 SBCodePage=T1H01027 SBCharSet=CZJHKG
Font=DBGOTHIC Size=100 Type=1 CodePage=T10300 CharSet=CZJHKG DB=1 SBCodePage=T1H01027 SBCharSet=CZJHKG
Font=DBGOTHIC Size=120 Type=0 CodePage=T10300 CharSet=CZJHKG DB=1 SBCodePage=T1H01027 SBCharSet=CZJHKG
Font=DBGOTHIC Size=140 Type=0 CodePage=T10300 CharSet=CZJHKG DB=1 SBCodePage=T1H01027 SBCharSet=CZJHKG
Font=DBGOTHIC Size=160 Type=0 CodePage=T10300 CharSet=CZJHKG DB=1 SBCodePage=T1H01027 SBCharSet=CZJHKG
Font=DBGOTHIC Size=180 Type=0 CodePage=T10300 CharSet=CZJHKG DB=1 SBCodePage=T1H01027 SBCharSet=CZJHKG

```

Figure 9. Heisei Gothic Portion of a Sample fonts.tab Configuration File

### image.tab Configuration File

This table defines values used to print image data. It contains the following parameters:

#### DEFRES

Specifies the default resolution used for printing image data if you do not specify a value for the **-r** flag of the **sap2afp** command. Valid values are **240**, **300**, **480**, and **600**.

**Width** Specifies the width of the dither matrix.

#### Height

Specifies the height of the dither matrix.

## sap2afp

**Cell** Specifies the values for the dither matrix.

### Transform

Specifies 256 grayscale correction values.

Figure 10 shows an example of the **image.tab** configuration file.

```
// image.tab
// from image.tab.851r
//
// This file is used to determine the dither matrix and the
// grayscale correction values.

// Define the default output resolution
DEFRES = 600

// Define the dither matrix
Width = 78
Height = 78
Cell =
  15  63 184 219 249 240 158 109  98  54  82 118 133 113  75  64
  87 104 166 215 234 229 179  62  38  4  15  59 186 220 246 240
166 123  87  61  65 108 133 118  78  64 100 105 167 219 234 230
  :
  28  73 193 223 253 247 199  76  31  8  20  93 148 156 203 178
136 126 144 186 201 155 151  90  43  24  28  75 199 222 254 251
196  79  31  7

//
// Grayscale correction values
//

Transform =
0
1
2
:
:
248
252
255
```

Figure 10. Sample **image.tab** Configuration File

### **pagedef.tab** Configuration File

The **pagedef** table provides the **PAGEDEF** and **FORMDEF** values used from the value of the **\*PJPAPER** parameter that is passed to the **sap2afp** transform with the **Z** access method. It also provides the fonts used for ABAP data.

The name of a **PAGEDEF** for line data is restricted to five digits instead of the usual six characters. The reason for this restriction is that the **PJPAPER** field is twelve bytes long and **must** begin with a **Z**. This restriction applies to ABAP reports (line data) with user-specific formatting only.

**Paper** Specifies the value of the OTF print option parameter **PJPAPER**. The value is not verified.

### **FormDef**

Specifies the name of the form definition to be used for printing both OTF and ABAP reports. This value is not verified. An error results if the form definition is not found on the print server system.

**PageDef**

Specifies the name of the page definition to be used for printing ABAP reports. This value is not verified. An error results if the page definition is not found on the print server system.

**FontNorm**

Specifies the normal coded font used for line data printing. The value is not verified.

**FontBold**

Specifies the bold coded font used for line data printing. The value is not verified.

Figure 11 shows a sample **pagedef.tab** configuration file:

```
// PageDef table
// Format : Paper=X_65_132 FormDef=F1A10111 PageDef=P1H01SP1
// FontNorm = 50D0 FontBold = 50F0

// Notes:
// =====
// 1) The pagedefs apply to letter size paper.
//    A4 paper size may require modifying the PageDef field.
// 2) Z_INCH12 is a sample for a user specification

Paper=X_65_132 FormDef=F1A10111 PageDef=P1V06683 FontNorm = GB2A FontBold = GB2A
Paper=X_44_120 FormDef=F1A10111 PageDef=P1V06683 FontNorm = GB2A FontBold = GB2A
Paper=X_58_170 FormDef=F1A10111 PageDef=P1V06683 FontNorm = GT8A FontBold = GT8A
Paper=X_65_255 FormDef=F1A10111 PageDef=P1V06683 FontNorm = GT24 FontBold = GT24
Paper=X_65_80 FormDef=F1A10111 PageDef=P1C09182 FontNorm = GT2A FontBold = GB2A
Paper=X_90_120 FormDef=F1A10111 PageDef=P1C09182 FontNorm = GT5A FontBold = GT5A
Paper=X_PAPER FormDef=F1A10111 PageDef=P1C09182 FontNorm = GT2A FontBold = GB2A
// Sample of an added user-defined pagedef entry:
// Paper=Z_INCH12 FormDef=F1SAPFD PageDef=P1SAPPD FontNorm = GT2A FontBold = GB2A
```

Figure 11. Sample pagedef.tab Configuration File

**printer.tab Configuration File**

Before you can use the R/3 output device, you must map it to an Infoprint logical printer. This is done in the **printer.tab** configuration file that comes with the **sap2afp** transform. **printer.tab** is located in the **/usr/lpp/psf/sap2afp** directory. Because SAP R/3 restricts the names of output devices to four characters, the **printer.tab** configuration file allows you to map these names to longer and more meaningful names.

**Note:** You must update the **printer.tab** file every time you add or delete an R/3 AFP printer.

**printer.tab** uses the following keyword-value pairs:

**Dest** Specifies the four-character name of the R/3 output device. Specify this value for the **-d** flag of the **sap2afp** command.

**System**

Specifies the operating system from which the **sap2afp** output is printed.

**Queue**

Specifies the name of the Infoprint logical destination.

**Node** Specifies the IP address of the target operating system. The content (a maximum of 15 bytes) is not verified.

**Node** is required for all values of the **System** keyword, but the value is used only when **System=OS/2**.

Figure 12 shows a sample **printer.tab** configuration file. Note that you can include comments in lines preceded by two slashes (*//*).

```
// Printer table
// Format : Dest=SPRT System=AIX Queue=pc14039 Node=192.9.200.220
// Note: The Node parameter is not used for entries where the
// System field is AIX or MVS, but you must still enter a value.
Dest=MVSP System=MVS Queue=pc14039 Node=192.9.200.220
Dest=AIX1 System=AIX Queue=pc14029 Node=192.9.200.116
Dest=AIX2 System=AIX Queue=PSF4039 Node=192.9.200.220
Dest=OS2P System=OS2 Queue=OS2AFP Node=192.9.201.66
Dest=OS2 System=OS2 Queue=OS2AFP Node=192.9.201.66
```

Figure 12. Sample printer.tab Configuration File

For example, suppose that you have defined an R/3 AFP printer called **AFPT**. To map **AFPT** to the Infoprint logical destination **psf3116**, add the following line to **printer.tab**:

```
Dest=AFPT System=AIX Queue=psf3116 Node=0.0.0.0
```

### xxxxyyyy.tab Configuration File

These tables are used for the mapping of characters of an individual SAP ASCII code page into an EBCDIC codepage. SAP uses two kinds of code pages: input code pages and output code pages.

SAP provides the the code page configuration files listed in Table 11.

Table 11. SAP Code Page Configuration Files

File Name	Input Code Page	Description	Output Code Page	Description
00000000.tab	T1000819	Latin-1 ISO ANSI 8-bit	T1V10273	Germany F.R./Austria-CECP
11000000.tab	T1000819	Latin-1 ISO ANSI 8-bit	T1V10273	Germany F.R./Austria-CECP
40010000.tab	T1000876 <sup>1</sup>	OCR-A ASCII	T1000892	OCR-A
40040000.tab	T1000877 <sup>1</sup>	OCR-B ASCII	T1000893	OCR-B
80000000.tab	IBM-932	Japanese	IBM-1031-SAP2AFP	Japanese

1. Both the OCR-A and the OCR-B code pages are equivalent to ISO-8859/1 with the special characters **hook**, **fork**, and **chair**.

The file names correspond to the 4-digit value of the **INPUTCODEPAGE** plus the 4-digit value **OUTPUTCODEPAGE** parameter of the **CP** OTF command.

```
// Codepage table

// Inp CodePage 0000
// Out CodePage 0000

// Format : Ascii=Ebcdic

000 = 000
001 = 001
002 = 002
003 = 003
  :
253 = 064
254 = 062
255 = 223
```

Figure 13. Sample xxxxyyyy.tab Configuration File (Single-Byte Code Pages)

```
// Japanese
// SAP2AFP is configured to use IBM-932-SAP2AFP as the iconv
// "From" value.
// This table sets the "To" value to IBM-1031-SAP2AFP.
//

CONVERT FOR=8000
CONVERT TO=IBM-1031-SAP2AFP
```

Figure 14. Sample xxxxyyyy.tab Configuration File (Double-Byte Code Pages)

## Examples

### Transforming and Printing a File

This command converts the file **FONTSHP.OTF** and queues the AFP datastream for the destination called **3825**. After conversion, SAP R/3 erases the input file **FONTSHP.OTF**.

```
sap2afp -d 3825 -f FONTSHP.OTF
```

### Transforming and Printing from Standard Input

This command redirects the spooled file **SP11041** to **stdin**, which is read by the **sap2afp** transform. The input from **stdin** is placed in the **sap2afp.tmp** file, which is processed and then erased. AFP data stream output is sent to destination **LPRT**.

```
sap2afp -d LPRT -i < /usr/sap/DEV/DVEBMGS00/SP11041
```

### Tracing the Transform

This command converts the file **ANYFILE.OTF** and sends output to destination **3825**. A trace of the execution can be found in the file **sap2afp.trc**, which is placed in the current directory.

```
sap2afp -d 3825 -f ANYFILE.OTF -t
```

## tiff2afp Command: Transforms TIFF Data to AFP in Infoprint Manager for AIX

### Syntax

```
tiff2afp [-a ImageType] [-alg ProcessingAlgorithms]
          [-calib calibration] [-choice ImageChoice]
          [-C ConfigurationFile] [-clean cleanup]
          [-cmp compression] [-crop CropFactors]
          [-fit {trim | scale}] [-force]
          [-gcorr GrayscaleMappingTable] [-ink color] [-inv]
          [-j ScanOffsetFileName] [-l ImageLength ]
          [-M MemoryBound] [-mp | -nomp]
          [-ms space] [-msf SpaceFraction]
          [-o OutputFile] [-outbits NumberOfOutputBits]
          [-outcolor OutputColorModel] [-p PageRange]
          [-pagetype PageType] [-paper PaperSize]
          [-r resolution] [-respath ResourceSearchPath]
          [-rot rotation] [-scale ImageSize]
          [-sgcorr ScannerCorrection]
          [-sniff | -nosniff] [-term | -noterm]
          [-thresh HalftoneFile] [-v | -nov]
          [-w ImageWidth] [-wrkdir WorkDirectory]
          [-x LeftMargin] [-y TopMargin] [-z]
          [[file | directory | -f FileList | @FileList]...]
```

### Description

The **tiff2afp** command transforms a TIFF (Tag Image Format File) data stream into an AFP (MO:DCA-P) or PostScript Level 2 data stream file.

The transform can process extended TIFF Revision 6.0 images, including bilevel, grayscale and color images. The output can be bilevel (IM1 or IOCA FS10), 4-bit or 8-bit grayscale, or 24-bit YCbCr color (IOCA FS11). The transform automatically uses halftoning to convert the grayscale and color images to bilevel.

### Automatic Invocation

The PSF DSS automatically invokes the **tiff2afp** transform command whenever you submit a TIFF file for printing. You can pass options to **tiff2afp** using the **other-transform-options** attribute on the **pdpr** command or the **-o** flag of the AIX print commands and the **lprafp** command.

### Input and Output

**tiff2afp** can process either standard input, or multiple files specified on the command line. If no input file is specified, **stdin** is assumed. Standard input is cached to a file (see the **-wrkdir** option) and then processed. Only a single TIFF file should be submitted via **stdin**. If multiple TIFF files are concatenated via standard input, all except the first one are ignored.

If an input file is specified on the command line, it can be either a TIFF file, a directory, or a file list (**-f** and **@** prefixes). Multiple input file specifications are allowed. The transform processes each file in the order in which it was specified on the command line. If the **-z** option is specified, a list of file names to be processed



is also submitted via standard input. The files on the list are processed as if the list were given via the **-f** option on the same place on the command line as **-z**.

If the file name points to a directory, **tiff2afp** processes every file in that directory. The files are processed in the order they would be shown using the **ls -a** command. Directory search is not recursive, that is, the subdirectories are not searched.

If the file name is preceded by the **-f** option or the at sign (**@**), **tiff2afp** assumes that the file contains the list of TIFF files to be processed. Each of the files in the list is processed in the order it was listed.

If a TIFF file has the extension **.tif**, **.tiff**, **.TIF**, or **.TIFF**, this extension need not be given explicitly. **tiff2afp** first tries to open the file as specified and, if unsuccessful, tries to append the extensions **.tif**, **.tiff**, **.TIF**, and **.TIFF** in turn.

For example, suppose that:

- The directory `tFiles` contains the files `file1.tif`, `file2.tif`, `file3.tif`, and `file4.tif` and nothing else.
- The file `f1ist` in the current directory contains the two file names `tFiles/file2.tif` and `tFiles/file3.tif`. The names listed in the file list may have their extensions omitted.
- The file `f1ist2` contains the file name `tFiles/file4`. Again, the names listed in the file list may have their extensions omitted.

In order to process files `file1.tif`, `file2.tif`, `file3.tif`, and `file4.tif`, any of the following invocations of **tiff2afp** would work:

```
tiff2afp tFiles/file1.tif tFiles/file2.tif tFiles/file3.tif tFiles/file4.tif
tiff2afp tFiles/file1 tFiles/file2 tFiles/file3 tFiles/file4
tiff2afp tFiles/file*.tif
tiff2afp tFiles
tiff2afp tFiles/file1 -fflist tFiles/file4
tiff2afp tFiles/file1 -f f1ist tFiles/file4
tiff2afp tFiles/file1 -f f1ist -f f1ist2
tiff2afp tFiles/file1 @f1ist @f1ist2
```

The file list files allow the display text to be added for each file. A display text is any text starting with the pound character (**#**) and extending to the end of the line. The display text should follow the file name, and can extend over several lines, up to 2048 characters long. The initial **#** character on each line is discarded. If a display text is present for a file name, that text is displayed in the status and error messages instead of the file name. This is useful if the **tiff2afp** is invoked using temporary files whose names are meaningless to the user. Any display text before the first file name is treated as comment and discarded. Display text is allowed also if the **-z** option is used to submit the file list via standard input.

TIFF files may contain multiple images. The **tiff2afp** transform can process and output all the images in the file, both full and reduced resolutions, subject to the values given in the **-choice** and **-p** options. Transparency maps are ignored. If the page numbers are available in the TIFF data, the pages are sorted on output. The pages are not sorted across file boundaries.

The output file name can be either specified explicitly via the **-o** option, or derived from the input file name. If multiple input files have been specified, the default output file is standard output. If a single input file is given and the output file is not specified explicitly, the transform strips the **.tif** or **.tiff** extension from the input file

## tiff2afp

name (if one is present), and appends the **.afp** extension for AFP output, or the **.ps** extension for PostScript output, to get the output file name.

To disable automatic output file name generation and force the default output stream to be the standard output in all cases, set the environment variable **TIFF2AFP\_o** to **-** or **stdout**, or, alternatively, put the line **o=-** or **o=stdout** into the configuration file and invoke that configuration file using the **-C** option or the **TIFF2AFP\_C** environment variable.

For example, all the following commands:

```
tiff2afp myfile
tiff2afp myfile.tif
tiff2afp myfile -o myfile.afp
```

have `myfile.afp` as the output file. Note that there is no requirement for the explicitly specified input and output files to have **.tif** and **.afp** extensions. To process TIFF file `foo.bar` into an AFP file `foo.bar2`, invoke the transform using

```
tiff2afp foo.bar -o foo.bar2
```

The output data stream is MODCA-P IS/1, MODCAP-P IS/2, or PostScript Level 2. IS/1 images are bilevel and are encoded as IOCA Function Set 10 or IM1. IM1 images are uncompressed. IOCA FS10 output images can be either uncompressed, or compressed via one of the four available compression algorithms (see the **-cmp** option). The default is ITU-T T.6 Group 4 compression. IM1 images are always uncompressed. IS/2 images can be either bilevel, 4-bit or 8-bit grayscale, or 24 bit YCbCr color. Multibit images are encoded as IOCA Function Set 11. Be aware that the only product that supports IOCA FS11 images is the AFP Workbench, that is, grayscale and color AFP images are not currently supported by any printer.

PostScript Level 2 images can be uncompressed or ITU-T T.6 Group 4 bilevel, uncompressed 8-bit grayscale or uncompressed 24-bit RGB color. By default, the transform leaves scaling and halftoning to the printer (that is, color TIFF images are output as 24-bit RGB color images).

## Errors and Error Recovery

**tiff2afp** divides errors into fatal and non-fatal. The fatal error categories are the following:

- Errors in the user-specified parameters, either in the environment variables, the configuration file, or the command line arguments. These errors include unrecognized options, invalid values for parameters, or inability to open the configuration file or the output file.
- Out of memory errors. The requested memory is larger than the memory specified using the **-M** option or the dynamic memory allocation has failed.
- Disk space errors. The transform guards against trying to write to a full file system. See the **-ms** and **-msf** options for setting the minimum free disk space requirements. If the file system is full, the transform deletes the partial output file before terminating.
- Internal errors.

In the case of a fatal error, the last output page might not be complete.

Errors encountered in the TIFF files are non-fatal and **tiff2afp** attempts to recover from them. These errors include not being able to open an input file, an input file not being a TIFF file, or an input file containing features that cannot be processed.

If the transform fails to open 15 or more input files, it assumes an error in the parameter list (for example, **-f** was used with a file that does not contain a file list) and terminates.

If an error is encountered in a file, the transform attempts to recover with the next image in the file. If such recovery is not possible, **tiff2afp** attempts to recover with the next input file. In both cases, a warning message is issued. Errors and warnings are output to standard error.

For example, let a directory `tFiles` contain files `file1.tif`, `file1.txt`, `file2.tif` and `file3.tif`, where `file1.txt` is an ASCII file. Invoking the transform via `tiff2afp tFiles`

processes the bilevel images in all three TIFF files correctly. A warning is issued that `file1.txt` is not a TIFF file.

Non-fatal errors can be made fatal by using the option **-term**, or the corresponding environment variable or configuration file entry. If **-term** is set, the transform terminates in error if it encounters an error in the TIFF data stream.

## Data Transformations

If the input image is grayscale or color, and the output image type is bilevel (IOCA FS10 or IM1), the transform internally scales the image to the desired size, then uses a halftoning algorithm (ordered dither, the default, or Floyd-Steinberg) to convert it to bilevel. In converting the image to bilevel, the characteristics of the output device such as dot shape and dot gain must be taken into consideration. The internal grayscale mapping table has been optimized for the 600-pel IBM Infoprint 4000 laser printer. The **-gcorr** option can be used to specify a different mapping of gray levels.

For very light or very dark images, the halftoning algorithms can be automatically recalibrated to preserve details that would be lost using the default calibration. See the **-alg** option for more information.

To maintain the image quality, scaling must be done prior to halftoning. Halftoning algorithm is very computation-intensive. Unless the images are small, **tiff2afp** cannot process the color images fast enough to feed even a slow printer.

The size and position of the output image depend on several factors:

- The size specified to the transform
- The form map specified at print time
- The forms and options loaded in the printer

If the image is too large to fit on the page, it is trimmed to size by default. Use the **-fit scale** option to instruct the printer to scale the image to the paper size. If the paper size is not specified explicitly via the **-paper** option, the paper size defaults to US letter size (8.5 by 11 inches). If the image is larger than this, the paper dimensions are increased as necessary. If the paper size is been specified explicitly, it is not increased if the image does not fit on paper. The options **-l** and **-w** have the same effect as **-paper**.

The size of the actual image (as opposed to the paper size) is controlled by the **-scale** option. You can either specify a value of **orig** for the **-scale** option or give an actual size. If you specify **orig**, the output image is the same size as the input

## tiff2afp

image. If you specify **-scale** with an actual size, the output image is scaled to the desired size. You can also specify a percentage for enlargement or reduction.

Even if you specify **-scale orig**, the image may still have to be scaled if the input resolution is different from the output resolution. By default, the transform leaves scaling to the printer. The exceptions are:

- Images that are being halftoned, which are always scaled in the transform
- Images that have different resolutions in X and Y directions

You can use the **-alg** option to instruct the transform to perform internal image scaling. Options **-alg**, **-clean**, and **-ink** choose and configure various scaling algorithms.

If possible, **tiff2afp** rewraps the TIFF raster data in MODCA-P headers. This does not change the compression algorithm used in the data, even though it might be different from the output compression algorithm specified on the command line. The data is rewrapped only if no changes are to be made in the image and if the compression algorithm is supported by the IOCA standard. Besides uncompressed data, the bilevel compression algorithms supported by both TIFF and IOCA are ITU-T Group 3 and Group 4 algorithms.

For 8-bit grayscale and 24-bit color images, both TIFF and IOCA FS11 support JPEG compression algorithms. However, TIFF and JPEG standards have different subsampling defaults than IOCA FS11. Thus, most 24-bit color images are not suitable for rewrapping, even if they use a JPEG compression algorithm and a color model supported by IOCA FS11.

Note also that JPEG is a lossy compression algorithm. Decompressing a JPEG image and then recompressing it for output might result in reduced image quality. For that reason, the default is to use no compression for the gray or color output.

Be aware that not all the printers support all the recognized IOCA compression standards. To make sure that the transform decompresses the data and recompresses it using the specified algorithm, use the option **-force**. If the output image is IM1, the image is always decompressed and scaled in the transform.

The TIFF images are often divided into many segments for efficient memory handling. Some printers terminate the printing in error if the page is too complex. For that reason, **tiff2afp** decompresses, repartitions, and compresses the data if it deems there are too many segments in the picture.

## Parameters

**tiff2afp** behavior is governed by many parameters. The parameters are set by the following hierarchy (least significant first):

- Internal defaults
- Environment variables
- Configuration file
- Command-line arguments

### Command Line Arguments

Note the following points regarding the command line arguments for the **tiff2afp** transform:

- Options and input file names can appear on the command line in any order.
- When you run **tiff2afp** as a standalone transform, the blank between option and value is optional (for example, both **-inkblack** and **-ink black** are valid).

- When you use the **-o** flag of the **enq**, **lp**, **qprt**, or **lprafp** commands to pass options to **tiff2afp**, no blank is permitted between option and value is optional (for example, **-o-inkblack** is valid, but **-o -ink black** is not).
- When you use the **other-transform-options** attribute on the **pdpr** command to pass options to **tiff2afp**, any string containing a blank must be surrounded by single quotes (for example, both **other-transform-options=-inkblack** and **other-transform-options='-ink black'** are valid).
- All values except file names are case-insensitive.
- If an option is specified multiple times, the last specification remains in force.
- If multiple configuration file names are given, they are processed in order.

### Configuration File

The configuration file has entries of the form *option=value*, where each pair must reside on a separate line. Options and other syntax are the same as for the command line arguments and the option names are the same. Input files and configuration files cannot be specified in the configuration file (that is, nested configuration files are not supported). In the case of options without values (for example, **-inv**), the equals sign must be present.

Some command line options, for example, **-calib**, cannot be used in the configuration file or as environment variables. Options available only on the command line are noted as such in their descriptions.

If you do not specify a configuration file on the command line with the **-C** option, the transform checks for the existence of the default configuration file, **/usr/lpp/psf/tiff2afp/tiff2afp.cfg**. If this file exists, the transform uses it as the configuration file.

The following is an example of a valid configuration file:

```
scale = letter
r= 300
o = -
inv=
alg=afp
```

Note that the spaces around the equals sign (=) are optional. In this example, the option-value pair **o = -** means that the default output file is the standard output. Output file name computation has been disabled.

### Environment Variables

Environment variables have the form **TIFF2AFP\_option**, where *option* is the same as on the command line and the configuration file.

Some command line options, for example, **-calib**, cannot be used in the configuration file or as environment variables. Options available only on the command line are noted as such in their descriptions.

For example, to achieve the same effect as the configuration file in the last example, the following statements have to be executed in the calling shell:

```
export TIFF2AFP_scale=letter
export TIFF2AFP_r=300
export TIFF2AFP_o=-
export TIFF2AFP_inv=" "
export TIFF2AFP_alg=afp
```

## tiff2afp

There must be some value set for each desired option. For options that do not take a value, specify a blank surrounded by double quotes, for example:

```
export TIFF2AFP_inv=" "    correct
export TIFF2AFP_inv=      has no effect
```

## Resource Search Path

For resource files, such as scan offset files and grayscale correction files, the transform searches the current directory by default. You can use the **-respath** option to specify a list of directories to be searched for such files. This resource path does not apply to the configuration file.

## Limitations

- Only Huffman coding with baseline DCT JPEG algorithm is supported.
- Old style JPEG specification (Photometric Interpretation 6) is not supported. Photometric Interpretation 6 is obsolete and will be removed from the TIFF specification. Use the Photometric Interpretation 7 to incorporate the JPEG compressed images in TIFF files.
- Additional color information, such as alpha data, is disregarded.
- Transparency maps are ignored.
- At most 8-bit grayscale and 24-bit color are supported.

## Acknowledgments

This software is partially based on the Independent JPEG Group's JPEG compression and decompression code.

## Options and Values

### *@FileList*

Specifies a name of a file that contains a list of files to be processed by the transform. If the **@** option is present, the output file defaults to standard output, even if the list of files contains only a single entry. Multiple **@** options are allowed. Also see the **-f** and **-z** options. The **@** is not preceded by the dash, and is implemented to maintain compatibility with the **ps2afp** transform.

**-a {ioca | ioca10 | ioca11 | im1 | PS.2}**

**-a {IO1\_G4 | IM1 | IO1 | IO1\_MMR | PSEG\_IO1\_G4 | PSEG\_IM1 | PSEG\_IO1 | PSEG\_IO1\_MMR | OVLY\_IO1\_G4 | OVLY\_IM1 | OVLY\_IO1 | OVLY\_IO1\_MMR}**

Choice of the output image type. The first syntax chooses between the IOCA FS 10 (**ioca**, **ioca10**), IOCA FS11 (**ioca11**), IM1, and PostScript Level 2 (**PS.2**) output. IOCA FS10 and IM1 yield bilevel images, while IOCA FS11 results in 4-bit or 8-bit gray or 24-bit color output (see option **-outbits**). Note that presently the only product that supports IOCA FS11 is the AFP Workbench. The output compression algorithm is set via the option **-cmp**. To set the page type (page, overlay, page segment or object), use the **-pagetype** option.

The second syntax is to maintain compatibility with the **ps2afp** transform, and sets the image type (**IO1** for IOCA FS10 or **IM1** for IM1 output), compression (**G4** for Group 4 or **MMR** for Group 3), and page type (**PSEG** for page segment or **OVLY** for overlay). If **PSEG** or **OVLY** is not specified,

the output is a printable page. If no compression algorithm is specified, the output is not compressed. The second syntax cannot be used for IOCA FS11 output.

Some older printers do not support IOCA images. In such cases, the IM1 output type should be chosen. IM1 images are uncompressed and thus use more space. The processing might also take longer since the IM1 image cannot be scaled by the printer and so internal scaling algorithms must be used. See option **-alg**.

The default is **ioca** for IOCA FS10 output compressed via Group 4 algorithm.

This option is similar to the **image-out-format** document attribute on the **pdpr** command.

**-alg {afp | alg1 | alg2 | alg3}**

**-alg {htod1 | htfs}**

**-alg htcal1**

Choice of the scaling and halftoning algorithms. You can specify multiple choices, separated by commas, for one **-alg** option. The effect is the same as specifying multiple **-alg** options. For example, **-alg htfs,htcal1** is equivalent to **-alg htfs -alg htcal1**.

The scaling algorithms are:

- If **afp** is chosen, the scaling is done using the default algorithm in the printer. This makes the transform much faster. If the image must be reduced, however, this algorithm may drop some information from the image, such as thin lines.
- **alg1** activates the internal scaling algorithm to scale the image explicitly to the specified size. This algorithm is guaranteed not to discard any ink. "White space" in the image, however, may be lost (that is, features close to one another might merge). This algorithm makes the transform run longer, and might occasionally make for a "dirty" image, since the occasional "noise pixels" in the scanned images tend to be amplified.
- **alg2** activates the more flexible version of **alg1**. If this algorithm is selected, option **-clean** can be used to specify the amount of ink "cleanup" to be performed. Option **-clean 0.0** makes the algorithm **alg2** perform like **alg1** (albeit more slowly). Increasing the value specified in **-clean** discards more and more ink, until **-clean 1.0** results in a blank page.
- **alg3** activates a scaling algorithm that works by deleting or duplicating rows and columns in the image. This is a fast general-purpose algorithm.

For bilevel images, the default is **afp** if the output image type is IOCA and **alg3** if the output image type is IM1. For color images with bilevel output, the scaling is always done prior to the halftoning algorithm. If a grayscale or color output is chosen (**-a ioca11**), this option is ignored and the algorithm is set to **afp**.

The halftoning algorithms are:

- **htod1** uses an ordered dither with a screen derived from the value of the **-thresh** option. The default is an 85 line per inch screen.
- **htfs** uses the Floyd-Steinberg algorithm.

## tiff2afp

- **htcal1** recalibrates the halftoning algorithm for each image. **htcal1** forces the transform to read the whole image into memory and requires an additional pass through the image. It should be used only for very light or very dark images.

The default is **htod1**. Each halftoning algorithm uses a different internal default calibration curve. If the automatic calibration is turned on, a still different set of calibration curves are used.

See options **-clean**, **-gcorr**, **-ink**, **-paper**, **-scale**, **-thresh**, **-l**, **-w**, **-x**, and **-y**.

### **-calib scanner**

#### **-calib {scanner | printer | patch | patchr},name1...**

Transform calibration for the scanner or printer. If **scanner** is specified, **-sgcorr** must be present. If **printer** is specified, **-sgcorr** may or may not be present. If **patch** or **patchr** is specified, **-sgcorr** (if present) is ignored. Detailed explanation of the calibration process is beyond the scope of this entry.

You cannot specify **-calib** in the configuration file or as an environment variable.

#### **-choice {full | reduced | both}**

TIFF image files may contain both full and reduced resolution versions of each image. The transform can output both versions, or full resolution only, or reduced resolution only, depending on the value for this option. The default is to output the full resolution images only.

See the **-mp** and **-nomp** options.

#### **-C ConfigurationFileName**

The name of a configuration file containing option-value pairs. If multiple **-C** options are given on the command line, they are processed in order. Specifying the configuration file on the command line overrides any specification done via the **TIFF2AFP\_C** environment variable.

The default configuration file is **/usr/lpp/psf/tiff2afp/tiff2afp.cfg**.

#### **-clean {0.5 | x.xxx}**

The internal scaling algorithm **alg2** allows for variable thresholding. The scaled pixel is declared painted if the fraction of its area greater than the threshold is painted in the original image. The value *x.xxx* is a real number between zero and 1 inclusive and gives this threshold.

If the option **-clean 0.0** is issued, **alg2** behaves like **alg1** and turns on a pixel as long as any part of the pixel has been painted in the original image. **-clean 1.0** results in a blank image because the output pixels are never painted.

Note that setting **-clean 0.95** and **0.9999999** turns on the pixels that had essentially all the area painted in the original picture. Depending on the data, most of the image will probably be preserved. Increasing **-clean** by a small amount to **1.0** erases the image. If the scaling algorithm is not **alg2**, this option is ignored. The default is **-clean 0.5**.

#### **-cmp {none | mh | mmr | g3 | g4 | jpeg}**

Choice of the output image compression algorithm:

**none** Uncompressed output



<b>mh</b>	ITU-T T.4 G3 Modified Huffman
<b>mmr</b>	IBM Modified Modified Read
<b>g3</b>	ITU-T T.4 G3 Modified Read
<b>g4</b>	ITU-T T.6 G4
<b>jpeg</b>	JPEG non-differential Huffman coding with baseline DCT. The output image data should be compressed to reduce the file sizes and increase the printing speed.

The default compression is ITU-T T.6 Group 4 for bilevel images and no compression for grayscale or color images. Note that some printers may not support Group 4 compression algorithm and require using the **-cmp** option to choose a different one. The JPEG algorithm can compress only 8-bit grayscale and 24-bit color images. 4-bit grayscale images cannot be compressed.

**-crop** *t,b,l,r*[*i | m | p | d*]

Image cropping. *t,b,l,r* specify how much should be cropped from the image top, bottom, left edge, and right edge. The numbers are floating point and can be either positive or negative. Negative numbers indicate that a blank space should be inserted. The units are inches, millimeters, points, and dots (pels), with the default being dots. The cropping is specified in the context of the output page, so that “top” means the top of the output page and so on, regardless of the **-rot** option. To crop, the transform will enlarge the image by the amount to be cropped, then crop the specified amount by manipulating the actual bitmap. The resulting image has the size as specified by the explicit (or implicit) **-scale** option. See also option **-j**.

If **-fit trim** is specified, the right and the bottom edge of the image are not cropped. Instead, the image grows as necessary. Because **-fit trim** causes the output data stream to contain the “position and trim” specification, the printer discards any extra image.

**-f** *FileList*

Specifies the name of a file that contains a list of files to be processed by the transform. If the **-f** option is present, the output file defaults to standard output, even if the list of files contains only a single entry. Multiple **-f** options are allowed. See also options **@** and **-z**.

**-fit** {*trim | scale*}

Determines whether the printer behavior will be position-and-trim or scale-to-fit if the image is too large to fit on the paper. The default is **trim**.

This option is equivalent to the **image-fit** document attribute on the **pdpr** command.

**-force** If present, this option forces **tiff2afp** to decompress and recompress the image, regardless of other factors.

**-gcorr** *FileName*

Specifies a file with grayscale mapping table for halftoning of the grayscale and color images to bilevel for output. The mapping table must be provided to compensate for the printing characteristics of the particular output device and paper type, such as dot gain. This file must contain either:

- 256 real numbers, one for each level of gray in the 8-bit grayscale image
- The PostScript **settransfer** operator

The algorithm converts every image to 8-bit grayscale before applying the halftoning algorithm. The default internal mapping table has been optimized for the 600-peI IBM Infoprint 4000 laser printer. You shouldn't change this unless you know what you are doing. See also options **-alg** and **-thresh**. PostScript code submitted via the **-thresh** option can have the same effect as **-gcorr**.

**-ink {black | white}**

This option is used only with scaling algorithm **alg1** or **alg2**. The TIFF images can be either black on white or white on black. The internal scaling algorithm must know which, because "ink" is preserved at the expense of "non-ink". The default value, "black", indicates that the image is black on white.

If the option **-inv** is used to print the reversed image, the inversion is done as the data is read by the transform, before any processing is done. The black or white must thus be specified in the terms of the printed image, not in the terms of the input TIFF image.

**-inv** Reverses the image. Areas that are black in the original image become white and vice versa. Note that the reversed image may be either black on white or white on black, depending on the original image.

**-j** *ScanOffsetFileName*

Sometimes input images must be shifted to get the desired positioning on the page. The scan offset file contains the directions for shifting. The file has the format of

```
[attribute]
values
:
values
[attribute]
values
:
values
```

Currently, the recognized attributes are **[Units]** (values **millimeters**, **mm**, **inches**, **in**, **points**, **dots**, **pels**) **[Page\_Offset\_Type]** (values **crop** or **grow**) and **[Page\_Offsets]**. The values for page offsets are in the format *FileName,H<sub>horiz</sub>,V<sub>vert</sub>*. Each entry refers to a file. The file names must be specified (or at least the leading comma must), but are currently ignored and the offset factors are applied to each file in turn. Note that the same factors are applied to each image in the file. The *horiz* and *vert* values are the amount that the image is to be shifted, in the horizontal and vertical direction. The positive directions are down and right (that is, the origin is in the left upper corner of the page). The default units are millimeters. Like the values for the **-crop** option, the shifts are specified in the output space context.

Extra spaces and blank lines are allowed. Unrecognized attributes and their values are ignored. See the sample file **shift.sample**.

If the image is moved left or up, part of the bitmap is removed. If the image is moved down or right, removal is governed by the value of the **[Page\_Offset\_Type]** attribute. If **crop** is chosen, the transform removes the requisite amount from the right and bottom edges of the bitmap. If **grow** is chosen, the transform does not remove any space. The bitmap grows and the trimming, if any, is left to the printer. If the **-fit trim** option (the default) is

specified, **[Page\_Offset\_Type]** defaults to **grow**. For **-fit scale**, **[Page\_Offset\_Type]** defaults to **crop**.

**-l {11i | yyy.yy[d | m | i | p]}**

Specifies the paper length. The optional units are **dots** (pels), **millimeters**, **inches**, or **points**. The default unit is dots. If the unit is dots, decimals (if any) are ignored. The default paper length is 11 inches. See options **-w** to set the paper width or **-paper** to set both dimensions at the same time.

**-M {0 | nnn}**

Limits the amount of memory available to **tiff2afp**. *nnn* is the maximum amount of memory in kilobytes. A value of **0** means there is no memory limit. *nnn* can be set from **0** to the maximum value that AIX allows. The default is **0**.

**[-mp | -nomp]**

Each TIFF image is supposed to have a marker bit set if there are multiple TIFF images in the file. This marker is sometimes missing, even if there are multiple images present in the file. The **-mp** option instructs the transform to behave as if the multipage marker bit were set. The transform then processes all the images in the file, subject to the **-p** and **-choice** options. The default is to leave the marker bit unset (**-nomp**).

**-ms {10 | nnn}**

Requires that at least *nnn* kilobytes of disk space be available on the file system that contains the output file. This limit is enforced every time data is written to the output file. If the output is standard output, this option is ignored. The default is **10**. See option **-msf**.

**-msf {0.1 | x.xxx}**

The number *x.xxx* is a real number between 0 and 1. It denotes the minimum space that must be left unused on the file system containing the output file. The space is given as a fraction of the total space in the file system. This limit is enforced every time data is written to the output file. If the output is standard output, this option is ignored. The default is **0.1**. See option **-ms**.

**-nomp**

See **[-mp | -nomp]**.

**-nosniff**

See **[-sniff | -nosniff]**.

**-noterm**

See **[-term | -noterm]**.

**-nov** See **[-v | -nov]**.

**-o FileName**

Optional output file name. Specify **-** for standard output.

**-outbits NumberOfOutputBits**

Sets the number of bits per pel in output. This value must be **1**, **4**, **8**, or **24**. If the output image type is IOCA FS10 or IM1, the number of output bits is set to **1** and this option is ignored. For IOCA FS11 output, the default is **24**. Note that this number represents the maximum number of bits used per pel. Thus, even if the number of bits is set to **24**, a 4-bit grayscale image is still displayed in 4-bit format.

**-outcolor {rgb | ycbcr | ycrcb}**

Sets the output color model to RGB, YCbCr, or YCrCb if the image type is IOCA FS11 and the number of output bits is 24. Otherwise, this option is ignored. The default is **ycbcr**.

**-p {even | odd | nn | nn-mm | nn-}**

Specifies that the output should only contain the specified pages. If no **-p** option is given, all the pages are output (but see the **-choice** option for printing full or reduced resolution images of each page). Multiple **-p** options may be specified. Their effect is cumulative. Regardless of the order in which the pages are specified, they are always printed in ascending order. The recognized values are:

**even** Print all even pages

**odd** Print all odd pages

*nn* Print page *nn*

*nn-mm*

Print pages *nn* to *mm*, inclusive.

*nn-* Print all pages starting with page *nn*

Pages are numbered starting with 1.

**-pagetype {page | overlay | ovly | pseg | object}**

Sets the output page type to be page, overlay, page segment or object. The same page type is set for every page in the output. Thus, unless option **-p** is used to select a single page, multiple overlays, page segments or overlays are stored in the output file. The default is **page**. See option **-a**.

**-paper {a5 | a4 | a3 | letter | folio | legal | ledger | xxx.xx,yyy.yy[d | m | i | p]}**

Specifies the output paper size. The supported values are:

**a3** A3 format (297 by 420 mm or 11.69 by 16.54 inches)

**a4** A4 format (210 by 297 mm or 8.27 by 11.69 inches)

**a5** A5 format (148 by 210 mm or 5.83 by 8.27 inches)

**letter** 8.5 by 11 inches (216 by 279 mm)

**folio** 8.5 by 13.0 inches (216 by 330 mm)

**legal** 8.5 by 14.0 inches (216 by 356 mm)

**ledger** 11.0 by 17.0 inches (279 by 432 mm)

*xx.xx,yy.yy*[**d | m | i | p**]

Horizontal and vertical page dimensions. The optional units are **dots** (pels), **millimeters**, **inches**, or **points**.

The default paper size is letter. If **-paper** is not used, the paper size is increased, if necessary, to contain the output image.

See options **-l**, **-w**, and **-scale**.

**-r {300 | nnn}**

The output device resolution, specified in dots per inch. The default is **300**.

This option is equivalent to the **default-printer-resolution** document attribute on the **pdpr** command.

**-respath *directory*[:*directory*...]**

Sets the search path for resource files, such as the scan offset files and grayscale calibration curve files. If a resource file name is specified as a relative name (does not start with a */*), the transform searches every

directory in the path, in the order specified in the path, until it finds the file (or fails). See options **-j** and **-gcorr** for scan offsets and grayscale calibration curve. The default is the current directory.

**-rot {0 | 90 | 180 | 270[p | i]}**

The image is rotated in the clockwise direction by the amount specified. The default is zero, that is, no rotation.

If **p** is specified, the transform sets the output datastream in such a way that the printer performs the actual image rotation. If **i** is specified, the transform rotates the output bitmap. When **i** is chosen, the transform takes much longer to run and uses much more memory. If no letter is specified, the default or any previous value (such as the value specified in the configuration file) remains in force. The default is **p**.

**-scale {orig | a5 | a4 | a3 | letter | folio | legal | ledger | xxx.xx,yy.yy[d | m | i | p] | xxx%}**

Specifies the output image size. The image is scaled to this size and centered in the area defined by the paper size and margin options. The supported values are:

**orig** Preserve the input image size, regardless of the printable paper area.

**a3** A3 format (297 by 420 mm or 11.69 by 16.54 inches)

**a4** A4 format (210 by 297 mm or 8.27 by 11.69 inches)

**a5** A5 format (148 by 210 mm or 5.83 by 8.27 inches)

**letter** 8.5 by 11 inches (216 by 279 mm)

**folio** 8.5 by 13.0 inches (216 by 330 mm)

**legal** 8.5 by 14.0 inches (216 by 356 mm)

**ledger** 11.0 by 17.0 inches (279 by 432 mm)

**xx.xx,yy.yy[d | m | i | p]**

Horizontal and vertical image dimensions. The optional units are **dots** (pels), **millimeters**, **inches**, or **points**.

**xxx%** Magnification relative to the original image size. Numbers below 100% mean reduction, while Numbers above 100% mean enlargement. For example, **-scale 200%** causes the output image to be twice as long and twice as wide as the input image.

The default image size is **orig**.

**-sgcorr** *FileName*

Specifies the name of the scanner-related calibration file. To use this option in the calibration process (with the option **-calib**) you must specify a single file name. If **-calib** is absent, this option is ignored.

A detailed discussion of **-sgcorr** is beyond the scope of this document.

**[-sniff | -nosniff]**

Turns automatic conversion to black on white for bilevel images on (**-sniff**) or off (**-nosniff**). The automatic conversion algorithm counts the number of 0 and 1 bits in the image. If there are fewer zeros, it assumes the printed features are represented by zeros (white on black), and inverts the image to be black on white. The detection and conversion are done after the conversion specified by the Photometric Interpretation tag is applied (if any).

## tiff2afp

This option is ignored if the image is not bilevel. The default is **-nosniff**.

### **[-term | -noterm]**

Disables (**-term**) or enables (**-noterm**) error recovery.

- When error recovery is disabled, on encountering an error in a TIFF file, the transform terminates with an error message and a nonzero return code.
- When error recovery is enabled, the errors in TIFF files are treated as non-fatal. The transform attempts to recover with the next image in the file, or with the next file. The return code is zero.

The default is **-noterm**.

### **-thresh** *FileName*

Specifies a file that contains a PostScript Type 1 or Type 3 halftone dictionary. Alternatively, the PostScript code can specify the **setscreen** operator instead of a Type 1 dictionary. The halftone cell in the dictionary is used to overwrite the default ordered dither clustered dot halftone cell. If the PostScript code contains a transfer function, either in the halftone dictionary or specified by the **settransfer** operator, the current grayscale correction curve is overwritten as if **-gcorr** were used.

### **[-v | -nov]**

Turns verbose mode on (**-v**) or off (**-nov**).

- When verbose mode is on, the transform prints a message as it opens each resource file, then echoes the command line, then prints a message for each file name as it is processed.
- When verbose mode is off, the transform prints only error messages.

The default is **-nov**.

### **-w** {**8.5i** | *yyy.yy*[**d** | **m** | **i** | **p**]}

Specifies the paper width. The optional units are **dots** (pels), **millimeters**, **inches**, or **points**. The default unit is dots. The default page width is 8.5 inches. See options **-l** to set the paper length or **-paper** to set both dimensions at the same time.

### **-wrkdir** *WorkDirectoryName*

The TIFF data stream is by definition non-sequential. Thus, input from **stdin** must be cached on disk before it can be processed. This option specifies which directory to use for the caching of the standard input. If this option is absent or the directory cannot be opened, the transform first tries to use **/var/psf/tiff2afp** as the working directory and, if **/var/psf/tiff2afp** is absent, uses **/tmp**.

The **stdin** cache file is never visible to the user because it is immediately unlinked after creation. Thus, the cache file is always deleted when **tiff2afp** finishes execution, even if **tiff2afp** is killed or otherwise terminates in error.

### **-x** {**0** | *nnn.nn*[**d** | **m** | **i** | **p**]}

Specifies the left margin. The optional units are **dots** (pels), **millimeters**, **inches**, or **points**. The default unit is dots. The default is zero (no margin).

### **-y** {**0** | *nnn.nn*[**d** | **m** | **i** | **p**]}

Specifies the top margin. The optional units are **dots** (pels), **millimeters**, **inches**, or **points**. The default unit is dots. The default is zero (no margin).

**-z** Signifies that a list of files to be processed is submitted from standard input. See also options **-f** and **@**.

---

## Chapter 7. Infoprint Object Attributes

This chapter lists the attributes for these Infoprint print objects:

- “Attributes for Actual Destinations” on page 328
- “Attributes for Auxiliary-Sheet Objects” on page 443
- “Attributes for Documents and Default Documents” on page 449
- “Attributes for Jobs and Default Jobs” on page 523
- “Attributes for Logs” on page 573
- “Attributes for Logical Destinations” on page 578
- “Attributes for Media” on page 604
- “Attributes for Queues” on page 610
- “Attributes for Resource Contexts” on page 620
- “Attributes for Servers” on page 623
- “Attributes for Transforms (Windows NT or Window 2000 only)” on page 645

### Attribute Disclaimer

There are attributes and attribute values identified in the *ISO 10175-1 Information Technology - Text and Office Systems - Document Printing Application (DPA) Part 1: Abstract-Service Definition and Procedures* standard that Infoprint does not support. If you use any of these non-supported attributes or values, Infoprint may accept them. However, the results may be different than you expect. Sometimes, Infoprint may issue a message indicating that it does not support the attribute or value.

---

## About Destination Support Systems

The programs that the actual destination uses to send jobs to the output device are called the destination support system (DSS).

### Infoprint Manager for AIX supports the following DSSs:

#### AIX DSS

The AIX DSS permits Infoprint Manager to bridge to the AIX print-spooling subsystem. In standard AIX printing, users submit jobs to an AIX print queue. The AIX print-spooling subsystem schedules the jobs and passes them to a printer device by means of a backend program, usually **piobe**, or if the queue is a remote queue, **rembak**.

In the AIX DSS, users submit jobs to a destination from which an Infoprint queue receives them. The Infoprint physical printer submits jobs to the printer device using an AIX backend program.

You must attach this type of printer device as specified by its documentation before creating its associated Infoprint actual destination.

#### BSD DSS

The BSD DSS permits Infoprint Manager to bridge to existing UNIX/BSD printing subsystems. Infoprint Manager sends jobs submitted to BSD physical printers as separate print requests to a local or remote print queue.

For local printer devices, Infoprint Manager can use the **piobe** backend program. More typically, Infoprint Manager uses the **rembak** program to send jobs to a printer device connected to another processor. This processor can run AIX or any other operating system that supports the **lpd** protocol and that connects to the network using TCP/IP.

For remote printer devices, you must set up a remote queue and configure the remote system. Refer to the printer configuration documentation of the remote system.

#### PSF DSS

The PSF DSS permits Infoprint Manager to bridge to the IBM print Services Facility (PSF) printing subsystem. This DSS allows communication with output devices that have Intelligent Printer Data Stream (IPDS) functionality. The PSF DSS is the most flexible DSS. It provides a single point of control and tracking for print jobs. Infoprint Manager transforms jobs submitted to PSF destinations to IPDS or PCL before sending them to the output device.

The way in which Infoprint Manager communicates with the output device depends on the type of actual destination. For PSF DSS actual destinations, it also depends on the attachment type.

#### 3170 DSS

Infoprint Manager uses the 3170 DSS to communicate with IBM InfoColor 70 printer devices. Before creating the actual destination, you must determine the Internet Protocol (IP) address of the printer device.

#### Infoprint 2000 DSS

Infoprint Manager uses the Infoprint 2000 DSS to communicate with IBM Infoprint 2000 printer devices. Before creating the actual destination, you must determine the Internet Protocol (IP) address of the printer device.

#### Email DSS

Infoprint Manager uses the email DSS to communicate with electronic mailing systems.



**Fax DSS**

Infoprint Manager uses the fax DSS to communicate with fax devices.

## Infoprint Manager for Windows NT and Windows 2000 supports the following DSSs:

**BSD DSS**

The BSD DSS permits Infoprint Manager to bridge to remote printers or printing subsystems. Infoprint Manager sends jobs submitted to BSD physical printers as separate print requests to a remote print queue.

Infoprint Manager typically uses the **lpr** command to send jobs to a printer device or to another system. This can be any device or system that supports the **lpd** protocol and that connects to the network using TCP/IP. Refer to the printer configuration documentation of the remote device or system for details on how to set up a remote queue.

**PSF DSS**

The PSF DSS permits Infoprint Manager to bridge to the IBM Print Services Facility printing subsystem. This DSS allows communication with output devices that have Intelligent Printer Data Stream (IPDS) functionality or that have PCL functionality. The PSF DSS is the most flexible DSS. It provides a single point of control and tracking for print jobs. Infoprint Manager transforms jobs submitted to PSF destinations to the IPDS or PCL data stream before sending them to the output device.

The way in which Infoprint Manager communicates with the output device depends on the type of actual destination. For PSF DSS actual destinations, it also depends on the attachment type. (See "Understanding Attachment Types for PSF Actual Destinations".)

**Passthrough DSS**

The Passthrough DSS permits Infoprint Manager to bridge to the Windows print-spooling subsystem. This DSS supports mono-IPDS (PostScript or PCL) printers by using standard Windows NT/Windows 2000 ports and port monitors.

You must attach this type of printer device as specified by its documentation before creating its associated Infoprint Manager destination.

**IPP DSS**

Infoprint Manager uses the IPP DSS to communicate with destinations through the Internet Print Protocol (IPP). This DSS allows Infoprint Manager to access a printer using a Uniform Resource Locator (URL) string.

## Understanding Attachment Types for PSF Actual Destinations

The attachment type for an actual destination defines how the printer device attaches to the server and communications with Infoprint Manager. Based on the printer device, the attachment type is one of the following:

- **TCP/IP.** The printer device communicates using the Intelligent Printer Data Stream (IPDS) and attaches to the server through the TCP/IP network. To create the actual destination, you must specify the Internet Protocol (IP) address of the printer device and the port number through which Infoprint Manager communicates with the device. The port number for TCP/IP-attached printers is an integer from 5001 to 65535. For printers attached using the i-data 7913 IPDS Printer LAN Attachment, you must use **5001** as the port number.
- **Channel.** The IPDS printer device attaches to the server through a S/370 Channel Emulator/A adapter for Infoprint Manager for AIX and an IBM 4159

## Attributes

Model 001 S/390 Parallel Channel Emulator Card (using S/390 bus/tag cabling) for Infoprint Manager for Windows NT and Windows 2000. Before creating the actual destination, you must identify the slot number in the server that contains the card and the hexadecimal control unit address of the printer device.

- **Other-driver.** The PCL, PostScript, or PPDS printer device communicates using TCP/IP or attaches directly to the server through a parallel/serial port (or through a hardware alternative to such direct attachment). When you want to create the actual destination with Infoprint Manager for Windows NT and Windows 2000, you must specify the port associated with a port monitor needed to operate the printer.
- **Command.** You must attach this type of printer as specified by its documentation and configure it in AIX before creating its associated actual destination for Infoprint Manager for AIX **or** configure it to function as a Windows printer (using the standard Windows **Add Printer Wizard**) before creating its associated actual destination for Infoprint Manager for Windows NT and Windows 2000.
- **Upload-SNA.** With Infoprint Manager for AIX, the printer device is attached to a host system. Infoprint Manager communicates with PSF for OS/390 or PSF for MVS through the SNA network. Before creating the actual destination, you must determine the code pages used on both the AIX and host systems.
- **Upload-TCP/IP.** With Infoprint Manager for AIX, the printer device is attached to a host system. Infoprint Manager communicates with PSF for OS/390 or PSF for MVS through the TCP/IP network. Before creating the actual destination, you must determine the Internet Protocol (IP) address of the printer device and the port number through which Infoprint Manager communicates with the device. The port number for TCP/IP-attached printers is an integer from 5001 to 65535. You must also determine the code pages used on both the AIX and host systems.

## Attributes Displayed in the Infoprint Manager Administration GUI

Attributes that include **GUI Label** are shown in the corresponding properties notebooks in the Infoprint Manager Administration GUI. The following objects have properties notebooks:

- Actual Destination
- Documents and Default Documents
- Jobs and Default Jobs
- Logical Destinations
- Servers
- Transforms

---

## Attributes for Actual Destinations

- Infoprint uses actual destinations for job validation and scheduling. See “Appendix C. Job Validation and Scheduling” on page 695 for an explanation of job validation and scheduling and for tables showing the attributes used for these tasks.
- Infoprint uses the actual destination **xxx-supported** attributes for job validation. Infoprint uses both the **xxx-ready** and the **xxx-supported** attributes for job scheduling.
- Infoprint issues an error if you update an **xxx-ready** attribute with a value not currently assigned to the corresponding **xxx-supported** attribute.
- Actual destinations have different attribute sets based on the DSS that supports the destination.

- Infoprint supplies some files containing attributes that have the values for some of the actual destination attributes already set, based on the output device model or destination attachment type. You will find these files containing attributes in the **/usr/lpp/pd/attr** directory for Infoprint Manager for AIX and in the ***install\_path*\attr** directory for Infoprint Manager for Windows NT and Windows 2000.

## Attributes Not Displayed in the Infoprint Administrator's GUI

While all actual destination attributes and attribute values are supported for both basic and advanced Infoprint installations, neither Infoprint administrator's GUI displays a complete set.

- The basic Infoprint administrator's GUI displays only the attributes of greatest interest to Print on Demand (Commercial Printing) Infoprint administrators.
- The advanced Infoprint administrator's GUI displays most attributes and attribute values of greatest interest to Data Center (Production Printing) Infoprint administrators, but omits a few that are used primarily in basic Infoprint installations.

You can list the values of attributes not displayed in the Infoprint administrator's GUI using the **pdls** command. You can set the values of initially settable and resettable attributes using the **pdcreate** command. You can change the values of resettable attributes using the **pdset** command.

## Initially Settable Attribute Listing

You can set these attributes with the **pdcreate** command when you create an actual destination.

- attachment-type**
- destination-data-stream**
- destination-realization**
- destination-support-system**
- device-name**
- print-queue-name**

## Resettable Attribute Listing

You can set these attributes with the **pdcreate** command when you create an actual destination or modify them with the **pdset** command after you create the actual destination.

- accept-jobs**
- accounting-exit**
- ack-interval**
- add-carriage-returns**
- add-line-feeds**
- ascii-character-mapping**
- ascii-font-map**
- associated-queue**
- attribute-map**
- audit-exit**
- automatic-postscript-mode-switch**
- auxiliary-sheet-selections-supported**
- booklet-fold**
- carriage-control-types-supported**
- character-mappings-supported**
- checkpoint-at-stacker**
- color-mapping-table**

## Actual Destination

color-rip-servers  
connection-timeout  
content-orientations-supported  
convert-to-ebcdic-supported  
data-fidelity-problem-reported-supported  
default-font-fidelity-action  
default-font-resolution  
default-input-tray  
descriptor  
destination-command  
destination-locations  
destination-model  
destination-pass-through  
destination-register-threshold  
destination-release-timer  
destination-tcpip-internet-address  
destination-tcpip-port-number  
document-finishings-supported  
document-formats-ripped-at-destination  
document-formats-supported  
document-types-supported  
dss-job-message-disposition  
dss-job-message-log-size  
dss-job-message-log-wrap  
ebcdic-character-mapping  
end-message-supported  
end-sheets-supported  
font-resolutions-supported  
force-destination-setup  
form-definition  
halftones-supported  
image-fit-supported  
image-length  
image-out-formats-supported  
image-width  
input-data-user-exit  
input-trays-medium  
input-trays-supported (BSD only; otherwise non-settable)  
intervention-timer  
job-batches-ready  
job-finishings-supported  
job-retry-count-limit  
job-retry-interval  
job-rip-actions-supported  
job-size-range-ready  
job-size-range-supported  
job-start-wait-supported  
list-of-managers  
log-accounting-data  
logical-destinations-assigned  
maximum-concurrent-jobs  
maximum-copies-supported  
maximum-fonts-to-keep  
maximum-overlays-to-keep  
maximum-segments-to-keep  
media-ready (BSD only; otherwise non-settable)

media-supported  
message  
message-font-type  
message-form-definition  
non-process-runout-timer  
notification-profile  
notify-operator  
number-up-supported  
offset-stacking-available  
optimize-for-multiple-copies  
output-appearances-supported  
output-bin  
output-bin-numbers  
output-data-user-exit  
output-format-supported  
overlay  
page-select-supported  
pcl-server-address  
pcl-server-port  
plex  
plexes-supported  
postscript-server-address  
postscript-server-port  
presentation-fidelity-problem-reported  
print-edge-marks  
print-qualities-supported  
printer-end-sheet  
printer-escape-codes  
printer-memory  
printer-resolutions-ready  
printer-resolutions-supported  
printer-separator-sheet  
printer-start-sheet  
printer-s370-channel-device-address  
printer-s370-channel-slot-number  
printer-timeout-period  
protected-attributes  
psf-tray-characteristics  
remote-queue  
resource-context  
resource-context-font  
resource-context-form-definition  
resource-context-overlay  
resource-context-page-definition  
resource-context-page-segment  
reverse-output  
rip-ini-file  
rip-server  
scanner-corrections-supported  
screen-frequencies-supported  
scheduler-sort-primary-order  
scheduler-sort-secondary-order  
separator-sheets-supported  
sides  
sides-supported  
snmp-community-name

## Actual Destination

**snmp-retry-count**  
**snmp-timeout**  
**start-message-supported**  
**start-sheets-supported**  
**table-reference-characters-supported**  
**transform-sequence**  
**use-snmp**  
**wait-for-job-completion**  
**windows-nt-driver-names**  
**x-image-shift-range-supported**  
**y-image-shift-range-supported**

## accept-jobs

Indicates whether Infoprint can assign newly submitted or resubmitted jobs to this actual destination.

### GUI Label

Accept jobs

### DSS

All

### Type

Resettable, single-valued

### Allowed Values

You can enter one of these fixed values:

<i>Fixed Value</i>	<i>Input Synonym</i>
<b>true</b>	<b>yes</b>
<b>false</b>	<b>no</b>

### Default Value

**true**

### Usage Guidelines

- A value of **false** does not prevent you from using the basic Infoprint administrator's GUI to reassign jobs that have been assigned to another actual destination to this actual destination.
- When this value is **false** and the queue attribute **assign-to-destination** is true, Infoprint rejects jobs sent to this actual destination.
- Infoprint can assign jobs to this actual destination even if it is disabled. Of course, the jobs will not be printed or transmitted until the destination is enabled.
- The **accept-unsupported-jobs** server attribute overrides the **accept-jobs** attributes.

## accounting-exit

Specifies the name of an auxiliary-sheet object that sets accounting exit parameters.

### GUI Label

Accounting exit

### DSS

PSF, Infoprint 2000

**Type**

Resettable, single-valued

**Allowed Values**

You can enter the name of an auxiliary sheet or any of these fixed values:

**accounting-log**

Accounting information is written to the:

- **/var/psf/accounting.log** file for AIX
- **\install\_path\var\psf\accounting.log** file Windows NT and Windows 2000, where *install\_path* indicates the path where you installed Infoprint Manager.

**blank** This value is technically valid, but should not be used.

**brief** A sheet with brief accounting information is printed after the job.

**full** A sheet with full accounting information is printed after the job.

**job-ticket**

Accounting information is written to:

- **/var/psf/podaccounting.log** file for AIX
- **\install\_path\var\psf\podaccounting.log** file Windows NT and Windows 2000, where *install\_path* is the path where you installed Infoprint Manager for Windows NT and Windows 2000.

**none** No accounting information is produced.

**Default Value**

- For Infoprint Manager for AIX:

**Basic Infoprint administrator's GUI**  
**job-ticket**

**Advanced Infoprint administrator's GUI and command line**  
**accounting-log**

- For Infoprint Manager for Windows NT and Windows 2000: **accounting-log**

**Usage Guidelines**

For fax and email destinations, you can use **accounting-log**; however, while the name of entries is valid, the content of the entries may be inaccurate.

**ack-interval**

Determines how often Infoprint sends acknowledgement requests to the destination.

**GUI Label**

Acknowledgement interval (pages)

**DSS**

PSF, Fax, Email

**Type**

Resettable, single-valued

**Allowed Values**

You can enter a value of 1 through 9999. This value represents pages.

**Default Value**

**100**

**Usage Guidelines**

The unit for this attribute is pages. If you change this attribute value, the change can affect performance. You can control how often Infoprint updates the job attribute **pages-completed** by decreasing or increasing this value:

## Actual Destination

- Decreasing the value (number of pages) increases the number of acknowledgement requests during normal printing activities. This decreases the destination throughput and reduces the complexity of the exception recovery activities that Infoprint performs.
- Increasing the value (number of pages) decreases the number of acknowledgement requests. This provides less accurate information about the destination and exception conditions.

**Note:** This attribute is only used for IPDS printers.

## add-carriage-returns

Indicates whether Infoprint should add carriage return characters when transforming ASCII documents for printing on this actual destination.

### GUI Label

Add ASCII carriage returns

### DSS

PSF

### Type

Resettable, single-valued

### Allowed Values

You can enter one of these fixed values:

<i>Fixed Value</i>	<i>Input Synonym</i>
<b>true</b>	<b>yes</b>
<b>false</b>	<b>no</b>

### Default Value

No default value

## add-line-feeds

Indicates whether Infoprint should add line feed characters when transforming ASCII documents for printing on this actual destination.

### GUI Label

Add ASCII line feeds

### DSS

PSF

### Type

Resettable, single-valued

### Allowed Values

You can enter one of these fixed values:

<i>Fixed Value</i>	<i>Input Synonym</i>
<b>true</b>	<b>yes</b>
<b>false</b>	<b>no</b>

### Default Value

No default value



## ascii-character-map

Indicates the ASCII code page that AIX uses to map the attributes of this PSF upload-TCP/IP-attached or PSF upload-SNA-attached actual destination.

### GUI Label

ASCII code page to use

### DSS

PSF (AIX Only)

### Type

Resettable, single-valued

### Allowed Values

You can enter the name of an ASCII code page, such as ISO8859-1.

### Default Value

No default value

### Usage Guidelines

Infoprint requires this attribute for PSF upload-SNA-attached and upload-TCP/IP-attached actual destinations and ignores it for other attachment types.

## ascii-font-map

Defines how the destination maps the ASCII font escape sequences to AFP character sets that Infoprint uses for ASCII fonts. Infoprint uses this attribute to map each font-change escape to an AFP font character set.

### GUI Label

ASCII fonts mappings

### DSS

PSF

### Type

Resettable, multi-valued, complex

### Syntax

*font-escape:font-name*

Separate each pair of values with a colon, for example:

10cpi:C02055D0

### Components

**font-escape:** Specifies the name of an ASCII font-escape sequence.

*Type:* Single-valued

*Allowed Values:* You can enter a text string containing the sequence name.

**font-name:** Specifies the name of an AFP font character set.

*Type:* Single-valued

*Allowed Values:* You can enter a text string containing the font character set name.

## Actual Destination

### Default Values

<i>font-escape Value</i>	<i>font-name Value</i>
10cpi	C02055D0
10cpi-emphasized	C02075D0
10cpi-subscript	C02055P0
10cpi-subscript-emphasized	C02075P0
10cpi-2wide	C02059A0
10cpi-2wide-emphasized	C02079A0
10cpi-2wide-2high	C02059L0
10cpi-2wide-2high-emphasized	C02079L0
10cpi-2wide-subscript	C02055J0
10cpi-2wide-subscript-emphasized	C02075J0
10cpi-2high	C02051K0
10cpi-2high-emphasized	C02071K0
10cpi-condensed	C02055F0
10cpi-condensed-subscript	C02051R0
10cpi-condensed-2wide	C02059C0
10cpi-condensed-2wide-subscript	C02056N0
12cpi	C02055E0
12cpi-emphasized	C02075E0
12cpi-subscript	C02054Q0
12cpi-subscript-emphasized	C02074Q0
12cpi-2wide	C02059B0
12cpi-2wide-emphasized	C02079B0
12cpi-2wide-subscript	C02058M0
12cpi-2wide-subscript-emphasized	C02078M0
proportional	C02055G0
proportional-emphasized	C02075G0
proportional-subscript	C02055S0
proportional-subscript-emphasized	C02075S0
proportional-2wide	C02059G0
proportional-2wide-emphasized	C02079G0
proportional-2wide-subscript	C02051H0
proportional-2wide-subscript-emphasized	C02071H0
proportional-2high	C02055H0
proportional-2high-emphasized	C02075H0

## associated-queue

Identifies the queue from which this actual destination receives jobs.

### GUI Label

Queue fed by

### DSS

All

### Type

Resettable, single-valued

### Allowed Values

You can enter a text string up to 255 characters long that contains the ID of the queue. The ID cannot contain the cell name.

### Default Value

No default value

**Usage Guidelines**

The value for this attribute is the name of a queue. The associated queue must exist and be in communication with the destination before you can enable the actual destination.

**associated-server**

Identifies the name of the server in which this actual destination resides.

**GUI Label**

Server

**DSS**

All

**Type**

Non-settable, single-valued

**Allowed Values**

Infoprint sets this value to the value of the *ServerName* portion of the argument from the **pdcreate** command used to create this actual destination.

**Default Value**

No default value

**attachment-type**

Identifies how the output device that this actual destination represents attaches to the PSF DSS and how Infoprint communicates with the output device.

**DSS**

PSF

**Type**

Initially settable, single-valued

**Allowed Values**

You can enter one of these fixed values:

**Fixed Value**    **Explanation**

**command**    Infoprint communicates with this printer device by forwarding print requests to the remote print system or printer with a command. You may need to create a queue on the remote print system.

**channel**    Infoprint communicates with this S/370 channel-attached printer device through the channel.

**other-driver**    Infoprint communicates directly with the printer device through an AIX printer backend program or a Windows NT or Windows 2000 printer port.

**tcpip**    Infoprint communicates with this TCP/IP LAN-attached printer device directly through the TCP/IP network.

**upload-sna**    This printer device is attached to an MVS system. Infoprint communicates with PSF/MVS through the SNA LU 6.2 network.

**Note:** This value is only supported by the PSF DSS for AIX.

**upload-tcpip**    This printer device is attached to an MVS system. Infoprint communicates with PSF/MVS through the TCP/IP network.

## Actual Destination

**Note:** This value is only supported by the PSF DSS for AIX.

### Default Value

No default value

### Usage Guidelines

- You need to specify a value for this attribute when you create a PSF actual destination.
- Some actual destination attributes apply only to certain attachment types.

## attribute-map

Provides a list of Infoprint attributes and their associated generated command flags.

### GUI Label

Map attributes to flags

### DSS

BSD

### Type

Resettable, multi-valued, complex

### Syntax

*attribute:flag*

Separate each pair of values with a colon, for example:

*destination-pass-through:-o*

### Components

**attribute:** The name of an Infoprint document, job, or destination attribute that corresponds to a flag of the generated print command.

*GUI Label:* Infoprint attribute

*Type:* Single-valued

*Allowed Values:* You can enter a text string containing an attribute name.

**flag:** The name of a flag of the generated print command.

*GUI Label:* Output command option

*Type:* Single-valued

*Allowed Values:* You can enter a text string containing a flag.

### Default Values

**destination-pass-through:-o**

### Usage Guidelines

- With AIX by default, BSD assumes the generated command is a **rembak** command.
- With Windows NT or Window 2000 by default, BSD assumes the generated command is an **lpr** command.

- Some printer devices, for example, the IBM 4317 Network Printer 17, IBM Infoprint 20 Printer, and IBM Infoprint 32 Printer, do not support the BSD **-Z** flag. If you receive the following error message when you try to print on one of these printers:

```
0782-597 The value of _Z attribute is not in the ring list
        specified in the limits field
```

delete the **job-name:-o-Z** value from the **attribute-map** attribute.

## audit-exit

Specifies the name of the auxiliary-sheet object that sets audit exit parameters.

### GUI Label

Audit exit

### DSS

PSF, Email, Fax, Infoprint 2000

### Type

Resettable, single-valued

### Allowed Values

You can enter the name of an auxiliary sheet or any of these fixed values:

#### accounting-log

Audit information is written to the:

- **/var/psf/audit.log** file for AIX
- ***install\_path*\var\psf\audit.log** file for Windows NT and Windows 2000, where *install\_path* indicates the path where you installed Infoprint Manager.

**blank** This value is technically valid, but should not be used.

**brief** A sheet with brief audit information is printed after the job.

**full** A sheet with full audit information is printed after the job.

#### job-ticket

A sheet with full audit information from the job ticket is printed after the job.

**none** No audit information is produced.

### Default Value

No default value

### Usage Guidelines

If you do not set a value, Infoprint produces no audit information at the end of a job submitted to this actual destination.

## automatic-postscript-mode-switch

Indicates whether this actual destination supports switching into PostScript mode using controls placed in the data stream.

### GUI Label

Switch to PostScript automatically

### DSS

AIX

### Type

Resettable, single-valued

## Actual Destination

### Allowed Values

You can enter one of these fixed values:

<i>Fixed Value</i>	<i>Input Synonym</i>
true	yes
false	no

### Default Value

false

### Usage Guidelines

- If this actual destination has this feature, it can print PostScript documents among non-PostScript documents.
- The value for this attribute does not change if you delete the **document-formats-supported** value of **postscript**.

## auxiliary-sheet-selections-supported

Identifies the combination of start, separator, and end sheets selection that this actual destination supports for jobs.

### GUI Label

Auxiliary sheets allowed

### DSS

AIX, PSF, Infoprint 2000, IPP, Passthrough

### Type

Resettable, multi-valued

### Allowed Values

For AIX, PSF, and Infoprint 2000, you can enter any of these fixed values:

**end**  
**none**  
**sep**  
**sep-end**  
**start**  
**start-end**  
**start-sep**  
**start-sep-end**

For IPP and Passthrough, you can enter any of these fixed values:

**none**  
**start**

### Default Values

AIX, PSF, and Infoprint 2000 defaults: **end**, **none**, **sep**, **sep-end**, **start**, **start-end**, **start-sep**, **start-sep-end**.

Internet Printing Protocol (IPP) and Passthrough defaults: **none**, **start**.

### Usage Guidelines

- Infoprint compares the job attribute **auxiliary-sheet-selection** to this attribute for validation and scheduling.
- You can use this attribute to restrict how much control users have over **auxiliary-sheet-selection** on this actual destination.

- If you remove all values that specify a particular auxiliary sheet (such as **start**), the job submitter cannot “turn off” the corresponding actual destination attribute (such as **printer-start-sheet**).

### booklet-fold

Specifies how booklets are ordered and folded on this output device.

#### GUI Label

Fold booklet

#### DSS

PSF, Infoprint 2000

#### Type

Resettable, single-valued

#### Allowed Values

You can enter one of these fixed values:

**up**  
**down**

#### Default Value

**up**

#### Usage Guidelines

- The Infoprint 60 Finisher folds booklets **up**; that is, the cover (if any) is inserted at the beginning of the booklet, and after the booklet prints, the cover is saddle-stitched from the bottom and folded upward.
- The Infoprint 2000 and inline booklet makers attached to the Infoprint 4000 fold booklets **down**; that is, the cover (if any) is inserted at the end of the booklet, and after the booklet prints, it is saddle-stitched from the top and folded downward.

**Note:** The Infoprint 2000 DSS sets the booklet-fold to **down**, so that Infoprint 2000 customers don't have to specify the **booklet-fold** attribute. However, customers using the Infoprint 4000 need to specify the **booklet-fold** attribute at **down**.

### cancel-individual-document-supported

Indicates whether this actual destination is capable of cancelling a single document within a multi-document job.

#### DSS

All

#### Type

Non-settable, single-valued

#### Allowed Values

Infoprint sets this value to **false**.

#### Default Value

**false**

### carriage-control-types-supported

Identifies the types of carriage controls that this actual destination supports.

## Actual Destination

### GUI Label

Carriage control types allowed

### DSS

PSF, Email, Fax, Infoprint 2000

### Type

Resettable, multi-valued

### Allowed Values

You can enter any of these fixed values:

**ansi-ascii**  
**ansi-ebcdic**  
**machine**  
**none**

### Default Values

**ansi-ascii, ansi-ebcdic, machine, none**

### Usage Guidelines

- Infoprint compares the document attribute **carriage-control-type** to this attribute for validation and scheduling.
- You can use this attribute to restrict use of this actual destination.

## character-mappings-supported

Identifies the character mappings (code pages) that this actual destination supports.

### GUI Label

Character mappings allowed

### DSS

AIX, PSF, Email, Fax, Infoprint 2000

### Type

Resettable, multi-valued

### Allowed Values

You can enter any of these fixed values:

**ibm-437**  
**ibm-850**  
**ibm-860**  
**ibm-863**  
**ibm-865**  
**ibm-932**  
**ibm-938** with Infoprint Manager for AIX only  
**ibm-euccn**  
**ibm-eucjp**  
**ibm-euckr**  
**ibm-euctw**

### Default Values

**AIX** The value of the **destination-model** attribute for the actual destination determines the default value.

### PSF, Email, Fax, Infoprint 2000

**ibm-437, ibm-850, ibm-860, ibm-863, ibm-865, ibm-eucjp, ibm-euckr, ibm-euctw**



**Usage Guidelines**

Infoprint compares the document attribute **default-character-mapping** to this attribute for scheduling.

**checkpoint-at-stacker**

Indicates where to pause jobs printing on this actual destination.

**GUI Label**

Checkpoint at stacker

**DSS**

PSF

**Type**

Resettable, single-valued

**Allowed Values**

You can enter one of these fixed values:

<i>Fixed Value</i>	<i>Input Synonym</i>
<b>true</b>	<b>yes</b>
<b>false</b>	<b>no</b>

**Default Value**

**false**

**Usage Guidelines**

When this attribute is set to **false** (the default), the checkpoint for paused jobs occurs at the operator viewing point on the printer device (the printhead). This means that when a paused job resumes, printing begins where it stopped, without reprinting any pages.

Set this attribute to **yes** if you want the checkpoint to occur at the stacker. This means that when a paused job resumes, all pages not stacked will be reprinted. This guarantees that, even if there is a paper jam between the printhead and the stacker, you will have at least one copy of each printed page.

**checkpoint-formats-supported**

Infoprint sets this attribute to identify the checkpoints supported for paused jobs for this actual destination.

**GUI Label**

Checkpoint formats allowed

**DSS**

AIX, PSF, Email, Fax, 3170, Infoprint 2000

**Type**

Non-settable, multi-valued

**Allowed Values**

Infoprint sets this value to any of these fixed values:

**dsf-document-number**  
**dsf-job-copy**  
**dsf-results-profile**  
**no-context-info**  
**psf-interrupt**

## Actual Destination

### Default Values

AIX dsf-document-number, dsf-job-copy, dsf-results-profile  
PSF dsf-results-profile, psf-interrupt  
Email, Fax, Infoprint 2000  
dsf-results-profile

### Usage Guidelines

Infoprint uses this information to reschedule paused jobs.

## color-mapping-table

Identifies the default color mapping table (CMT) that the output device uses when printing a document.

### GUI Label

Color mapping table

### DSS

PSF

### Type

Resettable, single-valued

### Allowed Values

You can enter a text string of up to 8 characters that contains the identification of the color mapping table.

### Default Value

No default value

## color-rip-servers

Identifies the Internet Protocol address (IP Address parameter) and port number of hosts capable of RIPping documents for this actual destination.

### GUI Label

Color RIP servers

### DSS

3170

### Type

Resettable, multi-valued

### Allowed Values

You can enter a text string up to 4095 characters long that contains either of these types of address:

#### Dotted decimal address

A series of integers within the range of 0 to 255, each separated by a period, . (decimal address). For example:

9.99.12.85:11126

#### Hostname

For example:

leo.boulder.IBM.com:11126

### Default Value

The value of the **destination-tcpip-internet-address** attribute with a port number of 11126

**command**

See **destination-command**.

**connection-timeout**

Sets the connection timeout parameter for TCP/IP-attached actual destinations. This time period is the amount of time that Infoprint waits before it stops trying to communicate with the output device when it cannot make a connection.

**GUI Label**

Connection time out (sec)

**DSS**

PSF, Email, Fax

**Type**

Resettable, single-valued

**Allowed Values**

You can enter a value of 0 through 9999. The unit is seconds.

**Default Value**

30

**Usage Guidelines**

- A value of **0** prevents any time out.
- Infoprint uses this attribute with TCP/IP-attached actual destinations and ignores it for other attachment types.

**content-orientations-supported**

Identifies the page presentations that this actual destination supports.

**GUI Label**

Orientations allowed

**DSS**

AIX, 3170

**Type**

Resettable, multi-valued

**Input Synonym**

You can use the synonym **orientations-supported**.

**Allowed Values**

You can enter any of these fixed values:

**landscape**  
**portrait**  
**reverse-landscape**  
**reverse-portrait**

**Default Values**

**portrait**

**Usage Guidelines**

- Infoprint compares the document attribute **content-orientation** to this attribute for validation and scheduling.
- You can use this attribute to restrict use of this actual destination.

## Actual Destination

### convert-to-ebcdic-supported

Indicates whether this actual destination supports converting document data from ASCII to EBCDIC.

#### GUI Label

Convert to EBCDIC allowed

#### DSS

PSF, Email, Fax, Infoprint 2000

#### Type

Resettable, single-valued

#### Allowed Values

You can enter one of these fixed values:

<i>Fixed Value</i>	<i>Input Synonym</i>
true	yes
false	no

#### Default Value

true

#### Usage Guidelines

- Infoprint compares the value of the document attribute **convert-to-ebcdic** to this attribute for job validation and scheduling.
- Infoprint uses the document attribute **convert-to-ebcdic** when printing line-data documents.
- You can use this attribute to restrict use of this actual destination.

### data-fidelity-problem-reported-supported

Identifies which types of data fidelity errors this actual destination reports.

#### GUI Label

Data fidelity problems allowed

#### DSS

PSF, Infoprint 2000

#### Type

Resettable, multi-valued

#### Allowed Values

You can enter any of these fixed values:

**all**  
**character**  
**none**  
**position**

#### Default Values

**all, character, none, position**

#### Usage Guidelines

- Infoprint compares the document attribute **data-fidelity-problem-reported** to this attribute for scheduling.

- Use this attribute to specify whether Infoprint issues error messages for print-positioning and invalid-character errors that occur for channel-attached, TCP/IP-attached, upload-SNA-attached, and upload-TCP/IP-attached printer devices.

Print positioning errors occur when the print position for the data is beyond the valid printable areas as defined by the intersection of the physical and logical pages. (A logical page identifies the printing boundaries of a physical page.)

Invalid-character errors occur when the code point does not map to a character in a font.

## default-font-fidelity-action

Indicates what Infoprint should do if a font required to print a document is not available in the resolution specified by the data stream, the document **font-resolution** attribute, or the actual destination **default-font-resolution** attribute.

### GUI Label

Default font fidelity action

### DSS

PSF, Email, Fax

### Type

Resettable, single-valued

### Allowed Values

You can enter one of these fixed values:

<i>Fixed Value</i>	<i>Explanation</i>
<b>stop</b>	Stop printing the job.
<b>continue</b>	Attempt to substitute a similar font at a different resolution.

### Default Value

continue

### Usage Guidelines

The value of the document attribute **font-fidelity-action** and the value specified in the data stream override the value of this attribute.

## default-font-resolution

Specifies the font resolution used for documents printed on this actual destination when no value is specified in the data stream or by the document **font-resolution** attribute.

### GUI Label

Default font resolution

### DSS

PSF

### Type

Resettable, single-valued

### Allowed Values

You can enter one of these fixed values:

**240**

**300**

## Actual Destination

### outline

#### Default Value outline

#### Usage Guidelines

- The value of this attribute must be one of the values of the **font-resolutions-supported** attribute.
- Usually the font resolution and the printer resolution match, but there are two cases when they do not:
  - Some printer devices, for example, the Infoprint 60 and Infoprint 4000, can print fonts of any resolution, although the print head is always 600 pels.
  - It is possible to print a document created with fonts of one resolution on a printer device with a different resolution by substituting fonts. Depending on the document, the output may or may not be acceptable.

## default-input-tray

Specifies the name of the default input tray for a PSF actual destination.

#### GUI Label

Default input tray

#### DSS

PSF

#### Type

Resettable, single-valued

#### Allowed Values

You can enter any value as long as the value maps to one of the actual destination **input-trays-supported** or **psf-tray-characteristics** attribute values.

#### Default Value

No default value

#### Usage Guidelines

- The value you specify must be one of the values specified for the **input-trays-supported** or **psf-tray-characteristics** actual destination attribute.
- Infoprint only uses the value you supply for this attribute if:
  - The user does not specify a medium or input tray.
  - The form definition Infoprint uses for the job does not specify an input tray.

## descriptor

Provides a textual description of this actual destination.

#### GUI Label

Description

#### DSS

All

#### Type

Resettable, single-valued

**Allowed Values**

You can enter a text string up to 4095 characters long that describes this actual destination. You may want to include such things as the type and location of the output device that this actual destination represents and any usage information, such as restrictions for this actual destination.

**Default Value**

No default value

**Usage Guidelines**

The use of this attribute is optional. However, a detailed description is useful to users who want to specify a given destination or to determine which destination can handle their jobs. A description is also helpful when you create a new logical destination and want to determine which actual destinations you should associate with the new logical destination.

**destination-command**

Specifies the command-line entry to print the job data.

**GUI Label**

Printer command

**DSS**

AIX, BSD, PSF

**Type**

Resettable, single-valued

**Input Synonyms**

You can use the synonym **printer-command** or **command**.

**Allowed Values**

You can enter a text string up to 4095 characters long that contains the command.

**Default Value**

**AIX** /usr/lib/lpd/piobe

**BSD for Infoprint Manager for AIX**

/usr/lpd/rembak

**BSD for Infoprint Manager for Windows NT and Windows 2000**

No Default

**PSF other-driver attached actual destinations for Infoprint Manager for AIX**

only /usr/lib/lpd/piobe

**PSF command-attached actual destinations for Infoprint Manager for AIX**

qpri -P<sub>xxx</sub> -dp -Z!

where *xxx* is the value of the **print-queue-name** attribute. If there is no value for the **print-queue-name** attribute, *xxx* is

**asc** If the **destination-data-stream=ppds**

**pcl** If the **destination-data-stream=pcl4, pcl5, or pcl5c**

**PSF command-attached actual destinations for Infoprint Manager for Windows NT and Windows 2000**

No Default

**Usage Guidelines**

- For AIX actual destinations:

## Actual Destination

- Infoprint uses the value as the command that the AIX actual destination executes for each document printed. It should include the full path name for the print driver you are using for your printer device.

With the addition of the **wait-for-job-completion** actual destination attribute, there is a new backend program called `pioinfo` that can be used in place of the `piojetd` backend program. For example, **destination-command=/usr/lpd/pio/etc/pioinfo *ip\_address***, where *ip\_address* is the ip address of the printer.

See “wait-for-job-completion” on page 439 for more information.

- If the printer backend program is a variation of, or front end to, **rembak**, specify **true** on the **remote-queue** actual destination attribute. Examples of **rembak**-based backend programs include **pioflb** and **piocolor**.

For more information on **rembak**, see “remote-queue” on page 421.

- For PSF actual destinations:
  - Infoprint uses the value as the command string to print a job on the command-attached printer and to send the job to the correct remote queue.
  - With the PSF DSS for AIX:
    - Infoprint uses the command string to invoke the printer backend program for other-driver attached actual destinations.
    - If you do not specify this attribute for command-attached actual destinations, Infoprint fills in the value of *XXX* (shown under Default Value) with the value of the **print-queue-name** attribute.
    - With a PSF-other-driver attached printer, **destination-command** is supported for an AIX server; however, it is not supported for an NT server.

## destination-data-stream

Identifies the data stream format that is output to the printer device.

**GUI Label**  
Data Stream

**DSS**  
PSF

**Type**  
Initially settable, single-valued

### Allowed Values

You can enter one of these fixed values:

**pcl4**  
**pcl5**  
**pcl5c**  
**ppds**  
**ipds**

**Note:** **ipds** is not an allowed value for command-attached and other-driver attached printers.

**afpds**

**Note:** **afpds** is only allowed with an attachment type of Upload-SNA or Upload-TCPIP.

For more information on attachment types, see “Understanding Attachment Types for PSF Actual Destinations” on page 327.



**Input Synonym**

You can use the synonym **printer-data-stream**.

**Default Value**

**Other-driver attached actual destinations**

**pcl4**

**Command-attached actual destinations**

**pcl4**

**Other attachment types**

**ipds**

**destination-locations**

Identifies the location of the output device.

**GUI Label**

Locations

**DSS**

All

**Type**

Resettable, multi-valued

**Input Synonyms**

You can use the synonym **printer-locations** or **locations**.

**Allowed Values**

You can enter a text string up to 4095 characters long, for each value, that describes the physical location of the output device. Each value is a different description for the same location.

**Default Values**

No default values

**Usage Guidelines**

Infoprint compares the job attribute **destination-locations-requested** to this attribute for scheduling. The user can specify the **destination-locations-requested** job attribute to request that Infoprint use the output device at this specific location to process the job.

**destination-model**

Identifies the make and model number defined by the manufacturer of the output device.

**GUI Label**

Model

**DSS**

AIX, PSF, BSD, 3170, Infoprint 2000, Email, Fax, Passthrough, IPP

**Type**

Non-settable with AIX and PSF other-driver attached actual destinations; resettable, single-valued with other listed DSSs

**Input Synonyms**

You can use the synonym **printer-model** or **model**.

## Actual Destination

### Allowed Values

You can enter a text string up to 4095 characters long that contains the make and model number of the output device.

### Default Value

If SNMP communication is active, Infoprint queries the printer device and sets the values according to the response; otherwise no default value.

With Internet Printing Protocol (IPP) printers when SNMP communication is not active, the default comes from IPP.

### Usage Guidelines

- You must set this value when you create an AIX or PSF actual destination, unless Infoprint can determine the value by means of SNMP.
- If you allow SNMP to determine this value for an AIX actual destination or a PSF other-driver attached actual destination, it must be one of the values of the server **snmp-aix-printer-models** attribute.
- For AIX actual destinations and PSF other-driver attached actual destinations, this value must match the file prefix of a file in the **/usr/lib/lpd/pio/predef** directory on the AIX processor on which the actual destination was created.
- For AIX actual destinations, Infoprint uses the value you specify here to determine the values to set for the **document-formats-supported** attribute.
- For PSF TCP/IP-attached actual destinations capable of printing halftones, and for any PSF actual destination that represents a printer device with a finisher attached, specify the model name in the format **Infoprintxxxx**, where **xxxx** is the model number, for example, **Infoprint4000-708**. Do not put a space between **Infoprint** and the model number.

**Note:** If you configure these printer models as PSF other-driver attached actual destinations or as AIX actual destinations, specify the model name as the file prefix of a file in the **/usr/lib/lpd/pio/predef** directory.

- Infoprint compares the job attribute **destination-models-requested** to this attribute for scheduling.
- For IPP printers, Infoprint uses the **destination-model** information for validation and scheduling.
- If you specify a value for the **destination-model** attribute, you deactivate the default provided by SNMP.

## destination-name

Identifies the name of this actual destination.

### DSS

All

### Type

Non-settable, single-valued

### Input Synonyms

You can use the synonym **printer-name**, **printer**, or **physical-printer**.

### Allowed Values

Infoprint set this value to the *DestinationName* portion of the argument used with the **pdcreate** command or with the **pdmigpp** utility when this actual destination was created.

**Default Value**

No default value

**Usage Guidelines**

- Infoprint compares the job attribute **actual-destination-requested** to this attribute for validation and scheduling.
- The name must be unique within the namespace.

**destination-needs-attention-time**

Reports the amount of time the output device has been waiting for simple intervention, such as loading paper.

**GUI Label**

Attention needed

**DSS**

All

**Type**

Non-settable, single-valued

**Input Synonym**You can use the synonym **printer-needs-attention-time**.**Allowed Values**

Infoprint sets this value to *[HH:]MM*. The unit is minutes or hours and minutes, separated by a colon.

**Default Value**

No default value

**destination-needs-key-operator-attention-time**

Reports the amount of time the output device has been waiting for the attention of a key (or skilled) operator.

**GUI Label**

Operator needed

**DSS**

All

**Type**

Non-settable, single-valued

**Input Synonym**You can use the synonym **printer-needs-key-operator-attention-time**.**Allowed Values**

Infoprint sets this value to *[HH:]MM*. The unit is minutes or hours and minutes, separated by a colon.

**Default Value**

No default value

**destination-pass-through**

Contains information used to update the printer's colon file.

## Actual Destination

### GUI Label

Other options

### DSS

AIX

### Type

Resettable, single-valued

### Input Synonyms

You can use the synonym **printer-pass-through** or **other-options**.

### Allowed Values

You can enter a text string up to 4095 characters long containing update information.

### Syntax

*'colon-file-attribute=value ...'*

For example, to set the datastream filter attribute (**\_d**) in the printer colon file to "passthrough" (**p**), enter:

```
destination-pass-through='_d=p'
```

### Default Value

No default value

## destination-poll-interval

Specifies the amount of time in seconds between job status polls of a Internet Printing Protocol (IPP) printer or a Passthrough printer.

### GUI Label

Poll interval (sec)

### DSS

IPP, Passthrough

### Type

Resettable, single-valued

### Allowed Values

You can enter a value from 0 through 2147483647.

### Default Value

2

## destination-realization

Indicates whether the destination is an actual destination or a logical destination.

### DSS

All

### Type

Initially settable, single-valued

### Input Synonym

You can use the synonym **printer-realization**.

**Allowed Values**

You can enter one of these fixed values:

**actual**  
**logical**

**Default Value**

**logical**

**destination-register-threshold**

Specifies the amount of time that this actual destination will wait between attempts to communicate (register) with the server.

**GUI Label**

Attempt to register with server

**DSS**

All

**Type**

Resettable, single-valued

**Input Synonyms**

You can use the synonym **printer-register-threshold** or **register-threshold**.

**Allowed Values**

You can enter a value of *[HH:]MM*. The unit is minutes or hours and minutes, separated by a colon.

**Default Value**

**10**

**Usage Guidelines**

- If you lower this value, network traffic increases when the server is down, but the actual destination registers more quickly when you bring up the server.
- If you raise this value, network traffic decreases when the server is down, but the actual destination registers more slowly when you bring up the server.

**destination-release-timer**

Specifies the maximum amount of time between jobs, in seconds, before Infoprint gives up control of a PSF actual destination.

**GUI Label**

Release time (sec)

**DSS**

PSF

**Type**

Resettable, single-valued

**Input Synonym**

You can use the synonym **printer-release-timer**.

**Allowed Values**

You can enter an integer from 0 through 9999. The unit value is seconds.

**Default Value**

**9999**

## Actual Destination

### Usage Guidelines

- The **destination-release-timer** allows Infoprint to share an output device with a print manager, such as PSF Direct. Specify a value of 9999 if the output device is not shared.
- The **destination-release-timer** allows time for all processes to stop running gracefully as Infoprint gives up control of the attached PSF actual destination.
- If the **non-process-runout-timer** attribute has a greater value than the **destination-release-timer** attribute, Infoprint issues an automatic NPRO. However, IBM recommends that you set **non-process-runout-timer** to a lower value than **destination-release-timer**.

## destination-state

Identifies the current state of the actual destination.

### GUI Label

State

### DSS

All

### Type

Non-settable, single-valued

### Input Synonym

You can use the synonym **printer-state**.

### Allowed Values

Infoprint sets and updates the value to one of these fixed values:

<i>Fixed Value</i>	<i>Explanation</i>
<b>connecting-to-printer</b>	<p>The actual destination has received a job and is trying to connect to its printer device. After it connects to the device, the actual destination locks the printer device until it finishes processing the job so that another print system cannot use the device.</p> <p><b>Note:</b> This state applies only to AIX actual destinations and PSF other-driver attached actual destinations on Infoprint Manager for AIX.</p>
<b>idle</b>	<p>The actual destination is waiting for a job. An actual destination can be idle even if its output device is printing a job from some other AIX process or from the AIX print-spooling subsystem; or from some other Windows application or the Windows spooler.</p>
<b>needs-attention</b>	<p>The actual destination can connect to the output device, but for some reason the output device cannot print.</p>
<b>needs-key-operator</b>	<p>This state occurs when there is a serious problem with the output device. Either the actual destination cannot connect to the output device or there is some other problem. For example, a printer device may be out of toner. Infoprint automatically disables the actual destination when the actual destination</p>

## Actual Destination

enters this state. If the actual destination uses SNMP, Infoprint automatically re-enables it when the problem is corrected. To prevent automatic re-enabling, manually disable the actual destination.

### paused

The actual destination was paused with the **pdpause** command or by a job with **job-start-wait=true**.

### printing

The actual destination is processing a job.

### shutdown

The actual destination was shut down with the **pdshutdown** command.

**Note:** This state applies only to PSF actual destinations.

### timed-out

The actual destination received a job, but the actual destination could not connect to the printer device in the time specified by the **printer-timeout-period** actual destination attribute.

**Note:** This state applies only to AIX actual destinations and PSF other-driver attached actual destinations.

### Default Value

No default value

## destination-support-system

Identifies the type of destination support system for this actual destination.

### DSS

All

### Type

Initially settable, single-valued

### Input Synonym

You can use the synonym **device-support-system**.

### Allowed Values

You can enter one of these fixed values:

#### *Fixed Value*

**aix**

**bsd**

**psf**

**3170**

**email**

**fax**

**IP2000**

**IPP**

**windows**

#### *Input Synonym*

**piobe**

**passthrough**

### Default Value

**psf**

## Actual Destination

### Usage Guidelines

- Infoprint compares the job attribute **dss-requested** to this attribute for scheduling.
- You must enter a value for this attribute when you create an actual destination unless it will use the PSF DSS.

## destination-tcpip-internet-address

Identifies the Internet Protocol address (IP Address parameter) of this actual destination. This is the Internet Protocol address assigned to the output device.

### GUI Label

TCP/IP address

### DSS

AIX, BSD, PSF, 3170, Infoprint 2000, IPP, Passthrough

### Type

Resettable, single-valued

### Input Synonym

You can use the synonym **printer-tcpip-internet-address**.

### Allowed Values

You can enter a text string up to 4095 characters long that is either of these types of address:

#### Dotted decimal address

A series of integers within the range of 0 to 255, each separated by a period, . (decimal address). For example:

9.99.12.85

#### Hostname

For example:

leo.boulder.ibm.com

**Note:** When you create an SNMP printer, you must specify either the fully-qualified printer name or the internet address. If you create an SNMP printer with an abbreviated printer name, Infoprint issues the SNMP connection lost message when you attempt to enable the printer.

### Default Value

No default value

### Usage Guidelines

- You must enter a value for destinations to use SNMP. When you use NPM, the value for destinations to use SNMP must be a decimal address.
- You must enter a value for PSF TCP/IP-attached actual destinations, for PSF upload-TCP/IP-attached actual destinations, for 3170 actual destinations, and for Infoprint 2000 actual destinations.
- Infoprint ignores this attribute for PSF channel-attached and upload-SNA-attached actual destinations.
- For printers attached using the i-data 7913 IPDS Printer LAN Attachment, use the IP address of the 7913.



## destination-tcpip-port-number

Identifies the Port Number parameter for PSF TCP/IP-attached and upload-TCP/IP-attached actual destinations. This is the TCP/IP port number configured at the output device.

### GUI Label

TCP/IP port number

### DSS

PSF

### Type

Resettable, single-valued

### Input Synonym

You can use the synonym **printer-tcpip-port-number**.

### Allowed Values

You can enter an integer from 1 through 2147483647, but you typically enter an integer from 5001 to 65535. For devices whose port is configurable, the port you specify must match the port configured at the output device. For printers attached using the i-data 7913 IPDS Printer LAN attachment, you must use the value of 5001.

### Default Value

No default value

### Usage Guidelines

You must enter a value for PSF TCP/IP-attached and upload-TCP/IP-attached actual destinations. Infoprint ignores this attribute for other attachment types.

## destination-timeout-period

Specifies the amount of time, in seconds, that Infoprint allows for the server to try to connect to a shared network printer (printer device) after the actual destination receives a new job request.

### DSS

AIX, PSF

### Type

Resettable, single-valued

### Input Synonym

You can use the synonym **timeout-period** or **printer-timeout-period**.

### Allowed Values

You can enter an integer from 0 through 2147483647. The unit is seconds.

### Default Value

60

### Usage Guidelines

- For PSF actual destinations, this attribute applies only to actual destinations with an attachment type of **other**.
- While the server is attempting to connect to the printer device, this actual destination is in the **timed-out** state, but it can still accept jobs.

## Actual Destination

- If the server cannot connect to the printer device within the specified time, the following happens:
  - The printer state becomes **timed-out**.
  - This actual destination will not accept new jobs.
  - Infoprint may issue a warning message, depending on the notification profile of this actual destination.
  - The server continues to try to connect to the printer device until successful, or until this actual destination is disabled.
  - Infoprint sends a warning message at the end of each timeout period (if specified by the notification profile).

## device-name

Identifies the output device that this actual destination represents.

### GUI Label

Windows port name (Passthrough)  
Device (all other DSSs)  
URL (IPP)

### DSS

AIX, PSF, Email, Fax, Infoprint 2000, IPP, Passthrough

### Type

Initially settable, single-valued

### Allowed Values

You can enter a text string up to 255 characters long that contains the name (ID) of the output device that prints jobs assigned to this actual destination. The value usually identifies the path to the device name, commonly located in a **/dev** directory.

For Internet Printing Protocol (IPP) printers, enter the URL for the IPP printer.

For Passthrough printers, enter the Windows NT or Windows 2000 **Port Name**.

### Default Value

No default value

### Usage Guidelines

- You must enter a value for this attribute when you create a PSF command-attached actual destination on an AIX server; however, it is not supported for an NT server.
- You must enter a value for this attribute when you create a PSF other-driver-attached actual destination on Windows NT or Windows 2000; however, it is not supported on an AIX Server.
- On Windows NT and Windows 2000, the device name must be the name of a Windows NT or Windows 2000 port that has already been created.
- You must configure the device name you specify in AIX. You can determine which device names exist by using the SMIT fastpath **smit pdp** and then listing all defined printers and plotters. If you need to create the output device within AIX, use the SMIT fastpath **smit makprt**.
- If an AIX print queue has been configured for this actual destination, the device name appears in the **/etc/qconfig** file.

- Do not specify a value for PSF TCP/IP-attached, upload-TCP/IP-attached, upload-SNA-attached, or channel-attached destinations.
- When you are working with AIX DSS actual destinations, see “Creating and Managing Actual Destinations” in the *Infoprint Manager for AIX: Administrator’s Guide* for information on correcting the configuration of **remote-queue** printers that have **device-name** set to /dev/null.

## device-support-system

See **destination-support-system**.

## document-attributes-supported

Identifies the document attributes that this actual destination supports. Infoprint checks this attribute during validation to allow jobs whose documents have these attributes to continue on to this actual destination.

### DSS

All

### Type

Non-settable, multi-valued

### Allowed Values

Infoprint sets a text string that contains a list of document attributes that this actual destination supports.

**Note:** This list includes only document attributes that directly affect the actual destination. Documents with attributes that affect the server, for example, **initial-value-document**, can be printed even though those attributes are not on this list.

### Default Value

**AIX** **content-orientation, copy-count, default-input-tray, default-medium, destination-pass-through, document-comment, document-content, document-content-list, document-format, document-type, maximum-messages-printed, plex, print-quality, sides**

**BSD** **copy-count, destination-pass-through, document-comment, document-content, document-content-list, document-format, document-type, maximum-messages-printed, plex, print-quality, sides**

### PSF DSS for AIX

**account-text, address1-text, address2-text, address3-text, address4-text, base-printer, building-text, carriage-control-type, chars, convert-to-ebcdic, copy-count, data-fidelity-problem-reported, default-character-mapping, default-input-tray, default-medium, default-printer-resolution, department-text, destination-pass-through, document-comment, document-content, document-content-list, document-finishing, document-format, document-type, font-fidelity-action, font-resolution, form-definition, image-fit, image-length, image-out-format, image-width, input-exit, input-tray-select, maximum-messages-printed, maximum-transform-pages-ahead, mvs-class, mvs-destination, mvs-forms, mvs-segment-id, name-text, new-line-option, node-id-text, number-up, other-transform-options, output-appearance, output-bin, output-format, overlay, page-definition, page-media-select, page-select, plex, programmer-text, resource-context, resource-context-font,**

## Actual Destination

resource-context-form-definition, resource-context-overlay, resource-context-page-definition, resource-context-page-segment, resource-context-user, resource-exit, room-text, scanner-correction, screen-frequency, segment-file-size, shared-formdef, shift-out-shift-in, sides, start-on-new-sheet, table-reference-characters, title-text, transform-message-file-name, transform-output-file-name, user-id-text, x-image-shift, x-image-shift-back, y-image-shift, y-image-shift-back

### PSF DSS for Windows NT and Windows 2000

account-text, address1-text, address2-text, address3-text, address4-text, base-printer, building-text, carriage-control-type, chars, convert-to-ebcdic, copy-count, data-fidelity-problem-reported, default-character-mapping, default-input-tray, default-medium, default-printer-resolution, department-text, destination-pass-through, document-comment, document-content, document-content-list, document-finishing, document-format, document-type, font-fidelity-action, font-resolution, form-definition, image-fit, image-length, image-out-format, image-width, input-exit, input-tray-select, maximum-messages-printed, maximum-transform-pages-ahead, mvs-class, mvs-destination, mvs-forms, mvs-segment-id, name-text, new-line-option, node-id-text, number-up, other-transform-options, output-bin, output-format, overlay, page-definition, page-media-select, page-select, plex, programmer-text, resource-context, resource-context-font, resource-context-form-definition, resource-context-overlay, resource-context-page-definition, resource-context-page-segment, resource-context-user, resource-exit, room-text, segment-file-size, shared-formdef, shift-out-shift-in, sides, start-on-new-sheet, table-reference-characters, title-text, transform-message-file-name, transform-output-file-name, user-id-text, x-image-shift, x-image-shift-back, y-image-shift, y-image-shift-back

3170 bits-per-spot, black-overprint, cms-proclink, cms-product, compressed-output, content-orientation, control-strip, copy-count, default-medium, default-printer-resolution, destination-pass-through, document-content, document-content-list, document-format, document-type, dot-shape, enable-settrap, image-center-x, image-center-y, image-length, image-scale, image-width, maximum-messages-printed, output-bin, output-face-up, overprint, page-clip, plex, sides, x-image-shift, y-image-shift

Email account-text, address1-text, address2-text, address3-text, address4-text, carriage-control-type, chars, convert-to-ebcdic, copy-count, default-character-mapping, document-comment, document-content, document-format, document-type, email-from-address, email-to-address, form-definition, image-fit, image-length, image-width, input-exit, maximum-messages-printed, new-line-option, number-up, other-transform-options, output-format, overlay, page-definition, page-select, resource-context, resource-context-font, resource-context-form-definition, resource-context-overlay, resource-context-page-definition, resource-context-page-segment, resource-context-user, resource-exit, shared-formdef, shift-out-shift-in, subject-text, table-reference-characters, title-text, transform-message-file-name, transform-output-file-name, x-image-shift, y-image-shift

Fax account-text, address1-text, address2-text, address3-text, address4-text, callback-number, carriage-control-type, chars, convert-to-ebcdic, copy-count, default-character-mapping,

destination-company-text, document-comment, document-content, document-format, document-type, fax-number, fax-to-name, form-definition, image-fit, image-length, image-width, input-exit, maximum-messages-printed, new-line-option, number-up, originating-company-text, other-transform-options, output-format, overlay, page-definition, page-select, resource-context, resource-context-font, resource-context-form-definition, resource-context-overlay, resource-context-page-definition, resource-context-page-segment, resource-context-user, resource-exit, shared-formdef, shift-out-shift-in, subject-text, table-reference-characters, title-text, transform-message-file-name, transform-output-file-name, x-image-shift, y-image-shift

**Infoprint 2000**

account-text, base-printer, carriage-control-type, chars, copy-count, convert-to-ebcdic, default-character-mapping, default-medium, default-print-resolution, document-comment, document-content, document-format, document-type, form-definition, halftone, image-fit, image-length, image-out-format, image-width, input-exit, new-line-option, number-up, other-transform-options, output-bin, output-format, overlay, page-definition, page-select, plex, printer-pass-through, resource-context, resource-context-font, resource-context-form-definition, resource-context-page-definition, resource-context-page-segment, resource-context-overlay, resource-context-user, resource-exit, shift-out-shift-in, sides, start-on-new-sheet, table-reference-characters, transform-message-file-name, transform-output-file-name, x-image-shift, x-image-shift-back y-image-shift, y-image-shift-back

**Passthrough**

copy-count, default-medium, destination-pass-through, document-content, document-type

**IPP**

copy-count, default-medium, destination-pass-through, document-content, document-type

**document-finishing-supported**

Identifies the document finishing options that this actual destination supports.

**GUI Label**

Finishing options allowed

**DSS**

PSF

**Type**

Resettable, multi-valued

**Allowed Values**

You can enter any of these fixed values:

**z-fold**

**Default Values**

**z-fold**

**Usage Guidelines**

- Infoprint compares the document attribute **document-finishing** to this attribute for validation and scheduling.

## Actual Destination

- You can use this attribute to restrict use of this actual destination.

## document-formats-ripped-at-destination

Identifies the document formats that can be ripped at this actual destination.

### GUI Label

Formats to RIP at destination

### DSS

Email, Infoprint 2000

### Type

Resettable, multi-valued

### Allowed Values

You can enter any of these fixed values:

<i>Fixed Value</i>	<i>Input Synonym</i>	<i>DSS</i>
ascii		Infoprint 2000
kgi		Infoprint 2000
pcl	hppcl, hp-pcl	Infoprint 2000
postscript	ps	Email, Infoprint 2000
tiff		Email

### Default Values

No default values

## document-formats-supported

Identifies the document formats that this actual destination supports. Infoprint sets this value dynamically based on the DSS and the document formats for which transforms are available.

### GUI Label

Formats allowed

### DSS

All

### Type

Resettable, multi-valued

### Allowed Values

You can enter any of these fixed values:

<i>Fixed Value</i>	<i>Input Synonym</i>	<i>DSS</i>
ascii		AIX, BSD, PSF (except upload printers), Passthrough, IPP
dbcs-ascii		AIX, BSD, PSF, Infoprint 2000
ditroff		BSD, PSF DSS for AIX, email, fax, Infoprint 2000
d630		AIX, BSD
gif		BSD, PSF DSS for AIX, email, fax, Infoprint 2000
hpgl	hp-gl	AIX, BSD
iso-6429		AIX, BSD, Passthrough, IPP
jpeg		BSD, PSF DSS for AIX, email, fax, Infoprint 2000
kgi		BSD, Infoprint 2000
lcds		BSD

<i>Fixed Value</i>	<i>Input Synonym</i>	<i>DSS</i>
line-data		BSD, PSF, email, fax, Infoprint 2000
metacode		BSD
modca-p	afpds	BSD, PSF, email, fax, Infoprint 2000
passthru		AIX, BSD
pcl	hppcl, hp-pcl	AIX, BSD, PSF, email, fax, Infoprint 2000, Passthrough, IPP
pdf		BSD, PSF, email, fax, Infoprint 2000
postscript	ps	All
ppds		BSD
sap		BSD, PSF DSS for AIX, email, fax, Infoprint 2000, Passthrough
sap-abap		BSD, PSF DSS for AIX, email, fax, Infoprint 2000, Passthrough
simple-text	text	BSD, Passthrough, IPP
tiff		BSD, PSF DSS for AIX, email, fax, Infoprint 2000

## Default Values

**AIX** **ascii, hpgl, iso-6429, passthru, pcl, pdf, and postscript.**

Based on the value of the **destination-model** attribute and how the **/usr/lpd/pio/predef** directory defines the printer model.

**BSD** **ascii, iso-6429, pcl, ppds, postscript, simple-text.**

**PSF upload-SNA-attached and upload-TCP/IP-attached actual destinations**

If all transforms are available, **dbcs-ascii, ditroff, gif, jpeg, line-data, modca-p, pcl, postscript, sap, sap-abap, tiff**

**Other PSF actual destinations with PSF DSS for AIX**

If all transforms are available, **ascii, dbc-ascii, ditroff, gif, jpeg, line-data, modca-p, pcl, pdf, postscript, sap, sap-abap, tiff**

**Other PSF actual destinations with PSF DSS for Windows NT and Windows**

**2000** If all transforms are available, **ascii, dbc-ascii, line-data, modca-p, pcl, pdf, postscript**

**3170** **postscript**

**Infoprint 2000**

If all transforms are available, **dbcs-ascii, ditroff, gif, jpeg, kgl, line-data, modca-p, pcl, pdf, postscript, sap, sap-abap, sap-otf, tiff**

**Fax, Email**

If all transforms are available, **dbcs-ascii, ditroff, gif, jpeg, line-data, modca-p, pcl, pdf, postscript, sap, sap-abap, sap-otf, tiff**

**Passthrough**

**ascii, iso-6429, pcl, ppds, postscript, simple-text.**

**IPP** **ascii, iso-6429, pcl, ppds, postscript, simple-text.**

## Usage Guidelines

- When you create a PSF, email, fax, or Infoprint 2000 actual destination, Infoprint sets these values to the document formats for which transforms are available. When the server is shut down and restarted, Infoprint updates the values to reflect transforms that have been added or deleted. You can also modify these values.
- Infoprint compares the document attribute **document-format** to this attribute for validation and scheduling.

## Actual Destination

- Delete attribute values to restrict use of this actual destination.

## document-types-supported

Identifies the types of documents that this actual destination supports.

### GUI Label

Types allowed

### DSS

All

### Type

Resettable, multi-valued

### Allowed Values

You can enter any of these fixed values:

<i>Fixed Value</i>	<i>DSS</i>
<b>color-mapping-table</b>	PSF
<b>cover-sheet</b>	Fax
<b>document-definition</b>	PSF DSS for AIX, 3170, email, fax, Infoprint 2000
<b>email-body</b>	Email
<b>email-signature</b>	Email
<b>file-reference</b>	All
<b>font</b>	PSF, email, fax, Infoprint 2000
<b>form-definition</b>	PSF, email, fax, Infoprint 2000
<b>formatted-job-ticket</b>	PSF, 3170, email, fax, Infoprint 2000
<b>insert-sheet</b>	PSF, email, fax, Infoprint 2000
<b>job-ticket</b>	PSF, 3170, email, fax, Infoprint 2000
<b>overlay</b>	PSF, email, fax, Infoprint 2000
<b>page-definition</b>	PSF, email, fax, Infoprint 2000
<b>page-segment</b>	PSF, email, fax, Infoprint 2000
<b>page-shift-file</b>	PSF, email, fax, Infoprint 2000
<b>printable</b>	All
<b>resource</b>	PSF DSS for AIX, 3170, email, fax, Infoprint 2000
<b>variable-data</b>	PSF DSS for AIX, 3170, email, fax, Infoprint 2000

### Default Values

**AIX** file-reference, printable

**BSD** file-reference, printable

#### PSF DSS for AIX

color-mapping-table, document-definition, file-reference, font, form-definition, formatted-job-ticket, insert-sheet, job-ticket, overlay, page-definition, page-segment, page-shift-file, printable, resource, variable-data

#### PSF DSS for Windows NT and Windows 2000

color-mapping-table, file-reference, font, form-definition, formatted-job-ticket, insert-sheet, job-ticket, overlay, page-definition, page-segment, page-shift-file, printable

**3170** document-definition, file-reference, formatted-job-ticket, job-ticket, printable, resource, variable-data

**Email** document-definition, email-body, email-signature, file-reference, font,



form-definition, formatted-job-ticket, insert-sheet, job-ticket, overlay, page-definition, page-segment, page-shift-file, printable, resource, variable-data

**Fax** cover-sheet, document-definition, file-reference, font, form-definition, formatted-job-ticket, insert-sheet, job-ticket, overlay, page-definition, page-segment, page-shift-file, printable, resource, variable-data

**Infoprint 2000**

document-definition, file-reference, font, form-definition, formatted-job-ticket, form-definition, insert-sheet, job-ticket, overlay, page-definition, page-shift-file, printable resource, variable-data

**Passthrough**

file-reference, printable

**IPP** file-reference, printable

**Usage Guidelines**

- Infoprint compares the document attribute **document-type** to this attribute for scheduling.
- You can use this attribute to restrict use of this actual destination.

## dss-job-message-disposition

Indicates how job messages about errors detected by the the device support system (DSS), such as data stream errors, are recorded.

**GUI Label**

Record job messages

**DSS**

PSF

**Type**

Resettable, single-valued

**Allowed Values**

You can enter one of these fixed values:

**log**  
**print**

**Default Value**

**print**

**Usage Guidelines**

If you specify **log**, messages are written to the

- */var/psf/DestinationName/jobmessage.log* file for AIX, where *DestinationName* is the name of this actual destination.
- *\install\_path\var\psf\DestinationName\jobmessage.log* file Windows NT and Windows 2000, where *DestinationName* is the name of this actual destination and *install\_path* indicates the path where you installed Infoprint Manager.

## dss-job-message-log-size

Indicates the size, in kilobytes, the DSS job message log can grow to.

**GUI Label**

Job message log size (KBytes)

## Actual Destination

### DSS

PSF

### Type

Resettable, single-valued

### Allowed Values

You can enter an integer from 1 to Infoprint 2000000. The unit is kilobytes.

### Default Value

8192

### Usage Guidelines

This attribute is used only when the value of the **dss-job-message-disposition** attribute is **log**.

## dss-job-message-log-wrap

Indicates whether Infoprint should start overwriting messages at the beginning of the DSS job message log when the log is full.

### GUI Label

Wrap job message log

### DSS

PSF

### Type

Resettable, single-valued

### Allowed Values

You can enter one of these fixed values:

<i>Fixed Value</i>	<i>Input Synonym</i>
true	yes
false	no

### Default Value

true

### Usage Guidelines

This attribute is used only when the value of the **dss-job-message-disposition** attribute is **log**.

## ebcdic-character-mapping

Indicates the EBCDIC code page that PSF/MVS uses to map the attributes of this PSF upload-TCP/IP-attached or PSF upload-SNA-attached actual destination.

### GUI Label

EBCDIC code page to use

### DSS

PSF

### Type

Resettable, single-valued

### Allowed Values

You can enter the name of an EBCDIC code page.

**Default Value**

ibm-037

**Usage Guidelines**

Infoprint requires this attribute for PSF upload-SNA-attached and upload-TCP/IP-attached actual destinations and ignores it for other attachment types.

**enabled**

Indicates whether this actual destination is enabled and can accept jobs.

**GUI Label**

Enabled

**DSS**

All

**Type**

Non-settable, single-valued

**Allowed Values**

Infoprint sets this value to:

- **true** when an Infoprint administrator has issued the **pdenable** command, and the queue associated with the destination exists and is in communication with this actual destination.
- **false** when an Infoprint administrator has disabled this actual destination with the **pddisable** command, or when some printer error has been detected.

**Default Value**

false

**end-message-supported**

Indicates whether this actual destination supports the job attribute **job-end-message**.

**GUI Label**

Send job completed message

**DSS**

All

**Type**

Resettable, single-valued

**Allowed Values**

You can enter one of these fixed values:

<i>Fixed Value</i>	<i>Input Synonym</i>
true	yes
false	no

**Default Value**

true

**Usage Guidelines**

- Use this attribute to allow operators to receive messages that users specify with the **job-end-message** job attribute when they submit the job. When the value of

## Actual Destination

this attribute is **true**, Infoprint sends the message to the operators specified by the **notify-operator** attribute for this actual destination when the job finishes printing.

- Infoprint compares the job attribute **job-end-message** to this attribute for validation and scheduling.
- You can use this attribute to restrict use of this actual destination.

## end-sheets-supported

Identifies the types of end sheets that this actual destination supports.

### GUI Label

End sheets allowed

### DSS

AIX, PSF

### Type

Resettable, multi-valued

### Allowed Values

You can enter any of the following fixed values. For PSF only, you can enter a string up to 255 characters long that contains identifiers of auxiliary-sheet objects.

<i>Fixed Value</i>	<i>DSS</i>	<i>Explanation</i>
<b>accounting-log</b>	PSF	This value is technically valid, but should not be used for end sheets.
<b>blank</b>	PSF	The end sheet is blank.
<b>brief</b>	AIX, PSF	The end sheet style is brief.
<b>full</b>	AIX, PSF	The end sheet style is full.
<b>job-ticket</b>	PSF	The job ticket is printed on the end sheet.
<b>none</b>	AIX, PSF	No end sheet prints.

### Default Values

**AIX** **brief, full, none**

**PSF** **accounting-log, blank, brief, full, job-ticket, none**, and the names of other defined auxiliary sheets which have legal PSF auxiliary sheet attributes.

### Usage Guidelines

- PSF actual destinations can use auxiliary-sheet objects if they have valid **psf-exit-xxx** values. AIX actual destinations print start and end sheets, but they do not use auxiliary-sheet objects.
- Infoprint verifies that the value of the **printer-end-sheet** attribute is a value of this attribute.
- You cannot delete a value from this attribute if the value you want to delete is the value of the **printer-end-sheet** attribute.
- For PSF actual destinations, Infoprint sets this value dynamically to the names of all defined auxiliary sheets with legal attributes. You should never have to reset this value.

## font-resolutions-supported

Indicates the values of the document attribute **font-resolution** that this actual destination accepts.

**GUI Label**

Font resolutions allowed

**DSS**

PSF

**Type**

Resettable, multi-valued

**Allowed Values**

You can enter any of these fixed values:

**240****300****outline****Default Values****240, 300, outline****Usage Guidelines**

- Usually the font resolution and the printer resolution match, but there are two cases when they do not:
  - Some printer devices, for example, the Infoprint 60 and Infoprint 4000, can print fonts of any resolution, although the print head is always 600 pels.
  - It is possible to print a document created with fonts of one resolution on a printer device with a different resolution by substituting fonts. Depending on the document, the output may or may not be acceptable.
- Infoprint compares the document attribute **font-resolution** to this attribute for validation and scheduling.
- You can use this attribute to restrict use of this actual destination.

**force-destination-setup**

Indicates whether jobs requiring resources that this actual destination does not have ready or does not support should be held or scheduled to print.

**GUI Label**

Disable on job mismatch

**DSS**

All

**Type**

Resettable, single-valued

**Input Synonym**You can use the synonym **force-printer-setup**.**Allowed Values**

You can enter one of these fixed values:

**Fixed Value****true****false****Input Synonym****yes****no****Default Value****false**

## Actual Destination

### Usage Guidelines

- When the value of **force-destination-setup** is **false**, Infoprint checks that the actual destination can process each job in the queue before scheduling the job to print. If the job requires any resources that are not ready or not supported, the job is RIPped if appropriate, then held. The **required-resources-not-ready** job attribute indicates what resources are not ready. The **required-resources-not-supported** job attribute indicates what resources are not supported.
- When the value of **force-destination-setup** is **true**, Infoprint does not check whether the actual destination can process the job until the job is sent to the actual destination. At that time, if any required resources are not ready or not supported, Infoprint disables the actual destination and sends a message to the operator to change the destination setup. When the operator enables the actual destination, the job is printed or transmitted.

## force-printer-setup

See **force-destination-setup**.

## form-definition

Identifies the default form definition that the output device uses when printing or transmitting a document.

### GUI Label

Form definition

### DSS

PSF, Email, Fax, Infoprint 2000

### Type

Resettable, single-valued

### Allowed Values

You can enter a text string up to 8 characters long that contains the form-definition ID.

### Default Value

**Basic Infoprint administrator's GUI**

**F100D**

**Advanced Infoprint administrator's GUI and command line**

**F1A10111**

### Usage Guidelines

- The form definition controls positioning of the output image on the page.
- A form definition can specify overlays, a paper source for cut-sheet printers (input bin selection), duplex printing, and text suppression on a page.

## halftones-supported

Identifies the values for the document attribute **halftone** that this actual destination supports.

### GUI Label

Halftones allowed

### DSS

PSF

**Type**

Resettable, multi-valued

**Allowed Values**

The value of a **halftone** attribute is a combination of screen-name and output-appearance in the format: *screen-name:output-appearance*.

For custom halftones, the value can also be a combination of screen-name, output-appearance, and saved-calibration in the format: *screen-name:output-appearance:saved-calibration*.

You can enter a customized value or one of these fixed values:

**ibm71lpi:standard**  
**ibm71lpi:highlight-midtones**  
**ibm71lpi:dark**  
**ibm85lpi:standard**  
**ibm85lpi:highlight-midtones**  
**ibm85lpi:dark**  
**ibm106lpi:standard**  
**ibm106lpi:highlight-midtones**  
**ibm106lpi:dark**  
**ibm141lpi:standard**  
**ibm141lpi:highlight-midtones**  
**ibm141lpi:dark**

**Note:** With the Infoprint 21, you can select the following halftone values in addition to the fixed values listed above:

**ibm150lpi:standard**  
**ibm150lpi:highlight-midtones**  
**ibm150lpi:dark**  
**ibm200lpi:standard**  
**ibm200lpi:highlight-midtones**  
**ibm200lpi:dark**

You can enter one of the following fixed values if you are using enhanced toner on the IP4000 or IP4000-708 printer:

**ibm71lpi:standard.enhtoner**  
**ibm71lpi:highlight-midtones.enhtoner**  
**ibm71lpi:dark.enhtoner**  
**ibm85lpi:standard.enhtoner**  
**ibm85lpi:highlight-midtones.enhtoner**  
**ibm85lpi:dark.enhtoner**  
**ibm106lpi:standard.enhtoner**  
**ibm106lpi:highlight-midtones.enhtoner**  
**ibm106lpi:dark.enhtoner**  
**ibm141lpi:standard.enhtoner**  
**ibm141lpi:highlight-midtones.enhtoner**  
**ibm141lpi:dark.enhtoner**

**Default Value**

**ibm71lpi:standard**  
**ibm71lpi:highlight-midtones**  
**ibm71lpi:dark**  
**ibm85lpi:standard**  
**ibm85lpi:highlight-midtones**  
**ibm85lpi:dark**

## Actual Destination

**ibm106lpi:standard**  
**ibm106lpi:highlight-midtones**  
**ibm106lpi:dark**  
**ibm141lpi:standard**  
**ibm141lpi:highlight-midtones**  
**ibm141lpi:dark**

For the IP4000 and IP4000-708 printers, the following are also defaults:

**ibm71lpi:standard.enhtoner**  
**ibm71lpi:highlight-midtones.enhtoner**  
**ibm71lpi:dark.enhtoner**  
**ibm85lpi:standard.enhtoner**  
**ibm85lpi:highlight-midtones.enhtoner**  
**ibm85lpi:dark.enhtoner**  
**ibm106lpi:standard.enhtoner**  
**ibm106lpi:highlight-midtones.enhtoner**  
**ibm106lpi:dark.enhtoner**  
**ibm141lpi:standard.enhtoner**  
**ibm141lpi:highlight-midtones.enhtoner**  
**ibm141lpi:dark.enhtoner**

### Usage Guidelines

- Infoprint compares the document attribute **halftone** to this attribute for validation and scheduling.
- You can use this attribute to restrict the use of this actual destination.

## image-fit-supported

Specifies the methods of adjusting TIFF, GIF, and JPEG images to fit on the printed page that this actual destination supports.

### GUI Label

Image fit allowed

### DSS

PSF, Email, Fax, Infoprint 2000

### Type

Resettable, multi-valued

### Allowed Values

You can enter any of these fixed values:

**position-and-trim**  
**scale-to-fit**

### Default Value

No default value

### Usage Guidelines

Infoprint compares the document attribute **image-fit** to this attribute for validation and scheduling.

## image-length

Specifies the default length of a page of PostScript, PCL, TIFF, GIF, JPEG, or PDF data after it has been transformed for Infoprint printing or transmission.

### GUI Label

Finished page length (inches) or (mm)



**DSS**

PSF, Email, Fax, Infoprint 2000

**Type**

Resettable, single-valued

**Allowed Values**The value you specify is in the form *nnnn.nnnu**nnnn.nnn*

is a number that can optionally contain a decimal point.

*u* is the units in inches (**i**) or millimeters (**m**). If you do not specify a unit, the default unit is pels. You cannot use a decimal point when the unit is pels.

For 240-pel resolution printers, valid values are:

<b>16 - 8160</b>	pels
<b>0.065 - 34</b>	inches
<b>1.641 - 863.628</b>	millimeters

For 300-pel resolution printers, valid values are:

<b>16 - 10200</b>	pels
<b>0.052 - 34</b>	inches
<b>1.313 - 863.628</b>	millimeters

For 480-pel resolution printers, valid values are:

<b>16 - 16320</b>	pels
<b>0.065 - 34</b>	inches
<b>1.641 - 863.628</b>	millimeters

For 600-pel resolution printers, valid values are:

<b>16 - 20400</b>	pels
<b>0.052 - 34</b>	inches
<b>1.313 - 863.628</b>	millimeters

**Default Value**

No default value

**Usage Guidelines**

- This attribute is valid only for GIF, JPEG, PCL, PDF, PostScript, and TIFF documents.
- If a text margin is already built into the file, try **image-length=11i** to set the length to 11 inches.
- This attribute is used if you do not specify a value for the **image-length** document attribute or in the file specified by the **rip-ini-file** attribute.

**image-out-formats-supported**

Specifies the formats of image data, produced by the program that transforms line data to AFP data, that this actual destination supports.

**GUI Label**

Image out formats allowed

**DSS**

PSF, Infoprint 2000

## Actual Destination

### Type

Resettable, multi-valued

### Allowed Values

You can enter any of these fixed values:

**ioca-uncompressed**

**im1**

**io1**

**io1-g4**

**io1-mmr**

**asis**

### Default Values

**ioca-uncompressed, im1, io1, io1-g4, io1-mmr, asis**

### Usage Guidelines

Infoprint compares the document attribute **image-out-format** to this attribute for validation and scheduling. You should use the document attribute when you print line-data documents.

## image-width

Specifies the default width of a page of PostScript, PCL, TIFF, GIF, JPEG, or PDF data after it has been transformed for Infoprint printing or transmission.

### GUI Label

Finished page width (inches) or (mm)

### DSS

PSF, Fax, Email, Infoprint 2000

### Type

Resettable, single-valued

### Allowed Values

The value you specify is in the form *nnnn.nnnu*

*nnnn.nnn*

is a number that can optionally contain a decimal point.

*u* is the units in inches (**i**) or millimeters (**m**). If you do not specify a unit, the default unit is pels. You cannot use a decimal point when the unit is pels.

For 240-pel resolution printers, valid values are:

<b>16 - 8160</b>	pels
<b>0.065 - 34</b>	inches
<b>1.641 - 863.628</b>	millimeters

For 300-pel resolution printers, valid values are:

<b>16 - 10200</b>	pels
<b>0.052 - 34</b>	inches
<b>1.313 - 863.628</b>	millimeters

For 480-pel resolution printers, valid values are:

<b>16 - 16320</b>	pels
<b>0.065 - 34</b>	inches
<b>1.641 - 863.628</b>	millimeters

For 600-pel resolution printers, valid values are:

<b>16 - 20400</b>	pels
<b>0.052 - 34</b>	inches
<b>1.313 - 863.628</b>	millimeters

**Default Value**

No default value

**Usage Guidelines**

- This attribute is valid only for GIF, JPEG, PCL, PDF, PostScript, and TIFF documents.
- If a text margin is already built into the file, try **image-width=8.5i** to set the length to 8.5 inches.
- This attribute is used if you do not specify a value for the **image-width** document attribute or in the file specified by the **rip-ini-file** attribute.

**input-data-user-exit**

Specifies the name of a program that monitors input data to this actual destination. For example, if a certain document format is printed on special media, the input data exit program can issue a message requesting the operator to change the paper whenever a job in that format is submitted.

**GUI Label**

Input data exit

**DSS**

PSF, Email, Fax, Infoprint 2000

**Type**

Resettable, single-valued

**Allowed Values**

You can enter a text string of up to 255 characters.

**Default Value**

No default value

**Usage Guidelines**

You can use the sample input data exit program supplied:

- With Infoprint:
  - For AIX, **/usr/lpp/psf/bin/ainuxind** (source **/usr/lpp/psf/exits/ainuxind.c**)
  - For Windows NT and Windows 2000, **\install\_path\bin\ainuxind** (source **\install\_path\exits\ainuxind.c**), where *install\_path* indicates the path where you installed Infoprint Manager
- Write your own

For more information on user-exit programs for Infoprint Manager, visit the appropriate site from the IBM Printing Systems web site:  
<http://www.ibm.com/printers>.

**input-trays-medium**

Identifies which input medium is in which printer tray.

**GUI Label**

Media ready

## Actual Destination

### DSS

AIX

### Type

Resettable, multi-valued, complex

### Syntax

*tray-identification:medium-identifier*

Separate each pair of values with a colon, for example:

*tray-1:A4-colored*

### Components

**tray-identification:** Identifies the type of input tray.

*GUI Label:* Input tray

*Type:* Single-valued

*Allowed Values:* You can enter one of these fixed values:

<b>auto-envelope-feed</b>	<b>manual-envelope-feed</b>
<b>automatic-tray</b>	<b>middle</b>
<b>auxiliary-envelope</b>	<b>top</b>
<b>auxiliary-paper</b>	<b>tray-1</b>
<b>bottom</b>	<b>tray-2</b>
<b>continuous-form-feed</b>	<b>tray-3</b>
<b>current-selected-tray</b>	<b>tray-4</b>
<b>envelope</b>	<b>tray-5</b>
<b>large-capacity</b>	<b>capacity-2000-sheet</b>
<b>manual</b>	

*Default Value:* If Simple Network Management Protocol (SNMP) communication is active, Infoprint queries the printer device and sets the value according to the response; otherwise **tray-1**. However, if you specify a value for **input-tray**, you deactivate the SNMP default.

**medium-name:** Identifies the medium in the input tray.

*GUI Label:* Media ready

*Type:* Single-valued

*Allowed Values:* You can enter a text string up to 255 characters long that contains the name of the medium or one of the fixed values of the **medium-identifier** attributes of the default media. See the medium attribute **medium-identifier** for a list of these values.

*Default Value:* If Simple Network Management Protocol (SNMP) communication is active, Infoprint queries the printer device and sets the values according to the response; otherwise **letter**. However, if you specify a value for **medium-identifier**, you deactivate the SNMP default.

### Usage Guidelines

- Infoprint automatically sets the values for the **input-trays-supported** and **media-ready** attributes from the values of this attribute.

- Infoprint verifies that the values of the *medium-name* component of this attribute are values of the **media-supported** attribute.

## input-trays-supported

Identifies the types of input trays, such as top or envelope, supported on the printer device.

### GUI Label

Input trays allowed

### DSS

AIX, BSD, PSF, Fax, Email, 3170

### Type

Non-settable (AIX and PSF) or resettable (BSD), multi-valued

### Allowed Values

- AIX** Infoprint sets the values for this attribute based on the values of the **input-trays-medium** attribute.
- BSD** You can enter any names that describe input trays.
- PSF** Infoprint sets the values for this attribute based on the values of the **psf-tray-characteristics** attribute.

### Default Values

- AIX** The value of the **input-trays-medium** attribute
- BSD** No default value
- PSF** The value of the **psf-tray-characteristics** attribute

### Usage Guidelines

- Infoprint uses this attribute for job validation and scheduling:
  - AIX** Infoprint compares the document attribute **default-input-tray** to this attribute.
  - BSD** This attribute is for information only.
  - PSF** Infoprint compares the document attribute **default-input-tray** or **input-tray-select** to this attribute.
- You can use this attribute to restrict use of this actual destination.

## intervention-timer

Specifies the maximum amount of time, in seconds, that Infoprint waits before it treats an intervention-required condition at the output device as a permanent error.

### GUI Label

Intervention timer (sec)

### DSS

PSF

### Type

Resettable, single-valued

### Allowed Values

You can enter a value of 1 through 9999. The unit is seconds.

## Actual Destination

### Default Value

9999

### Usage Guidelines

A value of **9999** specifies that a permanent error condition can never occur.

## job-attributes-supported

Identifies the job attributes that this actual destination supports.

### DSS

All

### Type

Non-settable, multi-valued

### Allowed Values

Infoprint sets a text string that contains a list of job attributes that this actual destination supports.

**Note:** This list includes only job attributes that directly affect the actual destination. Jobs with attributes that affect the server, for example, **job-retention-period**, can be printed even though those attributes are not on this list.

### Default Values

**AIX** auxiliary-sheet-selection, job-batch, job-start-wait

**BSD** job-batch, job-start-wait

**PSF** auxiliary-sheet-selection, current-page-printing, delete-segment-list, formatted-job-ticket-content, job-batch, job-finishing, job-rip-action, job-start-wait, media-sheets-completed, optimize-for-multiple-copies, segment-list-file-name

**3170** formatted-job-ticket-content

**Email** delete-segment-list, formatted-job-ticket-content, job-batch, job-rip-action, job-ripped-by-server, job-start-wait, media-sheets-completed, segment-list-file-name

**Fax** delete-segment-list, formatted-job-ticket-content, job-rip-action, job-start-wait, media-sheets-completed, segment-list-file-name

### Infoprint 2000

auxiliary-sheet-selection, delete-segment-list, formatted-job-ticket-content, job-finishing, job-rip-action, job-ripped-by-server, media-sheets-completed, segment-list-file-name

### Passthrough

auxiliary-sheet-selection, job-batch, job-start-wait

**IPP** auxiliary-sheet-selection, job-batch, job-start-wait

## job-batches-ready

Specifies which job-batch values can currently print to this actual destination.

### GUI Label

Job batches ready

### DSS

All

**Type**

Resettable, multi-valued

**Allowed Values**

You can enter a text string up to 4095 characters long, for each value, that contains the job-batch name.

**Default Values**

No default values

**Usage Guidelines**

Infoprint compares the value of the job attribute **job-batch** to this attribute during job scheduling.

**job-finishings-supported**

Identifies the job finishing options that this actual destination supports.

**GUI Label**

Finishing options allowed

**DSS**

PSF, Infoprint 2000

**Type**

Resettable, multi-valued

**Allowed Values**

You can enter any of these fixed values for PSF-supported printers:

**edge-stitch**  
**edge-stitch-2**  
**edge-stitch-3**  
**saddle-stitch**  
**staple-bottom-left**  
**staple-top-left**

You can enter any of these fixed values for the Infoprint 2000:

**edge-stitch-2**  
**staple-bottom-left**  
**staple-top-left**  
**booklet-stitch-and-fold**  
**booklet-stitch-fold-and-trim**

**Default Values**

No default values

**Usage Guidelines**

- Infoprint compares the job attribute **job-finishing** to this attribute for validation and scheduling.
- You can use this attribute to restrict use of this actual destination.

**job-retry-count-limit**

Indicates the number of times that Infoprint should attempt to submit a job to this actual destination after an initial failure.

**GUI Label**

Number of times to retry jobs

## Actual Destination

### DSS

AIX, BSD, PSF, Fax, Passthrough, IPP

### Type

Resettable, single-valued

### Allowed Values

You can enter an integer from 0 through 2147483647.

### Default Value

0

### Usage Guidelines

- Values greater than **0** are useful when poor network line quality causes temporary loss of communication between this actual destination and the backend program. A second or subsequent attempt to submit the job may succeed if communication can be reestablished.
- If the job cannot be submitted within the specified number of attempts, Infoprint disables the destination and places it in the **needs-key-operator** state.
- The **job-retry-interval** actual destination attribute indicates the number of seconds between attempts.
- If the value of this attribute is **0**, the **job-retry-interval** attribute is ignored.
- If the value of the **job-retry-interval** attribute is **0**, this attribute is ignored.

## job-retry-interval

Indicates the number of seconds that Infoprint should wait between attempts to submit a job to this actual destination.

### GUI Label

Interval to retry jobs (sec)

### DSS

AIX, BSD, PSF, Passthrough, IPP

### Type

Resettable, single-valued

### Allowed Values

You can enter an integer from 0 through 2147483647.

### Default Value

0

### Usage Guidelines

- If the job cannot be submitted within the specified number of attempts, Infoprint disables the destination and places it in the **needs-key-operator** state.
- The **job-retry-count-limit** actual destination attribute indicates the number of attempts after an initial failure.
- If the value of this attribute is **0**, the **job-retry-count-limit** attribute is ignored.
- If the value of the **job-retry-count-limit** attribute is **0**, this attribute is ignored.

## job-rip-actions-supported

Indicates whether this actual destination supports converting a PostScript job to raster image patterns and holding the job, printing the job, or neither.



**GUI Label**

RIP options allowed

**DSS**

PSF, Email, Fax, Infoprint 2000

**Type**

Resettable, multi-valued

**Allowed Values**

You can enter any of these fixed values:

**rip-and-hold**  
**rip-and-hold-ignore-ready**  
**rip-and-print**  
**rip-and-print-ignore-ready**  
**rip-only**  
**rip-only-ignore-ready**

**Default Value**

**rip-and-hold, rip-and-hold-ignore-ready, rip-and-print, rip-and-print-ignore-ready, rip-only, rip-only-ignore-ready**

**Usage Guidelines**

Infoprint compares the job attribute **job-rip-action** to this attribute for validation and scheduling.

**job-size-range-ready**

Defines the range of job sizes in bytes (octets) that this actual destination can accept and print.

**GUI Label**

Size ready (Bytes)

**DSS**

All

**Type**

Resettable, single-valued, complex

**Syntax**

*lower-limit:upper-limit*

Separate the values with a colon, for example:

1025:1000000

You can omit either value, for example:

1025:  
:1000000

**Components**

**lower-limit:** Identifies the lower limit value of the job size. The unit value is octets (bytes).

**GUI Label:** Lower limit

**Type:** Single-valued

## Actual Destination

*Allowed Values:* You can enter an integer from 0 to 9223372036854775800. The lower limit must be less than or equal to the upper limit.

*Default Value:* **0**

**upper-limit:** Identifies the upper limit value of the job size. The unit value is octets (bytes).

*GUI Label:* Upper limit

*Type:* Single-valued

*Allowed Values:* You can enter an integer from 0 to 9223372036854775800. The upper limit must be greater than or equal to the lower limit.

*Default Value:* **9223372036854775800**

### Usage Guidelines

- You can use this attribute to restrict jobs sent to this actual destination according to the capacity of the output device or your policy for output device use.
- You must set the range for this attribute within the range of the **job-size-range-supported** value.
- Infoprint compares the job attribute **total-job-octets** to this attribute for scheduling.

## job-size-range-supported

Defines the range of job sizes in bytes (octets) that this actual destination can accept.

### GUI Label

Size allowed (Bytes)

### DSS

All

### Type

Resettable, single-valued, complex

### Syntax

*lower-limit:upper-limit*

Separate the values with a colon, for example:

1025:1000000

You can omit either value, for example:

1025:  
:1000000

### Components

**lower-limit:** Identifies the lower limit value of the job size. The unit value is octets (bytes).

*GUI Label:* Lower limit

*Type:* Single-valued

## Actual Destination

*Allowed Values:* You can enter an integer from 0 to 9223372036854775800. The lower limit must be less than or equal to the upper limit.

*Default Value:* **0**

**upper-limit:** Identifies the upper limit value of the job size. The unit value is octets (bytes).

*GUI Label:* Upper limit

*Type:* Single-valued

*Allowed Values:* You can enter an integer from 0 to 9223372036854775800. The upper limit must be greater than or equal to the lower limit.

*Default Value:* **9223372036854775800**

### Usage Guidelines

- You can use this attribute to restrict jobs sent to this actual destination according to the capacity of the output device or your policy for output device use.
- You must set the range for this attribute equal to or greater than the range you specify for the **job-size-range-ready** attribute value.
- Infoprint compares the job attribute **total-job-octets** to this attribute for validation and scheduling.

## job-start-wait-supported

Indicates whether job submitters are allowed to set the **job-start-wait** job attribute to pause the actual destination just before the job prints.

### GUI Label

Wait to start job allowed

### DSS

All

### Type

Resettable, single-valued

### Allowed Values

You can enter one of these fixed values:

<i>Fixed Value</i>	<i>Input Synonym</i>
true	yes
false	no

### Default Value

false

### Usage Guidelines

Infoprint compares the job attribute **job-start-wait** to this attribute for validation and scheduling.

## list-of-managers

Identifies the people responsible for the configuration of this actual destination and maintenance of the output device associated with this actual destination.

## Actual Destination

### GUI Label

Managers

### DSS

All

### Type

Resettable, multi-valued

### Input Synonym

You can use the synonym **managers**.

### Allowed Values

You can enter a text string up to 255 characters long, for each value, that contains such things as the name, user ID, office number, or telephone number of the person responsible for this actual destination and the output device associated with it.

### Default Values

No default values

### Usage Guidelines

This attribute is useful if a user needs to contact someone to report a problem or to request a change.

## locations

See **destination-locations**.

## log-accounting-data

Defines whether the accounting log is active for this actual destination. If you set the value to the default by using the == operator, the value of the server attribute **log-accounting-data** is used.

### GUI Label

Log accounting data

### DSS

All

### Type

Resettable, single-valued

### Allowed Values

You can enter one of these fixed values:

<i>Fixed Value</i>	<i>Input Synonym</i>
<b>true</b>	<b>yes</b>
<b>false</b>	<b>no</b>

**Note:** The accounting logs are stored in an Infoprint Server directory called **accounting.logs**.

### Default Value

No default value

### Usage Guidelines

You can use this attribute to activate or deactivate the accounting log for this actual destination.

**Note:** The accounting log contains the following job attributes and values for each job processed for this actual destination:

**actual destination name** (up to 255 characters)

**job owner** (up to 255 characters)

**global job-id** without *ServerName*

**submission-time** (GMT format)

**submission-time** (date in server's displayable locale and time zone)

**submission-time** (time in server's displayable locale and time zone)

**completion-time** (GMT format)

**completion-time** (date in server's displayable locale and time zone)

**completion-time** (time in server's displayable locale and time zone)

**pages-completed**

**octets-completed**

**data stream** (first document only)

**job name** (up to 255 characters)

### logical-destinations-assigned

Indicates the logical destination through which submissions to this actual destination are forwarded.

#### GUI Label

Logical destination assigned

#### DSS

All

#### Type

Resettable, single-valued

#### Allowed Values

You can enter a text string of up to 255 characters that contains the name of the logical destination.

#### Default Value

No default value

#### Usage Guidelines

The named logical destination must exist in the same Infoprint server as the actual destination.

When a job submission is received at an actual destination object with the **logical-destinations-assigned** set, the **actual-destinations-requested** attribute is set to the name of the actual destination that received the request, and then the job is submitted through the specified **logical-destinations-assigned**.

If **logical-destinations-assigned** is **not** set in the actual destination, the actual destination does not accept direct job submission requests, which are rejected with an unsupported error message.

### managers

See **list-of-managers**.

### maximum-concurrent-jobs

Defines an upper limit for the number of jobs that this actual destination can process at a time.

## Actual Destination

### GUI Label

Maximum concurrent jobs

### DSS

All

### Type

Resettable, single-valued

### Allowed Values

**AIX** You can enter an integer from 1 through 9.

**BSD** You can enter an integer from 1 through 9.

#### Infoprint 2000

You can enter an integer from 1 through 99.

**PSF** You can enter an integer from 1 through 99.

**Note:** When you are using a PSF other-driver attached actual destination, the maximum value is 2.

**3170** You can enter an integer from 1 through 99.

**Email** You can enter an integer from 1 through 99.

**Fax** You can enter an integer from 1 through 99.

#### Passthrough

You can enter an integer from 1 through 9.

**IPP** You can enter an integer from 1 through 9.

### Default Value

**AIX** 2

**BSD** 1

#### Infoprint 2000

12

#### PSF other-driver attached actual destinations

2

#### PSF command-attached actual destinations

1

#### Other PSF actual destinations

4

**3170** 4

**Email** 12

**Fax** 12

#### Passthrough

1

**IPP** 1

### Usage Guidelines

You can use this attribute to tune your Infoprint system to efficiently use your destination resources.

## maximum-copies-supported

Indicates the number of document copies, in a single job, that this actual destination allows.

### GUI Label

Maximum copies allowed

### DSS

All

**Type**

Resettable, single-valued

**Allowed Values**

You can enter an integer from 1 through 2147483647.

**Default Value**

2147483647

**Usage Guidelines**

- You can use this attribute to restrict jobs sent to this actual destination according to the capacity of the output device or your policy for output device use.
- Infoprint compares the document attribute **copy-count** to this attribute for scheduling.

**maximum-fonts-to-keep**

Specifies the maximum number of fonts to keep in the memory of the printer device between jobs.

**GUI Label**

Maximum fonts to keep

**DSS**

PSF

**Type**

Resettable, single-valued

**Allowed Values**

You can enter an integer from 0 through 999.

**Default Value**

10

**Usage Guidelines**

- Fonts are a single size and typeface in a particular type family, including letters, numerals, punctuation marks, special characters, and ligatures.
- If you specify that the printer device can store fonts in its memory between jobs, the printer will not have to download the same fonts for the next job. However, this requires additional printer memory.

**maximum-overlays-to-keep**

Specifies the maximum number of overlays to keep in the memory of the printer device between jobs.

**GUI Label**

Maximum overlays to keep

**DSS**

PSF

**Type**

Resettable, single-valued

**Allowed Values**

You can enter an integer from 0 through 999.

## Actual Destination

### Default Value

0

### Usage Guidelines

- Overlays are collections of predefined data such as lines, shading, test boxes, and logos that the printer device can merge with variable data on a page or a form.
- If you specify that the printer device can store overlays in its memory between jobs, the printer will not have to download the same overlays for the next job. However, this requires additional printer memory.

## maximum-segments-to-keep

Specifies the maximum number of page segments to keep in the memory of the printer device between jobs.

### GUI Label

Maximum segments to keep

### DSS

PSF

### Type

Resettable, single-valued

### Allowed Values

You can enter an integer from 0 through 999.

### Default Value

0

### Usage Guidelines

- Page segments contain text and images that the printer device can include at any addressable point on a page or an electronic overlay.
- If you specify that the printer device can store page segments in its memory between jobs, the printer will not have to download the same page segments for the next job. However, this requires additional printer memory.

## media-ready

Identifies the media now loaded in the printer device.

### GUI Label

Media ready

### DSS

AIX, BSD, PSF, 3170, Infoprint 2000, IPP, Passthrough

### Type

Non-settable (AIX and PSF) or resettable (BSD, 3170, IPP, and Passthrough), multi-valued

### Allowed Values

**AIX** Infoprint sets the values for this attribute based on the values of the **input-trays-medium** attribute.

**BSD** You can enter any values of the **media-supported** attribute.



**PSF, Infoprint 2000**

Infoprint sets the values for this attribute based on the values of the **psf-tray-characteristics** attribute.

**3170** Infoprint sets the values for this attribute based on the values of the **media-supported** attribute.

**IPP and Passthrough**

You can enter any values of the **media-supported** attribute.

**Default Values**

For AIX, BSD, PSF actual destinations, Passthrough, and IPP, if SNMP communication is active, Infoprint queries the printer device and sets the values according to the response; otherwise:

**AIX** The default comes from the values of the **input-trays-medium** attribute.

**BSD** No default value

**PSF, Infoprint 2000**

The default comes from the values of the **psf-tray-characteristics** attribute.

**3170** The values of the **media-supported** attribute.

**IPP** The default value comes from IPP.

**Passthrough**

There is no default.

**Usage Guidelines**

- Infoprint restricts the possible values for this attribute to the values currently specified for the **media-supported** attribute.
- Infoprint compares the document attribute **default-medium** to this attribute for job scheduling.
- If you specify a value for the **media-ready** attribute, you deactivate the default provided by SNMP.

**media-supported**

Identifies the types of media that the actual destination supports.

**GUI Label**

Media allowed

**DSS**

AIX, BSD, PSF, 3170, Infoprint 2000, IPP, Passthrough

**Type**

Resettable, multi-valued

**Allowed Values**

You can enter a text string up to 255 characters long that contains the names of the media. These can be:

- The medium identifiers of medium objects created by the **pdcrmed** utility. For these fixed values, see the medium **medium-identifier** attribute.
- The medium identifiers of medium objects you created yourself
- For PSF actual destinations, IPP printers, Passthrough printers, and BSD actual destinations, any names that describe the media, even if no medium objects with those names exist
- For Infoprint 2000 actual destinations, IPP printers, and Passthrough printers, medium objects must exist for all the names that you created for the Infoprint 2000 printers.

## Actual Destination

### Default Values

For AIX, BSD, PSF, IPP, and Passthrough actual destinations, if SNMP communication is active, Infoprint queries the printer device and sets the values according to the response; otherwise:

**AIX** letter

**BSD** No default values

**PSF, Infoprint 2000 (basic Infoprint administrator's GUI)**

All allowed fixed values

**PSF, Infoprint 2000 (advanced Infoprint administrator's GUI and command line)**

**Command-attached actual destinations**

letter

**other-driver attached actual destinations**

letter

**Other actual destinations**

No default values

**3170** The names of all default medium objects

**IPP** With Internet Printing Protocol (IPP) printers, the default comes from IPP.

**Passthrough**

There is no default.

### Usage Guidelines

- Infoprint uses this attribute for job validation:
  - AIX** Infoprint compares the document attribute **default-medium** to this attribute for job validation and scheduling.
  - BSD** This attribute is for information only.
  - PSF** Infoprint compares the document attribute **default-medium** or **page-media-select** to this attribute for job validation and scheduling.
  - 3170** Infoprint compares the document attribute **default-medium** to this attribute for job validation and scheduling.
- For AIX actual destinations, Infoprint verifies that the values of the *medium-identifier* component of the **input-trays-medium** attribute are values of this attribute.
- For PSF and Infoprint 2000 actual destinations, Infoprint verifies that the values of the *medium-loaded* component of the **psf-tray-characteristics** attribute are values of this attribute.
- The actual destination does not automatically update this attribute. When you create a medium object, you must add its medium identifier to each actual destination that supports it.
- You can use this attribute to restrict use of this actual destination.
- If you specify a value for the **media-supported** attribute, you deactivate the default provided by SNMP.

## message

Provides information associated with this actual destination.

### GUI Label

Message

### DSS

All

**Type**

Resettable, single-valued

**Allowed Values**

You can enter a text string up to 4095 characters long that contains information about this actual destination.

**Default Value**

No default value

**Usage Guidelines**

Use of this descriptive attribute is optional.

**message-font-type**

Identifies the font type that the printer device uses to print the message page.

**GUI Label**

Message page font type

**DSS**

PSF

**Type**

Resettable, single-valued

**Allowed Values**

You can enter one of these fixed values:

**normal**

**condensed**

**Default Value**

**normal**

**message-form-definition**

Identifies the AFP form definition that the printer device uses to process the message page.

**GUI Label**

Message page form definition

**DSS**

PSF

**Type**

Resettable, single-valued

**Allowed Values**

A text string up to 255 characters long that contains the form definition ID.

**Default Value**

**F1MG0110**

**model**

See **destination-model**.

## Actual Destination

### non-process-runout-timer

Designates the amount of time, in seconds, that a continuous-forms printer device waits for the next job before it runs the forms from the print transfer station to the stacker after the last page of a job prints.

#### GUI Label

Non-process runout timer (sec)

#### DSS

PSF

#### Type

Resettable, single-valued

#### Allowed Values

You can enter an integer from 0 through 9999. The unit is seconds.

#### Default Value

60

#### Usage Guidelines

If you enter a value of **0**, Infoprint does not allow the timer to expire.

### notification-profile

Designates which users Infoprint notifies of specified events related to this actual destination, and how Infoprint notifies them.

#### GUI Label

Notification profile

#### DSS

All

#### Type

Resettable, multi-valued, complex

#### Syntax

```
-x "notification-profile={event-identifiers=event ...  
    delivery-address=name@node delivery-method=value  
    event-comment='some text' locale=locale}"
```

You can omit any of these components, for example:

```
-x "notification-profile={event-identifiers=class-actual-destination-status  
    class-warning delivery-address=jeff@ttank  
    event-comment='Its still going' locale=En_US.IBM-850}"
```

#### Components

**event-identifiers:** Specifies the events for which the user receives messages.

**GUI Label:** Events

**Type:** Multi-valued

**Allowed Values:** You can enter any of the values listed for the server attribute **events-supported**.

## Actual Destination

**Default Values:** **object-deleted, object-cleaned, printer-needs-administrator, printer-needs-attention, printer-needs-operator, printer-timed-out**

**delivery-address:** Provides the address of the person who receives the event messages or the directory location and file name where Infoprint stores the message.

*GUI Label:* Address

*Type:* Single-valued

*Allowed Values:* You can enter a text string up to 255 characters long that contains the user name and node or the directory and file name.

*Default Value:* The login ID of the user who created this actual destination.

**delivery-method:** Specifies how the user or file receives event messages.

*GUI Label:* Method

*Type:* Single-valued

*Allowed Values:* You can enter one of these fixed values:

<b>Fixed Value</b>	<b>Input Synonym</b>
<b>electronic-mail</b>	<b>e-mail, email</b>
<b>file</b>	
<b>file-add-to</b>	
<b>message</b>	
<b>none</b>	

*Default Value:* **message**

*Usage Guidelines:* If you specify a value of **file** or **file-add-to**, you must specify a value for the **delivery-address** component.

**event-comment:** Supplies textual information that Infoprint appends to the event message.

*GUI Label:* Comment

*Type:* Single-valued

*Allowed Values:* You can enter a text string up to 4095 characters long that contains the comment.

*Default Value:* No default value

**locale:** Defines the language and code page of notification messages.

*Type:* Single-valued

*Allowed Values:* You can enter the name of any locale for which the Infoprint messages in the corresponding language are installed.

*Default Value:* The locale of the person who created this actual destination.

## Actual Destination

### notify-operator

Identifies people who are to receive the messages specified by the job attributes **job-start-message** and **job-end-message**.

#### GUI Label

Operators to notify

#### DSS

All

#### Type

Resettable, multi-valued, complex

#### Input Synonym

You can use the synonym **operators**.

#### Syntax

*delivery-method:delivery-address*

Separate each pair of values with a colon, for example:

message:op2@phyptr1

#### Components

**delivery-method:** Specifies how the person receives the messages.

*GUI Label:* Method

*Type:* Single-valued

*Allowed Values:* You can enter one of these fixed values:

**electronic-mail  
message  
none**

*Default Value:* **message**

**delivery-address:** Provides the address of the person to receive the messages.

*GUI Label:* Address

*Type:* Single-valued

*Allowed Values:* Enter a login ID and node.

*Default Value:* The login ID of the person who created this actual destination.

### number-up-supported

Specifies the number of pages that this actual destination can print on a single side of the paper.

#### GUI Label

Number up allowed

#### DSS

PSF, Email, Fax, Infoprint 2000

**Type**

Resettable, multi-valued

**Allowed Values**

You can enter any of these fixed values:

<i>Fixed Value</i>	<i>Input Synonym</i>
<b>imposition-simple-1-up</b>	<b>1up</b>
<b>imposition-simple-2-up</b>	<b>2up</b>
<b>imposition-simple-3-up</b>	<b>3up</b>
<b>imposition-simple-4-up</b>	<b>4up</b>
<b>generic-none</b>	

**Default Values**

**imposition-simple-1-up, imposition-simple-2-up, imposition-simple-3-up, imposition-simple-4-up, generic-none**

**Usage Guidelines**

- The value **generic-none** applies only to the actual destination. You cannot request this value with the document attribute **number-up**.

When the values for **number-up-supported** include **generic-none**, the actual destination accepts documents without a value for the **number-up** attribute. The actual destination also accepts documents without a value for the **number-up** attribute when there are no values for **number-up-supported**.

- Infoprint compares the document attribute **number-up** to this attribute for validation and scheduling.
- You can use this attribute to restrict use of this actual destination.

**object-class**

Identifies the object class to which this object belongs.

**DSS**

All

**Type**

Non-settable, single-valued

**Allowed Values**

Infoprint sets this value to **destination**.

**Default Value**

**destination**

**offset-stacking-available**

Indicates whether PSF command-attached or other-driver attached actual destinations support offsetting jobs in the output stack.

**GUI Label**

Allow offset stacking

**DSS**

PSF

**Type**

Resettable, single-valued

## Actual Destination

### Allowed Values

You can enter one of these fixed values:

<i>Fixed Value</i>	<i>Input Synonym</i>
true	yes
false	no

### Default Value

false

### Usage Guidelines

- This attribute applies only to PSF command-attached and other-driver attached actual destinations. Other actual destinations ignore this attribute.
- Offset stacking occurs only if the form definition for the job specifies offset stacking.
- PPDS and PCL4 data streams do not support the offset stacking option; therefore, this attribute has no effect on destinations using those data streams.
- This attribute is not used for job validation or scheduling.

## operators

See **notify-operator**.

## optimize-for-multiple-copies

Used with the **optimize-for-multiple-copies** job attribute to indicate whether the printer device should save pages in order to print multiple copies of the job faster.

### GUI Label

Optimize for multiple copies

### DSS

PSF

### Type

Resettable, single-valued

### Allowed Values

You can enter one of these fixed values:

<i>Fixed Value</i>	<i>Input Synonym</i>
true	yes
false	no

### Default Value

**true** actual destinations representing Infoprint 4000 printer devices (**printer-model=Infoprint4000**) that are migrated from PSF for AIX or created using the Infoprint administrator's GUI

**false** All other actual destinations

### Usage Guidelines

- This attribute is used in combination with the **optimize-for-multiple-copies** job attribute:

<i>Job Attribute</i>	<i>Destination Attribute</i>	<i>Results</i>
true	true	Pages are saved
true	false	Pages are not saved
false	true	Pages are not saved



## Actual Destination

<i>Job Attribute</i>	<i>Destination Attribute</i>	<i>Results</i>
<b>false</b>	<b>false</b>	Pages are not saved
No value	<b>true</b>	Pages are saved
No value	<b>false</b>	Pages are not saved

- If the printer device cannot save pages, the job is printed and this attribute is ignored.

## orientations-supported

See **content-orientations-supported**.

## other-options

See **destination-pass-through**.

## output-appearances-supported

Identifies the values for the document attribute **output-appearance** that this actual destination supports.

### DSS

PSF (AIX Only)

### Type

Resettable, multi-valued

### Allowed Values

You can enter a customized value or any of these fixed values:

**standard**  
**highlight-midtones**  
**dark**

### Default Values

**standard, highlight-midtones, dark**

### Usage Guidelines

- Infoprint compares the document attribute **output-appearance** to this attribute for validation and scheduling.
- You can use this attribute to restrict use of this actual destination.

## output-bin

Specifies the name of the output bin to which you want Infoprint to direct output.

### GUI Label

Default output bin

### DSS

PSF, Infoprint 2000

### Type

Resettable, single-valued

### Allowed Values

You can enter a text string up to 255 characters long that contains the output bin name.

## Actual Destination

### Default Value

**PSF** No default values

**3170** main, test

**Infoprint 2000**  
stapler

### Usage Guidelines

- The name you specify must match the name in one of the values for the following attribute:

**PSF** output-bin-numbers

**Infoprint 2000**  
output-bins-supported

- Infoprint only uses the value you specify for the **output-bin** actual destination attribute if the user does not specify a value for the **output-bin** document attribute and if the form definition Infoprint uses for the job does not specify an output bin.
- With Infoprint 2000:
  - If a job requests stapling or some other finishing, the job goes to the appropriate finishing output bin regardless of what output bin is specified with the **output-bin** attribute.
  - If a job specifies a finishing output bin and no finishing is specified, the job is printed and sent to the top bin.

## output-bin-numbers

Specifies a bin name followed by a bin number. Infoprint uses this attribute to map names of output bins, such as top, to bin numbers that the printer device understands.

### GUI Label

Map output bin to number

### DSS

PSF

### Type

Resettable, multi-valued, complex

### Syntax

*bin-name:bin-number*

Separate each pair of values with a colon, for example:

```
top:1  
staple:2
```

### Components

***bin-name:*** The name of an output bin.

***GUI Label:*** Bin name

***Type:*** Single-valued

***Allowed Values:*** You can enter a text string containing a bin name.

**bin-number:** The number that the printer device has assigned to the output bin.

**GUI Label:** Bin number

**Type:** Single-valued

**Allowed Values:** You can enter a numeric value.

### Default Values

If SNMP communication is active, Infoprint queries the printer device and sets the values according to the response; otherwise no default value.

### Usage Guidelines

- Infoprint automatically updates the **output-bins-supported** actual destination attribute from the value or values that you set for this attribute.
- If you set the **output-bins-numbers** attribute, you deactivate the default provided by SNMP.

## output-bins-supported

Identifies the supported output bins on the printer device.

### GUI Label

Output bins allowed

### DSS

PSF, 3170, Infoprint 2000

### Type

Resettable, multi-valued

### Allowed Values

**PSF** Infoprint sets this value from the values you supply for the **output-bin-numbers** actual destination attribute. If you add or delete a value from the **output-bin-numbers** attribute, Infoprint modifies this attribute to match your change.

**3170** Infoprint sets this value to the names of the output bins on the InfoColor 70 printer device.

### Infoprint 2000

**top, stapler, stacker, bookletmaker**

### Default Values

**PSF** No default values

**3170** **main, test**

### Infoprint 2000

**top, stapler**

### Usage Guidelines

- Infoprint compares the value of the **output-bin** document attribute to this attribute during job validation and scheduling.
- You can use this attribute to restrict the use of this actual destination.

## Actual Destination

### output-data-user-exit

Specifies the name of a program that monitors output data from this actual destination. For example, the output data exit program can print a report at the end of a job listing the start and end time and the number of fonts, page segments, and overlays in the job so that you can track output device performance.

#### GUI Label

Output data exit

#### DSS

PSF, Email, Fax, Infoprint 2000

#### Type

Resettable, single-valued

#### Allowed Values

You can enter a text string of up to 255 characters.

#### Default Value

No default value

#### Usage Guidelines

You can use the sample output data exit program supplied:

- With Infoprint:
  - With AIX, `/usr/lpp/psf/bin/ainuxout` (source `/usr/lpp/psf/exits/ainuxout.c`)
  - With Windows NT or Windows 2000, `\install_path\bin\ainuxout` (source `\install_path\usr\lpp\psf\exits\ainuxout.c`), where `install_path` indicates the path where you installed Infoprint Manager
  -
- Write your own

For more information on user-exit programs for Infoprint Manager, visit the appropriate site from the IBM Printing Systems web site:  
<http://www.ibm.com/printers>.

### output-format-supported

Used with the **number-up-supported** attribute to identify the ways of imposing pages on a sheet that this actual destination supports.

#### GUI Label

Output formats allowed

#### DSS

PSF, Email, Fax, Infoprint 2000

#### Type

Resettable, multi-valued

#### Allowed Values

You can specify any of these fixed values:

**side-by-side-copies**  
**simple-n-up**  
**booklet-print**  
**slit-and-merge**

**Note:** You can only specify **simple-n-up** with the PSF DSS for Windows NT and Windows 2000.

**Default Value**  
**side-by-side-copies**  
**simple-n-up**  
**booklet-print,**  
**slit-and-merge**

**Note:** **simple-n-up** is the only default with the PSF DSS for Windows NT and Windows 2000.

### Usage Guidelines

- See the document attribute **output-format** for explanations of the attribute values.
- Infoprint compares the document attribute **output-format** to this attribute for validation and scheduling.
- You can use this attribute to restrict use of this actual destination.

## overlay

Specifies an overlay that Infoprint uses for each sheet-side for all jobs printed on this actual destination.

**GUI Label**  
Medium overlay

**DSS**  
PSF, Email, Fax, Infoprint 2000

**Type**  
Resettable, single-valued

**Allowed Values**  
You can enter a text string up to eight characters long that contains the name of the overlay.

**Default Value**  
No default value

### Usage Guidelines

- When you specify **overlay**, **overlay-front**, and **overlay-back** on the command line, Infoprint honors all of them as long as the **form-definition** document attribute is **not** specified.
- When you specify a value for the **form definition** document attribute, Infoprint ignores the overlay you specify with **overlay**.

## page-select-supported

Specifies the type of page numbering that this actual destination supports.

**GUI Label**  
Range of pages allowed

**DSS**  
PSF, Email, Fax, Infoprint 2000

## Actual Destination

### Type

Resettable, multi-valued

### Allowed Values

You can enter a fixed value of **numeric**.

### Default Value

**numeric**

### Usage Guidelines

Infoprint compares the document attribute **page-select** to this attribute for validation and scheduling.

## pcl-server-address

Identifies the Internet Protocol address (IP Address parameter) of the host where the daemon that transforms PCL data imbedded in an AFP data file resides.

### GUI Label

PCL server address

### DSS

PSF, Email, Fax, Infoprint 2000

### Type

Resettable, single-valued

### Allowed Values

You can enter a text string up to 4095 characters long that is either of these types of address:

#### Dotted decimal address

A series of integers within the range of 0 to 255, each separated by a period, . (decimal address). For example:

9.99.12.85

#### Hostname

For example:

leo.boulder.ibm.com

### Default Value

**127.0.0.1** (the local host)

### Usage Guidelines

This attribute is not used in transforming PCL data that is not imbedded in AFP data files.

## pcl-server-port

Identifies the Port Number parameter of the host where the daemon that transforms PCL data imbedded in an AFP data file resides.

### GUI Label

PCL server port

### DSS

PSF, Email, Fax, Infoprint 2000

### Type

Resettable, single-valued

**Allowed Values**

You can enter an integer from 1 through 2147483647, but you typically enter an integer from 5001 to 65535.

**Default Value**

8253

**Usage Guidelines**

This attribute is not used in transforming PCL data that is not imbedded in AFP data files.

**physical-printer**

See **destination-name**.

**plex**

Identifies the plexes that this printer prints. Plex indicates whether the page images of the output document are conditioned for eventual one-sided or two-sided printing, and the relative orientation of consecutive pages.

**GUI Label**

Plex to print

**DSS**

PSF, Infoprint 2000

**Type**

Resettable, single-valued

**Allowed Values**

You can enter one of these fixed values:

**simplex**  
**tumble**

**Default Values**

**AIX** **simplex**

**Infoprint 2000**

**simplex**

**PSF** **simplex**

**Usage Guidelines**

- The value of the **plex** attribute must be one of the values of the **plexes-supported** attribute.
- Infoprint uses plex specifications in this order:
  1. **plex** document attribute
  2. The plex specification in the form definition
  3. **plex** actual destination attribute

**Note:** Because all IBM-supplied form definitions contain a plex specification, the **plex** actual destination attribute is used only with custom form definitions that do not contain a plex specification.

**plexes-supported**

Identifies the plexes that this actual destination supports. Plex indicates whether the page images of the output document are conditioned for eventual one-sided or two-sided printing, and the relative orientation of consecutive pages.

## Actual Destination

### GUI Label

Plexes allowed

### DSS

AIX, BSD, PSF, 3170, Infoprint 2000

### Type

Resettable, multi-valued

### Allowed Values

You can enter any of these fixed values:

**simplex**  
**tumble**

### Default Values

**AIX**    **simplex**

**BSD**    No default value

### PSF (basic Infoprint administrator's GUI)

If SNMP communication is active, Infoprint queries the printer device and sets the values according to the response; otherwise **simplex, tumble**.

### PSF (advanced Infoprint administrator's GUI and command line)

If SNMP communication is active, Infoprint queries the printer device and sets the values according to the response; otherwise **simplex**.

**3170**    **simplex, tumble**

### Usage Guidelines

- Infoprint compares the document attribute **plex** to this attribute for scheduling.
- If you specify a value for the **plexes-supported** attribute, you deactivate the default provided by SNMP.

## postscript-server-address

Identifies the Internet Protocol address (IP Address parameter) of the host where the daemon that transforms PostScript data imbedded in an AFP data file resides.

### GUI Label

PostScript server address

### DSS

PSF, Email, Fax, Infoprint 2000

### Type

Resettable, single-valued

### Allowed Values

You can enter a text string up to 4095 characters long that is either of these types of address:

#### Dotted decimal address

A series of integers within the range of 0 to 255, each separated by a period, . (decimal address). For example:

9.99.12.85

#### Hostname

For example:

leo.boulder.ibm.com



**Default Value**

127.0.0.1 (the local host)

**Usage Guidelines**

This attribute is not used in transforming PostScript data that is not imbedded in AFP data files.

**postscript-server-port**

Identifies the Port Number parameter of the host where the daemon that transforms PostScript data imbedded in an AFP data file resides.

**GUI Label**

PostScript server port

**DSS**

PSF, Email, Fax, Infoprint 2000

**Type**

Resettable, single-valued

**Allowed Values**

You can enter an integer from 1 through 2147483647, but you typically enter an integer from 5001 to 65535.

**Default Value**

8251

**Usage Guidelines**

This attribute is not used in transforming PostScript data that is not imbedded in AFP data files.

**presentation-fidelity-problem-reported**

Identifies the types of errors that cause this actual destination to stop printing when Infoprint detects them.

**GUI Label**

Presentation fidelity problem reported

**DSS**

PSF

**Type**

Resettable, single-valued

**Allowed Values**

You can enter one of these fixed values:

**Fixed Value****Explanation****barcode**

Infoprint stops printing the file when it detects an error in bar code data in the Bar Code Object Content Architecture (BCOCA) data stream, or if the printer device does not support BCOCA.

**image**

Infoprint stops printing the file when it detects an error in image or graphics data in the Image Object Content Architecture (IOCA) or Graphics Object Content Architecture (GOCA) data streams, or if the printer device does not support IOCA or GOCA.

## Actual Destination

- all** Infoprint stops printing the file if it detects either barcode or image data problems.
- none** Infoprint prints the file without reporting barcode or image errors.

**Default Value**  
**none**

## print-edge-marks

Specifies whether this actual destination prints edge marks on the output.

**GUI Label**  
Print edge marks

**DSS**  
PSF

**Type**  
Resettable, single-valued

**Allowed Values**  
You can enter one of these fixed values:

<i>Fixed Value</i>	<i>Input Synonym</i>
<b>true</b>	<b>yes</b>
<b>false</b>	<b>no</b>

**Default Value**  
**false**

## print-qualities-supported

Identifies the levels of print quality available on this actual destination.

**GUI Label**  
Print qualities allowed

**DSS**  
AIX, BSD

**Type**  
Resettable, multi-valued

**Input Synonym**  
You can use the synonym **qualities-supported**.

**Allowed Values**  
You can enter any of these fixed values:  
**draft**  
**high**  
**normal**

**Default Values**  
**AIX** **normal**  
**BSD** No default value

### Usage Guidelines

- Infoprint compares the document attribute **print-quality** to this attribute for validation and scheduling.
- You can use this attribute to restrict use of this actual destination.

**print-queue**

See **print-queue-name**.

**print-queue-name**

Specifies which AIX print queue is the default value for the **destination-command** attribute.

**GUI Label**

AIX print queue (AIX DSS)  
Windows print queue (Passthrough DSS)

**DSS**

PSF

**Type**

Initially settable, single-valued

**Input Synonym**

You can use the synonym **print-queue**.

**Allowed Values**

You can enter a text string up to 255 characters long that contains the name of the AIX print queue.

**Default Value**

No default value

**Usage Guidelines**

- Do not confuse this attribute with the **associated-queue** attribute, which specifies the Infoprint queue that sends jobs to this actual destination.
- If the attachment-type is **aix**, Infoprint uses this attribute to determine the default value following the **-P** flag in the **destination-command** attribute.
- If the attachment type is not **aix**, Infoprint does not use the **print-queue-name** attribute.

**printer**

See **destination-name**.

**printer-command**

See **destination-command**.

**printer-data-stream**

See **destination-data-stream**.

**printer-end-sheet**

Identifies the style of end sheet that the printer device uses.

**GUI Label**

End sheet

**DSS**

AIX, PSF

## Actual Destination

### Type

Resettable, single-valued

### Allowed Values

You can enter one of the following fixed values. For PSF only, you can enter an identifier of an auxiliary-sheet object.

<i>Fixed Value</i>	<i>DSS</i>	<i>Explanation</i>
<b>accounting-log</b>	PSF	This value is technically valid, but should not be used for end sheets.
<b>blank</b>	PSF	The end sheet is blank.
<b>brief</b>	AIX, PSF	The end sheet style is brief.
<b>full</b>	AIX, PSF	The end sheet style is full.
<b>job-ticket</b>	PSF	The job ticket is printed on the end sheet.
<b>none</b>	AIX, PSF	No end sheet prints.

### Default Value

AIX full  
PSF none

### Usage Guidelines

- PSF actual destinations can use auxiliary-sheet objects if they have valid **psf-exit-xxx** values. AIX actual destinations print auxiliary sheets, but they do not use auxiliary-sheet objects.
- Infoprint verifies that the value of this attribute is a value of the **end-sheets-supported** attribute.

## printer-escape-codes

Specifies the printer escape codes that this actual destination uses to print line-data jobs.

### GUI Label

Escape codes

### DSS

PSF

### Type

Resettable, single-valued

### Allowed Values

You can enter a string up to 255 characters long containing the printer escape codes.

### Syntax

Escape codes must be in lowercase format and cannot include spaces. You must enter unprintable characters, and may enter printable characters, in this format:

`\xnn`

where *nn* is a two-character (one-byte) hexadecimal code. For example:

`\x1b`

represents ESC

### Default Value

No default value

**Usage Guidelines**

Use printer escape codes to control fonts, line spacing, and the size of the output page, enabling more than 80 characters to print on a line.

For example, this hex string:

```
\x1b\x5b\x53\x0c\x00\x01\x20\x01\x20\x00\x00\x4b\x60\x38\x40\x4e\xc0
```

translates to the following values:

<b>1b</b>	ESC
<b>5b</b>	Left square bracket
<b>53</b>	S
<b>0c00</b>	Length of command
<b>0120</b>	Top margin (0.2 inches)
<b>0120</b>	Bottom margin (0.2 inches)
<b>0000</b>	Left margin (0 inches)
<b>4b60</b>	Right margin (13.4 inches)
<b>3840</b>	Page length (10 inches)
<b>4ec0</b>	Page width (14 inches)

The first four values (ESC, [, S, command length) are always the same in a string of escape codes specifying page dimensions. The values representing the margins and page length and width are hex values in 1440ths of an inch and can be changed to meet your specifications. All dimensions are measured as if the page were printed in portrait.

**printer-memory**

Defines the amount of printer memory (in kilobytes) for this PSF command-attached or other-driver attached printer.

**GUI Label**

Memory (KBytes)

**DSS**

PSF

**Type**

Resettable, single-valued

**Allowed Values**

You can enter an integer from 512 to 65535. The unit is kilobytes.

**Default Value**

**Other-driver attached actual destinations**

1024

**Command-attached actual destinations**

1024

**Other-driver attached types**

No default value

**Usage Guidelines**

- Infoprint uses this attribute with PSFcommand-attached actual destinations and other-driver attached actual destinations and ignores it for other attachment types.
- If the printer device reports an out-of-memory condition, you can add more memory to the printer device or decrease the value for this attribute.

## Actual Destination

### printer-locations

See **destination-location**.

### printer-model

See **destination-model**.

### printer-name

See **destination-name**.

### printer-needs-attention-time

See **destination-needs-attention-time**.

### printer-needs-key-operator-attention-time

See **destination-needs-key-operator-attention-time**.

### printer-pass-through

See **destination-pass-through**.

### printer-realization

See **destination-realization**.

### printer-register-threshold

See **destination-register-threshold**.

### printer-release-timer

See **destination-release-timer**.

### printer-resolutions-ready

Specifies which of the values specified for the **printer-resolutions-supported** attribute this actual destination is ready to use.

#### GUI Label

Resolutions ready

#### DSS

PSF, 3170

#### Type

Resettable, multi-valued

#### Allowed Values

You can enter any of these fixed values:

<i>Fixed Value</i>	<i>DSS</i>
240	PSF
300	PSF
480	PSF
600	PSF, 3170

The unit is pels.

#### Default Values

No default values

### Usage Guidelines

- This attribute applies only for printing image data. It has no effect on font resolutions.
- Refer to the printer device documentation for information on the resolution you should specify.
- If you specify a resolution that the printer device does not support, jobs will still print under most conditions. However, you may see poor printed results.
- The values of the **printer-resolutions-ready** attribute must be a subset of the values of the **printer-resolutions-supported** attribute.
- Infoprint compares the document attribute **default-printer-resolution** to this attribute for scheduling.

## printer-resolutions-supported

Specifies the resolution, in pels, at which the printer device can print PostScript and PCL jobs.

### GUI Label

Resolutions allowed

### DSS

PSF, 3170, Infoprint 2000

### Type

Resettable, multi-valued

### Allowed Values

You can enter any of these fixed values:

<i>Fixed Value</i>	<i>DSS</i>
240	PSF
300	PSF
480	PSF
600	PSF, 3170, Infoprint 2000

The unit is pels.

### Default Values

**PSF (basic Infoprint administrator's GUI)**

240, 300, 480, 600

**PSF (advanced Infoprint administrator's GUI and command line)**

240

**3170, Infoprint 2000**

600

### Usage Guidelines

- This attribute applies only for printing image data. It has no effect on font resolutions.
- Refer to the printer device documentation for information on the resolution you should specify.
- If you specify a resolution that the printer device does not support, jobs will still print under most conditions. However, you may see poor printed results.
- Infoprint compares the document attribute **default-printer-resolution** to this attribute for validation and scheduling.
- You can use this attribute to restrict use of this actual destination.

## Actual Destination

### printer-separator-sheet

Identifies the style of separator sheet that the printer device uses.

#### GUI Label

Slip/Separator sheet

#### DSS

AIX, PSF

#### Type

Resettable, single-valued

#### Allowed Values

You can enter one of the following fixed values. For PSF only, you can enter an identifier of an auxiliary-sheet object.

<i>Fixed Value</i>	<i>DSS</i>	<i>Explanation</i>
<b>accounting-log</b>	PSF	This value is technically valid, but should not be used for separator sheets.
<b>blank</b>	PSF	The separator sheet is blank.
<b>brief</b>	PSF	The separator sheet style is brief.
<b>full</b>	PSF	The separator sheet style is full.
<b>job-ticket</b>	PSF	The job ticket is printed on the separator sheet.
<b>none</b>	AIX, PSF	No separator sheet prints.

#### Default Value

AIX **none**

PSF **none**

#### Usage Guidelines

- PSF actual destinations can use auxiliary-sheet objects if they have valid **psf-exit-xxx** values. AIX actual destinations print start and end sheets, but they do not use auxiliary-sheet objects.
- Because AIX actual destinations do not print separator sheets, the only valid value for them is **none**.
- Infoprint verifies that the value of this attribute is a value of the **separator-sheets-supported** attribute.

### printer-start-sheet

Identifies the type of start sheet that this printer device uses.

#### GUI Label

Start sheet

#### DSS

AIX, PSF, 3170, IPP, Passthrough

#### Type

Resettable, single-valued

#### Allowed Values

You can enter one of the following fixed values. For PSF only, you can enter an identifier of an auxiliary-sheet object.



<i>Fixed Value</i>	<i>DSS</i>	<i>Explanation</i>
<b>accounting-log</b>	PSF	This value is technically valid, but should not be used for start sheets.
<b>blank</b>	PSF	The start sheet is blank.
<b>brief</b>	AIX, PSF, IPP, Passthrough	The start sheet style is brief.
<b>full</b>	AIX, PSF, 3170, IPP, Passthrough	The start sheet style is full.
<b>job-ticket</b>	PSF	The job ticket is printed on the start sheet.
<b>none</b>	AIX, PSF, 3170, IPP, Passthrough	No start sheet prints.
<b>filename</b>	IPP, Passthrough	The location of a customized auxiliary sheet template.

### Default Value

AIX, 3170, IPP, Passthrough

full

PSF (basic Infoprint administrator's GUI)

job-ticket

PSF (advanced Infoprint administrator's GUI and command line)

brief

### Usage Guidelines

- PSF actual destinations can use auxiliary-sheet objects if they have valid **psf-exit-xxx** values. AIX actual destinations print start and end sheets, and 3170 actual destinations print start sheets; but they do not use auxiliary-sheet objects.
- Infoprint verifies that the value of this attribute is a value of the **start-sheets-supported** attribute.
- For IPP and Passthrough printers, the auxiliary sheets specified with *filename* can be customized by copying and modifying one of the following template files shipped with Infoprint Manager for Windows NT and Windows 2000:

*\install-path\bin\brief.ps*

Template for "brief" format, Postscript output format

*\install-path\bin\full.ps*

Template for "full" format, Postscript output format

*\install-path\bin\brief.txt*

Template for "brief" format, PCL/ASCII output format

*\install-path\bin\full.txt*

Template for "full" format, PCL/ASCII output format

The template files contain special *insert formatting* characters that are used to indicate where the Passthrough DSS inserts certain information about the print job:

**%B** Large *banner style* job-owner/job-original/user-name (whichever is found first)

**%t, %T**  
job-name heading, job-name contents

**%p, %P**  
time printed heading, time printed contents

**%q, %Q**  
job-submission-time heading, job-submission-time contents

## Actual Destination

### **%h, %H**

actual-destination and server heading, actual-destination and server contents

### **%s, %S**

job-owner/job-original/user-name heading, job-owner/job-originator/user-name contents

### **%d, %D**

results-profile delivery-address, %s heading, results-profile delivery-address, or %S contents

### **%c, %C**

job-comment heading, job-comment contents

## printer-state

See **destination-state**.

## printer-s370-channel-device-address

Identifies the control unit address parameter for channel-attached actual destinations. This is the device address of the control unit for the printer device.

### **GUI Label**

S/370 channel address

### **DSS**

PSF

### **Type**

Resettable, single-valued

### **Allowed Values**

You can enter a hexadecimal address expressed as a series of characters in the range: integer (0..9), alpha (a..f, A..F); legal values are 00–FF.

### **Default Value**

No default value

### **Usage Guidelines**

You must enter a value for PSF channel-attached actual destinations. Infoprint ignores this attribute for other attachment types.

## printer-s370-channel-slot-number

Identifies the slot number parameter for channel-attached actual destinations. This is the slot number in which the S/390 Parallel Channel Emulator is installed.

### **GUI Label**

S/370 slot number

### **DSS**

PSF

### **Type**

Resettable, single-valued

### **Allowed Values**

You can enter an integer from 1 through 8.

**Default Value**

No default value

**Usage Guidelines**

- You must enter a value for PSF channel-attached actual destinations. Infoprint ignores this attribute for other attachment types.
- If a single IBM 4159 Model 001 Channel Card is installed in the computer, specify 1 for the slot address. If multiple channel cards are installed in the computer, see the 4159 procedures in the *Infoprint Manager for Windows NT and Windows 2000: Getting Started*.

**printer-tcpip-internet-address**See **destination-tcpip-internet-address**.**printer-tcpip-port-number**See **destination-tcpip-port-number**.**printer-timeout-period**See **destination-timeout-period**.**problem-message**

Provides information on the cause of a problem with a actual destination.

**GUI Label**

Problem message

**DSS**

All

**Type**

Non-settable, single-valued

**Allowed Values**

Infoprint sets this value to a text string that contains the message information.

**Default Value**

No default value

**Usage Guidelines**

- This attribute may contain problem information whenever the actual destination state is not **idle**, **connecting-to-printer**, or **printing**.
- If the actual destination state is **needs-key-operator**, Infoprint disables the actual destination. If the actual destination uses SNMP, Infoprint automatically re-enables it when the problem is corrected. To prevent automatic re-enabling, manually disable the actual destination.

**protected-attributes**

Specifies one or more actual destination attributes that DCE prevents Infoprint operators from setting or changing.

**GUI Label**

Protected attributes

**DSS**

All

## Actual Destination

### Type

Resettable, multi-valued

### Allowed Values

You can enter one or more actual destination attributes.

### Default Values

This attribute always specifies itself, **protected-attributes**, as a value.

### Usage Guidelines

#### With DCE security

Normally, anyone with DCE **write** permission for actual destinations can set values for actual destination attributes. By default, the **pd\_admin** and **pd\_operator** DCE groups both have **write** permission. Once you define an actual destination attribute as a protected attribute, you must have DCE **delete** permission to modify the attribute. Members of the **pd\_operator** DCE group do not have **delete** permission unless the DCE administrator modifies the default permissions for that group.

#### With Non-DCE security

Normally, anyone with **write** permission for actual destinations can set values for actual destination attributes. By default, the **admin** and **oper** groups both have **write** permission. Once you define an actual destination attribute as a protected attribute, you must have **actual-destination delete** permission to modify the attribute. Members of the **oper** group do not have **actual-destination delete** permission unless the administrator modifies the default permissions for that group.

## psf-tray-characteristics

Defines the current characteristics of the input trays on this output device.

### GUI Label

Media ready

### DSS

PSF, Infoprint 2000

### Type

Resettable, multi-valued, complex

### Syntax

*input-tray:medium-loaded:job-bin-number:tray-number:duplex-supported*

Separate values with colons, for example:

top:letter:1:1:false

### Components

**input-tray:** Specifies which input tray this value defines.

**GUI Label:** Input tray

**Type:** Single-valued

**Allowed Values:** You can enter any name you want, for example:

**alternate**  
**bottom**

**envelope**  
**insert**

**Note:** The **insert** input tray is on the finisher, not the printer device itself. This means that you cannot print inserts with the rest of the job. If you want printed inserts, preprint them and load the printed sheets into the **insert** input tray.

**large-capacity**  
**main**  
**manual**  
**side**  
**top**

*Default Value:* The default value for PSF command-attached and other-driver attached actual destinations is **top**. For other actual destinations, there is no default value.

**media-loaded:** Specifies the medium that is now in the input tray. Infoprint adds the value you specify for this component automatically to the **media-ready** actual destination attribute.

*GUI Label:* Media ready

*Type:* Single-valued

*Allowed Values:* The value you specify does not have to match one of the values specified by the **medium-identifier** medium attributes. However, it must be one of the values specified by the **media-supported** attribute for this actual destination.

*Default Value:* The default value for PSF command-attached and other-driver attached actual destinations is **letter**. For other actual destinations, there is no default value.

*Usage Guidelines:* If you want to change the value of this component, make sure you add the value to the **media-supported** attribute first.

**job-bin-number:** Specifies a bin number that the data stream can specify to select this input tray.

*GUI Label:* Bin number

*Type:* Single-valued

*Allowed Values:* You can enter an integer from 1 to 255.

*Default Value:* If SNMP communication is active, Infoprint queries the printer device and sets the values according to the response; otherwise:

- The default value for PSF command-attached and other-driver attached actual destinations is **1**. For other actual destinations, there is no default value.
- If you specify any of the values for the **input-tray** name shown in Table 12 on page 420, and no values for this component and the **tray-number** component, the values for both of these components default to the values shown in the explanation of this component. You can specify values for all three components if those values are not appropriate for a particular printer device.

*Usage Guidelines:* Each AFP printer device model has its own configuration of paper input trays, known as bins, each with a specific number. This component

## Actual Destination

maps the value specified for the input tray and loaded media to a bin number that Infoprint understands and uses. Some values have special meanings:

Table 12. Input Tray Names, Job Bin Numbers, and Tray Numbers on AFP Printer Devices

<b>Input Tray Name</b>	<b>Job Bin Number</b>	<b>Tray Number</b>
<b>alternate</b>	1	5
<b>bottom</b>	2	4
<b>envelope</b>	65	6
<b>manual</b>	100	2
<b>top</b>	1	1

**tray-number:** Identifies the tray number of the input tray, depending on the printer model, associated with the job bin number.

*GUI Label:* Tray number

*Type:* Single-valued

*Allowed Values:* You can enter an integer value of 1 or 2.

*Default Value:* The default value for PSF command-attached and other-driver attached actual destinations is **1**. This component does not apply to other attachment types.

For command-attached actual destinations and other-driver attached actual destinations, if you specify any of the values for the **input-tray** name shown in the table under **job-bin-number** and no value for this component, the value for this component defaults to the value shown in the explanation of the **job-bin-number** component.

*Usage Guidelines:* See the documentation for the printer device for further information on which types of input trays this printer supports.

**duplex-supported:** Specifies whether two-sided printing is possible from this input tray.

*GUI Label:* Duplex

*Type:* Single-valued

*Allowed Values:* You can enter one of these fixed values:

<b>Fixed Value</b>	<b>Input Synonym</b>
<b>true</b>	<b>yes</b>
<b>false</b>	<b>no</b>

*Default Value:* The default value for PSF command-attached and other-driver attached actual destinations is **false**. This component does not apply to other attachment types.

### Default Values

If SNMP communication is active, Infoprint queries the printer device and sets the values according to the response; otherwise, the default values are as described for each component.

**Usage Guidelines**

- With PSF command-attached or PSF other-driver attached printers, you can specify a maximum of 15 values, one for each input tray of the printer device.
- With PSF TCP/IP attached printers, there is no limit on the number of values you can specify for **psf-tray-characteristics**.
- Infoprint automatically sets the **media-ready** and **input-trays-supported** actual destination attributes from the value you set here.
- Infoprint verifies that the values of the **media-loaded** component of this attribute are values of the **media-supported** attribute.

**qualities-supported**

See **print-qualities-supported**.

**register-threshold**

See **destination-register-threshold**.

**registered-with-spooler**

Indicates whether this actual destination and the server containing the actual destination's queue have established communication.

**GUI Label**

Registered with spooler

**DSS**

All

**Type**

Non-settable, single-valued

**Allowed Values**

Infoprint sets one of these fixed values:

**true**

**false**

**Default Value**

**false**

**remote-queue**

Indicates whether the backend program sends data to a remote print queue rather than controlling this AIX actual destination directly.

**GUI Label**

Use remote print queue

**DSS**

AIX, PSF (AIX only with other-driver attachment type)

**Type**

Resettable, single-valued

**Allowed Values**

You can enter one of these fixed values:

**Fixed Value**

**true**

**false**

**Input Synonym**

**yes**

**no**

## Actual Destination

### Default Value

false

### Usage Guidelines

- If the printer backend program is a variation of, or front end to, **rembak**, specify **true**. Examples of **rembak**-based backend programs include **piorflb** and **piocolor**.
- When you are working with AIX DSS actual destinations, see “Creating and Managing Actual Destinations” in the *Infoprint Manager for AIX: Administrator's Guide* for information on correcting the configuration of **remote-queue** printers that have **device-name** set to /dev/null.

## resource-context

Defines the default directory paths that Infoprint searches for AFP resources, including fonts, form definitions, overlays, page definitions, page segments, and color mapping table.

### GUI Label

Location of resources

### DSS

PSF, Email, Fax, Infoprint 2000

### Type

Resettable, single-valued

### Allowed Values

You can enter the name of a resource-context object or a text string up to 255 characters long that defines the directory path to fonts. You can specify one or more paths for one resource context. You can specify paths for file systems mounted to AIX, such as MVS data sets and VM minidisks.

### Syntax

*path:path* for AIX

*path;path* for Windows NT or Window 2000

Separate multiple paths with a colon on AIX or a semicolon on Windows NT or Window 2000, for example:

- In AIX,  
/fonts:/dept123/fonts
- In Windows NT or Windows 2000,  
\fontlib;\dept123\fonts

### Default Value

With AIX, no default values, but Infoprint always searches:

1. **/usr/lpp/psf/reslib**
2. **/usr/lpp/afpfonts**
3. **/usr/lpp/psf/fontlib**

With Windows NT or Windows 2000, no default values, but Infoprint always searches:

1. **\install\_path\reslib**
2. **\install\_path\afpfonts**



3. `\install_path\fontlib`**Usage Guidelines**

- You can use this attribute to locate default resources or color mapping tables.
- Infoprint searches resource paths in this order:
  1. **resource-context-user** document attribute
  2. **resource-context-font**, **resource-context-form-definition**, **resource-context-overlay**, **resource-context-page-definition**, or **resource-context-page-segment** document attribute, as appropriate for the type of resource.
  3. **resource-context** document attribute
  4. **PSFPATH** environment variable
  5. **resource-context-font**, **resource-context-form-definition**, **resource-context-overlay**, **resource-context-page-definition**, or **resource-context-page-segment** actual destination attribute, as appropriate for the type of resource
  6. **resource-context** actual destination attribute
  7. With AIX:
    - a. `/usr/lpp/psf/reslib`
    - b. `/usr/lpp/afpfonts`
    - c. `/usr/lpp/psf/fontlib`
  8. With Windows NT or Window 2000, where *install\_path* indicates the path where you installed Infoprint Manager:
    - a. `\install_path\reslib`
    - b. `\install_path\afpfonts`
    - c. `\install_path\fontlib`

If Infoprint cannot find the resource because none of the paths contain the resource, it still processes the job and prints error messages at the end of the job. Infoprint reports the job as completed.

**resource-context-font**

Defines the directory paths that Infoprint searches for fonts for the job.

**GUI Label**

Location of fonts

**DSS**

PSF, Email, Fax, Infoprint 2000

**Type**

Resettable, single-valued

**Allowed Values**

You can enter the name of a resource-context object or a text string up to 255 characters long that defines the directory path to the AFP resources. You can specify one or more paths for one resource context.

**Syntax**

*path:path* for AIX

*path;path* for Windows NT or Window 2000

Separate multiple paths with a colon on AIX or a semicolon on Windows NT or Window 2000.

## Actual Destination

### Default Value

With AIX, no default values, but Infoprint always searches **/usr/lpp/psf/reslib**.

With Windows NT or Windows 2000, no default values, but Infoprint always searches **\install\_path\reslib**.

### Usage Guidelines

You can use this attribute to locate default resources or color mapping tables.

Infoprint searches resource paths in this order:

1. **resource-context-user** document attribute
2. **resource-context-font**, **resource-context-form-definition**, **resource-context-overlay**, **resource-context-page-definition**, or **resource-context-page-segment** document attribute, as appropriate for the type of resource
3. **resource-context** document attribute
4. **PSFPATH** environment variable
5. **resource-context-font**, **resource-context-form-definition**, **resource-context-overlay**, **resource-context-page-definition**, or **resource-context-page-segment** actual destination attribute, as appropriate for the type of resource
6. **resource-context** actual destination attribute
7. With AIX:
  - a. **/usr/lpp/psf/reslib**
  - b. **/usr/lpp/afpfonts** for fonts
  - c. **/usr/lpp/psf/fontlib** for fonts
8. With Windows NT or Windows 2000:
  - a. **\install\_path\reslib**
  - b. **\install\_path\afpfonts** for fonts
  - c. **\install\_path\fontlib** for fonts

If Infoprint cannot find the resource because none of the paths contain the resource, it still processes the job and prints error messages at the end of the job. Infoprint reports the job as completed.

## resource-context-form-definition

Defines the directory paths that Infoprint searches for the form definition for the job.

### GUI Label

Location of form definitions

### DSS

PSF, Email, Fax, Infoprint 2000

### Type

Resettable, single-valued

### Allowed Values

You can enter the name of a resource-context object or a text string up to 255 characters long that defines the directory path to form definitions. You can specify one or more paths for one resource context. In AIX, you can specify paths for file systems mounted to AIX, such as MVS data sets and VM minidisks.

## Syntax

*path:path* for AIX  
*path;path* for Windows NT or Window 2000

Separate path names with colons on AIX and semicolons on Windows NT or Window 2000, for example:

- For AIX:  
   */formdef:/dept123/form*
- For Windows NT or Window 2000:  
   *\reslib\formdef;\dept123\form*

## Default Value

With AIX, no default values, but Infoprint always searches **/usr/lpp/psf/reslib**.

With Windows NT or Window 2000, no default values, but Infoprint always searches **\install\_path\reslib**.

## Usage Guidelines

- You can use either the document or the actual destination **form-definition** attribute to specify the form definition.
- Infoprint searches paths in this order:
  1. **resource-context-user** document attribute
  2. **resource-context-form-definition** document attribute
  3. **resource-context** document attribute
  4. **PSFPATH** environment variable
  5. **resource-context-form-definition** actual destination attribute
  6. With AIX, **/usr/lpp/psf/reslib**
  7. With Windows NT or Window 2000, **\install\_path\reslib**
- If Infoprint cannot find the resource because none of the paths contain the resource, it still processes the job and prints error messages at the end of the job. Infoprint reports the job as completed.

## resource-context-overlay

Defines the directory paths that Infoprint searches for an overlay for the job.

### GUI Label

Location of overlays

### DSS

PSF, Email, Fax, Infoprint 2000

### Type

Resettable, single-valued

### Allowed Values

You can enter the name of a resource-context object or a text string up to 255 characters long that defines the directory path to overlays. You can specify one or more paths for one resource context. You can specify paths for file systems mounted to AIX, such as MVS data sets and VM minidisks.

## Syntax

*path:path* for AIX  
*path;path* for Windows NT or Window 2000

## Actual Destination

Separate path names with colons on AIX, for example:

```
/overlay:/dept123/overlay
```

Separate path names with semicolons on Windows NT or Window 2000, for example:

```
\overlay;\dept123\overlay
```

### Default Value

With AIX, no default values, but Infoprint always searches **/usr/lpp/psf/reslib**.

With Windows NT or Window 2000, no default values, but Infoprint always searches **\install\_path\reslib**.

### Usage Guidelines

- You use a form definition for the job to specify the overlay.
- Infoprint searches paths in this order:
  1. **resource-context-user** document attribute
  2. **resource-context-overlay** document attribute
  3. **resource-context** document attribute
  4. **PSFPATH** environment variable
  5. **resource-context-overlay** actual destination attribute
  6. With AIX, **/usr/lpp/psf/reslib**
  7. With Windows NT or Window 2000, **\install\_path\reslib**
- If Infoprint cannot find the resource because none of the paths contain the resource, it still processes the job and prints an error messages at the end of the job. Infoprint reports the job as completed.

## resource-context-page-definition

Defines the directory paths that Infoprint searches for a page definition for the job.

### GUI Label

Location of page definitions

### DSS

PSF, Email, Fax, Infoprint 2000

### Type

Resettable, single-valued

### Allowed Values

You can enter the name of a resource-context object or a text string up to 255 characters long that defines the directory path to page definitions. You can specify one or more paths for one resource context. You can specify paths for file systems mounted to AIX, such as MVS data sets and VM minidisks.

### Syntax

*path:path* for AIX

*path;path* Windows NT or Window 2000

Separate path names with colons on AIX, for example:

```
/pagedef:/dept123/page-definition
```

Separate path names with semicolons on Windows NT or Window 2000, for example:

```
\pagedef;\dept123\page-definition
```

**Default Value**

With AIX, no default values, but Infoprint always searches `/usr/lpp/psf/reslib`.

With Windows NT or Windows 2000, no default values, but Infoprint always searches `\install_path\reslib`.

**Usage Guidelines**

- You use the **page-definition** document attribute to specify the page definition for the job.
- Infoprint searches paths in this order:
  1. **resource-context-user** document attribute
  2. **resource-context-page-definition** document attribute
  3. **resource-context** document attribute
  4. **PSFPATH** environment variable
  5. **resource-context-page-definition** actual destination attribute
  6. With AIX, `/usr/lpp/psf/reslib`
  7. With Windows NT or Window 2000, `\install_path\reslib`
- If Infoprint cannot find the resource because none of the paths contain the resource, it still processes the job and prints error messages at the end of the job. Infoprint reports the job as completed.

**resource-context-page-segment**

Defines the directory paths that Infoprint searches for page segments for the job.

**GUI Label**

Location of page segments

**DSS**

PSF, Email, Fax, Infoprint 2000

**Type**

Resettable, single-valued

**Allowed Values**

You can enter the name of a resource-context object or a text string up to 255 characters long that defines the directory path to page segments. You can specify one or more paths for one resource context. You can specify paths for file systems mounted to AIX, such as MVS data sets and VM minidisks.

**Syntax**

*path:path* for AIX

*path;path* for Windows NT or Window 2000

Separate path names with colons on AIX, for example:

`/pageseg:/dept123/page-segment`

Separate path names with semicolons on Windows NT or Window 2000, for example:

`/pageseg;/dept123/page-segment`

**Default Value**

With AIX, no default values, but Infoprint always searches `/usr/lpp/psf/reslib`.

With Windows NT or Window 2000, no default values, but Infoprint always searches `\install_path\reslib`.

## Actual Destination

### Usage Guidelines

- You specify the page segments within the job.
- Infoprint searches paths in this order:
  1. **resource-context-user** document attribute
  2. **resource-context-page-segment** document attribute
  3. **resource-context** document attribute
  4. **PSFPATH** environment variable
  5. **resource-context-page-segment** actual destination attribute
  6. For AIX, **/usr/lpp/psf/reslib**
  7. For Windows NT or Window 2000, **\install\_path\reslib**
- If Infoprint cannot find the resource because none of the paths contain the resource, it still processes the job and prints error messages at the end of the job. Infoprint reports the job as completed.

## reverse-output

Indicates whether this actual destination should print jobs in reverse (last page first).

### GUI Label

Print last page first

### DSS

3170

### Type

Resettable, single-valued

### Allowed Values

You can enter one of these fixed values:

<i>Fixed Value</i>	<i>Input Synonym</i>
<b>true</b>	<b>yes</b>
<b>false</b>	<b>no</b>

### Default Value

**false**

### Usage Guidelines

If you specify **true**, you may also wish to specify **true** for the document attribute **output-face-up** so that pages will be collated in the right order.

## rip-ini-file

Identifies the default **.ini** file for this actual destination. This file contains default page setup values used to RIP files.

### GUI Label

RIP ini file

### DSS

3170

### Type

Resettable, single-valued

### Allowed Values

You can enter a text string up to 255 characters long that contains the full path name of the file.

**Default Value**  
/usr/lpp/pd/bin/default.ini

## rip-server

See **color-rip-servers**.

## scanner-corrections-supported

Identifies the scanner calibration methods for which this actual destination supports correction.

**GUI Label**  
Scanner corrections allowed

**DSS**  
PSF (AIX Only)

**Type**  
Resettable, multi-valued

**Allowed Values**  
You can enter any of these fixed values:  
**Ricoh420**  
**XeroxDocuimage620S**  
**none**

**Default Values**  
**Ricoh420, XeroxDocuimage620S, none**

**Usage Guidelines**  
Infoprint compares the document attribute **scanner-correction** to this attribute for validation and scheduling.

## scheduler-sort-primary-order

Identifies which of the schedulers specified by the **schedulers-supported** attribute Infoprint uses to determine how to schedule jobs.

**GUI Label**  
Primary scheduler

**DSS**  
All

**Type**  
Resettable, single-valued

**Allowed Values**  
You can enter one of these fixed values:

**Fixed Value**  
*Explanation*

**deadline** Infoprint schedules jobs with the earliest deadline first.  
**fifo** Infoprint schedules jobs in the order they are submitted.  
**job-priority** Infoprint schedules jobs in order of priority.  
**longest-job-first** Infoprint schedules jobs in order of size, longest first.

## Actual Destination

### **shortest-job-first**

Infoprint schedules jobs in order of size, shortest first.

### **Default Value**

**job-priority**

## scheduler-sort-secondary-order

Identifies which of the schedulers specified by the **schedulers-supported** attribute Infoprint uses to determine how to break ties produced by the scheduler specified by the **scheduler-sort-primary-order** attribute. For example, if you normally schedule jobs by priority, you can specify that when two jobs have the same priority, Infoprint should schedule the shorter one first.

### **GUI Label**

Secondary scheduler

### **DSS**

All

### **Type**

Resettable, single-valued

### **Allowed Values**

You can enter one of these fixed values:

#### **Fixed Value**

##### **Definition**

#### **deadline**

Infoprint schedules jobs with the earliest deadline first.

**fifo** Infoprint schedules jobs in the order they are submitted.

#### **job-priority**

Infoprint schedules jobs in order of priority.

#### **longest-job-first**

Infoprint schedules jobs in order of size, longest first.

#### **shortest-job-first**

Infoprint schedules jobs in order of size, shortest first.

### **Default Value**

**fifo**

## schedulers-supported

Identifies the scheduling algorithms that this actual destination supports.

### **GUI Label**

Schedulers allowed

### **DSS**

All

### **Type**

Non-settable, multi-valued

### **Allowed Values**

Infoprint sets this value to these fixed values:

#### **Fixed Value**

##### **Definition**



**deadline**

Infoprint schedules jobs with the earliest deadline first.

**fifo** Infoprint schedules jobs in the order they are submitted.

**job-priority**

Infoprint schedules jobs in order of priority.

**longest-job-first**

Infoprint schedules jobs in order of size, longest first.

**shortest-job-first**

Infoprint schedules jobs in order of size, shortest first.

**Default Values**

**deadline, fifo, job-priority, longest-job-first, shortest-job-first**

**screen-frequencies-supported**

Identifies the screen frequencies used for printing halftones that this actual destination supports.

**DSS**

PSF (AIX Only)

**Type**

Resettable, multi-valued

**Allowed Values**

You can enter any of these fixed values:

71

85

106

141

**Default Values**

71, 85, 106, 141

**Usage Guidelines**

Infoprint compares the document attribute **screen-frequency** to this attribute for validation and scheduling.

**Note:** The **halftones-supported** attribute provides more values for halftones than the **screen-frequency supported** attribute.

See “halftones-supported” on page 372 for more information..

**separator-sheets-supported**

Identifies the separator sheets that this actual destination supports.

**GUI Label**

Slip/Separator sheets allowed

**DSS**

AIX, PSF

**Type**

Resettable, multi-valued

**Allowed Values**

You can enter any of the following fixed values. For PSF only, you can enter a string up to 255 characters long that contains identifiers of auxiliary-sheet objects.

## Actual Destination

<i>Fixed Value</i>	<i>DSS</i>	<i>Explanation</i>
<b>accounting-log</b>	PSF	This value is technically valid, but should not be used for separator sheets.
<b>blank</b>	PSF	The separator sheet is blank.
<b>brief</b>	PSF	The separator sheet style is brief.
<b>full</b>	PSF	The separator sheet style is full.
<b>job-ticket</b>	PSF	The job ticket is printed on the separator sheet.
<b>none</b>	AIX, PSF	No separator sheet prints.

## Default Values

**AIX** none

**PSF** **accounting-log**, **blank**, **brief**, **full**, **job-ticket**, **none**, and the names of other defined auxiliary sheets which have legal PSF auxiliary sheet attributes.

## Usage Guidelines

- PSF actual destinations can use auxiliary-sheet objects if they have valid **psf-exit-xxx** values. AIX actual destinations print start and end sheets, but they do not use auxiliary-sheet objects.
- Because AIX actual destinations do not print separator sheets, the only valid value for them is **none**.
- Infoprint verifies that the value of the **printer-separator-sheet** attribute is a value of this attribute.
- You cannot delete a value from this attribute if the value you want to delete is the value of the **printer-separator-sheet** attribute.
- For PSF actual destinations, Infoprint sets this value dynamically to the names of all defined auxiliary sheets with legal attributes. You should never have to reset this value.

## shared-printer-name

Specifies the names of the Infoprint gateway shared printer, if any, that forwards jobs to this destination.

### GUI Label

Shared gateway printer

### DSS

All with NT/2000 servers

### Type

Resettable, single-valued

### Allowed Values

Text name of a gateway shared printer.

### Default Values

Derived from the actual destination name if the server's **auto-create-shared-printers** attribute is **true**; otherwise, no default.

### Usage Guidelines

The **shared-printer-name** is automatically set by IBM when the gateway printers are automatically created.

**sides**

Indicates whether the printer device prints on one or two sides of the media.

**GUI Label**

Sides to print

**DSS**

PSF, Infoprint 2000, Passthrough

**Type**

Resettable, single-valued

**Allowed Values**

You can enter an integer value of **1** or **2**.

**Default Values**

If SNMP communication is active, Infoprint queries the printer device and sets the values according to the response; otherwise:

**PSF** 1

**Infoprint 2000**  
2

**Passthrough**  
1

**Usage Guidelines**

- The value of the **sides** attribute must be one of the values of the **sides-supported** attribute.
- Infoprint uses sides specifications in this order:
  1. **sides** document attribute
  2. The sides specification in the form definition
  3. **sides** actual destination attribute

**Note:** Because all IBM-supplied form definitions contain a sides specification, the **sides** actual destination attribute is used only with custom form definitions that do not contain a sides specification.

**sides-supported**

Indicates whether this actual destination supports printing on one or two sides of the media.

**GUI Label**

Sides allowed

**DSS**

AIX, BSD, PSF, 3170, Infoprint 2000, Passthrough

**Type**

Resettable, multi-valued

**Allowed Values**

You can enter an integer of 1 or 2.

**Default Values**

With AIX, PSF, and BSD, if SNMP communication is active, Infoprint queries the printer device and sets the values according to the response; otherwise, the default follows:

**AIX** 1

## Actual Destination

**BSD** No default value

**PSF (basic Infoprint administrator's GUI)**

1, 2

**PSF (advanced Infoprint administrator's GUI and command line)**

1

**3170** 1, 2

**Passthrough**

1

### Usage Guidelines

- You can use this attribute to restrict jobs sent to this actual destination according to the capacity of the output device or your policy for output device use.
- Infoprint compares the document attribute **sides** to this attribute for scheduling.
- If you specify a value for the **sides-supported** attribute, you deactivate the default that SMNP provides.

## snmp-active

Indicates whether Infoprint has established Simple Network Management Protocol (SNMP) communications with the output device that this actual destination represents.

### GUI Label

SNMP is acive

### DSS

AIX, BSD, PSF, IPP, Passthrough

### Type

Non-settable, single-valued

### Allowed Values

Infoprint sets this value to one of these fixed values:

**true**

**false**

### Default Value

If you have defined a value for the **destination-tcpip-internet-address** attribute and Infoprint has established SNMP communication with the printer device, **true**; otherwise **false**.

## snmp-community-name

Specifies the name of the SNMP community to which the printer device that this actual destination represents belongs.

### GUI Label

Community name

### DSS

AIX, BSD, PSF, IPP, Passthrough

### Type

Resettable, single-valued

### Allowed Values

You can enter a text string up to 255 characters long that contains the SNMP community name.

**Default Value**  
public

**Usage Guidelines**

If the value of the **use-snmp** attribute is **false**, this attribute is ignored.

## snmp-retry-count

Specifies the number of times, after an initial failure, that Infoprint should attempt to establish SNMP communication with the printer device that this actual destination represents.

**GUI Label**

Number of times to retry

**DSS**

AIX, BSD, PSF, IPP, Passthrough

**Type**

Resettable, single-valued

**Allowed Values**

You can enter an integer from 0 through 2147483647.

**Default Value**

2

**Usage Guidelines**

- If the value of the **use-snmp** attribute is **true**, and if you have defined a value for the **destination-tcpip-internet-address** attribute, Infoprint attempts to establish SNMP communication with the printer device when:
  - The actual destination is created.
  - Any of the SNMP attributes of the actual destination are changed,
  - The actual destination is enabled and the value of the **snmp-active** attribute is **false**.
  - The server is started.
- If the value of the **use-snmp** attribute is **false**, this attribute is ignored.

## snmp-timeout

Specifies the number of seconds that Infoprint should wait for SNMP operations on the printer device that this actual destination represents to complete.

**GUI Label**

Timeout (sec)

**DSS**

AIX, BSD, PSF, IPP, Passthrough

**Type**

Resettable, single-valued

**Allowed Values**

You can enter an integer from 0 through 2147483647.

**Default Value**

5

## Actual Destination

### Usage Guidelines

- Set a value of **0** to use the SNMP default timeout period.
- If the value of the **use-snmp** attribute is **false**, this attribute is ignored.

## start-message-supported

Indicates whether the actual destination supports the job attribute **job-start-message**.

### GUI Label

Send job start message

### DSS

All

### Type

Resettable, single-valued

### Allowed Values

You can enter one of these fixed values:

<i>Fixed Value</i>	<i>Input Synonym</i>
true	yes
false	no

### Default Value

true

### Usage Guidelines

- When you set this attribute value to **true**, operators can receive messages that users specify with the **job-start-message** job attribute when they submit the job. Infoprint sends the message to the operators specified by the **notify-operator** attribute for this actual destination when the job starts printing. Sending a start message does not stop the job from printing; normally the job prints without operator intervention.
- Infoprint compares the job attribute **job-start-message** to this attribute for validation and scheduling.
- You can use this attribute to restrict use of this actual destination.

## start-sheets-supported

Identifies the start sheets that this actual destination supports.

### GUI Label

Start sheets allowed

### DSS

AIX, PSF, 3170, IPP, Passthrough

### Type

Resettable, multi-valued

### Allowed Values

You can enter any of the following fixed values. For PSF only, you can enter a string up to 255 characters long that contains identifiers of auxiliary-sheet objects.

<i>Fixed Value</i>	<i>DSS</i>	<i>Explanation</i>
accounting-log	PSF	This value is technically valid, but should not be used for start sheets.

## Actual Destination

<i>Fixed Value</i>	<i>DSS</i>	<i>Explanation</i>
<b>blank</b>	PSF	The start sheet is blank.
<b>brief</b>	AIX, PSF, IPP, Passthrough	The start sheet style is brief.
<b>full</b>	AIX, PSF, 3170, IPP, Passthrough	The start sheet style is full.
<b>job-ticket</b>	PSF	The job ticket is printed on the start sheet.
<b>none</b>	AIX, PSF, 3170, IPP, Passthrough	No start sheet prints.

### Default Values

**AIX, IPP, Passthrough**  
**brief, full, none**

**PSF** **accounting-log, blank, brief, full, job-ticket, none**, and the names of other defined auxiliary sheets which have legal PSF auxiliary sheet attributes.

**3170** **full, none**

### Usage Guidelines

- PSF actual destinations can use auxiliary-sheet objects if they have valid **psf-exit-xxx** values. AIX actual destinations print start and end sheets, and 3170 actual destinations print start sheets; but they do not use auxiliary-sheet objects.
- Infoprint verifies that the value of the **printer-start-sheet** attribute is a value of this attribute.
- You cannot delete a value from this attribute if the value you want to delete is the value of the **printer-start-sheet** attribute.
- For PSF actual destinations, Infoprint sets this value dynamically to the names of all defined auxiliary sheets with legal attributes. You should never have to reset this value.

## table-reference-characters-supported

Indicates whether this actual destination supports table reference characters. Some line-data applications produce table reference characters to specify font changes.

### GUI Label

Table reference characters allowed

### DSS

PSF, Email, Fax, Infoprint 2000

### Type

Resettable, single-valued

### Allowed Values

You can enter one of these fixed values:

<i>Fixed Value</i>	<i>Input Synonym</i>
<b>true</b>	<b>yes</b>
<b>false</b>	<b>no</b>

### Default Value

**true**

## Actual Destination

### Usage Guidelines

- Infoprint compares the document attribute **table-reference-characters** to this attribute for scheduling.
- You can use this attribute to restrict use of this actual destination.

## timeout-period

See **printer-timeout-period**.

## transform-sequence

Specifies a list of names of transform objects that make up the transform sequence for this actual destination. The order of the values in this attribute determines the order that the transforms are run.

### GUI Label

Transforms to use

### DSS

All with NT/2000 servers

### Type

Resettable, multi-valued

### Allowed Values

Names of the transform objects.

### Default Values

None.

## use-snmp

Indicates whether Infoprint should attempt SNMP communication with the output device that this actual destination represents.

### GUI Label

Use SNMP

### DSS

AIX, BSD, PSF, IPP, Passthrough

### Type

Resettable, single-valued

### Allowed Values

You can enter one of these fixed values:

<i>Fixed Value</i>	<i>Input Synonym</i>
<b>true</b>	<b>yes</b>
<b>false</b>	<b>no</b>

### Default Value

**true**

### Usage Guidelines

If Infoprint fails to establish SNMP contact with an output device, it uses the **ping** command to test whether it is possible to communicate with the device in other ways. If the **ping** command succeeds, Infoprint concludes that the device is not an SNMP device and resets this attribute to **false**.



## wait-for-job-completion

Indicates whether Infoprint Manager waits for the job to print completely before reporting the job as completed or reports the job as completed as soon as all the data has been sent to the printer.

### DSS

AIX

### Type

Resettable, single-valued

### Allowed Values

You can enter one of these fixed values:

<i>Fixed Value</i>	<i>Input Synonym</i>
<b>true</b>	<b>yes</b>
<b>false</b>	<b>no</b>

### Default Value

**true** when the printer and backend support PJI USTATUS; or **false** when the printer or the backend do not support PJI USTATUS.

### Usage Guidelines

- This attribute can be used to activate or deactivate reporting of job completion.

**Note:** There is a new backend program called piointo for use with printers that can be used in place of the piojetd backend program. For example, **destination-command=/usr/lpd/pio/etc/piointo ip\_address**, where *ip\_address* is the ip address of the printer.

- There is a performance trade-off when you use this attribute: if you choose **true**, your printer performance may be reduced slightly; and when you choose **false**, the job completion messages are not accurate.

## warning-message

Provides information about printer device conditions that require attention but allow printing to continue, such as low paper or low toner.

### GUI Label

Warning message

### DSS

AIX, BSD, PSF, IPP, Passthrough

### Type

Non-settable, single-valued

### Allowed Values

Infoprint sets this value to a text string that contains the message information.

### Default Value

No default value

### Usage Guidelines

Infoprint uses this attribute only when SNMP communication is active with the printer device.

## Actual Destination

### windows-nt-driver-names

Identifies the 32-bit Windows print drivers that can submit a data stream to this actual destination.

#### GUI Label

Windows drivers

#### DSS

IPP, Passthrough

#### Type

Resettable, multi-valued

#### Input Synonyms

You can use the synonym **windows-nt-drivers** or **nt-drivers**.

#### Allowed Values

You can enter a text string that contains the string form of the Windows print driver for each permitted Windows print driver. Begin and end the string with single quotation marks.

#### Default Values

No default values

#### Usage Guidelines

Perform the following procedure to determine the valid Windows driver names:

1. Select **My Computer** from the desktop.
2. Select and open the **Control Panel** icon.
3. Select and open the **Printers** icon,
4. Select and open the **Add Printer** icon.
5. The values listed in the **Printers:** list box in the **Add Printer Wizard** are the names of the Windows destination drivers that you can install on the workstation; for example, **IBM 4039 LaserPrinter PS**.

#### Notes:

1. Other destination drivers are available and may not display in the list for a particular workstation.
2. If you will be submitting jobs from the Windows client to a PSF actual destination, you should select a generic destination driver, such as a PostScript driver, instead of one for a specific type of destination. Otherwise, the driver may generate device-specific data streams that Infoprint cannot transform correctly.

### x-image-shift-range-supported

Specifies, in millimeters, the lower and upper numeric boundaries for the X offset of a page. The X offset, along with the Y offset, sets the origin of the logical page on the physical page.

#### GUI Label

Move image right (inches) or (mm)

#### DSS

PSF, 3170, Email, Fax, Infoprint 2000

#### Type

Resettable, single-valued, complex

## Syntax

*lower-limit:upper-limit*

Separate values with colons, for example,

1:10

## Components

**lower-limit:** Defines the minimum amount of image shift that you can specify with the document or default document attribute **x-image-shift** or **x-image-shift-back**.

*Type:* Single-valued

*Allowed Values:* You can enter a numeric value from -577.99 mm through 577.97 mm. The unit of measure is millimeters.

*Default Value:* **0**

**upper-limit:** Defines the maximum amount of image shift that you can specify with the document or default document attribute **x-image-shift** or **x-image-shift-back**.

*Type:* Single-valued

*Allowed Values:* You can enter a numeric value from -577.99 mm through 577.97 mm. The unit of measure is millimeters.

*Default Value:* **577.97 mm**

## Usage Guidelines

- Infoprint compares the document attributes **x-image-shift** and **x-image-shift-back** to this attribute for validation and scheduling.
- You can use this attribute to restrict use of this actual destination.

## y-image-shift-range-supported

Specifies, in millimeters, the lower and upper numeric boundaries for the Y offset of a page. The Y offset, along with the X offset, sets the origin of the logical page on the physical page.

### GUI Label

Move image down (inches) or (mm)

### DSS

PSF, 3170, Email, Fax, Infoprint 2000

### Type

Resettable, single-valued, complex

## Syntax

*lower-limit:upper-limit*

Separate values with colons, for example,

1:20

## Actual Destination

### Components

**lower-limit:** Defines the minimum amount of image shift that you can specify with the document or default document attribute **y-image-shift** or **y-image-shift-back**.

*Type:* Single-valued

*Allowed Values:* You can enter a numeric value from -577.99 mm through 577.97 mm. The unit of measure is millimeters.

*Default Value:* **0**

**upper-limit:**

*Type:* Single-valued

*Allowed Values:* You can enter a numeric value from -577.99 mm through 577.97 mm. The unit of measure is millimeters.

*Default Value:* **577.97 mm**

### Usage Guidelines

- Infoprint compares the document attributes **y-image-shift** and **y-image-shift-back** to this attribute for validation and scheduling.
- You can use this attribute to restrict use of this actual destination.

## Attributes for Auxiliary-Sheet Objects

An auxiliary-sheet object represents:

- An auxiliary sheet that prints with a job sent to a PSF actual destination
- An exit program that generates information about the job for printing on an auxiliary sheet or writing to an accounting log or an audit log

An auxiliary sheet is a sheet of paper that prints at the beginning or end of output, or separating different parts of the output. The auxiliary sheet may have information printed on it identifying the output or may be blank.

The PSF DSS uses the names of auxiliary-sheet objects as values for actual destination attributes, such as **accounting-exit**, **audit-exit**, **start-sheets-supported**, and **printer-start-sheet**. The fax and email DSSs use the names of auxiliary-sheet objects as values for the **accounting-exit** and **audit-exit** actual destination attributes. AIX actual destinations print start and end sheets, and 3170 actual destinations print start sheets; but they do not use auxiliary-sheet objects.

## Initially Settable Attribute Listing

There are no initially settable attributes for auxiliary-sheet objects.

## Resettable Attribute Listing

You can set these attributes with the **pdcreate** command when you create an auxiliary-sheet object or you can modify them with the **pdset** command after you create the object.

**descriptor**  
**psf-exit-form-definition**  
**psf-exit-page-mark**  
**psf-exit-program-name**

## associated-server

Indicates the name of the server where this auxiliary sheet resides.

### Type

Non-settable, single-valued

### Allowed Values

Infoprint sets this value when you create an auxiliary sheet for a given server. Infoprint assigns the *ServerName* portion of the argument from the **pdcreate** command used to create this auxiliary sheet object.

### Default Value

No default value

## auxiliary-sheet-identifier

Identifies the auxiliary sheet ID.

### Type

Non-settable, single-valued

### Allowed Values

Infoprint sets this value when you create an auxiliary sheet for a given server. Infoprint sets this value to the *AuxiliarySheet* portion of the argument used with the **pdcreate** command when this auxiliary sheet object was created. The value of this attribute must be unique within the server.

## Auxiliary Sheet

### Default Value

No default value

## descriptor

Provides a description of this auxiliary sheet.

### Type

Resettable, single-valued

### Allowed Values

You can enter a text string of up to 4095 characters that describes this auxiliary sheet.

### Default Value

No default value

### Usage Guidelines

The use of this attribute is optional. However, a detailed description of this auxiliary sheet might be useful to other users or to someone who needs to modify its contents.

## object-class

Identifies the object class to which this object belongs.

### Type

Non-settable, single-valued

### Allowed Values

Infoprint sets this value to **auxiliary-sheet**.

### Default Value

**auxiliary-sheet**

## psf-exit-form-definition

Sets the form definition to use when printing this auxiliary sheet.

### Type

Resettable, single-valued

### Allowed Values

You can enter a text string of up to 255 characters that contains the name of the form definition. See "Appendix D. Form Definitions and Page Definitions Supplied with Infoprint" on page 699 for a list of available form definitions.

### Default Value

No default value

### Usage Guidelines

A form definition defines the placement of the data on the auxiliary sheet and other formatting information, such as a printer device bin number. You can use the form definition to select a bin for the auxiliary sheet that is different from the bin used for jobs. For example, you can print auxiliary sheets on a different colored paper than used for the jobs.

## psf-exit-page-mark

Specifies whether you want page marks (black marks at the extreme edge of the page used for sorting) to print on this auxiliary sheet.

**Type**

Resettable, single-valued

**Allowed Values**

You can enter one of these fixed values:

<i>Fixed Value</i>	<i>Input Synonym</i>
false	no
true	yes

**Default Value**

No default value

**Usage Guidelines**

Page marks are useful for printer devices that cannot perform offset stacking, such as continuous form printers. The marks allow printer operators to see the boundaries of jobs.

**psf-exit-program-name**

Sets the name of the exit program used to generate this auxiliary sheet.

**Type**

Resettable, single-valued

**Allowed Values**

You can enter a text string of up to 4095 characters that contains a name of a user exit program, an empty string, or no value.

***Names of some user exit programs that you can use with AIX:****Accounting:*

**/usr/psf/bin/ainuxacc2**

Full style

**/usr/psf/bin/ainuxacc**

Brief style

**/usr/ps/bin/ainuxaccp**

Job ticket

**/usr/lpp/psf/bin/ainacclog**

Log

*Auditing:*

**/usr/lpp/psf/bin/ainuxaud2**

Full style

**/usr/lpp/psf/bin/ainuxaud**

Brief style

**/usr/lpp/psf/bin/ainuxaudp**

Job ticket

**/usr/lpp/psf/bin/ainaudlog**

Log

*Start Sheets:*

**/usr/lpp/psf/bin/ainuxhdr2**

Full style

**/usr/lpp/psf/bin/ainuxhdr**

Brief style

**/usr/lpp/psf/bin/ainuxhdrp**

Job ticket

## Auxiliary Sheet

**/usr/lpp/psf/bin/ainuxhdrx**

Start sheet without vertical lines for IBM 64xx printers

**/usr/lpp/psf/bin/pduxblkh**

Blank

*Separator Sheets:*

**/usr/lpp/psf/bin/ainuxsep2**

Full style

**/usr/lpp/psf/bin/ainuxsep**

Brief style

**/usr/lpp/psf/bin/ainuxsepp**

Job ticket

**/usr/lpp/psf/bin/ainuxsepx**

Separator sheet without vertical lines for IBM 64xx printers

**/usr/lpp/psf/bin/pduxblks**

Blank

*End Sheets:*

**/usr/lpp/psf/bin/ainuxtlr2**

Full style

**/usr/lpp/psf/bin/ainuxtlr**

Brief style

**/usr/lpp/psf/bin/ainuxtlrp**

Job ticket

**/usr/lpp/psf/bin/ainuxtlrx**

End sheet without vertical lines for IBM 64xx printers

**/usr/lpp/psf/bin/pduxblkt**

Blank

*Input Data:*

**/usr/lpp/psf/bin/ainuxind**

This example does not perform any tasks. Use it as a model for writing your own user exit program.

*Output Data:*

**/usr/lpp/psf/bin/ainuxout**

This example does not perform any tasks. Use it as a model for writing your own user exit program.

***Names of some user exit programs that you can use with Windows NT or***

***Window 2000:*** In these names, *install\_path* indicates the path where you installed Infoprint Manager:

*Accounting:*

***install\_path*\bin\ainuxacc2**

Full style

***install\_path*\bin\ainuxacc**

Brief style

***install\_path*\bin\ainuxaccp**

Job ticket

***install\_path*\bin\ainuxacclog**

Log

*Auditing:*

***install\_path*\bin\ainuxaud2**

Full style



`\install_path\bin\ainuxaud`

Brief style

`\install_path\bin\ainuxaudp`

Job ticket

`\install_path\bin\ainaudlog`

Log

*Start Sheets:*

`\install_path\bin\ainuxhdr2`

Full style

`\install_path\bin\ainuxhdr`

Brief style

`\install_path\bin\ainuxhdrp`

Job ticket

`\install_path\bin\ainuxhdrx`

Start sheet without vertical lines

`\install_path\bin\pduxblkh`

Blank

*Separator Sheets:*

`\install_path\bin\ainuxsep2`

Full style

`\install_path\bin\ainuxsep`

Brief style

`\install_path\bin\ainuxsepp`

Job ticket

`\install_path\bin\ainuxsepx`

Separator sheet without vertical lines

`\install_path\bin\pduxblks`

Blank

*End Sheets:*

`\install_path\bin\ainuxtlr2`

Full style

`\install_path\bin\ainuxtlr`

Brief style

`\install_path\bin\ainuxtlrp`

Job ticket

`\install_path\bin\ainuxtlrx`

End sheet without vertical lines

`\install_path\bin\pduxblkt`

Blank

*Input Data:*

`\install_path\bin\ainuxind`

This example does not perform any tasks. Use it as a model for writing your own user exit program.

*Output Data:*

`\install_path\bin\ainuxout`

This example does not perform any tasks. Use it as a model for writing your own user exit program.

**Default Value**

No default value

## Auxiliary Sheet

### Usage Guidelines

- If the attribute has:

#### No value

The auxiliary sheet does not print.

#### An empty string ("")

Infoprint uses the default user exit program:

**Accounting** For AIX, **/usr/lpp/psf/bin/ainacclog**; for Windows NT or Window 2000, **\install\_path\bin\ainacclog**

**Audit** No default program

**Start sheet** For AIX, **/usr/lpp/psf/bin/ainuxhdr**; for Windows NT or Window 2000, **\install\_path\bin\ainuxhdr**

#### Separator sheet

No default program

**End sheet** No default program

**Input data** No default program

**Output data** No default program

#### Any other value

Infoprint uses the specified user exit program to generate auxiliary sheets.

- While you can specify only one user exit program as a value for this attribute, the default auxiliary-sheet objects can invoke any of a set of user exit programs. For example with AIX, the **brief** default auxiliary-sheet object invokes **/usr/lpp/psf/bin/ainuxacc** for accounting exits, **/usr/lpp/psf/bin/ainuxaud** for audit exits, **/usr/lpp/psf/bin/ainuxhdr** for start sheets, **/usr/lpp/psf/bin/ainuxsep** for separator sheets, and **/usr/lpp/psf/bin/ainuxplr** for end sheets. For example with Windows NT or Window 2000, the **brief** default auxiliary-sheet object invokes **\install\_path\bin\ainuxacc** for accounting exits, **\install\_path\bin\ainuxaud** for audit exits, **\bin\ainuxhdr** for start sheets, **\install\_path\bin\ainuxsep** for separator sheets, and **\install\_path\bin\ainuxplr** for end sheets.

## Attributes for Documents and Default Documents

This section contains the attributes for both documents and default documents.

### Document

An Infoprint document represents a grouping of data within a job. A job can contain one or more documents. The documents in a job can differ from each other in some ways. For example, they can contain different data. A document within a job can contain printable data or a resource that is not printable by itself.

### Default Document

Use default documents to set default values for document attributes.

Default documents contain two types of attributes:

- Attributes that describe the default document itself
- Attributes that you can set as default values for document attributes

### Attributes Not Displayed in the Infoprint Administrator's GUI

While all document and default document attributes and attribute values are supported for both basic and advanced Infoprint installations, neither Infoprint administrator's GUI displays a complete set.

- The basic Infoprint administrator's GUI displays only the attributes of greatest interest to Print on Demand (Commercial Printing) Infoprint administrators.
- The advanced Infoprint administrator's GUI displays most attributes and attribute values of greatest interest to Data Center (Production Printing) Infoprint administrators, but omits a few that are used primarily in basic Infoprint installations.

You can list the values of attributes not displayed in the Infoprint administrator's GUI using the **pdls** command or the **pdq** command. You can set the values of initially settable and resettable attributes using the **pdcreate** command or the **pdpr** command. You can change the values of resettable attributes using the **pdmod** command or the **pdset** command.

### Initially Settable Attribute Listing

You can set these attributes with the **pdpr** command when you create a document.

**document-file-name**  
**document-type**  
**initial-value-document**  
**transfer-method**

There are no initially settable attributes for default documents.

### Resettable Attribute Listing

You can set these attributes with the **pdpr** command when you create a document or with the **pdcreate** command when you create a default document. You can modify them with the **pdset** command after you create the document or the default document. You can also modify them for the document using the **pdmod** command.

**account-text**  
**address1-text**  
**address2-text**  
**address3-text**  
**address4-text**

## Document/Default Document

**base-printer**  
**bits-per-spot**  
**black-overprint**  
**building-text**  
**callback-number**  
**carriage-control-type**  
**chars**  
**cms-proclink**  
**cms-product**  
**compressed-output**  
**content-orientation**  
**control-strip**  
**convert-to-ebcdic**  
**copy-count**  
**data-fidelity-problem-reported**  
**default-character-mapping**  
**default-input-tray**  
**default-medium**  
**default-printer-resolution**  
**department-text**  
**descriptor** (default document only)  
**destination-company-text**  
**destination-pass-through**  
**document-comment**  
**document-finishing**  
**document-format**  
**dot-shape**  
**email-from-address**  
**email-to-address**  
**enable-settrap**  
**fax-number**  
**fax-to-name**  
**font-fidelity-action**  
**font-processing-messages**  
**font-resolution**  
**form-definition**  
**halftone**  
**image-center-x**  
**image-center-y**  
**image-fit**  
**image-length**  
**image-out-format**  
**image-scale**  
**image-width**  
**input-exit**  
**input-tray-select**  
**jog-between-job-copies**  
**list-of-managers** (default document only)  
**maximum-messages-printed**  
**maximum-transform-pages-ahead**  
**message** (default document only)  
**mvs-class**  
**mvs-destination**  
**mvs-forms**  
**mvs-segment-id**  
**name-text**

new-line-option  
 node-id-text  
 number-up (document only)  
 originating-company-text  
 other-transform-options  
 output-appearance  
 output-bin  
 output-face-up  
 output-format  
 overlay  
 overlay-front  
 overlay-back  
 overprint  
 page-clip  
 page-count (document only)  
 page-definition  
 page-media-select  
 page-select (document only)  
 plex  
 print-quality  
 programmer-text  
 resource-context  
 resource-context-font  
 resource-context-form-definition  
 resource-context-overlay  
 resource-context-page-definition  
 resource-context-page-segment  
 resource-context-user  
 resource-exit  
 room-text  
 scanner-correction  
 screen-frequency  
 segment-file-size  
 shared-formdef  
 shift-out-shift-in  
 sides  
 start-on-new-sheet  
 subject-text  
 table-reference-characters  
 title-text  
 transform-message-file-name  
 transform-output-file-name  
 user-id-text  
 x-image-shift  
 x-image-shift-back  
 y-image-shift  
 y-image-shift-back

## Per-Document Attribute Listing

These attributes can have a different value for each document in a job. For initially settable and resettable per-document attributes, you can specify a different value for each document in a job using the **pdpr** command. Specify **-x** "*AttributeName=value*" before the name of each file.

## Document/Default Document

For example, to print a job consisting of two documents, one with an estimated size of 10 pages and the other with an estimated size of 15 pages, enter:

```
pdpr -x "page-count=10" -f File1 -x "page-count=15" File2
```

**Note:** All documents in a job must have the same value for all initially settable and resettable attributes if

- The job is submitted from tape
- The documents are in ASCII format

## Document/Default Document

### *Initially Settable* document-type

*Resettable*  
black-overprint  
carriage-control-type  
chars  
cms-proclink  
cms-product  
compressed-output  
content-orientation  
convert-to-ebcdic  
copy-count  
default-input-tray  
default-medium  
document-finishing  
document-format  
dot-shape  
enable-settrap  
image-center-x  
image-center-y  
image-fit  
image-length  
image-out-format  
image-scale  
image-width  
input-exit  
medium-map-name  
new-line-option  
other-transform-options  
output-appearance  
output-bin  
output-face-up  
overprint  
page-clip  
page-count  
page-definition  
page-select  
plex  
print-quality  
resource-context-page-definition  
resource-context-user  
resource-exit  
sides  
scanner-correction  
screen-frequency  
shift-out-shift-in  
start-on-new-sheet  
table-reference-characters  
transform-message-file-name  
transform-output-file-name  
x-image-shift  
x-image-shift-back  
y-image-shift  
y-image-shift-back

*Non-Settable*  
document-content  
document-content-list  
document-sequence-number  
initial-value-document  
octet-count

All other document attributes are per-job attributes. They must have the same value for each document in the job.

### **account-text**

Specifies account information that Infoprint prints in the **ACCOUNT:** field of an auxiliary sheet if the job uses the **full** auxiliary-sheet object.

## Document/Default Document

### GUI Label

Account

### DSS

PSF, Email, Fax, Infoprint 2000

### Type

Resettable, single-valued, per-job

### Allowed Values

You can enter a text string of up to 4095 characters that contains the account information.

### Default Value

No default value

### Usage Guidelines

- While you can specify more characters, you should limit the text string you supply to 20 characters or less to ensure that there is enough room available on the printed page for all of the account information.
- If the text string you specify contains blank spaces, enclose the text string in single quotation marks.

## address1-text

Specifies address information that Infoprint prints on the first line of the **ADDRESS:** field of an auxiliary sheet if the job uses the **full** auxiliary-sheet object.

For Fax, this attribute maps to a user-defined customizable field.

### GUI Label

Address line 1

### DSS

PSF, Fax

### Type

Resettable, single-valued, per-job

### Allowed Values

You can enter a text string of up to 4095 characters that contains the address information.

### Default Value

No default value

### Usage Guidelines

- While you can specify more characters, you should limit the value you supply to 57 characters or less to ensure that there is enough room available on the printed page for all address information.
- If the text string you specify contains blank spaces, enclose the text string in single quotation marks.

## address2-text

Specifies address information that Infoprint prints on the second line of the **ADDRESS:** field of an auxiliary sheet if the job uses the **full** auxiliary-sheet object.

For Fax, this attribute maps to a user-defined customizable field.



**GUI Label**

Address line 2

**DSS**

PSF, Fax

**Type**

Resettable, single-valued, per-job

**Allowed Values**

You can enter a text string of up to 4095 characters that contains the address information.

**Default Value**

No default value

**Usage Guidelines**

- While you can specify more characters, you should limit the value you supply to 57 characters or less to ensure that there is enough room available on the printed page for all address information.
- If the text string you specify contains blank spaces, enclose the text string in single quotation marks.

**address3-text**

Specifies address information that Infoprint prints on the third line of the **ADDRESS:** field of an auxiliary sheet if the job uses the **full** auxiliary-sheet object.

For Fax, this attribute maps to a user-defined customizable field.

**GUI Label**

Address line 3

**DSS**

PSF, Fax

**Type**

Resettable, single-valued, per-job

**Allowed Values**

You can enter a text string of up to 4095 characters that contains the address information.

**Default Value**

No default value

**Usage Guidelines**

- While you can specify more characters, you should limit the value you supply to 57 characters or less to ensure that there is enough room available on the printed page for all address information.
- If the text string you specify contains blank spaces, enclose the text string in single quotation marks.

**address4-text**

Specifies address information that Infoprint prints on the fourth line of the **ADDRESS:** field of an auxiliary sheet if the job uses the **full** auxiliary-sheet object.

For Fax, this attribute maps to a user-defined customizable field.

## Document/Default Document

### GUI Label

Address line 4

### DSS

PSF, Fax

### Type

Resettable, single-valued, per-job

### Allowed Values

You can enter a text string of up to 4095 characters that contains the address information.

### Default Value

No default value

### Usage Guidelines

- While you can specify more characters, you should limit the value you supply to 57 characters or less to ensure that there is enough room available on the printed page for all address information.
- If the text string you specify contains blank spaces, enclose the text string in single quotation marks.

## associated-server (Default Document Only)

Indicates the name of the server in which this default document resides.

### DSS

All

### Type

Non-settable, single-valued

### Allowed Values

Infoprint sets this value to the *ServerName*: portion of the argument used with the **pdcreate** command when this default document is created.

### Default Value

No default value

## base-printer

Indicates the printer model you want to RIP the document for.

### GUI Label

RIP for

### DSS

PSF, Infoprint 2000

### Type

Resettable, single-valued, per-job

### Allowed Values

You can enter one of these fixed values:

**InfoprintColor100AFP**

**Infoprint20**

Infoprint32

**Infoprint40**

**Infoprint60**

Infoprint2000  
 Infoprint3000  
 Infoprint4000

**Default Value**

The value of the **printer-model** attribute for the actual destination where the document prints.

**Usage Guidelines**

You can RIP a document for a different printer than you actually print it on. This is useful for printing proof documents.

**bits-per-spot**

Specifies the number of bits used to describe the gray value for each pixel.

**GUI Label**

Bits per spot

**DSS**

3170

**Type**

Non-settable, single-valued, per-job

**Allowed Values**

You can enter an integer value of **2** or **4**.

**Default Value**

No default value

**Usage Guidelines**

- A value of **2** means that each pixel can have one of four levels of gray from 0 to maximum density. A value of **4** means that each pixel can have one of sixteen levels of gray from 0 to maximum density.
- If you do not specify a value for this attribute, Infoprint uses the value in the file specified by the **rip-ini-file** actual destination attribute.

**black-overprint**

Indicates whether to print black over colors.

**GUI Label**

Black overprint

**DSS**

3170

**Type**

Resettable, single-valued, per-document

**Allowed Values**

You can enter one of these fixed values:

<i>Fixed Value</i>	<i>Input Synonym</i>
true	yes
false	no

**Default Value**

No default value

## Document/Default Document

### Usage Guidelines

- Specify **true** to print a colored background with black over it. Specify **false** to omit colors from areas where black will be printed.
- If you do not specify a value for this attribute, Infoprint uses the value in the file specified by the **rip-ini-file** actual destination attribute.

## building-text

Specifies building information that Infoprint prints in the **BUILDING:** field of an auxiliary sheet if the job uses the **full** auxiliary-sheet object.

### GUI Label

Building

### DSS

PSF

### Type

Resettable, single-valued, per-job

### Allowed Values

You can enter a text string of up to 4095 characters that contains the building information.

### Default Value

No default value

### Usage Guidelines

- While you can specify more characters, you should limit the value you supply to 24 characters or less to ensure that there is enough room available on the printed page for all building information.
- If the text string you specify contains blank spaces, enclose the text string in single quotation marks.

## callback-number

Specifies the callback telephone number that appears on the cover sheet of a fax job.

### DSS

Fax

### Type

Resettable, single-valued, per-job

### Allowed Values

You can enter a text string up to 4096 characters long that contains the telephone number.

### Default Value

No default value

## carriage-control-type

Identifies the type of carriage control characters that the printer device uses when interpreting and printing this document.

### GUI Label

Type of carriage control characters

**DSS**

PSF, Email, Fax, Infoprint 2000

**Type**

Resettable, single-valued, per-document

**Allowed Values**

You can enter one of these fixed values:

**ansi-ascii****ansi-ebcdic****machine****none****Default Value****none****Usage Guidelines**

- Infoprint validates and schedules jobs using this attribute against the destination attribute **carriage-control-types-supported**.
- This attribute is valid only for line-data documents.

**chars**

Identifies from zero to four coded fonts used to print a line-data document.

Coded fonts are character set and code page pairs. Coded font names begin with a two-character prefix (X0 or XZ), followed by up to four alphanumeric characters. X042B2 is an example of a coded font name.

**GUI Label**

Fonts

**DSS**

PSF, Email, Fax, Infoprint 2000

**Type**

Resettable, multi-valued, per-document

**Allowed Values**

You can enter a text string that contains the name or global ID of the fonts. The name of each font can be one to four characters long. Omit the two-character prefix from the coded font name or the alternate coded font name.

For the names of coded fonts, refer to *IBM AFP Fonts: Font Summary*.

If you specify more than one coded font on the command line, separate the font names by spaces and surround the attribute and value with double quotation marks, for example:

```
"chars=GT10 GT12"
```

If you specify more than one coded font in the Infoprint administrator's GUI, separate the font names by commas, for example:

```
GT10,GT12
```

**Default Value**

No default value

## Document/Default Document

### Usage Guidelines

- This attribute is valid only for line-data documents.
- If the page definition does not identify fonts, you must specify fonts with this attribute if you want to print in more than one font.
- If you specify more than one coded font with the **chars** attribute, the file must contain table reference characters and you must specify the **table-reference-characters** attribute value as **true**.
- Infoprint uses this attribute only if the page definition specifies no coded fonts. If you specify fonts with this attribute and the page definition also specifies fonts, Infoprint uses the fonts named in the page definition.

## cms-proclink

Identifies the translation table used by the Xeikon color correction program.

### GUI Label

Translation table

### DSS

3170

### Type

Resettable, single-valued, per-document

### Allowed Values

You can enter one of these fixed values:

#### **matchp\_ndtg2xkn\_2**

Match print, normal dot gain, 2 bits per spot

#### **matchp\_ndtg2xkn\_4**

Match print, normal dot gain, 4 bits per spot

#### **swop\_crom2xkn\_2**

SWOP Cromalin, 2 bits per spot

#### **swop\_crom2xkn\_4**

SWOP Cromalin, 4 bits per spot

### Default Value

No default value

### Usage Guidelines

- To enable Xeikon color correction, specify a value of **xeikon** for the **cms-product** attribute or in the file specified by the **rip-ini-file** actual destination attribute.
- If you do not specify a value for this attribute, Infoprint uses the value in the file specified by the **rip-ini-file** actual destination attribute.

## cms-product

Identifies the color correction program.

### GUI Label

Color correction

### DSS

3170

### Type

Resettable, single-valued, per-document

**Allowed Values**

You can enter one of these fixed values:

**xeikon**

**Default Value**

No default value

**Usage Guidelines**

- When Xeikon color correction is enabled, you must specify a translation table using the **cms-proclink** attribute or in the file specified by the **rip-ini-file** actual destination attribute.
- If you do not specify a value for this attribute, Infoprint uses the value in the file specified by the **rip-ini-file** actual destination attribute.

**color-mapping-table**

Identifies the color mapping table (CMT) to be used when printing this document.

**GUI Label**

Color mapping table

**DSS**

PSF

**Type**

Resettable, single-valued, per-job attribute.

**Allowed Values**

You can enter a text string of up to 8 characters that contains the identification for this resource.

**Default Value**

There is no default value. If you omit this attribute or it contains no value, Infoprint uses the color mapping table defined by the actual destination **color-mapping-table** attribute, if any.

**compressed-output**

Indicates whether to compress the RIPped file.

**GUI Label**

Compress output

**DSS**

3170

**Type**

Resettable, single-valued, per-document

**Allowed Values**

You can enter one of these fixed values:

<i>Fixed Value</i>	<i>Input Synonym</i>
<b>true</b>	<b>yes</b>
<b>false</b>	<b>no</b>

**Default Value**

No default value

## Document/Default Document

### Usage Guidelines

If you do not specify a value for this attribute, Infoprint uses the value in the file specified by the **rip-ini-file** actual destination attribute.

## content-orientation

Identifies the page presentation (the placement of data on a page) for the document.

### GUI Label

Orientation

### DSS

AIX, 3170

### Type

Resettable, single-valued, per-document

### Input Synonym

You can use the synonym **orientation**.

### Allowed Values

You can enter one of these fixed values:

**landscape**  
**portrait**  
**reverse-portrait**  
**reverse-landscape**

### Default Value

**AIX** The first value of the destination attribute **content-orientations-supported**  
**3170** No default value

### Usage Guidelines

- Infoprint validates and schedules jobs using this attribute against the destination attribute **content-orientations-supported**.
- For the 3170 DSS, if you do not specify a value for this attribute, Infoprint uses the value in the file specified by the **rip-ini-file** actual destination attribute.

## control-strip

Specifies the control strip to print with this document.

### GUI Label

Control strip

### DSS

3170

### Type

Resettable, single-valued, per-job

### Allowed Values

You can enter a text string of up to 255 characters that contains the name of the control strip.

### Default Value

No default value



**Usage Guidelines**

- The control strip must be pre-RIPped and must reside in the collator.
- If you do not specify a value for this attribute, Infoprint uses the value in the file specified by the **rip-ini-file** actual destination attribute.

**convert-to-ebcdic**

Indicates whether to convert this file from ASCII to EBCDIC before the document prints.

**GUI Label**

Convert to EBCDIC

**DSS**

PSF, Email, Fax, Infoprint 2000

**Type**

Resettable, single-valued, per-document

**Allowed Values**

You can enter one of these fixed values:

<i>Fixed Value</i>	<i>Input Synonym</i>
true	yes
false	no

**Default Value**

No default value

**Usage Guidelines**

- Infoprint validates and schedules jobs using this attribute against the destination attribute **convert-to-ebcdic-supported**.
- This attribute is valid only for line-data documents.

**copies**

See **copy-count**.

**copy-count**

Specifies the number of document copies printed per job copy.

**GUI Label**

Copy count

**DSS**

All

**Type**

Resettable, single-valued, per-document

**Input Synonym**

You can use the synonym **copies**.

**Allowed Values**

You can enter an integer from 1 through 2147483647.

**Default Value**

1

## Document/Default Document

### Usage Guidelines

- Infoprint validates and schedules jobs using this attribute against the destination attribute **maximum-copies-supported**.
- This attribute is not valid for AFP documents with inline resources. To print multiple copies of these documents, use the *job-copies* component of the **results-profile** job attribute.
- For BSD (by default), this document attribute maps to the **qprt -N** option.

## data-fidelity-problem-reported

Indicates the type of data fidelity problems, print-positioning or invalid-character errors, that the destination reports while printing this document.

### GUI Label

Data fidelity problem reported

### DSS

PSF, Infoprint 2000

### Type

Resettable, single-valued, per-job

### Allowed Values

You can enter one of these fixed values:

<i>Fixed Value</i>	<i>Report</i>
<b>all</b>	Both print-positioning and invalid-character errors
<b>character</b>	Only invalid-character errors
<b>none</b>	No errors
<b>position</b>	Only print-positioning errors

### Default Value

**none**

### Usage Guidelines

Infoprint validates and schedules jobs using this attribute against the destination attribute **data-fidelity-problem-reported-supported**.

## default-character-mapping

Defines the character-mapping (codepage) used while printing an ASCII or double-byte character set (DBCS) ASCII document.

### GUI Label

Default character mapping

### DSS

AIX, PSF, Email, Fax, Infoprint 2000

### Type

Resettable, single-valued, per-job

### Allowed Values

You can enter one of these fixed values:

**ibm-437**  
**ibm-850**  
**ibm-860**  
**ibm-863**  
**ibm-865**

**ibm-932**  
**ibm-938** for Infoprint Manager for AIX only  
**ibm-euccn**  
**ibm-eucjp**  
**ibm-euckr**  
**ibm-euctw**

**Default Value**

No default value

**Usage Guidelines**

Infoprint validates and schedules jobs using this attribute against the destination attribute **character-mappings-supported**.

**default-input-tray**

Identifies an input-tray on the printer device that contains the medium that Infoprint uses for normal document pages.

**GUI Label**

Input tray requested

**DSS**

AIX, PSF, Infoprint 2000

**Type**

Resettable, single-valued, per-document

**Allowed Values**

For AIX actual destinations, use one of these values:

<b>auto-envelope-feed</b>	<b>manual-envelope-feed</b>
<b>automatic-tray</b>	<b>middle</b>
<b>auxiliary-envelope</b>	<b>top</b>
<b>auxiliary-paper</b>	<b>tray-1</b>
<b>bottom</b>	<b>tray-2</b>
<b>continuous-form-feed</b>	<b>tray-3</b>
<b>current-selected-tray</b>	<b>tray-4</b>
<b>envelope</b>	<b>tray-5</b>
<b>large-capacity</b>	<b>capacity-2000-sheet</b>
<b>manual</b>	

For PSF and Infoprint 2000 actual destinations, you can enter one of these values or any other value that maps to one of the actual destination **psf-tray-characteristics** attribute values.

**Default Value**

No default value

**Usage Guidelines**

- Infoprint validates and schedules jobs using this attribute against the destination attribute **input-trays-supported**.
- For AIX actual destinations, any input tray selection in the data stream or form definition overrides the value you specify for this attribute.
- For PSF actual destinations, the value you specify for this attribute overrides any input tray selection in the data stream or form definition, with one exception. If you specify different values for this attribute for each document in a job, and also

## Document/Default Document

specify a value for the document **form-definition** attribute, Infoprint ignores the different values and uses the input tray selection in the form definition.

- If this attribute and the **default-medium** attribute have conflicting values, Infoprint uses the value of the **default-medium** attribute.

## default-medium

Identifies the medium for document pages on which this document prints.

### GUI Label

Medium requested

### DSS

AIX, PSF, 3170, Infoprint 2000, Passthrough, IPP

### Type

Resettable, single-valued, per-document

### Allowed Values

**AIX** You can enter a text string of up to 255 characters that contains one of the values listed for the **medium-identifier** attribute for the medium object or a name of a medium you have created. Refer to the medium object **medium-identifier** attribute.

**2000** You can specify any text string that is listed as a supported medium.

**PSF** You can specify any text string that is listed as a supported medium.

### Passthrough

The Passthrough DSS uses this attribute for job validation and scheduling only. It does not affect print output.

### Default Value

No default value

### Usage Guidelines

- Infoprint validates the document against the logical destination attribute **media-supported** and the actual destination attribute **media-supported**.
- Infoprint schedules the document against the actual destination attributes **media-supported** and **media-ready**.
- For AIX actual destinations, any medium selection in the data stream or form definition overrides the value you specify for this attribute.
- For PSF actual destinations, the value you specify for this attribute overrides any medium selection in the data stream or form definition, with one exception. If you specify different values for this attribute for each document in a job, and also specify a value for the document **form-definition** attribute, Infoprint ignores the different values and uses the medium selection in the form definition.
- If this attribute and the **default-input-tray** attribute have conflicting values, Infoprint uses the value of this attribute.
- For Infoprint 2000 actual destinations, the value specified must map to an existing medium object.
- For the 3170 DSS, if you do not specify a value for this attribute, Infoprint uses the smallest medium that the image will fit on.

## default-printer-resolution

Specifies the resolution, in pels, at which the printer device should print this document.

### GUI Label

Printer resolution requested

### DSS

PSF, 3170, Infoprint 2000

### Type

Resettable, single-valued, per-job

### Allowed Values

You can enter one of these fixed values:

<i>Fixed Value</i>	<i>DSS</i>
240	PSF
300	PSF
480	PSF
600	PSF, 3170, Infoprint 2000

### Default Value

PSF 240

3170 600

Infoprint 2000

600

### Usage Guidelines

- This attribute is valid only for GIF, JPEG, PCL, PDF, PostScript, and TIFF documents.
- This attribute applies only to image data. It has no effect on font resolutions.
- Infoprint validates jobs using this attribute against the destination attribute **printer-resolutions-supported**.
- Infoprint schedules jobs using this attribute against the destination attribute **printer-resolutions-ready**.

## department-text

Specifies department information that Infoprint prints in the **DEPARTMENT:** field of an auxiliary sheet if the job uses the **full** auxiliary-sheet object.

### GUI Label

Department

### DSS

PSF

### Type

Resettable, single-valued, per-job

### Allowed Values

You can enter a text string of up to 4095 characters that contains the department information.

### Default Value

No default value

## Document/Default Document

### Usage Guidelines

- While you can specify more characters, you should limit the value you supply to 24 characters or less to ensure that there is enough room available on the printed page for all department information.
- If the text string you specify contains blank spaces, enclose the text string in single quotation marks.

## descriptor (Default Document Only)

Provides a description of this default document.

### DSS

All

### Type

Resettable, single-valued

### Allowed Values

You can enter a text string of up to 4095 characters that describes this default document.

### Default Value

No default value

### Usage Guidelines

The use of this attribute is optional. However, a detailed description helps job submitters to determine if this is the default document they want to use.

## destination-company-text

Specifies the name of the destination company that appears on the fax cover sheet.

### DSS

Fax

### Type

Resettable, single-valued, per-job

### Allowed Values

You can enter a text string up to 4095 characters long that contains the name of the destination company.

### Default Value

No default value

## destination-initial-value-document (Document Only)

Identifies the default document associated with the logical destination to which you submitted the document and that Infoprint used to create the document.

### GUI Label

Default document used

### DSS

All

### Type

Non-settable, single-valued, per-job

**Input Synonym**

You can use the synonym **printer-initial-value-document**.

**Allowed Values**

Infoprint sets this value to the name of the default document used.

**Default Value**

No default value

**destination-pass-through**

Allows you to submit specific DSS (print driver) information along with the document. Infoprint does not process the information, but passes it directly to the DSS.

**GUI Label**

Other options

**DSS**

AIX, BSD, PSF, Infoprint 2000

**Type**

Resettable, single-valued, per-job

**Input Synonyms**

You can use the synonym **printer-pass-through** or **other-options**.

**Allowed Values**

You can enter a text string of up to 4095 characters that contains the DSS information.

**Default Value**

No default value

**Usage Guidelines**

For BSD, Infoprint appends the contents of this attribute to the contents of the actual destination attribute **destination-command** after the mapped options.

**document-comment**

Provides information that Infoprint associates with this document.

**DSS**

AIX, BSD, PSF, Email, Fax, Infoprint 2000

**Type**

Resettable, single-valued, per-job

**Allowed Values**

You can enter a text string of up to 4095 characters that contains information about this document, such as the fonts it requires.

**Default Value**

No default value

**document-content (Document Only)**

Contains the document file identifier.

**DSS**

All

## Document/Default Document

### Type

Non-settable, single-valued, per-document

### Allowed Values

Infoprint sets this value to an internal value that is not displayed on queries.

### Default Value

No default value

## document-content-list (Document Only)

Lists the files in a file-reference document.

### DSS

All

### Type

Non-settable, multi-valued, per-document

### Allowed Values

Infoprint sets this value to a list of file identifiers.

### Default Value

No default value

### Usage Guidelines

A file-reference document is a list of similar printable documents. All the printable documents must have the same format, because Infoprint processes them all the same way.

## document-file-name (Document Only)

Provides the name you want to assign to the file (document).

### GUI Label

File names

### DSS

All

### Type

Non-settable, single-valued, per-document

### Input Synonym

You can use the synonym **file-name**.

### Allowed Values

You can enter a text string of up to 4095 characters that contains the file name or source specified with the **pdpr** command.

### Default Value

The file name of the first document in the job.

## document-finishing

Identifies the finishing options for this document.

### GUI Label

Finishing options



**DSS**

PSF

**Type**

Resettable, multi-valued, per-document

**Allowed Values**

You can enter any of these fixed values:

**z-fold****Default Values**

No default values

**Usage Guidelines**

- When you specify a value for **document-finishing**, Infoprint creates a form definition. Do not use the **form-definition** attribute to specify another form definition.
- Infoprint validates and schedules jobs using this attribute against the destination attribute **document-finishings-supported**.

**document-format**

Identifies the format (data type) of this document.

**GUI Label**

Format

**DSS**

All

**Type**

Resettable, single-valued, per-document

**Input Synonym**You can use the synonym **format**.**Allowed Values**

You can enter one of these fixed values:

<i>Fixed Value</i>	<i>Input Synonym</i>	<i>DSS</i>
<b>ascii</b>		AIX, BSD, PSF (except upload printers), Passthrough, IPP
<b>dbcs-ascii</b>		AIX, BSD, PSF, Infoprint 2000
<b>ditroff</b>		BSD, PSF DSS for AIX, email, fax, Infoprint 2000
<b>d630</b>		AIX, BSD
<b>gif</b>		BSD, PSF DSS for AIX, email, fax, Infoprint 2000
<b>hpgl</b>	<b>hp-gl</b>	AIX, BSD
<b>iso-6429</b>		AIX, BSD, Passthrough, IPP
<b>jpeg</b>		BSD, PSF DSS for AIX, email, fax, Infoprint 2000
<b>kgl</b>		BSD, Infoprint 2000
<b>lcds</b>		BSD
<b>line-data</b>		BSD, PSF, email, fax, Infoprint 2000
<b>metacode</b>		BSD
<b>modca-p</b>	<b>afpds</b>	BSD, PSF, email, fax, Infoprint 2000
<b>passthru</b>		AIX, BSD
<b>pcl</b>	<b>hppcl, hp-pcl</b>	AIX, BSD, PSF, email, fax, Infoprint 2000, Passthrough, IPP
<b>pdf</b>		BSD, PSF, email, fax, Infoprint 2000
<b>postscript</b>	<b>ps</b>	All

## Document/Default Document

<i>Fixed Value</i>	<i>Input Synonym</i>	<i>DSS</i>
ppds		BSD
sap		BSD, PSF DSS for AIX, email, fax, Infoprint 2000, Passthrough
sap-abap		BSD, PSF DSS for AIX, email, fax, Infoprint 2000, Passthrough
simple-text	text	BSD, Passthrough, IPP
tiff		BSD, PSF DSS for AIX, email, fax, Infoprint 2000

**Note:** By default, BSD actual destinations support only a subset of the formats that the BSD DSS can print. You can update the destination attribute **document-format-supported** to include any or all of these values.

### Default Value

The server identifies the document format. If the format cannot be determined, **ascii**

### Usage Guidelines

- If you or a default document you specify do not provide a value for this attribute with the **pdpr** command, the server attempts to determine the file format. If it is unable to determine the format, Infoprint uses the default.
- Infoprint validates and schedules jobs using this attribute against the destination attribute **document-formats-supported**.
- You cannot print ASCII documents and documents with other formats in the same job.

## document-number (Document Only)

See **document-sequence-number**.

## document-sequence-number (Document Only)

Identifies this document in relation to the other documents of a multi-document job.

### DSS

All

### Type

Non-settable, single-valued, per-document

### Input Synonyms

You can use the synonym **sequence-number** or **document-number**.

### Allowed Values

An integer from 1 through 2147483647.

### Default Value

No default value

### Usage Guidelines

Use this number as part of the local ID or global ID to identify a given document within a job.

## document-type (Document Only)

Indicates that the document is either a printable document, a group of printable documents, a font, or some other resource.

**GUI Label**

Types

**DSS**

All

**Type**

Initially settable, single-valued, per-document

**Input Synonym**You can use the synonym **type**.**Allowed Values**

You can enter one of these fixed values:

<i>Fixed Value</i>	<i>DSS</i>
<b>book-ticket-file</b>	3170
<b>color-mapping-table</b>	PSF
<b>cover-sheet</b>	Fax
<b>document-definition</b>	PSF DSS for AIX, 3170, email, fax, Infoprint 2000
<b>email-body</b>	Email
<b>email-signature</b>	Email
<b>file-reference</b>	All
<b>font</b>	PSF, email, fax, Infoprint 2000
<b>form-definition</b>	PSF, email, fax, Infoprint 2000
<b>formatted-job-ticket</b>	PSF, 3170, email, fax, Infoprint 2000
<b>insert-sheet</b>	PSF, email, fax, Infoprint 2000
<b>job-ticket</b>	PSF, 3170, email, fax, Infoprint 2000
<b>overlay</b>	PSF, email, fax, Infoprint 2000
<b>overlay-back</b>	PSF, email, fax, Infoprint 2000
<b>overlay-front</b>	PSF, email, fax, Infoprint 2000
<b>page-definition</b>	PSF, email, fax, Infoprint 2000
<b>page-segment</b>	PSF, email, fax, Infoprint 2000
<b>page-shift-file</b>	PSF, email, fax, Infoprint 2000
<b>printable</b>	All
<b>resource</b>	PSF DSS for AIX, 3170, email, fax, Infoprint 2000
<b>rip-ini-file</b>	3170
<b>variable-data</b>	PSF DSS for AIX, 3170, email, fax, Infoprint 2000

**Default Value****printable****Usage Guidelines**

- A file-reference document is a list of similar printable documents. All the printable documents must have the same format, because Infoprint processes them all the same way.
- Insert documents normally require media sheets from the **insert** input tray, which is on the finisher. This means that you cannot print an insert with the rest of the job. If you want printed inserts, preprint them and load the printed sheets into the **insert** tray.

This does not mean that the insert document should not have any printable content. The insert document should be a MO:DCA-P, PostScript, or TIFF (not ASCII) file containing text like this:

This is an insert sheet.

## Document/Default Document

A MO:DCA-P insert document is supplied with Infoprint Submit. If you submit jobs in other ways, create your own insert document.

If the **insert** input tray is not available (for example, if you are proofing a job on a printer without a finisher), Infoprint prints the insert document on a sheet from the default input bin, so that you can easily see where sheets from the insert tray will be inserted in the final job.

- To print a booklet with a cover, specify **insert** as the document format of the first document in the job.
- A fax job must not include more than one **cover-sheet** document.
- An email job must not include more than one **email-body** document or more than one **email-signature** document.
- Infoprint validates and schedules jobs using this attribute against the destination attribute **document-types-supported**.
- As Infoprint processes your job, it creates a book-ticket file. To override this file, specify the **book-ticket-file** allowed value and include your own book-ticket file with the job. By specifying your own book-ticket file, you can specify the files that you want Infoprint to process, and then provide other files that you **do not** want Infoprint to process for the actual destination. The other files are printed at the actual destination. Remember to ensure that the other files are available at the actual destination, because Infoprint does no checking for files that you do not include with the book-ticket file.
- As Infoprint processes your job, it also creates a temporary rip-ini file. Infoprint uses this temporary rip-ini file to contain the defaults associated with each actual destination and the job attributes supplied with the job.

To override this temporary rip-ini file, specify the **rip-ini-file** allowed value and include your own rip-ini file with the job. By specifying your own rip-ini file, you can specify the job attributes that you want Infoprint to use when ripping the job. The rip-ini file you supply takes effect on the document, and any subsequent documents, until another rip-ini file is provided.

When you supply a rip-ini file, Infoprint reads in the defaults associated with the actual destination, merges in the attributes from the supplied rip-ini file, and then applies the attributes from the document that affect the rip. This combined rip-ini file is used to process the document.

## dot-shape

Indicates the shape of pixels.

### GUI Label

Dot shape

### DSS

3170

### Type

Resettable, single-valued, per-document

### Allowed Values

You can enter a customized value or one of these fixed values:

#### *Fixed Value*

**classic**

**combined**

**sofocles**

**sofocles-not-calibrated**

#### *Equivalent*

/c=r,170,15/m=r,170,75/y=r,170,90/k=r,170,45

/c=c,170,15/m=c,170,75/y=c,170,90/k=c,170,45

/c=l,158,15/m=l,158,75/y=l,158,90/k=l,158,45

/c=ln,158,15/m=ln,158,75/y=ln,158,90/k=ln,158,45

**Default Value**

No default value

**Usage Guidelines**

- Customized values have the following format:

*/color,=shape,lp,angle...*

for example:

*/c=r,170,15/m=r,170,75/y=r,170,90/k=r,170,45*

where:

*color* Indicates the dot color:

<b>c</b>	Cyan
<b>m</b>	Magenta
<b>y</b>	Yellow
<b>b</b>	Black

*shape* Indicates the dot shape:

<b>r</b>	Round
<b>c</b>	Combined
<b>l</b>	Line
<b>ln</b>	Line not calibrated

*lp* Is the screen frequency in lines per inch. Specify **600** for no screening.

*angle* Is the screen angle.

- If you do not specify a value for this attribute, Infoprint uses the value in the file specified by the **rip-ini-file** actual destination attribute.

**email-from-address**

Specifies the electronic mailing address of the sender of this document.

**DSS**

Email

**Type**

Resettable, single-valued, per-job

**Allowed Values**

You can enter a text string up to 4096 characters long that contains the electronic mailing address.

**Default Value**

No default value

**email-to-address**

Specifies the electronic mailing address of the recipient of this document.

**DSS**

Email

**Type**

Resettable, single-valued, per-job

**Allowed Values**

You can enter a text string up to 4096 characters long that contains the electronic mailing address.

## Document/Default Document

### Default Value

No default value

### Usage Guidelines

This value is required for documents submitted to email destinations.

## enable-settrap

Indicates whether to turn on trapping for Quark XPress jobs.

### GUI Label

Enable Quark SetTrap

### DSS

3170

### Type

Resettable, single-valued, per-document

### Allowed Values

You can enter one of these fixed values:

<i>Fixed Value</i>	<i>Input Synonym</i>
true	yes
false	no

### Default Value

No default value

### Usage Guidelines

- The InfoColor 70 receives composite PostScript jobs. Because Quark XPress cannot change the dimensions of PostScript elements to create chokes and spreads with composite PostScript, it sends PostScript codes to indicate what changes are needed. These changes are called the *settrap operators*.
- If you do not specify a value for this attribute, Infoprint uses the value in the file specified by the **rip-ini-file** actual destination attribute.

## fax-number

Specifies the fax number of the recipient of this document.

### DSS

Fax

### Type

Resettable, single-valued, per-job

### Allowed Values

You can enter a text string up to 4096 characters long that contains the fax number.

### Default Value

No default value

### Usage Guidelines

This value is required for documents submitted to fax destinations.

## fax-to-name

Specifies the name of the person to whom this fax document is addressed.

**DSS**

Fax

**Type**

Resettable, single-valued, per-job

**Allowed Values**

You can enter a text string up to 4096 characters long that contains the person's name.

**Default Value**

No default value

**file-name (Document Only)**See **document-file-name**.**font-fidelity-action**

Indicates what Infoprint should do if a font required to print the document is not available in the resolution specified by the data stream, the **font-resolution** attribute, or the actual destination **default-font-resolution** attribute.

**GUI Label**

Font fidelity action

**DSS**

PSF

**Type**

Resettable, single-valued, per-job

**Allowed Values**

You can enter one of these fixed values:

**Fixed Value**

**stop**  
**continue**

**Explanation**

Stop printing the job.  
Attempt to substitute a similar font at a different resolution.

**Default Value**

No default value. If you do not specify a value for this attribute, Infoprint uses the value in the data stream, then the value of the actual destination attribute **default-font-fidelity-action**.

**font-processing-messages**

Indicates whether Infoprint should issue messages when it substitutes a font with a different resolution for a font with the resolution specified by the data stream, the **font-resolution** attribute, or the actual destination **default-font-resolution** attribute.

**GUI Label**

Issue font processing messages

**DSS**

PSF

**Type**

Resettable, single-valued, per-job

## Document/Default Document

### Allowed Values

You can enter one of these fixed values:

<i>Fixed Value</i>	<i>Input Synonym</i>
true	yes
false	no

### Default Value

false

## font-resolution

Identifies the resolution of the fonts used to create this document.

### GUI Label

Font resolution

### DSS

PSF

### Type

Resettable, single-valued, per-job

### Allowed Values

You can enter one of these fixed values:

**240**  
**300**  
**outline**

### Default Value

No default value. If there is no font resolution specified in the data stream and you do not specify a value for this attribute, Infoprint uses the value of the actual destination attribute **default-font-resolution**.

### Usage Guidelines

- The font resolution specified in the data stream overrides this attribute.
- Usually the font resolution and the printer resolution match, but there are two cases when they do not:
  - Some printer devices, for example, the Infoprint 60 and Infoprint 4000, can print fonts of any resolution, although the print head is always 600 pels.
  - It is possible to print a document created with fonts of one resolution on a printer with a different resolution by substituting fonts. Depending on the document, the output may or may not be acceptable.
- Infoprint validates and schedules jobs using this attribute against the destination attribute **font-resolutions-supported**.

## form-definition

Identifies the form definition used when printing this document.

### GUI Label

Form definition

### DSS

PSF, Email, Fax, Infoprint 2000

### Type

Resettable, single-valued, per-job



**Allowed Values**

You can enter a text string of up to 8 characters that contains the identification for this resource.

**Default Value**

No default value. If you omit this attribute or if it contains no value, and if Infoprint does not create a form definition using the values of other document and job attributes, Infoprint uses the form definition defined by the actual destination attribute **form-definition**.

**Usage Guidelines**

- For PSF, if you specify a value for the **document-finishing** or **job-finishing** attribute, Infoprint creates its own form definition. Do not specify a value for this attribute.
- Infoprint does not support inline form definitions in multi-document jobs. If you want to print more than one PostScript document in a single job, configure the **/usr/lpp/psf/ps2afp/ps2afpd.cfg** file to include this line:  

```
device_controls = any
```

and use this attribute to specify a form definition when you submit the job to print.

- For Infoprint 2000, you can specify job-finishing with or without a form definition. Infoprint does not create a form definition for finishing on the Infoprint 2000.

**format**

See **document-format**.

**halftone**

Identifies the desired combination of screen name, output appearance, and calibration to use for printing halftones.

**GUI Label**

Halftone

**DSS**

PSF, Infoprint 2000

**Type**

Resettable, single-valued, complex, per-document

**Syntax**

*screen-name:output-appearance:saved-calibration*

Separate the values with colons, for example:

```
ibm1061pi:dark
```

The *saved-calibration* value is used only for custom halftones.

**Allowed Values**

The value of a **halftone** attribute is a combination of screen name and output appearance in the format: *screen-name:output-appearance*. For custom halftones, the value can also be a combination of screen name, output appearance, and saved calibration in the format: *screen-name:output-appearance:saved-calibration*.

You can enter a customized value or one of these fixed values:

## Document/Default Document

**ibm71lpi:standard**  
**ibm71lpi:highlight-midtones**  
**ibm71lpi:dark**  
**ibm85lpi:standard**  
**ibm85lpi:highlight-midtones**  
**ibm85lpi:dark**  
**ibm106lpi:standard**  
**ibm106lpi:highlight-midtones**  
**ibm106lpi:dark**  
**ibm141lpi:standard**  
**ibm141lpi:highlight-midtones**  
**ibm141lpi:dark**

You can enter one of the following fixed values if you are using enhanced toner on the IP4000 or IP4000-708 printer:

**ibm71lpi:standard.enhtoner**  
**ibm71lpi:highlight-midtones.enhtoner**  
**ibm71lpi:dark.enhtoner**  
**ibm85lpi:standard.enhtoner**  
**ibm85lpi:highlight-midtones.enhtoner**  
**ibm85lpi:dark.enhtoner**  
**ibm106lpi:standard.enhtoner**  
**ibm106lpi:highlight-midtones.enhtoner**  
**ibm106lpi:dark.enhtoner**  
**ibm141lpi:standard.enhtoner**  
**ibm141lpi:highlight-midtones.enhtoner**  
**ibm141lpi:dark.enhtoner**

### Default Value

No default value

### Usage Guidelines

- This document is used only for GIF, JPEG, PDF, PostScript, and TIFF documents.
- Infoprint validates and schedules jobs using this attribute against the actual destination attribute **halftones-supported**.

## image-center-x

Indicates whether to center the image horizontally.

### GUI Label

Center image horizontally

### DSS

3170

### Type

Resettable, single-valued, per-document

### Allowed Values

You can enter one of these fixed values:

<i>Fixed Value</i>	<i>Input Synonym</i>
<b>true</b>	<b>yes</b>
<b>false</b>	<b>no</b>

### Default Value

No default value

**Usage Guidelines**

- This attribute overrides the **x-image-shift** attribute.
- If you do not specify a value for this attribute, Infoprint uses the value in the file specified by the **rip-ini-file** actual destination attribute.

**image-center-y**

Indicates whether to center the image vertically.

**GUI Label**

Center image vertically

**DSS**

3170

**Type**

Resettable, single-valued, per-document

**Allowed Values**

You can enter one of these fixed values:

<i>Fixed Value</i>	<i>Input Synonym</i>
true	yes
false	no

**Default Value**

No default value

**Usage Guidelines**

- This attribute overrides the **y-image-shift** attribute.
- If you do not specify a value for this attribute, Infoprint uses the value in the file specified by the **rip-ini-file** actual destination attribute.

**image-fit**

Specifies how Infoprint adjusts a TIFF, GIF, or JPEG image to fit on the printed page.

**GUI Label**

Image fit

**DSS**

PSF, Email, Fax, Infoprint 2000

**Type**

Resettable, single-valued, per-document

**Allowed Values**

You can specify one of these fixed values:

**position-and-trim**  
**scale-to-fit**

**Default Value**

No default value

**Usage Guidelines**

- When the value of **image-fit** is **position-and-trim**, images larger than the page size are trimmed to fit on any sides that extend beyond the page boundary. For

## Document/Default Document

example, if the top left corner of the image is aligned with the top left corner of the logical page, the right side and bottom of the image are trimmed off.

Use the **x-image-shift**, **x-image-shift-back**, **y-image-shift**, and **y-image-shift-back** attributes to adjust the positioning of the image on the page.

Images smaller than the page size are not changed.

- Images larger than the page size are reduced proportionately in both dimensions to fit. The whole image is preserved, but it is smaller than the original.

Images smaller than the page size are not changed.

- Infoprint validates and schedules jobs using this attribute against the destination attribute **image-fits-supported**.

## image-length

Specifies the length of a page of PostScript, PCL, TIFF, GIF, JPEG, or PDF data after it has been transformed for Infoprint printing.

### GUI Label

Finished page length (inches) or (mm)

### DSS

PSF, 3170, Email, Fax, Infoprint 2000

### Type

Resettable, single-valued, per-document

### Allowed Values

The value you specify is in the form *nnnn.nnnu*

*nnnn.nnn*

is a number that can optionally contain a decimal point.

*u* is the units in inches (**i**) or millimeters (**m**). If you do not specify a unit, the default unit is pels. You cannot use a decimal point when the unit is pels.

For 240-pel resolution printers, valid values are:

<b>16 - 5280</b>	pels
<b>0.067 - 22.000</b>	inches
<b>1.701 - 588.852</b>	millimeters

For 300-pel resolution printers, valid values are:

<b>16 - 6600</b>	pels
<b>0.053 - 22.000</b>	inches
<b>1.346 - 588.852</b>	millimeters

For 480-pel resolution printers, valid values are:

<b>16 - 10560</b>	pels
<b>0.067 - 22.000</b>	inches
<b>0.838 - 588.852</b>	millimeters

For 600-pel resolution printers, valid values are:

<b>16 - 20400</b>	pels
<b>0.267 - 34.000</b>	inches
<b>1.346 - 863.6</b>	millimeters

### Default Value

No default value

### Usage Guidelines

- This attribute is valid only for GIF, JPEG, PCL, PDF, PostScript, and TIFF documents.
- If a text margin is already built into the file, try **image-length=11i** to set the length to 11 inches.
- For the 3170 DSS, if you do not specify a value for this attribute, Infoprint uses the value in the file specified by the **rip-ini-file** actual destination attribute.

## image-out-format

Indicates which type of image data Infoprint produces.

### GUI Label

Image out format

### DSS

PSF, Infoprint 2000

### Type

Resettable, single-valued, per-document

### Allowed Values

For PSF, you can enter one of these fixed values:

<i>Fixed Value</i>	<i>Explanation</i>
<b>ioca-uncompressed</b>	Infoprint produces all image data in the Image Object Content Architecture (IOCA) uncompressed format.
<b>im1</b>	Infoprint produces all image data in IBM's IM uncompressed format. This image format prints on all Infoprint printers.
<b>io1</b>	Infoprint produces all image data in the Image Object Content Architecture uncompressed format.
<b>io1-g4</b>	Infoprint produces all image data in the Image Object Content Architecture compressed G4 Modified Modified Read (MMR) format.
<b>io1-mmr</b>	Infoprint produces all image data in the Image Object Content Architecture compressed Modified Modified Read (MMR) format.
<b>asis</b>	Infoprint produces all image data in the same format as it is in the input file.

For Infoprint 2000, you can only enter this fixed value:

**io1-g4**

### Default Value

No default value

### Usage Guidelines

- This attribute is valid only for GIF, JPEG, line-data, PCL, PDF, PostScript, and TIFF documents.
- Infoprint validates and schedules jobs using this attribute against the destination attribute **image-out-formats-supported**.

## image-scale

Specifies the scaling factor for the image.

## Document/Default Document

### GUI Label

Scale (%)

### DSS

3170

### Type

Resettable, single-valued, per-document

### Allowed Values

You can enter a numeric value from 0 to 2147483647.

The value you specify is in the form *nnnn.nnn*, which is a number that can optionally contain a decimal point. For example, to scale 120%, enter:

1.2

### Default Value

No default value

### Usage Guidelines

If you do not specify a value for this attribute, Infoprint uses the value in the file specified by the **rip-ini-file** actual destination attribute.

## image-width

Specifies the width of a page of PostScript, PCL, TIFF, GIF, JPEG, or PDF data after it has been transformed for Infoprint printing.

### GUI Label

Finished page width (inches) or (mm)

### DSS

PSF, 3170, Email, Fax, Infoprint 2000

### Type

Resettable, single-valued, per-document

### Allowed Values

The value you specify is in the form *nnnn.nnnu*

*nnnn.nnn*

is a number that can optionally contain a decimal point.

*u* is the units in inches (**i**) or millimeters (**m**). If you do not specify a unit, the default unit is pels. You cannot use a decimal point when the unit is pels.

For 240-pel resolution printers, valid values are:

<b>16 - 5280</b>	pels
<b>0.067 - 17.000</b>	inches
<b>1.701 - 431.852</b>	millimeters

For 300-pel resolution printers, valid values are:

<b>16 - 6600</b>	pels
<b>0.053 - 17.000</b>	inches
<b>1.346 - 558.852</b>	millimeters

For 480-pel resolution printers, valid values are:

<b>16 - 10560</b>	pels
<b>0.033 - 17.000</b>	inches
<b>0.838 - 558.852</b>	millimeters

For 600-pel resolution printers, valid values are:

<b>16 - 20400</b>	pels
<b>0.267 - 34.000</b>	inches
<b>1.346 - 863.6</b>	millimeters

### Default Value

No default value

### Usage Guidelines

- This attribute is valid only for GIF, JPEG, PCL, PDF, PostScript, and TIFF documents.
- If a text margin is already built into the file, try **image-width=8.5i** to set the length to 8.5 inches.
- For the 3170 DSS, if you do not specify a value for this attribute, Infoprint uses the value in the file specified by the **rip-ini-file** actual destination attribute.

## initial-value-document (Document Only)

Identifies a default document (within a given server) that Infoprint uses to create this document.

### DSS

All

### Type

Initially settable, single-valued, per-document

### Allowed Values

You can enter a text string of up to 255 characters that contains the name of the desired default document.

### Default Value

No default value

### Usage Guidelines

If you specify this attribute, Infoprint uses the attribute values from the default document to set the document attribute values, unless you override the default document attribute values by supplying attribute values at the command line.

## initial-value-document-identifier (Default Document Only)

Identifies this default document.

### DSS

All

### Type

Non-settable, single-valued

### Allowed Values

Infoprint sets this value to the *DefaultDocumentName* portion of the argument used with the **pdcreate** command when this default document is created.

### Default Value

No default value

### Usage Guidelines

The value for this attribute must be unique within the server.

## input-exit

Specifies the name or the full path name of the input record exit program that Infoprint uses to process this line-data document. With Infoprint Manager for AIX, if you specify the file name without a path, Infoprint searches for the exit program in the paths specified by the **PATH** environment variable. With Infoprint Manager for Windows NT and Windows 2000, you must specify a fully-qualified path name for the exit program. If you do not specify this option, the Infoprint does not use an input record exit program.

### GUI Label

Input exit program

### DSS

PSF, Email, Fax, Infoprint 2000

### Type

Resettable, single-valued, per-document

### Allowed Values

You can enter any valid input record exit program name. The exit program name is case-sensitive.

### Default Value

No default value

### Usage Guidelines

- This attribute is valid only for line-data documents.
- If the input file is unformatted ASCII, but the fonts you are using contain EBCDIC, not ASCII, code points (you specify **convert-to-ebcdic=yes**), you can specify:
  - For Infoprint Manager for AIX:
    - /usr/lpp/psf/bin/apka2e**  
Converts ASCII stream data to EBCDIC stream data.
    - /usr/lpp/psf/bin/asciinpe**  
Converts unformatted ASCII data into a record format and then converts the ASCII stream data to EBCDIC stream data.
  - For Infoprint Manager for Windows NT and Windows 2000
    - \install\_path\bin\apka2e**  
Converts ASCII stream data to EBCDIC stream data.
    - \install\_path\bin\asciinpe**  
Converts unformatted ASCII data into a record format and then converts the ASCII stream data to EBCDIC stream data.
- If your input file uses fonts that have ASCII code points (you specify **convert-to-ebcdic=no**), you should *not* use the **apka2e** or **asciinpe** exit programs. However, if your unformatted ASCII file contains carriage returns and form feeds, you may want to specify the following exit program supplied with Infoprint:
  - For Infoprint Manager for AIX:
    - /usr/lpp/psf/bin/asciinp**  
Converts unformatted ASCII data that contains carriage returns and form feeds into a record format that contains an American National Standards Institute (ANSI) carriage control character. This exit encodes the ANSI carriage control character in byte 0 of every record.
  - For Infoprint Manager for Windows NT and Windows 2000:



*install\_path*\bin\asciinp

Converts unformatted ASCII data that contains carriage returns and form feeds into a record format that contains an American National Standards Institute (ANSI) carriage control character. This exit encodes the ANSI carriage control character in byte 0 of every record.

**input-tray-select**

Use the **default-input-tray** attribute or default to the input tray specified in the data stream or form definition.

**DSS**

PSF

**jog-between-job-copies**

Indicates whether to jog stacked output between job copies.

**GUI Label**

Jog between copies

**DSS**

PSF

**Type**

Resettable, single-valued, per-job

**Allowed Values**

You can enter one of these fixed values:

<i>Fixed Value</i>	<i>Input Synonym</i>
<b>true</b>	<b>yes</b>
<b>false</b>	<b>no</b>

**Default Value**

No default value. If you omit this attribute or it contains no value, output is jogged between job copies on printers that support jog.

**Usage Guidelines**

This attribute controls whether stacked output is jogged (offset) between job copies. When used on printers that do not support jogging output, the value of this attribute is ignored. When used on printers that do support jogging output, if the value of this attribute is **true** or **yes**, the stacked output is jogged. If the value is **false** or **no**, the output is not jogged.

**list-of-managers (Default Document Only)**

Lists the people responsible for this default document.

**DSS**

All

**Type**

Resettable, multi-valued

**Input Synonym**

You can use the synonym **managers**.

**Allowed Values**

You can enter a text string up to 255 characters long, per value, that contains the name or user ID of the person responsible for this default document.

## Document/Default Document

### Default Values

No default values

### Usage Guidelines

This attribute is useful if a user needs to contact someone to report a problem or to request a change.

## logical-destinations-ready (Default Document Only)

Lists the enabled logical destinations that reference this default document.

### DSS

All

### Type

Non-settable, multi-valued

### Input Synonym

You can use the synonym **logical-printers-ready**.

### Allowed Values

Infoprint sets and updates this value with the destination names of the enabled logical destinations that reference this object.

### Default Values

No default values

### Usage Guidelines

- Infoprint sets this attribute when the destination attribute **destination-initial-value-document** of an enabled logical destination references this default document.
- Infoprint removes the destination identification from the list if the destination is disabled.
- You cannot delete this default document while any of the logical destinations identified in this list are enabled.

## logical-printers-ready (Default Document Only)

See **logical-destinations-ready**.

## managers (Default Document Only)

See **list-of-managers**.

## maximum-messages-printed

Specifies the maximum number of error messages Infoprint prints with the job.

### GUI Label

Maximum messages printed

### DSS

PSF, Infoprint 2000

### Type

Resettable, single-valued, per-job

### Allowed Values

You can enter an integer from 0 through 9999.

**Default Value**

9999

**Usage Guidelines**

- This attribute identifies how many error messages Infoprint prints, not how many messages Infoprint generates.
- If the value is:
  - 0** No messages print
  - 9999** All messages print

**maximum-transform-pages-ahead**

Specifies the maximum number of pages by which the Infoprint transform programs can get ahead of the printing process.

**GUI Label**

Maximum pages to transform ahead

**DSS**

PSF

**Type**

Resettable, single-valued, per-job

**Allowed Values**

You can enter an integer from 500 through 2147483647.

**Default Value**

No default value

**Usage Guidelines**

Pages that have been transformed but not printed are stored in a print buffer. Set a value for this attribute to keep the print buffer from overflowing.

**message (Default Document Only)**

Provides a message associated with this default document.

**DSS**

All

**Type**

Resettable, single-valued

**Allowed Values**

You can enter a text string of up to 4095 characters that contains information about this default document.

**Default Value**

No default value

**mvs-class**

For jobs originating on MVS systems and directed to Infoprint through the MVS Download program, this attribute contains the value specified for the MVS **class** parameter. Infoprint can print the class information on an auxiliary sheet if the job uses the **full** auxiliary-sheet object.

**GUI Label**

Class

## Document/Default Document

### DSS

PSF

### Type

Resettable, single-valued, per-job

### Allowed Values

You can enter a single alphanumeric character.

### Default Value

If you do not specify a class value when you submit the job from the MVS system, MVS defaults the value of the **class** parameter to **A**.

### Usage Guidelines

- See the *Print Services Facility/MVS: MVS Download Guide* for further information, including restrictions, on the MVS **class** parameter.
- You can use this attribute within a shell script used with MVS Download.

## mvs-destination

For jobs originating on MVS systems and directed to Infoprint through the MVS Download program, this attribute contains the value specified for the MVS **dest** parameter. Infoprint can print the destination information on an auxiliary sheet if the job uses the **full** auxiliary-sheet object.

### GUI Label

Destination

### DSS

PSF

### Type

Resettable, single-valued, per-job

### Allowed Values

You can enter a one-to-eight character destination name.

### Default Value

No default value

### Usage Guidelines

- See the *Print Services Facility/MVS: MVS Download Guide* for further information, including restrictions, on the MVS **dest** parameter.
- You can use this attribute within a shell script used with MVS Download.

## mvs-forms

For jobs originating on MVS systems and directed to Infoprint through the MVS Download program, this attribute contains the value specified for the MVS **forms** parameter. Infoprint can print the forms information on an auxiliary sheet if the job uses the **full** auxiliary-sheet object.

### GUI Label

Forms

### DSS

PSF

**Type**

Resettable, single-valued, per-job

**Allowed Values**

You can enter a one-to-eight character form name.

**Default Value**

If you do not specify a forms value when you submit the job from the MVS system, MVS defaults the value of the **forms** parameter to an installation-defined default.

**Usage Guidelines**

- See the *Print Services Facility/MVS: MVS Download Guide* for further information on the MVS **forms** parameter.
- You can use this attribute within a shell script used with MVS Download.

**mvs-segment-id**

For line-mode data jobs originating on MVS systems and directed to Infoprint through the MVS Download program, this attribute contains the value specified for the MVS **segment** parameter. The **segment** parameter specifies that output data is segmented into separate data sets consisting of the number of pages specified by the parameter value. The MVS Download program transmits each data set separately.

**GUI Label**

Segment ID

**DSS**

PSF

**Type**

Resettable, single-valued, per-job

**Allowed Values**

You can enter a one-to-ten character segment identifier representing the page count.

**Default Value**

No default value

**Usage Guidelines**

- See the *Print Services Facility/MVS: MVS Download Guide* for further information, including restrictions, on the MVS **segment** parameter.
- You can use this attribute within a shell script used with MVS Download.

**name-text**

Specifies name information that Infoprint prints in the **NAME:** field of an auxiliary sheet if the job uses the **full** auxiliary-sheet object.

**GUI Label**

Name

**DSS**

PSF

**Type**

Resettable, single-valued, per-job

## Document/Default Document

### Allowed Values

You can enter a text string of up to 4095 characters that contains the name information.

### Default Value

No default value

### Usage Guidelines

- While you can specify more characters, you should limit the value you supply to 24 characters or less to ensure that there is enough room available on the printed page for all name information.
- If the text string you specify contains blank spaces, enclose the text string in single quotation marks.

## new-line-option

Identifies how the document input data delimits lines.

### GUI Label

New line option

### DSS

PSF, Email, Fax, Infoprint 2000

### Type

Resettable, single-valued, per-document

### Allowed Values

You can enter one of these fixed values:

#### *Fixed Value*

**two bytes**

**if**

**record,*n***

#### *FILEFORMAT*

**RECORD** (S/370 format record)

**STREAM**

**RECORD,*n*** (S/370 format record data where each line is *n* bytes long)

*n* is an integer from 1 to 32767

### Default Value

**if**

### Usage Guidelines

- This attribute is valid only for line-data documents.
- This attribute corresponds to the **fileformat** print submission parameter information for the **line2afp** transform.

## node-id-text

Specifies node-identification information that Infoprint prints in the **NODEID:** field of an auxiliary sheet.

### GUI Label

Node ID

### DSS

PSF

### Type

Resettable, single-valued, per-job

**Allowed Values**

You can enter a text string of up to 4095 characters that contains the node-identification information.

**Default Value**

No default value

**Usage Guidelines**

- While you can specify more characters, you should limit the value you supply to 10 characters or less to ensure that there is enough room available on the printed page for all node-identification information.
- If the text string you specify contains blank spaces, enclose the text string in single quotation marks.

**number-up**

Specifies the number of pages to print on a single side of the paper when the value of the **output-format** attribute is **side-by-side-copies** or **simple-n-up**.

**GUI Label**

Number up

**DSS**

PSF, Email, Fax, Infoprint 2000

**Type**

Resettable, single-valued, per-job

**Allowed Values**

You can enter one of these fixed values:

<i>Fixed Value</i>	<i>Input Synonym</i>
<b>imposition-simple-1-up</b>	<b>1up</b>
<b>imposition-simple-2-up</b>	<b>2up</b>
<b>imposition-simple-3-up</b>	<b>3up</b>
<b>imposition-simple-4-up</b>	<b>4up</b>

**Default Value**

No default value

**Usage Guidelines**

- In two-sided jobs, the number of pages printed on each sheet is twice the **number-up** value.
- This attribute is not valid for ASCII documents.
- If you specify a value for the document **form-definition** attribute, Infoprint ignores the **number-up** attribute and uses the number-up value in the form definition.
- Infoprint validates and schedules jobs using this attribute against the destination attribute **number-up-supported**.

**object-class**

Identifies the object class to which this object belongs.

**DSS**

All

## Document/Default Document

### Type

Non-settable, single-valued, per-job

### Allowed Values

Infoprint sets this value to **document** for a document or to **initial-value-document** for a default document.

### Default Value

**Document**

**document**

**Default document**

**initial-value-document**

## octet-count (Document Only)

Specifies the document size in octets (bytes).

### GUI Label

Size (KBytes)

### DSS

All

### Type

Non-settable, single-valued, per-document

### Allowed Values

Infoprint computes this value when it creates the document. The value can be an integer from 0 to 9223372036854775800.

### Default Value

The size of the document in bytes (octets).

### Usage Guidelines

- Infoprint uses this attribute to compute total octet count for a job and to provide information about this document.
- For jobs consisting of two or more documents, you can query for the octet count of each document in the job by specifying **-r octet-count** with the **pdls** command.

## offset-stacking-between-job-copies

See **jog-between-job-copies**.

## orientation

See **content-orientation**.

## originating-company-text

Specifies the name of the sending company that appears on the fax cover sheet.

### DSS

Fax

### Type

Resettable, single-valued, per-job

### Allowed Values

You can enter a text string up to 4095 characters long that contains the name of the sending company.



**Default Value**

No default value

**other-options**See **destination-pass-through**.**other-transform-options**

Allows you to submit options for the transform that converts this document to the AFP data stream.

**GUI Label**

Transform options

**DSS**

PSF, Email, Fax, Infoprint 2000

**Type**

Resettable, single-valued, per-document

**Allowed Values**

You can enter a text string of up to 4095 characters that contains the transform options.

**Default Value**

No default value

**Usage Guidelines**

See "Chapter 6. Infoprint Transform Commands" on page 201 for information about transform options.

**output-appearance**

Identifies the desired style of the printed document.

**DSS**

PSF (AIX Only)

**Type**

Resettable, single-valued, per-document

**Allowed Values**

You can enter a customized value or one of these fixed values:

**standard**  
**highlight-midtones**  
**dark**

**Default Value**

No default value

**Usage Guidelines**

- This attribute is valid only for GIF, JPEG, PDF, PostScript, and TIFF documents.
- Infoprint validates and schedules jobs using this attribute against the destination attribute **output-appearances-supported**.

**output-bin**

Specifies the name of the output bin to which you want Infoprint to direct the output from your job.

## Document/Default Document

### GUI Label

Output bin requested

### DSS

PSF, 3170, Infoprint 2000

### Type

Resettable, single-valued, per-document

### Allowed Values

You can enter an output bin name of up to 255 characters that contains the name of an output bin, such as top or staple.

### Default Value

No default value

### Usage Guidelines

- The value you specify for the **output-bin** attribute overrides any output bin specified in the form definition Infoprint uses to process the job.
- For PSF, Infoprint validates and schedules jobs using this attribute against the **output-bins-supported** actual destination attribute, which Infoprint sets according to the values supplied for the **output-bin-numbers** PSF actual destination attribute.
- For PSF, Infoprint maps the value to an actual bin number using the actual destination attribute **output-bin-numbers**.
- For 3170, if you do not specify a value for this attribute, Infoprint uses the value in the file specified by the **rip-ini-file** actual destination attribute.
- For Infoprint 2000,
  - If you don't specify this attribute or the **job finishings=booklet-stitch-and-fold** or the **booklet-stitch-fold-and-trim** attribute, Infoprint uses the output bin specified in the destination attribute.
  - If a job requests stapling or some other finishing, the job goes to the appropriate finishing output bin regardless of what output bin is specified with the **output-bin** attribute.
  - If a job specifies a finishing output bin and no finishing is specified, the job is printed and sent to the top bin.

## output-face-up

Indicates whether to start the document on the side of the sheet that faces up in the output bin.

### GUI Label

Start face down

### DSS

3170

### Type

Resettable, single-valued, per-document

### Allowed Values

You can enter one of these fixed values:

<i>Fixed Value</i>	<i>Input Synonym</i>
true	yes
false	no

**Default Value**

No default value

**Usage Guidelines**

- A value of **true** for this attribute corresponds to a value of **0** for the **outputfaceup** keyword in the **.ini** file and results in face-up output. A value of **false** for this attribute corresponds to a value of **1** for the **outputfaceup** keyword in the **.ini** file and results in face-down output.
- You may want to specify **true** for this attribute when the value of the actual destination attribute **reverse-output** is **true** so that pages will be collated in the right order.
- When printing multiple-document duplex jobs, use this attribute to control whether a document starts on a new sheet. For example, if you specify **output-face-up=false** for the first document in the job, which is 3 pages long, specify **output-face-up=false** for the second document to make it start on a new sheet. Specify **output-face-up=true** for the second document to make it start on the reverse of the last page of the first document. If you specify the same value for all the documents in the job, they will all start on new sheets whether the preceding document has an odd or even number of pages.
- If you do not specify a value for this attribute, Infoprint uses the value in the file specified by the **rip-ini-file** actual destination attribute.

**output-format**

Used with the **number-up** attribute to specify how pages should be imposed on a sheet of paper.

**GUI Label**

Layout format

**DSS**

PSF, Email, Fax, Infoprint 2000

**Type**

Resettable, single-valued, per-job

**Allowed Values**

You can specify one of these fixed values:

**side-by-side-copies**  
**simple-n-up**  
**booklet-print**  
**booklet-print-with-integrated-cover**  
**slit-and-merge**

**Note:** You can only specify **simple-n-up** with the PSF DSS for Windows NT and Windows 2000.

**Default Value**

No default value

**Usage Guidelines**

- **side-by-side-copies** and **simple-n-up** both print as many pages on one sheet as the **number-up** value allows.
  - **side-by-side-copies** prints multiple copies of one page on the sheet.
  - **simple-n-up** prints multiple pages on the sheet in numerical order.

## Document/Default Document

- **booklet-print** and **booklet-print-with-integrated-cover** arrange pages like this:

Page 2 backed by Page 1	Page n-1 backed by Page n
-------------------------------	---------------------------------

so that when the sheet is folded in half and collated with the rest of the booklet, the pages appear in sequence.

To print a booklet with a cover, specify **insert** as the document format of the first document in the job.

**Note:** When the Infoprint server adds blank pages to the job to make it a multiple of four with **booklet-print-with-integrated-cover**, Infoprint adds the blank pages inside of the back cover.

For PSF, to saddle-stitch the booklet, specify a value of **saddle-stitch** for the **job-finishing** job attribute.

For Infoprint 2000, specify **job-finishing=booklet-stitch-and-fold** or **booklet-stitch-fold-and-trim** to send the booklet to the bookletmaker finishing device.

**booklet-print** does not require a value for **number-up**.

- **slit-and-merge** arranges pages like this:

Page 1 backed by Page 2	Page 3 backed by Page 4
-------------------------------	-------------------------------

so that when the sheet is cut in half and the left half is stacked on top of the right half, the pages appear in sequence.

**slit-and-merge** does not require a value for **number-up**.

- You can specify one-sided or two-sided printing and simplex or tumble with any of these formats except **booklet-print**.
- This attribute is not valid for ASCII or KGL documents, or any combination of these documents.
- If you specify a value for the document **form-definition** attribute, Infoprint ignores the **output-format** attribute and uses the value in the form definition.
- Infoprint validates and schedules jobs using this attribute against the destination attribute **output-format-supported**.

## overlay

Specifies the name of an overlay that Infoprint uses for each sheet-side in the document. An overlay contains predefined data, such as lines, shading, text, boxes, or logos that can merge with variable data on a page.

### GUI Label

Medium overlay

### DSS

PSF, Email, Fax, Infoprint 2000

### Type

Resettable, single-valued, per-job

**Allowed Values**

You can enter an overlay name up to eight characters in length.

**Default Value**

No default value

**Usage Guidelines**

This overlay prints in addition to any overlay specified by the form definition for the job, and in addition to the overlays specified in the **overlay-front** and **overlay-back** attributes.

**overlay-back**

Specifies the name of an overlay that Infoprint uses for the back of each sheet in the document. An overlay contains predefined data, such as lines, shading, text, boxes, or logos that can merge with variable data on a page.

**GUI Label**

Medium overlay for back side

**DSS**

PSF, Email, Fax, Infoprint 2000

**Type**

Resettable, single-valued, per-job

**Allowed Values**

You can enter an overlay name up to eight characters in length.

**Default Value**

No default value

**Usage Guidelines**

This overlay prints in addition to any overlay specified by the form definition for the job, and in addition to any overlays specified in the **overlay** and **overlay-front** attributes.

**overlay-front**

Specifies the name of an overlay that Infoprint uses for the front of each sheet in the document. An overlay contains predefined data, such as lines, shading, text, boxes, or logos that can merge with variable data on a page.

**GUI Label**

Medium overlay for front side

**DSS**

PSF, Email, Fax, Infoprint 2000

**Type**

Resettable, single-valued, per-job

**Allowed Values**

You can enter an overlay name up to eight characters in length.

**Default Value**

No default value

## Document/Default Document

### Usage Guidelines

This overlay prints in addition to any overlay specified by the form definition for the job, and in addition to any overlays specified in the **overlay** and **overlay-back** attributes.

## overprint

Indicates how to handle overprinting.

### GUI Label

Overprint

### DSS

3170

### Type

Resettable, single-valued, per-document

### Allowed Values

You can enter one of these fixed values:

<b>overprint-on</b>	Render objects as if they would truly overprint each other
<b>overprint-off</b>	Ignore overprinting
<b>overprint-from-postscript</b>	Handle overprinting according to PostScript specifications, knocking out in separations where the object applies ink

### Default Value

No default value

### Usage Guidelines

If you do not specify a value for this attribute, Infoprint uses the value in the file specified by the **rip-ini-file** actual destination attribute.

## page-clip

Indicates how to clip images that are too wide for the page.

### GUI Label

Clipping

### DSS

3170

### Type

Resettable, single-valued, per-document

### Allowed Values

You can enter one of these fixed values:

<b>center-clip</b>	Center the image horizontally and clip both sides
<b>right-clip</b>	Clip the right side of the image
<b>error</b>	Issue an error message and end the job

### Default Value

No default value

### Usage Guidelines

If you do not specify a value for this attribute, Infoprint uses the value in the file specified by the **rip-ini-file** actual destination attribute.

**page-count (Document Only)**

Specifies the estimated length of the document in pages.

**GUI Label**

Page count

**DSS**

All

**Type**

Resettable, single-valued, per-document

**Allowed Values**

You can enter an integer from 1 through 2147483647.

**Default Value**

When Infoprint can determine a page count from the PostScript or PCL input, Infoprint sets the page count in this attribute.

**Usage Guidelines**

- Infoprint determines the size of a job based on the total number of octets (bytes) in the job. For operator job-management purposes, you may find that job size based on pages is easier.

**Note:** When Infoprint can not estimate document or job size in pages or use the page-count value you specify, the value for the **page-count** attribute should closely represent the actual number of pages in one copy of the document if the operator is to make valid decisions based on page count.

- Infoprint uses the value specified with the **page-count** attribute and the value specified with the **copy-count** document attribute (and the **job-copies** component in the **results-profile**) to calculate the value for the **job-page-count** attribute.

**page-definition**

Identifies the page definition used when printing an ASCII or line-data document.

**GUI Label**

Page definition

**DSS**

PSF, Email, Fax, Infoprint 2000

**Type**

Resettable, single-valued, per-document

**Allowed Values**

You can enter a text string of up to 8 characters that contains the name of the desired page-definition resource.

**Default Value**

No default value

**Usage Guidelines**

You must supply a value for this attribute for line-data documents. This attribute is optional for ASCII documents. It is not valid for any other document format.

## Document/Default Document

### page-media-select

Use the **default-medium** attribute or default to the medium specified in the data stream or form definition.

**DSS**  
PSF

### page-select (Document Only)

Specifies the first and last page of a document that Infoprint prints.

**GUI Label**  
Pages to process

**DSS**  
PSF, Email, Fax, Infoprint 2000

**Type**  
Resettable, single-valued, complex, per-document

#### Syntax

*first-page:last-page*

Separate the values with a colon, for example:

25:48

You can omit the first-page value or the last-page value, for example:

:6  
10:

See “Usage Guidelines”.

#### Components

**first-page:** Specifies the number of the page where printing starts.

*GUI Label:* Lower limit

*Type:* Single-valued

*Allowed Values:* You can enter a value of 1 through 2147483647.

*Default Value:* No default value

**last-page:** Specifies the number of the page where printing ends.

*GUI Label:* Upper limit

*Type:* Single-valued

*Allowed Values:* You can enter a value of 1 through 2147483647.

*Default Value:* No default value



## Usage Guidelines

- Page numbering always starts at one, (**1**) even if the job you print uses an alternate numbering system, such as roman numerals or folio-by-chapter (1-1, 1-2, and so on) numbering. You cannot request a range of pages using page numbers from an alternate numbering system.
- This attribute is not valid for ASCII, KGL, metacode, or lcmds documents.
- If you omit the first-page value, for example **:6**, Infoprint prints from the first page of the job through page 6.
- If you omit the last-page value, for example **6:**, Infoprint prints from page 6 through the last page of the job.
- Entering a combination of first-page last-page values where the first-page value is greater than the last-page value is an error.
- If Infoprint cannot find the first-page value in the document, no pages print and Infoprint issues an error.
- If Infoprint cannot find the last-page value in the document, it prints pages from first-page value to the end of the document. Infoprint does not issue an error.

## plex

Indicates whether Infoprint conditions the page images of this document for one-sided or two-sided printing and the relative orientation of consecutive pages.

### GUI Label

Plex to print

### DSS

AIX, BSD, PSF, 3170, Infoprint 2000

### Type

Resettable, single-valued, per-document

### Allowed Values

You can enter one of these fixed values:

**simplex**  
**tumble**

### Default Value

**AIX** The first value listed in the destination attribute **plexes-supported**

**BSD** No default value

**2000** **simplex**

**PSF** **simplex**

**3170** No default value

### Usage Guidelines

- Infoprint validates and schedules jobs using this attribute against the destination attribute **plexes-supported**.
- Infoprint uses this attribute in combination with the **sides** attribute. The results are:

<b>plex Value</b>	<b>sides Value</b>	<b>Output</b>
<b>simplex</b>	<b>1</b>	Simplex
<b>simplex</b>	<b>2</b>	Duplex
<b>tumble</b>	<b>1</b>	Not valid
<b>tumble</b>	<b>2</b>	Tumble duplex

- Infoprint uses plex specifications in this order:

## Document/Default Document

1. **plex** document attribute unless you specify different values for this attribute for each document in a job, and also specify a value for the document **form-definition** attribute. In that case, Infoprint ignores the document **plex** attribute.
2. For the 3170 DSS, the value in the file specified by the **rip-ini-file** actual destination attribute.
3. The plex specification in the form definition
4. **plex** actual destination attribute

## print-quality

Specifies the desired output quality of the printed document.

### GUI Label

Print quality

### DSS

AIX, BSD

### Type

Resettable, single-valued, per-document

### Allowed Values

You can enter one of these fixed values:

**draft**

**high**

**normal**

### Default Value

**normal**

### Usage Guidelines

Infoprint validates and schedules jobs using this attribute against the destination attribute **print-qualities-supported**.

## printer-initial-value-document (Document Only)

See **destination-initial-value-document**.

## printer-pass-through

See **destination-pass-through**.

## programmer-text

Specifies programmer information that Infoprint prints in the **PROGRAMMER:** field of an auxiliary sheet if the job uses the **full** auxiliary-sheet object.

### GUI Label

Programmer

### DSS

PSF

### Type

Resettable, single-valued, per-job

### Allowed Values

You can enter a text string of up to 4095 characters that contains the programmer information.

**Default Value**

No default value

**Usage Guidelines**

- While you can specify more characters, you should limit the value you specify to 24 characters or less to ensure that there is enough room available on the printed page for all programmer information.
- If the text string you specify contains blank spaces, enclose the text string in single quotation marks.

**resource-context**

Defines the directory path location for all document-specific resources: fonts, form definitions, overlays, page definitions, and page segments.

**GUI Label**

Location of resources

**DSS**

PSF, Email, Fax, Infoprint 2000

**Type**

Resettable, single-valued, per-job

**Allowed Values**

You can enter the name of a resource-context object or a text string of up to 255 characters that contains a specific directory path name for resources.

**Syntax**

*path:path* on AIX

*path;path* on Windows NT or Window 2000

Separate multiple paths with a colon on AIX or a semicolon on Windows NT or Window 2000, for example with AIX:

*/res:/dept123/res*

**Default Value**

No default value

**Usage Guidelines**

- Because Infoprint searches the path specified by this attribute *after* the individual paths for different types of resources, you can use this attribute to locate default resources.
- You can use this attribute instead of specifying individual values for:
  - color-mapping-table**
  - resource-context-font**
  - resource-context-form-definition**
  - resource-context-overlay**
  - resource-context-page-definition**
  - resource-context-page-segment**
- Infoprint searches paths in this order:
  1. **color-mapping-table** document attribute
  2. **resource-context-user** document attribute

## Document/Default Document

3. **resource-context-font**, **resource-context-form-definition**, **resource-context-overlay**, **resource-context-page-definition**, or **resource-context-page-segment** document attribute, as appropriate for the type of resource
  4. **resource-context** document attribute
  5. **PSFPATH** environment variable
  6. **resource-context-font**, **resource-context-form-definition**, **resource-context-overlay**, **resource-context-page-definition**, or **resource-context-page-segment** actual destination attribute, as appropriate for the type of resource
  7. With AIX:
    - a. **/usr/lpp/psf/reslib**
    - b. **/usr/lpp/afpfonts**
    - c. **/usr/lpp/psf/fontlib**
  8. With Windows NT or Window 2000, where *install\_path* indicates the path where you installed Infoprint Manager:
    - a. **\install\_path\reslib**
    - b. **\install\_path\afpfonts**
    - c. **\install\_path\fontlib**
- If Infoprint cannot find the resource because none of the paths contain the resource, it still processes the job and prints error messages at the end of the job. Infoprint reports the job as completed.

## resource-context-font

Defines the directory path location of the document-specific fonts.

### GUI Label

Location of fonts

### DSS

PSF, Email, Fax, Infoprint 2000

### Type

Resettable, single-valued, per-job

### Allowed Values

You can enter the name of a resource-context object or a text string of up to 255 characters that contains a specific directory path name for fonts.

### Syntax

*path:path* on AIX

*path;path* on Windows NT or Window 2000

Separate multiple paths with a colon on AIX or a semicolon on Windows NT or Window 2000, for example with AIX:

*/fonts:/dept123/fonts*

### Default Value

For Infoprint Manager for AIX, **/usr/lpp/psf/reslib**.

For Infoprint Manager for Windows NT and Windows 2000, **\install\_path\reslib**.

## Usage Guidelines

- You can specify fonts either within the job or in a page definition for the job.
- Infoprint searches paths in this order:
  1. **resource-context-user** document attribute
  2. **resource-context-font** document attribute
  3. **resource-context** document attribute
  4. **PSFPATH** environment variable
  5. **resource-context-font** actual destination attribute
  6. With AIX:
    - a. **/usr/lpp/psf/reslib**
    - b. **/usr/lpp/afpfonts**
    - c. **/usr/lpp/psf/fontlib**
  7. With Windows NT or Window 2000, where *install\_path* indicates the path where you installed Infoprint Manager:
    - a. **\install\_path\reslib**
    - b. **\install\_path\afpfonts**
    - c. **\install\_path\fontlib**
- If Infoprint cannot find the resource because none of the paths contain the resource, it still processes the job and prints error messages at the end of the job. Infoprint reports the job as completed.

## resource-context-form-definition

Defines the directory path location of the document-specific form definitions.

### GUI Label

Location of form definitions

### DSS

PSF, Email, Fax, Infoprint 2000

### Type

Resettable, single-valued, per-job

### Allowed Values

You can enter the name of a resource-context object or a text string of up to 255 characters that contains a specific directory path name for form definitions.

### Syntax

*path:path* on AIX

*path;path* on Windows NT or Window 2000

Separate multiple paths with a colon on AIX and a semicolon on Windows NT or Window 2000, for example with AIX:

*/form\_definition:/dept123/form\_definition*

### Default Value

For Infoprint Manager for AIX, **/usr/lpp/psf/reslib**.

For Infoprint Manager for Windows NT and Windows 2000, **\install\_path\reslib**.

## Usage Guidelines

- You can use either the document or the actual destination **form-definition** attribute to specify the form definition.

## Document/Default Document

- Infoprint searches paths in this order:
  1. **resource-context-user** document attribute
  2. **resource-context-form-definition** document attribute
  3. **resource-context** document attribute
  4. **PSFPATH** environment variable
  5. **resource-context-form-definition** actual destination attribute
  6. For Infoprint Manager for AIX, **/usr/lpp/psf/reslib**; for Infoprint Manager for Windows NT and Windows 2000, **\install\_path\reslib**.
- If Infoprint cannot find the resource because none of the paths contain the resource, it still processes the job and prints error messages at the end of the job. Infoprint reports the job as completed.

## resource-context-overlay

Defines the directory path location of the document-specific overlays.

### GUI Label

Location of overlays

### DSS

PSF, Email, Fax, Infoprint 2000

### Type

Resettable, single-valued, per-job

### Allowed Values

You can enter the name of a resource-context object or a text string of up to 255 characters that contains a specific directory path name for overlays.

### Syntax

*path:path* on AIX

*path;path* on Windows NT or Window 2000

Separate multiple paths with a colon on AIX and a semicolon on Windows NT or Window 2000, for example with AIX:

*/overlay:/dept123/overlay*

### Default Value

For Infoprint Manager for AIX, **/usr/lpp/psf/reslib**.

For Infoprint Manager for Windows NT and Windows 2000, **\install\_path\reslib**.

### Usage Guidelines

- You use a form definition for the job to specify the overlay.
- Infoprint searches paths in this order:
  1. **resource-context-user** document attribute
  2. **resource-context-overlay** document attribute
  3. **resource-context** document attribute
  4. **PSFPATH** environment variable
  5. **resource-context-overlay** actual destination attribute
  6. For Infoprint Manager for AIX, **/usr/lpp/psf/reslib**; for Infoprint Manager for Windows NT and Windows 2000, **\install\_path\reslib**.
- If Infoprint cannot find the resource because none of the paths contain the resource, it still processes the job and prints error messages at the end of the job. Infoprint reports the job as completed.

## resource-context-page-definition

Defines the directory path location of the document-specific page definitions.

### GUI Label

Location of page definitions

### DSS

PSF, Email, Fax, Infoprint 2000

### Type

Resettable, single-valued, per-document

### Allowed Values

You can enter the name of a resource-context object or a text string of up to 255 characters that contains a specific directory path name for page definitions.

### Syntax

*path:path* on AIX

*path;path* on Windows NT or Windows 2000

Separate multiple paths with a colon on AIX and a semicolon on Windows NT or Windows 2000, for example with AIX:

*/page\_definition:/dept123/page\_definition*

### Default Value

For Infoprint Manager for AIX, */usr/lpp/psf/reslib*.

For Infoprint Manager for Windows NT and Windows 2000, *\install\_path\reslib*.

### Usage Guidelines

- This attribute is valid only for line-data documents.
- You use the **page-definition** document attribute to specify the page definition for the job.
- Infoprint searches paths in this order:
  1. **resource-context-user** document attribute
  2. **resource-context-page-definition** document attribute
  3. **resource-context** document attribute
  4. **PSFPATH** environment variable
  5. **resource-context-page-definition** actual destination attribute
  6. For Infoprint Manager for AIX, */usr/lpp/psf/reslib*; for Infoprint Manager for Windows NT and Windows 2000, *\install\_path\reslib*.
- If Infoprint cannot find the resource because none of the paths contain the resource, it still processes the job and prints error messages at the end of the job. Infoprint reports the job as completed.

## resource-context-page-segment

Defines the directory path location of the document-specific page segments.

### GUI Label

Location of page segments

### DSS

PSF, Email, Fax, Infoprint 2000

## Document/Default Document

### Type

Resettable, single-valued, per-job

### Allowed Values

You can enter the name of a resource-context object or a text string of up to 255 characters that contains a specific directory path name for page segments.

### Syntax

*path:path* for AIX

*path;path* for Windows NT or Window 2000

Separate multiple paths with a colon on AIX and a semicolon on Windows NT or Window 2000, for example with AIX:

*/page\_segment:/dept123/page\_segment*

### Default Value

For Infoprint Manager for AIX, ***/usr/lpp/psf/reslib***.

For Infoprint Manager for Windows NT and Windows 2000, ***\install\_path\reslib***.

### Usage Guidelines

- You specify the page segments within the job.
- Infoprint searches paths in this order:
  1. **resource-context-user** document attribute
  2. **resource-context-page-segment** document attribute
  3. **resource-context** document attribute
  4. **PSFPATH** environment variable
  5. **resource-context-page-segment** actual destination attribute
  6. For Infoprint Manager for AIX, ***/usr/lpp/psf/reslib***; for Infoprint Manager for Windows NT and Windows 2000, ***\install\_path\reslib***.
- If Infoprint cannot find the resource because none of the paths contain the resource, it still processes the job and prints error messages at the end of the job. Infoprint reports the job as completed.

## resource-context-user

Defines the directory path location for all document-specific resources: fonts, form definitions, overlays, page definitions, and page segments.

### GUI Label

Location of document resources

### DSS

PSF, Email, Fax, Infoprint 2000

### Type

Resettable, single-valued, per-document

### Allowed Values

You can enter the name of a resource-context object or a text string of up to 255 characters that contains a specific directory path name for resources.

### Syntax

*path:path* for AIX

*path;path* for Windows NT or Window 2000



Separate multiple paths with a colon on AIX and a semicolon on Windows NT or Window 2000, for example with AIX:

```
/res:/dept123/res
```

### Default Value

No default value

### Usage Guidelines

- This attribute is valid only for line-data documents.
- You should use this attribute only to migrate the PSF for AIX job script keyword **userlib**.
- Infoprint searches paths in this order:
  1. **resource-context-user** document attribute
  2. **resource-context-font**, **resource-context-form-definition**, **resource-context-overlay**, **resource-context-page-definition**, or **resource-context-page-segment** document attribute, as appropriate for the type of resource
  3. **resource-context** document attribute
  4. **PSFPATH** environment variable
  5. **resource-context-font**, **resource-context-form-definition**, **resource-context-overlay**, **resource-context-page-definition**, or **resource-context-page-segment** actual destination attribute, as appropriate for the type of resource
  6. With AIX:
    - a. **/usr/lpp/psf/reslib**
    - b. **/usr/lpp/afpfonts**
    - c. **/usr/lpp/psf/fontlib**
  7. With Windows NT or Window 2000, where *install\_path* indicates the path where you installed Infoprint Manager:
    - a. **\install\_path\reslib**
    - b. **\install\_path\afpfonts**
    - c. **\install\_path\fontlib**
- If Infoprint cannot find the resource because none of the paths contain the resource, it still processes the job and prints error messages at the end of the job. Infoprint reports the job as completed.

## resource-exit

Specifies the name or the full path name of the resource exit program that Infoprint uses to retrieve resources for this line-data document. If you specify the file name without a path, Infoprint searches for the exit program in the paths specified by the **PATH** environment variable. If you do not specify this option, the Infoprint does not use a resource exit program.

### GUI Label

Resource exit program

### DSS

PSF, Infoprint 2000

### Type

Resettable, single-valued, per-document

## Document/Default Document

### Allowed Values

You can enter any valid input record exit program name. The exit program name is case-sensitive.

### Default Value

No default value

### Usage Guidelines

This attribute is valid only for line-data documents.

## room-text

Specifies room information that Infoprint prints in the **ROOM:** field of an auxiliary sheet if the job uses the **full** auxiliary-sheet object.

### GUI Label

Room

### DSS

PSF

### Type

Resettable, single-valued, per-job

### Allowed Values

You can enter a text string of up to 4095 characters that contains the room information.

### Default Value

No default value

### Usage Guidelines

- While you can specify more characters, you should limit the value you supply to 24 characters or less to ensure that there is enough room available on the printed page for all room information.
- If the text string you specify contains blank spaces, enclose the text string in single quotation marks.

## scanner-correction

Indicates how you calibrated the scanner used to scan input images so that Infoprint can make the appropriate modifications to halftones.

### GUI Label

Scanner correction

### DSS

PSF (AIX Only)

### Type

Resettable, single-valued, per-document

### Allowed Values

You can enter one of these fixed values:

**Ricoh420**  
**XeroxDocuimage620S**  
**none**

### Default Value

No default value

**Usage Guidelines**

- This attribute is valid only for GIF, JPEG, PDF, PostScript, and TIFF documents.
- Infoprint validates and schedules jobs using this attribute against the destination attribute **scanner-corrections-supported**.

**screen-frequency**

Indicates the screen frequency, in lines per inch, to use for printing halftones.

**DSS**

PSF (AIX Only)

**Type**

Resettable, single-valued, per-document

**Allowed Values**

You can enter one of these fixed values:

**71**

**85**

**106**

**141**

**Default Value**

**85**

**Usage Guidelines**

- This attribute is valid only for GIF, JPEG, PDF, PostScript, and TIFF documents.
- Change the screen frequency if you see moire or two-dimensional repeating patterns in halftone images.
- Set the screen frequency to **106** if you see dark and light bands in printed output, with halftone images possibly showing a herringbone pattern under magnification.
- Infoprint validates and schedules jobs using this attribute against the destination attribute **screen-frequencies-supported**.

**segment-file-size**

Specifies the minimum size in kilobytes of the segment files into which Infoprint breaks jobs for processing.

**GUI Label**

Size of segment file (KBytes)

**DSS**

PSF

**Type**

Resettable, single-valued, per-job

**Allowed Values**

You can enter an integer from 1 to 102400.

**Default Value**

**100**

**Usage Guidelines**

Small values can adversely affect performance; large numbers can detract from Infoprint's ability to send the beginning of a job to a destination while still processing the remainder of the job.

## Document/Default Document

### sequence-number (Document Only)

See **document-sequence-number**.

### shared-formdef

For MO:DCA-P documents originating on MVS systems and directed to Infoprint through the MVS Download program, this attribute Indicates whether the form definition used to print or transmit this document should be processed the same way as PSF/MVS would process it.

#### GUI Label

Process form definitions same as MVS

#### DSS

PSF, Email, Fax, Infoprint 2000

#### Type

Resettable, single-valued, per-job

#### Allowed Values

You can enter one of these fixed values:

<i>Fixed Value</i>	<i>Input Synonym</i>
<b>true</b>	<b>yes</b>
<b>false</b>	<b>no</b>

#### Default Value

<b>Default job</b>	No default value
<b>Job</b>	<b>false</b>

#### Usage Guidelines

- A value of **true** ensures consistent page placement when multiple pages are printed or transmitted on a single side of the sheet.
- If the document was created with a form definition defined specifically for the PSF DSS or for PSF for AIX, specify **false**.

### shift-out-shift-in

Specifies the printer scanning modes used when processing EBCDIC line-data that prints with either a single-byte or a double-byte font.

#### GUI Label

Shift-out shift-in processing

#### DSS

PSF, Email, Fax, Infoprint 2000

#### Type

Resettable, single-valued, per-document

#### Allowed Values

You can enter an 8-character alphanumeric string, which is passed to all ACIF user exits, or one of these fixed values:

<i>Fixed Value</i>	<i>Explanation</i>
<b>one</b>	The <b>line2afp</b> transform uses a value of <b>SOSI1</b> for the <b>prmode=</b> parameter. It converts each shift-out, shift-in code to a blank and a Set Coded Font Local text control.

**two**

The **line2afp** transform uses a value of **SOSI2** for the **prmode=** parameter. It converts each shift-out, shift-in code to a Set Coded Font Local text control.

See “line2afp Command: Transforms S/370 Line Data and ASCII Data to AFP” on page 236 for more information about the **prmode=** parameter of the **line2afp** transform. Refer to *AFP Conversion and Indexing Facility: User’s Guide* for information about ACIF user exits.

**Default Value**

No default value

**Usage Guidelines**

- This attribute is valid only for line-data documents.
- For the shift-in, shift-out process to work correctly, two coded fonts must be specified by the **chars** attribute or the page definition. The first must be a single-byte font and the second must be a double-byte font.

**sides**

Specifies the number of media sides on which this document prints.

**GUI Label**

Sides to print

**DSS**

AIX, BSD, PSF, 3170, Infoprint 2000

**Type**

Resettable, single-valued, per-document

**Allowed Values**You can enter an integer value of **1** or **2**.**Default Value****AIX** 1**BSD** No value; the printer device defaults the value**PSF** The value in the form definition**3170** No default value**Usage Guidelines**

- Infoprint validates and schedules jobs using this attribute against the destination attribute **sides-supported**.
- Infoprint uses this attribute in combination with the **plex** attribute. The results are:

<b>sides Value</b>	<b>plex Value</b>	<b>Output</b>
1	<b>simplex</b>	Simplex
2	<b>simplex</b>	Duplex
1	<b>tumble</b>	Not valid
2	<b>tumble</b>	Tumble duplex

- Infoprint uses sides specifications in this order:
  1. **sides** document attribute, unless you specify different values for this attribute for each document in a job, and also specify a value for the document **form-definition** attribute. In that case, Infoprint ignores the document **sides** attribute.

## Document/Default Document

2. For the 3170 DSS, the value in the file specified by the **rip-ini-file** actual destination attribute.
3. The sides specification in the form definition
4. **sides** actual destination attribute

## start-on-new-sheet

Indicates whether to start printing this document on a new sheet of paper.

### GUI Label

Start on new sheet

### DSS

PSF, Infoprint 2000

### Type

Resettable, single-valued, per-document

### Allowed Values

You can enter one of these fixed values:

<i>Fixed Value</i>	<i>Input Synonym</i>
true	yes
false	no

### Default Value

true

### Usage Guidelines

- When you print multiple-document jobs and do not want blank pages between the end of one document and the beginning of the next, set this attribute to **false**.
- If you specify a form definition, it takes priority over the **start-on-new-sheet** attribute, and any value you specify with **start-on-new-sheet** is ignored. Infoprint ignores the **start-on-new-sheet** attribute and uses the value in the form definition.

## subject-text

Specifies the subject text that appears on the cover sheet of fax jobs or the subject line of electronic mail jobs.

### DSS

Email, Fax

### Type

Resettable, single-valued, per-job

### Allowed Values

You can enter a text string up to 4095 characters long that contains the subject.

### Default Value

No default value

## table-reference-characters

Specifies whether the first character of each line in the document (or second character, if carriage control characters are used) is a table reference character. A table reference character selects a font character set named by the **chars** attribute or in the page definition used to print the job.

**GUI Label**

Table reference characters

**DSS**

PSF, Email, Fax, Infoprint 2000

**Type**

Resettable, single-valued, per-document

**Allowed Values**

You can enter one of these fixed values:

<i>Fixed Value</i>	<i>Input Synonym</i>
<b>true</b>	<b>yes</b>
<b>false</b>	<b>no</b>

**Default Value**

No default value

**Usage Guidelines**

- This attribute is valid only for line-data documents.
- Infoprint validates and schedules jobs using this attribute against the destination attribute **table-reference-characters-supported**.
- If the value of this attribute is **true** and the page definition does not identify fonts, you must specify fonts with the **chars** attribute.
- If the line data contains TRCs and you do not specify this attribute, your printed output will not be correct. Infoprint interprets the TRCs as text characters instead of font identifiers.

**title-text**

Specifies title information that Infoprint prints in the **TITLE:** field of an auxiliary sheet if the job uses the **full** auxiliary-sheet object.

**GUI Label**

Title

**DSS**

PSF

**Type**

Resettable, single-valued, per-job

**Allowed Values**

You can enter a text string of up to 4095 characters that contains the title information.

**Default Value**

No default value

**Usage Guidelines**

- While you can specify more characters, you should limit the value you supply to 55 characters or less to ensure that there is enough room available on the printed page for all title information.
- If the text string you specify contains blank spaces, enclose the text string in single quotation marks.

## Document/Default Document

### transfer-method (Document Only)

Identifies the method by which Infoprint transfers the document to the print server.

#### GUI Label

Transferred to server

#### DSS

All

#### Type

Initially settable, single-valued, per-job

#### Allowed Values

You can enter one of these fixed values:

**pipe-pull**

**with-request**

#### Default Value

**pipe-pull**

#### Usage Guidelines

Infoprint validates jobs using this attribute against the server attribute **transfer-methods-supported**.

### transform-message-file-name

Specifies the file name where the transform that Infoprint uses to process this document writes messages.

#### GUI Label

Transform message file

#### DSS

PSF, Email, Fax, Infoprint 2000

#### Type

Resettable, single-valued, per-document

#### Allowed Values

You can enter a text string of up to 4095 characters that contains the file name.

#### Default Value

No default value. If you do not specify this attribute or if it has no value, the transform writes messages to **\$PDBASE/servername/error.log** for Infoprint Manager for AIX and **\workspace path\servername/error.log** for Infoprint Manager for Windows NT and Windows 2000.

#### Usage Guidelines

This attribute is valid only for line-data documents.

### transform-output-file-name

Specifies the file name of the output file produced by the Infoprint transform that converts this document to the AFP data stream.

#### GUI Label

Transform output file name

#### DSS

PSF, Email, Fax, Infoprint 2000



**Type**

Resettable, single-valued, per-document

**Allowed Values**

You can enter a text string of up to 4095 characters that contains the file name.

**Default Value**

No default value unless the output format is **side-by-side-copies** or **booklet-print**. In that case, Infoprint saves the transformed file in the directory specified by the **PDBASE** environment variable or in one of its subdirectories.

**Usage Guidelines**

- Use this attribute to save transformed files.
- Transform programs write output to a temporary file in the directory specified by the **PDBASE** environment variable or in one of its subdirectories. No single user can create a file larger than the amount of free space in the file system containing this directory. If many users are submitting print jobs that invoke transform programs, the directory may fill up and prevent all users from successfully running the transform programs.

**type (Document Only)**

See **document-type**.

**user-id-text**

Specifies user-identification information that Infoprint prints at the top of the page and in the **USERID:** field of an auxiliary sheet.

**GUI Label**

User ID

**DSS**

PSF

**Type**

Resettable, single-valued, per-job

**Allowed Values**

You can enter a text string of up to 4095 characters that contains the user-identification information.

**Default Value**

No default value

**Usage Guidelines**

- While you can specify more characters, you should limit the value you supply to 10 characters or less to ensure that there is enough room available on the printed page for all user-identification information.
- If the text string you specify contains blank spaces, enclose the text string in single quotation marks.

**x-image-shift**

Specifies the X offset, in millimeters, of the logical page origin to the right of the physical page origin.

**GUI Label**

Move image right (inches) or (mm)

## Document/Default Document

### DSS

PSF, 3170, Email, Fax, Infoprint 2000

### Type

Resettable, single-valued, per-document

### Allowed Values

You can enter a numeric value from -577.99 mm to 577.97 mm.

The value you specify is in the form *nnnn.nnn*, which is a number that can optionally contain a decimal point. Millimeters is the unit of measure for the value you specify.

### Default Value

No default value

### Usage Guidelines

- This attribute overrides any X-offset value in the form definition Infoprint uses for the job, with one exception. If you specify different values for this attribute for each document in a job, and also specify a value for the document **form-definition** attribute, Infoprint ignores the **x-image-shift** attribute and uses the X-offset value in the form definition.
- For the 3170 DSS, the **image-center-x** attribute overrides this attribute.
- For the 3170 DSS, if you do not specify a value for this attribute, Infoprint uses the value in the file specified by the **rip-ini-file** actual destination attribute.
- Infoprint validates and schedules jobs using this attribute against the **x-image-shift-range-supported** actual destination attribute.

## x-image-shift-back

Specifies the X offset, in millimeters, of the logical page origin to the right of the physical page origin on the back side of a double-sided sheet.

### GUI Label

Move image right on back side (inches) or (mm)

### DSS

PSF, Infoprint 2000

### Type

Resettable, single-valued, per-document

### Allowed Values

You can enter a numeric value from -577.99 mm to 577.97 mm.

The value you specify is in the form *nnnn.nnn*, which is a number that can optionally contain a decimal point. Millimeters is the unit of measure for the value you specify.

### Default Value

No default value

### Usage Guidelines

- This attribute is not valid for ASCII documents.
- If you specify a value for the document **form-definition** attribute, Infoprint ignores the **x-image-shift-back** attribute and uses the X-offset value in the form definition. This attribute overrides the X-offset value in any other form definition.

- Infoprint validates and schedules jobs using this attribute against the **x-image-shift-range-supported** actual destination attribute.

## y-image-shift

Specifies the Y offset, in millimeters, of the logical page origin below the physical page origin.

### GUI Label

Move image down (inches) or (mm)

### DSS

PSF, 3170, Email, Fax, Infoprint 2000

### Type

Resettable, single-valued, per-document

### Allowed Values

You can enter a numeric value from -577.99 mm to 577.97 mm.

The value you specify is in the form *nnnn.nnn*, which is a number that can optionally contain a decimal point. Millimeters is the unit of measure for the value you specify.

### Default Value

No default value

### Usage Guidelines

- This attribute overrides any Y-offset value in the form definition Infoprint uses for the job, with one exception. If you specify different values for this attribute for each document in a job, and also specify a value for the document **form-definition** attribute, Infoprint ignores the **y-image-shift** attribute and uses the Y-offset value in the form definition.
- For the 3170 DSS, the **image-center-y** attribute overrides this attribute.
- For the 3170 DSS, if you do not specify a value for this attribute, Infoprint uses the value in the file specified by the **rip-ini-file** actual destination attribute.
- Infoprint validates and schedules jobs using this attribute against the **y-image-shift-range-supported** actual destination attribute.

## y-image-shift-back

Specifies the Y offset, in millimeters, of the logical page origin below the physical page origin on the back side of a double-sided sheet.

### GUI Label

Move image down on back side (inches) or (mm)

### DSS

PSF, Infoprint 2000

### Type

Resettable, single-valued, per-document

### Allowed Values

You can enter a numeric value from -577.99 mm to 577.97 mm.

## Document/Default Document

The value you specify is in the form *nnnn.nnn*, which is a number that can optionally contain a decimal point. Millimeters is the unit of measure for the value you specify.

### Default Value

No default value

### Usage Guidelines

- This attribute is not valid for ASCII documents.
- If you specify a value for the document **form-definition** attribute, Infoprint ignores the **y-image-shift-back** attribute and uses the Y-offset value in the form definition. This attribute overrides the Y-offset value in any other form definition.
- Infoprint validates and schedules jobs using this attribute against the **y-image-shift-range-supported** actual destination attribute.

## Attributes for Jobs and Default Jobs

This section contains the attributes for default jobs and jobs.

### Default Job

Use default jobs to set default values for job attributes.

Default jobs contain two types of attributes:

- Attributes that describe the default job itself
- Attributes that you can set as default values for job attributes

### Job

A job is an Infoprint object that represents a request to print or transmit one or more documents in a single session.

## Attributes Not Displayed in the Infoprint Administrator's GUI

While all job and default job attributes and attribute values are supported for both basic and advanced Infoprint installations, neither Infoprint administrator's GUI displays a complete set.

- The basic Infoprint administrator's GUI displays only the attributes of greatest interest to Infoprint administrators.
- The advanced Infoprint administrator's GUI displays most attributes and attribute values, but omits a few that are used primarily in basic Infoprint installations.

You can list the values of attributes not displayed in the Infoprint administrator's GUI using the **pdls** command or the **pdq** command. You can set the values of initially settable and resettable attributes using the **pdcreate** command or the **pdpr** command. You can change the values of resettable attributes using the **pdmod** command or the **pdset** command.

## Initially Settable Attribute Listing

You can set these attributes with the **pdpr** command when you submit the job.

**destination-name-requested**  
**initial-value-job**  
**job-originator**  
**job-owner**  
**tape-exit**  
**tape-format**  
**tape-labeled**  
**tape-max-block-size**  
**tape-rewind-before**  
**tape-rewind-unload**

**Note:** There are no initially settable attributes for a default job.

## Resettable Attribute Listing

You can set these attributes with the **pdpr** command when you submit a job or with the **pdcreate** command when you create a default job. You can modify them with the **pdset** command after Infoprint has accepted the job or after you create the default job. You can also use the **pdmod** command to modify a job after Infoprint accepts it.

**actual-destinations-requested**  
**auxiliary-sheet-selection**

## Job/Default Job

**delete-segment-list**  
**descriptor** (default job only)  
**destination-locations-requested**  
**destination-models-requested**  
**dss-requested**  
**estimated-processing-time** (job only)  
**job-batch**  
**job-comment**  
**job-deadline-time** (job only)  
**job-discard-time** (job only)  
**job-end-message**  
**job-finishing**  
**job-hold**  
**job-media-sheet-count** (job only)  
**job-message-from-administrator** (job only)  
**job-message-to-operator**  
**job-name**  
**job-page-count** (job only)  
**job-print-after** (job only)  
**job-priority**  
**job-retain-until** (job only)  
**job-retention-period**  
**job-rip-action**  
**job-start-message**  
**job-start-wait**  
**list-of-managers** (default job only)  
**message** (default job only)  
**notification-profile**  
**optimize-for-multiple-copies**  
**results-profile**

## actual-destinations-requested

Identifies a list of actual destinations, any one of which Infoprint may use to process the job.

### GUI Label

Actual destinations requested

### DSS

All

### Type

Resettable, multi-valued

### Input Synonym

You can use the synonym **physical-printers-requested**.

### Allowed Values

You can enter a text string of up to 255 characters, per value, that contains the name of an actual destination.

### Default Values

No default values

### Usage Guidelines

- Infoprint validates and schedules jobs using this attribute against the destination attribute **destination-name**.

- If you request more than one actual destination, the job will process on the first one that becomes available that can support the job.

## associated-server (Default Job Only)

Indicates the name of the server in which this default job resides.

### DSS

All

### Type

Non-settable, single-valued

### Allowed Values

Infoprint sets this value to the *ServerName*: portion of the argument used with the **pdcreate** command when this default job is created.

### Default Value

No default value

## auxiliary-sheet-selection

Identifies the combination of start, separator, and end sheets requested for this job. Whether Infoprint prints the requested sheets depends on the actual destination.

### GUI Label

Auxiliary/Separator sheets

### DSS

AIX, PSF, Passthrough

### Type

Resettable, single-valued

### Allowed Values

You can enter one of these fixed values:

<i>Fixed Value</i>	<i>Start</i>	<i>Separator</i>	<i>End</i>
end	No	No	Yes
none	No	No	No
sep	No	Yes	No
sep-end	No	Yes	Yes
start	Yes	No	No
start-end	Yes	No	Yes
start-sep	Yes	Yes	No
start-sep-end	Yes	Yes	Yes

### Default Value

Default job

No default value

Job

**start-sep-end**

### Usage Guidelines

Infoprint validates and schedules jobs using this attribute against the destination attribute **auxiliary-sheet-selections-supported**.

## comment

See **job-comment**.

## Job/Default Job

### completion-time (Job Only)

Identifies the time when the job completed printing or transmitting.

#### GUI Label

Completed

#### DSS

All

#### Type

Non-settable, single-valued

#### Allowed Values

Infoprint sets the value for this attribute in the local time format; USA is "HH:MM:SS mm/dd/yy".

#### Default Value

No default value

#### Usage Guidelines

Provides status information.

### current-job-state (Job Only)

Identifies the current state of the job.

#### GUI Label

State

#### DSS

All

#### Type

Non-settable, single-valued

#### Input Synonym

You can use the synonym **job-state**.

#### Allowed Values

Infoprint sets and updates this value as the job processes. The value set at a given time is one of these fixed values:

<i>Fixed Value</i>	<i>Reason</i>
<b>cancelled</b>	The job submitter or an operator cancelled the job. The <b>job-state-reasons</b> job attribute provides the reason.
<b>held</b>	The job is in a queue and Infoprint cannot schedule it. Either the <b>job-hold</b> job attribute is set to <b>true</b> or the job is held for some other reason, such as resources not ready. The <b>job-state-reasons</b> job attribute provides the reason.
<b>imposing</b>	Infoprint is arranging the job's pages so that they will print on the press sheets in the right order for final cutting, folding, and binding.
<b>paused</b>	The job was paused with the <b>pdpause</b> command.
<b>pending</b>	The job is in a queue and is waiting for Infoprint to schedule and send it to an actual destination.



<b>pre-processing</b>	Infoprint is creating the job.
<b>printing</b>	The job is printing on a PSF or 3170 actual destination. The <b>printing</b> state is not supported by the AIX, BSD, fax, email, or Infoprint 2000 DSS. Jobs printing on AIX or BSD actual destinations, or transmitting on fax or email destinations, are in the <b>processing</b> state.
<b>processing</b>	Infoprint has sent the job to an actual destination. The job is processing and printing on an AIX, BSD, or Infoprint 2000 actual destination, processing and transmitting on a fax or email destination, or processing on a PSF or 3170 actual destination. Depending on the output device, this can indicate that Infoprint has sent at least one document in the job to the output device.
<b>retained</b>	Infoprint has retained the job in the server after it finished printing or transmitting or after it was cancelled. Either the value of the <b>job-retention-period</b> job attribute for the job is greater than zero, or the value of the <b>job-retain-until</b> job attribute for the job is a future time.
<b>ripping</b>	Infoprint is converting the job to raster image patterns for printing. The <b>ripping</b> state is supported only by the PSF, 3170, fax, email, and Infoprint 2000 DSS.
<b>terminating</b>	The job is terminating, either because it has finished processing or because it was aborted. The <b>job-state-reasons</b> job attribute provides the reason.
<b>unknown</b>	The server does not know the state of the job because it lost communication with the actual destination to which Infoprint sent the job.

**Default Value**

No default value

**Usage Guidelines**

Jobs are in the job state **cancelled**, **pre-processing**, and **terminating** for only a very short time. You may never see them as values for this attribute; however, you may see them as values for the **previous-job-state** job attribute.

**current-page-printing (Job Only)**

Reports the page number of the currently printing or transmitting page.

**GUI Label**

Page currently printing

**DSS**

PSF

**Type**

Non-settable, single-valued

## Job/Default Job

### Allowed Values

Infoprint sets and updates this value to an integer from 0 through 2147483647.

### Default Value

No default value

### Usage Guidelines

The differences between this attribute and **pages-completed** are:

- **current-page-printing** is the number of the page being printed or transmitted, while **pages-completed** is the number of pages placed in the stacker. For example, when page 12 of the first copy of a double-sided job is printing, the value of **current-page-printing** is 12 and the value of **pages-completed** is 10.
- **current-page-printing** is reset with every job copy, while **pages-completed** is cumulative within a job. For example, when page 6 of the second copy of a 10-page job is printing, the value of **current-page-printing** is 6. When the same page is stacked, the value of **pages-completed** is 16.

## d-s-s-requested

See **dss-requested**.

## deadline-in-jeopardy (Job Only)

Indicates whether the job is in danger of not completing before the time specified by the **job-deadline-time** attribute.

### GUI Label

Deadline in jeopardy

### DSS

PSF, Email, Fax, Infoprint 2000

### Type

Non-settable, single-valued

### Allowed Values

Infoprint sets this value to one of these fixed values:

**true**  
**false**

### Default Value

No default value

### Usage Guidelines

Infoprint sets **deadline-in-jeopardy** to **true** under these conditions:

- If the queue attribute **assign-to-destination=true**, when the value of the **estimated-completion-time** attribute is later than the value of the **job-deadline-time** attribute.
- If the queue attribute **assign-to-destination=false**, when the current time is later than the value of the **job-deadline-time** attribute. Infoprint cannot calculate a value for the **estimated-completion-time** attribute if **assign-to-destination=false**.

## delete-segment-list

Indicates whether to delete the segment list file, where Infoprint lists the segment files into which it breaks the job for processing, after the job is complete.

**GUI Label**

Delete segment list

**DSS**

PSF, Email, Fax, and Infoprint 2000

**Type**

Resettable, single-valued

**Allowed Values**

You can enter one of these fixed values:

<i>Fixed Value</i>	<i>Input Synonym</i>
true	yes
false	no

**Default Value**

Default job	No default value
Job	false

**descriptor (Default Job Only)**

Provides a description of this default job.

**DSS**

All

**Type**

Resettable, single-valued

**Allowed Values**

You can enter a text string of up to 4095 characters that describes this default job.

**Default Value**

No default value

**Usage Guidelines**

The use of this attribute is optional. However, a detailed description helps job submitters to determine if this default job is the one they want to use.

**destination-initial-value-job (Job Only)**

Identifies the default job associated with the logical destination to which you submitted the job and used to create the job.

**GUI Label**

Default job used

**DSS**

All

**Type**

Non-settable, single-valued

**Input Synonym**You can use the synonym **printer-initial-value-job**.**Allowed Values**

Infoprint sets this value to the name of the default job used.

## Job/Default Job

### Default Value

No default value

## destination-locations-requested

Identifies a list of destination locations. Infoprint may use a destination at any of these locations to process the job.

### GUI Label

Actual destination locations requested

### DSS

All

### Type

Resettable, multi-valued

### Input Synonyms

You can use the synonym **printer-locations-requested** or **locations-requested**.

### Allowed Values

You can enter a text string of up to 4095 characters, per value, that contains the actual location of each destination requested. Infoprint will process the job on a destination at one of the locations if the validation is successful.

### Default Values

No default values

### Usage Guidelines

- Infoprint validates jobs using this attribute against the logical and actual destination attribute **destination-locations**.
- Infoprint schedules the job against the actual destination attribute **destination-locations**.
- Any individual value specified for this attribute can select more than one actual destination. For example, the output devices could all be in the same location, such as a printer room.
- The values for both the job and destination attributes are text strings that can include blanks. They must match exactly for validation to occur.

## destination-models-requested

Identifies a list of destination make and model IDs. Infoprint may use any one of these destinations to process the job.

### GUI Label

Actual destination models requested

### DSS

All

### Type

Resettable, multi-valued

### Input Synonyms

You can use the synonym **printer-models-requested** or **models-requested**.

### Allowed Values

You can enter a text string of up to 4095 characters, per value, that identifies the destination model.

**Default Values**

No default values

**Usage Guidelines**

- Infoprint validates jobs using this attribute against the logical and actual destination attribute **destination-model**. Only one value must match for Infoprint to validate the job.
- Infoprint schedules the job against the actual destination attribute **destination-model**. Only one value must match for Infoprint to schedule the job.
- This attribute is multi-valued whereas the destination attributes are single-valued.
- Any individual value specified for this attribute can select more than one actual destination.
- The value for this attribute and the values for the destination attributes for the BSD, PSF, 3170, email, and fax actual destinations are text strings that can include blanks. (The values for the AIX actual destination attribute never contain blanks.)
- The value for this attribute and the value for the destination attribute must match exactly for validation to occur.

**destination-name-requested (Job Only)**

Identifies the logical destination to which you submitted this job.

**GUI Label**

Submitted to

**DSS**

All

**Type**

Initially settable, single-valued

**Input Synonyms**

You can use the synonym **printer-name-requested**, **printer-requested**, or **logical-printer-requested**.

**Allowed Values**

You can enter a text string of up to 255 characters that contains the name of the logical destination.

**Default Value**

No default value

**Usage Guidelines**

- If you do not specify a value for this attribute, Infoprint uses the **-p** or **-d** value on the **pdpr** command, or the **PDPRINTER** environment variable of the job submitter.  
To move the job to a different logical destination, use the **pdresubmit** command.

**destinations-assigned (Job Only)**

Identifies the actual destination to which Infoprint assigned the job for processing.

**GUI Label**

Destination

## Job/Default Job

### DSS

All

### Type

Non-settable, single-valued

### Input Synonym

You can use the synonym **printers-assigned**.

### Allowed Values

Infoprint sets this value to the name of the actual destination where it sent the job.

### Default Values

No default value

### Usage Guidelines

If the value for this attribute is blank, the job is still waiting for Infoprint to assign it to an actual destination.

## destinations-used (Job Only)

Identifies the actual destination that printed or transmitted this job.

### GUI Label

Destinations used

### DSS

All

### Type

Non-settable, multi-valued

### Input Synonym

You can use the synonym **printers-used**.

### Allowed Values

Infoprint sets this value to the names of the actual destinations where it sent the job.

### Default Values

No default value

### Usage Guidelines

Normally this value only contains one actual destination name. However, if Infoprint restarted the job on another actual destination because the first actual destination failed for some reason, this value could contain more than one actual destination name.

## device-support-system-requested

See **dss-requested**.

## discard-time (Job Only)

See **job-discard-time**.

## dss-requested

Identifies the destination support system (DSS) requested for the job.

**GUI Label**

Actual destination type requested

**DSS**

All

**Type**

Resettable, single-valued

**Input Synonyms**

You can use the synonyms **device-support-system-requested** or **d-s-s-requested**.

**Allowed Values**

You can enter one of these fixed values:

<i>Fixed Value</i>	<i>Input Synonym</i>
aix	piobe
bsd	
psf	
3170	
email	
fax	
IP2000	

**Default Value**

No default value

**Usage Guidelines**

- Infoprint validates jobs using this attribute against the logical and actual destination attribute **device-support-system**.
- Infoprint schedules the job against the actual destination attribute **device-support-system**.

**end-message**

See **job-end-message**.

**estimated-completion-time (Job Only)**

Indicates the time when Infoprint expects the job to finish printing or transmitting.

**GUI Label**

Estimated completion time

**DSS**

All

**Type**

Non-settable, single-valued

**Allowed Values**

Infoprint sets the value for this attribute in the local time format; USA is "HH:MM:SS mm/dd/yy".

**Default Value**

No default value

## Job/Default Job

### Usage Guidelines

- Infoprint uses the values it calculated for the **estimated-processing-time** attribute of this job and the jobs ahead of it in the queue to estimate the job's completion time.
- Infoprint can calculate a value for this attribute only when the queue attribute **assign-to-destination** is set to **true**.

## estimated-processing-time (Job Only)

Indicates how long the job should take to process.

### GUI Label

Estimated processing time

### DSS

All

### Type

Resettable, single-valued

### Allowed Values

You can enter a value using *[HH:]MM*. The unit is minutes or hours and minutes, separated by a colon.

### Default Value

No default value

### Usage Guidelines

- Infoprint uses the values of the **total-job-octets** and **job-complexity** attributes to estimate the job's processing time. You can change this value.
- Infoprint can calculate a value for this attribute only when the queue attribute **assign-to-destination** is set to **true**.

## formatted-job-ticket-content (Job Only)

Contains the job ticket document for the job in human-readable format.

### DSS

PSF, Email, Fax, 3170, Infoprint 2000

### Type

Non-settable, single-valued

### Input Synonyms

You can use the synonym **job-ticket-content** or **ticket-content**.

### Allowed Values

Infoprint sets the value of this attribute to the contents of the formatted job ticket document.

### Default Value

No default value

## global-id (Job Only)

See **job-identifier**.

## hold

See **job-hold**.



**initial-value-job (Job Only)**

Identifies the default job (within a given server) that Infoprint uses to create this job.

**DSS**

All

**Type**

Initially settable, single-valued

**Allowed Values**

You can enter the name of an existing default job.

**Default Value**

No default value

**Usage Guidelines**

If you specify a value for this attribute, the job uses the attributes and values from the specified object unless you override those with attribute values supplied at the command line.

**initial-value-job-identifier (Default Job Only)**

Identifies this default job within the server.

**DSS**

All

**Type**

Non-settable, single-valued

**Allowed Values**

Infoprint sets this value to the *DefaultJobName* value of the **pdcreate** command argument *ServerName:DefaultName* when this default job is created.

**Default Value**

No default value

**Usage Guidelines**

The value for this attribute must be unique within a server.

**intervening-jobs (Job Only)**

Indicates the number of jobs in the queue before this job.

**GUI Label**

Position in queue

**DSS**

All

**Type**

Non-settable, single-valued

**Input Synonyms**

You can use the synonym **position-in-queue** or **queue-position**.

**Allowed Values**

Infoprint sets and updates this value to an integer from 0 through 2147483647.

## Job/Default Job

### Default Value

No default value

### Usage Guidelines

- This attribute provides status information.
- A value of zero (0) means that the job is currently printing or transmitting.

## job-batch

Specifies that you have marked the job you are submitting as a specific type of job. Infoprint processes this job only on an actual destination that is ready to print or transmit that specified job-batch type.

### GUI Label

Batch

### DSS

All

### Type

Resettable, single-valued

### Allowed Values

You can enter a text string of up to 4095 characters that contains the job-batch name.

### Default Value

No default value

### Usage Guidelines

Infoprint schedules jobs using this attribute against the **job-batches-ready** actual destination attribute.

## job-client-id (Job Only)

Identifies the local job identifier number for the job.

### GUI Label

ID

### DSS

All

### Type

Resettable, single-valued

### Allowed Values

Infoprint sets this value from 1 through the number specified as the value for the **PDIDTABLE** environment variable.

### Default Value

No default value

## job-comment

Provides information associated with this job.

### GUI Label

Description

**DSS**

All

**Type**

Resettable, single-valued

**Input Synonym**You can use the synonym **comment**.**Allowed Values**

You can enter a text string of up to 4095 characters that contains information associated with this job.

**Default Value**

No default value

**job-complexity**

Indicates the relative complexity of the job, based on the contents of the documents in the job. For example, a job with many graphics is more complex than a job that is mostly text.

**GUI Label**

Complexity (1–10)

**DSS**

All

**Type**

Resettable, single-valued

**Allowed Values**You can enter an integer from **1** to **9**.**Default Value****3****Usage Guidelines**

- The default value, **3**, represents an average job. A job with complexity **1** is one-third as complex as the average job; a job with complexity **9** is three times as complex as average.
- Infoprint uses this value and the size of the job to estimate the job processing time.
- Infoprint uses this attribute only when the queue attribute **assign-to-destination** is set to **true**.

**job-copies-completed (Job Only)**

Indicates the total number of copies of the job that have finished printing or transmitting.

**GUI Label**

Copies completed

**DSS**

All

**Type**

Non-settable, single-valued

## Job/Default Job

### Allowed Values

Infoprint sets and updates this value to an integer from 0 through 2147483647 when:

<b>AIX</b>	Each job copy completes.
<b>BSD</b>	Each result-set completes.
<b>Infoprint 2000</b>	Each result-set completes.
<b>PSF</b>	Each job copy completes.
<b>3170</b>	Each result-set completes.
<b>Email</b>	Each result-set completes.
<b>Fax</b>	Each result-set completes.
<b>Passthrough</b>	Each result-set completes.
<b>IPP</b>	Each result-set completes.

### Default Value

No default value

## job-deadline-time (Job Only)

Specifies the time or time and calendar date by which you want to the job to complete.

### GUI Label

Deadline time

### DSS

All

### Type

Resettable, single-valued

### Allowed Values

You can enter a value using the local time format. The USA format is *HH:MM:SS* or "*HH:MM:SS mm/dd/yy*". You must delimit the string with quotation marks if you specify a date. If you specify a time but no date, the date defaults to today.

### Default Value

No default value

## job-discard-time (Job Only)

Specifies the time or time and calendar date at which Infoprint discards the job even if it is not complete.

### GUI Label

Discard time

### DSS

All

### Type

Resettable, single-valued

### Input Synonym

You can use the synonym **discard-time**.

### Allowed Values

You can enter a value using the local time format. The USA format is *HH:MM:SS* or "*HH:MM:SS mm/dd/yy*". You must delimit the string with quotation marks if you specify a date. If you specify a time but no date, the date defaults to today.

**Default Value**

No default value

**job-end-message**

Provides a message conveying information about output handling when the job is complete.

**GUI Label**

End message

**DSS**

All

**Type**

Resettable, single-valued

**Input Synonym**You can use the synonym **end-message**.**Allowed Values**

You can enter a text string of up to 4095 characters that contains instructions to an operator, such as special output delivery instructions.

**Default Value**

No default value

**Usage Guidelines**

- Infoprint validates and schedules jobs using this attribute against the destination attribute **end-message-supported**.
- Infoprint sends this message if the attribute **end-message-supported** value is **true** for the actual destination to which Infoprint submitted the job.
- The destination attribute **notify-operator** identifies the operators that are to receive the message.

**job-finishing**

Identifies the finishing options for this job.

**GUI Label**

Finishing options

**DSS**

PSF, Infoprint 2000

**Type**

Resettable, multi-valued

**Allowed Values**

For PSF, you can enter any of these fixed values:

**edge-stitch**  
**edge-stitch-2**  
**edge-stitch-3**  
**saddle-stitch**  
**staple-bottom-left**  
**staple-top-left**

For Infoprint 2000, you can enter any of these fixed values:

**edge-stitch-2**

## Job/Default Job

**saddle-stitch**  
**staple-bottom-left**  
**staple-top-left**  
**booklet-stitch-and-fold**  
**booklet-stitch-fold-and-trim**

### Default Values

No default values

### Usage Guidelines

- **edge-stitch-2**, **edge-stitch-3**, and **edge-stitch** all staple one edge of the job. The difference is the number of staples: 2, 3, or the finisher default.
- The placement of staples in relation to the data depends on the image orientation and the way the paper is loaded in the printer. Letter and A4 paper are normally loaded long edge first, but are loaded short edge first when rotated. Long media sheets, like legal paper, are always loaded short edge first.

Table 13. Staple Position for PSF DSS

Value	Long Edge First		Short Edge First	
	Portrait	Landscape	Portrait	Landscape
<b>edge-stitch</b> <b>edge-stitch-2</b> <b>edge-stitch-3</b>	Left edge	Top edge	Top edge	Right edge
<b>saddle-stitch</b>	Not valid		Across center of sheet	
<b>staple-bottom-left</b>	Bottom left	Top left	Top left	Top right
<b>staple-top-left</b>	Top left	Top right	Top right	Bottom right

- For PSF DSS, **saddle-stitch** is valid only for the following medium sizes, all loaded short edge first:
  - A3**
  - A4** (rotated)
  - ledger**
  - legal**
  - letter** (rotated)
- For PSF DSS, when you specify a value for **job-finishing**, Infoprint creates a form definition. Do not use the document attribute **form-definition** to specify another form definition.
- Infoprint validates and schedules jobs using this attribute against the destination attribute **job-finishings-supported**.

## job-hold

Indicates whether Infoprint can schedule the job for printing or transmission.

### GUI Label

Hold

### DSS

All

### Type

Resettable, single-valued

**Input Synonym**

You can use the synonym **hold**.

**Allowed Values**

You can enter one of these fixed values:

<i>Fixed Value</i>	<i>Input Synonym</i>
<b>true</b>	<b>yes</b>
<b>false</b>	<b>no</b>

**Default Value**

<b>Default job</b>	No default value
<b>Job</b>	<b>false</b>

**Usage Guidelines**

- If **job-hold** is **true**, the **job-state** changes to **held** and Infoprint sets the **job-state-reasons** to **job-hold-set**.
- A held job remains in the queue until:
  - **job-hold** is set to **false** and the job is printed or transmitted.
  - The time set in the **job-discard-time** attribute is reached and the job is discarded.
- When a job with **job-rip-action=rip-and-print-ignore-ready** is placed in the **held** state after RIPping because a required resource is not ready, the value of **job-hold** remains **false**. The job is automatically released when all required resources become ready.

**job-identifier (Job Only)**

Identifies the global job identifier. The global job ID uniquely identifies the job within the server.

**GUI Label**

Global ID

**DSS**

All

**Type**

Non-settable, single-valued

**Input Synonym**

You can use the synonym **global-id**.

**Allowed Values**

Infoprint sets this value.

**Default Value**

No default value

**job-log (Job Only)**

Contains messages that Infoprint issues as this job is processed.

**DSS**

All

**Type**

Non-settable, multi-valued

## Job/Default Job

### Allowed Values

Infoprint sets the value of this attribute to the messages issued as the job is processed.

### Default Values

No default value

### Usage Guidelines

Infoprint creates this attribute when the value of the **delivery-method** component of the **notification-profile** attribute is **job-log**.

## job-media-sheet-count (Job Only)

Identifies the estimated total number of sheets used to print the job.

### GUI Label

Number of media sheets

### DSS

All

### Type

Resettable, single-valued

### Input Synonym

You can use the synonym **media-sheet-count**.

### Allowed Values

You can enter an integer from 1 through 2147483647.

### Default Value

No default value

## job-message-from-administrator (Job Only)

Describes the reasons that you are changing or have changed the job.

### GUI Label

Message from administrator

### DSS

All

### Type

Resettable, single-valued

### Input Synonym

You can use the synonym **message-from-administrator**.

### Allowed Values

The administrator can enter a text string up to 4095 characters long that provides information concerning why a given action was taken. The administrator uses the **-m** flag or the command attribute **message** of certain Infoprint commands. See "Usage Guidelines" for how you can set the value.

### Default Value

No default value

### Usage Guidelines

Set this attribute by specifying a value with the **-m** flag or the **message** command attribute of these commands:



**pdmod**  
**pdpause**  
**pdpromote**  
**pdresume**  
**pdrm**  
**pdset**

## job-message-to-operator

Provides a message that Infoprint can send to an operator when it adds the job to the queue.

### GUI Label

Message to operator

### DSS

All

### Type

Resettable, single-valued

### Input Synonym

You can use the synonym **message-to-operator**.

### Allowed Values

You can enter a text string of up to 4095 characters that contains information about job processing requirements, such as some type of special handling.

### Default Value

No default value

### Usage Guidelines

The queue attribute **notify-operator** identifies the operator who receives the message.

## job-name

Provides a human-readable job identification.

### GUI Label

Name

### DSS

All

### Type

Resettable, single-valued

### Input Synonym

You can use the synonym **name**.

### Allowed Values

You can enter a text string of up to 255 characters that contains the identification. The string can include any of the following characters:

- Uppercase alphabetic characters (A-Z)
- Lowercase alphabetic characters (a-z)
- Numeric characters (0-9)
- Underscore (\_)
- Hyphen (-)
- Period (.)

## Job/Default Job

### Default Value

Default job  
Job

No default value  
The file name of the first document in the job

### Usage Guidelines

For PSF, this identification may print on the start sheet in the **JOB NAME** field.

## job-originator (Job Only)

Identifies the person who submitted the job or the program that initiated the job.

### DSS

All

### Type

Initially settable, single-valued

### Input Synonym

You can use the synonym **originator**.

### Allowed Values

You can enter a text string up to 255 characters long that contains the name, login ID, or login ID and node of the person submitting the job, or the name of the program initiating the job.

### Default Value

*username@node* of the person submitting the job.

### Usage Guidelines

You can use this attribute to identify yourself by name or to identify the program that initiated the job.

## job-owner (Job Only)

Identifies the person responsible for the job by name or login ID.

### GUI Label

Sent by

### DSS

All

### Type

Initially settable, single-valued

### Input Synonym

You can use the synonym **owner**.

### Allowed Values

You can enter a text string of up to 255 characters. Normally the string contains the *username@node* of the person that is responsible for this job.

### Default Value

The value of the job attribute **job-originator**.

### Usage Guidelines

- You can use this attribute to specify a person other than yourself who is responsible for the job.
- For BSD, Infoprint maps this attribute value to the **qprt -D** option.
- For PSF, this identification may print on the start sheet in the **USERID** field.

## job-page-count (Job Only)

Identifies the estimated total number of pages in the job.

### GUI Label

Number of pages

### DSS

All

### Type

Resettable, single-valued

### Allowed Values

An integer from 1 through 2147483647.

### Default Value

The total of the values of the **page-count** attribute for all documents multiplied times the value in the **copy-count** attribute (and the **job-copies** component in the **results-profile**) for all the documents in the job.

### Usage Guidelines

- Infoprint calculates the value for **job-page-count** as follows:
  1. Multiplying the value for the total number of printable pages specified with the **page-count** document attribute for all printable documents in the job times the value for the **copy-count** document attribute for all printable documents in the job.
  2. Infoprint then multiplies the value from step 1 times the **job-copies** component of the **results-profile** job attribute and inserts the result of this multiplication in the **job-page-count** attribute.
- If you choose to specify a value for the **job-page-count** attribute, the value should closely represent the total number of pages expected for the complete job.
- Infoprint determines the size of a job based on the total number of octets (bytes) in the job. For operator job-management purposes, you may find that job size based on pages is easier.

**Note:** This attribute overrides the page count that Infoprint calculates.

## job-print-after (Job Only)

Specifies the time or time and calendar date after which Infoprint can schedule the job for printing or transmission.

### GUI Label

Print after

### DSS

All

### Type

Resettable, single-valued

### Input Synonym

You can use the synonym **print-after**.

## Job/Default Job

### Allowed Values

You can enter a value using the local time format. The USA format is *HH:MM:SS* or "*HH:MM:SS mm/dd/yy*". You must delimit the string with quotation marks if you specify a date. If you specify a time but no date, the date defaults to today.

### Default Value

No default value

### Usage Guidelines

- If you submit the job before the specified time, Infoprint sets the **job-state** to **held** and the **job-state-reasons** attribute value for the job is **job-print-after-specified**.
- If you submit the job after the specified time, the job is printed or transmitted as soon as possible.

## job-priority

Specifies a number representing the scheduling priority for the job. Queues that employ a priority-based scheduler use this attribute. A larger value specifies a higher priority.

### GUI Label

Priority (1–100)

### DSS

All

### Type

Resettable, single-valued

### Allowed Values

You can enter an integer from 1 to 100.

### Default Value

Default job	No default value
Job	<b>50</b>

### Usage Guidelines

If you use DCE:

- A job submitter cannot set this value higher than 50 unless the job submitter is an administrator. If the job submitter specifies a value greater than 50, Infoprint sets the value to 50.
- An administrator can set the value to any valid value.

## job-retain-until (Job Only)

Specifies the time or time and calendar date until which Infoprint retains the completed job before the server discards it.

### GUI Label

Retain until

### DSS

All

### Type

Resettable, single-valued

**Allowed Values**

You can enter a value using the local time format. The USA format is *HH:MM:SS* or "*HH:MM:SS mm/dd/yy*". You must delimit the string with quotation marks if you specify a date. If you specify a time but no date, the date defaults to today.

**Default Value**

No default value

**Usage Guidelines**

You can specify a value for either **job-retain-until** or **job-retention-period**, but not both.

**job-retention-period**

Specifies the period of time that Infoprint retains the job before the server discards it, whether it has completed or not.

**GUI Label**

Retain for

**DSS**

All

**Type**

Resettable, single-valued

**Input Synonym**

You can use the synonym **retention-period**.

**Allowed Values**

You can enter a value using *[HH:]MM*. The unit is minutes or hours and minutes, separated by a colon.

**Default Value**

No default value

**Usage Guidelines**

- You can specify a value for either **job-retain-until** or **job-retention-period**, but not both.
- The retention period starts when the job enters the **retained** state.

**job-rip-action**

Indicates that Infoprint should convert the job to raster image patterns and whether to hold the RIPped job, print or transmit it, or neither.

**GUI Label**

Rip option

**DSS**

PSF, Email, Fax, 3170, Infoprint 2000

**Type**

Resettable, single-valued

**Allowed Values**

You can enter one of these fixed values:

**Fixed Value****Explanation**

## Job/Default Job

### **rip-and-hold, rip-and-hold-ignore-ready**

Infoprint RIPs the job and returns it to the scheduler in the **held** state. The value of the **job-state-reasons** attribute is **rip-and-hold-completed**.

### **rip-and-print**

If all required resources are ready on an actual destination, Infoprint RIPs and prints the job. Otherwise, Infoprint returns the job to the scheduler in the **held** state, without RIPping it. The value of the **job-state-reasons** attribute is **required-resource-not-ready**.

### **rip-and-print-ignore-ready**

If all required resources are ready, Infoprint RIPs and prints the job. Otherwise, Infoprint RIPs the job and returns it to the scheduler in the **held** state. The value of the **job-state-reasons** attribute is **rip-completed**. When the required resources become ready, Infoprint automatically releases the job to print.

### **rip-only, rip-only-ignore-ready**

Infoprint RIPs the job and discards or retains it according to the values of the **job-retain-until** and **job-retention-period** attributes. For a retained job, the value of the **job-state-reasons** attribute is **completed**, **completed successfully**, or **completed with errors**.

### **Default Value**

No default value

### **Usage Guidelines**

- Use the **rip-only** and **rip-only-ignore-ready** values to test for RIPping errors.
- The **rip-and-hold** and **rip-and-hold-ignore-ready** values override a value of **false** for the server **save-rip-files** attribute.
- Infoprint validates and schedules jobs using this attribute against the destination attribute **job-rip-actions-supported**.

## **job-ripped-by-server**

Indicates whether Infoprint should convert the job to MOD:CA-P and transmit it as email or to be printed on the Infoprint Infoprint 2000. If this attribute is **true**, the server converts the job into MOD:CA-P. If this attribute is **false**, the server determines if the job can be printed directly by the Infoprint Infoprint 2000 printer or sent directly as email without converting to MOD:CA-P. When a job cannot be handled directly without conversion, the job is requeued on the spooler.

### **GUI Label**

Override RIP at destination

### **DSS**

Email, Infoprint 2000

### **Type**

Resettable, single-valued

### **Allowed Values**

You can enter one of these fixed values:

<i>Fixed Value</i>	<i>Input Synonym</i>
<b>true</b>	<b>yes</b>
<b>false</b>	<b>no</b>

**Default Value**

true

**Usage Guidelines**

- When a job requires special processing of its input files, the server transforms the job into MOD:CA-P regardless of the **job-ripped-by-server** job attribute or the document formats listed in the **document-formats-ripped-at-destination** actual destination attribute.
- The following document formats cannot be converted to MOD:CA-P:
  - ASCII
  - KGL
  - LCDS
  - METACODE

Infoprint sends these document formats in passthru mode. For documents to print successfully in passthru mode, the **job-finishing** job attribute and the following document attributes must not be specified:

**account-text**  
**base-printer**  
**carriage-control-type**  
**chars**  
**convert-to-ebcdic**  
**default-character-mapping**  
**default-medium**  
**default-font-fidelity-action**  
**form-defintion**  
**halftone**  
**image-fit**  
**image-length**  
**image-width**  
**input-exit**  
**new-line-option**  
**number-up**  
**other-transform-options**  
**output-bin**  
**output-format**  
**overlay**  
**page-defintion**  
**page-select**  
**plex**  
**printer-pass-through**  
**resource-context**  
**resource-context-font**  
**resource-context-form-definition**  
**resource-context-page-definition**  
**resource-context-page-segment**  
**resource-context-overlay**  
**resource-context-user**  
**shift-out-shift-in**  
**sides**  
**start-on-new-sheet**  
**subject-text**  
**table-reference-characters**  
**transform-message-file-name**  
**transform-output-file-name**  
**x-image-shift**

## Job/Default Job

x-image-shift-back  
y-image-shift  
y-image-shift-back

**Note:** If any of these attributes are specified, Infoprint converts the job to MOD:CA-P.

- When the **job-finishing** job attribute and the following document attributes are specified for an email with color, Infoprint converts the job into MOD:CA-P and presents the email in black and white:

account-text  
address1-text  
address2-text  
address3-text  
address4-text  
carriage-control-type  
chars  
convert-to-ebcdic  
default-character-mapping  
font-fidelity-action  
font-resolution  
form-definition  
image-fit  
image-length  
image-width  
input-exit  
new-line-option  
number-up  
other-transform-options  
output-bin  
output-format  
overlay  
page-definition  
page-select  
plex  
resource-context  
resource-context-font  
resource-context-form-definition  
resource-context-page-definition  
resource-context-page-segment  
resource-context-overlay  
resource-context-user  
shared-formdef  
shift-out-shift-in  
sides  
table-reference-characters  
transform-message-file-name  
transform-output-file-name  
x-image-shift  
y-image-shift

**Note:** If any of these attributes are specified, Infoprint converts the job to MOD:CA-P.

In addition to the listed attributes, any of the following job characteristics also require that Infoprint converts the job into MOD:CA-P:

- Job contains more than one printable document.



- Job contains an insert sheet.
- Job contains a file-reference document.
- Job contains a document whose document-format is MOD:CA-P.
- Job requests **job-rip-action=rip-and-hold**, **rip-only**, **rip-only-ignore-ready**, or **rip-and-hold-ignore-ready**.
- Job requests more than one copy with the **copy-count** attribute.
- Job contains a variable data document.
- Job contains a resource document.
- Job contains a document-definition-document.

## job-size (Job Only)

See **total-job-octets**.

## job-start-message

Provides a message that Infoprint can send to an operator when the job starts printing or transmitting. This message can alert the operator to something special about the job, for example, that the job contains confidential information.

### GUI Label

Start message

### DSS

All

### Type

Resettable, single-valued

### Input Synonym

You can use the synonym **start-message**.

### Allowed Values

You can enter a text string of up to 4095 characters that contains information about the job such as:

"This job is very important; call me if there is a problem."

### Default Value

No default value

### Usage Guidelines

- Infoprint validates and schedules jobs using this attribute against the destination attribute **start-message-supported**.
- Infoprint sends a message if the actual destination attribute **start-message-supported** value is **true** for the actual destination to which Infoprint submitted the job.
- The destination attribute **notify-operator** contains the identity of the operators that are to receive the message.
- Sending the start message does not stop the job; normally the job is printed or transmitted without operator intervention.
- Sending a start message is particularly useful for AIX printer devices that have manual forms feed capabilities. The user can send a message alerting the operator to load a special type of paper before starting the job.
- Use this attribute with the **job-start-wait** attribute for jobs that require operator intervention, for example, loading special forms in the printer device. If the values of the **job-start-message** and **job-start-wait** are true, when the job is about to be printed or transmitted, Infoprint pauses the actual destination and the person

## Job/Default Job

specified by the actual destination **notify-operator** attribute receives the message specified by the **job-start-message** attribute. When the operator resumes the actual destination, the job is printed or transmitted.

## job-start-wait

Pauses the actual destination just before the job is printed or transmitted.

### GUI Label

Wait to start job

### DSS

All

### Type

Resettable, single-valued

### Allowed Values

You can enter one of these fixed values:

<i>Fixed Value</i>	<i>Input Synonym</i>
true	yes
false	no

### Default Value

Default job

No default value

Job

false

### Usage Guidelines

- Use this attribute with the **job-start-message** attribute for jobs that require operator intervention, for example, loading special forms in the printer device. If the values of the **job-start-wait** and **job-start-message** are true, when the job is about to be printed or transmitted, Infoprint pauses the actual destination and the person specified by the actual destination **notify-operator** attribute receives the message specified by the **job-start-message** attribute. When the operator resumes the actual destination, the job is printed or transmitted.
- Infoprint validates and schedules jobs using this attribute against the destination attribute **job-start-wait-supported**.

## job-state (Job Only)

See **current-job-state**.

## job-state-reasons (Job Only)

Identifies the reasons that a job is in the **held**, **terminating**, or **retained** state. If this attribute value is blank, the job is not in one of these states.

### GUI Label

Reasons

### DSS

All

### Type

Non-settable, multi-valued

### Input Synonyms

You can use the synonym **state-reasons** or **reasons**.

**Allowed Values**

Infoprint sets this value to any of these fixed values:

**Fixed Value Explanation****aborted-by-system**

The server aborted the job.

**cancelled-by-operator**

An operator or system administrator cancelled the job.

**cancelled-by-user**

The person who submitted the job cancelled the job.

**completed**

The job completed without any errors or warnings that Infoprint could detect. This does not guarantee that there were no errors of any kind.

**completed-successfully**

The job completed without any errors or warnings.

**completed-with-errors**

The job completed with errors. Based on the **dss-job-message-disposition** actual destination attribute, the messages associated with the errors either print at the end of the job or in a message log. See “dss-job-message-disposition” on page 367.

**deadline-in-jeopardy**

The value of the **estimated-completion-time** attribute for the job is later than the time specified by the **job-deadline-time** attribute; or the time specified by the **job-deadline-time** attribute is past.

**imposition-failed**

Infoprint could not arrange the pages in the job on the press sheet.

**Note:** You will see this reason only if the job is retained or if the value of the **requeue-failed-jobs** queue attribute is **true**. When neither of these conditions is true, jobs that fail to impose are discarded.

**job-hold-set**

The job is in a queue and the **job-hold** job attribute of the job has a **true** value.

**job-print-after-specified**

The job is in a queue and the time specified by the **job-print-after** job attribute has not yet occurred.

**required-resource-not-ready**

The job is in a queue but Infoprint cannot schedule it because one or more of the resources required by the job (such as media, fonts, and so on) are not ready on any of the actual destinations that can accept the job. The job's **required-resource-not-ready** attribute identifies the resources that need to be made ready.

**required-resource-not-supported**

The job is in a queue but Infoprint cannot schedule it because none of the actual destinations that can accept the job support one or more of the resources required by the job (such as media, fonts, and so on). The job's **required-resource-not-supported** attribute identifies the resources that are not supported.

**rip-and-hold-completed**

The RIP has successfully converted the job. The job has not been

## Job/Default Job

scheduled because the value of the **job-rip-action** attribute is **rip-and-hold** or is **rip-and-hold-ignore-ready**.

**rip-completed** A job with **job-rip-action=rip-and-print-ignore-ready** has been RIPPed, but Infoprint cannot schedule it because one or more of the resources required by the job are not ready on any of the actual destinations that can accept the job. Jobs held for this reason are released automatically when the required resources become ready.

**rip-failed** The RIP failed to convert the job.

**Note:** You will see this reason only if the job is retained or if the value of the **requeue-failed-jobs** queue attribute is **true**. When neither of these conditions is true, jobs that fail to rip are discarded.

### Default Values

No default values

## job-submission-complete (Job Only)

Indicates whether the server has received all documents of the job.

### GUI Label

Submission complete

### DSS

All

### Type

Non-settable, single-valued

### Allowed Values

Infoprint sets this value to one of these fixed values:

**true**

**false**

### Default Value

No default value

## job-ticket-content

See **formatted-job-ticket-content**.

## last-accessor (Job Only)

See **name-of-last-accessor**.

## last-modifier (Job Only)

See **name-of-last-accessor**.

## list-of-managers (Default Job Only)

Identifies the persons responsible for the maintenance of this default job.

### DSS

All

### Type

Resettable, multi-valued

**Input Synonym**

You can use the synonym **managers**.

**Allowed Values**

You can enter a text string up to 255 characters long, per value, that contains the name or user ID of the person responsible for this default job.

**Default Values**

No default values

**Usage Guidelines**

This attribute is useful if a user needs to contact someone to report a problem or to request a change.

**locations-requested**

See **destination-locations-requested**.

**logical-destinations-ready (Default Job Only)**

Lists the enabled logical destinations that reference this default job.

**DSS**

All

**Type**

Non-settable, multi-valued

**Allowed Values**

Infoprint sets or deletes a text string containing the global ID of any logical destination that references this default job when the logical destination is enabled or disabled.

**Input Synonym**

You can use the synonym **logical-printers-ready**.

**Default Values**

No default values

**Usage Guidelines**

- Infoprint adds a value when a logical destination that references this default job through its **destination-initial-value-job** attribute is enabled.
- Infoprint removes a value when a logical destination that references this default job is disabled.
- You cannot delete this default job until Infoprint has removed all logical destinations from this list.

**logical-printer-requested**

See **destination-name-requested**.

**logical-printers-ready (Default Job Only)**

See **logical-destinations-ready**.

**managers (Default Job Only)**

See **list-of-managers**.

## Job/Default Job

### media-sheet-count (Job Only)

See [job-media-sheet-count](#).

### media-sheets-completed (Job Only)

Reports the number of sheets that have been used to print this job.

#### GUI Label

Media sheets completed

#### DSS

PSF, Email, Fax, Infoprint 2000, Passthrough

#### Type

Non-settable, single-valued

#### Allowed Values

Infoprint sets and updates this value to an integer from 0 through 2147483647 at the completion of each result-set.

#### Default Value

No default value

#### Usage Guidelines

How this value relates to the value of **pages-completed** depends on the values of the **output-format**, **number-up**, and **sides** document attributes.

- For a single-sided, 1-up job, **pages-completed** is equal to **media-sheets-completed**.
- For a single-sided, slit-and-merge (2-up) job, **pages-completed** is twice as large as **media-sheets-completed**.
- For a double-sided, 3-up job, **pages-completed** is six times as large as **media-sheets-completed**.

### message (Default Job Only)

Provides a message associated with the default job.

#### DSS

All

#### Type

Resettable, single-valued

#### Allowed Values

You can enter a text string of up to 4095 characters that provides information about this object.

#### Default Value

No default value

### message-from-administrator (Job Only)

See [job-message-from-administrator](#).

### message-to-operator

See [job-message-to-operator](#).

**models-requested**

See **destination-models-requested**.

**modification-time (Job Only)**

Identifies the time when the last modification to this job occurred.

**GUI Label**

Last modified

**DSS**

All

**Type**

Non-settable, single-valued

**Allowed Values**

Infoprint sets this value in the local time format; for example, "*HH:MM:SS mm/dd/yy*" in the USA.

**Default Value**

No default value

**name**

See **job-name**.

**name-of-last-accessor (Job Only)**

Identifies the person or program that submitted the job, or most recently modified the job.

**GUI Label**

Last modified by

**DSS**

All

**Type**

Non-settable, single-valued

**Input Synonyms**

You can use the synonym **last-accessor** or **last-modifier**.

**Allowed Values**

Infoprint sets this value to the login ID of the person or the name of the program that submitted or most recently modified the job.

**Default Value**

The login ID of the person or the name of the program that submitted or most recently modified the job.

**new-job-identifier (Job Only)**

Identifies the global job identifier for a job resubmitted to a logical destination on a different server than where you first submitted the job.

**GUI Label**

New ID

## Job/Default Job

### DSS

All

### Type

Non-settable, single-valued

### Allowed Values

Infoprint sets this value to the correct values for *ServerName:JobIdentifier*

### Default Value

No default value

### Usage Guidelines

If you resubmit the job to a logical destination on the same server, the job identifier remains the same.

## notification-profile

Designates the people that Infoprint notifies when specified events relating to this job occur and how Infoprint notifies the people.

### GUI Label

Notification profile

### DSS

All

### Type

Resettable, multi-valued, complex

### Syntax

```
-x "notification-profile={event-identifiers=event ...  
    delivery-address=name@node delivery-method=value  
    event-comment='some text' locale=locale}"
```

For example,

```
-x "notification-profile={event-identifiers=class-state-changed  
    job-completed delivery-address=joe@newhope delivery-method=message  
    locale=En_US.IBM-850}"
```

You can omit any of these components.

### Components

**event-identifiers:** Specifies the events for which the addressee receives notification that something has taken place.

*GUI Label:* Events

*Type:* Multi-valued

*Allowed Values:* The values can be any of the job events or classes of job events listed for the server. See the **events-supported** attribute for the server for more information.

*Default Values:*

- For default jobs, this component has no default values.



- For jobs, the default values are **document-aborted-by-destination**, **document-aborted-by-server**, **document-cancelled-at-destination**, **job-aborted-by-server**, **job-cancelled-by-operator**, **job-cannot-be-scheduled**, **job-completed**, **past-discard-time**, **destination-needs-attention**, **destination-needs-operator**, **destinations-not-ready-for-job**

**delivery-address:** Specifies the address of the person that receives the event messages or the directory and file name where Infoprint sends the message.

*GUI Label:* Address

*Type:* Single-valued

*Allowed Values:* You can enter a text string that contains the name and node of the person that receives the information or the path to the file.

*Default Value:*

- For default jobs, this component has no default value.
- For jobs, the default value is the login ID of the person who submitted the job.

**delivery-method:** Specifies how the user or file receives event messages.

*GUI Label:* Method

*Type:* Single-valued

*Allowed Values:* You can enter one of these fixed values:

<i>Fixed Value</i>	<i>Input Synonym</i>
<b>electronic-mail</b>	<b>e-mail, email</b>
<b>file</b>	
<b>file-add-to</b>	
<b>job-log</b>	
<b>message</b>	
<b>sapcb</b>	
<b>none</b>	

*Default Value:* **message**

*Usage Guidelines:*

- If you specify a value of **file** or **file-add-to**, you must specify a value for the **delivery-address** component.
- If you specify a value of **job-log**, you cannot specify a value for the **delivery-address** component.
- The **sapcb** notification method causes the SAP callback daemon to return messages about job events to the SAP database. The SAP print command sets this value; you should never have to specify it.

**event-comment:** Provides information that Infoprint appends to the event message.

*GUI Label:* Comment

*Type:* Single-valued

## Job/Default Job

*Allowed Values:* You can enter a text string of up to 4095 characters that supplies additional information.

*Default Value:* No default value

### **locale:**

*Type:* Single-valued

*Allowed Values:* You can enter the name of any locale for which the Infoprint messages in the corresponding language are installed.

*Default Value:*

- For default jobs, this component has no default value.
- For jobs, the default value is the locale of the user who submitted the job.

### **Usage Guidelines**

A default job can have a notification profile that only has one or two components set. When you request this default job for a job, Infoprint fills the remaining components with default values for that job.

## number-of-documents (Job Only)

Identifies the number of documents in the job, including resource documents such as fonts.

### **GUI Label**

Number of documents in job

### **DSS**

All

### **Type**

Non-settable, single-valued

### **Allowed Values**

Infoprint sets this value to an integer from 1 through 2147483647.

### **Default Value**

No default value

## object-class

Identifies the object class to which this object belongs.

### **DSS**

All

### **Type**

Non-settable, single-valued

### **Allowed Values**

Infoprint sets this value to **job** for a job or to **initial-value-job** for a default job.

### **Default Value**

**Job**

**Default job**

**job**

**initial-value-job**

**octets-completed (Job Only)**

Reports the number of octets (bytes) in this job that have been printed or transmitted.

**GUI Label**

KBytes completed

**DSS**

All

**Type**

Non-settable, single-valued

**Allowed Values**

Infoprint sets and updates this value to an integer from 0 to 9223372036854775800 when:

**AIX** You query the job or after each document copy completes.

**BSD** Each result-set completes.

**PSF** Each result-set completes.

**3170** Each result-set completes.

**Email** Each result-set completes.

**Fax** Each result-set completes.

**Passthrough**

Each result-set completes.

**IPP** Each result-set completes.

**Default Value**

No default value

**optimize-for-multiple-copies**

Used with the **optimize-for-multiple-copies** actual destination attribute to indicate whether the destination should save pages in order to print multiple copies of the job faster.

**GUI Label**

Optimize copies

**DSS**

PSF

**Type**

Resettable, single-valued

**Allowed Values**

You can enter one of these fixed values:

<i>Fixed Value</i>	<i>Input Synonym</i>
<b>true</b>	<b>yes</b>
<b>false</b>	<b>no</b>

**Default Value**

No default value

**Usage Guidelines**

- This attribute is used in combination with the **optimize-for-multiple-copies** actual destination attribute:

## Job/Default Job

<i>Job Attribute</i>	<i>Destination Attribute</i>	<i>Results</i>
true	true	Pages are saved
true	false	Pages are not saved
false	true	Pages are not saved
false	false	Pages are not saved
No value	true	Pages are saved
No value	false	Pages are not saved

- If the actual destination cannot save pages, the job is printed and this attribute is ignored.

## originator (Job Only)

See **job-originator**.

## owner (Job Only)

See **job-owner**.

## pages-completed (Job Only)

Reports the number of pages in this job that have been printed, and if you are using the PSF DSS, stacked.

### GUI Label

Pages completed

### DSS

AIX, PSF, Infoprint 2000, Email, Fax

### Type

Non-settable, single-valued

### Allowed Values

Infoprint sets and updates this value to an integer from 0 through 2147483647 when:

- AIX** You query the job or after each document copy completes.
- PSF** The number of pages specified by the actual destination attribute **ack-interval** have printed and at the completion of each result-set.

### Default Value

No default value

### Usage Guidelines

#### PSF DSS

The differences between this attribute and **current-page-printing** are:

- **current-page-printing** is the number of the page being printed or transmitted, while **pages-completed** is the number of pages placed in the stacker. For example, when page 12 of the first copy of a double-sided job is printing, the value of **current-page-printing** is 12 and the value of **pages-completed** is 10.
- **current-page-printing** is reset with every job copy, while **pages-completed** is cumulative within a job. For example, when page 6 of the second copy of a 10-page job is printing, the value of **current-page-printing** is 6. When the same page is stacked, the value of **pages-completed** is 16.

**Note:** Stacking is applicable only with the PSF DSS.

### AIX DSS

The AIX DSS determines **pages-completed** in the following order:

1. If the page count presented by the backend is not zero, Infoprint uses that page count.
2. If the user specified a page count with the **page-count** document attribute, Infoprint uses that page count.
3. When Infoprint can determine a page count from the PostScript or PCL input, Infoprint uses that page count.

### Email and Fax DSSs

Infoprint uses the number of pages completed when the email or fax is successful.

**Note:** Infoprint does not count unsuccessful emails or faxes.

### Infoprint 2000

Infoprint uses the number of pages in the job when it has been spooled to the Infoprint 2000 printer.

## physical-printers-requested

See **actual-destinations-requested**.

## position-in-queue (Job Only)

See **intervening-jobs**.

## previous-job-state (Job Only)

Identifies the state of the job before the last job-state change.

### GUI Label

Previous state

### DSS

All

### Type

Non-settable, single-valued

### Input Synonym

You can use the synonym **previous-state**.

### Allowed Values

Infoprint sets and updates this value to one of these fixed values:

**cancelled**  
**held**  
**imposing**  
**paused**  
**pending**  
**pre-processing**  
**printing**  
**processing**  
**retained**  
**ripping**  
**terminating**  
**unknown**

## Job/Default Job

See the **current-job-state** attribute for a description of these values.

### Default Value

No default value

## previous-state (Job Only)

See **previous-job-state**.

## print-after (Job Only)

See **job-print-after**.

## printer-initial-value-job (Job Only)

See **destination-initial-value-job**.

## printer-locations-requested

See **destination-locations-requested**.

## printer-models-requested

See **destination-models-requested**.

## printer-name-requested

See **destination-name-requested**.

## printer-requested

See **destination-name-requested**.

## printers-assigned (Job Only)

See **destinations-assigned**.

## printers-used (Job Only)

See **destinations-used**.

## processing-time (Job Only)

Reports the amount of time that the job has been printing or transmitting on the output device. If processing has completed, this value is the total amount of time needed to process the job.

### GUI Label

Processing time

### DSS

All

### Type

Non-settable, single-valued

### Allowed Values

Infoprint sets and updates this value using *[HH:]MM*. The unit is minutes or hours and minutes, separated by a colon.

### Default Value

No default value

**Usage Guidelines**

Infoprint updates this attribute when a user queries the job with the **pdls** command. Infoprint calculates the value by comparing the value of the **started-printing-time** job-attribute value with the current time.

**queue-assigned (Job Only)**

Identifies the queue to which Infoprint assigned the job.

**GUI Label**

Queue

**DSS**

All

**Type**

Non-settable, single-valued

**Allowed Values**

Infoprint sets this value to the name of the queue assigned.

**Default Value**

No default value

**Usage Guidelines**

If this attribute is blank, the job does not currently reside in a queue (it may be in the **retained** state).

**queue-position (Job Only)**

See **intervening-jobs**.

**reasons (Job Only)**

See **job-state-reasons**.

**required-resources-not-ready (Job Only)**

Lists attribute values that this job requires, but that are not ready on the actual destination to which this job is assigned, or if the job is not assigned, on the most suitable actual destination.

**GUI Label**

Resources not ready

**DSS**

All

**Type**

Non-settable, multi-valued

**Allowed Values**

Infoprint sets this attribute to the names of the resources that are not ready.

**Default Value**

No default value

**Usage Guidelines**

- When the value of the actual destination attribute **force-destination-setup** is **true**, Infoprint can assign a job to an actual destination even if the required resources are not ready. When the job is about to be printed or transmitted,

## Job/Default Job

Infoprint disables the actual destination and sends a message to the operator to make the destination ready. When the operator enables the destination, the job is processed.

- When the value of the actual destination attribute **force-destination-setup** is **false** for all suitable actual destinations, Infoprint holds jobs that require resources that are not ready and sets **required-resources-not-ready** to a list of those resources.

## required-resources-not-supported (Job Only)

Lists attribute values that this job requires, but that are not supported by the actual destination to which this job is assigned, or if the job is not assigned, by the most suitable actual destination.

### GUI Label

Resources not supported

### DSS

All

### Type

Non-settable, multi-valued

### Allowed Values

Infoprint sets this attribute to the names of the unsupported resources.

### Default Value

No default value

### Usage Guidelines

- Jobs that require unsupported attribute values can be found in the queue under either of these conditions:
  - The value of the server attribute **accept-unsupported-jobs** is **true**.
  - Job, document, or actual destination attributes change after the job has been accepted.
- When the value of the actual destination attribute **force-destination-setup** is **true**, Infoprint can assign a job to an actual destination even if the required resources are not supported. When the job is about to be printed or transmitted, Infoprint disables the actual destination and sends a message to the operator to make the destination ready. When the operator enables the destination, the job is printed or transmitted.
- When the value of the actual destination attribute **force-destination-setup** is **false** for all suitable destinations, Infoprint holds jobs that require resources that are not supported and sets **required-resources-not-ready** to a list of those resources.

## results-profile

Specifies the delivery method for the hardcopy output, and designates who receives output and the number of copies for the recipient.

### DSS

All

### Type

AIX, BSD, PSF, IPP, Passthrough

Resettable, multi-valued, complex



Infoprint 2000

Resettable, single-valued, complex

**Syntax**

```
-x "results-profile=name@node:method:number:'some text':bin"
```

For example:

```
-x "results-profile=nr6445@b1d25:pickup:2:'Please read'"
```

**Components**

**delivery-address:** Specifies the address of the person who receives the job output.

*Type:* Single-valued

*Allowed Values:* You can enter a text string that contains the address.

**AIX** Prints the first 42 characters of the address.

**PSF** Prints the first 8 characters of the address.

*Default Value:* The address of the person who submitted the job.

**delivery-method:**

*Type:* Single-valued

*Allowed Values:* You can only enter the fixed value of **pickup**.

*Default Value:* **pickup**

**job-copies:**

*Type:* Single-valued

*Allowed Values:* You can enter an integer identifying the number of copies. A value of **0** is an error.

*Default Value:* **1**

**results-set-comment:** Supplies a text string that describes the results-set value. This information may print on start sheets.

*Type:* Single-valued

*Allowed Values:* You can enter a text string of up to 4095 characters that provides information such as "Please staple this document" for the operator, or information such as "Please read before meeting tomorrow" for the person who receives the document.

*Default Value:* No default value

**output-bin:** The server does not support this component.

**Usage Guidelines**

The only component that the BSD DSS uses from this complex attribute is the *job-copies* component.

## Job/Default Job

### retained-time (Job Only)

Identifies the time that the job entered the retained state.

#### GUI Label

Became retained

#### DSS

All

#### Type

Non-settable, single-valued

#### Allowed Values

Infoprint sets the value for this attribute in the local time format; USA is "*HH:MM:SS mm/dd/yy*".

#### Default Value

No default value

#### Usage Guidelines

Provides status information.

### retention-period

See [job-retention-period](#).

### start-message

See [job-start-message](#).

### started-printing-time (Job Only)

Identifies the time when Infoprint sent the job to the output device.

#### GUI Label

Started printing

#### DSS

All

#### Type

Non-settable, single-valued

#### Allowed Values

Infoprint sets this value using the local time format. The USA format is "*HH:MM:SS mm/dd/yy*".

#### Default Value

No default value

### state-reasons (Job Only)

See [job-state-reasons](#).

### submission-time (Job Only)

Identifies the time that Infoprint added the job to the queue.

#### GUI Label

Submit time

**DSS**

All

**Type**

Non-settable, single-valued

**Allowed Values**

Infoprint sets this value using the local time format. The USA format is *"HH:MM:SS mm/dd/yy"*.

**Default Value**

No default value

**Usage Guidelines**

The AIX DSS prints this information on the start sheet.

**tape-exit (Job Only)**

Identifies the user exit program used for reading this job from tape.

**DSS**

PSF (AIX Only), Email, Fax, Infoprint 2000

**Type**

Initially settable, single-valued

**Allowed Values**

You can enter any valid program name.

**Default Value**

No default value

**Usage Guidelines**

- You must use this attribute if the tape is not in a standard format, or if you do not specify the format for an unlabeled tape.
- The **pdls** command does not display the value of this attribute.

**tape-format (Job Only)**

Identifies the format of the tape from which Infoprint reads this job.

**DSS**

PSF (AIX Only), Email, Fax, Infoprint 2000

**Type**

Initially settable, single-valued

**Allowed Values**

You can enter one of these fixed values:

- f** IBM fixed-block format
- v** IBM variable-block format
- j** JES2 spool offload format
- a** Auto-detect. For IBM standard labeled tapes, Infoprint determines the tape format.
- p** Passthrough format. Data is passed from the tape to the tape exit program for formatting.

**Default Value****IBM standard labeled tapes****a**

## Job/Default Job

### Nonstandard and unlabeled tapes

p

#### Usage Guidelines

The **pdls** command does not display the value of this attribute.

## tape-labeled (Job Only)

Indicates whether the tape from which Infoprint reads this job is an IBM standard labeled tape.

#### DSS

PSF (AIX Only), Email, Fax, Infoprint 2000

#### Type

Initially settable, single-valued

#### Allowed Values

You can enter one of these fixed values:

<i>Fixed Value</i>	<i>Input Synonym</i>
true	yes
false	no

#### Default Value

true

#### Usage Guidelines

The **pdls** command does not display the value of this attribute.

## tape-max-block-size (Job Only)

Identifies the maximum block size of the tape from which Infoprint reads this job.

#### DSS

PSF (AIX Only), Email, Fax, Infoprint 2000

#### Type

Initially settable, single-valued

#### Allowed Values

You can enter an integer from 1 to 10485760.

#### Default Value

32768

#### Usage Guidelines

- The default value is acceptable for all IBM standard labeled tapes from MVS host systems. Use the **tdump** utility to determine the maximum block size for other tapes. See “tdump Utility: Outputs Tape Contents in Human-Readable Format in Infoprint Manager for AIX” on page 181.
- The **pdls** command does not display the value of this attribute.

## tape-rewind-before (Job Only)

Indicates whether to rewind the tape before reading this job.

#### DSS

PSF (AIX Only), Email, Fax, Infoprint 2000

**Type**

Initially settable, single-valued

**Allowed Values**

You can enter one of these fixed values:

<i>Fixed Value</i>	<i>Input Synonym</i>
true	yes
false	no

**Default Value**

false

**Usage Guidelines**The **pdls** command does not display the value of this attribute.**tape-rewind-unload (Job Only)**

Indicates whether to rewind and unload the tape after reading this job.

**DSS**

PSF (AIX Only), Email, Fax, Infoprint 2000

**Type**

Initially settable, single-valued

**Allowed Values**

You can enter one of these fixed values:

<i>Fixed Value</i>	<i>Input Synonym</i>
true	yes
false	no

**Default Value**

true

**Usage Guidelines**The **pdls** command does not display the value of this attribute.**ticket-content (Job Only)**See **formatted-job-ticket-content**.**total-job-octets (Job Only)**

Identifies the size of the job, which is the sum of all printable octets (bytes) in the job.

**GUI Label**

Size (KBytes)

**DSS**

All

**Type**

Non-settable, single-valued

**Input Synonym**You can use the synonym **job-size**.**Allowed Values**

Infoprint sets this value to an integer from 0 to 9223372036854775800.

## Job/Default Job

### Default Value

No default value

### Usage Guidelines

- The server computes this value by totaling the size of all printable documents, using this algorithm:
  1. For each printable document in the job, multiply the value of **octet-count** by the value of **copy-count**.
  2. Total the values from Step 1.
  3. Multiply the total by the value of **job-copies** component of the **results-profile** job attribute.
- Infoprint validates jobs using this attribute against the actual destination attribute **job-size-range-supported**.
- Infoprint schedules the job against the **job-size-range-ready** actual destination attribute and the **job-size-range-supported** actual destination attribute.

## user-locale (Job Only)

Identifies the language of the information that appears on the start, separator, and end sheets printed with the job and the messages for the job.

### GUI Label

Submitter locale

### DSS

All

### Type

Non-settable, single-valued

### Allowed Values

The locale of the job submitter.

### Default Value

Infoprint sets this value to the locale of the job submitter.

## user-name (Job Only)

Identifies the login ID of the job submitter.

### GUI Label

Submitter ID

### DSS

All

### Type

Non-settable, single-valued

### Allowed Values

Infoprint sets this value to the login ID of the job submitter: *username@node*.

### Default Value

No default value

## Attributes for Logs

Infoprint automatically creates logs when a server initializes. These logs contain and keep track of such things as error messages and trace messages for the server and objects contained in the server. You cannot create or delete these logs, but you can enable or disable them. Infoprint uses a configuration file to set the initial values of attributes for error and trace logs when servers start.

The following restrictions apply to log attributes:

- The **log-severity** attribute applies only to error logs.
- The **log-trace-groups** attribute applies only to trace logs.
- You cannot set the values for the following attributes with the **pdset** command for trace logs. You can specify values using configuration files that Infoprint uses during server initialization.

**log-address**

**log-size**

**log-wrap**

## Initially Settable Attribute Listing

You set this attribute based on the object type.

**log-type**

## Resettable Attribute Listing

You can set these attributes with the **pdset** command after Infoprint creates the log.

**descriptor**

**log-address**

**log-severity**

**log-size** (error logs only; non-settable for trace logs)

**log-trace-groups**

**log-wrap**

## associated-server

Indicates the name of the server in which this log resides.

### Type

Non-settable, single-valued

### Allowed Values

Infoprint sets this value to the name of the server when it creates the log.

### Default Value

No default value

## descriptor

Provides a description of this log.

### Type

Resettable, single-valued

### Allowed Values

You can enter a text string of up to 4095 characters that describes this log.

### Default Value

If you do not enter a value, Infoprint sets the value to:

## log

<i>Log Type</i>	<i>Value</i>
Error	'This is the standard error log.'
Trace	'This is the standard trace log.'

### Usage Guidelines

The use of this attribute is optional. However, a detailed description of the way you set up this log is useful to someone who wants to obtain information from the log.

## enabled

Indicates if the log is enabled. An enabled log writes messages to a log file.

### Type

Non-settable, single-valued

### Allowed Values

Infoprint sets this value to one of these fixed values:

**true**  
**false**

Infoprint implicitly sets this value through the **pdenable** and **pddisable** commands.

### Default Value

The default values are:

<i>Log Type</i>	<i>Value</i>
Error	<b>true</b>
Trace	<b>false</b>

## log-address

Specifies the pathname where the log resides.

### Type

Non-settable, single-valued

### Allowed Values

Infoprint sets this value to the pathname.

### Default Value

The path defined by the **PDBASE** environment variable plus the ServerName (**\$PDBASE/ServerName**).

## log-identifier

Uniquely identifies this log.

### Type

Non-settable, single-valued

### Allowed Values

Infoprint sets this value to the name of the log.

### Default Value

<i>Log Type</i>	<i>Value</i>
Error	<b>default_error</b>
Trace	<b>default_trace</b>



## log-messages

Contains error messages that Infoprint can return to you on a query.

### Type

Non-settable, multi-valued

### Allowed Values

Infoprint stores error log information as the value of this attribute.

### Default Values

No default values

### Usage Guidelines

Use this attribute in conjunction with the **pdls** command and its **message-count** attribute to query for error log information.

## log-severity

Identifies the severity level of the messages that Infoprint logs in this error log.

### Type

Resettable, single-valued

### Allowed Values

You can enter one of these fixed values:

<b>Fixed Value</b>	<b>Explanation</b>
<b>error</b>	This setting produces a minimum of logging. Infoprint only logs error messages. The letter <b>E</b> precedes each message. An error referencing a job signals a condition that may prevent the job from completing successfully, depending on the setting of other parameters.
<b>warning</b>	Infoprint logs both error and warning messages. The letter <b>W</b> precedes each warning message. A warning referencing a job signals a condition that will not prevent completion of the job, but may require some action on the part of the user or operator.
<b>audit</b>	This is the default log severity setting. Infoprint logs error, warning, and audit messages. The letter <b>A</b> precedes each audit message.
<b>debug</b>	This setting logs error, warning, audit, and debug messages. Servers generate debug messages when they begin processing each command and when they communicate with other servers. Debug messages are useful for helping to track what command a server was processing when an error occurred. The letter <b>D</b> precedes each debug messages.
<b>info</b>	This setting logs error, warning, audit, debug, and informational messages. Servers generate informational messages when potentially abnormal situations occur, such as when a server is unable to deliver a notification message to a user because the user is logged off. The letter <b>I</b> precedes each informational message.

### Default Value

**debug**

### Usage Guidelines

This attribute is only for error logs.

## log

### log-size

Specifies how large, in kilobytes, a log file can get before the file wraps, or Infoprint stops logging events. The attribute **log-wrap** determines whether a log file wraps or stops logging.

#### Type

Non-settable (trace logs) or resettable (error logs), single-valued

#### Allowed Values

For an error log, you can enter an integer from 1 through 2147483647 (value represents kilobytes)

#### Default Value

<i>Log Type</i>	<i>Value</i>
Error	1024
Trace	8192

#### Usage Guidelines

- The value specified in the configuration file, if one is specified, overrides the default value when Infoprint creates the server.
- If you change the value for this attribute, Infoprint renames the current log file from *errorlogname* to *errorlogname.BAK*, and creates a new log file.

### log-trace-groups

Specifies the active trace groups for the selective tracing of Infoprint component groups.

#### Type

Resettable, multi-valued

#### Allowed Values

You can enter a text string of up to 4095 characters that contains trace group IDs that Infoprint traces. You should enter a value only at the request of an IBM Service Representative.

#### Default Value

???? -1 (All trace groups)

#### Usage Guidelines

This attribute is only for trace logs. You should use it only at the request of an IBM Service Representative.

### log-type

Identifies the type of log.

#### Type

Non-settable, single-valued

#### Allowed Values

Infoprint sets this value to one of these fixed values:

**errorlog**  
**tracelog**

#### Default Value

No default value

## log-wrap

Specifies whether the log file should wrap when it reaches the specified value in the **log-size** attribute.

### Type

Resettable, single-valued

### Allowed Values

You can enter one of these fixed values:

<i>Fixed Value</i>	<i>Input Synonym</i>
true	yes
false	no

### Default Value

true

### Usage Guidelines

The value specified in the configuration file overrides the default value when Infoprint creates the server.

## object-class

Identifies the object class to which this object belongs.

### Type

Non-settable, single-valued

### Allowed Values

Infoprint sets this value to **log**.

### Default Value

log

### Attributes for Logical Destinations

Infoprint uses logical destinations for job routing, defaulting, and job validation. Some logical destination attributes specify the values that the logical destination supports for the corresponding job and document attributes. Before accepting a job, Infoprint verifies that the logical destination supports the values of these job and document attributes.

#### Notes:

1. If a logical destination attribute has no value, the logical destination supports all valid values for the corresponding job or document attribute.
2. If the value of the server attribute **accept-unsupported-jobs** is **false**, Infoprint also verifies that at least one actual destination supports the job and document attribute values before accepting the job.
3. See “Appendix C. Job Validation and Scheduling” on page 695 for tables showing the attributes used for job validation.

### Attributes Not Displayed in the Infoprint Administrator’s GUI

While all logical destination attributes and attribute values are supported for both basic and advanced Infoprint installations, neither Infoprint administrator’s GUI displays a complete set.

- The basic Infoprint administrator’s GUI displays only the attributes of greatest interest to Infoprint administrators.
- The advanced Infoprint administrator’s GUI displays most attributes and attribute values, but omits a few that are used primarily in basic Infoprint installations.

You can list the values of attributes not displayed in the Infoprint administrator’s GUI using the **pdls** command. You can set the values of initially settable and resettable attributes using the **pdcreate** command. You can change the values of resettable attributes using the **pdset** command.

### Initially Settable Attribute Listing

You can set this attribute with the **pdcreate** command when you create a logical destination.

**destination-realization**

### Resettable Attribute Listing

You can set these attributes with the **pdcreate** command when you create a logical destination or modify them with the **pdset** command after you create the logical destination.

**associated-queue**  
**authorize-jobs**  
**auxiliary-sheet-selections-supported**  
**carriage-control-types-supported**  
**character-mappings-supported**  
**content-orientations-supported**  
**convert-to-ebcdic-supported**  
**data-fidelity-problem-reported-supported**  
**descriptor**  
**destination-initial-value-document**  
**destination-initial-value-job**  
**destination-locations**  
**destination-model**  
**destination-support-system**

document-formats-supported  
 document-types-supported  
 end-message-supported  
 image-out-formats-supported  
 input-trays-supported  
 job-size-range-supported  
 list-of-managers  
 maximum-copies-supported  
 media-supported  
 message  
 notification-profile  
 os2-driver-names  
 page-select-supported  
 plexes-supported  
 print-qualities-supported  
 protected-attributes  
 sides-supported  
 start-message-supported  
 table-reference-characters-supported  
 windows-driver-names  
 windows-nt-driver-names  
 x-image-shift-range-supported  
 y-image-shift-range-supported

## associated-queue

Identifies the queue associated with this destination. Whenever Infoprint accepts a job submitted to this logical destination, it sends the job to the queue specified by this attribute.

### GUI Label

Queue fed

### Type

Resettable, single-valued

### Allowed Values

You can enter a text string of up to 255 characters that contains the name of the queue.

### Default Value

No default value

## associated-server

Indicates the name of the server in which this logical destination resides.

### GUI Label

Server

### Type

Non-settable, single-valued

### Allowed Values

Infoprint sets this value to the *DestinationName* portion of the argument when this logical destination was created.

### Default Value

No default value

## Logical Destination

### authorize-jobs

Indicates whether the person submitting the job requires DCE authorization to submit a job to this logical destination.

#### Type

Resettable, single-valued

#### Allowed Values

You can enter one of these fixed values:

<i>Fixed Value</i>	<i>Input Synonym</i>
true	yes
false	no

#### Default Value

false

#### Usage Guidelines

When the server security level is **medium**, the following rules apply when the value for this attribute is:

<b>true</b>	Infoprint uses the login ID of the job submitter to check if the person has <b>read</b> authority for this destination. If the person does have <b>read</b> authority, Infoprint authorizes the job.
<b>false</b>	Infoprint automatically authorizes the job.

### auxiliary-sheet-selections-supported

Identifies the combination of start, separator, and end sheets that this logical destination supports for jobs.

#### Type

Resettable, multi-valued

#### Allowed Values

You can enter any of these fixed values:

**end**  
**none**  
**sep**  
**sep-end**  
**start**  
**start-end**  
**start-sep**  
**start-sep-end**

#### Default Values

No default values (all valid values supported).

#### Usage Guidelines

- If you do not specify a value, the corresponding actual destination attribute controls which auxiliary sheets a user can request. The default values for the actual destination attribute are all of the supported values.
- Infoprint compares the job attribute **auxiliary-sheet-selection** to this attribute for validation.
- You can use this attribute to restrict use of this logical destination.

## carriage-control-types-supported

Identifies the types of carriage controls that this logical destination supports.

### Type

Resettable, multi-valued

### Allowed Values

You can enter any of these fixed values:

**ansi-ascii**  
**ansi-ebcdic**  
**machine**  
**none**

### Default Values

No default values (all valid values supported).

### Usage Guidelines

- Infoprint compares the document attribute **carriage-control-type** to this attribute for job validation.
- You can use this attribute to restrict use of this logical destination.

## character-mappings-supported

Identifies the character mappings (code pages) that this logical destination supports.

### Type

Resettable, multi-valued

### Allowed Values

You can enter any of these fixed values:

**ibm-437**  
**ibm-850**  
**ibm-860**  
**ibm-863**  
**ibm-865**  
**ibm-932**  
**ibm-938**  
**ibm-euccn**  
**ibm-eucjp**  
**ibm-euckr**  
**IBM-euctw**

### Default Values

No default values (all valid values supported).

### Usage Guidelines

- Infoprint compares the document attribute **default-character-mappings** to this attribute for job validation.
- You can use this attribute to restrict use of this logical destination.

## content-orientations-supported

Identifies the page presentations that this logical destination supports.

### Type

Resettable, multi-valued

## Logical Destination

### Input Synonym

You can use the synonym **orientations-supported**.

### Allowed Values

You can enter any of these fixed values:

**landscape**  
**portrait**  
**reverse-portrait**  
**reverse-landscape**

### Default Values

No default values (all valid values supported).

### Usage Guidelines

- Infoprint compares the document attribute **content-orientation** to this attribute for job validation.
- If you do not specify a value for this attribute, the corresponding actual destination attribute controls orientations. The default for the actual destination attribute is **portrait**.
- Infoprint supplies attribute files that specify the values that a particular destination model supports.
- You can use this attribute to restrict use of this logical destination.

## convert-to-ebcdic-supported

Indicates whether this logical destination supports converting document data from ASCII to EBCDIC.

### Type

Resettable, single-valued

### Allowed Values

You can enter one of these fixed values:

<i>Fixed Value</i>	<i>Input Synonym</i>
<b>true</b>	<b>yes</b>
<b>false</b>	<b>no</b>

### Default Value

No default value (all valid values supported).

### Usage Guidelines

- Use this attribute to request conversion for line-data jobs sent to a PSF actual destination.
- If you do not specify a value for this attribute, the corresponding actual destination attribute controls conversion. The default value for the actual destination attribute is **true**.

**Note:** The corresponding document attribute, **convert-to-ebcdic**, defaults to no value. Users specify **true** only if they want to convert the content of the document from ASCII to EBCDIC. Validation only fails if the user sets **convert-to-ebcdic** to **true** and either this logical destination value or the actual destination attribute value is **false**.

- Infoprint compares the document attribute **convert-to-ebcdic** to this attribute for job validation.
- You can use this attribute to restrict use of this logical destination.



**data-fidelity-problem-reported-supported**

Indicates which type of data fidelity errors this logical destination can report.

**Type**

Resettable, multi-valued

**Allowed Values**

You can enter any of these fixed values:

**all**  
**character**  
**none**  
**position**

**Default Values**

No default values (all valid values supported).

**Usage Guidelines**

- Use this attribute to specify whether Infoprint issues error messages for print-positioning and invalid-character errors that occur for channel-attached and TCP/IP-attached printer devices.  
 Print positioning errors occur when the print position for the data is beyond the valid printable areas as defined by the intersection of the physical and logical pages. (A logical page identifies the printing boundaries of a physical page.)  
 Invalid-character errors occur when the code point does not map to a character in a font.
- Infoprint compares the document attribute **data-fidelity-problem-reported** to this attribute for validation.
- You can use this attribute to restrict use of this logical destination.

**descriptor**

Provides a textual description of this logical destination.

**GUI Label**

Description

**Type**

Resettable, single-valued

**Allowed Values**

You can enter a text string of up to 4095 characters that contains a description of this logical destination. You may want to include such information as:

- The name of the department or the account number of the users who use this logical destination.
- Usage information, such as whether the logical destination provides default values for jobs or restricts use of actual destination capabilities.

**Default Value**

No default value

**Usage Guidelines**

The use of this attribute is optional. However, a detailed description is useful if you have several logical destinations or have set up restriction for this logical destination.

## Logical Destination

### destination-associated-destinations

Identifies the actual destinations that receive jobs from the queue associated with this logical destination.

#### Type

Non-settable, multi-valued

#### Input Synonym

You can use the synonym **printer-associated-printers**.

#### Allowed Values

Infoprint sets this value, and the queue attribute **actual-destinations-assigned** of the queue associated with this logical destination, when the actual destination registers.

#### Default Values

No default value

### destination-initial-value-document

Associates a default document with this logical destination.

#### GUI Label

Default document

#### Type

Resettable, single-valued

#### Input Synonym

You can use the synonym **printer-initial-value-document**.

#### Allowed Values

You can enter a text string of up to 255 characters that contains the name of the default document.

#### Default Value

No default value

#### Usage Guidelines

The default document supplies values for attributes for documents submitted to this logical destination. These values override server defaults but are overridden by document attribute values specified on the command line.

### destination-initial-value-job

Associates a default job with this logical destination.

#### GUI Label

Default job

#### Type

Resettable, single-valued

#### Input Synonym

You can use the synonym **printer-initial-value-job**.

#### Allowed Values

You can enter a text string of up to 255 characters that contains the name of the default job.

**Default Value**

No default value

**Usage Guidelines**

The associated default job supplies values for attributes of jobs submitted to this logical destination. These values override server defaults but are overridden by job attribute values specified on the command line.

**destination-locations**

Identifies the locations of output devices, or the areas they service, that this logical destination allows for jobs.

**GUI Label**

Actual destination locations

**Type**

Resettable, multi-valued

**Input Synonyms**

You can use the synonym **printer-locations** or **locations**.

**Allowed Values**

You can enter a text string of up to 4095 characters, per value, that contains the locations of the output devices associated with this logical destination.

**Default Values**

No default values (all valid values supported).

**Usage Guidelines**

- Infoprint compares the job attribute **destination-locations-requested** to this attribute for validation.
- You can use this attribute to restrict use of this logical destination.
- You can query this attribute to find where destinations are located.

**destination-model**

Identifies the make and model ID of an output device that can accept jobs submitted through this logical destination.

**Type**

Resettable, single-valued

**Input Synonyms**

You can use the synonym **printer-model** or **model**.

**Allowed Values**

You can enter a text string of up to 4095 characters, per value, that contains the make and model of an output device.

**Default Value**

No default value (all valid values supported).

**destination-name**

Identifies this logical destination.

**Type**

Non-settable, single-valued

## Logical Destination

### Input Synonyms

You can use the synonym **printer-name**, **printer**, or **logical-printer**.

### Allowed Values

Infoprint sets this value to the *DestinationName* portion of the argument specified by the **pdcreate** command used to create this logical destination.

### Default Value

No default value

### Usage Guidelines

- The logical destination name must be unique within the namespace.
- Infoprint compares the job attribute **actual-destination-requested** to this attribute for validation.

## destination-realization

Indicates whether the destination is an actual destination or a logical destination.

### Type

Initially settable, single-valued

### Input Synonym

You can use the synonym **printer-realization**.

### Allowed Values

You can enter one of these values:

**actual**  
**logical**

### Default Value

**logical**

## destination-support-system

Identifies the DSS (type of device driver) allowed for jobs submitted to this logical destination.

### Type

Resettable, single-valued

### Input Synonym

You can use the synonym **device-support-system**.

### Allowed Values

You can enter one of these fixed values:

<i>Fixed Value</i>	<i>Input Synonym</i>
<b>aix</b>	<b>piobe</b>
<b>bsd</b>	
<b>psf</b>	
<b>3170</b>	
<b>email</b>	
<b>fax</b>	
<b>Passthrough</b>	
<b>IPP</b>	

### Default Value

No default value (all valid values supported).

**Usage Guidelines**

Infoprint compares the job attribute **dss-requested** to this attribute for validation.

**destinations-ready**

Identifies the actual destinations associated with this logical destination that are ready to process a job.

**Type**

Non-settable, multi-valued

**Input Synonym**

You can use the synonym **printers-ready**.

**Allowed Values**

Infoprint sets this value with the name of an actual destination when a registered actual destination is ready.

A ready actual destination is one that is enabled and whose state is **idle**, **connecting-to-printer**, or **printing**.

**Default Values**

No default value

**device-support-system**

See **destination-support-system**.

**document-formats-supported**

Identifies the document formats that this logical destination supports.

**Type**

Resettable, multi-valued

**Allowed Values**

You can enter any of these fixed values:

<i>Fixed Value</i>	<i>Input Synonym</i>
ascii	
dbcs-ascii	
ditroff	
d630	
gif	
hpgl	hp-gl
iso-6429	
jpeg	
line-data	
modca-p	afpds
passthru	
pcl	hppcl, hp-pcl
pdf	
postscript	ps
ppds	
sap	
sap-abap	
simple-text	text
tiff	

## Logical Destination

### Default Values

No default values (all valid values supported).

### Usage Guidelines

- Infoprint compares the document attribute **document-format** to this attribute for job validation.
- All documents in a job must have the same format.
- You can use this attribute to restrict use of this logical destination.

## document-types-supported

Identifies the types of documents that this logical destination supports.

### Type

Resettable, multi-valued

### Allowed Values

You can enter any of these fixed values:

**cover-sheet**  
**document-definition**  
**email-body**  
**email-signature**  
**file-reference**  
**font**  
**form-definition**  
**formatted-job-ticket**  
**insert**  
**job-ticket**  
**overlay**  
**page-definition**  
**page-segment**  
**page-shift-file**  
**printable**  
**resource**  
**variable-data**

### Default Values

No default values (all valid values supported).

### Usage Guidelines

- Infoprint compares the document attribute **document-type** to this attribute for job validation.
- You can use this attribute to restrict use of this logical destination.

## enabled

Indicates whether this logical destination is enabled and can accept jobs.

### Type

Non-settable, single-valued

### Allowed Values

Infoprint sets and resets this value to one of these fixed values:

**true**  
**false**

Infoprint sets and resets this value based on the **pdenable** and **pddisable** commands.

**Default Value**

false

**end-message-supported**

Indicates whether this logical destination supports the job attribute **job-end-message**.

**Type**

Resettable, single-valued

**Allowed Values**

You can enter one of these fixed values:

<i>Fixed Value</i>	<i>Input Synonym</i>
<b>true</b>	<b>yes</b>
<b>false</b>	<b>no</b>

**Default Value**

No default value (all valid values supported).

**Usage Guidelines**

- When you set this attribute value to **true**, operators can receive messages that users specify with the **job-end-message** job attribute when they submit the job. Infoprint sends the message to the operators specified by the **notify-operator** attribute for this actual destination when the job finishes printing.
- Infoprint compares the job attribute **job-end-message** to this attribute for validation.
- You can use this attribute to restrict use of this logical destination.

**image-out-formats-supported**

Specifies the formats of the image data, produced by the program that converts line data to AFP data, that this logical destination supports.

**Type**

Resettable, multi-valued

**Allowed Values**

You can enter any of these fixed values:

**ioca-uncompressed**  
**im1**  
**io1**  
**io1-g4**  
**io1-mmr**  
**asis**

**Default Values**

No default values (all valid values supported).

**Usage Guidelines**

- Infoprint compares the document attribute **image-out-format** to this attribute for job validation. You should use the document attribute when you print line-data documents.
- The value **io1-g4** applies only to the destination. You cannot request this value with the document attribute **image-out-format**. If the document format is **postscript** and the value **io1-g4** for this attribute is:

## Logical Destination

<b>Present</b>	The PostScript transform produces IO1-G4 images.
<b>Not present</b>	The PostScript transform produces IM1 images instead of IO1-G4 images, which the printer device associated with an actual destination that receives jobs from the queue associated with this logical destination cannot print.

## input-trays-supported

Specifies the types of input trays that this logical destination supports.

### Type

Resettable, multi-valued

### Allowed Values

You can enter any of these fixed values:

<b>auto-envelope-feed</b>	<b>manual-envelope-feed</b>
<b>automatic-tray</b>	<b>middle</b>
<b>auxiliary-envelope</b>	<b>top</b>
<b>auxiliary-paper</b>	<b>tray-1</b>
<b>bottom</b>	<b>tray-2</b>
<b>continuous-form-feed</b>	<b>tray-3</b>
<b>current-selected-tray</b>	<b>tray-4</b>
<b>envelope</b>	<b>tray-5</b>
<b>large-capacity</b>	<b>2000-sheet</b>
<b>manual</b>	

or any input tray name, for example:

**alternate**  
**auto-envelope-feed**  
**bottom**  
**continuous-form-feed**  
**envelope**  
**insert**  
**large-capacity**  
**manual**  
**manual-envelope-feed**  
**middle**  
**top**

### Default Values

No default values (all valid values supported).

### Usage Guidelines

- You can use this attribute to restrict the use of this logical destination.
- If you do not specify a value for this attribute, the corresponding actual destination attribute determines which input trays the actual destination supports and users can request.
- Infoprint compares the document attribute **default-input-trays** or **input-tray-select** to this attribute for job validation.

## job-size-range-supported

Defines the range of job sizes in bytes (octets) that this logical destination will accept.



**Type**

Resettable, single-value, complex

**Syntax**

*lower-limit:upper-limit*

Separate the limits by a colon (:), for example:

0:1000000000

You can omit either value, for example:

0:  
:1000000000

**Note:** If you enter a single value without a colon (*integer:*), it is considered the lower limit.

**Components**

**lower-limit:** Provides the lower limit of the job size range.

*Type:* Single-valued

*Allowed Values:* You can enter an integer from 0 to 9223372036854775800. The lower limit must be less than or equal to the upper limit. The unit value is bytes (octets).

*Default Value:* No default value

**upper-limit:** Provides the upper limit of the job size range.

*Type:* Single-valued

*Allowed Values:* You can enter an integer from 0 to 9223372036854775800. The upper limit must be greater than or equal to the lower limit. The unit value is bytes (octets).

*Default Value:* 9223372036854775800

**Usage Guidelines**

- Infoprint compares the job attribute **total-job-octets** to this attribute for validation.
- You can use this attribute to restrict the use of this logical destination.

**list-of-managers**

Lists the people responsible for the configuration and operation of this logical destination.

**GUI Label**

Managers

**Type**

Resettable, multi-valued

**Input Synonym**

You can use the synonym **managers**.

## Logical Destination

### Allowed Values

You can enter a text string up to 255 characters long, per value, that contains the name or user ID of the person responsible for this logical destination.

### Default Values

No default values

### Usage Guidelines

This attribute is useful if a user needs to contact someone to report a problem or to request a change.

## locations

See **destination-locations**.

## logical-printer

See **destination-name**.

## managers

See **list-of-managers**.

## maximum-copies-supported

Indicates the number of document copies, in a single job, that this logical destination allows.

### Type

Resettable, single-valued

### Allowed Values

You can enter an integer from 1 through 2147483647.

### Default Value

No default value (all valid values supported).

### Usage Guidelines

- You can use this attribute to restrict the use of this logical destination by limiting the number of document copies that a user can request for jobs submitted to this logical destination.
- If you do not specify a value for this attribute, the corresponding actual destination attribute controls the number of copies allowed.
- Infoprint compares the document attribute **copy-count** to this attribute for job validation.

## media-supported

Identifies the types of media that this logical destination supports.

### Type

Resettable, multi-valued

### Allowed Values

You can enter a text string up to 255 characters long that contains the names of the media. These can be:

- The medium identifiers of medium objects created by the **pdcrmed** utility. For these fixed values, see the medium **medium-identifier** attribute.
- The medium identifiers of medium objects you created yourself.

## Logical Destination

- Any names that describe the media, even if no medium objects with those names exist.

### Default Values

No default values (all valid values supported).

### Usage Guidelines

- You can restrict the use of this logical destination by limiting the type of media that a user can request for jobs submitted to actual destinations.
- If you do not specify a value for this attribute, the corresponding actual destination attribute determines which media the actual destination supports and users can request.
- Infoprint compares the document attribute **default-medium** or **page-media-select** to this attribute for job validation.

## message

Provides information associated with this logical destination.

### Type

Resettable, single-valued

### Allowed Values

You can enter a text string of up to 4095 characters that contains information about this logical destination.

### Default Value

No default value

## model

See **destination-model**.

## notification-profile

Designates which persons Infoprint notifies of specific events related to this logical destination, and how Infoprint notifies them.

### Type

Resettable, multi-valued, complex

### Syntax

```
-x "notification-profile={event-identifiers=event ...  
  delivery-address=name@node delivery-method=value  
  event-comment='some text' locale=locale}"
```

For example:

```
-x "notification-profile={event-identifiers=class-logical-destination-status  
  delivery-address=jim@staff delivery-method=e-mail  
  event-comment='everything ok' locale=En_US.IBM-850}"
```

You can omit any of these components.

### Components

**event-identifiers:** Specifies the events for which Infoprint issues notification messages.

## Logical Destination

*Type:* Multi-valued

*Allowed Values:* You can enter any of the values listed for the server **events-supported** attribute.

*Default Values:* **object-deleted, object-cleaned**

**delivery-address:** Identifies the address of the person who receives event messages or the directory and file name where Infoprint stores messages.

*Type:* Single-valued

*Allowed Values:* You can enter a name and node or a path and file name.

*Default Value:* The login ID of the user who created this logical destination.

**delivery-method:** Specifies how event messages are received.

*Type:* Single-valued

*Allowed Values:* You can enter one of these fixed values:

<i>Fixed Value</i>	<i>Input Synonym</i>
<b>electronic-mail</b>	<b>e-mail, email</b>
<b>file</b>	
<b>file-add-to</b>	
<b>message</b>	
<b>none</b>	

*Default Value:* **message**

*Usage Guidelines:* If you specify a value of **file** or **file-add-to** for this component, you must specify a value for the **delivery-address** component.

**event-comment:** Provides a comment that Infoprint appends to the event message.

*Type:* Single-valued

*Allowed Values:* You can enter a text string of up to 4095 characters that contains the comment.

*Default Value:* No default value

**locale:** Defines the language and code page of notification messages.

*Type:* Single-valued

*Allowed Values:* You can enter any locale for which the Infoprint messages in the corresponding language are installed.

*Default Value:* The locale of the person who created this logical destination.

## nt-drivers

See **windows-nt-driver-names**.

**object-class**

Identifies the object class to which this object belongs.

**Type**

Non-settable, single-valued

**Allowed Values**

Infoprint sets this value to **destination**.

**Default Value**

**destination**

**orientations-supported**

See **content-orientations-supported**.

**os2-driver-names**

Identifies the OS/2 print drivers that can submit a data stream to this logical destination.

**GUI Label**

OS/2 drivers

**Type**

Resettable, multi-valued

**Input Synonym**

You can use the synonym **os2-drivers**.

**Allowed Values**

You can enter a text string that contains the name of the OS/2 print driver in this format:

'filename.descriptive name'

Begin and end the string with single quotation marks.

**Default Values**

No default values

**Usage Guidelines**

- Perform the following procedure on the OS/2 workstation to determine the valid OS/2 driver names:

1. Open the OS/2 **Templates** folder.
2. Drag the **Printer** icon to your Desktop. The OS/2 **Create a Printer** window displays.
3. Select the **Install new destination driver...** push button. The **Install New Printer Driver** window displays listing the names of destination drivers shipped with OS/2.

If OS/2 does not provide the destination driver that you want to use, select the **Other OS/2 destination driver** radio button and load the diskette containing the driver. OS/2 refreshes the list with the drivers contained on the diskette.

4. Locate the destination driver or drivers you want to use for jobs submitted through the OS/2 client and record the names you will assign to the **os2-driver-names** logical destination attribute. The format of the name you will assign as a value for the logical destination attribute differs from the

## Logical Destination

format in the OS/2 list. First, record the file name of the driver followed by a period, such as **LASERJET**. (all driver files listed have the **DRV** file extension). Next, record the descriptive name of the driver, such as **IBM 4019 LaserPrinter E**. For each driver listed by OS/2, the descriptive name appears twice on the same line, separated by a colon. Finally, surround the driver name and descriptive name with single quotation marks.

See the following examples of how to construct values for the **os2-driver-names** logical destination attribute:

- To use the destination driver listed as **IBM 4019 LaserPrinter E: IBM 4019 LaserPrinter E (IBM4019.DRV)**, record the name **'IBM4019.IBM 4019 LaserPrinter E'**
  - To use the destination driver listed as **IBM 4019 v52\_1 (17 Fonts): IBM 4019 v52\_1 (17 Fonts) (PSCRIPT.DRV)**, record the name **'PSCRIPT.IBM 4019 v52\_1 (17 Fonts)'**
  - To use the destination driver listed as **IBM 4029 (39 Fonts 600 Dpi): IBM 4029 (39 Fonts 600 Dpi) (PSCRIPT.DRV)**, record the name **'PSCRIPT.IBM 4029 (39 Fonts 600 Dpi)'**
5. You must have any driver that you specify as a value for the **os2-driver-names** logical destination attribute installed on the OS/2 workstation. To determine if the driver is installed, select the **Install** push button.
- If the driver is installed, OS/2 displays a message indicating this.
  - If the driver is not installed, OS/2 displays a window requesting that you load the media containing the driver. You must install the destination driver if you want to use it. Select the **Help** button in the window to access the OS/2 help information for installing destination drivers.
- In most cases, you select the driver based on the data stream required by the output device. However, if you will be submitting jobs from the OS/2 client to a PSF actual destination, you should select a generic destination driver, such as **PSCRIPT.DRV**, instead of one for a specific device. Otherwise, the driver may generate device-specific data streams that Infoprint cannot transform correctly.
6. After you have recorded the OS/2 driver names and ensured that the drivers you want to use are installed, close all OS/2 windows that you opened during this procedure.
- You can use this attribute to restrict use of this logical destination.

## os2-drivers

See **os2-driver-names**.

## page-select-supported

Specifies the type of page number that this logical destination supports.

### Type

Resettable, multi-valued

### Allowed Values

You can enter a fixed value of **numeric**. This means that the value for the document attribute **page-select** can only be numeric.

### Default Value

**numeric**

**Usage Guidelines**

Infoprint compares the document attribute **page-select** against this attribute for job validation and scheduling.

**plexes-supported**

Identifies the plexes that this destination supports. Plex indicates whether the page images of the output document are conditioned for eventual one-sided or two-sided printing, and the relative orientation of consecutive pages.

**Type**

Resettable, multi-valued

**Allowed Values**

You can enter any of these fixed values:

- simplex**
- tumble**

**Default Values**

No default values (all valid values supported).

**Usage Guidelines**

Infoprint compares the document attribute **plex** to this attribute for job validation.

**print-qualities-supported**

Identifies the levels of print quality that this logical destination supports.

**Type**

Resettable, multi-valued

**Input Synonym**

You can use the synonym **qualities-supported**.

**Allowed Values**

You can enter any of these fixed values:

- draft**
- high**
- normal**

**Default Values**

No default values (all valid values supported).

**Usage Guidelines**

- Infoprint compares the document attribute **print-quality** to this attribute for job validation.
- You can use this attribute to restrict use of this logical destination.

**printer**

See **destination-name**.

**printer-associated-printers**

See **destination-associated-destinations**.

**printer-initial-value-document**

See **destination-initial-value-document**.

## Logical Destination

### printer-initial-value-job

See **destination-initial-value-job**.

### printer-locations

See **destination-locations**.

### printer-model

See **destination-model**.

### printer-name

See **destination-name**.

### printer-realization

See **destination-realization**.

### printers-ready

See **destinations-ready**.

### protected-attributes

Specifies one or more logical destination attributes that DCE prevents Infoprint operators from setting or changing.

#### Type

Resettable, multi-valued

#### Allowed Values

You can enter one or more logical destination attribute names.

#### Default Values

This attribute always specifies itself, **protected-attributes**, as a value.

#### Usage Guidelines

Normally, anyone with DCE **write** permission for logical destinations can set values for logical destination attributes. By default, the **pd\_admin** and **pd\_operator** DCE groups both have **write** permission. Once you define a logical destination attribute as a protected attribute, you must have DCE **delete** permission to modify the attribute. Members of the **pd\_operator** DCE group do not have **delete** permission unless the DCE administrator has modified the default permissions for that group.

### qualities-supported

See **print-qualities-supported**.

### sides-supported

Identifies whether this logical destination supports printing on one or both sides of the media.

#### Type

Resettable, multi-valued

#### Allowed Values

You can enter an value of **1**, **2**, or both.



**Default Values**

No default values (all valid values supported).

**Usage Guidelines**

- You can use this attribute to restrict use of this logical destination.
- If you do not specify a value for this attribute, the corresponding actual destination attribute controls the printable sides that users can request.
- Infoprint compares the document attribute **sides** to this attribute for job validation.

**start-message-supported**

Indicates whether this logical destination supports the job attribute **job-start-message**.

**Type**

Resettable, single-valued

**Allowed Values**

You can enter one of these fixed values:

<i>Fixed Value</i>	<i>Input Synonym</i>
<b>true</b>	<b>yes</b>
<b>false</b>	<b>no</b>

**Default Value**

No default value (all valid values supported).

**Usage Guidelines**

- When you set this attribute value to **true**, operators can receive messages that users specify with the **job-start-message** job attribute when they submit the job. Infoprint sends the message to the operators specified by the **notify-operator** attribute for this actual destination when the job starts printing. Sending a start message does not stop the job from printing; normally the job prints without operator intervention.
- Infoprint compares the job attribute **job-start-message** to this attribute for validation.
- You can use this attribute to restrict use of this logical destination.

**table-reference-characters-supported**

Identifies whether this logical destination supports table-reference characters. Some line-data applications produce table-reference characters to specify font changes.

**Type**

Resettable, single-valued

**Allowed Values**

You can enter one of these fixed values:

<i>Fixed Value</i>	<i>Input Synonym</i>
<b>true</b>	<b>yes</b>
<b>false</b>	<b>no</b>

**Default Value**

No default value (all valid values supported).

## Logical Destination

### Usage Guidelines

- If you do not specify a value for this attribute, the corresponding actual destination attribute determines whether the actual destination can process table reference characters.

The corresponding document attribute, **table-reference-characters**, defaults to no value. The user specifies **true** only if the line data contains table reference characters that should be processed. Validation fails only if the user sets **table-reference-characters** to **true** and either this logical destination value or the actual destination attribute value is **false**.

- Infoprint compares the document attribute **table-reference-characters-supported** to this attribute for job validation.
- You can use this attribute to restrict use of this logical destination.

## windows-driver-names

Identifies the Windows 3.1.1 or WIN-OS/2 print drivers that can submit a data stream to this logical destination.

### GUI Label

Windows 3.1 drivers

### Type

Resettable, multi-valued

### Input Synonym

You can use the synonym **windows-drivers**.

### Allowed Values

You can enter a text string that contains the string form of the Windows print driver for each permitted Windows print driver. Begin and end the string with single quotation marks.

### Default Values

No default values

### Usage Guidelines

- Perform the following procedure to determine the valid Windows driver names.
  1. For WIN-OS/2, start a WIN-OS/2 full-screen session to access the Windows **Program Manager**.
  2. Select and open the **Control Panel** icon from the main window.
  3. Select and open the **Printers** icon.
  4. Select the **Add >>** push button from the **Printers** dialog box.
  5. The values listed in the **List of Printers:** list box are the names of the Windows destination drivers that you can install on the workstation; for example, **IBM 4039 LaserPrinter PS**.

#### Notes:

1. Other destination drivers are available and may not display in the list for a particular workstation.
  2. If you will be submitting jobs from the Windows client to a PSF actual destination, you should select a generic device driver, such as a PostScript driver, instead of one for a specific device. Otherwise, the driver may generate device-specific data streams that Infoprint cannot transform correctly.
- You can use this attribute to restrict use of this logical destination.

## windows-drivers

See **windows-driver-names**.

## windows-nt-driver-names

Identifies the 32-bit Windows print drivers that can submit a data stream to this logical destination.

### GUI Label

Windows drivers

### Type

Resettable, multi-valued

### Input Synonyms

You can use the synonym **windows-nt-drivers** or **nt-drivers**.

### Allowed Values

You can enter a text string that contains the string form of the Windows print driver for each permitted Windows print driver. Begin and end the string with single quotation marks.

### Default Values

No default values

### Usage Guidelines

- Perform the following procedure to determine the valid Windows driver names:
  1. Select **My Computer** from the desktop.
  2. Select and open the **Control Panel** icon.
  3. Select and open the **Printers** icon,
  4. Select and open the **Add Printer** icon.
  5. The values listed in the **Printers:** list box in the **Add Printer Wizard** are the names of the Windows destination drivers that you can install on the workstation; for example, **IBM 4039 LaserPrinter PS**.

#### Notes:

1. Other destination drivers are available and may not display in the list for a particular workstation.
  2. If you will be submitting jobs from the Windows client to a PSF actual destination, you should select a generic destination driver, such as a PostScript driver, instead of one for a specific type of destination. Otherwise, the driver may generate device-specific data streams that Infoprint cannot transform correctly.
- You can use this attribute to restrict use of this logical destination.

## windows-nt-drivers

See **windows-nt-driver-names**.

## x-image-shift-range-supported

Specifies, in millimeters, the lower and upper numeric boundaries for the X offset of a page. The X offset, along with the Y offset, sets the origin of the logical page on the physical page.

### Type

Resettable, single-valued, complex

## Logical Destination

### Syntax

*lower-limit:upper-limit*

Each value uses a format of *nnnn.nnn* where *nnnn.nnn* is the decimal millimeter value. Separate the values with a colon, for example:

1:10

### Components

**lower-limit:** Defines the minimum amount of image shift that the document or default document attribute **x-image-shift** or **x-image-shift-back** can specify.

*Type:* Single-valued

*Allowed Values:* You can enter a numeric value from -577.99 mm through 577.97 mm.

*Default Value:* No default value

**upper-limit:** Defines the maximum amount of image shift that the document or default document attribute **x-image-shift** or **x-image-shift-back** can specify.

*Type:* Single-valued

*Allowed Values:* You can enter a numeric value from -577.99 mm through 577.97 mm.

*Default Value:* No default value

### Usage Guidelines

You can use this attribute to restrict use of this logical destination.

## y-image-shift-range-supported

Specifies, in millimeters, the lower and upper numeric boundaries for the Y offset of a page. The Y offset, along with the X offset, sets the origin of the logical page on the physical page.

### Type

Resettable, single-valued, complex

### Syntax

*lower-limit:upper-limit*

Each value uses a format of *nnnn.nnn* where *nnnn.nnn* is the decimal millimeter value. Separate the values with a colon, for example:

1:20

### Components

**lower-limit:** Defines the minimum amount of image shift that the document or default document attribute **y-image-shift** or **y-image-shift-back** can specify.

*Type:* Single-valued

## Logical Destination

*Allowed Values:* You can enter a numeric value from -577.99 mm through 577.97 mm.

*Default Value:* No default value

***upper-limit:*** Defines the maximum amount of image shift that the document or default document attribute **y-image-shift** or **y-image-shift-back** can specify.

*Type:* Single-valued

*Allowed Values:* You can enter a numeric value from -577.99 mm through 577.97 mm.

*Default Value:* No default value

### Usage Guidelines

You can use this attribute to restrict use of this logical destination.

### Attributes for Media

A medium represents the type of media, that is, paper, envelopes, transparencies, or multi-part forms, on which a printer device prints.

Infoprint uses the names of media as values for actual destination attributes, such as **media-supported**. Actual destination attributes that reference media can use any name as long as the name is within syntax limits. The AIX and 3170 DSSs validate any actual destination attribute that references a medium to ensure that the object exists. The BSD and PSF DSSs accept values that are not the names of existing media.

You must create at least the default medium objects. The **startsrv** utility normally creates the default medium objects. If it fails to do so, use the **pdcrdflt** utility to create the default medium and auxiliary sheet objects.

### Attributes Not Displayed in the Infoprint Administrator's GUI

While all medium attributes are supported for both basic and advanced Infoprint installations, the basic Infoprint administrator's GUI displays only the medium attributes of greatest interest to Infoprint administrators. The advanced Infoprint administrator's GUI does not display media.

You can list the values of attributes not displayed in the Infoprint administrator's GUI using the **pdls** command. You can set the values of initially settable and resettable attributes using the **pdcreate** command. You can change the values of resettable attributes using the **pdset** command.

### Initially Settable Attribute Listing

There are no initially settable attributes for a medium.

### Resettable Attribute Listing

You can set these attributes with the **pdcreate** command when you create a medium or modify them with the **pdset** command after you create the medium.

- descriptor**
- medium-color**
- medium-dimensions**
- medium-form-parts**
- medium-holes-count**
- medium-sides**
- medium-size**
- medium-type**
- message**

### associated-server

Indicates the name of the server in which this medium resides.

#### Type

Non-settable, single-valued

#### Allowed Values

Infoprint sets this value to the value of the *ServerName* portion of the argument when you create the medium using the **pdcreate** command.

#### Default Value

No default value

**descriptor**

Provides a description of the medium.

**Type**

Resettable, single-valued

**Allowed Values**

You can enter a text string up to 4095 characters long that describes this medium.

**Default Value**

No default value

**Usage Guidelines**

The use of this attribute is optional. However, a detailed description of this medium and its use is helpful to users who want to determine if this is the medium that they want to use.

**medium-color**

Indicates the color of this medium.

**Type**

Resettable, single-valued

**Allowed Values**

You can enter one of these fixed values or some other color:

<i>Fixed Value</i>	<i>Input Synonym</i>
blue	
buff	
goldenrod	
green	
pink	
transparent	untinted
white	
yellow	

**Default Value**

No default value

**Usage Guidelines**

Specifying the color can be useful if you have configured a large number of AIX actual destinations and have used the **media-supported** and **input-trays-medium** attributes to identify the different types of media that the actual destination supports and the media currently loaded in the input trays of each printer device. This allows a user to query and filter for the colors of various medium objects to determine the medium to use for a job.

**medium-dimensions**

Specifies the physical size (width and length), in millimeters, of the medium.

**Type**

Resettable, single-valued, complex

**Syntax**

You can enter two positive real numbers separated by a colon.

*x-dimension:y-dimension*

## Medium

For example:

100.8:200.4

### Components

***x-dimension:*** Specifies the width of the medium, which is usually the shorter dimension in respect to how the medium is loaded into the printer device.

*Type:* Single-valued

*Allowed Values:* You can enter a positive real number, which may optionally contain a decimal point. The unit is millimeters.

*Default Value:* No default value

***y-dimension:*** Specifies the height of the medium, which is usually the longer dimension in respect to how the medium is loaded into the printer device.

*Type:* Single-valued

*Allowed Values:* You can enter a positive real number, which may optionally contain a decimal point. The unit is millimeters.

*Default Value:* No default value

### Usage Guidelines

- The medium must contain this value if AIX actual destinations use the medium.
- The **pio** backend uses the value of this attribute to determine the printable area of the medium.
- How you specify the dimensions depends on the printer model and how the medium is loaded. If you get unexpected output from a printer device, try reversing the order in which you specify the dimensions for a medium that the actual destination references.

## medium-form-parts

Indicates the number of form parts for this multi-part form medium.

### Type

Resettable, single-valued

### Allowed Values

You can enter an integer from 1 through 2147483647.

### Default Value

No default value

### Usage Guidelines

This attribute only applies to media whose **medium-type** is **multi-part-forms**.

## medium-holes-count

Indicates the number of holes (if any), pre-punched in the medium.

### Type

Resettable, single-valued

### Allowed Values

You can enter an integer from 0 through 2147483647.



**Default Value**

No default value

**medium-identifier**

Uniquely identifies a particular medium within a server.

**Type**

Non-settable, single-valued

**Allowed Values**

Infoprint sets this value to the *MediumName* portion of the argument when you create this medium. The value is either a text string up to **255** characters that you enter or one of these fixed values:

A0	B8	JPOSTD
A1	B9	hagaki
A2	B10	legal
A3	C4-envelope	letter
A3-colored	C5-envelope	letter-tab
A4	a	manual
A4-colored	b	monarch-envelope
A4-tab	c	na-legal-colored
A4-transparent	d	na-letter-colored
A5	designated-long-envelope	na-letter-transparent
A5-colored	e	na-number-9-envelope
A6	executive	na-number-10-envelope
A7	folio	na-6x9-envelope
A8	invoice	na-7x9-envelope
A9	jis-b0-white	na-9x11-envelope
A10	jis-b1-white	na-9x12-envelope
B0	jis-b2-white	na-10x13-envelope
B1	jis-b3-white	na-10x14-envelope
B2	jis-b4-colored	na-10x15-envelope
B3	jis-b4-white	quarto
B4	jis-b5-colored	statement
B4-colored	jis-b5-white	tabloid
B4-envelope	jis-b6-white	universal-paper
B5	jis-b7-white	universal-envelope
B5-colored	jis-b8-white	8x10.5
B5-envelope	jis-b9-white	
B6	jis-b10-white	
B7		

**Default Value**

No default value

**medium-sides**

Indicates the number of printable sides for the medium.

**Type**

Resettable, single-valued

**Allowed Values**You can enter an integer of **1** or **2**.**Default Value**

No default value

## Medium

### medium-size

Specifies the size of the medium by means of a predefined name for the size. Examples of values include **invoice**, which specifies a medium of 5.5 inches by 8.5 inches, and **ledger**, which specifies a size of 11 inches by 17 inches.

#### Type

Resettable, single-valued

#### Allowed Values

You can enter one of these fixed values:

iso-a0	iso-b9	jis-b5
iso-a1	iso-b10	jis-b6
iso-a2	iso-c3	jis-b7
iso-a3	iso-c4	jis-b8
iso-a4	iso-c5	jis-b9
iso-a5	iso-c6	jis-b10
iso-a6	a	ledger
iso-a7	b	legal
iso-a8	c	letter
iso-a9	d	monarch-envelope
iso-a10	iso-designated-long	na-number-9-envelope
iso-b0	e	na-number-10-envelope
iso-b1	executive	na-6x9-envelope
iso-b2	folio	na-7x9-envelope
iso-b3	invoice	na-9x11-envelope
iso-b4	jis-b0	na-9x12-envelope
iso-b5	jis-b1	na-10x13-envelope
iso-b6	jis-b3	na-10x14-envelope
iso-b7	jis-b4	na-10x15-envelope
iso-b8		quarto

#### Default Value

No default value

### medium-type

Identifies the medium type.

#### Type

Resettable, single-valued

#### Allowed Values

You can enter one of these fixed values:

<i>Fixed Value</i>	<i>Description</i>
<b>continuous-long</b>	Continuous-forms paper with the forms connecting along the long edge of the form.
<b>continuous-short</b>	Continuous-forms paper with the forms connecting along the short edge of the form.
<b>envelope</b>	Standard envelopes that may or may not have preprinted information and that do not have windows.
<b>labels</b>	Any type of label.
<b>multi-part-form</b>	Forms containing multiple layers that are not attached to one another.

<b>plain</b>	Separately cut sheets of paper
<b>stationery</b>	Separately cut sheets of paper
<b>tab-stock</b>	Paper that has tabs.
<b>transparency</b>	Separate sheets of a transparent material.

**Default Value**

No default value

**medium-weight**

Identifies the medium weight.

**Type**

Resettable, single-valued

**Allowed Values**

You can enter a positive real number.

**Default Value**

No default value

**message**

Provides a message associated with this medium object.

**Type**

Resettable, single-valued

**Allowed Values**

You can enter a text string up to 4095 characters long that contains information about this medium object.

**Default Value**

No default value

**object-class**

Identifies the object class to which this object belongs.

**Type**

Non-settable, single-valued

**Allowed Values**Infoprint sets this value to **medium**.**Default Value****medium**

### Attributes for Queues

A queue is an Infoprint object that manages a collection of jobs that are waiting to print. A queue receives jobs from one or more logical destinations and sends jobs to one or more actual destinations.

### Initially Settable Attribute Listing

There are no initially settable attributes for queues.

### Resettable Attribute Listing

You can set these attributes with the **pdcreate** command when you create the queue or modify them with the **pdset** command after you create the queue.

- assign-to-destination**
- backlog-lower-bound**
- backlog-update-interval**
- backlog-upper-bound**
- descriptor**
- list-of-managers**
- message**
- notification-profile**
- notify-operator**
- protected-attributes**
- requeue-failed-jobs**

### actual-destinations-assigned

Lists the actual destinations that receive jobs from this queue.

#### Type

Non-settable, multi-valued

#### Input Synonym

You can use the synonym **physical-printers-assigned**.

#### Allowed Values

Infoprint adds the actual destination name to this value when each actual destination registers and its **associated-queue** attribute value is the name of this queue.

#### Default Values

No default values

### actual-destinations-ready

Lists the ready actual destinations that can receive jobs from this queue.

#### Type

Non-settable, multi-valued

#### Input Synonym

You can use the synonym **physical-printers-ready**.

#### Allowed Values

Infoprint adds an actual destination name to this value for each actual destination that can receive a job from this queue. An actual destination becomes ready when it is enabled and the state is either **idle**, **connecting-to-destination**, or **printing**.

**Default Values**

No default values

**assign-to-destination**

Indicates whether the queue assigns jobs to actual destinations as soon as they are accepted or waits until an actual destination is available.

**Type**

Resettable, single-valued

**Input Synonym**You can use the synonym **assign-to-printer**.**Allowed Values**

You can enter one of these fixed values:

<i>Fixed Value</i>	<i>Input Synonym</i>
<b>true</b>	<b>yes</b>
<b>false</b>	<b>no</b>

**Default Value****Basic****true****Advanced****false****Usage Guidelines**

- When the value of **assign-to-destination** is **true**, the queue assigns jobs to an actual destination as soon as the server accepts them (early binding), unless no actual destination supports a job's required attribute values. If something prevents the assigned actual destination from printing the job, or if another actual destination becomes available first, you must reassign the job using the Infoprint administrator's GUI.

Early binding is the defining characteristic of a basic Infoprint installation.

- When the value of **assign-to-destination** is **false**, the queue waits until a job is next to be scheduled to print, then assigns it to the first suitable actual destination to become available (late binding).
- Late binding is the defining characteristic of an advanced Infoprint installation.
- A job must be assigned to an actual destination before Infoprint can calculate the estimated completion time for the job.
- The server accepts the job even when the **actual-destinations-requested** specifies a non-existent actual destination **only when accept-unsupported-jobs** is **true** and the print queue has **assign-to-printer** as **false**,

**associated-server**

Indicates the name of the server in which this queue resides.

**Type**

Non-settable, single-valued

**Allowed Values**

Infoprint sets this value to the *ServerName* portion of the argument you specify when you create this queue with the **pdcreate** command.

**Default Value**

No default value

## Queue

### backlog

See **queue-backlog**.

### backlog-lower-bound

Identifies the limit (time to print jobs within the queue) below which you do not consider the queue backlogged. Infoprint resets a backlogged condition when the **queue-backlog** value is less than this value, if you enable backlog computing.

#### Type

Resettable, single-valued

#### Allowed Values

You can enter a value using *[HH:]MM*. The unit is minutes or hours and minutes, separated by a colon.

#### Syntax

```
backlog-lower-bound=[HH:]MM
```

For example:

```
backlog-lower-bound=70  
backlog-lower-bound=1:10
```

#### Default Value

No default value

#### Usage Guidelines

- You must set the value for this attribute to less than or equal to the value you specify for the **backlog-upper-bound** attribute.
- Infoprint sets the value for the attribute **backlogged** to **false** when the value for the **queue-backlog** attribute becomes less than this value if you enable backlog computing (**backlog-update-interval** value not equal to 0).

### backlog-update-interval

Specifies how often Infoprint computes the queue backlog.

#### Type

Resettable, single-valued

#### Allowed Values

You can enter a value using *[HH:]MM*. The unit is minutes or hours and minutes, separated by a colon.

Setting this value to 0 disables backlog computing.

#### Default Value

The greater value of the following:

1 minute

The value of the **backlog-upper-bound** attribute divided by 30.

#### Usage Guidelines

- You must set the value for this attribute to be less than or equal to the value you specify for the **backlog-upper-bound** attribute.
- Infoprint sets this default value when you create the queue. If you change the value for the **backlog-upper-bound** attribute later with the **pdset** command, Infoprint does not change the value for this attribute.

## backlog-upper-bound

Identifies the limit (time to print the jobs in the queue) above which you consider the queue backlogged.

### Type

Resettable, single-valued

### Allowed Values

You can enter a value using *[HH:]MM*. The unit is minutes or hours and minutes, separated by a colon.

### Default Value

No default value

### Usage Guidelines

- You must set the value for this attribute to be greater than or equal to the value you specify for the **backlog-lower-bound** attribute.
- Infoprint sets the value for the attribute **backlogged** to **true** when the value for the **queue-backlog** attribute exceeds this value if you enable backlog computing.

## backlogged

Identifies whether the queue is backlogged.

### Type

Non-settable, single-valued

### Allowed Values

Infoprint sets this value to one of these fixed values:

**true**  
**false**

### Default Value

**false**

### Usage Guidelines

- Infoprint sets this attribute value to **true** when you enable backlog computing (**backlog-update-interval** not equal to 0) and the **queue-backlog** value exceeds the **backlog-upper-bound** value.
- Infoprint sets this attribute value to **false** when the **queue-backlog** value falls below the **backlog-lower-bound** value.

## current-backlog

See **queue-backlog**.

## descriptor

Provides a description of this queue.

### Type

Resettable, single-valued

### Allowed Values

You can enter a text string of up to 4095 characters that describes this queue. You may want to specify such things as:

- The name of the department or the account number for the users of this queue.
- Any other information that is unique to your company or organization.

## Queue

### Default Value

No default value

### Usage Guidelines

The use of this attribute is optional. However, a detailed description of this queue is helpful to users who want to determine where to submit a given job or administrators who want to determine which queue to associate with a logical destination.

## list-of-managers

Lists the people responsible for the configuration and operation of this queue.

### Type

Resettable, multi-valued

### Input Synonym

You can use this synonym **managers**.

### Allowed Values

You can enter a text string up to 255 characters long, per value, that contains the name or ID of the person responsible for this queue.

### Default Values

No default values

### Usage Guidelines

This attribute is useful if a user needs to contact someone to report a problem or to request a change.

## logical-destinations-assigned

Lists the logical destinations associated with this queue.

### Type

Non-settable, multi-valued

### Input Synonym

You can use the synonym **logical-printers-assigned**.

### Allowed Values

Infoprint adds to this value the logical destination name of a newly created logical destination if the **associated-queue** attribute value for that logical destination identifies this queue.

### Default Values

No default values

## logical-destinations-ready

Lists the enabled logical destinations that can send jobs to this queue.

### Type

Non-settable, multi-valued

### Input Synonym

You can use the synonym **logical-printers-ready**.

### Allowed Values

Infoprint adds a logical destination name to this value for each logical destination that is assigned to the queue and that is enabled.



**Default Values**

No default values

**Usage Guidelines**

Infoprint changes this value as you enable or disable logical destinations.

**logical-printers-assigned**

See **logical-destinations-assigned**.

**logical-printers-ready**

See **logical-destinations-ready**.

**managers**

See **list-of-managers**.

**message**

Provides a message associated with this queue.

**Type**

Resettable, single-valued

**Allowed Values**

You can enter a text string of up to 4095 characters that contains information about this queue.

**Default Value**

No default value

**notification-profile**

Designates which persons Infoprint notifies of specific events related to this queue, and how Infoprint notifies them.

**Type**

Resettable, multi-valued, complex

**Syntax**

```
-x "notification-profile={event-identifiers=event ...
  delivery-address=name@node delivery-method=value
  event-comment='some text' locale=locale}"
```

For example:

```
-x "notification-profile={event-identifiers=queue-state-changed
  object-cleaned delivery-address=Kathy@test delivery-method=message
  event-comment='Better check' locale=En_US.IBM-850}"
```

You can omit any of these components.

**Components**

**event-identifiers:** Specifies the events for which the person receives messages.

*Type:* Multi-valued

*Allowed Values:* You can enter queue events listed for the server **events-supported** attribute.

## Queue

*Default Values:* **object-cleaned, object-deleted, queue-backlogged**

**delivery-address:** Specifies the address of the person who receives the event messages or the directory location and file name where Infoprint stores the message.

*Type:* Single-valued

*Allowed Values:* You can enter the login ID and node of the person who is to receive the messages or the path of the directory and a file name.

*Default Value:* The login ID of the person who created this queue.

**delivery-method:** Specifies how the user receives the event messages.

*Type:* Single-valued

*Allowed Values:* You can enter one of these fixed values:

<b>Fixed Value</b>	<b>Input Synonym</b>
<b>electronic-mail</b>	<b>e-mail, email</b>
<b>file</b>	
<b>file-add-to</b>	
<b>message</b>	
<b>none</b>	

*Default Value:* **message**

*Usage Guidelines:* If you specify a value of **file** or **file-add-to** for this component, you must specify a value for the **delivery-address** component.

**event-comment:** Provides textual information that Infoprint appends to the event message.

*Type:* Single-valued

*Allowed Values:* You can enter a text string of up to 4095 characters that contains the information about the event.

*Default Value:* No default value

**locale:** Defines the language and code page of notification messages.

*Type:* Single-valued

*Allowed Values:* You can enter any locale for which the Infoprint messages in the corresponding language are installed.

*Default Value:* The locale of the person who created this queue.

## notify-operator

Identifies people who are to receive the message defined by the job attribute **job-message-to-operator**.

### Type

Resettable, multi-valued, complex

**Input Synonym**

You can use the synonym **operators**.

**Syntax**

*delivery-method:delivery-address*

Separate the components with a colon, for example:

message:op3@fastpr

**Components**

***delivery-method***: Specifies how the person is to receive the messages.

*Type*: Single-valued

*Allowed Values*: You can enter one of these fixed values:

**electronic-mail**  
**message**  
**none**

*Default Value*: **message**

***delivery-address***: Specifies the address of the person who receives the message.

*Type*: Single-valued

*Allowed Values*: You can enter a text string that contains the login ID and node of the person who receives the message.

*Default Value*: The login ID of the person who created this queue.

**object-class**

Identifies the object class to which this object belongs.

**Type**

Non-settable, single-valued

**Allowed Values**

Infoprint sets this value to **queue**.

**Default Value**

**queue**

**operators**

See **notify-operator**.

**physical-printers-assigned**

See **actual-destinations-assigned**.

**physical-printers-ready**

See **actual-destinations-ready**.

## Queue

### protected-attributes

Specifies one or more queue attributes that DCE prevents Infoprint operators from setting or changing.

#### Type

Resettable, multi-valued

#### Allowed Values

You can enter one or more queue attribute names.

#### Default Values

This attribute always specifies itself, **protected-attributes**, as a value.

#### Usage Guidelines

Normally, anyone with DCE **write** permission for queues can set values for queue attributes. By default, the **pd\_admin** and **pd\_operator** DCE groups both have **write** permission. Once you define a queue attribute as a protected attribute, you must have DCE **delete** permission to modify the attribute. Members of the **pd\_operator** DCE group do not have **delete** permission unless the DCE administrator has modified the default permissions for that group.

### queue-backlog

Specifies the amount of time that this queue might be backlogged. This is a computed estimate of time it takes to print all of the jobs currently in the queue.

#### Type

Non-settable, single-valued

#### Input Synonyms

You can use the synonyms **backlog** or **current-backlog**.

#### Allowed Values

Infoprint sets this value to *[HH:]MM*. The unit is minutes or hours and minutes, separated by a colon.

#### Default Value

No default value

### queue-name

Uniquely identifies this queue object.

#### Type

Non-settable, single-valued

#### Allowed Values

Infoprint set this value to the *QueueName* portion of the argument from the **pdcreate** command when this queue is created.

#### Default Value

No default value

#### Usage Guidelines

This queue name must be unique within the namespace.

### queue-state

Identifies the current state of the queue.

**Type**

Non-settable, single-valued

**Allowed Values**

Infoprint sets this value to one of these fixed values:

<i>Fixed Value</i>	<i>Explanation</i>
<b>paused</b>	Infoprint will not schedule jobs in the queue to the actual destinations associated with this queue. The queue will still receive jobs from its associated logical destinations if they are enabled.
<b>ready</b>	Infoprint can schedule jobs in the queue to the actual destinations associated with this queue.

**Default Value**

No default value

**requeue-failed-jobs**

Indicates whether jobs that fail to RIP, impose, or print should be replaced in the queue.

**Type**

Resettable, single-valued

**Allowed Values**

You can enter one of these fixed values:

<i>Fixed Value</i>	<i>Input Synonym</i>
<b>true</b>	<b>yes</b>
<b>false</b>	<b>no</b>

**Default Value**

<b>Basic</b>	<b>true</b>
<b>Advanced</b>	<b>false</b>

**Usage Guidelines**

- When the value of **requeue-failed-jobs** is **true**, jobs that fail to print for any of these reasons:
  - The server cancels the job.
  - Infoprint fails to RIP the job.
  - Infoprint fails to impose the job.
 are replaced in the queue in the **held** state.
- When the value of **requeue-failed-jobs** is **false**, jobs that fail to print for these reasons are retained if there is a value for the **job-retain-until** or **job-retention-period** job attribute. Otherwise, these jobs are discarded.
- For any value of **requeue-failed-jobs**, jobs that fail to print because of actual destination problems are replaced in the queue in the **pending** state. If another actual destination is available, these jobs are rescheduled.

### Attributes for Resource Contexts

Infoprint uses resource contexts to determine the location of PSF resources. Actual destination attributes, such as **resource-context**, **resource-context-font**, or **resource-context-overlay**, reference the names of resource contexts.

The different types of AFP resources are:

**Fonts** A font is a single size and typeface in a particular type family including letters, numerals, punctuation marks, special characters, and ligatures.

**Form definitions**

Form definitions provide instructions on how output devices position data on the page. Form definitions can specify overlays, a paper source for cut-sheet printer devices, duplexing, text suppression, data position, and the number and modifications of pages.

**Overlays**

Overlays are collections of predefined data such as lines, shading, text boxes, or logos, that an output device can merge with variable data on a page or a form.

**Page definitions**

Page definitions contain the formatting controls for line data. Page definitions can include controls for the number of lines per logical page, font selection, print direction, and the mapping of individual fields to positions on the logical page.

**Page segments**

Page segments contain text and images that an output device can include at any addressable point on a page or an electronic overlay.

The resource context attribute **context-address** identifies the path name of the directory that contains the corresponding PSF resource. Instead of entering the full path name as the value of an actual destination attribute, you can reference the resource context. You can also reference resource contexts during print submission using certain document attributes.

Only PSF, fax, and email actual destinations use resource contexts.

### Initially Settable Attribute Listing

There are no initially settable attributes for a resource context.

### Resettable Attribute Listing

You can set these attributes with the **pdcreate** command when you create a resource context or modify them with the **pdset** command after you create the resource context.

**context-address**  
**descriptor**

### associated-server

Indicates the server in which this resource context resides.

**Type**

Non-settable, single-valued

**Allowed Values**

Infoprint sets this value to the *ServerName* portion of the argument specified with the **pdcreate** command when this resource context is created.

**Default Value**

No default value

**context-address**

Defines the path for the location of this PSF resource.

**Type**

Resettable, single-valued

**Allowed Values**

You enter a text string up to 4095 characters long that contains the path name. Separate multiple path names with colons.

**Syntax**

*path:path*

For example:

*/fonts:/dept123/fonts*

**Default Value**

No default value

**descriptor**

Provides a description of this resource context.

**Type**

Resettable, single-valued

**Allowed Values**

You can enter a text string up to 4095 characters long that describes this resource context.

**Default Value**

No default value

**Usage Guidelines**

The use of this attribute is optional. However, a detailed description of the resource that this resource context references can be helpful to a users who need to determine which resource context to use.

**object-class**

Identifies the object class to which this object belongs.

**Type**

Non-settable, single-valued

**Allowed Values**

Infoprint sets this value to **resource-context**.

**Default Value**

**resource-context**

## Resource Context

### resource-context-identifier

Uniquely identifies this resource context within a server.

#### Type

Non-settable, single-valued

#### Allowed Values

Infoprint sets this value to the *ResourceContextName* portion of the argument specified with the **pdcreate** command when this resource context is created.

#### Default Value

No default value



## Attributes for Servers

An Infoprint server is an object that represents the server that manages the validation, routing, and scheduling of jobs.

### Initially Settable Attribute Listing

There are no specifiable attributes for a server.

### Resettable Attribute Listing

You can modify these attributes with the **pdset** command after you create a server.

**accept-unsupported-jobs**  
**auto-create-shared-printers**  
**descriptor**  
**job-submission-timer**  
**list-of-managers**  
**log-accounting-data**  
**maximum-barco-rips**  
**maximum-non-raster-rips**  
**maximum-raster-rips**  
**message**  
**notification-profile**  
**npm-server-ip-address**  
**npm-server-port-number**  
**protected-attributes**  
**save-rip-files**  
**security-level**  
**smtp-server-host**  
**smtp-server-port-number**  
**snmp-discovery-during-startup**  
**snmp-normal-poll-interval**  
**snmp-problem-poll-interval**

### accept-unsupported-jobs

Indicates whether the server accepts jobs even when no actual destination supports the required attribute values.

#### GUI Label

Accept unsupported jobs

#### Type

Resettable, single-valued

#### Allowed Values

You can enter one of these fixed values:

<i>Fixed Value</i>	<i>Input Synonym</i>
<b>true</b>	<b>yes</b>
<b>false</b>	<b>no</b>

#### Default Value

<b>Basic</b>	<b>true</b>
<b>Advanced</b>	<b>false</b>

### Usage Guidelines

- When the value of the **accept-unsupported-jobs** is **true**, the server accepts jobs even when no actual destination supports the required attribute values. Infoprint holds these jobs and sets the **required-resources-not-supported** job attribute to a list of the unsupported values.

The server accepts the job even when the **actual-destinations-requested** specifies a non-existent actual destination **only when** **accept-unsupported-jobs** is **true** and the print queue has **assign-to-printer** as **false**.

- When the value of **accept-unsupported-jobs** is **true**, the actual destination **accept-job** attribute is ignored.
- When the value of **accept-unsupported-jobs** is **false**:
  - The server rejects jobs that require unsupported attribute values.
  - The **accept-job** actual destination attribute is honored if the **assign-to-printer** queue attribute is **true**.
- If changes to job or actual destination attributes after the job has been accepted produce unsupported attribute values, Infoprint holds the job and sets the **required-resources-not-supported** job attribute to the list of unsupported values.

### actual-destinations-ready

Identifies the supported actual destinations that are ready to receive jobs from queues in this server.

#### Type

Non-settable, multi-valued

#### Input Synonym

You can use the synonym **physical-printers-ready**.

#### Allowed Values

Infoprint sets this value to the names of the actual destinations that are ready to accept jobs. A actual destination name is:

- Added when actual destinations associated with queues in this server are enabled and are in the **idle**, **connecting-to-printer**, or **printing** state.
- Removed when you disable or pause an actual destination and one of these destination states (**timed-out**, **needs-attention**, or **needs-key-operator**) exists.

#### Default Values

No default values

### actual-destinations-supported

Identifies the actual destinations that this server supports.

#### Type

Non-settable, multi-valued

#### Input Synonym

You can use the synonym **physical-printers-supported**.

#### Allowed Values

Infoprint sets this value to the names of the actual destinations associated with the queues contained in this server. Infoprint adds the destination name when an actual destination associated with queues in this server registers with this server.

**Default Values**

No default values

**auto-create-shared-printers (Windows NT and Windows 2000 Only)**

Indicates whether or not destinations created in this server that can be print submission targets should automatically create a corresponding Infoprint gateway shared printer.

**GUI Label**

Automatically create gateway printer

**Type**

Resettable, single-valued

**Allowed Values**

You can enter one of these fixed values:

<i>Fixed Value</i>	<i>Input Synonym</i>
<b>true</b>	<b>yes</b>
<b>false</b>	<b>no</b>

**Default Value****False****Usage Guidelines**

- When the value of the **auto-create-shared-printers** is **true**, Infoprint automatically creates a corresponding Infoprint gateway printer with:
  - A windows print driver with the first value in the server's **windows-nt-driver-names** attribute
  - A polling interval of 0

**Note:** The server accepts the job even when the **actual-destinations-requested** specifies a non-existent actual destination **only when** **accept-unsupported-jobs** is **true** and the print queue has **assign-to-printer** as **false**.

**cancel-individual-document-supported**

Indicates whether the server is capable of cancelling individual documents within a multi-document job.

**Type**

Non-settable, single-valued

**Allowed Values**Infoprint sets this value to **false**.**Default Value****false****descriptor**

Provides a description of this server.

**Type**

Resettable, single-valued

## Server

### Allowed Values

You can enter a text string up to 4095 characters long that contains a description of this server. You may want to specify things such as:

- The purpose of the server; which users, user groups, or departments will use the objects contained in this server.
- Any other information that is unique to your company or organization.

### Default Value

No default value

### Usage Guidelines

The use of this attribute is optional. However, a detailed description is useful if you have a large number of servers or if you have many people managing your network printing system.

## destination-states-supported

Identifies the destination states that this server supports.

### Type

Non-settable, multi-valued

### Input Synonym

You can use the synonym **printer-states-supported**.

### Allowed Values

Infoprint sets this value to any of these fixed values:

**connecting-to-printer**  
**idle**  
**needs-attention**  
**needs-key-operator**  
**paused**  
**printing**  
**shutdown**  
**timed-out**

### Default Values

No default values

## destination-support-systems-supported

Identifies the DSSs that this server supports.

### Type

Non-settable, multi-valued

### Allowed Values

For AIX:

**bsd**  
**email**  
**fax**  
**ip2000**  
**aix**  
**psf**  
**3170**

For Windows NT or Window 2000:

**bsd**

psf  
passthrough  
ipp

### Default Values

No default values

## document-attributes-supported

Identifies the document attributes that the server supports.

### Type

Non-settable, multi-valued

### Allowed Values

Infoprint sets these values to include all the document attributes supported by any actual destination registered with the server. These values are dynamic; Infoprint adds and removes values based on the values of registered actual destinations.

### Default Values

No default values

## events-supported

Lists the events that the server or the objects in the server support.

### Type

Non-settable, multi-valued

### Allowed Values

Infoprint sets these values to the following events:

- checkpoint-taken
- class-aborted
- class-actual-destination-attention
- class-actual-destination-configuration
- class-actual-destination-default
- class-actual-destination-status
- class-error
- class-job-attention
- class-job-default
- class-job-problem
- class-job-status
- class-logical-destination-attention
- class-logical-destination-configuration
- class-logical-destination-default
- class-logical-destination-status
- class-queue-attention
- class-queue-configuration
- class-queue-default
- class-queue-status
- class-report
- class-server-attention
- class-server-configuration
- class-server-default
- class-server-status
- class-state-changed
- class-warning
- close-to-discard-time

## Server

destination-disabled  
destination-enabled  
destination-function-unavailable  
destination-needs-administrator  
destination-needs-attention  
destination-needs-operator  
destination-registered  
destination-shutdown-job-requeued  
destination-state-changed  
destination-timed-out  
destination-unregistered  
destinations-not-ready-for-job  
detailed-messages  
document-aborted-by-destination  
document-aborted-by-server  
document-cancelled-at-destination  
document-content  
file-transferred  
internal-server-error  
job-aborted-by-server  
job-assigned-to-destination  
job-assigned-to-destination-at-end  
job-assigned-to-queue  
job-cancelled-by-operator  
job-cancelled-by-user  
job-cannot-be-scheduled  
job-discarded  
job-modified  
job-paused  
job-promoted  
job-reordered  
job-requeued  
job-resubmitted  
job-resumed  
job-retained  
job-state-changed  
job-submission-not-complete  
job-unassigned  
no-document  
no-resource  
object-cleaned  
object-created  
object-deleted  
object-modified  
object-paused  
object-resumed  
other-error  
other-warning  
past-discard-time  
processing-started  
queue-backlogged  
queue-no-longer-backlogged  
queue-state-changed  
resource-needs-attention  
resource-needs-operator  
server-shutdown-complete

**server-shutdown-started**  
**server-startup-complete**  
**server-state-changed**  
**unable-to-register**  
**unrecognized-resource**

### Default Values

See “Allowed Values”.

## hostname

See **server-hostname**.

## i-p-address

See **server-ip-address**.

## ip-address

See **server-ip-address**.

## job-attributes-supported

Identifies the job attributes that this server supports.

### Type

Non-settable, multi-valued

### Allowed Values

Infoprint sets these values to include all the job attributes supported by any actual destination registered with the server. These values are dynamic; Infoprint adds and removes values based on the values of registered actual destinations.

### Default Values

No default values

## job-state-reasons-supported

### Type

Non-settable, multi-valued

### Allowed Values

Infoprint sets the value of this attribute to these fixed values:

**aborted-by-system**  
**cancelled-by-operator**  
**cancelled-by-user**  
**completed**  
**completed-successfully**  
**completed-with-errors**  
**deadline-in-jeopardy**  
**imposition-failed**  
**job-hold-set**  
**job-print-after-specified**  
**required-resource-not-ready**  
**required-resource-not-supported**  
**rip-and-hold-complete**  
**rip-failed**

## Server

### Default Values

See “Allowed Values”.

## job-states-supported

Identifies the job states that this server supports.

### Type

Non-settable, multi-valued

### Allowed Values

Infoprint sets the value of this attribute to these fixed values:

- cancelled
- held
- imposing
- paused
- pending
- pre-processing
- printing
- processing
- retained
- ripping
- terminating
- unknown

### Default Values

See “Allowed Values”.

## job-submission-timer

Specifies the maximum time that the server will try to assemble a job before it will time out if it has not assembled all the documents.

### GUI Label

Job submission timeout

### Type

Resettable, single-valued

### Allowed Values

You can enter a value using *[HH:]MM*. The unit is minutes or hours and minutes, separated by a colon.

### Default Value

30

### Usage Guidelines

If the server has not completed the assembly of a job within the specified time, it identifies the job submission as complete and sends the job to the queue.

## list-of-managers

Lists the people that are responsible for the configuration and operation of this server.

### Type

Resettable, multi-valued

### Input Synonym

You can use the synonym **managers**.



**Allowed Values**

You can enter a text string up to 255 characters long, per value, that contains the name or user ID of the person responsible for this server. You may also want to include the telephone number and office location of the person.

**Default Values**

No default values

**Usage Guidelines**

This attribute is useful if a user needs to contact someone to report a problem or to request a change.

**locale**

Identifies the locale for this server.

**GUI Label**

Locale

**Type**

Non-settable, single-valued

**Allowed Values**

Infoprint sets this value based on the environment variables for this server at startup time. The priority sequence to obtain the language for the locale from the environment variables is:

1. **LC\_ALL**
2. **LC\_MESSAGES**
3. **LANG**

**Default Value**

No default value

**log-accounting-data**

Defines whether the accounting logs for all associated actual destinations are activated or deactivated by default. The actual destination attribute **log-accounting-data** setting overrides the setting of this value for that actual destination.

**GUI Label**

Log accounting data

**Type**

Resettable, single-valued

**Allowed Values**

You can enter one of these values:

<i>Fixed Value</i>	<i>Input Synonym</i>
<b>true</b>	<b>yes</b>
<b>false</b>	<b>no</b>

**Default Value**

**false**

**Usage Guidelines**

If the value for any actual destination associated with this server is set to the default attribute value (no value), the value set for this server attribute sets the condition for that actual destination.

## Server

The accounting log for each actual destination contains the following job attributes and values for each job submitted to that actual destination separated by commas:

**actual destination name** (up to 255 characters)  
**job owner** (up to 255 characters)  
**global job-id** without *ServerName*  
**submission-time** (GMT format)  
**submission-time** (date in server's displayable locale and time zone)  
**submission-time** (time in server's displayable locale and time zone)  
**completion-time** (GMT format)  
**completion-time** (date in server's displayable locale and time zone)  
**completion-time** (time in server's displayable locale and time zone)  
**pages-completed**  
**octets-completed**  
**data stream** (first document only)  
**job name** (up to 255 characters)

### logical-destinations-ready

Identifies which logical destinations within this server are ready to accept jobs.

#### Type

Non-settable, multi-valued

#### Input Synonym

You can use the synonym **logical-printers-ready**.

#### Allowed Values

Infoprint sets and resets this value as administrators enable or disable logical destinations within this server.

#### Default Values

No default values

### logical-destinations-supported

Identifies the logical destinations that this server supports.

#### Type

Non-settable, multi-valued

#### Input Synonym

You can use the synonym **logical-printers-supported**.

#### Allowed Values

Infoprint sets and resets this value as administrators create or delete logical destinations within this server.

#### Default Values

No default values

### logical-printers-ready

See **logical-destinations-ready**.

### logical-printers-supported

See **logical-destinations-supported**.

## managers

See **list-of-managers**.

## maximum-barco-rips

Indicates the maximum number of PostScript jobs that Infoprint can RIP at one time for printing on a 3170 actual destination.

### Type

Resettable, single-valued

### Allowed Values

You can enter an integer from 0 through 2147483647.

### Default Value

4

### Usage Guidelines

- For good performance, this value should be the same as the number of AIX systems specified as values of the **rip-server** actual destination attribute.
- Infoprint reads this value the first time that a job is RIPPed after the server is started. Therefore, whenever you change this value, you must restart the server.

## maximum-non-raster-rips

Indicates the maximum number of jobs other than TIFF, GIF, or JPEG jobs that Infoprint can RIP at one time for printing on a PSF actual destination.

### GUI Label

Maximum nonraster RIPs

### Type

Resettable, single-valued

### Allowed Values

You can enter an integer from 0 through 2147483647.

### Default Value

No default value

### Usage Guidelines

- You can limit the number of concurrent RIPs to improve performance.
- Infoprint reads this value the first time that a job is RIPPed after the server is started. Therefore, whenever you change this value, you must restart the server.

## maximum-raster-rips

Indicates the maximum number of TIFF, GIF, and JPEG jobs that Infoprint can RIP at one time for printing on a PSF actual destination.

### GUI Label

Maximum raster RIPs

### Type

Resettable, single-valued

### Allowed Values

You can enter an integer from 0 through 2147483647.

## Server

### Default Value

No default value

### Usage Guidelines

- You can limit the number of concurrent RIPs to improve performance.
- Infoprint reads this value the first time that a job is RIPped after the server is started. Therefore, whenever you change this value, you must restart the server.

## message

Provides information associated with this server.

### Type

Resettable, single-valued

### Allowed Values

You can enter a text string up to 4095 characters long that contains information about this server.

### Default Value

No default value

## modify-individual-document-supported

Indicates whether this server is capable of modifying individual documents within a multiple document job.

### Type

Non-settable, single-valued

### Allowed Values

Infoprint sets this value to **true**.

### Default Value

**true**

## multiple-documents-supported

Indicates whether this server supports multiple documents in a single job.

### Type

Non-settable, single-valued

### Allowed Values

Infoprint sets this value to **true**.

### Default Value

**true**

## notification-delivery-methods-supported

Identifies the methods this server supports for sending messages to the person specified to receive the messages.

### Type

Non-settable, multi-valued

### Allowed Values

Infoprint sets this value to any of these fixed values:

**electronic-mail**

**message**  
**file**  
**file-add-to**  
**sapcb**  
**none**

### Default Values

No default values

### Usage Guidelines

The **sapcb** notification method causes the SAP callback daemon to return messages about job events to the SAP database. It is used only for jobs submitted by SAP users.

## notification-profile

Designates which users Infoprint notifies of specific events related to this server, and how Infoprint notifies them.

### GUI Label

Notification profile

### Type

Resettable, multi-valued, complex

### Syntax

```
-x "notification-profile={event-identifiers=event ...
  delivery-address=name@node delivery-method=value
  event-comment='some text' locale=locale}"
```

For example:

```
-x "notification-profile={events-identifiers=class-server-status
  delivery-address=Tom@master delivery-method=message
  event-comment='Too much data' locale=En_US.IBM-850}"
```

You can omit any of these values.

### Components

**event-identifiers:** Specifies the events for which the person receives messages.

*Type:* Multi-valued

*Allowed Values:* You can enter any of the values listed for the **events-supported** attribute.

*Default Values:* **internal-server-error, object-cleaned, object-deleted, server-shutdown-complete, sapcbd-down**

**delivery-address:** Specifies the address of the person who receives event messages concerning this server or the directory location and file name where Infoprint stores messages.

*Type:* Single-valued

*Allowed Values:* You can enter a text string that contains the login ID and node or the path to the directory and file name.

## Server

*Default Value:* The login ID of the user who created this server.

***delivery-method:*** Specifies how the user receives the event messages.

*Type:* Single-valued

*Allowed Values:* You can enter one of these fixed values:

<b><i>Fixed Value</i></b>	<b><i>Input Synonym</i></b>
<b>electronic-mail</b>	<b>e-mail, email</b>
<b>message</b>	
<b>file</b>	
<b>file-add-to</b>	
<b>none</b>	

*Default Value:* **message**

*Usage Guidelines:* If you specify a value of **file** or **file-add-to** for this component, you must specify a value for the **delivery-address** component.

***event-comment:*** Provides information that Infoprint appends to the event message.

*Type:* Single-valued

*Allowed Values:* You can enter a text string up to 4095 characters long that contains the comment.

*Default Value:* No default value

***locale:*** Defines the language and code page of notification messages.

*Type:* Single-valued

*Allowed Values:* You can enter any locale for which the Infoprint messages in the corresponding language are installed.

*Default Value:* The locale of the person who created this server.

## npm-server-ip-address

Identifies the Internet Protocol address (IP Address parameter) of the system where the Network Print Manager (NPM) server is running.

### **GUI Label**

NPM server IP address

### **Type**

Resettable, single-valued

### **Allowed Values**

You can enter a text string up to 4095 characters long that is either of these types of address:

#### **Dotted decimal address**

A series of integers within the range of 0 to 255, each separated by a period, . (decimal address). For example:

9.99.12.85

#### **Hostname**

For example:

teo.boulder.IBM.com

### Default Value

127.0.0.1

### Usage Guidelines

You must enter a value in order to display the Simple Network Management Protocol (SNMP) Printer Status dialog from the Infoprint Manager Operations GUI.

## npm-server-port-number

Identifies the Port Number parameter on the system where the NPM server is running.

### GUI Label

NPM server port

### Type

Resettable, single-valued

### Allowed Values

You can enter an integer from 1 through 2147483647, but you typically enter an integer from 5001 to 65535.

### Default Value

6795

### Usage Guidelines

You must enter a value in order to display the SNMP Printer Status dialog from the Infoprint Manager Operations GUI.

## object-class

Identifies the object class to which this object belongs.

### Type

Non-settable, single-valued

### Allowed Values

Infoprint sets this value to **server**.

### Default Value

**server**

## object-classes-supported

Lists the object classes that this server supports.

### Type

Non-settable, multi-valued

### Allowed Values

Infoprint sets this value to these fixed values:

- auxiliary-sheet**
- destination**
- document**
- initial-value-document**
- initial-value-job**
- job**
- log**
- medium**

## Server

**queue**  
**resource-context**  
**server**  
**transform** for Windows NT or Window 2000 only

**Default Values**  
See “Allowed Values”.

## physical-printers-ready

See **actual-destinations-ready**.

## physical-printers-supported

See **actual-destinations-supported**.

## printer-states-supported

See **destination-states-supported**.

## problem-child

Indicates whether one of the objects that this server manages has a problem.

**Type**  
Non-settable, single-valued

**Allowed Values**  
Infoprint sets this value to one of these fixed values:  
**true**  
**false**

**Default Value**  
No default value

**Usage Guidelines**  
The Infoprint administrator’s GUI uses this attribute value to determine the problem status of this server.

## protected-attributes

Specifies one or more server attributes that DCE prevents Infoprint operators from setting or changing.

**GUI Label**  
Protected attributes

**Type**  
Resettable, multi-valued

**Allowed Values**  
You can enter one or more server attribute names.

**Default Values**  
This attribute always specifies itself, **protected-attributes**, as a value.

**Usage Guidelines**  
Normally, anyone with DCE **write** permission for server can set values for server attributes. By default, the **pd\_admin** and **pd\_operator** DCE groups both have **write** permission. Once you define a server attribute as a protected attribute, you must have DCE **delete** permission to modify the attribute. Members of the **pd\_operator**



DCE group do not have **delete** permission unless the DCE administrator has modified the default permissions for that group.

## queues-supported

Identifies the queues contained in this server.

### Type

Non-settable, multi-valued

### Allowed Values

Infoprint sets and resets this value when you create or delete queues.

### Default Values

No default values

## save-rip-files

Indicates whether this server saves the output files from jobs converted to raster image patterns.

### GUI Label

Save ripped files

### Type

Resettable, single-valued

### Allowed Values

You can enter one of these fixed values:

<i>Fixed Value</i>	<i>Input Synonym</i>
<b>true</b>	<b>yes</b>
<b>false</b>	<b>no</b>

### Default Value

<b>Basic</b>	<b>true</b>
<b>Advanced</b>	<b>false</b>

### Usage Guidelines

- If you move a RIPped job from a server with **save-rip-files=true** to one with **save-rip-files=false**, the new server keeps the RIP files only until the job is printed, then discards them.
- RIPped files are saved in the directory specified by the **PDBASE** environment variable or in one of its subdirectories. No single user can create a file larger than the amount of free space in the file system containing this directory. If many users are submitting RIPped jobs, the directory may fill up and prevent all users from successfully RIPping files.

## security-level

Identifies the security level for this server.

### GUI Label

Security level

### Type

Resettable, single-valued

### Allowed Values

You can enter the following value for DCE:

## Server

**medium** DCE controls access to objects. Clients can execute all commands if the client and server are in the same namespace. If they are not in the same namespace, the client can execute only the **pdls**, **pdpr**, **pdq**, **pdmod**, and **pdrm** commands.

You can enter one of these fixed values for non-DCE:

**none** No security checking is performed.

**low** Uses standard non-DCE access control list and group security checking.

### Default Value

With non-DCE

**low**

With DCE

**medium**

## server-hostname

Identifies the host processor on which this server is running.

### Type

Non-settable, single-valued

### Input Synonym

You can use the synonym **hostname**.

### Syntax

*node.node.node*

For example:

*boxer.denver.gym.*

### Allowed Values

Infoprint sets this value to the host name of the processor where this server was created.

### Default Value

The host name of the processor where this server was created.

## server-ip-address

Identifies the Internet Address of the host processor on which this server is running.

### Type

Non-settable, single-valued

### Input Synonyms

You can use the synonym **ip-address** or **i-p-address**.

### Allowed Values

Infoprint sets this value to the IP address of the host on which this server was created. The value is in the format of integers in series within the range of 0 to 255. A period, . , separates each integer from the others in the format

*nn.nn.nn.nn*

For example:

*9.99.9.143*

**Default Value**

The IP address of the host on which this server was created.

**server-name**

Uniquely identifies this server.

**Type**

Non-settable, single-valued

**Allowed Values**

Infoprint sets this value to the name you enter when you create this server.

**Default Value**

No default value

**server-state**

Identifies the current state of this server.

**Type**

Non-settable, single-valued

**Allowed Values**

Infoprint sets this value to one of these fixed values:

**initializing**

**ready**

**terminating**

**unavailable**

**Default Value**

No default value

**smtp-server-host (Windows NT and Windows 2000 Only)**

Identifies the Domain Name System (DNS) hostname or Internet Protocol address of the system where the Simple Mail Transfer Protocol (SMTP) server or gateway is running.

**Type**

Resettable, single-valued

**Allowed Values**

You can enter a text string up to 4095 characters long that is either of these types of addresses:

**Hostname**

For example, leo.boulder.IBM.com.

**Dotted decimal address**

For example, 9.99.12.85.

**Default Values**

**localhost**

**Usage Guidelines**

- You must enter a value in order to receive notifications through the **electronic-mail** notification delivery method.

**Note:** Select client notifications use the **electronic-mail** notification delivery method.

## Server

### smtp-server-port-number (Windows NT and Windows 2000 Only)

Identifies the port number on which the Simple Mail Transfer Protocol (SMTP) server is listening.

#### Type

Resettable, single-valued

#### Allowed Values

You can enter an integer from 1 through 2147483647, but you typically enter an integer from 5001 to 65535.

#### Default Values

25

**Note:** This is the Internet Assigned Numbers Authority (IANA) reserved port number for SMTP.

#### Usage Guidelines

- You must enter a value in order to receive notifications through the **electronic-mail** notification delivery method.

**Note:** Select client notifications use the **electronic-mail** notification delivery method.

### snmp-aix-printer-models

Identifies the SNMP descriptive printer model names that the AIX DSS recognizes.

#### GUI Label

AIX printer models

#### Type

Non-settable, multi-valued

#### Allowed Values

Infoprint sets this value to a list of recognized SNMP printer models.

#### Default Values

A list of recognized SNMP printer models.

### snmp-discovery-during-startup

Specifies that during startup, the server should issue an SNMP query for each SNMP printer to obtain the most up-to-date status.

#### GUI Label

Discover printers at startup

#### Type

Resettable, single-valued

#### Allowed Values

##### *Fixed Value*

true  
false

##### *Input Synonym*

yes  
no

#### Default Value

true

### Usage Guidelines

- When **SNMP-discovery-during startup** is **true**, the SNMP queries can cause long startup times, especially when there are lots of SNMP printers and a significant number of them are powered off or disconnected.
- When **SNMP-discovery-during startup** is **false**, the server bypasses the initial SNMP queries, and the SNMP printers show whatever their status was when the server was shutdown the last time. When set to **false**, the printer status becomes up-to-date over time as the SNMP polling loop runs.

## snmp-normal-poll-interval

Indicates the number of seconds that the server should wait between polling output devices that use SNMP and that are not known to have a problem.

### GUI Label

Normal poll interval (sec)

### Type

Resettable, single-valued

### Allowed Values

You can enter an integer from 0 through 2147483647.

### Default Value

300

### Usage Guidelines

- When normal polling finds that an output device has a problem, Infoprint disables the actual destination if necessary and transfers the device to the list of devices to be polled at the problem interval.
- Output devices with which the server has not established, or has lost, SNMP communication, are polled at the normal interval, not the problem interval.
- Set a value of **0** to disable normal polling.

## snmp-problem-poll-interval

Indicates the number of seconds that the server should wait between polling output devices that use SNMP and that are known to have a problem.

### GUI Label

Problem poll interval (sec)

### Type

Resettable, single-valued

### Allowed Values

You can enter an integer from 0 through 2147483647.

### Default Value

60

### Usage Guidelines

- When problem polling finds that an output device no longer has a problem, Infoprint reenables the actual destination if necessary and transfers the device to the list of devices to be polled at the normal interval. To prevent Infoprint from reenabling the actual destination, manually disable it.
- Output devices with which the server has not established, or has lost, SNMP communication, are polled at the normal interval, not the problem interval.

## Server

- Set a value of **0** to disable problem polling.

### transfer-methods-supported

Identifies the transfer methods that this server supports.

#### Type

Non-settable, multi-valued

#### Allowed Values

Infoprint sets this value to any of these fixed values:

**pipe-pull**  
**with-request**

#### Default Values

**pipe-pull, with-request**

#### Usage Guidelines

Infoprint compares the document attribute **transfer-method** to this attribute for validation.

### windows-drivers

See **windows-nt-driver-names**.

### windows-nt-driver-names

Identifies the 32-bit Windows print driver that can be used as the device driver for automatically created gateway shared printers on this server.

#### GUI Label

Windows drivers

#### Type

Resettable, single-valued

#### Input Synonyms

You can use the synonym **windows-nt-drivers** or **nt-drivers**.

#### Allowed Values

You can enter a text string that contains the string form of the Windows print driver.

#### Default Values

No default values

#### Usage Guidelines

- Perform the following procedure to determine the valid Windows driver names:
  1. Select **My Computer** from the desktop.
  2. Select and open the **Control Panel** icon.
  3. Select and open the **Printers** icon,
  4. Select and open the **Add Printer** icon.
  5. The values listed in the **Printers:** list box in the **Add Printer Wizard** are the names of the Windows destination drivers that you can install on the workstation; for example, **IBM 4039 LaserPrinter PS**.

**Note:** Other destination drivers are available and may not display in the list for a particular workstation.

## windows-nt-drivers

See `windows-nt-driver-names`.

---

## Attributes for Transforms (Windows NT or Window 2000 only)

Infoprint uses transform objects to indicate how specific document formats sent to an associated actual destination are to be transformed before printing or storing.

### Initially Settable Attribute Listing

`output-document-format`  
`transform-id`

### Resettable Attribute Listing

You can set these attributes with the `pdcreate` command when you create a transform or modify them with the `pdset` command after you create the transform. You can also erase a transform with the `pddelete` command or list selectable attribute values for a transform with the `pdls` command.

`descriptor`  
`document-formats-supported`  
`other-transform-options`

### associated-server

Indicates the name of the server where this transform resides.

#### GUI Label

Server

#### Type

Non-settable, single-valued

#### Allowed Values

Infoprint sets this value when you create a transform for a given server. Infoprint assigns the *ServerName* portion of the argument from the `pdcreate` command used to create this transform object.

#### Default Value

No default value

### descriptor

Provides a description of this transform.

#### GUI Label

Description

#### Type

Resettable, single-valued

#### Allowed Values

You can enter a text string up to 4095 characters long that describes this transform.

#### Default Value

No default value

## Transforms

### Usage Guidelines

The use of this attribute is optional. However, a detailed description of the transform that this references can be helpful to a users who need to determine which transform to use.

## document-formats-supported

Identifies the document formats that this transform supports.

### GUI Label

Document formats allowed

### Type

Resettable, multi-valued

### Allowed Values

You can enter any of these fixed values:

<i>Fixed Value</i>	<i>Input Synonym</i>
ascii	
dbcs-ascii	
ditroff	
d630	
gif	
hpgl	hp-gl
iso-6429	
jpeg	
kgi	
lcds	
line-data	
metacode	
modca-p	afpds
passthru	
pcl	hppcl, hp-pcl
pdf	
postscript	ps
ppds	
sap	
sap-abap	
simple-text	text
tiff	

### Default Values

ASCII, MODCA-P (AFPDS), PCL, PostScript

### Usage Guidelines

- When a document's format is not supported, the document bypasses the transform.

## object-class

Identifies the object class to which this object belongs.

### Type

Non-settable, single-valued

### Allowed Values

Infoprint sets this value to **transform**.



### Default Value

transform

## other-transform-options

Specifies the command line that executes when this transform is run.

### GUI Label

Transform options

### Type

Resettable, single-valued

### Allowed Values

You can enter a text string of up to 4095 characters that contains the command line for this transform.

### Default Value

No default value

### Usage Guidelines

For **transform-library=command-line-transform**, this attribute contains the command line that specifies the transform. The supported substitution control sequences that may be used in **other-transform-options** follow:

**%i** The name of the input-file to transform.

**%o** The name of the file in which to store the output transform.

**Note:** If no data is stored in this file and this is a non-terminating transform, Infoprint Manager assumes that the transform did not want to modify the input data, so Infoprint Manager simply passes the input file on to the next transform in sequence.

**%e** The name of the file in which to store any transform information or error messages. If anything is written to this file, it is logged in the Infoprint Manager server log.

**%j** The name of the original print file name, minus the path (from **document-file-name** attribute).

**Note:** This file may not be accessible. This should only be used to construct another name, for example, for a temporary file.

**%n** The name of the original print file name, minus the path and minus the extension (from **document-file-name** attribute).

**Note:** This file may not be accessible. This should only be used to construct another name, for example, for a temporary file.

**%d** A string representing the document-format of the input file:

**ascii** ASCII

**afpds** AFPDS

**pcl** PCL

**postscript**  
PS

**%p** The value of the **destination-pass-through** attribute.

**%q** The name of the actual destination that is doing this transform.

## Transforms

**%#** The job-identifier of the job.

### **Examples for other-transform-objects:**

- To run the **ps2afp** transform and print the generated AFP data, you would specify a one-step transform sequence consisting of a transform object as follows:

```
other-transform-options="ps2afp -o %o %i"
```

- To run the **ps2afp** transform and also save a copy of the generated AFP data in "c:\afp\\*.afp", you could create a transform sequence consisting of two transform objects as follows:

1.

```
other-transform-options="ps2afp -o %o %i"
```

This step does the PostScript to AFP transform and stores the output in the designated output file, which becomes the input file for step 2.

2.

```
other-transform-options="copy %i c:\afp\%n.afp"
```

This step copies the AFP file from step 1. However, in this example, nothing is put in the %o file, so the %i file (the transformed AFP) is passed through to the DSS for printing.

- To run a customized program that removes PostScript controls that may create a problem at the printer, you would use a one-step transform sequence consisting of a transform object as follows:

```
other-transform-options="d:\tools\my_ps_filter.exe %i %o"
```

## output-document-format

Identifies the format of the output file generated by the transform. This is a required attribute.

### **GUI Label**

Format of output file

### **Type**

Non-settable, single-valued

### **Allowed Values**

You can enter any of these fixed values:

<i>Fixed Value</i>	<i>Input Synonym</i>
ascii	
dbcs-ascii	
ditroff	
d630	
gif	
hpgl	hp-gl
iso-6429	
jpeg	
kgl	
lcds	
line-data	
metacode	
modca-p	afpds
passthru	
pcl	hppcl, hp-pcl

<i>Fixed Value</i>	<i>Input Synonym</i>
pdf	
postscript	ps
ppds	
sap	
sap-abap	
simple-text	text
tiff	

**Default Value**  
No default value

## terminating-transform

Indicates whether or not this is a terminating transform.

**GUI Label**  
How to process jobs

**Type**  
Settable, single-valued

**Allowed Values**  
You can enter one of these fixed values:

<i>Fixed Value</i>	<i>Input Synonym</i>
true	yes
false	no

**Default Value**  
false

**Usage Guidelines**  
When you specify **true** for **terminating-transform**, Infoprint Manager ends the transform sequence and marks the job complete without printing through the DSS backend.

A terminating transform may be used to create an actual destination that only performs a transform and then stores/forwards the transformed data without ever printing it to an output device.

Since the DSS is never actually executed, a terminating transform can be associated with any type of DSS. You should associate a terminating transform with a BSD DSS destination to minimize unnecessary overhead, such as creating files, ports, and so on.

### Examples for terminating-transform

- For example, a BSD DSS destination could be created and associated with a transform that runs **ps2afp** and stores the resulting AFP file in a library.
- As another example, you could also use a BSD DSS destination fed by one queue and associated with a transform that runs **ps2afp** and then **pdpr**'s the resulting AFP file to a logical destination that feeds a real printer. This example gives you a way to do *pre-spool* transforms.

## transform-identifier

Uniquely identifies this transform.

## Transforms

### Type

Non-settable, single-valued

### Allowed Values

Infoprint sets this value to the *SimpleName* portion of the argument specified with the **pdcreate** command when this transform is created.

### Default Value

No default value

## transform-library

Identifies the name of the DLL/Shared library that implements this transform.

### Type

Non-settable, single-valued

### Allowed Values

command-line-transform

### Default Value

command-line-transform

## Chapter 8. Infoprint Environment Variables

Table 14, Table 15 on page 652, Table 16 on page 653, and Table 17 on page 654 describe the environment variables that affect how Infoprint processes commands and utilities.

Table 14. Infoprint Environment Variables Defaulted or Set for Infoprint Manager for AIX and Infoprint Manager for Windows NT and Windows 2000

Variable	Description
<b>PATH</b>	<p>With Infoprint Manager for AIX, the directories that AIX searches for command files. Separate multiple directories by a colon, : .</p> <p><b>Commands:</b> All</p> <p><b>Default:</b> <code>\$PATH:/usr/lpp/pd/bin:/usr/lpp/psf/bin</code>, where <code>\$PATH</code> is the value when Infoprint is installed</p> <p>With Infoprint Manager for Windows NT and Windows 2000, the directories that AIX searches for command files. Separate multiple directories by a semi-colon, ; .</p> <p><b>Commands:</b> All</p> <p><b>Default:</b> <code>%PATH%:install_path\pd\bin;install_path\psf\bin</code>, where <code>%PATH%</code> is the value when Infoprint is installed</p>
<b>PDIDTABLE</b>	<p>Defines the upper limit (boundary) of local job identifiers that Infoprint can assign for each user before wrapping to 1. The maximum valid integer is 32767. If you do not set a value, Infoprint uses 100 as the upper limit. Setting the value to a lower value decreases memory usage but increases the chances of duplicate local job identifiers.</p>
<b>PDPATH</b>	<p>A path of directories that Infoprint searches for the file name specified by the <code>-X attributes file name</code> flag. Separate multiple directories by a colon, : . If the <b>PDPATH</b> environment variable does not exist, Infoprint uses the current working directory of the person submitting the command.</p> <p><b>Commands:</b> All</p>
<b>PDPRINTER</b>	<p>Used as the default logical destination when you do not specify the <code>-d DestinationName</code>, the <code>-p DestinationName</code> flag, or the <b>destination-name-requested</b> job attribute.</p> <p><b>Commands:</b> <code>pdls, pdq, pdpr</code></p> <p>Infoprint also uses this variable to identify the server for other commands.</p>
<b>PD_CONFIRM_DELETE</b>	<p>Specifies whether Infoprint issues a confirmation message before deleting an object.</p> <p><b>Commands:</b> <code>pdclean, pddelete, pdrm</code></p> <p><b>Values:</b> <code>yes, no</code></p> <p><b>Default:</b> <code>yes</code></p>

## Environment Variables

Table 14. Infoprint Environment Variables Defaulted or Set for Infoprint Manager for AIX and Infoprint Manager for Windows NT and Windows 2000 (continued)

<b>Variable</b>	<b>Description</b>
<b>PD_ENABLE_TIMEOUT</b>	Specifies the number of seconds that a server waits for an actual destination to register when the actual destination is enabled. <b>Default:</b> <b>15</b>
<b>PD_LISTEN_COUNT</b>	Specifies the number of simultaneous requests that a server can process. If this number is exceeded, the server issues an error message. <b>Default:</b> <b>10</b>
<b>PD_SOCKET</b>	Identifies the port number used by the Infoprint communications daemon. Internet services reserve socket numbers up to 255. Other non-Infoprint services reserve socket numbers in the range 256 through 1023. To determine the socket numbers already reserved before assigning a socket number to an Infoprint communications daemon, look at the contents of the <b>/etc/services</b> file. <b>Default:</b> <b>6874</b>
<b>PSFDBLANG</b>	The language and code page used by the <b>db2afp</b> transform program. <b>Values:</b> <b>j</b> (Japanese, code page 932), <b>c</b> (Traditional Chinese, code page 938), <b>je</b> (Japanese EUC), <b>ce</b> (Traditional Chinese EUC), <b>ke</b> (Korean EUC)
<b>PSFPATH</b>	A path of directories that Infoprint searches for print resources (fonts, form definitions, overlays, page definitions, and page segments). Separate multiple directories by a colon, : . <b>Commands:</b> <b>pdpr</b>

Table 15. Infoprint Environment Variables Defaulted or Set in the **/etc/environment** File in Infoprint Manager for AIX

<b>Variable</b>	<b>Description</b>
<b>GIF2AFP_option</b>	Specifies options for the <b>GIF2AFP</b> transform command. See "gif2afp Command: Transforms GIF Data to AFP in Infoprint Manager for AIX" on page 209.
<b>IPR_PREDPROD</b>	Used during migration to specify the product that preceded Infoprint. <b>Value:</b> <b>PSF</b> (PSF for AIX)
<b>JPEG2AFP_option</b>	Specifies options for the <b>JPEG2AFP</b> transform command. See "jpeg2afp Command: Transforms JPEG Data to AFP in Infoprint Manager for AIX" on page 223.
<b>MANPATH</b>	A path of directories that AIX searches for man pages. Separate multiple directories by a colon, : . <b>Commands:</b> <b>man</b>

## Environment Variables

Table 15. Infoprint Environment Variables Defaulted or Set in the /etc/environment File in Infoprint Manager for AIX (continued)

<b>Variable</b>	<b>Description</b>
<b>PDBASE</b>	Specifies the root directory where the Infoprint server stores all of its working files, such as log or trace files. Each server has its own subdirectory under this directory to avoid name conflicts when multiple servers are on the same AIX processor. <b>Utilities:</b> <b>start_server, startsrv</b> <b>Default:</b> <b>/var/pd</b>
<b>PDNAMESP</b>	Specifies the namespace. <b>Commands:</b> All <b>Default:</b> <b>/var/pddir/default_cell</b> (without DCE) <b>./:./subsys/ldr</b> (with DCE)
<b>PPO_DEFAULT_ENV</b>	The fully qualified name of the Infoprint SMIT production print operations interface environment file, which contains a shell script that defines all other Infoprint SMIT production print operations interface environment variables. <b>Default:</b> <b>/usr/lpp/pd/bin/ppo.env</b>
<b>TIFF2AFP_option</b>	Specifies options for the <b>TIFF2AFP</b> transform command. See “tiff2afp Command: Transforms TIFF Data to AFP in Infoprint Manager for AIX” on page 310.
<b>TYPESETTER</b>	Determines how <b>troff</b> files are processed for printing. <b>Values:</b> <b>afp, hplj, psc</b>
<b>XBMLANGPATH</b>	A path of directories that AIX searches for the icons used by graphical user interfaces. Separate multiple directories by a colon, : .

Table 16. Infoprint Environment Variables Set in the Infoprint SMIT Production Print Operations Interface Environment File for Infoprint Manager for AIX

<b>Variable</b>	<b>Description</b>
<b>PPO_CANCEL_ALL_OPTION</b>	Specifies whether operators have the option of cancelling all jobs. <b>Values:</b> <b>0</b> (no), <b>1</b> (yes) <b>Default:</b> <b>1</b> (yes)
<b>PPO_FORM</b>	The list of forms (media) that your printing operation can use. Separate form names by blanks.
<b>PPO_JOB_BATCH</b>	The list of job batches that your printing operation can use. Separate job batch names by blanks.
<b>PPO_JOB_DETAILS_ATTRS</b>	The job and document attributes that are displayed in the Infoprint SMIT production print operations interface job status window. Separate attribute names by commas.
<b>PPO_LP</b>	The name of the default logical destination to which the Infoprint SMIT production print operations interface resubmits print jobs.

## Environment Variables

Table 16. Infoprint Environment Variables Set in the Infoprint SMIT Production Print Operations Interface Environment File for Infoprint Manager for AIX (continued)

<b>Variable</b>	<b>Description</b>
<b>PPO_LPS</b>	The names of logical destinations that are available for job submission. Separate logical destination names by blanks.
<b>PPO_PP_ATTRS</b>	The actual destination attributes that are displayed in the Infoprint SMIT production print operations interface destination status window. Separate attribute names by commas.
<b>PPO_PPS</b>	The names of the actual destinations that the Infoprint SMIT production print operations interface manages. Separate actual destination names by blanks.
<b>PPO_QUEUE</b>	The name of the queue that the Infoprint SMIT production print operations interface manages.
<b>PPO_QUEUE_ATTRS</b>	The queue attributes that are displayed in the Infoprint SMIT production print operations interface queue status window. Separate attribute names by commas.
<b>PPO_QUEUE_INFO_FILE</b>	In installations that use multiple queues, the name of the file that maps queues to their environment files.
<b>PPO_SERVER</b>	The name of the server that the Infoprint SMIT production print operations interface manages.
<b>PPO_TRACE_FILE</b>	The name of the file containing trace records for the Infoprint SMIT production print operations interface manages. Use this environment variable only under the direction of IBM service.

Table 17. AIX Environment Variables

<b>Variable</b>	<b>Description</b>
<b>LANG</b>	The name of the locale to use for locale categories when neither <b>LC_ALL</b> nor the corresponding environment variable beginning with <b>LC_</b> specifies a locale. Used to determine the language, territory, or character set of messages and other information that Infoprint sends to a person. <b>Commands:</b> All
<b>LC_ALL</b>	The name of the locale used to override any values for locale categories specified by the setting of <b>LANG</b> or any environment variables beginning with <b>LC_</b> . <b>Commands:</b> All
<b>LC_CTYPE</b>	The name of the locale for character classification. <b>Commands:</b> All
<b>LC_MONETARY</b>	The name of the locale containing monetary-related numeric editing information. <b>Commands:</b> All
<b>LC_NUMERIC</b>	The name of the locale containing numeric editing, such as radix and character information. <b>Commands:</b> All



Table 17. AIX Environment Variables (continued)

Variable	Description
LC_TIME	The name of the locale for date and time formatting information. <b>Commands:</b> All
LC_MESSAGES	The name of the locale for <b>STDERR</b> messaging. <b>Commands:</b> All
NLSPATH	A path of directories that AIX searches for locale-dependent files. Separate multiple directories by a colon, : .

---

## Querying Environment Variables

You can use the **echo** command to query the value of an environment variable. For example, to determine the default logical destination, enter:

```
echo $PDPRINTER
```

To query all environment variables that have values set, enter:

```
env
```

---

## Setting Environment Variables

You can use the **export** command to set environment variables:

- If you are an administrator, in an environment file.
  - You can set AIX environment variables and many Infoprint environment variables in the **/etc/environment** file.
  - You can set some Infoprint environment variables that affect the Infoprint SMIT production print operations interface in the Infoprint SMIT production print operations interface environment file. The **PPO\_DEFAULT\_ENV** environment variable defines the name of this file.

Settings in the environment files apply to all sessions for all users, unless a user resets the environment variables in the **.profile** file or on the command line.

**Note:** These settings do not apply to processes that are already running when you edit the file. For example, a server is a process. To make your changes effective, stop and restart the server.

- In the **.profile** file in your home directory. Settings in the **.profile** file override settings in the **/etc/environment** file and the Infoprint SMIT production print operations interface environment file. These settings apply only to you and are in effect for all your AIX sessions, unless you reset the environment variables on the command line.
- On the command line for a single AIX session. Command line settings override settings in the **/etc/environment** file, the Infoprint SMIT production print operations interface environment file, and your **.profile** file. These settings apply only to you and are in effect only until you exit the session.

## Environment Variables

### In a File

To set an environment variable in a file, you need to edit the file with an editor. If you do not know how to use an editor, or the editor you are using is not capable of saving in the plain text (ASCII) file format, do not start. Ask your administrator for assistance.

The following example shows how to set the **PDPRINTER** environment variable in your **.profile** file, using the **vi** editor.

1. Enter the following command to change to your home directory:

```
cd
```

2. Make a backup copy of the file:

```
cp -p .profile .profile.org
```

The **-p** flag gives the copy the same file permissions and modification date and time as the original file.

3. Enter the following command:

```
vi .profile
```

4. A typical **.profile** file contains lines similar to the following:

```
PATH=.:$HOME/bin:/bin:/usr/bin:/etc:/usr/ucb:/usr/bin/X11:tools/  
usr/bin:/usr/lpp/cmvc/bin:/usr/OV/bin:/usr/local/tools/rs6/bin:/usr  
/local/tools/rs6:/usr/dt/bin  
  
export PATH  
export EDITOR=vi
```

5. Insert or modify the following line in the **.profile** file:

```
export PDPRINTER=LogicalDestinationName
```

where *LogicalDestinationName* is the name of the logical destination you want to set as your default.

6. Save the change in plain text format and exit from the editor.
7. Make the change effective by entering the following command:

```
..profile
```

8. Verify the change by entering the command:

```
echo $PDPRINTER
```

The logical destination name you entered displays.

### On the Command Line

To set the value of the environment variable **PDPRINTER** to **Destination3** for a single AIX session, enter:

```
export PDPRINTER=Destination3
```

## Chapter 9. Notification Events and Event Classes

Table 18 alphabetically lists the names of individual events that you can specify as values for the **event-identifiers** component of the **notification-profile** attribute. The information for each event includes a description, the event class or classes to which the event belongs, the Infoprint objects that support the notification of the event, and the text of the notification message that Infoprint generates for the event. Items in the message text shown in *italics* are variables for which Infoprint supplies values when it issues the message.

Table 18. Notification Events

<b>Event</b>	<b>Event Class</b>	<b>Objects Supported</b>
	<b>Description</b>	
	<b>Message</b>	
<b>checkpoint-taken</b>	<b>class-job-status</b> <b>class-report</b>	Job
	When this job was paused, the server saved checkpoint information for it. The server can restart the job at the checkpoint. <b>Note:</b> The server does not save checkpoint information for jobs terminated by errors.	
	5010-218 The server saved checkpoint information for job <i>JobID</i> ( <i>ServerName:GlobalID</i> ).	
<b>close-to-discard-time</b>	<b>class-job-attention</b> <b>class-warning</b>	Job Server
	The date and time specified by the <b>job-discard-time</b> or the <b>job-retention-period</b> attribute is approaching. Infoprint will delete the job at the discard time.	
	5010-234 Job <i>JobID</i> ( <i>ServerName:GlobalID</i> ) is close to being discarded.	
<b>destination-disabled</b>	<b>class-actual-destination-attention</b> <b>class-logical-destination-attention</b> <b>class-warning</b>	Actual destination Logical destination Queue Server
	Infoprint disabled a logical destination or actual destination and it will not accept new jobs.	
	5010-240 Successfully disabled destination <i>ServerName:DestinationName</i> .	
<b>destination-enabled</b>	<b>class-actual-destination-attention</b> <b>class-logical-destination-attention</b> <b>class-warning</b>	Actual destination Logical destination Queue Server
	Infoprint enabled a logical destination or actual destination and it now accepts jobs.	
	5010-226 Successfully enabled destination <i>ServerName:DestinationName</i> .	

## Notification Events

Table 18. Notification Events (continued)

Event	Event Class	Objects Supported
	Description	
	Message	
destination-function-unavailable	<b>class-actual-destination-status</b> <b>class-job-attention</b> <b>class-warning</b>	Actual destination Server
	The actual destination requires an output device function, such as duplex or offset stacking, that is not available. The function is disabled, but processing continues.	
	5010-307 The destination <i>ServerName:DestinationName</i> requires a function that is not available.	
destination-needs-administrator	<b>class-actual-destination-attention</b> <b>class-actual-destination-default</b> <b>class-job-attention</b> <b>class-warning</b>	Actual destination Job Server
	The server or actual destination detected a condition requiring administrator intervention. The actual destination is disabled.	
	5010-306 The destination <i>ServerName:DestinnationName</i> needs administrator attention.	
destination-needs-attention	<b>class-actual-destination-attention</b> <b>class-actual-destination-default</b> <b>class-job-attention</b> <b>class-job-default</b> <b>class-warning</b>	Actual destination Job Server
	The actual destination needs attention from a person, not necessarily the operator. The actual destination cannot process jobs until it receives attention.	
	5010-245 Actual destination <i>ServerName:destinnationname</i> needs attention.	
destination-needs-operator	<b>class-actual-destination-attention</b> <b>class-actual-destination-default</b> <b>class-job-attention</b> <b>class-job-default</b> <b>class-warning</b>	Actual destination Job Server
	An actual destination needs operator attention. The actual destination cannot process jobs until it receives attention.	
	5010-246 Actual destination <i>ServerName:DestinationName</i> needs operator attention.	
destination-registered	<b>class-actual-destination-status</b> <b>class-report</b>	Actual destination Queue Server
	An actual destination has registered with this queue. The queue can now schedule jobs to this actual destination.	
	5010-223 Actual destination <i>ServerName:DestinationName</i> registered with queue <i>ServerName:QueueName</i> .	

Table 18. Notification Events (continued)

<b>Event</b>	<b>Event Class</b>	<b>Objects Supported</b>
	<b>Description</b>	
	<b>Message</b>	
<b>destination-shutdown-job-queued</b>	<b>class-actual-destination-attention</b> <b>class-job-attention</b> <b>class-warning</b>	Actual destination Job Server
	The actual destination shut down after this job started processing. The job was requeued and will be scheduled again.	
	5010-237 Actual destination <i>ServerName:DestinationName</i> was shut down after job <i>JobID (ServerName:GlobalID)</i> started processing.	
<b>destination-state-changed</b>	<b>class-actual-destination-status</b> <b>class-state-changed</b>	Actual destination
	The actual destination state changed. Processing continues.	
	5010-228 The state of actual destination <i>ServerName:DestinationName</i> changed to <i>State</i> .	
<b>destination-timed-out</b>	<b>class-actual-destination-attention</b> <b>class-actual-destination-default</b> <b>class-warning</b>	Actual destination Server
	The actual destination did not connect or get a response from the output device in the time specified by the <b>destination-timeout-period</b> actual destination attribute. Another application is using the output device or job progress at the output device has stopped. The actual destination continues its attempts to connect or print to the output device. The actual destination cannot process jobs until it connects to the device. Check the server error log for additional information.	
	5010-247 Actual destination <i>ServerName:DestinationName</i> has timed out.	
<b>destination-unregistered</b>	<b>class-actual-destination-status</b> <b>class-warning</b>	Actual destination Queue Server
	This actual destination is no longer registered with this queue and the queue no longer sends jobs to this actual destination.	
	5010-243 Actual destination <i>ServerName:DestinationName</i> is no longer registered with <i>ServerName:QueueName</i> .	
<b>destinations-not-ready-for-job</b>	<b>class-job-attention</b> <b>class-job-default</b> <b>class-warning</b>	Job Queue Server
	There are no actual destinations currently available that can support the “ready” attributes for the job. Ready attributes include <b>job-batch</b> , <b>total-job-octets</b> , <b>default-medium</b> , and <b>page-media-select</b> .	
	5010-702 The job <i>JobID (ServerName:GlobalID)</i> cannot be scheduled to an actual destination because resources are not currently ready.	
<b>detailed-messages</b>	<b>class-job-attention</b> <b>class-report</b>	Actual destination Job Server
	The print backend has sent a message.	
	5010-302 <i>Message from the print backend program</i>	

## Notification Events

Table 18. Notification Events (continued)

Event	Event Class	Objects Supported
	Description	
	Message	
document-aborted-by-destination	<b>class-aborted</b> <b>class-job-attention</b> <b>class-job-default</b>	Actual destination Job Server
	The actual destination deleted the document without printing or transmitting it. Errors occurred during processing.	
	5010-292 Document <i>DocNum FileName</i> in job <i>JobID</i> ( <i>ServerName:GlobalID</i> ) was aborted by the actual destination.	
document-aborted-by-server	<b>class-aborted</b> <b>class-job-attention</b> <b>class-job-default</b>	Actual destination Job (AIX DSS only) Server
	The server aborted this document and deleted it.	
	5010-206 Document <i>DocNum (FileName)</i> in print job <i>JobID</i> ( <i>ServerName:GlobalID</i> ) was aborted by the server.	
document-cancelled-at-destination	<b>class-aborted</b> <b>class-job-attention</b> <b>class-job-default</b>	Actual destination Job Server
	The document was cancelled at the actual destination.	
	5010-293 Document <i>DocNum (FileName)</i> in job <i>JobID</i> ( <i>ServerName:GlobalID</i> ) was cancelled at the actual destination.	
document-content	<b>class-error</b> <b>class-job-problem</b>	Actual destination Server
	The server detected an error in the content of this file during printing. An example of this type of error is a syntax error in the page description language for this file.	
	5010-208 An error was detected in document <i>DocNum (FileName)</i> of job <i>JobID</i> ( <i>ServerName:GlobalID</i> ) during printing.	
file-transferred	<b>class-job-status</b> <b>class-report</b>	Job
	A file transfer completed successfully. The file may now be modified without affecting the output.	
	5010-219 Server ( <i>ServerName</i> ) completed the transfer of document <i>DocNum (FileName)</i> in job <i>JobID</i> ( <i>ServerName:GlobalID</i> ).	
internal-server-error	<b>class-error</b> <b>class-server-attention</b> <b>class-server-default</b>	Server
	A server error occurred. The process failed.	
	5010-215 An internal error was detected in server <i>ServerName</i> .	
job-aborted-by-server	<b>class-aborted</b> <b>class-job-attention</b> <b>class-job-default</b>	Actual destination Job Queue Server
	The server aborted this job because job or output device errors occurred during printing or transmission.	
	5010-204 Job <i>JobID</i> ( <i>ServerName:GlobalID</i> ) stopped printing due to job or device errors.	

Table 18. Notification Events (continued)

Event	Event Class	Objects Supported
	Description	
	Message	
job-assigned-to-destination	class-report	Job
	This job was assigned to this actual destination.	
	5010-660 The job <i>JobID (ServerName:GlobalID)</i> is assigned to destination <i>ServerName:DestinationName</i>	
job-assigned-to-destination-at-end	class-report	Job
	This job is the last job assigned to this actual destination.	
	5010-659 The job <i>JobID (ServerName:GlobalID)</i> is the last job assigned to destination <i>ServerName:DestinationName</i>	
job-assigned-to-queue	class-job-status class-report	Job Queue Server
	This job was assigned to this queue in this state. Processing continues.	
	5010-301 The job <i>JobID (ServerName:GlobalID)</i> is assigned to queue <i>ServerName:QueueName</i> and is in the <i>State</i> state.	
job-cancelled-by-operator	class-aborted class-job-attention class-job-default	Actual destination Job Queue Server
	The operator or administrator deleted the job.	
	5010-196 Job <i>JobID (ServerName:GlobalID)</i> was cancelled by the operator or administrator.	
job-cancelled-by-user	class-aborted class-job-attention	Actual destination Job Queue Server
	The user deleted the job.	
	5010-197 Job <i>JobID (ServerName:GlobalID)</i> was cancelled by the user.	
job-cannot-be-scheduled	class-job-attention class-job-default class-warning	Job Queue Server
	There are no longer any actual destinations available that can support the attributes for the job. The actual destination that supported the attributes for the job at submission is no longer available. The job remains in the queue. Resubmit the job to a logical destination that supports the attributes for the job.	
	5010-103 The job <i>JobID (ServerName:GlobalID)</i> cannot be scheduled to an actual destination.	

## Notification Events

Table 18. Notification Events (continued)

Event	Event Class	Objects Supported
	Description	
	Message	
job-completed	<b>class-job-default</b> <b>class-job-status</b> <b>class-report</b>	Actual destination Job Queue Server
	The job completed processing. If more than one actual destination processed this job, the last actual destination is identified in the message. It may or may not have completed successfully. Check the output.	
	5010-055 Job name <i>jobname</i> with ID <i>JobID</i> ( <i>ServerName:GlobalID</i> ) completed on <i>DestinationName</i> .	
job-discarded	<b>class-job-attention</b> <b>class-job-default</b> <b>class-report</b>	Job Queue Server
	The date and time specified by the <b>job-discard-time</b> , the <b>job-retain-until</b> , or the <b>job-retention-period</b> attribute passed. Infoprint deleted the job. The job may or may not have printed if it was discarded because of the <b>job-retain-until</b> or <b>job-retention-period</b> value.	
	5010-220 Job <i>JobID</i> ( <i>ServerName:GlobalID</i> ) was discarded by the server after it printed or the retention period expired.	
job-modified	<b>class-job-status</b> <b>class-warning</b>	Job
	The job was modified. Processing continues.	
	5010-202 Job <i>JobID</i> ( <i>ServerName:GlobalID</i> ) was modified.	
job-paused	<b>class-job-attention</b> <b>class-warning</b>	Job
	The job was paused. If the job state was <b>processing</b> or <b>printing</b> , it stopped. Infoprint cannot schedule the job until it is resumed.	
	5010-203 Job <i>JobID</i> ( <i>ServerName:GlobalID</i> ) was paused.	
job-promoted	<b>class-job-status</b> <b>class-report</b>	Job Queue Server
	The job was promoted to the highest position in the queue.	
	5010-198 Job <i>JobID</i> ( <i>ServerName:GlobalID</i> ) was promoted.	
job-reordered	<b>class-job-status</b> <b>class-report</b>	Job Queue Server
	The job was successfully moved to a different actual destination or to the unassigned jobs area.	
	5010-846 Job <i>JobID</i> ( <i>ServerName:GlobalID</i> ) was moved from <i>ServerName1:DestinationName1</i> to <i>ServerName2:DestinationName2</i> .	
job-reequed	<b>class-job-status</b> <b>class-warning</b>	Job
	Infoprint added to the job to the queue for rescheduling because the actual destination that accepted the job can no longer print the job.	
	5010-322 Job <i>JobID</i> ( <i>ServerName:GlobalID</i> ) is added to the queue to be scheduled again.	



Table 18. Notification Events (continued)

Event	Event Class	Objects Supported
	Description	
	Message	
job-resubmitted	class-job-status class-report	Job Queue Server
	The job was successfully resubmitted to a different logical destination. Processing continues.	
	5010-222 Job <i>JobID</i> ( <i>ServerName:GlobalID</i> ) was resubmitted to logical destination <i>ServerName:DestinationName</i> from queue <i>ServerName:QueueName</i> .	
job-resumed	class-job-status class-report	Job Queue Server
	The job was resumed. If the job state is pending, Infoprint can schedule the job to an actual destination.	
	5010-199 Job <i>JobID</i> ( <i>ServerName:GlobalID</i> ) was resumed.	
job-retained	class-report	Job
	The job is retained.	
	5010-199 The job <i>JobID</i> ( <i>ServerName:GlobalID</i> ) is retained.	
job-state-changed	class-job-status class-state-changed	Job
	The state of the job has changed. Processing continues.	
	5010-201 The state of job <i>JobID</i> ( <i>ServerName:GlobalID</i> ) changed to <i>State</i> .	
job-submission-not-complete	class-error class-job-problem	Job Server
	The server waited for the amount of time specified in its <b>job-submission-timer</b> attribute to receive an indication that all of the document objects in a job have been sent. It did not receive that indication. The server will process the documents it has received as a complete job.	
	5010-209 The final document indication for job <i>JobID</i> ( <i>ServerName:GlobalID</i> ) was not received by the server within the server's job-submission-timer interval. Job processing will continue.	
job-unassigned	class-report	Job
	This job has been placed in the server's unassigned jobs area.	
	5010-661 The job <i>JobID</i> ( <i>ServerName:GlobalID</i> ) is not assigned to any destination.	
no-document	class-error class-job-problem	Actual destination Job Server
	The server could not access the document. The document and possibly the entire job have been aborted. Check the error log for messages related to this failure.	
	5010-210 Document <i>DocNum</i> ( <i>FileName</i> ) in job <i>JobID</i> ( <i>ServerName:GlobalID</i> ) could not be accessed by the server.	

## Notification Events

Table 18. Notification Events (continued)

<b>Event</b>	<b>Event Class</b>	<b>Objects Supported</b>
	<b>Description</b>	
	<b>Message</b>	
<b>no-resource</b>	<b>class-error</b> <b>class-job-problem</b>	Actual destination Server
	A resource needed by this job is unavailable. Infoprint aborted the job. Check the error log for messages related to this failure.	
	5010-211 The resource <i>Resource</i> needed by job <i>JobID</i> ( <i>ServerName:GlobalID</i> ) was not available.	
<b>object-cleaned</b>	<b>class-actual-destination-default</b> <b>class-actual-destination-status</b> <b>class-logical-destination-default</b> <b>class-logical-destination-status</b> <b>class-queue-default</b> <b>class-queue-status</b> <b>class-server-default</b> <b>class-server-status</b> <b>class-warning</b>	Actual destination Logical destination Queue Server
	Infoprint deleted jobs from this object. Processing continues.	
	5010-244 Successfully cleaned object <i>ObjectClass</i> <i>ServerName:ObjectName</i> .	
<b>object-created</b>	<b>class-actual-destination-configuration</b> <b>class-logical-destination-configuration</b> <b>class-queue-configuration</b> <b>class-report</b>	Actual destination Logical destination Queue Server
	The object was created.	
	5010-224 Successfully created object <i>ObjectClass</i> <i>ServerName:ObjectName</i> .	
<b>object-deleted</b>	<b>class-actual-destination-configuration</b> <b>class-actual-destination-default</b> <b>class-logical-destination-configuration</b> <b>class-logical-destination-default</b> <b>class-queue-configuration</b> <b>class-queue-default</b> <b>class-server-configuration</b> <b>class-server-default</b> <b>class-report</b>	Actual destination Job Logical destination Queue Server
	The object was deleted.	
	5010-225 Successfully deleted object <i>ObjectClass</i> <i>ServerName:ObjectName</i> .	
<b>object-modified</b>	<b>class-actual-destination-configuration</b> <b>class-logical-destination-configuration</b> <b>class-queue-configuration</b> <b>class-server-configuration</b> <b>class-server-default</b> <b>class-warning</b>	Actual destination Logical destination Queue Server
	The object was modified.	
	5010-241 Successfully modified object <i>ObjectClass</i> <i>ServerName:ObjectName</i> .	

Table 18. Notification Events (continued)

<b>Event</b>	<b>Event Class</b>	<b>Objects Supported</b>
	<b>Description</b>	
	<b>Message</b>	
<b>object-paused</b>	<b>class-actual-destination-attention</b> <b>class-queue-attention</b> <b>class-warning</b>	Actual destination Job Queue Server
	Infoprint paused an actual destination or queue and it cannot process jobs.	
	5010-242 Successfully paused object <i>ObjectClass</i> <i>ServerName:ObjectName</i> .	
<b>object-resumed</b>	<b>class-actual-destination-status</b> <b>class-queue-status</b> <b>class-report</b>	Actual destination Job Queue Server
	Infoprint resumed an actual destination or queue.	
	5010-227 Successfully resumed object <i>ObjectClass</i> <i>ServerName:ObjectName</i> .	
<b>other-error</b>	<b>class-error</b> <b>class-server-attention</b>	Actual destination Server
	An error occurred for this object that no other message describes. Check the error log for messages related to this failure.	
	5010-217 Server <i>ServerName</i> encountered an error.	
<b>other-warning</b>	<b>class-server-attention</b> <b>class-warning</b>	Actual destination Server
	The object encountered a warning condition that no other event describes. This warning condition may precede an error. Check the error log for messages related to this failure.	
	5010-236 Server <i>ServerName</i> has encountered a warning condition.	
<b>past-discard-time</b>	<b>class-error</b> <b>class-job-attention</b>	Job Queue Server
	The date and time specified by the <b>job-discard-time</b> job attribute passed before the job printed and Infoprint discarded the job.	
	5010-213 Job <i>JobID</i> ( <i>ServerName:GlobalID</i> ) was discarded before it printed.	
<b>processing-started</b>	<b>class-job-status</b> <b>class-report</b>	Actual destination Job Queue Server
	The server has begun to process the job. Infoprint has scheduled the job to print on an actual destination.	
	5010-200 Job <i>JobID</i> ( <i>ServerName:GlobalID</i> ) is processing.	

## Notification Events

Table 18. Notification Events (continued)

Event	Event Class	Objects Supported
	Description	
	Message	
queue-backlogged	<b>class-queue-attention</b> <b>class-queue-default</b> <b>class-warning</b>	Job Queue Server
	Infoprint calculates that there are too many jobs in this queue for all jobs to print within the amount of time specified for the <b>object-class-backlog-upper-bound</b> attribute. The queue continues to accept jobs, but there is a delay before they print.	
	5010-304 The queue <i>ServerName:QueueName</i> is backlogged.	
queue-no-longer-backlogged	<b>class-queue-status</b> <b>class-report</b>	Job Queue Server
	The queue is no longer backlogged. Infoprint calculates that the jobs currently in the queue will print within the amount of time specified for the <b>object-class-backlog-lower-bound</b> attribute.	
	5010-299 The queue <i>ServerName:QueueName</i> is no longer backlogged.	
queue-state-changed	<b>class-queue-status</b> <b>class-state-changed</b>	Queue
	The queue state changed. Processing continues.	
	5010-230 The state of queue <i>ServerName:QueueName</i> changed to <i>State</i> .	
resource-needs-attention	<b>class-actual-destination-attention</b> <b>class-warning</b>	Actual destination Server
	This resource needs attention from a person, not necessarily the operator. Infoprint cannot process jobs requiring this resource until someone corrects the problem.	
	5010-238 Resource <i>Resource</i> on actual destination <i>ServerName:DestinationName</i> needs attention.	
resource-needs-operator	<b>class-actual-destination-attention</b> <b>class-warning</b>	Actual destination Server
	This resource needs attention from an operator. Infoprint cannot process jobs requiring this resource until an operator corrects the problem.	
	5010-239 Resource <i>Resource</i> on actual destination <i>ServerName:DestinationName</i> needs operator attention.	
server-shutdown-complete	<b>class-server-attention</b> <b>class-server-default</b> <b>class-report</b>	Server
	This server has shut down and is no longer available.	
	5010-295 Successfully shut down server <i>ServerName</i> .	
server-shutdown-started	<b>class-server-attention</b> <b>class-warning</b>	Server
	This server has begun to shut down. It does not accept jobs.	
	5010-305 The server <i>ServerName</i> is shutting down.	

Table 18. Notification Events (continued)

Event	Event Class	Objects Supported
	Description	
	Message	
server-startup-complete	class-report class-server-configuration	Server
	Infoprint started this server.	
	5010-294 Successfully started server <i>ServerName</i> .	
server-state-changed	class-server-status class-state-changed	Server
	The state of the server has changed.	
	5010-299 The state of server <i>ServerName</i> changed to <i>State</i> .	
unable-to-register	class-warning	Actual destination Server
	The actual destination could not register with the queue within the amount of time specified for the <b>destination-register-threshold</b> actual destination attribute. Infoprint cannot schedule jobs to the actual destination.	
	5010-437 The actual destination <i>ServerName:DestinationName</i> cannot register with the queue <i>QueueName</i> .	
unrecognized-resource	class-error class-job-problem	Actual destination Server
	A resource required for this job is not known to the server. The job was aborted. Check the server error log for messages related to this failure.	
	5010-214 Resource <i>Resource</i> that is required for job <i>JobID</i> ( <i>ServerName:GlobalID</i> ) is not known to the server.	

An event class is an easy way to include multiple events in a value. Event classes group events based on the functions for which they provide notification. For example, some classes are specific to configuration tasks while other classes provide information about the status of Infoprint objects. Each event class name begins with **class**.

**Note:** An event identifier can occur in more than one class. For example, **object-cleaned** occurs in **class-logical-destination-default**, **class-logical-destination-status**, **class-actual-destination-default**, **class-actual-destination-status**, **class-object-class-default**, **class-object-class-status**, **class-server-default**, **class-server-status**, and **class-warning**. If the notification profile values list any of these event classes and you clean a logical destination, actual destination, queue, or server, Infoprint sends a message to the person identified in that value.

## Notification Events

Table 19. Notification Event Classes

<b>Event Class</b>	<b>Description</b>
	<b>Events</b>
<b>class-aborted</b>	An aborted event occurs whenever a server aborts a job or document object, or when the user or operator cancels a job.
	<b>document-aborted-by-destination</b> <b>document-aborted-by-server</b> <b>document-cancelled-at-destination</b> <b>job-aborted-by-server</b> <b>job-cancelled-by-operator</b> <b>job-cancelled-by-user</b>
<b>class-actual-destination-attention</b>	These events indicate that problems exist with the actual destination. Such problems usually require an operator or administrator to intervene.
	<b>destination-disabled</b> <b>destination-needs-administrator</b> <b>destination-needs-attention</b> <b>destination-needs-operator</b> <b>destination-shutdown-job-queued</b> <b>destination-timed-out</b> <b>object-paused</b> <b>resource-needs-attention</b> <b>resource-needs-operator</b>
<b>class-actual-destination-configuration</b>	These events have to do with the creation or deletion of an actual destination, or with modification of the attributes of an actual destination.
	<b>object-created</b> <b>object-deleted</b> <b>object-modified</b>
<b>class-actual-destination-default</b>	This is the default event class for actual destinations.
	<b>destination-needs-administrator</b> <b>destination-needs-attention</b> <b>destination-needs-operator</b> <b>destination-timed-out</b> <b>object-cleaned</b> <b>object-deleted</b>
<b>class-actual-destination-status</b>	This event class includes events that give detailed status about the actual destination. These changes in status are often routine and do not require intervention.
	<b>destination-enabled</b> <b>destination-function-unavailable</b> <b>destination-registered</b> <b>destination-state-changed</b> <b>destination-unregistered</b> <b>object-cleaned</b> <b>object-resumed</b>

Table 19. Notification Event Classes (continued)

<b>Event Class</b>	<b>Description</b>
	<b>Events</b>
<b>class-error</b>	<p>An error event occurs whenever an error occurs. Generally, an error event signals a condition that may prevent the job from completing successfully, depending on the settings of other parameters.</p> <p><b>document-content</b>  <b>internal-server-error</b>  <b>job-submission-not-complete</b>  <b>no-document</b>  <b>no-resource</b>  <b>other-error</b>  <b>past-discard-time</b>  <b>unrecognized-resource</b></p>
<b>class-job-attention</b>	<p>These events indicate that problems exist with a job. They usually require an operator or administrator to intervene.</p> <p><b>close-to-discard-time</b>  <b>destination-function-unavailable</b>  <b>destination-needs-administrator</b>  <b>destination-needs-attention</b>  <b>destination-needs-operator</b>  <b>destination-shutdown-job-queued</b>  <b>destinations-not-ready-for-job</b>  <b>detailed-messages</b>  <b>document-aborted-by-destination</b>  <b>document-aborted-by-server</b>  <b>document-cancelled-at-destination</b>  <b>job-aborted-by-server</b>  <b>job-cancelled-by-operator</b>  <b>job-cancelled-by-user</b>  <b>job-cannot-be-scheduled</b>  <b>job-discarded</b>  <b>job-paused</b>  <b>past-discard-time</b></p>
<b>class-job-default</b>	<p>This is the default event class for jobs.</p> <p><b>document-aborted-by-destination</b>  <b>document-aborted-by-server</b>  <b>document-cancelled-at-destination</b>  <b>destination-needs-attention</b>  <b>destination-needs-operator</b>  <b>destinations-not-ready-for-job</b>  <b>job-aborted-by-server</b>  <b>job-cancelled-by-operator</b>  <b>job-cannot-be-scheduled</b>  <b>job-completed</b>  <b>past-discard-time</b></p>
<b>class-job-problem</b>	<p>These are events in which the job has encountered a problem but will attempt to proceed.</p> <p><b>document-content</b>  <b>job-submission-not-complete</b>  <b>no-document</b>  <b>no-resource</b>  <b>unrecognized-resource</b></p>

## Notification Events

Table 19. Notification Event Classes (continued)

<b>Event Class</b>	<b>Description</b>
	<b>Events</b>
<b>class-job-status</b>	This event class includes events that give detailed status about the job. These changes in status are often routine and do not require intervention.
	<b>checkpoint-taken</b> <b>file-transferred</b> <b>job-assigned-to-queue</b> <b>job-completed</b> <b>job-modified</b> <b>job-promoted</b> <b>job-reordered</b> <b>job-requeued</b> <b>job-resubmitted</b> <b>job-resumed</b> <b>job-state-changed</b> <b>processing-started</b>
<b>class-logical-destination-attention</b>	This event indicates that a problem exists with the logical destination. An operator or administrator usually has to intervene.
	<b>destination-disabled</b>
<b>class-logical-destination-configuration</b>	These events have to do with the creation or deletion of a logical destination, or with modification of the attributes of a logical destination.
	<b>object-created</b> <b>object-deleted</b> <b>object-modified</b>
<b>class-logical-destination-default</b>	This is the default event class for logical destinations.
	<b>object-cleaned</b> <b>object-deleted</b>
<b>class-logical-destination-status</b>	This event class includes events that give detailed status about the logical destination. These changes in status are often routine and do not require intervention.
	<b>destination-enabled</b> <b>object-cleaned</b>
<b>class-queue-attention</b>	These events indicate that problems exist with the queue. An operator or administrator usually has to intervene.
	<b>object-paused</b> <b>queue-backlogged</b>
<b>class-queue-configuration</b>	These events have to do with the creation or deletion of a queue, or with the modification of the attributes of a queue.
	<b>object-created</b> <b>object-deleted</b> <b>object-modified</b>
<b>class-queue-default</b>	This is the default event class for queues.
	<b>object-cleaned</b> <b>object-deleted</b> <b>queue-backlogged</b>



Table 19. Notification Event Classes (continued)

<b>Event Class</b>	<b>Description</b>
	<b>Events</b>
<b>class-queue-status</b>	This event class includes events that give detailed status about the queue. These changes in status are often routine and do not require intervention.
	<b>object-cleaned</b> <b>object-resumed</b> <b>queue-no-longer-backlogged</b> <b>queue-state-changed</b>
<b>class-report</b>	A report event occurs whenever a significant point in processing occurs.
	<b>checkpoint-taken</b> <b>destination-enabled</b> <b>destination-registered</b> <b>detailed-messages</b> <b>file-transferred</b> <b>job-assigned-to-destination</b> <b>job-assigned-to-destination-at-end</b> <b>job-assigned-to-queue</b> <b>job-completed</b> <b>job-discarded</b> <b>job-promoted</b> <b>job-reordered</b> <b>job-resubmitted</b> <b>job-resumed</b> <b>job-retained</b> <b>job-unassigned</b> <b>object-created</b> <b>object-deleted</b> <b>object-resumed</b> <b>processing-started</b> <b>queue-no-longer-backlogged</b> <b>server-shutdown-complete</b> <b>server-startup-complete</b>
<b>class-server-attention</b>	These events indicate that problems exist with the server. They usually require an administrator to intervene.
	<b>internal-server-error</b> <b>other-error</b> <b>other-warning</b> <b>server-shutdown-complete</b> <b>server-shutdown-started</b>
<b>class-server-configuration</b>	These events have to do with the creation or deletion of a server or with modification of the attributes for a server.
	<b>object-deleted</b> <b>object-modified</b> <b>server-startup-complete</b>
<b>class-server-default</b>	This is the default event class for servers.
	<b>internal-server-error</b> <b>object-cleaned</b> <b>object-deleted</b> <b>server-shutdown-complete</b>

## Notification Events

Table 19. Notification Event Classes (continued)

<b>Event Class</b>	<b>Description</b>
	<b>Events</b>
<b>class-server-status</b>	This event class includes events that give detailed status about the server. These changes in status are often routine and do not require intervention.
	<b>object-cleaned</b> <b>server-state-changed</b>
<b>class-state-changed</b>	A state-change event occurs whenever the state of an actual destination, job, queue, or server changes.
	<b>destination-state-changed</b> <b>job-state-changed</b> <b>queue-state-changed</b> <b>server-state-changed</b>
<b>class-warning</b>	A warning event occurs whenever a condition arises which affects processing. Generally, a warning event signals a condition that does not prevent completion of the processing, but it may require some action by the operator or user.
	<b>close-to-discard-time</b> <b>destination-disabled</b> <b>destination-function-unavailable</b> <b>destination-needs-administrator</b> <b>destination-needs-attention</b> <b>destination-needs-operator</b> <b>destination-shutdown-job-queued</b> <b>destination-timed-out</b> <b>destination-unregistered</b> <b>destinations-not-ready-for-job</b> <b>job-cannot-be-scheduled</b> <b>job-modified</b> <b>job-paused</b> <b>job-queued</b> <b>object-cleaned</b> <b>object-modified</b> <b>object-paused</b> <b>other-warning</b> <b>queue-backlogged</b> <b>resource-needs-attention</b> <b>resource-needs-operator</b> <b>server-shutdown-started</b> <b>unable-to-register</b>

## Appendix A. Attribute-to-Object Listing

<i>Attribute</i>	<i>Objects</i>	<i>See Page</i>
<b>accept-jobs</b>	Actual destination	332
<b>accept-unsupported-jobs</b>	Server	623
<b>account-text</b>	Default document Document	453 453
<b>accounting-exit</b>	Actual destination	332
<b>ack-interval</b>	Actual destination	333
<b>actual-destinations-assigned</b>	Queue	610
<b>actual-destinations-ready</b>	Queue Server	610 624
<b>actual-destinations-requested</b>	Default job Job	524 524
<b>actual-destinations-supported</b>	Server	624
<b>add-carriage-returns</b>	Actual destination	334
<b>add-line-feeds</b>	Actual destination	334
<b>address1-text</b>	Default document Document	454 454
<b>address2-text</b>	Default document Document	454 454
<b>address3-text</b>	Default document Document	455 455
<b>address4-text</b>	Default document Document	455 455
<b>ascii-character-map</b>	Actual destination	335
<b>ascii-font-map</b>	Actual destination	335
<b>assign-to-destination</b>	Queue	611
<b>assign-to-printer</b>	Queue	611
<b>associated-queue</b>	Actual destination Logical destination	336 579
<b>associated-server</b>	Actual destination Auxiliary sheet Default document Default job Log Logical destination Medium Queue Resource context Transform	337 443 456 525 573 579 604 611 620 645
<b>attachment-type</b>	Actual destination	337
<b>attribute-map</b>	Actual destination	338
<b>audit-exit</b>	Actual destination	339
<b>authorize-jobs</b>	Logical destination	580
<b>auto-create-shared-printers</b>	Server	580
<b>automatic-postscript-mode-switch</b>	Actual destination	625

<b>Attribute</b>	<b>Objects</b>	<b>See Page</b>
<b>auxiliary-sheet-identifier</b>	Auxiliary sheet	443
<b>auxiliary-sheet-selection</b>	Default job Job	525 525
<b>auxiliary-sheet-selections-supported</b>	Actual destination Logical destination	340 580
<b>backlog</b>	Queue	618
<b>backlog-lower-bound</b>	Queue	612
<b>backlog-update-interval</b>	Queue	612
<b>backlog-upper-bound</b>	Queue	613
<b>backlogged</b>	Queue	613
<b>base-printer</b>	Default Document Document	456 456
<b>bits-per-spot</b>	Default document Document	457 457
<b>black-overprint</b>	Default document Document	457 457
<b>booklet-fold</b>	Actual destination	341
<b>building-text</b>	Default document Document	458 458
<b>cancel-individual-document-supported</b>	Actual destination Server	341 625
<b>callback-number</b>	Default document Document	458 458
<b>carriage-control-type</b>	Default document Document	458 458
<b>carriage-control-types-supported</b>	Actual destination Logical destination	341 581
<b>character-mappings-supported</b>	Actual destination Logical destination	342 581
<b>chars</b>	Default document Document	459 459
<b>checkpoint-at-stacker</b>	Actual destination	343
<b>checkpoint-formats-supported</b>	Actual destination	343
<b>cms-proclink</b>	Default document Document	460 460
<b>cms-product</b>	Default document Document	460 460
<b>color-mapping-table</b>	Actual destination Default document Document	344 461 461
<b>command</b>	Actual destination	349
<b>color-rip-servers</b>	Actual destination	344
<b>comment</b>	Default job Job	536 536
<b>completion-time</b>	Job	526

<b>Attribute</b>	<b>Objects</b>	<b>See Page</b>
<b>compressed-output</b>	Default document	461
	Document	461
<b>connection-timeout</b>	Actual destination	345
<b>content-orientation</b>	Default document	462
	Document	462
<b>content-orientations-supported</b>	Actual destination	345
	Logical destination	581
<b>context-address</b>	Resource context	621
<b>control-strip</b>	Default document	462
	Document	462
<b>convert-to-ebcdic</b>	Default document	463
	Document	463
<b>convert-to-ebcdic-supported</b>	Actual destination	346
	Logical destination	582
<b>copies</b>	Default document	463
	Document	463
<b>copy-count</b>	Default document	463
	Document	463
<b>current-backlog</b>	Queue	618
<b>current-job-state</b>	Job	526
<b>current-page-printing</b>	Job	527
<b>d-s-s-requested</b>	Default job	532
	Job	532
<b>data-fidelity-problem-reported</b>	Default document	464
	Document	464
<b>data-fidelity-problem-reported-supported</b>	Actual destination	346
	Logical destination	583
<b>deadline-in-jeopardy</b>	Job	528
<b>default-character-mapping</b>	Default document	464
	Document	464
<b>default-font-fidelity-action</b>	Actual destination	347
<b>default-font-resolution</b>	Actual destination	347
<b>default-input-tray</b>	Actual destination	348
	Default document	465
	Document	465
<b>default-medium</b>	Default document	466
	Document	466
<b>default-printer-resolution</b>	Default document	467
	Document	467
<b>delete-segment-list</b>	Default job	528
	Job	528
<b>department-text</b>	Default document	467
	Document	467

<b>Attribute</b>	<b>Objects</b>	<b>See Page</b>
<b>descriptor</b>	Actual destination	348
	Auxiliary sheet	444
	Default document	468
	Default job	529
	Log	573
	Logical destination	583
	Medium	605
	Queue	613
	Resource context	621
	Server	625
	Transform	645
<b>destination-associated-destinations</b>	Logical destination	584
<b>destination-command</b>	Actual destination	349
<b>destination-company-text</b>	Default document	468
	Document	468
<b>destination-data-stream</b>	Actual destination	350
<b>destination-initial-value-document</b>	Document	468
	Logical destination	584
<b>destination-initial-value-job</b>	Job	529
	Logical destination	584
<b>destination-locations</b>	Actual destination	351
	Logical destination	585
<b>destination-locations-requested</b>	Default job	530
	Job	530
<b>destination-model</b>	Actual destination	351
	Logical destination	585
<b>destination-models-requested</b>	Default job	530
	Job	530
<b>destination-name</b>	Actual destination	352
	Logical destination	585
<b>destination-name-requested</b>	Job	531
<b>destination-needs-attention-time</b>	Actual destination	353
<b>destination-needs-key-operator-attention-time</b>	Actual destination	353
<b>destination-pass-through</b>	Actual destination	353
	Default document	469
	Document	469
<b>destination-poll-interval</b>	Actual destination	354
<b>destination-realization</b>	Actual destination	354
	Logical destination	586
<b>destination-register-threshold</b>	Actual destination	355
<b>destination-release-timer</b>	Actual destination	355
<b>destination-state</b>	Actual destination	356
<b>destination-states-supported</b>	Server	626
<b>destination-support-system</b>	Actual destination	357
	Logical destination	586
<b>destination-support-systems-supported</b>	Server	626
<b>destination-tcpip-internet-address</b>	Actual destination	358

<b>Attribute</b>	<b>Objects</b>	<b>See Page</b>
<b>destination-tcpip-port-number</b>	Actual destination	359
<b>destination-timeout-period</b>	Actual destination	359
<b>destinations-assigned</b>	Job	531
<b>destinations-ready</b>	Logical destination	587
<b>destinations-used</b>	Job	532
<b>device-name</b>	Actual destination	360
<b>device-support-system</b>	Actual destination Logical destination	357 586
<b>device-support-system-requested</b>	Default job Job	532 532
<b>discard-time</b>	Job	538
<b>document-attributes-supported</b>	Actual destination Server	361 627
<b>document-comment</b>	Default document Document	469 469
<b>document-content</b>	Document	469
<b>document-content-list</b>	Document	470
<b>document-file-name</b>	Document	470
<b>document-finishing</b>	Default document Document	470 470
<b>document-finishings-supported</b>	Actual destination	363
<b>document-format</b>	Default document Document	471 471
<b>document-formats-ripped-at-destination</b>	Actual destination Logical destination	364 587
<b>document-formats-supported</b>	Actual destination Logical destination Transform	364 587 646
<b>document-number</b>	Document	472
<b>document-sequence-number</b>	Document	472
<b>document-type</b>	Document	472
<b>document-types-supported</b>	Actual destination Logical destination	366 588
<b>dot-shape</b>	Default document Document	474 474
<b>dss-job-message-disposition</b>	Actual destination	367
<b>dss-job-message-log-size</b>	Actual destination	367
<b>dss-job-message-log-wrap</b>	Actual destination	368
<b>dss-requested</b>	Default job Job	532 532
<b>ebcdic-character-mapping</b>	Actual destination	368
<b>email-from-address</b>	Default document Document	475 475
<b>email-to-address</b>	Default document Document	475 475

<b>Attribute</b>	<b>Objects</b>	<b>See Page</b>
<b>enable-settrap</b>	Default document	476
	Document	476
<b>enabled</b>	Actual destination	369
	Log	574
	Logical destination	588
<b>end-message</b>	Default job	539
	Job	539
<b>end-message-supported</b>	Actual destination	369
	Logical destination	589
<b>end-sheets-supported</b>	Actual destination	370
<b>estimated-completion-time</b>	Job	533
<b>estimated-processing-time</b>	Job	534
<b>events-supported</b>	Server	627
<b>fax-number</b>	Default document	476
	Document	476
<b>fax-to-name</b>	Default document	476
	Document	476
<b>file-name</b>	Document	470
<b>font-fidelity-action</b>	Default document	477
	Document	477
<b>font-processing-messages</b>	Default document	477
	Document	477
<b>font-resolution</b>	Default document	478
	Document	478
<b>font-resolutions-supported</b>	Actual destination	370
<b>force-destination-setup</b>	Actual destination	371
<b>force-printer-setup</b>	Actual destination	371
<b>form-definition</b>	Actual destination	372
	Default document	478
	Document	478
<b>format</b>	Default document	471
	Document	471
<b>formatted-job-ticket-content</b>	Job	534
<b>global-id</b>	Job	541
<b>halftone</b>	Default document	479
	Document	479
<b>halftones-supported</b>	Actual destination	372
<b>hold</b>	Default job	540
	Job	540
<b>hostname</b>	Server	640
<b>i-p-address</b>	Server	640
<b>ip-address</b>	Server	640
<b>image-center-x</b>	Default document	480
	Document	480
<b>image-center-y</b>	Default document	481
	Document	481



<b>Attribute</b>	<b>Objects</b>	<b>See Page</b>
<b>image-fit</b>	Default document	481
	Document	481
<b>image-fit-supported</b>	Actual destination	374
<b>image-length</b>	Actual destination	374
	Default document	482
	Document	482
<b>image-out-format</b>	Default document	483
	Document	483
<b>image-out-formats-supported</b>	Actual destination	375
	Logical destination	589
<b>image-scale</b>	Default document	483
	Document	483
<b>image-width</b>	Actual destination	376
	Default document	484
	Document	484
<b>initial-value-document</b>	Document	485
<b>initial-value-document-identifier</b>	Default document	485
<b>initial-value-job</b>	Job	535
<b>initial-value-job-identifier</b>	Default job	535
<b>input-data-user-exit</b>	Actual destination	377
<b>input-exit</b>	Default document	486
	Document	486
<b>input-tray-select</b>	Default document	487
	Document	487
<b>input-trays-medium</b>	Actual destination	377
<b>input-trays-supported</b>	Actual destination	379
	Logical destination	590
<b>intervening-jobs</b>	Job	535
<b>intervention-timer</b>	Actual destination	379
<b>ip-address</b>	Server	640
<b>job-attributes-supported</b>	Actual destination	380
	Server	629
<b>job-batch</b>	Default job	536
	Job	536
<b>job-batches-ready</b>	Actual destination	380
<b>job-client-id</b>	Job	536
<b>job-comment</b>	Default job	536
	Job	536
<b>job-complexity</b>	Default job	537
	Job	537
<b>job-copies-completed</b>	Job	537
<b>job-deadline-time</b>	Job	538
<b>job-discard-time</b>	Job	538
<b>job-end-message</b>	Default job	539
	Job	539

<b>Attribute</b>	<b>Objects</b>	<b>See Page</b>
<b>job-finishing</b>	Default job	539
	Job	539
<b>job-finishings-supported</b>	Actual destination	381
<b>job-hold</b>	Default job	540
	Job	540
<b>job-identifier</b>	Job	541
<b>job-log</b>	Job	541
<b>job-media-sheet-count</b>	Job	542
<b>job-message-from-administrator</b>	Job	542
<b>job-message-to-operator</b>	Default job	543
	Job	543
<b>job-name</b>	Default job	543
	Job	543
<b>job-originator</b>	Job	544
<b>job-owner</b>	Job	544
<b>job-page-count</b>	Job	545
<b>job-print-after</b>	Job	545
<b>job-priority</b>	Default job	546
	Job	546
<b>job-retain-until</b>	Job	546
<b>job-retention-period</b>	Default job	547
	Job	547
<b>job-retry-count-limit</b>	Actual destination	381
<b>job-retry-interval</b>	Actual destination	382
<b>job-rip-action</b>	Default job	547
	Job	547
<b>job-rip-actions-supported</b>	Actual destination	382
<b>job-ripped-by-server</b>	Default job	548
	Job	548
<b>job-size</b>	Job	571
<b>job-size-range-ready</b>	Actual destination	383
<b>job-size-range-supported</b>	Actual destination	384
	Logical destination	590
<b>job-start-message</b>	Default job	551
	Job	551
<b>job-start-wait</b>	Default job	552
	Job	552
<b>job-start-wait-supported</b>	Actual destination	385
<b>job-state</b>	Job	526
<b>job-state-reasons</b>	Job	552
<b>job-state-reasons-supported</b>	Server	629
<b>job-states-supported</b>	Server	630
<b>job-submission-complete</b>	Job	554
<b>job-submission-timer</b>	Server	630

<b>Attribute</b>	<b>Objects</b>	<b>See Page</b>
<b>job-ticket-content</b>	Job	534
<b>jog-between-job-copies</b>	Default document Document	487 487
<b>last-accessor</b>	Job	557
<b>last-modifier</b>	Job	557
<b>list-of-managers</b>	Actual destination Default document Default job Logical destination Queue Server	385 487 554 591 614 630
<b>locale</b>	Server	631
<b>locations</b>	Actual destination Logical destination	351 585
<b>locations-requested</b>	Default job Job	530 530
<b>log-accounting data</b>	Actual destination Server	386 631
<b>log-address</b>	Log	574
<b>log-identifier</b>	Log	574
<b>log-messages</b>	Log	575
<b>log-severity</b>	Log	575
<b>log-size</b>	Log	576
<b>log-trace-groups</b>	Log	576
<b>log-type</b>	Log	576
<b>log-wrap</b>	Log	577
<b>logical-destinations-assigned</b>	Actual destination Queue	387 614
<b>logical-destinations-ready</b>	Default document Default job Queue Server	488 555 614 632
<b>logical-destinations-supported</b>	Server	632
<b>logical-printer</b>	Logical destination	585
<b>logical-printer-requested</b>	Job	531
<b>logical-printers-assigned</b>	Queue	614
<b>logical-printers-ready</b>	Default document Default job Queue Server	488 555 614 632
<b>logical-printers-supported</b>	Server	632
<b>managers</b>	Actual destination Default document Default job Logical destination Queue Server	385 487 554 591 614 630

<b>Attribute</b>	<b>Objects</b>	<b>See Page</b>
<b>maximum-barco-rips</b>	Server	633
<b>maximum-concurrent-jobs</b>	Actual destination	387
<b>maximum-copies-supported</b>	Actual destination Logical destination	388 592
<b>maximum-fonts-to-keep</b>	Actual destination	389
<b>maximum-messages-printed</b>	Default document Document	488 488
<b>maximum-non-raster-rips</b>	Server	633
<b>maximum-overlays-to-keep</b>	Actual destination	389
<b>maximum-raster-rips</b>	Server	633
<b>maximum-segments-to-keep</b>	Actual destination	390
<b>maximum-transform-pages-ahead</b>	Default document Document	489 489
<b>media-ready</b>	Actual destination	390
<b>media-sheet-count</b>	Job	542
<b>media-sheets-completed</b>	Job	556
<b>media-supported</b>	Actual destination Logical destination	391 592
<b>medium-color</b>	Medium	605
<b>medium-dimensions</b>	Medium	605
<b>medium-form-parts</b>	Medium	606
<b>medium-holes-count</b>	Medium	606
<b>medium-identifier</b>	Medium	607
<b>medium-sides</b>	Medium	607
<b>medium-size</b>	Medium	608
<b>medium-type</b>	Medium	608
<b>medium-weight</b>	Medium	609
<b>message</b>	Actual destination Default document Default job Logical destination Medium Queue Server	392 489 556 593 609 615 634
<b>message-font-type</b>	Actual destination	393
<b>message-form-definition</b>	Actual destination	393
<b>message-from-administrator</b>	Job	542
<b>message-to-operator</b>	Default job Job	543 543
<b>model</b>	Actual destination Logical destination	351 585
<b>models-requested</b>	Default job Job	530 530
<b>modification-time</b>	Job	557
<b>modify-individual-document-supported</b>	Server	634

<b>Attribute</b>	<b>Objects</b>	<b>See Page</b>
<b>multiple-documents-supported</b>	Server	634
<b>mvs-class</b>	Default document Document	489 489
<b>mvs-destination</b>	Default document Document	490 490
<b>mvs-forms</b>	Default document Document	490 490
<b>mvs-segment-id</b>	Default document Document	491 491
<b>name</b>	Default job Job	543 543
<b>name-of-last-accessor</b>	Job	557
<b>name-text</b>	Default document Document	491 491
<b>new-job-identifier</b>	Job	557
<b>new-line-option</b>	Default document Document	492 492
<b>node-id-text</b>	Default document Document	492 492
<b>non-process-runout-timer</b>	Actual destination	394
<b>notification-delivery-methods-supported</b>	Server	634
<b>notification-profile</b>	Actual destination Default job Job Logical destination Queue Server	394 558 558 593 615 635
<b>notify-operator</b>	Actual destination Queue	396 616
<b>npm-server-ip-address</b>	Server	636
<b>npm-server-port-number</b>	Server	637
<b>nt-drivers</b>	Logical destination	601
<b>number-of-documents</b>	Job	560
<b>number-up</b>	Default document Document	493 493
<b>number-up-supported</b>	Actual destination	396
<b>object-class</b>	Actual destination Auxiliary sheet Default document Document Default job Job Log Logical destination Medium Queue Resource context Server Server	397 444 493 493 560 560 577 595 609 617 621 637 646

<b>Attribute</b>	<b>Objects</b>	<b>See Page</b>
<b>object-classes-supported</b>	Server	637
<b>octet-count</b>	Document	494
<b>octets-completed</b>	Job	561
<b>offset-stacking-available</b>	Actual destination	397
<b>offset-stacking-between-jobs</b>	Default document	494
	Document	494
<b>operators</b>	Actual destination	396
	Queue	616
<b>optimize-for-multiple-copies</b>	Actual destination	398
	Default job	561
	Job	561
<b>orientation</b>	Default document	462
	Document	462
<b>orientations-supported</b>	Actual destination	345
	Logical destination	581
<b>originating-company-text</b>	Default document	494
	Document	494
<b>originator</b>	Job	544
<b>os2-driver-names</b>	Logical destination	595
<b>os2-drivers</b>	Logical destination	595
<b>other-options</b>	Actual destination	353
	Default document	469
	Document	469
<b>other-transform-options</b>	Default document	495
	Document	495
	Transform	647
<b>output-appearance</b>	Default document	495
	Document	495
<b>output-appearances-supported</b>	Actual destination	399
<b>output-bin</b>	Actual destination	399
	Default document	495
	Document	495
<b>output-bin-numbers</b>	Actual destination	400
<b>output-bins-supported</b>	Actual destination	401
<b>output-data-user-exit</b>	Actual destination	402
<b>output-document-format</b>	Transform	648
<b>output-face-up</b>	Default document	496
	Document	496
<b>output-format</b>	Default document	497
	Document	497
<b>output-format-supported</b>	Actual destination	402
<b>overlay</b>	Actual destination	403
	Default document	498
	Document	498
<b>overlay-back</b>	Default document	499
	Document	499

<b>Attribute</b>	<b>Objects</b>	<b>See Page</b>
<b>overlay-front</b>	Default document	499
	Document	499
<b>overprint</b>	Default document	500
	Document	500
<b>owner</b>	Job	544
<b>page-clip</b>	Default document	500
	Document	500
<b>page-count</b>	Document	501
<b>page-definition</b>	Default document	501
	Document	501
<b>page-media-select</b>	Default document	502
	Document	502
<b>page-select</b>	Document	502
<b>page-select-supported</b>	Actual destination	403
	Logical destination	596
<b>pages-completed</b>	Job	562
<b>pcl-server-address</b>	Actual destination	404
<b>pcl-server-port</b>	Actual destination	404
<b>physical-printer</b>	Actual destination	352
<b>physical-printers-assigned</b>	Queue	610
<b>physical-printers-ready</b>	Queue	610
	Server	624
<b>physical-printers-requested</b>	Default job	524
	Job	524
<b>physical-printers-supported</b>	Server	624
<b>plex</b>	Actual destination	405
	Default document	503
	Document	503
<b>plexes-supported</b>	Actual destination	405
	Logical destination	597
<b>position-in-queue</b>	Job	535
<b>postscript-server-address</b>	Actual destination	406
<b>postscript-server-port</b>	Actual destination	407
<b>presentation-fidelity-problem-reported</b>	Actual destination	407
<b>previous-job-state</b>	Job	563
<b>previous-state</b>	Job	563
<b>print-after</b>	Job	545
<b>print-edge-marks</b>	Actual destination	408
<b>print-qualities-supported</b>	Actual destination	408
	Logical destination	597
<b>print-quality</b>	Default document	504
	Document	504
<b>print-queue</b>	Actual destination	409
<b>print-queue-name</b>	Actual destination	409

<b>Attribute</b>	<b>Objects</b>	<b>See Page</b>
<b>printer</b>	Actual destination	352
	Logical destination	585
<b>printer-associated-printers</b>	Logical destination	584
<b>printer-command</b>	Actual destination	349
<b>printer-data-stream</b>	Actual destination	350
<b>printer-end-sheet</b>	Actual destination	409
<b>printer-escape-codes</b>	Actual destination	410
<b>printer-initial-value-document</b>	Document	468
	Logical destination	584
<b>printer-initial-value-job</b>	Job	529
	Logical destination	584
<b>printer-locations</b>	Actual destination	351
	Logical destination	585
<b>printer-locations-requested</b>	Default job	530
	Job	530
<b>printer-memory</b>	Actual destination	411
<b>printer-model</b>	Actual destination	351
	Logical destination	585
<b>printer-models-requested</b>	Default job	530
	Job	530
<b>printer-name</b>	Actual destination	352
	Logical destination	585
<b>printer-name-requested</b>	Default job	531
	Job	531
<b>printer-needs-attention-time</b>	Actual destination	353
<b>printer-needs-key-operator-attention-time</b>	Actual destination	353
<b>printer-pass-through</b>	Actual destination	353
	Default document	469
	Document	469
<b>printer-realization</b>	Actual destination	354
	Logical destination	586
<b>printer-register-threshold</b>	Actual destination	355
<b>printer-release-timer</b>	Actual destination	355
<b>printer-requested</b>	Default job	531
	Job	531
<b>printer-resolutions-ready</b>	Actual destination	412
<b>printer-resolutions-supported</b>	Actual destination	413
<b>printer-separator-sheet</b>	Actual destination	414
<b>printer-start-sheet</b>	Actual destination	414
<b>printer-state</b>	Actual destination	356
<b>printer-states-supported</b>	Server	626
<b>printer-s370-channel-device-address</b>	Actual destination	416
<b>printer-s370-channel-slot-number</b>	Actual destination	416
<b>printer-tcpip-internet-address</b>	Actual destination	358
<b>printer-tcpip-port-number</b>	Actual destination	359



<b>Attribute</b>	<b>Objects</b>	<b>See Page</b>
<b>printer-timeout-period</b>	Actual destination	417
<b>printers-assigned</b>	Job	531
<b>printers-ready</b>	Logical destination	587
<b>printers-used</b>	Job	532
<b>problem-child</b>	Server	638
<b>problem-message</b>	Actual destination	417
<b>processing-time</b>	Job	564
<b>programmer-text</b>	Default document Document	504 504
<b>protected-attributes</b>	Actual destination Logical destination Queue Server	417 598 618 638
<b>psf-exit-form-definition</b>	Auxiliary sheet	444
<b>psf-exit-page-mark</b>	Auxiliary sheet	444
<b>psf-exit-program-name</b>	Auxiliary sheet	445
<b>psf-tray-characteristics</b>	Actual destination	418
<b>qualities-supported</b>	Actual destination Logical destination	408 597
<b>queue-assigned</b>	Job	565
<b>queue-backlog</b>	Queue	618
<b>queue-name</b>	Queue	618
<b>queue-position</b>	Job	535
<b>queue-state</b>	Queue	618
<b>queues-supported</b>	Server	639
<b>reasons</b>	Job	552
<b>register-threshold</b>	Actual destination	355
<b>registered-with-spooler</b>	Actual destination	421
<b>remote-queue</b>	Actual destination	421
<b>requeue-failed-jobs</b>	Queue	619
<b>required-resources-not-ready</b>	Job	565
<b>required-resources-not-supported</b>	Job	566
<b>resource-context</b>	Actual destination Default document Document	422 505 505
<b>resource-context-font</b>	Actual destination Default document Document	423 506 506
<b>resource-context-form-definition</b>	Actual destination Default document Document	424 507 507
<b>resource-context-identifier</b>	Resource context	622
<b>resource-context-overlay</b>	Actual destination Default document Document	425 508 508

<b>Attribute</b>	<b>Objects</b>	<b>See Page</b>
<b>resource-context-page-definition</b>	Actual destination	426
	Default document	509
	Document	509
<b>resource-context-page-segment</b>	Actual destination	427
	Default document	509
	Document	509
<b>resource-context-user</b>	Default document	510
	Document	510
<b>resource-exit</b>	Default document	511
	Document	511
<b>results-profile</b>	Default job	566
	Job	566
<b>retained-time</b>	Job	566
<b>retention-period</b>	Default job	547
	Job	547
<b>reverse-output</b>	Actual destination	428
<b>rip-ini-file</b>	Actual destination	428
<b>rip-server</b>	Actual destination	429
<b>room-text</b>	Default document	512
	Document	
<b>save-rip-files</b>	Server	639
<b>scanner-correction</b>	Default document	512
	Document	512
<b>scanner-corrections-supported</b>	Actual destination	429
<b>scheduler-sort-primary-order</b>	Actual destination	429
<b>scheduler-sort-secondary-order</b>	Actual destination	430
<b>schedulers-supported</b>	Actual destination	430
<b>screen-frequencies-supported</b>	Actual destination	431
<b>screen-frequency</b>	Default document	513
	Document	
<b>security-level</b>	Server	639
<b>segment-file-size</b>	Default document	513
	Document	513
<b>separator-sheets-supported</b>	Actual destination	431
<b>sequence-number</b>	Document	472
<b>server-hostname</b>	Server	640
<b>server-ip-address</b>	Server	640
<b>server-name</b>	Server	641
<b>server-state</b>	Server	641
<b>shared-formdef</b>	Default document	514
	Document	514
<b>shared-printer-name</b>	Actual destination	432
<b>shift-out-shift-in</b>	Default document	514
	Document	514

<b>Attribute</b>	<b>Objects</b>	<b>See Page</b>
<b>sides</b>	Actual destination	433
	Default document	515
	Document	515
<b>sides-supported</b>	Actual destination	433
	Logical destination	598
<b>smtp-server-host</b>	Server	641
<b>smtp-server-port-number</b>	Server	642
<b>snmp-active</b>	Actual destination	434
<b>snmp-aix-printer-models</b>	Server	642
<b>snmp-community-name</b>	Actual destination	434
<b>snmp-discovery-during-stamp</b>	Server	642
<b>snmp-normal-poll-interval</b>	Server	643
<b>snmp-problem-poll-interval</b>	Server	643
<b>snmp-retry-count</b>	Actual destination	435
<b>snmp-timeout</b>	Actual destination	435
<b>start-message</b>	Default job	551
	Job	551
<b>start-message-supported</b>	Actual destination	436
	Logical destination	599
<b>start-on-new-sheet</b>	Default document	516
	Document	516
<b>start-sheets-supported</b>	Actual destination	436
<b>started-printing-time</b>	Job	568
<b>state-reasons</b>	Job	552
<b>subject-text</b>	Default document	516
	Document	516
<b>submission-time</b>	Job	568
<b>table-reference-characters</b>	Default document	516
	Document	516
<b>table-reference-characters-supported</b>	Actual destination	437
	Logical destination	599
<b>tape-exit</b>	Job	569
<b>tape-format</b>	Job	569
<b>tape-labeled</b>	Job	570
<b>tape-max-block-size</b>	Job	570
<b>tape-rewind-before</b>	Job	570
<b>tape-rewind-unload</b>	Job	571
<b>terminating-transform</b>	Transform	649
<b>ticket-content</b>	Job	534
<b>timeout-period</b>	Actual destination	417
<b>title-text</b>	Default document	517
	Document	517
<b>total-job-octets</b>	Job	571
<b>transfer-method</b>	Document	518

<b>Attribute</b>	<b>Objects</b>	<b>See Page</b>
<b>transfer-methods-supported</b>	Server	644
<b>transform-identifier</b>	Transform	649
<b>transform-library</b>	Transform	650
<b>transform-message-file-name</b>	Default document Document	518 518
<b>transform-output-file-name</b>	Default document Document	518 518
<b>transform-sequence</b>	Actual destination	438
<b>type</b>	Document	472
<b>use-snmp</b>	Actual destination	438
<b>user-id-text</b>	Default document Document	519 519
<b>user-locale</b>	Job	572
<b>user-name</b>	Job	572
<b>wait-for-job-completion</b>	Actual destination	439
<b>warning-message</b>	Actual destination	439
<b>windows-driver-names</b>	Logical destination	600
<b>windows-drivers</b>	Logical destination Server	600 644
<b>windows-nt-driver-names</b>	Actual destination Logical destination Server	440 601 644
<b>windows-nt-drivers</b>	Logical destination Server	601 644
<b>x-image-shift</b>	Default document Document	519 519
<b>x-image-shift-back</b>	Default document Document	520 520
<b>x-image-shift-range-supported</b>	Actual destination Logical destination	440 601
<b>y-image-shift</b>	Default document Document	521 521
<b>y-image-shift-back</b>	Default document Document	521 521
<b>y-image-shift-range-supported</b>	Actual destination Logical destination	441 602

## Appendix B. Migrating PSF for AIX Job Script Keywords to Infoprint Equivalents

Table 20 and Table 21 on page 693 list the PSF for AIX job script keywords that the **jsmigr** utility (see “jsmigr Utility: Migrates PSF for AIX Job Scripts in Infoprint Manager for AIX” on page 148) migrates to Infoprint document and job attributes, or to flags and arguments of the **pdpr** command.

### Notes:

1. See “jsmigr Utility: Migrates PSF for AIX Job Scripts in Infoprint Manager for AIX” on page 148 for notes on migration.
2. Keywords not listed in this table have no equivalent.

Table 20. PSF for AIX Keywords Used in Job Script Files and Infoprint Equivalents

<b>PSF Keyword</b>	<b>Infoprint Attribute, Flag, or Argument</b>
<b>a_Cc</b> <b>a_Cctype</b>	<b>carriage-control-type</b>
<b>Note:</b> <b>cc</b> and <b>cctype</b> are examined together to generate <b>carriage-control-type</b> . If <b>jsmigr</b> encounters <b>cctype</b> before <b>cc</b> , it assumes the default value of <b>yes</b> for <b>cc</b> .	
<b>a_Chars</b>	<b>chars</b>
<b>a_Fileformat</b>	<b>new-line-option</b>
<b>a_Imageout</b>	<b>image-out-format</b>
<b>a_InpExit</b>	<b>input-exit</b>
<b>a_OtherOptions</b>	<b>other-transform-options</b>
<b>a_Pagedef</b>	<b>page-definition</b>
<b>a_Parmdd</b>	Attributes file
<b>a_Pdeflib</b>	<b>resource-context-page-definition</b>
<b>a_Prmode</b>	<b>shift-out-shift-in</b>
<b>a_Trnc</b>	<b>table-reference-characters</b>
<b>db_euc</b> <b>db_language</b>	<b>default-character-mapping</b>
<b>Note:</b> <b>db_euc</b> and <b>db_language</b> must be used together to generate <b>default-character-mapping</b> .	
<b>e_ConsoleMsg</b>	<b>job-start-message</b> <b>job-start-wait</b>
<b>e_FileMsg</b>	<b>job-start-message</b> <b>job-start-wait</b>
<b>e_Notify</b>	<b>notification-profile</b> ( <b>delivery-method</b> component)
<b>e_PrintQueue</b>	<b>-p</b> flag of <b>pdpr</b> command
<b>e_Priority</b>	<b>job-priority</b>
<b>i_Exit</b>	<b>tape-exit</b>
<b>i_Filenames</b>	Job scripts invoked by this keyword (extension <b>.js</b> ) are migrated to attributes files invoked with the <b>-X</b> flag of the <b>pdpr</b> command. Print files are migrated to arguments of the <b>pdpr</b> command in the <b>pdpr</b> script.
<b>i_Fileformat</b>	<b>new-line-option</b>
<b>i_Format</b>	No equivalent

Table 20. PSF for AIX Keywords Used in Job Script Files and Infoprint  
Equivalents (continued)

<b>PSF Keyword</b>	<b>Infoprint Attribute, Flag, or Argument</b>
<b>i_InputDevice</b>	<b>-f, -T, or -</b> flag of <b>pdpr</b> command
<b>i_Labeled</b>	<b>tape-labeled</b>
<b>i_MaxBlockSize</b>	<b>tape-max-block-size</b>
<b>i_OutExit</b>	No equivalent
<b>i_PgsAhead</b>	<b>maximum-transform-pages-ahead</b>
<b>i_RewindBefore</b>	<b>tape-rewind-before</b>
<b>i_RewindUnload</b>	<b>tape-rewind-unload</b>
<b>JsFileType</b>	<b>document-format</b>
<b>oa_Formdef</b>	<b>form-definition</b>
<b>oa_SrchAFP</b>	<b>resource-context</b>
<b>oa_SrchFd</b>	<b>resource-context-form-definition</b>
<b>oa_SrchOvly</b>	<b>resource-context-overlay</b>
<b>oa_SrchPs</b>	<b>resource-context-page-segment</b>
<b>oa_SrchFO</b>	<b>resource-context-font</b>
<b>oa_SrchSf</b>	No equivalent
<b>o_Account</b>	<b>account-text</b>
<b>o_Address1</b>	<b>address1-text</b>
<b>o_Address2</b>	<b>address2-text</b>
<b>o_Address3</b>	<b>address3-text</b>
<b>o_Address3</b>	<b>address3-text</b>
<b>o_Bin</b>	<b>destination-pass-through</b> to <b>ainbe</b>
<b>o_Building</b>	<b>building-text</b>
<b>o_Codeset</b>	<b>default-character-mapping</b>
<b>o_Copies</b>	<b>results-profile</b> ( <b>job-copies</b> component)
<b>o_DataCk</b>	<b>data-fidelity-problem-reported</b>
<b>o_Department</b>	<b>department-text</b>
<b>o_Distribution</b>	<b>results-profile</b> ( <b>delivery-address</b> component)
<b>o_Duplex</b>	<b>plex</b> <b>sides</b>
<b>o_Header</b>	<b>auxiliary-sheet-selection</b>
<b>Note: o_Header, o_Separator, and o_Trailer are examined together to generate auxiliary-sheet-selection.</b>	
<b>o_JobName</b>	<b>job-name</b>
<b>o_MsgCount</b>	<b>maximum-messages-printed</b>
<b>o_Name</b>	<b>name-text</b>
<b>o_Nodeid</b>	<b>node-id-text</b>
<b>o_Outbin</b>	<b>output-bin</b>
<b>o_Overlay</b>	<b>overlay</b>

Table 20. PSF for AIX Keywords Used in Job Script Files and Infoprint Equivalents (continued)

<b>PSF Keyword</b>	<b>Infoprint Attribute, Flag, or Argument</b>
<b>o_PassThru</b>	<b>mvs-class</b> <b>mvs-dest</b> <b>mvs-forms</b> <b>mvs-segment-id</b>
<b>o_Programmer</b>	<b>programmer-text</b>
<b>o_Room</b>	<b>room-text</b>
<b>o_Separator</b>	<b>auxiliary-sheet-selection</b>
<b>Note: o_Header, o_Separator, and o_Trailer are examined together to generate auxiliary-sheet-selection.</b>	
<b>o_SetupFile</b>	No equivalent
<b>o_Title</b>	<b>title-text</b>
<b>o_Trailer</b>	<b>auxiliary-sheet-selection</b>
<b>Note: o_Header, o_Separator, and o_Trailer are examined together to generate auxiliary-sheet-selection.</b>	
<b>o_Userid</b>	<b>user-id-text</b>
<b>o_Xoffset</b>	<b>x-image-shift</b>
<b>o_Yoffset</b>	<b>y-image-shift</b>
<b>p_Config</b>	Attributes file <b>other-transform-options</b>
<b>p_Length</b>	<b>image-length</b>
<b>p_OtherOptions</b>	<b>other-transform-options</b>
<b>p_OutputType</b>	<b>image-out-format</b>
<b>Note: There is no equivalent for some values of p_OutputType.</b>	
<b>p_Resolution</b>	<b>default-printer-resolution</b>
<b>p_Width</b>	<b>image-width</b>
<b>s_SegSize</b>	<b>segment-file-size</b>

Table 21. PSF for AIX Keywords Used in parmdd Files

<b>PSF Keyword</b>	<b>Infoprint Attribute, Flag, or Argument</b>
<b>cc</b> <b>cctype</b>	<b>carriage-control-type</b>
<b>Note: cc and cctype are examined together to generate carriage-control-type. If jsmigr encounters cctype before cc, it assumes the default value of yes for cc.</b>	
<b>chars</b>	<b>chars</b>
<b>fdeflib</b>	<b>resource-context-form-definition</b>
<b>fileformat</b>	<b>new-line-option</b>
<b>fontlib</b>	<b>resource-context-font</b>
<b>formdef</b>	<b>form-definition</b>
<b>imageout</b>	<b>image-out-format</b>
<b>inpexit</b>	<b>input-exit</b>
<b>inputdd</b>	No equivalent
<b>msgdd</b>	<b>transform-message-file-name</b>

Table 21. PSF for AIX Keywords Used in parmdd Files (continued)

<b>PSF Keyword</b>	<b>Infoprint Attribute, Flag, or Argument</b>
<b>outexit</b>	No equivalent
<b>outputdd</b>	<b>transform-output-file-name</b>
<b>ovlylib</b>	<b>resource-context-overlay</b>
<b>pagedef</b>	<b>page-definition</b>
<b>parmdd</b>	Attributes file
<b>pdeflib</b>	<b>resource-context-page-definition</b>
<b>prmode</b>	<b>shift-out-shift-in</b>
<b>pseglib</b>	<b>resource-context-page-segment</b>
<b>resexit</b>	<b>resource-exit</b>
<b>reslib</b>	<b>resource-context</b>
<b>trc</b>	<b>table-reference-characters</b>
<b>userlib</b>	<b>resource-context-user</b>



---

## Appendix C. Job Validation and Scheduling

Table 22 on page 696 and Table 23 on page 697 list the document, job, and destination attributes used to validate and schedule each job.

1. Infoprint validates the value of the document or job attribute in the first column against the values of the logical destination attribute in the second column. If the logical destination does not support the document or job attribute value, Infoprint rejects the job.

**Note:** If the logical destination attribute has no value, the logical destination supports all valid values of the document or job attribute.

2. If the value of the server attribute **accept-unsupported-jobs** is **false**, Infoprint validates the value of the document or job attribute in the first column against the values of the actual destination attribute in the second column. If no actual destination supports the document or job attribute value, Infoprint rejects the job.
3. If the value of the queue attribute **assign-to-destination** is **true**, Infoprint assigns the job to an actual destination that supports all the job's attribute values.

**Note:** If the value of the **force-destination-setup** actual destination attribute is **true**, Infoprint assumes that the actual destination supports all valid attribute values.

4. Infoprint checks the attribute (or, for rescheduling, the checkpoint) in the first column against the attributes in the third column to determine if any actual destinations can process the job.
  - If the job has been assigned to an actual destination, Infoprint checks only that actual destination.
  - If the job has not been assigned to an actual destination, Infoprint checks all actual destinations that receive jobs from the queue.

**Note:** If the value of the **force-destination-setup** actual destination attribute is **true**, Infoprint assumes that the actual destination can process any job with valid attribute values.

5. Infoprint acts according to the result of step 4:
  - If a required resource is not ready, Infoprint holds the job. The **required-resources-not-ready** job attribute indicates the resources that a job or document attribute specifies and that are not ready on the actual destination to which the job is assigned, or, if the job is not assigned, on the most suitable actual destination.
    - If the value of the job attribute **job-rip-action** is **rip-and-print-ignore-ready**, Infoprint RIPs the job before placing it in the **held** state and sets the value of the **job-state-reasons** job attribute to **rip-completed**. The job is automatically released and scheduled for printing or transmission when the resources become ready.
    - Otherwise, Infoprint sets the value of the **job-state-reasons** job attribute to **required-resource-not-ready**. You must release the job after making the resources ready. Infoprint will not release it automatically.
  - If a required resource is not supported, Infoprint holds the job and sets the value of the **job-state-reasons** job attribute to **required-resource-not-supported**. The **required-resources-not-supported** job attribute indicates the resources that a job or document attribute specifies and that are not

supported on the actual destination to which the job is assigned, or, if the job is not assigned, on the most suitable actual destination.

This situation can arise when the value of the server attribute **accept-unsupported-jobs** is **true** or when you change document, job, or actual destination attribute values after Infoprint accepts a job.

You can change job, document, or actual destination attribute values so that at least one actual destination supports the job. You must then release the job before it can be printed or transmitted. Infoprint will not release it automatically.

- If at least one actual destination can handle the job, Infoprint schedules the job for printing or transmission.
6. If the job has not already been assigned to an actual destination, Infoprint assigns it to the first suitable actual destination to become available after the job reaches the top of the queue.
  7. If the job is assigned to an actual destination with a value of **true** for the **force-destination-setup** attribute, Infoprint checks the attributes in the third column when the job is about to be printed or transmitted. If any resources are not ready or not supported, Infoprint disables the actual destination and sends a message to the operator. The operator changes the destination setup and enables the actual destination.
  8. The job is printed or transmitted.

Table 22. Document and Destination Attributes Used for Validation and Scheduling

<i>Document Attribute</i>	<i>Validation Attribute</i>	<i>Scheduling Attribute</i>
carriage-control-type	carriage-control-types-supported	carriage-control-types-supported
content-orientation	content-orientation-supported	content-orientation-supported
convert-to-ebcdic	convert-to-ebcdic-supported	convert-to-ebcdic-supported
copy-count	maximum-copies-supported	maximum-copies-supported
data-fidelity-problem-reported	data-fidelity-problem-reported-supported	data-fidelity-problem-reported-supported
default-character-mapping	character-mappings-supported	character-mappings-supported
default-input-tray	input-trays-supported	input-trays-supported
default-medium	media-supported	media-ready media-supported
default-printer-resolution	printer-resolutions-supported	printer-resolutions-ready printer-resolutions-supported
document-finishing	document-finishings-supported <sup>1</sup>	document-finishings-supported
document-format	document-formats-supported	document-formats-supported
document-type	document-types-supported	document-types-supported
font-resolution	font-resolutions-supported <sup>1</sup>	font-resolutions-supported
image-fit	image-fit-supported <sup>1</sup>	image-fit-supported
image-out-format	image-out-formats-supported	image-out-formats-supported
input-tray-select	input-trays-supported	input-trays-supported
number-up	number-up-supported <sup>1</sup>	number-up-supported
output-appearance	output-appearances-supported <sup>1</sup>	output-appearances-supported
output-bin	output-bins-supported <sup>1</sup>	output-bins-supported
output-format	output-formats-supported <sup>1</sup>	output-formats-supported
page-media-select	media-supported	media-ready media-supported

Table 22. Document and Destination Attributes Used for Validation and Scheduling (continued)

<b>Document Attribute</b>	<b>Validation Attribute</b>	<b>Scheduling Attribute</b>
page-select	page-select-supported	page-select-supported
plex	plexes-supported	plexes-supported
print-quality	print-qualities-supported	print-qualities-supported
scanner-correction	scanner-corrections-supported <sup>1</sup>	scanner-corrections-supported
screen-frequency	screen-frequencies-supported <sup>1</sup>	screen-frequencies-supported
sides	sides-supported	sides-supported
table-reference-characters	table-reference-characters-supported	table-reference-characters-supported
x-image-shift	x-image-shift-range-supported	x-image-shift-range-supported
x-image-shift-back	x-image-shift-range-supported	x-image-shift-range-supported
y-image-shift	y-image-shift-range-supported	y-image-shift-range-supported
y-image-shift-back	y-image-shift-range-supported	y-image-shift-range-supported
All document attributes affecting the actual destination	document-attributes-supported <sup>1</sup>	document-attributes-supported

1. This attribute applies only to actual destinations, not logical destinations.

Table 23. Job and Destination Attributes Used for Validation and Scheduling

<b>Job Attribute</b>	<b>Validation Attribute</b>	<b>Scheduling Attribute</b>
actual-destinations-requested	destination-name <sup>2</sup>	destination-name
auxiliary-sheet-selection	auxiliary-sheet-selections-supported	auxiliary-sheet-selections-supported
destination-locations-requested	destination-locations	destination-locations
destination-models-requested	destination-model	destination-model
dss-requested	destination-support-system	destination-support-system
job-batch		job-batches-ready
job-end-message	end-message-supported	end-message-supported
job-finishing	job-finishings-supported <sup>1</sup>	job-finishings-supported
job-rip-action	job-rip-actions-supported <sup>1</sup>	job-rip-actions-supported
job-start-message	start-message-supported	start-message-supported
job-start-wait	job-start-wait-supported <sup>1</sup>	job-start-wait-supported
total-job-octets	job-size-range-supported <sup>1</sup>	job-size-range-ready job-size-range-supported
All job attributes affecting the actual destination	job-attributes-supported <sup>1</sup>	job-attributes-supported
Checkpoint where the job was paused		checkpoint-formats-supported <sup>3</sup>

1. This attribute applies only to actual destinations, not logical destinations.  
2. This attribute applies to both logical destinations and actual destinations, but only the actual destination attribute is used for validation. If validation fails, Infoprint rejects the job even if the value of **accept-unsupported-jobs** is **true**.  
3. This attribute is used to reschedule paused jobs.



## Appendix D. Form Definitions and Page Definitions Supplied with Infoprint

This section describes the form definitions and page definitions that are supplied with Infoprint. Form definitions provide instructions on how printers position data on the page and are located in directory **/usr/lpp/psf/reslib**. Page definitions contain formatting controls for jobs and are also located in directory **/usr/lpp/psf/reslib**.

### Default Form Definitions

Default form definitions are determined by the output data stream format accepted by the printer that Infoprint assigns to print the job:

<i>Data Stream</i>	<i>Default Form Definition</i>
Intelligent Printer Data Stream (IPDS)	<b>F1ACIF</b>
Personal Printer Data Stream (PPDS)	<b>F1PP0110</b>
Printer Control Language 4 (PCL4)	<b>F1HP0111</b>
PCL5 and PCL5C	<b>F1H50111</b>

Table 24 describes the characteristics controlled by these form definitions.

Table 24. Default Form Definition Characteristics

<i>Form Definition</i>	<i>Bin</i>	<i>Sides</i>	<i>Presentation Mode</i>	<i>Print Direction</i>	<i>Page Position (in inches from the top-left corner of the page)</i>
<b>F1ACIF</b>	1	2	Portrait	Across	0.165, 0.165
<b>F1PP0110</b>	1	1	Portrait	Across	0.25, 0.165
<b>F1HP0111</b>	1	2	Portrait	Across	0.165, 0.2
<b>F1H50111</b>	1	2	Portrait	Across	0.165, 0.165

### General-Purpose Form Definitions

You can specify different form definitions with jobs if the default form definitions do not satisfy your requirements. Table 25 lists the general-purpose form definitions that you can select.

Table 25. General-Purpose Form Definitions

<i>Form Definition</i>	<i>Bin</i>	<i>Sides</i>	<i>Presentation Mode</i>	<i>Print Direction</i>	<i>Page Position (in inches from the top-left corner of the page)</i>
<b>F1A10110</b> <sup>1</sup>	1	1	Portrait	Across	0.165, 0.165
<b>F1A10111</b> <sup>1</sup>	1	2	Portrait	Across	0.165, 0.165
<b>F1A10112</b> <sup>1</sup>	1	Tumble	Portrait	Across	0.165, 0.165
<b>F1A10120</b> <sup>1</sup>	2	1	Portrait	Across	0.165, 0.165
<b>F1A10121</b> <sup>1</sup>	2	2	Portrait	Across	0.165, 0.165
<b>F1A10122</b> <sup>1</sup>	2	Tumble	Portrait	Across	0.165, 0.165
<b>F1A10130</b>	3	1	Portrait	Across	0.165, 0.165
<b>F1A10131</b>	3	2	Portrait	Across	0.165, 0.165
<b>F1A10132</b>	3	Tumble	Portrait	Across	0.165, 0.165
<b>F1A10140</b>	4	1	Portrait	Across	0.165, 0.165

Table 25. General-Purpose Form Definitions (continued)

<b>Form Definition</b>	<b>Bin</b>	<b>Sides</b>	<b>Presentation Mode</b>	<b>Print Direction</b>	<b>Page Position (in inches from the top-left corner of the page)</b>
<b>F1A10141</b>	4	2	Portrait	Across	0.165, 0.165
<b>F1A10142</b>	4	Tumble	Portrait	Across	0.165, 0.165
<b>F1A10150</b>	5	1	Portrait	Across	0.165, 0.165
<b>F1A10151</b>	5	2	Portrait	Across	0.165, 0.165
<b>F1A10152</b>	5	Tumble	Portrait	Across	0.165, 0.165
<b>F1ACIF</b> <sup>1</sup>	1	2	Portrait	Across	0.165, 0.165
<b>F1H50110</b> <sup>2</sup>	1	1	Portrait	Across	0.165, 0.165
<b>F1H50111</b> <sup>2</sup>	1	2	Portrait	Across	0.165, 0.165
<b>F1H50120</b> <sup>2</sup>	2	1	Portrait	Across	0.165, 0.165
<b>F1H50121</b> <sup>2</sup>	2	2	Portrait	Across	0.165, 0.165
<b>F1HP0110</b> <sup>3</sup>	1	1	Portrait	Across	0.165, 0.2
<b>F1HP0111</b> <sup>3</sup>	1	2	Portrait	Across	0.165, 0.2
<b>F1HP0120</b> <sup>3</sup>	2	1	Portrait	Across	0.165, 0.2
<b>F1HP0121</b> <sup>3</sup>	2	2	Portrait	Across	0.165, 0.2
<b>F1MG0110</b> <sup>4</sup>	1	1	Portrait	Across	0.33, 0.33
<b>F1MG0111</b> <sup>4</sup>	1	2	Portrait	Across	0.33, 0.33
<b>F1MG0120</b> <sup>4</sup>	2	1	Portrait	Across	0.33, 0.33
<b>F1MG0121</b> <sup>4</sup>	2	2	Portrait	Across	0.33, 0.33
<b>F1PP0110</b> <sup>5</sup>	1	1	Portrait	Across	0.25, 0.165
<b>F1PP0111</b> <sup>5</sup>	1	2	Portrait	Across	0.25, 0.165
<b>F1PP0120</b> <sup>5</sup>	2	1	Portrait	Across	0.25, 0.165
<b>F1PP0121</b> <sup>5</sup>	2	2	Portrait	Across	0.25, 0.165

1. Designed for use with IBM 3820, 3827, and 3835 printers.
2. These form definitions are recommended for printer devices that support the PCL5 and PCL5C data streams. They position the page of data so that the data is not placed in the unprintable area.
3. These form definitions are recommended for printer devices that support the PCL4 and PCL5 data streams. They position the page of data so that the data is not placed in the unprintable area.
4. These form definitions are recommended for the message pages printed by Infoprint supported printers.
5. These form definitions are recommended for printer devices that support the PPDS data stream. They position the page of data so that the data is not placed in the unprintable area.

## Form Definitions for Printing Envelopes

Use the form definitions in Table 26 to print envelopes and use the manual input bin on the IBM LaserPrinter 4028. You can use these form definitions with other printers that use bin 65 as the envelope bin and bin 100 as the manual feed bin.

Table 26. Form Definitions Supplied with Infoprint for Printing Envelopes

<b>Form Definition</b>	<b>Bin</b>	<b>Sides</b>	<b>Presentation Mode</b>	<b>Print Direction</b>	<b>Page Position (in inches from the paper edge)</b>
<b>F1A000E0</b>	Envelope	1	Landscape	Across	0, 0
<b>F1A000M0</b>	Manual	1	Landscape	Across	0, 0
<b>F1A101E0</b>	Envelope	1	Landscape	Across	0.165, 0.165
<b>F1A101M0</b>	Manual	1	Landscape	Across	0.165, 0.165

## Form Definitions for 17 by 11 Inch Paper

Use the form definitions in Table 27 for jobs that require 17 by 11 inch paper.

Table 27. Form Definitions Supplied for 17 by 11 Paper

<b>Form Definition</b>	<b>Bin</b>	<b>Sides</b>	<b>Presentation Mode</b>	<b>Print Direction</b>	<b>Page Position (in inches from the top-left corner of the page)</b>
<b>F100LS</b>	1, 2, 3, 4, 5	1	Landscape	Across	0, 0
<b>F100LD</b>	1, 2, 3, 4, 5	2	Landscape	Across	0, 0
<b>F100LT</b>	1, 2, 3, 4, 5	Tumble	Landscape	Across	0, 0
<b>F100LAND</b> <sup>1</sup>	1, 2, 3, 4, 5	2	Landscape	Across	0, 0

1. Used for N\_UP of 1.

## Form Definitions Specifying a 0, 0 Offset

The form definitions in Table 28 specify a 0, 0 offset from the upper-left corner of the page. Use these form definitions if images or data in the job prints off-center or appears to be shifting on the page.

Table 28. Form Definitions Supplied with Infoprint Specifying a 0, 0 Offset

<b>Form Definition</b>	<b>Bin</b>	<b>Sides</b>	<b>Presentation Mode</b>	<b>Print Direction</b>	<b>Page Position (in inches from the top-left corner of the page)</b>
F100S	1, 2, 3, 4, 5	1	Portrait	Across	0, 0
F100D	1, 2, 3, 4, 5	2	Portrait	Across	0, 0
F100T	1, 2, 3, 4, 5	Tumble	Portrait	Across	0, 0
F1A00010	1	1	Portrait	Across	0, 0
F1A00011	1	2	Portrait	Across	0, 0
F1A00012	1	Tumble	Portrait	Across	0, 0
F1A00020	2	1	Portrait	Across	0, 0
F1A00021	2	2	Portrait	Across	0, 0
F1A00022	2	Tumble	Portrait	Across	0, 0
F1A00030	3	1	Portrait	Across	0, 0
F1A00031	3	2	Portrait	Across	0, 0
F1A00032	3	Tumble	Portrait	Across	0, 0
F1A00040	4	1	Portrait	Across	0, 0
F1A00041	4	2	Portrait	Across	0, 0
F1A00042	4	Tumble	Portrait	Across	0, 0
F1A00050	5	1	Portrait	Across	0, 0
F1A00051	5	2	Portrait	Across	0, 0
F1A00052	5	Tumble	Portrait	Across	0, 0



## Form Definitions Specifying N\_UP Page Positioning

The form definitions in Table 29 have various N\_UP values and page placement. Refer to *IBM Page Printer Formatting Aid: User's Guide* more information about N\_UP printing.

Table 29. Form Definitions for N\_UP Page Positioning

Form Definition	Bin	Sides	N_UP	Page Placement	Presentation Mode	Print Direction	Page Position <sup>1</sup>
F1BOOK <sup>2</sup>	1	2	2	Page 1 at 1 Front Page 2 at 2 Front Page 3 at 2 Back Page 4 at 1 Back	Portrait	Across	0, 0
F1N2SST1 <sup>2</sup>	1, 2, 3, 4, 5	Tumble	2	Page 1 at 1 Front Page 2 at 1 Back Page 3 at 2 Front Page 4 at 2 Back	Portrait	Across	0, 0
F1N2SS11 <sup>2</sup>	1, 2, 3, 4, 5	2	2	Page 1 at 1 Front Page 2 at 2 Back Page 3 at 2 Front Page 4 at 1 Back	Portrait	Across	0, 0
F1N2SS12 <sup>2</sup>	1, 2, 3, 4, 5	2	2	Page 1 at 1 Front Page 2 at 2 Front Page 3 at 1 Back Page 4 at 2 Back	Portrait	Across	0, 0
F1N2SS13 <sup>2</sup>	1, 2, 3, 4, 5	2	3	Page 1 at 1 Front Page 2 at 2 Front Page 3 at 3 Front Page 4 at 1 Back Page 5 at 2 Back Page 6 at 3 Back	Portrait	Across	0, 0
F1N20010	1	1	2	Default	Portrait	Across	0, 0
F1N20011	1	2	2	Default	Portrait	Across	0, 0
F1N20012	1	Tumble	2	Default	Portrait	Across	0, 0
F1N20110	1	1	2	Default	Portrait	Across	0.165, 0.165
F1N20111	1	2	2	Default	Portrait	Across	0.165, 0.165
F1N20112	1	Tumble	2	Default	Portrait	Across	0.165, 0.165
F1N20120	2	1	2	Default	Portrait	Across	0.165, 0.165
F1N20121	2	2	2	Default	Portrait	Across	0.165, 0.165
F1N20122	2	Tumble	2	Default	Portrait	Across	0.165, 0.165
F1N20130	3	1	2	Default	Portrait	Across	0.165, 0.165
F1N20131	3	2	2	Default	Portrait	Across	0.165, 0.165
F1N20132	3	Tumble	2	Default	Portrait	Across	0.165, 0.165
F1N20140	4	1	2	Default	Portrait	Across	0.165, 0.165
F1N20141	4	2	2	Default	Portrait	Across	0.165, 0.165
F1N20142	4	Tumble	2	Default	Portrait	Across	0.165, 0.165
F1N20150	5	1	2	Default	Portrait	Across	0.165, 0.165
F1N20151	5	2	2	Default	Portrait	Across	0.165, 0.165
F1N20152	5	Tumble	2	Default	Portrait	Across	0.165, 0.165
F1N201LA	1	1	2	Default	Landscape	Across	0.0, 0.5

Table 29. Form Definitions for N\_UP Page Positioning (continued)

<b>Form Definition</b>	<b>Bin</b>	<b>Sides</b>	<b>N_UP</b>	<b>Page Placement</b>	<b>Presentation Mode</b>	<b>Print Direction</b>	<b>Page Position<sup>1</sup></b>
<b>F1N201LD</b>	1	1	2	Default	Landscape	Down	0.0, 0.5
<b>F1N201PA</b>	1	1	2	Default	Portrait	Across	0.0, 0.5
<b>F1N201PD</b>	1	1	2	Default	Portrait	Down	0.0, 0.5

1. Specified in inches from the top-left corner of the page.  
 2. Used with printers that support enhanced N\_UP values.

## Form Definitions for Printing on Prepunched Paper

Use the form definitions in Table 30 for jobs that require prepunched paper.

Table 30. Form Definitions for Prepunched Paper

<b>Form Definition</b>	<b>Bin</b>	<b>Sides</b>	<b>Presentation Mode</b>	<b>Print Direction</b>	<b>Page Position (in inches from the top-left corner of the page)</b>
<b>F1H10110</b>	1	1	Portrait	Across	1.000, 0.165
<b>F1H10111</b>	1	2	Portrait	Across	1.000, 0.165, 0.165, 0.165
<b>F1H10112</b>	1	Tumble	Portrait	Across	1.000, 0.165, 1.000, 0.165
<b>F1H10120</b>	2	1	Portrait	Across	1.000, 0.165
<b>F1H10121</b>	2	2	Portrait	Across	1.000, 0.165, 0.165, 0.165
<b>F1H10122</b>	2	Tumble	Portrait	Across	1.000, 0.165, 1.000, 0.165
<b>F1H10130</b>	3	1	Portrait	Across	1.000, 0.165
<b>F1H10131</b>	3	2	Portrait	Across	1.000, 0.165, 0.165, 0.165
<b>F1H10132</b>	3	Tumble	Portrait	Across	1.000, 0.165, 1.000, 0.165
<b>F1H10140</b>	4	1	Portrait	Across	1.000, 0.165
<b>F1H10141</b>	4	2	Portrait	Across	1.000, 0.165, 0.165, 0.165
<b>F1H10142</b>	4	Tumble	Portrait	Across	1.000, 0.165, 1.000, 0.165
<b>F1H10150</b>	5	1	Portrait	Across	1.000, 0.165
<b>F1H10151</b>	5	2	Portrait	Across	1.000, 0.165, 0.165, 0.165
<b>F1H10152</b>	5	Tumble	Portrait	Across	1.000, 0.165, 1.000, 0.165

## Form Definitions for Specific Models of IBM Printers

Use the form definitions in Table 31 with the IBM 3831 Page Printer, IBM 3835, and IBM 3900 Advanced Function Printers.

Table 31. Form Definitions Supplied for IBM 3831, 3835, and 3900 Printers

<b>Form Definition</b>	<b>Printer Type Compatible with</b>	<b>Bin</b>	<b>Sides</b>	<b>Presentation Mode</b>	<b>Print Direction</b>	<b>Page Position<sup>1</sup></b>
<b>F1OGL</b> <sup>2</sup>	3800	1	1	Landscape	Across	0.0, 0.0
<b>F10101LA</b>	3800 wide forms	1	1	Landscape	Across	0.00, 0.50
<b>F10101LD</b>	3800 narrow forms	1	1	Landscape	Down	0.00, 0.50
<b>F10101PA</b>	3800 narrow forms	1	1	Portrait	Across	0.00, 0.50
<b>F10101PD</b>	3800 wide forms	1	1	Portrait	Down	0.00, 0.50
<b>F1C10110</b> <sup>3</sup>	Cut-sheet	1	1	Landscape	Down	0.165, 0.165
<b>F1C10111</b> <sup>4</sup>	Cut-sheet	1	2	Landscape	Down	0.165, 0.165
<b>F1C10112</b> <sup>4</sup>	Cut-sheet	1	Tumble	Landscape	Down	0.165, 0.165

1. Specified in inches from the paper edge.
2. Created using Overlay Generation Language (OGL). Positions sample overlays.
3. Designed for use with the IBM 3835 printer.
4. Designed for use with advanced function printers. Specify these form definitions when printing data that has been formatted for cut-sheet printers.

Use the form definitions in Table 32 with the IBM 3935 Advanced Function Printer and the IBM 3160 Advanced Function Printer.

Table 32. Form Definition Supplied for IBM 3935 and 3160 Printers

<b>Form Definition</b>	<b>Bin</b>	<b>Sides</b>	<b>Presentation Mode</b>	<b>Print Direction</b>	<b>Page Position (in inches from the top-left corner of the page)</b>
<b>F1A1BIN2</b>	2	1	Portrait	Across	0.165, 0.165
<b>F1A1BIN3</b>	3	1	Portrait	Across	0.165, 0.165
<b>F1A1BIN4</b>	4	1	Portrait	Across	0.165, 0.165
<b>F1A1BIN5</b>	5	1	Portrait	Across	0.165, 0.165

## Page Definitions Supplied with Infoprint

Table 33 through Table 37 on page 708 list the page definitions that are supplied with Infoprint. The page definitions are grouped by the size of the paper on which the job prints.

### Page Definitions for Letter-Sized Paper

Table 33. Page Definitions for Letter-Sized Paper

<b>Page Definition</b>	<b>Printable Area (Width by Height, In Inches)</b>	<b>Print Lines per Page</b>	<b>Print Position: Down/Across</b>	<b>Recom- mended Font</b>	<b>Printing Direction</b>	<b>Page Presentation</b>
<b>P1A06462</b> <sup>1, 2</sup>	8.17 by 10.67	64 at 6.0 lpi	30/0	<b>GT10</b>	Across	Portrait
<b>P1A08682</b> <sup>3</sup>	8.17 by 10.67	86 at 8.2 lpi	24/0	<b>GT12</b>	Across	Portrait

1. This page definition is also valid for 9.5 by 11.0 inch continuous-form paper.
2. Designed for use with IBM 3812, 3816, 3820, 3825, 3827, 3835, 3900, 4028, 4224, and 4234 printers.
3. Designed for use with IBM 3820, 3827, and 3835 printers.

### Page Definitions for A4-Sized Paper

Table 34. Page Definitions for A4-Sized Paper

<b>Page Definition</b>	<b>Printable Area (Width by Height, In Inches)</b>	<b>Print Lines per Page</b>	<b>Print Position: Down/Across</b>	<b>Recom- mended Font</b>	<b>Printing Direction</b>	<b>Page Presentation</b>
<b>P1C09182</b> <sup>1</sup>	7.94 by 11.36	91 at 8.2 lpi	25/0	<b>GT12</b>	Across	Portrait
<b>P1V0436B</b> <sup>2</sup>	10.67 by 7.11	43 at 6.1 lpi	30/0	<b>GT10</b>	Up	Landscape
<b>P1V04863</b> <sup>1, 2</sup>	10.67 by 7.94	48 at 6.1 lpi	30/0	<b>GT10</b>	Down	Landscape
<b>P1V0588B</b> <sup>2</sup>	10.67 by 7.11	58 at 8.2 lpi	24/0	<b>GT12</b>	Up	Landscape
<b>P1V0598B</b> <sup>2</sup>	10.67 by 7.11	59 at 8.2 lpi	24/0	<b>GT12</b>	Up	Landscape
<b>P1V0608B</b> <sup>2, 3</sup>	10.67 by 7.11	60 at 8.5 lpi	24/224	<b>GT15</b>	Up	Landscape
<b>P1V0618B</b> <sup>2, 3</sup>	10.67 by 7.11	61 at 8.5 lpi	24/224	<b>GT15</b>	Up	Landscape
<b>P1V06483</b> <sup>1, 2</sup>	10.67 by 7.94	64 at 8.2 lpi	24/0	<b>GT12</b>	Down	Landscape
<b>P1V06683</b> <sup>1, 2, 3</sup>	10.67 by 7.94	66 at 8.5 lpi	24/224	<b>GT15</b>	Down	Landscape
<b>P1X04763</b> <sup>2, 4</sup>	10.60 by 7.77	47 at 6.1 lpi	30/0	<b>GT10</b>	Down	Landscape

1. Designed to work with 3820, 3827, 3835 printers.
2. Designed to work for letter-sized and A4-sized paper.
3. The printable area is 9.74 by 7.94 inches because of the 224 logical unit offset in the "Print Position: Down/Across" column.
4. Designed for use with HPCL and PPDS data streams.

## Page Definitions for Letter- and A4-Sized Paper with Multiple-Up of 2 and 4

Table 35. Page Definitions for Letter- and A4-Sized Paper with Multiple-Up of 2 and 4

<b>Page Definition</b>	<b>Printable Area (Width by Height, In Inches)</b>	<b>Print Lines per Page</b>	<b>Print Position: Down/Across</b>	<b>Recom- mended Font</b>	<b>Printing Direction</b>	<b>Page Presentation</b>
<b>P1W1168B</b>	10.67 by 7.11	58 at 8.2 lpi	Page 1 24/0 Page 2 24/1281	<b>GT15</b>	Up	Landscape
<b>P1W1188B</b>	10.67 by 7.11	59 at 8.2 lpi	Page 1 24/0 Page 2 24/1281	<b>GT15</b>	Up	Landscape
<b>P1W120C2</b> <sup>1</sup>	7.94 by 10.67	60 at 12.0 lpi	Page 1 16/160 Page 2 1344/160	<b>GT20</b>	Across	Portrait
<b>P1W12883</b> <sup>1</sup>	10.67 by 7.94	64 at 8.2 lpi	Page 1 24/0 Page 2 24/1281	<b>GT15</b>	Down	Landscape
<b>P1W216FB</b>	10.67 by 7.11	54 at 15.2 lpi	Page 1 16/48 Page 2 890/48 Page 3 16/1322 Page 4 890/1322	<b>GT24</b>	Up	Landscape
<b>P1W220FB</b>	10.67 by 7.11	55 at 15.2 lpi	Page 1 16/48 Page 2 890/48 Page 3 16/1322 Page 4 890/1322	<b>GT24</b>	Up	Landscape
<b>P1W240F3</b> <sup>1</sup>	10.67 by 7.94	60 at 15.2 lpi	Page 1 16/48 Page 2 968/48 Page 3 16/1322 Page 4 968/1322	<b>GT24</b>	Down	Landscape

1. Designed to work with 3820, 3827, 3835 printers.

## Page Definitions for Legal-Sized Paper

Table 36. Page Definitions for Legal-Sized Paper

<b>Page Definition</b>	<b>Printable Area (Width by Height, In Inches)</b>	<b>Print Lines per Page</b>	<b>Print Position: Down/Across</b>	<b>Recom- mended Font</b>	<b>Printing Direction</b>	<b>Page Presentation</b>
<b>P1B0446B</b>	13.67 by 7.34	44 at 6.0 lpi	30/0	<b>GT10</b>	Up	Landscape
<b>P1B04963</b> <sup>1</sup>	13.67 by 8.17	49 at 6.0 lpi	30/0	<b>GT10</b>	Down	Landscape
<b>P1B0608B</b>	13.67 by 7.34	60 at 8.2 lpi	24/0	<b>GT12</b>	Up	Landscape
<b>P1B06683</b> <sup>1</sup>	13.67 by 8.17	66 at 8.2 lpi	24/0	<b>GT12</b>	Down	Landscape
<b>P1B08262</b> <sup>2</sup>	8.17 by 13.67	82 at 6.0 lpi	30/0	<b>GT10</b>	Across	Portrait
<b>P1B11082</b> <sup>1</sup>	8.17 by 13.67	110 at 8.2 lpi	24/0	<b>GT12</b>	Across	Portrait
<b>P1R04763</b> <sup>3</sup>	13.6 by 8.0	47 at 6.0 lpi	30/0	<b>GT10</b>	Down	Landscape

1. Designed for use with IBM 3820, 3827, and 3835 printers.  
2. Designed for use with IBM 3812, 3816, 3820, 3825, 3827, 3828, 3835, 3900, 4028, and 4224 printers.  
3. Designed for use with HPCL and PPDS data streams.

## Page Definitions for B4-Sized Paper

Table 37. Page Definitions for B4-Sized Paper

<b>Page Definition</b>	<b>Printable Area (Width by Height, In Inches)</b>	<b>Print Lines per Page</b>	<b>Print Position: Down/Across</b>	<b>Recom- mended Font</b>	<b>Printing Direction</b>	<b>Page Presentation</b>
<b>P1D0556B</b>	14.0 by 8.96	55 at 6.1 lpi	30/0	<b>GT10</b>	Up	Landscape
<b>P1D06063</b> <sup>1</sup>	14.0 by 9.79	60 at 6.1 lpi	30/0	<b>GT10</b>	Down	Landscape
<b>P1D0748B</b>	14.0 by 8.96	74 at 8.2 lpi	24/0	<b>GT12</b>	Up	Landscape
<b>P1D08083</b> <sup>1</sup>	14.0 by 9.79	80 at 8.2 lpi	24/0	<b>GT12</b>	Down	Landscape
<b>P1D08462</b> <sup>1</sup>	9.79 by 14.0	84 at 6.0 lpi	30/0	<b>GT10</b>	Across	Portrait
<b>P1D11382</b> <sup>1</sup>	9.79 by 14.0	113 at 8.2 lpi	24/0	<b>GT12</b>	Across	Portrait
1. Designed for use with IBM 3820, 3827, and 3835 printers.						

---

## Glossary

This glossary provides definitions of specialized terms used by IBM Infoprint Control (Infoprint). This glossary does not define terms that are defined in non-technical dictionaries or that have no special meaning in information processing.

---

## Sources and References

This glossary includes definitions from the following sources:

- Definitions reprinted from a published section of the International Organization for Standardization's (ISO) *Vocabulary—Information Processing* or from a published section of the ISO *Vocabulary—Office Machines* are identified by the symbol (I) following the definition.
- Definitions reprinted from working documents, draft proposals, or draft international standards of ISO Technical Committee 97, Subcommittee 1 (Vocabulary) are identified by (T), indicating that final agreement has not yet been reached among its participating members.
- Definitions from *Introduction to OSF DCE*, by Open Systems Foundation, published by Prentice-Hall, are identified by (OSF).
- Definitions from *Portable Operating System Interface (POSIX) System Administration Interface/Printing Standards Project* are identified by (P).
- Definitions from *Information technology—Document printing application (DPA)—Part 1: Abstract-service definition and procedures* are identified by (D).
- Definitions from *AIX Version 4.1 Topic Index and Glossary* are identified by (X).
- Definitions from *IBM Dictionary of Computing*.
- Definitions that are specific to IBM products are so labeled, for example, "in Infoprint", or "In DCE".

This glossary uses the following cross references:

**Contrast with.** This refers to a term that has an opposed or substantively different meaning.

**Synonym for.** This indicates that the term has the same meaning as a preferred term, which is defined in its proper place in the glossary.

**Synonymous with.** This is a backward reference from a defined term to all other terms that have the same meaning.

**See.** This refers you to multiple-word terms that have the same last word.

**See also.** This refers you to terms that have a related, but not synonymous, meaning.

## Special Characters

**.Guidefaults file.** A file created by Infoprint in the home directory of a person using the Infoprint GUI. Infoprint uses this file to save and reference information about the servers you are monitoring and the windows you are working in.

## A

**Access Control List (ACL).** In computer security, a collection of all access rights for one object. In DCE, a list associated with each object in the namespace that specifies the access authorization level for each user or user group.

**ACL.** Access control list.

**acl editor.** A command line interface that allows you to view, add, update, and delete access authorization records in an ACL.

**action.** In the Infoprint GUI, an icon that represents an operation that you can perform on an Infoprint object. You drag and drop the action onto an object to initiate the operation for that object; for example, using the **Enable** action to enable a disabled actual destination.

**actual destination.** In Infoprint, an object that represents the output device that performs the printing or transmission function. See *email destination*, *fax destination*; see also *physical printer*, *printer device*; contrast with *logical destination*.

**additive color system.** A system that reproduces an image by mixing (adding) appropriate quantities of red, green, and blue light (the additive primary colors) to create all other colors of light, either direct or transmitted. When the additive primaries are superimposed on one another, they create white light. Contrast with *subtractive color system*.

**administrator.** In Infoprint, the person who creates and manages one or more components of a printing system, such as servers and actual destinations. By default, Infoprint gives administrators authorization to

perform some Infoprint operations and to access certain information that is not available to the operators or job submitters.

**Adobe Acrobat.** An Adobe software program that provides instant access to documents in their original format, independent of computer platform. With the Adobe Reader, you can view, navigate, print, and present any Portable Document Format (.pdf) file.

**Adobe PageMaker.** A desktop publishing program that produces PostScript documents.

**Adobe PostScript Raster to Image Transform (RIP).** See *raster image processor (RIP)*.

**ADSM/6000.** *Advanced Distributed Storage Manager.*

**Advanced Distributed Storage Manager (ADSM/6000).** A program that provides storage management for archived files.

**Advanced Function Common Control Unit (AFCCU).** An IBM RISC-based control unit with code common to all printers that use the AFCCU.

**Advanced Function Presentation (AFP).** A set of licensed programs, together with user applications, that use the all-points-addressable concept to print data on a wide variety of printers or to display data on a wide variety of display devices. AFP includes creating, formatting, archiving, retrieving, viewing, distributing, and printing information.

**Advanced Function Presentation data stream (AFP data stream).** The printer data stream used for printing AFP data. The AFP data stream includes composed text, page segments, electronic overlays, form definitions, and fonts downloaded from the operating system to the printer. A presentation data stream that is processed in AFP environments. The AFP data stream includes MO:DCA-P-based data streams.

**Advanced Interactive Executive (AIX).** An operating system used with RS/6000 computers. The AIX operating system is IBM's implementation of the UNIX operating system.

**AFCCU.** Advanced Function Common Control Unit.

**AFP.** Advanced Function Presentation.

**AFP data stream.** Advanced Function Presentation data stream.

**ainbe.** The printer input/output backend program used by the PSF DSS to send jobs to printer devices. Depending on the incoming data stream of the job, the PSF DSS may have transformed the data stream of the job prior to the backend program sending it to the printer device.

**AIX.** Advanced Interactive Executive.

**AIX-attached printer.** A printer device, attached to an RS/6000 through the network or through a serial or parallel port, that receives jobs from an AIX print queue. In Infoprint, a PSF physical printer that represents an AIX-attached printer device. See also *channel-attached printer*, *direct-attached printer*, *TCP/IP-attached printer*, *upload-SNA-attached printer*, *upload-TCP/IP-attached printer*.

**AIX destination support system.** In Infoprint, the destination support system that communicates with the standard AIX print backend (**pio**be), or with certain variations of the **rembak** print backend, to print jobs.

**AIX physical printer.** In Infoprint, the object representing a printer device that uses the AIX destination support system.

**aliasing.** In a digitized image, the creation of diagonal lines by combining short, horizontal, and vertical line segments that approximate the path of the desired line.

**all-points-addressability (APA).** The capability to address, reference, and position text, overlays, and images at any defined point of the printable area of the paper or display medium.

**alphameric.** Synonym for *alphanumeric*.

**alphanumeric.** Pertaining to a character set containing letters, digits, and other symbols such as punctuation marks. Synonymous with *alphameric*.

**AMPV.** Average monthly print volume.

**analog.** Pertaining to a continuous variable sampling of information between two points that achieves an even smooth transition of photographic material.

**analog color proof.** An off-press color proof made from separation films.

**anti-aliasing.** The rendering of hard-edged objects so that they blend smoothly into the background. PhotoShop offers anti-aliasing when rasterizing an EPS file. Removing the jagged "stairstep" quality in diagonal lines produced on a computer screen by aliasing. This removal is affected by creating less densely shaded fields parallel to the diagonal line.

**APA.** All-points-addressability.

**API.** Application Program Interface.

**Application Program Interface (API).** The call interface between a client program and the procedures that implement the printing system, as defined by the specification. Clients use the API to access servers. (P)

**architecture.** The set of rules and conventions that govern the creation and control of data types such as text, image, graphics, font, fax, color, audio, bar code, and multimedia.



**archiving.** The transfer of digital information from an online system onto magnetic tape, floppy disk, compact disc, or other media for offline storage. The original copy is deleted from the online system. See also *retrieval*.

**array inkjet.** An ordered collection of multiple print heads used in an inkjet printer.

**ASCII.** American National Standard Code for Information Interchange. The standard code, using a coded character set consisting of 7-bit coded characters (8-bits including a parity check), that is used for information interchange among data processing systems, data communications systems, and associated equipment. The ASCII set consists of control characters and graphic characters.

**asynchronous.** Pertaining to two or more processes that do not depend upon the occurrence of specific events, such as common timing signals. (T) In Infoprint, occurring without a regular or predictable time relationship to a specified action. Contrast with *synchronous*.

**attachment type.** Defines the method by which a printer device is attached to the system from which it receives data. See *AIX-attached printer*, *channel-attached printer*, *TCP/IP-attached printer*, *direct-attached printer*, *upload-SNA-attached printer*, *upload-TCP/IP-attached printer*.

**attribute.** A defined characteristic of an object, such as the number of copies required of a job, or the document formats accepted by a physical printer.

**attribute name.** A string that identifies an attribute. Typically, in Infoprint attribute names consist of two or more words separated by hyphens.

**attribute value.** The element of an attribute that specifies the characteristics relating to the attribute.

**authorization.** In computer security, verification of the eligibility of a user to access an object.

**authorized user.** A person with the appropriate permissions to access an object or to issue a command.

**automatic recovery.** A function of printer logic that permits the printer to reprint a job if the job is misprinted or damaged or if a component has failed.

**auxiliary sheet.** In Infoprint, an object that represents a particular sheet of paper, blank or otherwise, that can precede a job, separate documents within a job, or follow a job.

**auxiliary-sheet selections.** A particular combination of start, separator, and end sheets that print with jobs on a particular printer device.

## B

**backend.** In AIX, the program that is invoked by the **qdaemon** process to run a print or batch job. Synonymous with *backend program*.

**backend program.** Synonym for *backend*.

**backlog.** In Infoprint, the amount of time calculated by Infoprint that is required to print all of the jobs currently in a queue.

**backspace.** In Infoprint, the action used to back up and reprint pages in a job.

**bar code.** A code representing characters by sets of parallel bars of varying thickness and separation that are read optically by transverse scanning. In architecture, an array of parallel rectangular bars and spaces that together represent data elements or characters in a particular symbology. The bars and spaces are arranged in a predetermined pattern following unambiguous rules defined by the symbology.

**BCOCA.** Bar code object content architecture.

**Bezier curves.** A method of defining curves using anchor points, control handles, and tangent lines. The PostScript path passes through anchor points, and its approach direction is along the tangent lines that are controlled by the control handles. Many PC programs use this drawing method. Type 1 PostScript fonts are defined using Bezier curves.

**binding.** The cover and materials that hold a book together. See *edition binding*, *perfect binding*, *spiral binding*, *wire-o binding*. The process of applying the binding to a book. In Infoprint, assigning a job to an actual destination. See *early binding*, *late binding*. In DCE, pointers stored in a DCE cell that are used to connect clients to servers.

**bitmapped.** Pertaining to an image formed by a rectangular grid of pixels. Each pixel is assigned a value to denote its color. One-bit images are black and white; 8-bit images have 256 colors (or grays); 24-bit images have full color. CMYK images have 32 bits per pixel to encode 256 levels in each of four channels. Bitmapped images are also called raster images.

**bleed.** An extra amount of printed image that extends beyond the trim edge of the sheet. Bleed ensures that no white gap appears at the edge of the sheet.

**boot.** To prepare a computer for operating by loading an operating system.

**BSD.** Berkeley Software Distribution.

**BSD destination support system.** In Infoprint, the destination support system that generates a print command string that the shell runs to print jobs.

**BSD physical printer.** In Infoprint, the object representing a printer device that uses the BSD destination support system.

**burn.** In platemaking, an exposure. Burn is named because of the extremely bright ultraviolet lamps used to transfer images from film to plate. In photography, to lengthen the exposure time to increase the final density of print.

## C

**cathode ray tube (CRT).** A vacuum tube in which a beam of electrons can be moved to draw lines or form characters or symbols on its luminescent (phosphor-coated) screen. CRTs are the heart of all modern computer display screens. Black and white displays have only white phosphor scanned by one electron beam, while color displays have RGB phosphors scanned by three beams.

**CDE.** Common Desktop Environment.

**cell.** Synonym for *DCE cell*.

**Cell Directory Service.** A DCE component that manages a database of information about resources within a cell.

**channel-attached printer.** A printer attached to an RS/6000 by cables, rather than through telecommunication lines. In Infoprint, a PSF physical printer that represents a channel-attached printer device. See also *AIX-attached printer*, *direct-attached printer*, *TCP/IP-attached printer*, *upload-SNA-attached printer*, *upload-TCP/IP-attached printer*.

**child.** See *parent/child relationship*.

**choke.** In color printing, an area whose dimensions have been reduced to avoid overlapping another color. Contrast with *spread*.

**class.** Synonym for *object class*.

**clean.** In Infoprint, an action used to remove all the jobs from specified servers, actual destinations, or queues, or all the jobs submitted to specified logical destinations.

**CLI.** Command Line Interface.

**client.** In Infoprint, the component of the print system that assembles a print request and submits the request to a server. The client generates the local ID numbers for each job, submits the jobs to the servers, and keeps track of where each user's jobs have been submitted. IBM Infoprint Control and IBM Infoprint Submit include clients; you can also install the IBM Infoprint Select clients on workstations.

**CMY.** Cyan, magenta, yellow.

**CMYK.** Cyan, magenta, yellow, black.

**collator.** In some printers, for example, the IBM InfoColor 70, a special-purpose hard drive disk array used to store RIPped files and later transfer them to the LED print heads for imaging.

**color balance.** The relative levels of cyan, magenta, and yellow channels in an image to produce accurate color rendition of an original image.

**color correction.** The adjustment of the color balance in an image to produce accurate color rendition of an original image. Color correction is used for two- or three-spot-color jobs.

**color key.** A color proof similar to Cromalin, but typically not laminated and not necessarily accurate in color. Color keys are used to verify that breaks or color assignments and traps have been made accurately.

**Command Line Interface (CLI).** A type of user interface where commands are specified on the command line. Contrast with *Graphical User Interface*.

**Common Desktop Environment (CDE).** A graphical user interface running on a UNIX operating system.

**complex attribute.** In Infoprint, an attribute that can have multiple values with each value containing multiple components.

**constant data.** Data that does not change between jobs and that is merged with variable data to produce personalized copies of documents. For example, a form letter (constant data) can be merged with a customer's name and address (variable data).

**contextual help.** A type of online help that provides specific information about each selectable object, menu choice, notebook tab, field, control and pushbutton in a window.

**control strip.** A strip of information that can be attached to a print job and used to measure registration and density.

**Cromalin.** The Dupont color proofing system. Four layers (CMYK) of light-sensitive material are exposed through final halftone negative films, then laminated together on an opaque backing to produce a color and trap-accurate final proof showing actual half-tone dot structure. Cromalin is sometimes called an analog proof.

**crop.** To remove unwanted areas of an image, usually indicated by crop marks on the original.

**CRT.** Cathode ray tube.

**CTS.** Cutter-trimmer-stacker.

**cutter-trimmer-stacker (CTS).** A post-processing device attached to a printer device and used for paper handling.

**cyan, magenta, yellow (CMY).** The subtractive primary colors.

**cyan, magenta, yellow, black (CMYK).** The four basic colors used in offset printing, as opposed to the three basic colors of light: red, green, and blue. Magenta, yellow, and cyan are the subtractive primaries. Black is added to provide better density and to produce a true black.

## D

**daemon.** A program that runs unattended to perform a standard service. Some daemons are triggered automatically to perform their task; others operate periodically. Daemon processes generally provide service that must be available at all times to more than one task or user, such as sending data to a printer.

**DAT.** Digital audio tape.

**DataBase 2/6000 (DB2\*/6000).** The component of the Infoprint Library that indexes data for easy retrieval.

**data stream.** All information (data and control commands) sent over a data link. A continuous stream of data that has a defined format. In Infoprint, pertaining to the incoming format of the job and the output format required by the printer device. Infoprint transforms the incoming format into the output format, as required. See also *document format*.

**DB2\*/6000.** DataBase 2/6000.

**DCE.** Distributed Computing Environment.

**DCE authority.** The permission granted by DCE to access an object.

**DCE cell.** The basic unit of operation and administration in DCE. A group of DCE machines that work together and are administered as a unit. A cell represents a group of users, systems, and resources that typically have a common purpose and share common DCE services.

**DCE login ID.** The identifier of a person logging into DCE. DCE uses this ID to determine a user's authenticity and authorization levels for accessing and modifying data in the DCE cell.

**DCE ticket.** The time-limited DCE authority granted whenever a user logs into DCE. When the DCE ticket expires, the user must log into DCE again in order to access objects protected by DCE.

**deadline.** In Infoprint, a queuing technique where the next job assigned to the first position in the queue is the one whose deadline is closest. Contrast with *fifo* (*first-in-first-out*), *job-priority*, *longest-job-first*, and *shortest-job-first*.

**default document.** In Infoprint, an object that represents default attribute values for a document within a job. Synonymous with *initial value document*.

**default job.** In Infoprint, an object that represents default attribute values for a job. Synonymous with *initial value job*.

**default object.** In Infoprint, a general term that refers either to an *default document* or an *default job*. Synonymous with *initial value object*.

**default value.** A value stored in the system that is used when no other value is specified.

**delete.** In Infoprint, an action used to delete default objects, jobs, logical destinations, actual destinations, or queues from the server.

**desktop publishing.** Performing print-related activities on a personal computer, including but not limited to layout, design, photo manipulation, creating fonts, editing text, color separation, scanning, and animation.

**destination.** See *actual destination*, *logical destination*.

**destination support system (DSS).** In Infoprint, the programs that an actual destination uses to communicate with the output device. Synonymous with *device support system*. See *AIX destination support system*, *BSD destination support system*, *email destination support system*, *fax destination support system*, *PSF destination support system*, *3170 destination support system*.

**device.** An individual piece of equipment (hardware) that attaches to a computer, such as a printer device.

**device address.** The identification of an input or output device by its channel and unit number.

**device driver.** A file that communicates with a specific device such as a printer, disk drive, or display. An application that sends output to a device controls the actions of the device through the device driver. See *printer driver*.

**device support system (DSS).** Synonym for *destination support system*.

**DFS.** Distributed File Service.

**digital.** Pertaining to data represented by digits, sometimes with special characters and the space character.

**digital audio tape (DAT).** A high-capacity, low-cost megabyte bulk storage system used for archiving, copying (for backup purposes), and transferring large files. Typical DAT units store 1.3 GB on inexpensive cassette tapes.

**digital color proof.** An off-press color proof made from a color printer attached to a computer.

**digital printing.** A filmless and plateless printing process in which digital data for each page is transferred directly to a light-sensitive drum and then to paper for a final image.

**direct-attached printer.** A printer device, attached to an RS/6000 through the network or through a serial or parallel port. In Infoprint, a PSF physical printer that represents a direct-attached printer device. See also *AIX-attached printer*, *channel-attached printer*, *TCP/IP-attached printer*, *upload-SNA-attached printer*, *upload-TCP/IP-attached printer*.

**disable.** In Infoprint, an action used to stop the acceptance of jobs on destinations, queues, or servers, or to stop writing information to logs.

**Distributed Computing Environment (DCE).** A software system from the Open Software Foundation (OSF). DCE provides the services that allow a distributed application to interact with a collection of possibly heterogeneous computers, operating systems, and networks as if they were a single system.

**Distributed File System (DFS).** A DCE component consisting of a single, integrated file system that is shared among all DCE users and host computers in a DCE cell. DFS allows users to access and share files stored in a network, without having to know the physical location of the files. It also prevents users from simultaneously modifying the same information.

**distributed print system.** A computer system with the ability to interchange print data and controls among different computing environments with the intent of printing the data on a different system from the one where the print request was generated. For example, in host-to-LAN distributed printing, data that resides on the host is printed on printers attached to a local area network.

**dithering.** A technique of filling the gap between two pixels with another pixel having an average value of the two to minimize the difference or add detail to smooth the result.

**document.** In Infoprint, an object representing a grouping of data within a job. A job can contain one or more documents. The documents in a job can differ from each other in some ways. For example, they can contain different data and can have different document formats. A document within a job can contain printable data or a resource that is not printable by itself. See *file-reference document*, *printable document*, and *resource document*.

**document element.** A portion of a document at least a single page in size.

**document format.** In Infoprint, a document format describes the type of the data and control characters in the document, such as line data or PostScript. The

format of the data determines which printer devices are capable of printing the document and whether Infoprint must transform the format.

**document identifier.** A string that identifies a document within a job. It consists of a job ID followed by a period (.) and a document sequence number. For example, 12.2. Document sequence numbers are integers starting at 1.

**Document Printing Application (DPA).** An ISO/IEC 10175 standard that addresses those aspects of document processing that enable users in a distributed open systems environment to send electronic documents to shared, possibly geographically-dispersed printers. Infoprint supports the DPA standard.

**document transfer method.** In Infoprint, the transfer method describes how documents are transferred to, or acquired by, servers. See *pipe-pull* and *with-request*.

**document type.** In Infoprint, the document type describes the kind of data in the document. A *printable document* can only contain printable data. A *resource document* can only contain data such as fonts or form definitions that are not printable. A *file reference document* can only contain names of files entered on separate lines.

**dot.** The individual elements of a halftone.

**dot gain.** An increase in the size of a halftone dot during printing, caused by ink spreading. Generally, this value is known precisely, and the scanning and filming production process is calibrated to compensate for it. The Cromalin proofing system simulates this effect.

**dots per inch (dpi).** A measure of data density per unit distance. Typical values for desktop publishing work range from 200 to 300 dpi. Values for printing with the IBM InfoColor 70 range as high as 600 dpi.

**DPA.** Document Printing Application.

**dpi.** Dots per inch.

**drag and drop.** In graphical user interfaces, a procedure by which you perform actions and tasks. Using the mouse, you drag (move) an action or object icon to a new position where you want the action or task to occur.

**DSS.** Destination support system.

**dummy.** A rough paste-up or hand-drawn representation of the anticipated finished product. A dummy is used for basic design and pagination.

**duplex printing.** Printing on both sides of the paper. Contrast with *simplex printing (1)*. Printing on both sides of the paper, placing output images on the media in a head-to-head format, so that the top of one image is at

the same edge as the top of the next image. Contrast with *tumble duplex printing*; see also *simplex printing (2)*.

## E

**early binding.** In Infoprint, assigning a job to an actual destination as soon as it is accepted. Early binding permits Infoprint to estimate the time when the job will be completed. Contrast with *late binding*.

**edition binding.** A type of book binding in which printed sheets are folded into 16- or 32-page signatures. Four-page endleaves are pasted on the outside of the first and last signature. The signatures are then collated by machine and sewn together using special sewing machines. Contrast with *perfect binding*, *spiral binding*, *wire-o binding*.

**electronic document.** A document stored in a computer instead of printed on paper.

**electronic mail.** Correspondence in the form of messages transmitted between workstations over a network. Synonymous with *email*.

**electrophotographic.** Pertaining to a type of printer technology that creates an image on paper by uniformly charging the photoconductor, creating an electrostatic image on the photoconductor, attracting negatively charged toner to the discharged areas of the photoconductor, and transferring and fusing the toner to paper.

**em.** In composition, a unit of measurement exactly as wide and as high as the point size of the font being set. The name is derived from the fact that the letter M in early typefaces was usually cast on a square body.

**email.** Electronic mail.

**email destination.** In Infoprint, an actual destination representing an electronic mailing system.

**email destination support system.** In Infoprint, the destination support system that supports email destinations.

**embellishments.** Variable data added to all copies of assembled pages to make the unit seem like a whole; for example, headers, footers, page numbers, a table of contents, and chapter separations.

**en.** In composition, exactly one half an em.

**enable.** In Infoprint, the action that makes a destination, queue, or server able to accept jobs, or a log able to accept information.

**end sheet.** The sheet of paper, blank or otherwise, that can follow a job. See also *auxiliary sheet*.

**Enhanced X-Windows.** A tool designed to permit multiple application processes to operate within multiple windows displayed on a virtual terminal. See *X-Windows*.

**environment variable.** Any one of a number of variables that describe the way an operating system runs and the devices it recognizes.

**error log.** A data set or file in a product or system where error information is stored for later access.

**estimate.** The professional cost analysis made by a print shop in response to a customer's request for a price quotation on a print job.

**event.** In Infoprint, an occurrence in the printing system during an operation; for example, the completion of a command.

**event log.** In Infoprint, a collection of messages about events that have occurred.

**event notification.** The notification that is sent by Infoprint for an event.

**extensions.** An IBM program-provided software component that enables users to incorporate variable data into fixed-text documents to produce personalized or customized documents.

## F

**fax destination.** In Infoprint, an actual destination representing a fax device.

**fax destination support system.** In Infoprint, the destination support system that supports fax destinations.

**FIFO (first-in-first-out).** In Infoprint, a queuing technique where the next job assigned to the first position in the queue is the job that has been in the queue for the longest time. Infoprint processes jobs in the order in which they are received. Contrast with *deadline*, *job-priority*, *longest-job-first*, and *shortest-job-first*.

**file-reference document.** In Infoprint, a file containing the names of other files, each entered on a separate line. Job submitters can specify this file for printing when they specify a document type of **file-reference**. Infoprint prints each file listed in the reference document.

**File Transfer Protocol.** In TCP/IP, the application protocol that makes it possible to transfer data to and from host computers and to use foreign hosts indirectly.

**finisher.** A hardware device attached to a printer that performs such operations as folding or stapling the printed page.

**finishing.** In a print shop, the final operations on a printed product, such as stapling, trimming, drilling, folding, embossing, varnishing, gluing, shrink wrapping, perforating, laminating, collating, and so on.

**flag.** A modifier of a command that specifies the action of the command. A dash usually precedes a flag. Synonymous with *option*. See also *keyword*.

**FOCA.** Font object content architecture.

**folder.** In the Infoprint GUI, an object that represents a container for a collection of similar objects. For example, the Retained Jobs folder contains retained jobs.

**font.** A family of characters of a given size and style; for example, 9-point Helvetica. One size and one typeface in particular type family, including letters, numerals, punctuation marks, special characters, and ligatures. A paired character set and code page that can be used together for printing a string of text characters. A double-byte font can consist of multiple pairs of character sets and code pages.

**form definition.** A resource object used by Infoprint that defines the characteristics of the form or printed media, which include: overlays to be used, the paper source (for cut-sheet printers), duplex printing, text suppression, and the position of composed-text data on the form.

**forward space.** In Infoprint, the action used to move ahead and skip the printing of a specified number of pages in a job.

**FPO.** Low-quality (sometimes photographic) images placed in a dummy to represent final images. Desktop publishing software produces images as display-screen resolution FPOs.

**front panel.** In the CDE, a workspace area containing controls that represent various tasks you can perform and workspace switches. In basic Infoprint installations, the front panel has been customized for Infoprint.

**FTP.** File Transfer Protocol.

## G

**GCR.** Gray component replacement.

**GIF.** Graphics Interchange Format.

**global change.** In the Infoprint GUI, an action used to make changes to one or more attributes of several objects at once. You can also perform the same action on several objects of the same object class at the same time; for example, disabling two or more actual destinations at the same time.

**global character.** A character or set of characters used to specify an unknown number or set of characters

in a search string. In Infoprint, a global character is represented by an asterisk (\*).

**global ID.** Global job identifier.

**global job identifier.** An unambiguous job identifier. In Infoprint, it is represented as the name of the server managing the job followed by a colon (:) and a generated integer. This ID uniquely identifies the job within the Infoprint server.

**glyph.** An image, usually of a character, in a font.

**GOCA.** Graphics object content architecture.

**graphic character.** A visual representation of a character, other than a control character, that is normally produced by writing, printing, or displaying.

**Graphical User Interface (GUI).** A type of user interface that takes advantage of a high-resolution monitor and includes a combination of graphics to implement an object-action paradigm, the use of pointing devices, menu bars, overlapping windows, and icons. Contrast with *Command Line Interface*.

**Graphics Interchange Format (GIF).** A compresses graphics format widely used on the Internet.

**gray component replacement (GCR).** Synonym for *under color removal (UCR)*.

**gray scale.** A strip of standard gray tones, ranging from white to black, placed at the side of the original copy during photography to measure the tonal range and contrast obtained.

**GUI.** Graphical User Interface.

**gutter.** The blank area or inner margin from the printing area to the binding.

## H

**halftone.** A printing method that simulates continuous-tone shading using dots of varying sizes laid out on a regular grid. Larger dots simulate darker tones and smaller dots simulate lighter tones. Typical grid spacings are 85 lines per inch (lpi) (newspaper), 133 lpi (low end), 150 lpi (midrange), and 175+ lpi (high quality).

**help.** In the Infoprint GUI, an action used to display the online help for a specific template, object, action, button, control or area in an application window. The name of a button used to access the online help.

**hold.** An indication determined by the **job-hold** attribute that is used to keep a job in the queue and prevent Infoprint from scheduling it.

**hostname.** The name given to an AIX system.

**hot folder.** A workstation directory where users copy jobs to submit them to print.

**hypertext.** A way of presenting information online with connections between one piece of information and another. These connections are called hypertext links. See also *hypertext link*.

**hypertext link.** A connection between one piece of information and another. Selecting a link displays the target piece of information.

## I

**IBM InfoColor 70.** A duplex, process color, web-fed printer with 600 dpi pel resolution.

**IBM Infoprint.** A solution of software and hardware products that can supplement or replace the offset presses and copiers in print shops with high-quality, non-impact, black and white, or process color printers. Infoprint takes documents from creation to the published, kitted, and shipped product.

**IBM Infoprint Control.** The administration and management component of Infoprint Manager. It runs on AIX and provides a complete set of system administrator and operator functions to control all aspects of a print environment, as well as job submitter printing functions to submit and control jobs.

**IBM Infoprint Library.** A component of Infoprint Manager. IBM Infoprint Library is a document archival and retrieval system in which job tickets and their associated resource files (graphics, fonts, images, and PostScript data) are stored and from which these data types can be retrieved for reuse.

**Infoprint Manager.** The software component of IBM Infoprint. Infoprint Manager handles the scheduling, archiving, retrieving, and assembly of a print job and its related resource files. It also tracks the finishing and packaging of the printed product.

Infoprint is based on Palladium technology developed at MIT/Project Athena. It conforms to the ISO DPA and POSIX standards.

**IBM Infoprint Network.** The local area network running TCP/IP protocol that InfoPrint uses to communicate among servers, clients, and output devices.

**IBM Infoprint Scan.** The component of Infoprint Manager that allows users to scan images as TIFF files to be included in jobs submitted by Infoprint Submit from a Windows workstation.

**IBM Infoprint Select.** The component of Infoprint Manager that allows users to submit jobs from an OS/2 or Windows workstation.

**IBM Infoprint Submit.** The component of Infoprint Manager that allows users to submit jobs with a job ticket from a Windows or Macintosh workstation.

**IBM Infoprint 20.** A black and white, large-format, cut-sheet workgroup laser printer with optional duplexing and 600-dpi resolution.

**IBM Infoprint 4000.** A duplex, black and white, continuous-forms printer with 600-dpi resolution.

**IBM Infoprint 60.** A duplex, black and white, cut-sheet printer with 600-dpi resolution.

**icon.** A graphic symbol displayed on a screen that a user can select to invoke a function or software application.

**image.** Toned and untoned pels arranged in a pattern.

**image data.** Rectangular arrays of raster information that define an image.

**imagesetter.** A high resolution (1270 dpi–3600+ dpi) printer that uses an Argon (green) laser to write to film using digital input. Imagesetting is the step before Cromalin proofing and platemaking.

**imposition.** The process of arranging pages on a press sheet to ensure the correct order during final cutting, folding, and binding. Electronic imposition builds press sheets automatically during the RIP and outputs film formatted for immediate use in platemaking.

**Infoprint.** IBM Infoprint. In IBM Infoprint software publications, Infoprint Manager or any of its components, especially IBM Infoprint Control.

**initial value document.** Synonym for *default document*.

**initial value job.** Synonym for *default job*.

**initial value object.** Synonym for *default object*.

**initially settable attribute.** An attribute whose value can be established when an object is created but cannot be subsequently set or modified. See also *resettable attribute*; contrast with *non-settable attribute*.

**input focus.** The area of a window where user interaction is possible from either the keyboard or the mouse.

**input tray.** For a printer device, the container that holds the medium upon which the printer prints its output.

**Intelligent Printer Data Stream (IPDS).** An all-points-addressable data stream that enables users to position text, images, and graphics at any defined point on a printed page. Information that the host sends to IBM IPDS printers. This information generally contains basic formatting, error recovery, and character data and

enables the printers to make decisions. An architected host-to-printer data stream that contains both data (text, image, graphics, and bar codes) and controls defining how the data is to be presented. IPDS provides a device-independent interface for controlling and managing all-points-addressable (APA) printers.

**International Organization for Standardization (ISO).** An organization of national standards bodies from various countries established to promote development standards to facilitate international exchange of goods and services, and develop cooperation in intellectual, scientific, technological, and economic activity.

**Internet.** A wide area network connecting thousands of disparate networks in industry, education, government, and research. The Internet network uses TCP/IP as the protocol for transmitting information.

**Internet Protocol.** The set of rules that determines how to route data from its source to its destination in an Internet environment.

**intervening jobs.** In Infoprint, the number of jobs in a queue that are scheduled to print before the job in question.

**IOCA.** Image object content architecture.

**IP address.** The Internet Protocol address of the server in a dotted decimal format where each node is an integer. (For example, 9.99.9.143).

**IPDS.** Intelligent Printer Data Stream.

**ISO.** International Organization for Standardization.

## J

**job.** In Infoprint, an object that represents a request to print or transmit one or more documents together in a single printing session. A job includes the data to be printed or transmitted and resources such as fonts, images, and overlays. Depending on how it was submitted, it may also include a job ticket. Synonymous with *job bundle*, *print job*.

**job bundle.** Synonym for *job*.

**job data.** The page descriptions, merge data, and embellishments that compose a document in a job, either directly or by reference.

**job ID.** A local or a global identifier that identifies a job to a job submitter, administrator, operator, or Infoprint. See *local job identifier*, *global job identifier*.

**job-priority.** In Infoprint, a queuing technique where the next job assigned to the first position in the queue is the one with the highest priority. Contrast with *deadline*, *FIFO (first-in-first-out)*, *longest-job-first*, and *shortest-job-first*.

**job submitter.** In Infoprint, the person who submits jobs for printing. Often, this person is an application programmer who maintains applications that generate data to be printed.

**job ticket.** The customer's hardcopy or electronic instructions listing all the variables describing a print job, either directly or by reference. The print shop can add specifications to the job ticket and can print the job ticket.

**Joint Photographic Experts Group (JPEG).** A compressed graphics format widely used on the Internet.

**JPEG.** Joint Photographic Experts Group.

## K

**Kerning.** In typesetting, adjusting the relative spacing of two characters to improve their appearance and readability. Kerning pairs are specific sets of characters with built-in relative spacing. Some typefaces have as many as 100 kerning pairs.

**keyword.** A name or symbol that identifies a parameter. Part of a command operand that consists of a specific character string, such as **DSNAME=**.

**kitting.** In the print shop environment, packaging the completed published work with attendant binders, tabs, diskettes, and other equipment or information, before shipping the finished product.

## L

**LAN.** Local Area Network.

**laser (light amplification by stimulated emission of radiation).** In IBM printers, a device that emits a beam of coherent light that forms the image on the photoconductor that is subsequently transferred to the paper.

**late binding.** In Infoprint, waiting to assign a job to an actual destination until it is about to be processed. Late binding permits Infoprint to route a job to the first suitable actual destination that becomes available. Contrast with *early binding*.

**LED.** Light-emitting diode.

**light-emitting diode (LED).** The imaging device element for electrophotographic print units.

**lines per inch (lpi).** A measure of the density of the grid used to space halftone dots. Typical grid spacings are 85 lpi (newspaper), 133 lpi (low end), 150 lpi (midrange) and 175+ lpi (high quality).

**Local Area Network (LAN).** A computer network at one location that consisting of devices connected to one



another and communicating. This network can also be connected to a larger network.

**local ID.** Local job identifier.

**local job identifier.** In Infoprint, a job identifier automatically generated by the server, identifying the job to the person who submitted it. Infoprint maps a local job ID to a global job ID.

**locale.** The human language and character set of information presented to a user. In Infoprint, the language Infoprint uses when sending notification and error messages or displaying the Infoprint graphical user interfaces.

**log.** A collection of messages or message segments added to a file for accounting or data collection purposes. To record messages in a file.

**logical destination.** In Infoprint, an object to which users submit their jobs. The destination routes jobs to one or more actual destinations representing output devices such as printers, electronic mail systems, or fax machines. See also *logical printer*; contrast with *actual destination*.

**logical printer.** In Infoprint, a type of logical destination. The logical printer routes jobs to one or more physical printers representing printing devices.

**logical unit (LU).** A type of network accessible unit that enables end users to gain access to network resources and communicate with each other.

**logical unit (LU) 6.2.** A type of logical unit that supports general communication between programs in a distributed processing environment. LU 6.2 is characterized by (a) a peer relationship between session partners, (b) efficient utilization of a session for multiple transactions, (c) comprehensive end-to-end error processing, and (d) a generic application program interface (API) consisting of structured verbs that are mapped into a product implementation.

**longest-job-first.** In Infoprint, a queuing technique where the next job assigned to the first position in the queue is the longest job in the queue. Contrast with *deadline*, *FIFO (first-in-first-out)*, *job-priority*, and *shortest-job-first*.

**lpi.** Lines per inch.

**LU.** Logical unit.

## M

**magnetic-ink character recognition (MICR).** Identification of characters printed with ink that contain particles of magnetic material.

**mainframe processor.** A functional unit that interprets and executes instructions in a large computer to which

other computers are connected so that they can share the facilities the mainframe provides.

**makeready.** All the setup work involved in preparing a press for a print run.

**manage.** In the Infoprint GUI, the action used to put an object into a mode where its icon reflects changes of status.

**mechanical.** A camera-ready layout. The mechanical can consist of multiple sheets or overlays for each spot or process color used. Final images, if not stripped in later, should be at final size, cropped and screened to the correct final-line frequency.

**medium.** In Infoprint, an object representing the physical material upon which a job is printed.

**merge data.** Data that is unique to each copy of a document and that customizes the document; for example, serial numbers or mailing information. Merge data is typically a small percentage of the total data in a document.

**message catalog.** A file of all the possible messages than can display during the processing of an application.

**MICR.** Magnetic ink character recognition.

**Mixed Object Document Content Architecture (MO:DCA).** An architected, device-independent data stream for interchanging documents.

**MO:DCA-P.** Mixed Object Document Content Architecture Presentation.

**modify.** In Infoprint, an action used to modify the values of attributes within the object attributes notebook.

**moire.** Undesirable interference patterns caused by two overprinting halftone screens with incorrect halftone dot angles.

**monospaced.** In typesetting, a typeface in which all the characters have equal widths. Monospaced typefaces are useful for tabulating figures.

**Multiple Virtual Storage (MVS).** An operating system developed by IBM. The design of MVS incorporates an addressing architecture that provides a unique address space to each job in the system.

**MVS.** Multiple Virtual Storage.

## N

**N\_UP.** Pertaining to the number of forms placed together in a layout. Typical layouts are 2\_UP, 4\_UP, 8\_UP, 16\_UP, and so on. N\_UP printing is done to use the maximum area of the print sheet.

**name service.** The DCE service that administers the namespace and provides the network binding information that a client requires to access the server.

**namespace.** A global name repository available to all utilities and API procedures. The namespace contains mappings of object names to other related objects. For example, the namespace provides the mapping of a logical destination to the server in which it resides.

**Network File System (NFS).** A protocol developed by Sun Microsystems that uses Internet Protocol to allow a set of cooperating computers to access each other's file systems as if they were local.

**newline options.** The different ways in which the printer determines how lines are delimited in a document data stream.

**NFS.** Network File System.

**non-process-runout (NPRO).** A printer function that moves the last printed sheet to the stacker of the printer device.

**non-settable attribute.** An attribute that is neither initially settable nor resettable. The values for these attributes are controlled by Infoprint. Contrast with *initially settable attribute*, *resettable attribute*.

**notification.** The act of reporting the occurrence of events. In Infoprint, notification of events appears as messages in event logs or messages sent to administrators, operators, and job submitters. In the Infoprint GUI, notification of events also appears as changes to the appearance of icons.

**notification-profile.** In Infoprint, an attribute associated with an object that contains information designating the people to whom Infoprint sends notification about events for that object, which event information it sends, and how it sends the information.

**NPRO.** Non-process-runout.

## O

**object.** A collection of attributes that represent a physical or logical entity in the print system. For example, a specific printer device is represented by an actual destination (physical printer) object. An object is identified by its object name. Objects are grouped into classes. See also *object class*.

**object class.** A group of objects that share a common definition and therefore share common properties, operations, and behavior as defined by their attributes. For example, all Infoprint queue objects are in the same object class and each queue has the same set of queue attributes. However, the values for those attributes can differ for each queue within the queue object class.

**Object Identifier (OID).** In architecture, a notation that assigns a globally unambiguous identifier to an object or a document component. The notation is defined in international standard ISO.IEC 8824(E).

**object name.** The alphanumeric term that identifies an object.

**object state.** The state of an object indicates its availability and readiness for performing its functions. An object can be in one of a number of states such as ready, busy, or unknown.

**OCR.** Optical character recognition.

**octet.** A byte that consists of eight binary digits (bits).

**offset stacking.** In certain printer devices, a function that allows the printer to offset the printed output pages for easy separation of the jobs.

**OID.** Object Identifier.

**open destinations window.** In the Infoprint GUI, the action used to open a new application window displaying the logical and actual destinations associated with a queue.

**Open Prepress Interface (OPI).** An industry standard for replacing low-resolution images in review documents with high-resolution images needed for high-quality final output.

**Open Software Foundation (OSF).** A nonprofit research and development organization created by a consortium of companies that work together to develop software in the open systems market. OSF developed the Distributed Computing Environment (DCE).

**open window.** In the Infoprint GUI, the action used to open a new application window representing one or more objects displayed in the currently open application window.

**operation.** An action performed on one or more data items.

**operator.** In Infoprint, the person responsible for printer devices. Also, this person performs a subset of tasks for Infoprint queues and actual destinations, and performs some job-related tasks.

**OPI.** Open Prepress Interface.

**optical character recognition (OCR).** Conversion of scanned text to editable ASCII characters.

**option.** A modifier of a command that specifies the action of the command. A dash usually precedes an option. Synonymous with *flag*. See also *keyword*.

**orphan logical destination.** In the Infoprint GUI, an object that represents a logical destination that is not associated with an existing queue.

**orphan logical printer.** In the Infoprint GUI, an object that represents a logical printer that is not associated with an existing queue.

**OSF.** Open Software Foundation

**overlay.** A collection of constant data, such as lines, shading, text, boxes, or logos, that is electronically composed in the host processor and stored in a library, and that can be merged with variable data during printing.

## P

**PAC.** Privilege Attribute Certificate.

**page definition.** A resource that contains the formatting controls for line data. In Infoprint, a resource that defines the rules of transforming line data into composed pages and text controls.

**page segment.** A resource that contains composed text and images, prepared before formatting and included during printing.

**Palladium.** A distributed print system developed at MIT/Project Athena with participation from Digital Equipment Corporation (DEC), International Business Machines (IBM), and Hewlett-Packard (HP). It is a reference implementation for the OSI Document Printing Architecture (DPA) standard, ISO/IEC 10175. Infoprint was designed using Palladium concepts.

**pane.** In the Work Area of the Infoprint administrator's GUI, an area containing a group of objects of a specific type, such as an actual destinations pane.

**parent/child relationship.** In Infoprint, servers, queues, and destinations are related to one another in a parent/child relationship. For example, a server is the parent of all the queues that reside in that server and these queues are its children.

**pass through.** In Infoprint, referring to options submitted with a job that are used by the device driver, but not Infoprint. Infoprint does not process or validate this information; it passes it along to the device driver. See *device driver*.

**path.** The route used to locate files; the storage location of a file. A fully qualified path lists the drive identifier (if any), directory name, subdirectory name (if any), and file name with the associated extension.

**pause.** In Infoprint, the action used to temporarily halt the printing of jobs on physical printers or the distribution of jobs from servers or queues.

**pdcrds.** In Infoprint, a utility used to create directories within the DCE namespace.

**pdcreate.** In Infoprint, the command used to create a new object and set its attributes to specified values.

**PDF.** Portable Document Format. Printer description file.

**pdmsg.** In Infoprint, a utility used to display information about a message.

**pdpr.** In Infoprint, the command used to create and submit a job, consisting of one or more documents, to a server for printing or transmission.

**perfect binding.** A type of book binding in which the pages are held together with flexible adhesive. Contrast with *edition binding*, *spiral binding*, *wire-o binding*.

**permissions.** In AIX, codes that determine who can access a file and what operations they can perform on the file.

**physical printer.** In Infoprint, a type of actual destination that represents a printer device. See also *printer device*.

**piobe.** The standard printer input/output backend program used by AIX for printing. See also *ainbe*.

**pipe-pull.** In Infoprint, a document transfer method where Infoprint saves the documents in a file and transfers the address of the file to the server. Infoprint transfers the file to the server upon the request from the server. This is an efficient transfer method for large jobs and is the default transfer method at job submission. Contrast with *with-request*.

**plex.** A document or actual destination attribute used to define the placement of output images on the page. See the plex values *simplex* and *tumble*.

**plug-ins.** A component of Adobe PageMaker that enables users to incorporate variable data into fixed-text documents to produce personalized or customized documents.

**Portable Document Format (PDF).** An Adobe PostScript data format that can be viewed or printed.

**Portable Operating System Interface for Computer Environments (POSIX).** An Institute of Electrical and Electronics Engineers (IEEE) standard for computer operating systems.

**POSIX.** Portable Operating System Interface for Computer Environments.

**PostScript.** Adobe's page-description language. PostScript has become a standard for graphic design and layout software. PostScript files can contain both vector and raster data. Fonts are described using PostScript coding. Many desktop publishing systems produce PostScript data as their output data stream.

**PostScript printer description (PPD).** A file that contains options for printing PostScript data on various printer devices.

**PPD.** PostScript printer description.

**preflight.** To assess all resources for a job before the actual print run.

**prepress.** Work done in the print shop before printing a job, such as preparing data and art, page imposition, color retouching, electronic editing, and page layout.

**print database.** The set of files on disk which provide a permanent repository for the attributes of all print objects such as logical destinations, queues, and actual destinations.

**print job.** Synonym for *job*.

**Print Quality Enhancement (PQE).** A printer facility that provides edge smoothing along diagonal lines, fine fidelity protection, and independent boldness control.

**Print Services Facility (PSF).** Any of several programs, including PSF for AIX, PSF/MVS, PSF/VM, and PSF/VSE, that produce printer commands from the data sent to them.

**print system.** A group of one or more print servers and one or more printing devices, which may or may not be located in the same geographical area. The components of a print system are assumed to be interconnected in some manner, providing at least one network interface to print clients, and acting synergistically to supply the defined document print service. (D)

**printable document.** In Infoprint, an object that represents text or data to be printed by a job. Contrast with *resource document*.

**printer description file (PDF).** A file that contains options for printing PostScript data on a specific printer device.

**printer device.** The physical output device that performs the printing function. See also *physical printer*.

**printer driver.** A file that describes the physical characteristics of a printer or other peripheral device, and is used to convert graphics and text into device-specific data at the time of printing or plotting. Synonymous with *device driver*.

**priority.** In Infoprint, a number assigned to a job that determines its precedence in being printed. Jobs with higher priority numbers are handled before jobs with lower priority numbers.

**Privilege Attribute Certificate (PAC).** In DCE, a certified set of access privileges that can be presented by a user or administrator to establish access rights to objects.

**process color.** Color made up of CMYK inks simulating a specified color. This is the traditional method of reproducing continuous tone color images

(color separations). Because of the nature of color inks, certain inks do not reproduce well.

**processor.** In a computer, a functional unit that interprets and executes instructions. A processor consists of at least an instruction control unit and an arithmetic and logic unit. (T)

**promote.** In Infoprint, an action used to advance a queued job to the beginning of the queue so it will print on the next available printer that can handle that job.

**protocol.** A set of semantic and syntactic rules that determines the behavior of functional units in achieving communication.

**PSF.** Print Services Facility.

**PSF destination support system.** In Infoprint, the destination support system that communicates with PSF for AIX to print jobs.

**PSF physical printer.** In Infoprint, the object representing a printer device that uses the PSF destination support system.

## Q

**QuarkXpress.** A desktop publishing system produced by Quark, Incorporated.

**queue.** In Infoprint, an object that manages a collection of jobs that are waiting to print. A queue receives jobs from one or more logical destinations and sends jobs to one or more actual destinations. A line or list formed by items waiting for processing.

## R

**raster.** A pattern of dots comprised of varying data depths. Black and white images are one-bit (on/off); grayscale images are 8-bit (256 levels); RGB images are 24-bit; CMYK images are 32-bit.

**raster image processor (RIP).** A processor in which a PostScript data stream is converted into dot patterns that are transferred to the final print medium. Infoprint uses an Adobe RIP to convert PostScript to IPDS for such printers as the IBM Infoprint 4000 and IBM Infoprint 60.

**rc.pd.** In Infoprint, a utility used to start the Infoprint servers listed in the */etc/pd.servers* file.

**read-only.** In Infoprint, describes an attribute value that cannot be set by the user but may change based on other activity.

**ready.** A state in which an object is ready and able to perform tasks. An available resource, such as a value of the **media-ready** attribute. Contrast with *supported*.

**red, green, blue (RGB).** The colors of CRT display phosphors. RGB images are for screen display only. They must be converted to CMYK images before printing.

**registration.** The accuracy of printing on paper relative to the edges of the paper. The accuracy of printing a single color (cyan, magenta, or yellow) relative to black. The accuracy of printing on one side of a page relative to printing on the reverse side of the page.

**Remote Procedure Call (RPC).** A DCE component that manages communication between clients and servers in a DCE environment. It allows requests from a client program to access a procedure anywhere in the network.

**reprographics.** The process of copying or duplicating documents or information.

**requested.** In Infoprint, pertaining to the specific values of attributes requested by a job when it is submitted. The requested attribute values of a job are validated against supported attribute values for a physical printer to determine if the printer can handle that job. Contrast with *supported*.

**resettable attribute.** An attribute whose value can be set or modified after an object has been created, assuming the object is in an appropriate state to be modified. See also *initially settable attribute*; contrast with *non-settable attribute*.

**resource.** In AFP, a file containing a collection of printing instructions used when printing a job. Resources include fonts, overlays, form definitions, page definitions, and page segments.

**resource context.** In Infoprint, an object that contains directory path information that helps the print system locate resources needed for printing a job. The resources include fonts, overlays, form definitions, page definitions, and page segments.

**resource document.** In Infoprint, an object that represents a resource, such as graphics or fonts, used by a job to print a printable document. Contrast with *printable document*.

**resubmit.** In Infoprint, an action used to reroute pending or retained jobs to a different logical destination than the one through which the job was originally submitted.

**resume.** In Infoprint, the action used to resume the printing of paused jobs or resume the distribution of jobs from paused servers or queues.

**retained job.** In Infoprint, an object that represents a job that is being stored in the print system, normally

after the completion of printing the job, for a specified amount of time. A retained job does not reside in a queue.

**retention.** The process of storing data after completion of a process for a certain length of time.

**retrieval.** The process of bringing digital archived data out of storage and into online memory for reuse. See also *archiving*.

**RGB.** Red, green, blue.

**RIP.** Raster image processor. To convert data to dot patterns using a raster image processor.

**root user.** In the AIX environment, the system user with the most authority who can log in and execute restricted commands, shut down the system, and edit or delete protected files. Synonymous with *superuser*.

**RPC.** Remote Procedure Call.

**RS/6000.** A family of workstations and servers based on IBM's POWER architecture. They are primarily designed for running multi-user numerical computing applications that use the AIX operating system.

## S

**scanner.** A device that converts hardcopy source data into digital format (halftone dots) to avoid retyping the data.

**scheduler.** In Infoprint, the scheduling method that the queue uses when assigning a job to an actual destination.

**separator sheet.** The sheet of paper, blank or otherwise, that separates documents within a job. See also *auxiliary sheet*.

**server.** In Infoprint, the object that accepts configuration, management, and printing requests, performs the requested operations, and sends responses back as a result of the operation.

**settable attribute.** See *initially settable attribute*, *resettable attribute*.

**severity.** An indication of how serious an error condition is.

**shell.** In the AIX operating system, a command interpreter that acts as an interface between the user and the operating system. In Infoprint documentation, all shell examples use the Korn shell.

**shift-out, shift-in code.** Control characters used to indicate the beginning and end of a string of double-byte, ideographic characters.

**shortest-job-first.** In Infoprint, a queuing technique where the next job assigned to the first position in the queue is the shortest job in the queue. Contrast with *deadline*, *FIFO (first-in-first-out)*, *job-priority*, and *longest-job-first*.

**shut down.** In Infoprint, the action used to halt all server or actual destination processes without deleting the server or actual destination.

**signature.** A group of pages that are printed, folded, cut, and bound together. Manual placement of pages on the signature is determined using a folding dummy.

**simplex.** In Infoprint, the value of the document or actual destination **plex** attribute indicating that output images are placed on the media in a head-to-head format, so that the top of one image is at the same edge as the top of the next image. Depending on the value of the document or actual destination **sides** attribute, the document may be printed on one or both sides of the paper. Contrast with *tumble*; see also *simplex printing (2)*, *duplex printing (2)*.

**simplex printing.** Printing on only one side of the paper. Contrast with *duplex printing (1)*. Printing on one or both sides of the paper, placing output images on the media in a head-to-head format, so that the top of one image is at the same edge as the top of the next image. Contrast with *tumble duplex printing*; see also *duplex printing (2)*.

**SMIT.** System Management Interface Tool.

**SNA.** Systems Network Architecture.

**spiral binding.** A type of book binding in which wire or plastic coils are threaded through a series of holes or slots in the binding edge. Contrast with *edition binding*, *perfect binding*, *wire-o binding*.

**spot color.** Individual colored inks formulated to exactly match a specified color. Spot color is used when CMYK process color is unable to produce a reasonable facsimile of the color or when vivid color is needed. Spot color also is used when fluorescent or metallic colors are needed.

**spread.** In color printing, an area whose dimensions have been enlarged to eliminate white space between it and another color. Contrast with *choke*.

**start sheet.** The sheet of paper, blank or otherwise, that can precede a job. See also *auxiliary sheet*.

**state.** Synonym for *object state*.

**stripping.** The process of mechanically assembling film into plate layouts. Page imposition takes place during stripping.

**subnet mask.** A bit template indicating which part of an IP address represents the network. A 1 in the subnet

mask means that the corresponding bit in the IP address is part of the network address; a 0 means that it is not. For example, if the IP address is 9.99.12.137 and the subnet mask is 255.255.255.0, the network address is 9.99.12.0.

**subnetwork.** Any group of nodes that have common characteristics, such as the same network ID. In the AIX operating system, one of a group of multiple logical divisions of another network, such as can be created by TCP/IP.

**subtractive color system.** A system that reproduces an image by mixing (adding) appropriate quantities of cyan, magenta, and yellow paints on white paper. These paints reflect certain colors and absorb—or subtract—others. Contrast with *additive color system*.

**superuser.** Synonym for *root user*.

**supported.** In Infoprint, pertaining to the specific job attribute values that the actual destination can accept during job validation. Infoprint validates the requested attribute values of the job against the supported attribute values of the actual destination to determine whether the actual destination can handle that job. Contrast with *requested*.

**synchronous.** Occurring with a regular or predictable time relationship to a specified action. Contrast with *asynchronous*.

**system administrator.** Synonym for *administrator*.

**System Management Interface Tool (SMIT).** In the AIX operating system, an interface tool for installation, maintenance, configuration and diagnostic tasks. SMIT allows you to perform tasks without entering any commands.

**Systems Network Architecture (SNA).** The description of IBM's logical structure, formats, protocols, and operational sequences for transmitting units through, and controlling the configuration and operation of, networks.

## T

**table reference character (TRC).** An optional control character in a print data set. The TRC identifies the font used to print the record and can be used to select a font during printing.

**Tagged Image File Format (TIFF).** A digital format for storing scanned images. TIFF files are also referred to as raster format files (as opposed to vector format files). When used in desktop publishing, TIFF files produce only a low-resolution FPO image; the high-resolution data remains on the hard disk.

**task help.** A type of online help that provides a list of tasks that can be completed with a selected object.

When you select a task, the help provides step-by-step information about how to complete the task.

**TCP/IP.** Transmission Control Protocol/Internet Protocol.

**TCP/IP-attached printer.** A printer device attached to an RS/6000 through telecommunication lines using the TCP/IP protocol. In Infoprint, a PSF physical printer that represents a TCP/IP-attached printer device. See also *AIX-attached printer*, *channel-attached printer*, *direct-attached printer*, *upload-SNA-attached printer*, *upload-TCP/IP-attached printer*.

**template.** In the Infoprint GUI, an object that represents a set of default attribute values that has been defined for creating a particular type of object, such as an actual destination.

**ticket.** See *job ticket*, *DCE ticket*.

**TIFF.** Tagged Image File Format.

**Transmission Control Protocol/Internet Protocol (TCP/IP).** A set of communication rules used in the Internet and in any network that follows the U.S. Department of Defense standards for inter-network protocol. TCP provides a reliable host-to-host protocol between hosts in packet-switched communications networks and in interconnected systems of such networks. It assumes that the Internet Protocol (IP) is the underlying protocol. See also *Internet Protocol*.

**trapping.** In desktop publishing, the amount of overlap in overprinting colors. Trapping prevents white paper showing through gaps caused by normal errors in registration. On sheet-fed presses, trapping is usually 0.25 point. See also *choke*, *spread*.

**TRC.** Table reference character.

**tumble.** In Infoprint, the value of the document or actual destination **plex** attribute indicating that output images are placed on the media in a head-to-toe format, so that the top of one image is at the same edge as the bottom of the next image. The document must be printed on both sides of the paper. Contrast with *simplex*.

**tumble duplex printing.** Printing on both sides of the paper, placing output images on the media in a head-to-toe format, so that the top of one image is at the same edge as the bottom of the next image. Contrast with *simplex printing (2)*, *duplex printing (2)*.

## U

**UCR.** Under color removal.

**under color removal (UCR).** Conversion of neutral color areas to black ink that reduces use of CMY inks, improves trapping, and reduces setup time. Generally, UCR is performed during image scanning, but some

RIPs perform it during processing. Synonymous with *gray component replacement (GCR)*.

**unmanage.** In the Infoprint GUI, the action used to put an object into a mode where its icon does not reflect the changes of status for the object.

**upload printer.** See *upload-SNA-attached printer*, *upload-TCP/IP-attached printer*.

**upload-SNA-attached-printer.** In Infoprint, a PSF physical printer that represents a printer device attached to an MVS system and managed by PSF/MVS. Infoprint communicates with the MVS system through the SNA network. See also *AIX-attached printer*, *channel-attached printer*, *direct-attached printer*, *TCP/IP-attached printer*, *upload-TCP/IP-attached printer*.

**upload-TCP/IP-attached-printer.** In Infoprint, a PSF physical printer that represents a printer device attached to an MVS system and managed by PSF/MVS. Infoprint communicates with the MVS system through the TCP/IP network. See also *AIX-attached printer*, *channel-attached printer*, *direct-attached printer*, *TCP/IP-attached printer*, *upload-SNA-attached printer*.

## V

**validate.** In Infoprint, to compare the attribute values requested by a job with the supported attribute values of the actual destinations in the system and to determine whether there is an actual destination capable of printing or transmitting the job.

**value.** A specific characteristic of an attribute.

**variable.** A name used to represent a data item whose value can change while the program is running.

**variable data.** Data that can be changed between jobs. For example, a form letter (constant data) can be merged with variable data such as a customer's name and address to produce personalized copies of documents.

**varnish.** A protective layer applied to a finished sheet, usually for photos, but sometimes used as a design element due to its reflective nature. Varnishes can be tinted.

**vector.** An absolute coordinate point and line in space. PostScript files can contain vector artwork. Vector files are converted to rasters during the RIP process.

**velox.** A black and white photographic print made from a halftone negative, to be used as a proof copy.

**vignette.** An image with soft, fade-away edges.

**Virtual Machine (VM).** An IBM licensed product that manages the resources of a single computer so that multiple computing systems appear to exist. A virtual data processing system that appears to be at the

exclusive disposal of a particular user, but whose functions are accomplished by sharing the resources of a real data processing system. (T)

**Virtual Storage Extended (VSE).** An IBM licensed program whose full name is the Virtual Storage Extended/Advanced Function. It is a software operating system controlling the execution of programs.

**Visual Systems Management (VSM).** In AIX, a type of graphical user interface that allows system management through the direct manipulation of objects.

**VM.** Virtual Machine.

**VSE.** Virtual Storage Extended.

**VSM.** Visual Systems Management.

## W

**web.** A roll of paper used in web or rotary printing.

**well.** In the Infoprint administrator's GUI, an area within a pane that contains a group of objects related to the objects in the pane; for example, a queues well within a servers pane.

**what you see is what you get (WYSIWYG).** Refers to the fact that the composite image displayed on the screen at a computer workstation has the appearance of the final printed image.

**window.** A rectangular area of the screen that you can move about, place on top of, or pull under other windows, or reduce to an icon.

**wire-o binding.** A continuous double series of wire loops run through punched slots along the binding side of a booklet. Contrast with *edition binding*, *perfect binding*, *spiral binding*.

**with-request.** In Infoprint, a document transfer method where the client transfers the documents directly to the server. Contrast with *pipe-pull*.

**workstation.** A terminal or microcomputer, usually one that is connected to a mainframe or to a network, at which a user can use applications.

**write access.** A level of authorization that grants the ability to modify data.

**WYSIWYG.** What you see is what you get.

## X

**X-Windows.** A network-transparent windowing system developed by MIT. It is the basis for Enhanced X-Windows, which runs on the AIX Operating System.

**xerography.** A dry printing process using corona-charged photoconductive surfaces to hold latent

images that are developed with a dry toner and then transferred to paper and fused with heat.

**Xstation.** A terminal that is connected through a network to an RS/6000 system, from which a user can perform command-line functions and run X-Windows based applications.

**Xtensions.** A UNIX-provided software component that enables users to incorporate variable data into fixed-text documents to produce personalized or customized documents.

## Numerics

**3170 destination support system.** The destination support system used by the IBM InfoColor 70 to print jobs.

**3170 physical printer.** A physical printer representing an IBM InfoColor 70 printer device.



---

## Notices

---

### Licenses

References in this publication to products or services of IBM do not suggest or imply that IBM will make them available in all countries where IBM does business or that only products or services of IBM may be used. Noninfringing equivalents may be substituted, but the user must verify that such substitutes, unless expressly designated by IBM, work correctly. No license, expressed or implied, to patents or copyrights of IBM is granted by furnishing this document. You can send license inquiries, in writing, to the IBM Director of Licensing, IBM Corporation, 500 Columbus Avenue, Thornwood, NY 10594, USA.

Licensees of this program who wish to have information about it for the purpose of enabling: (1) the exchange of information between independently created programs and other programs (including this one) and (2) the mutual use of the information, which has been exchanged, should contact: IBM Corporation, Printing Systems Legal Department, Mail Drop 002S, Boulder, Colorado 80301 USA. Such information may be available, subject to appropriate terms and conditions, including in some cases, payment of a fee.

---

### Trademarks

The following are trademarks or registered trademarks of International Business Machines Corporation:

- ACF/NCP
- ACF/VTAM
- ADSM/6000
- Advanced Distributed Storage Manager/6000
- Advanced Function Common Control Unit
- Advanced Function Presentation
- Advanced Peer-to-Peer Networking
- AFCCU
- AFP
- APPN
- AIX<sup>®</sup>
- AIXwindows<sup>®</sup>
- AIX/6000
- Application System/400
- AS/400
- Bar Code Object Content Architecture
- BCOCA
- DB2\*/6000
- GXT150M
- IBM<sup>®</sup>
- InfoColor<sup>®</sup>
- InfoPrint<sup>®</sup>
- Intelligent Printer Data Stream
- IPDS
- Magstar
- Micro Channel
- MO:DCA
- NCP
- NetView<sup>®</sup>
- Operating System/400

OS/2  
OS/400  
POWERserver  
POWERstation  
Print Services Facility for AIX  
Proprinter<sup>®</sup>  
PS/2<sup>®</sup>  
PSF  
PSF for AIX  
QuietWriter<sup>®</sup>  
RS/6000<sup>®</sup>  
System/370  
SNA Gateway/6000  
SNA Server/6000  
SystemView  
S/370  
S/390  
VTAM  
WIN-OS/2

The following are trademarks of other companies:

- Acrobat, Adobe, Adobe PostScript Extreme, Adobe PageMaker, and PostScript are trademarks of Adobe Systems, Incorporated.
- Ethernet is a trademark of the Xerox Corporation.
- Helvetica is a trademark of Linotype-Hell Company.
- Hewlett-Packard, Hewlett-Packard Printer Control Language, HP, and LaserJet are trademarks of Hewlett-Packard Company.
- i-data is a trademark of i-data international a-s.
- Lotus Notes is a trademark of Lotus Development Corporation.
- Macintosh is a trademark of Apple Computer, Inc.
- Microsoft is a trademark of Microsoft Corporation.
- NFS and Sun are trademarks of Sun Microsystems, Inc..
- Novell is a trademark of Novell, Inc.
- OSF is a trademark of Open Software Foundation.
- QuarkXPress is a trademark of Quark Corporation.
- R/3, SAP, and SAPscript are registered trademarks of SAP AG.
- TIFF is a trademark of Aldus Corporation.
- Times New Roman is a trademark of Monotype Typography, Inc.
- UNIX is a trademark in the United States and other countries, licensed exclusively through X/Open Company Limited.
- Windows and Windows NT are registered trademarks of Microsoft Corporation.

---

# Index

## Special Characters

`\install_path\reslib` 424, 427  
\* (wildcard) 9  
`\usr\lpp\psf\reslib` directory 423  
`/etc/services` file 176, 179, 652  
`install_path\reslib` directory 425  
`/usr/lib/lpd/pio/pio/predef` directory 352  
`/usr/lpd/pio/predef` directory 365  
`/usr/lpp/pd/attr` directory 329  
`/usr/lpp/psf/reslib` directory 422, 424, 425, 426, 427

## Numerics

00000000.tab file 308  
240-pel  
    output for PDF 291  
    output for PostScript 291  
300-pel  
    output for PDF 291  
    output for PostScript 291  
3170 destination support system (DSS) 326  
40010000.tab file 308  
40040000.tab file 308  
480-pel  
    output for PDF 291  
    output for PostScript 291  
600-pel  
    output for PDF 291  
    output for PostScript 291

## A

accept-jobs attribute  
    actual destination 332  
accept-unsupported-jobs attribute  
    server 623  
account-text attribute  
    default document 453  
    document 453  
accounting data  
    reporting by destination 134  
    reporting by job 131  
    reporting by user  
        for all users 130, 135  
        for specified user 132, 136  
accounting-exit attribute  
    actual destination 332  
accounting information  
    for a specific server 19  
    specified time 19  
ack-interval attribute  
    actual destination 333  
actual destinations, attributes of  
    accept-jobs 332  
    accounting-exit 332  
    ack-interval 333  
    add-carriage-returns 334  
    add-line-feeds 334  
    actual destinations, attributes of (*continued*)  
        ascii-character-mapping 335  
        ascii-font-map 335  
        associated-queue 336  
        associated-server 337  
        attachment-type 337  
        attribute-map 338  
        audit-exit 339  
        automatic-postscript-mode-switch 339  
        auxiliary-sheet-selections-supported 340  
        booklet-fold 341  
        cancel-individual-document-supported 341  
        carriage-control-types-supported 341  
        character-mappings-supported 342  
        checkpoint-at-stacker 343  
        checkpoint-formats-supported 343  
        color-mapping-table 344  
        color-rip-servers 344  
        command 349  
        connection-timeout 345  
        content-orientations-supported 345  
        convert-to-ebcdic-supported 346  
        data-fidelity-problem-reported-supported 346  
        default-font-fidelity-action 347  
        default-font-resolution 347  
        default-input-tray 348  
        descriptor 348  
        destination-command 349  
        destination-data-stream 350  
        destination-locations 351  
        destination-model 351  
        destination-name 352  
        destination-needs-attention-time 353  
        destination-needs-key-operator-attention-time 353  
        destination-pass-through 353  
        destination-poll-interval 354  
        destination-realization 354  
        destination-register-threshold 355  
        destination-release-timer 355  
        destination-state 356  
        destination-support-system 357  
        destination-tcpip-internet-address 358  
        destination-tcpip-port-number 359  
        destination-timeout-period 359  
        device-name 360  
        device-support-system 357  
        document-attributes-supported 361  
        document-finishings-supported 363  
        document-formats-ripped-at-destination 364  
        document-formats-supported 364, 646  
        document-types-supported 366  
        dss-job-message-disposition 367  
        dss-job-message-log-size 367  
        dss-job-message-log-wrap 368  
        ebcdic-character-mapping 368  
        enabled 369  
        end-message-supported 369  
        end-sheets-supported 370

actual destinations, attributes of *(continued)*

- font-resolutions-supported 370
- force-destination-setup 371
- force-printer-setup 371
- form-definition 372
- halftones-supported 372
- image-fit-supported 374
- image-length 374
- image-out-formats-supported 375
- image-width 376
- input-data-user-exit 377
- input-trays-medium 377
- input-trays-supported 379
- intervention-timer 379
- job-attributes-supported 380
- job-batches-ready 380
- job-finishings-supported 381
- job-retry-count-limit 381
- job-retry-interval 382
- job-rip-actions-supported 382
- job-size-range-ready 383
- job-size-range-supported 384
- job-start-wait-supported 385
- list-of-managers 385
- locations 351
- log-accounting-data 386
- logical-destinations-assigned 387
- managers 385
- maximum-concurrent-jobs 387
- maximum-copies-supported 388
- maximum-fonts-to-keep 389
- maximum-overlays-to-keep 389
- maximum-segments-to-keep 390
- media-ready 390
- media-supported 391
- message 392
- message-font-type 393
- message-form-definition 393
- model 351
- non-process-runout-timer 394
- notification-profile 394
- notify-operator 396
- number-up-supported 396
- object-class 397
- offset-stacking-available 397
- operators 396
- optimize-for-multiple-copies 398
- orientations-supported 345
- other-options 353
- output-appearances-supported 399
- output-bin 399
- output-bin-numbers 400
- output-bins-supported 401
- output-data-user-exit 402
- output-format-supported 402
- overlay 403
- page-select-supported 403
- pcl-server-address 404
- pcl-server-port 404
- physical-printer 352
- plex 405

actual destinations, attributes of *(continued)*

- plexes-supported 405
- postscript-server-address 406
- presentation-fidelity-problem-reported 407
- print-edge-marks 408
- print-qualities-supported 408
- print-queue 409
- print-queue-name 409
- printer 352
- printer-command 349
- printer-data-stream 350
- printer-end-sheet 409
- printer-escape-codes 410
- printer-locations 351
- printer-memory 411
- printer-model 351
- printer-name 352
- printer-needs-attention-time 353
- printer-needs-key-operator-attention-time 353
- printer-pass-through 353
- printer-realization 354
- printer-register-threshold 355
- printer-release-timer 355
- printer-resolutions-ready 412
- printer-resolutions-supported 413
- printer-s370-channel-device-address 416
- printer-s370-channel-slot-number 416
- printer-separator-sheet 414
- printer-start-sheet 414
- printer-state 356
- printer-tcpip-internet-address 358
- printer-tcpip-port-number 359
- problem-message 417
- protected-attributes 417
- psf-tray-characteristics 418
- qualities-supported 408
- register-threshold 355
- registered-with-spooler 421
- remote-queue 421
- resource-context 422, 423
- resource-context-form-definition 424
- resource-context-overlay 425
- resource-context-page-definition 426
- resource-context-page-segment 427
- reverse-output 428
- rip-ini-file 428
- rip-server 429
- scanner-corrections-supported 429
- scheduler-sort-primary-order 429
- scheduler-sort-secondary-order 430
- schedulers-supported 430
- screen-frequencies-supported 431
- separator-sheets-supported 431
- shared-printer-name 432
- sides 433
- sides-supported 433
- snmp-active 434
- snmp-community-name 434
- snmp-retry-count 435
- snmp-timeout 435
- start-message-supported 436

- actual destinations, attributes of *(continued)*
  - start-sheets-supported 436
  - table-reference-characters-supported 437
  - timeout-period 359
  - transform-sequence 438
  - use-snmp 438
  - used for job scheduling 695
  - used for job validation 695
  - wait-for-job-completion 439
  - warning-message 439
  - x-image-shift-supported 440
  - y-image-shift-supported 441
- actual-destinations-assigned attribute
  - queue 610
- actual-destinations-ready attribute
  - queue 610
  - server 624
- actual-destinations-requested attribute
  - default job 524
  - job 524
- actual-destinations-supported attribute
  - server 624
- add-carriage-returns attribute
  - actual destination 334
- add-line-feeds attribute
  - actual destination 334
- address1-text attribute
  - default document 454
  - document 454
- address2-text attribute
  - default document 454
  - document 454
- address3-text attribute
  - default document 455
  - document 455
- address4-text attribute
  - default document 455
  - document 455
- admingui utility
  - arguments 128
  - description 128
  - examples 128
  - flags 128
  - syntax 128
- advancing a job to the top of a queue 72
- afpsplit utility
  - arguments 129
  - description 129
  - examples 129
  - flags 129
  - syntax 129
- ainurpt1 utility
  - description 130, 134
  - examples 130, 134
  - syntax 130, 134
- ainurpt2 utility
  - description 131, 135
  - examples 131, 135
  - syntax 131, 135
- ainurpt3 utility
  - description 132, 136
- ainurpt3 utility *(continued)*
  - examples 132, 136
  - syntax 132, 136
- ainurpt4 utility
  - description 138
  - examples 138
  - syntax 138
- ainurpt5 utility
  - description 139
  - examples 139
  - syntax 139
- ainurpt6 utility
  - description 140
  - examples 140
  - syntax 140
- AIX destination support system (DSS) 326
- AIX print queues
  - migrating 159
- ANSI carriage-control characters
  - encoded in ASCII 240
  - encoded in EBCDIC 240
- apka2e exit program 248
- arguments
  - general description of 8
  - of commands
    - lprafp 15
    - mkfntmap 17
    - pdaccount 20
    - pdclean 23
    - pdcreate 27
    - pddelete 31
    - pddisable 35
    - pdenable 38
    - pdls 45
    - pdmod 54
    - pdpause 60
    - pdpr 67
    - pdpromote 73
    - pdq 77
    - pdreorder 80
    - pdresubmit 83
    - pdresume 86
    - pdrm 89
    - pdset 94
    - pdshutdown 99
    - pdspace 102
  - of utilities
    - admingui 128
    - afpsplit 129
    - cfu 142
    - jsmigr 149
    - opergui 151
    - pdcrflt 155
    - pdcrmed 156
    - pdinitports 157
    - pdmigpp 159
    - pdmincfg 161
    - sense 167, 169
    - start\_server 177
    - startsrv 179
    - stop\_server 180

- ascii-character-mapping attribute
  - actual destination 335
- ASCII characters
  - conversion table for sap2afp transform 302
- ascii-font-map attribute
  - actual destination 335
- asciinp exit program 248
- asciinpe exit program 248
- assign-to-destination attribute
  - queue 611
- assign-to-printer attribute
  - queue 611
- associated-queue attribute
  - actual destination 336
  - logical destination 579
- associated-server attribute
  - actual destination 337
  - auxiliary sheet 443
  - default document 456
  - log 573
  - logical destination 579
  - medium 604
  - queue 611
  - resource context 620
- attachment-type attribute
  - actual destination 337
- attribute-map attribute
  - actual destination 338
- attribute operators for filters on the pdls command 42
- attributes
  - accept-jobs
    - actual destination 332
  - accept-unsupported-jobs
    - server 623
  - account-text
    - default document 453
    - document 453
  - accounting-exit
    - actual destination 332
  - ack-interval
    - actual destination 333
  - actual-destinations-assigned
    - queue 610
  - actual-destinations-ready
    - queue 610
    - server 624
  - actual-destinations-requested
    - default job 524
    - job 524
  - actual-destinations-supported
    - server 624
  - add-carriage-returns
    - actual destination 334
  - add-line-feeds
    - actual destination 334
  - address1-text
    - default document 454
    - document 454
  - address2-text
    - default document 454
    - document 454
  - attributes (*continued*)
    - address3-text
      - default document 455
      - document 455
    - address4-text
      - default document 455
      - document 455
    - ascii-character-mapping
      - actual destination 335
    - ascii-font-map
      - actual destination 335
    - assign-to-destination
      - queue 611
    - assign-to-printer
      - queue 611
    - associated-queue
      - actual destination 336
      - logical destination 579
    - associated-server
      - actual destination 337
      - auxiliary sheet 443
      - default document 456
      - log 573
      - logical destination 579
      - medium 604
      - queue 611
      - resource context 620
    - attachment-type
      - actual destination 337
    - attribute-map
      - actual destination 338
    - audit-exit
      - actual destination 339
    - authorize-jobs
      - logical destination 580
    - auto-create-shared-printers
      - server 625
    - automatic-postscript-mode-switch
      - actual destination 339
    - auxiliary-sheet-identifier
      - auxiliary sheet 443
    - auxiliary-sheet-selection
      - default job 525
      - job 525
    - auxiliary-sheet-selections-supported
      - actual destination 340
      - logical destination 580
    - backlog
      - queue 618
    - backlog-lower-bound
      - queue 612
    - backlog-update-interval
      - queue 612
    - backlog-upper-bound
      - queue 613
    - backlogged
      - queue 613
    - base-printer
      - default document 456
      - document 456

- attributes *(continued)*
  - bits-per-spot
    - default document 457
    - document 457
  - black-overprint
    - default document 457
    - document 457
  - booklet-fold
    - actual destination 341
  - building-text
    - default document 458
    - document 458
  - callback-number
    - default document 458
    - document 458
  - cancel-individual-document-supported
    - actual destination 341
    - server 625
  - carriage-control-type
    - default document 458
    - document 458
  - carriage-control-types-supported
    - actual destination 341
    - logical destination 581
  - character-mappings-supported
    - actual destination 342
    - logical destination 581
  - chars
    - default document 459
    - document 459
  - checkpoint-at-stacker
    - actual destination 343
  - checkpoint-formats-supported
    - actual destination 343
  - cms-proclink
    - default document 460
    - document 460
  - cms-product
    - default document 460
    - document 460
  - color-mapping-table
    - actual destination 344
    - default document 461
    - document 461
  - color-rip-servers
    - actual destination 344
  - command
    - actual destination 349
  - comment
    - default job 536
    - job 536
  - completion-time
    - job 526, 568
  - complex, specifying 6
  - compressed-output
    - default document 461
    - document 461
  - connection-timeout
    - actual destination 345
  - content-orientation
    - default document 462

- attributes *(continued)*
  - content-orientation *(continued)*
    - document 462
  - content-orientations-supported
    - actual destination 345
    - logical destination 581
  - context-address
    - resource context 621
  - control-strip
    - default document 462
    - document 462
  - convert-to-ebcdic
    - default document 463
    - document 463
  - convert-to-ebcdic-supported
    - actual destination 346
    - logical destination 582
  - copies
    - default document 463
    - document 463
  - copy-count
    - default document 463
    - document 463
  - current-backlog
    - queue 618
  - current-job-state
    - job 526
  - current-page-printing
    - job 527
  - d-s-s-requested
    - default job 532
    - job 532
  - data-fidelity-problem-reported
    - default document 464
    - document 464
  - data-fidelity-problem-reported-supported
    - actual destination 346
    - logical destination 583
  - deadline-in-jeopardy
    - job 528
  - default-character-mapping
    - default document 464
    - document 464
  - default-font-fidelity-action
    - actual destination 347
  - default-font-resolution
    - actual destination 347
  - default-input-tray
    - actual destination 348
    - default document 465
    - document 465
  - default-medium
    - default document 466
    - document 466
  - default-printer-resolution
    - default document 467
    - document 467
  - delete-segment-list
    - default job 528
    - job 528

attributes (*continued*)

- department-text
  - default document 467
  - document 467
- descriptor
  - actual destination 348
  - auxiliary sheet 444
  - default document 468
  - default job 529
  - log 573
  - logical destination 583
  - medium 605
  - queue 613
  - resource context 621
  - server 625
  - transform 645
- destination-associated-printers
  - logical destination 584
- destination-command
  - actual destination 349
- destination-company-text
  - default document 468, 494
  - document 468, 494
- destination-data-stream
  - actual destination 350
- destination-initial-value-document
  - logical destination 584
- destination-initial-value-job
  - job 529
  - logical destination 584
- destination-locations
  - actual destination 351
  - logical destination 585
- destination-locations-requested
  - default job 530
  - job 530
- destination-model
  - actual destination 351
  - logical destination 585
- destination-models-requested
  - default job 530
  - job 530
- destination-name
  - actual destination 352
  - logical destination 585
- destination-name-requested
  - job 531
- destination-needs-attention-time
  - actual destination 353
- destination-needs-key-operator-attention-time
  - actual destination 353
- destination-pass-through
  - actual destination 353
  - default document 469
  - document 469
- destination-poll-interval
  - actual destination 354
- destination-realization
  - actual destination 354
  - logical destination 586

attributes (*continued*)

- destination-register-threshold
  - actual destination 355
- destination-release-timer
  - actual destination 355
- destination-state
  - actual destination 356
- destination-states-supported
  - server 626
- destination-support-system
  - actual destination 357
  - logical destination 586
- destination-support-systems-supported
  - server 626
- destination-tcpip-internet-address
  - actual destination 358
- destination-tcpip-port-number
  - actual destination 359
- destinations-assigned
  - job 531
- destinations-ready
  - logical destination 587
- destinations-used
  - job 532
- device-name
  - actual destination 360
- device-support-system
  - actual destination 357
  - logical destination 586
- device-support-system-requested
  - default job 532
  - job 532
- discard-time
  - job 538
- document-attributes-supported
  - actual destination 361
  - server 627
- document-comment
  - default document 469
  - document 469
- document-content
  - document 469
- document-file-name
  - document 470
- document-finishing
  - default document 470
  - document 470
- document-finishings-supported
  - actual destination 363
- document-format
  - default document 471
  - document 471
- document-formats-ripped-at-destination
  - actual destination 364
- document-formats-supported
  - actual destination 364, 646
  - logical destination 587
- document-number
  - document 472
- document-sequence-number
  - document 472



- attributes *(continued)*
  - document-type
    - default document 472
    - document 472
  - document-types-supported
    - actual destination 366
    - logical destination 588
  - dot-shape
    - default document 474
    - document 474
  - dss-job-message-disposition
    - actual destination 367
  - dss-job-message-log-size
    - actual destination 367
  - dss-job-message-log-wrap
    - actual destination 368
  - dss-requested
    - default job 532
    - job 532
  - ebcdic-character-mapping
    - actual destination 368
  - email-from-address
    - default document 475
    - document 475
  - email-to-address
    - default document 475
    - document 475
  - enable-settrap
    - default document 476
    - document 476
  - enabled
    - actual destination 369
    - log 574
    - logical destination 588
  - end-message
    - default job 539
    - job 539
  - end-message-supported
    - actual destination 369
    - logical destination 589
  - end-sheets-supported
    - actual destination 370
  - estimated-completion-time
    - job 533
  - estimated-processing-time
    - job 534
  - events-supported
    - server 627
  - fax-number
    - default document 476
    - document 476
  - fax-to-name
    - default document 476
    - document 476
  - file-name
    - document 470
  - font-fidelity-action
    - default document 477
    - document 477
  - font-processing-messages
    - default document 477

- attributes *(continued)*
  - font-processing-messages *(continued)*
    - document 477
  - font-resolution
    - default document 478
    - document 478
  - font-resolutions-supported
    - actual destination 370
  - force-destination-setup
    - actual destination 371
  - force-printer-setup
    - actual destination 371
  - form-definition
    - actual destination 372
    - default document 478
    - document 478
  - format
    - default document 471
    - document 471
  - formatted-job-ticket-content
    - job 534
  - global-id
    - job 541
  - halftone
    - default document 479
    - document 479
  - halftones-supported
    - actual destination 372
  - hold
    - default job 540
    - job 540
  - hostname
    - server 640
  - i-p-address
    - server 640
  - image-center-x
    - default document 480
    - document 480
  - image-center-y
    - default document 481
    - document 481
  - image-fit
    - default document 481
    - document 481
  - image-fit-supported
    - actual destination 374
  - image-length
    - actual destination 374
    - default document 482
    - document 482
  - image-out-format
    - default document 483
    - document 483
  - image-out-formats-supported
    - actual destination 375
    - logical destination 589
  - image-scale
    - default document 483
    - document 483
  - image-width
    - actual destination 376

attributes (*continued*)  
 default document 484  
 document 484  
 initial-value-document  
 document 485  
 initial-value-document-identifier  
 default document 485  
 initial-value-job  
 job 535  
 initial-value-job-identifier  
 default job 535  
 input-data-user-exit  
 actual destination 377  
 input-exit  
 default document 486  
 document 486  
 input-tray-select  
 default document 487  
 document 487  
 input-trays-medium  
 actual destination 377  
 input-trays-supported  
 actual destination 379  
 logical destination 590  
 intervening-jobs  
 job 535  
 intervention-timer  
 actual destination 379  
 ip-address  
 server 640  
 job-attributes-supported  
 actual destination 380  
 server 629  
 job-batch  
 default job 536  
 job 536  
 job-batches-ready  
 actual destination 380  
 job-client-id  
 job 536  
 job-comment  
 default job 536  
 job 536  
 job-complexity  
 job 537  
 job-copies-completed  
 job 537  
 job-deadline-time  
 job 538  
 job-discard-time  
 job 538  
 job-end-message  
 default job 539  
 job 539  
 job-finishing  
 default job 539  
 job 539  
 job-finishings-supported  
 actual destination 381  
 job-hold  
 default job 540

attributes (*continued*)  
 job-hold (*continued*)  
 job 540  
 job-identifier  
 job 541  
 job-log  
 job 541  
 job-media-sheet-count  
 job 542  
 job-message-from-administrator  
 job 542  
 job-message-to-operator  
 default job 543  
 job 543  
 job-name  
 job 543  
 job-originator  
 default job 544  
 job 544  
 job-owner  
 job 544  
 job-page-count  
 job 545  
 job-print-after  
 job 545  
 job-priority  
 default job 546  
 job 546  
 job-retain-until  
 job 546  
 job-retention-period  
 default job 547  
 job 547  
 job-retry-count-limit  
 actual destination 381  
 job-retry-interval  
 actual destination 382  
 job-rip-action  
 default job 547  
 job 547  
 job-rip-actions-supported  
 actual destination 382  
 job-ripped-by-server  
 default job 548  
 job 548  
 job-size  
 job 571  
 job-size-range-ready  
 actual destination 383  
 job-size-range-supported  
 actual destination 384  
 logical destination 590  
 job-start-message  
 default job 551  
 job 551  
 job-start-wait  
 job 552  
 job-start-wait-supported  
 job 385  
 job-state  
 job 526

- attributes (*continued*)
  - job-state-reasons
    - job 552
  - job-states-supported
    - server 630
  - job-submission-complete
    - job 554
  - job-submission-timer
    - server 630
  - job-ticket-content
    - job 534
  - job-between-job-copies
    - default document 487
    - document 487
  - last-accessor
    - job 557
  - last-modifier
    - job 557
  - list-of-managers
    - actual destination 385
    - default document 487
    - default job 554
    - logical destination 591
    - queue 614
    - server 630
  - locale
    - server 631
  - locations
    - actual destination 351
    - logical destination 585
  - locations-requested
    - default job 530
    - job 530
  - log-accounting-data
    - actual destination 386
    - server 631
  - log-address
    - log 574
  - log-identifier
    - log 574
  - log-message
    - log 575
  - log-severity
    - log 575
  - log-size
    - log 576
  - log-trace-groups
    - log 576
  - log-type
    - log 576
  - log-wrap
    - log 577
  - logical-destinations-assigned
    - actual destination 387
    - queue 614
  - logical-destinations-ready
    - default document 488
    - default job 555
    - queue 614
    - server 632

- attributes (*continued*)
  - logical-destinations-supported
    - server 632
  - logical-printer
    - logical destination 585
  - logical-printer-requested
    - job 531
  - logical-printers-assigned
    - queue 614
  - logical-printers-ready
    - default document 488
    - default job 555
    - queue 614
    - server 632
  - logical-printers-supported
    - server 632
  - managers
    - actual destination 385
    - default document 487
    - default job 554
    - logical destination 591
    - queue 614
    - server 630
  - maximum-barco-rips
    - server 633
  - maximum-concurrent-jobs
    - actual destination 387
  - maximum-copies-supported
    - actual destination 388
    - logical destination 592
  - maximum-fonts-to-keep
    - actual destination 389
  - maximum-messages-printed
    - default document 488
    - document 488
  - maximum-non-raster-rips
    - server 633
  - maximum-overlays-to-keep
    - actual destination 389
  - maximum-raster-rips
    - server 633
  - maximum-segments-to keep
    - actual destination 390
  - maximum-transform-pages-ahead
    - default document 489
    - document 489
  - media-ready
    - actual destination 390
  - media-sheet-count
    - job 542
  - media-sheets-completed
    - job 556
  - media-supported
    - actual destination 391
    - logical destination 592
  - medium-color
    - medium 605
  - medium-dimensions
    - medium 605
  - medium-form-parts
    - medium 606

attributes (*continued*)

- medium-holes-count
  - medium 606
- medium-identifier
  - medium 607
- medium-sides
  - medium 607
- medium-size
  - medium 608
- medium-type
  - medium 608
- medium-weight
  - medium-weight 609
- message
  - actual destination 392
  - default document 489
  - default job 556
  - logical destination 593
  - medium 609
  - queue 615
  - server 634
- message-font-type
  - actual destination 393
- message-form-definition
  - actual destination 393
- message-from-administrator
  - job 542
- message-to-operator
  - default job 543
  - job 543
- model
  - actual destination 351
  - logical destination 585
- models-requested
  - default job 530
  - job 530
- modification-time
  - job 557
- modify-individual-document-supported
  - server 634
- multiple-documents-supported
  - server 634
- mvs-class
  - default document 489
  - document 489
- mvs-destination
  - default document 490
  - document 490
- mvs-forms
  - default document 490
  - document 490
- mvs-segment-id
  - default document 491
  - document 491
- name
  - job 543
- name-of-last-accessor
  - job 557
- name-text
  - default document 491
  - document 491

attributes (*continued*)

- new-job-identifier
  - job 557
- new-line-option
  - default document 492
  - document 492
- node-id-text
  - default document 492
  - document 492
- non-process-runout-timer
  - actual destination 394
- notification-delivery-methods-supported
  - server 634
- notification-profile
  - actual destination 394
  - default job 558
  - job 558
  - logical destination 593
  - queue 615
  - server 635
- notify-operator
  - actual destination 396
  - queue 616
- npm-server-ip-address
  - server 636
- npm-server-port-number
  - server 637
- nt-drivers
  - actual destination 440
  - logical destination 601
  - server 644
- number-of-documents
  - job 560
- number-up
  - document 493
- number-up-supported
  - actual destination 396
- object-class
  - actual destination 397
  - auxiliary sheet 444
  - default document 493
  - default job 560
  - document 493
  - job 560
  - log 577
  - logical destination 595
  - medium 609
  - queue 617
  - resource context 621, 646
  - server 637
- object-classes-supported
  - server 637
- octet-count
  - document 494
- octets-completed
  - job 561
- of actual destinations 328
- of default documents 449
- of documents 449
- of jobs 523
- of logical destinations 578

- attributes *(continued)*
  - of logs 573
  - of media 604
  - of queues 610
  - of resource contexts 620
  - of servers 623
  - of transforms 645
  - offset-stacking-available
    - actual destination 397
- operators
  - actual destination 396
  - queue 616
- optimize-for-multiple-copies
  - actual destination 398
  - default job 561
  - job 561
- orientation
  - default document 462
  - document 462
- orientations-supported
  - actual destination 345
  - logical destination 581
- originator
  - default job 544
  - job 544
- os2-driver-names
  - logical destination 595
- os2-drivers
  - logical destination 595
- other-options
  - actual destination 353
  - default document 469
  - document 469
- other-transform-options
  - default document 495
  - document 495
- output-appearance
  - default document 495
  - document 495
- output-appearances-supported
  - actual destination 399
- output-bin
  - actual destination 399
  - default document 495
  - document 495
- output-bin-numbers
  - actual destination 400
- output-bins-supported
  - actual destination 401
- output-data-user-exit
  - actual destination 402
- output-face-up
  - default document 496
  - document 496
- output-format
  - default document 497
  - document 497
- output-format-supported
  - actual destination 402
- overlay
  - actual destination 403

- attributes *(continued)*
  - overlay *(continued)*
    - default document 498
    - document 498
  - overlay-back
    - default document 499
    - document 499
  - overlay-front
    - default document 499
    - document 499
  - overprint
    - default document 500
    - document 500
  - owner
    - job 544
  - page-clip
    - default document 500
    - document 500
  - page-count
    - document 501
  - page-definition
    - default document 501
    - document 501
  - page-media-select
    - default document 502
    - document 502
  - page-select
    - document 502
  - page-select-supported
    - actual destination 403
  - pages-completed
    - job 562
  - pcl-server-address
    - actual destination 404
  - pcl-server-port
    - actual destination 404
  - physical-printer
    - actual destination 352
  - physical-printers-assigned
    - queue 610
  - physical-printers-ready
    - queue 610
    - server 624
  - physical-printers-requested
    - default job 524
    - job 524
  - physical-printers-supported
    - server 624
  - plex
    - actual destination 405
    - default document 503
    - document 503
  - plexes-supported
    - actual destination 405
    - logical destination 597
  - position-in-queue
    - job 535
  - postscript-server-address
    - actual destination 406
    - logical destination 596

attributes (*continued*)

- postscript-server-port
  - actual destination 407
- presentation-fidelity-problem-reported
  - actual destination 407
- previous-job-state
  - job 563
- previous-state
  - job 563
- print-after
  - job 545
- print-edge-marks
  - actual destination 408
- print-qualities-supported
  - actual destination 408
  - logical destination 597
- print-quality
  - default document 504
  - document 504
- print-queue
  - actual destination 409
- print-queue-name
  - actual destination 409
- printer
  - actual destination 352
  - logical destination 585
- printer-associated-printers
  - logical destination 584
- printer-command
  - actual destination 349
- printer-data-stream
  - actual destination 350
- printer-end-sheet
  - actual destination 409
- printer-escape-codes
  - actual destination 410
- printer-initial-value-document
  - document 468
  - logical destination 584
- printer-initial-value-job
  - job 529
  - logical destination 584
- printer-locations
  - actual destination 351
  - logical destination 585
- printer-locations-requested
  - default job 530
  - job 530
- printer-memory
  - actual destination 411
- printer-model
  - actual destination 351
  - logical destination 585
- printer-models-requested
  - default job 530
  - job 530
- printer-name
  - actual destination 352
  - logical destination 585
- printer-name-requested
  - job 531

attributes (*continued*)

- printer-needs-attention-time
  - actual destination 353
- printer-needs-key-operator-attention-time
  - actual destination 353
- printer-pass-through
  - actual destination 353
  - default document 469
  - document 469
- printer-realization
  - actual destination 354
  - logical destination 586
- printer-register-threshold
  - actual destination 355
- printer-release-timer
  - actual destination 355
- printer-requested
  - job 531
- printer-resolutions-ready
  - actual destination 412
- printer-resolutions-supported
  - actual destination 413
- printer-s370-channel-device-address
  - actual destination 416
- printer-s370-channel-slot-number
  - actual destination 416
- printer-separator-sheet
  - actual destination 414
- printer-start-sheet
  - actual destination 414
- printer-state
  - actual destination 356
- printer-states-supported
  - server 626
- printer-tcpip-internet-address
  - actual destination 358
- printer-tcpip-port-number
  - actual destination 359
- printer-timeout-period
  - actual destination 359
- printers-assigned
  - job 531
- printers-ready
  - logical destination 587
- printers-used
  - job 532
- problem-child
  - server 638
- problem-message
  - actual destination 417
- processing-time
  - job 564
- programmer-text
  - default document 504
  - document 504
- protected-attributes
  - actual destination 417
  - logical destination 598
- queue
  - server 618
- server
  - 638

- attributes (*continued*)
  - psf-exit-form-definition
    - auxiliary sheet 444
  - psf-exit-page-mark
    - auxiliary sheet 444
  - psf-exit-program-name
    - auxiliary sheet 445
  - psf-tray-characteristics
    - actual destination 418
  - qualities-supported
    - actual destination 408
    - logical destination 597
  - queue-assigned
    - job 565
  - queue-backlog
    - queue 618
  - queue-name
    - queue 618
  - queue-position
    - job 535
  - queue-state
    - queue 618
  - queues-supported
    - server 639
  - reasons
    - job 552
  - register-threshold
    - actual destination 355
  - registered-with-spooler
    - actual destination 421
  - remote-queue
    - actual destination 421
  - requeue-failed-jobs
    - queue 619
  - required-resources-not-ready
    - job 565
  - required-resources-not-supported
    - job 566
  - resource-context
    - actual destination 422
    - default document 505
    - document 505
  - resource-context-font
    - actual destination 423
    - default document 506
    - document 506
  - resource-context-form-definition
    - actual destination 424
    - default document 507
    - document 507
  - resource-context-identifier
    - resource context 622
  - resource-context-overlay
    - actual destination 425
    - default document 508
    - document 508
  - resource-context-page-definition
    - actual destination 426
    - default document 509
    - document 509

- attributes (*continued*)
  - resource-context-page-segment
    - actual destination 427
    - default document 509
    - document 509
  - resource-context-user
    - default document 510
    - document 510
  - resource-exit
    - default document 511
    - document 511
  - results-profile
    - default job 566
    - job 566
  - retention-period
    - default job 547
    - job 547
  - reverse-output
    - actual destination 428
  - rip-ini-file
    - actual destination 428
  - rip-server
    - actual destination 429
  - room-text
    - default document 512
    - document 512
  - save-rip-files
    - server 639
  - scanner-correction
    - default document 512
    - document 512
  - scanner-corrections-supported
    - actual destination 429
  - scheduler-sort-primary-order
    - actual destination 429
  - scheduler-sort-secondary-order
    - actual destination 430
  - schedulers-supported
    - actual destination 430
  - screen-frequencies-supported
    - actual destination 431
  - screen-frequency
    - default document 513
    - document 513
  - security-level
    - server 639
  - segment-file-size
    - default document 513
    - document 513
  - separator-sheets-supported
    - actual destination 431
  - sequence-number
    - document 472
  - server-hostname
    - server 640
  - server-ip-address
    - server 640
  - server-name
    - server 641
  - server-state
    - server 641

attributes (*continued*)

- shared-formdef
  - default document 514
  - document 514
- shared-printer-name
  - actual destination 432
- shift-out-shift-in
  - default document 514
  - document 514
- sides
  - actual destination 433
  - default document 515
  - document 515
- sides-supported
  - actual destination 433
  - logical destination 598
- smtp-server-host
  - server 641
- smtp-server-port-number
  - server 642
- snmp-active
  - actual destination 434
- snmp-aix-printer-models
  - server 642
- snmp-community-name
  - actual destination 434
- snmp-normal-poll-interval
  - server 643
- snmp-problem-poll-interval
  - server 643
- snmp-retry-count
  - actual destination 435
- snmp-timeout
  - actual destination 435
- start-message
  - default job 551
  - job 551
- start-message-supported
  - actual destination 436
  - logical destination 599
- start-on-new-sheet
  - default document 516
  - document 516
- start-sheets-supported
  - actual destination 436
- started-printing-time
  - job 568
- state-reasons
  - job 552
- subject-text
  - default document 516
  - document 516
- submission-time
  - job 568
- table-reference-characters
  - default document 516
  - document 516
- table-reference-characters-supported
  - actual destination 437
  - logical destination 599

attributes (*continued*)

- tape-exit
  - job 569
- tape-format
  - job 569
- tape-labeled
  - default job 570
  - job 570
- tape-max-block-size
  - default job 570
  - job 570
- tape-rewind-before
  - job 570
- tape-rewind-unload
  - job 571
- ticket-content
  - job 534
- timeout-period
  - actual destination 359
- title-text
  - default document 517
  - document 517
- total-job-octets
  - job 571
- transfer-method
  - document 518
- transfer-methods-supported
  - server 644
- transform-message-file-name
  - default document 518
  - document 518
- transform-output-file-name
  - document 518
- transform-sequence
  - actual destination 438
- type
  - default document 472
  - document 472
- use-snmp
  - actual destination 438
- used for job scheduling 695
- used for job validation 695
- user-id-text
  - default document 519
  - document 519
- user-locale
  - job 572
- user-name
  - job 572
- wait-for-job-completion
  - actual destination 439
- warning-message
  - actual destination 439
- windows-driver-names
  - logical destination 600
- windows-drivers
  - logical destination 600
- windows-nt-driver-names
  - actual destination 440
  - logical destination 601
- servers 644



- attributes (*continued*)
  - windows-nt-drivers
    - actual destination 440
    - logical destination 601
    - server 644
  - x-image-shift
    - default document 519
    - document 519
  - x-image-shift-back
    - default document 520
    - document 520
  - x-image-shift-range-supported
    - actual destination 440
    - logical destination 601
  - y-image-shift
    - default document 521
    - document 521
  - y-image-shift-back
    - default document 521
    - document 521
  - y-image-shift-range-supported
    - actual destination 441
    - logical destination 602
- attributes files, creating 148
- audit data
  - reporting by destination 138
  - reporting by user
    - for all users 139
    - for specified user 140
- audit-exit attribute
  - actual destination 339
- authorize-jobs attribute
  - logical destination 580
- auto-create-shared-printers attribute
  - server 625
- automatic-postscript-mode-switch attribute
  - actual destination 339
- auxiliary-sheet-identifier attribute
  - auxiliary sheet 443
- auxiliary-sheet-selection attribute
  - default job 525
  - job 525
- auxiliary-sheet-selections-supported attribute
  - actual destination 340
  - logical destination 580
- auxiliary sheets, attributes of
  - associated-server 443
  - auxiliary-sheet-identifier 443
  - descriptor 444
  - object-class 444
  - psf-exit-form-definition 444
  - psf-exit-page-mark 444
  - psf-exit-program-name 445
  - resettable attribute listing 443
  - summary of 443

## B

- backlog attribute
  - queue 618

- backlog-lower-bound attribute
  - queue 612
- backlog-update-interval attribute
  - queue 612
- backlog-upper-bound attribute
  - queue 613
- backlogged attribute
  - queue 613
- barcode.tab configuration file
  - ModWidth optional keyword 300
  - Ratio optional keyword 300
- barcode.tab file 300
- bars in commands xxxix
- base-printer attribute
  - default document 456
  - document 456
- bin-name component
  - output-bin-numbers attribute, actual destination 400
- bin-number component
  - output-bin-numbers attribute, actual destination 401
- bits-per-spot attribute
  - default document 457
  - document 457
- black-overprint attribute
  - default document 457
  - document 457
- booklet-fold attribute
  - actual destination 341
- braces in commands xxxix, xl
- brackets in commands xxxix
- BSD destination support system (DSS) 326, 327
- BSD-flag component
  - attribute-map attribute, actual destination 338
- building-text attribute
  - default document 458
  - document 458

## C

- callback-number attribute
  - default document 458
  - document 458
- cancel-individual-document-supported attribute
  - actual destination 341
  - server 625
- carriage control characters
  - specifying presence 239
  - specifying type 239
- carriage-control-type attribute
  - default document 458
  - document 458
- carriage-control-types-supported attribute
  - actual destination 341
  - logical destination 581
- cc option 239
- cctype option 239
- cfu utility
  - arguments 142
  - build file format 141
  - description 141, 143
  - examples 142

- cfu utility (*continued*)
  - flags 141
  - syntax 141
- channel-attached printers, sensing 167
- character-mappings-supported attribute
  - actual destination 342
  - logical destination 581
- chars attribute
  - default document 459
  - document 459
- chars option 240, 256
- checkpoint-at-stacker attribute
  - actual destination 343
- checkpoint-formats-supported attribute
  - actual destination 343
- cms-prolink attribute
  - default document 460
  - document 460
- cms-product attribute
  - default document 460
  - document 460
- cmt utility
  - build color mapping table 143
  - flags 143
  - syntax 143
- code page
  - mapping ASCII to EBCDIC for sap2afp 308
- coded fonts, building 141
- collecting accounting information
  - for a specific server 19
  - specified time 19
- colons in commands xl
- Color Mapping Table, building 143
- color-mapping-table attribute
  - actual destination 344
  - default document 461
  - document 461
- color-rip-servers attribute
  - actual destination 344
- command attribute
  - actual destination 349
- command attributes 4, 8
- command attributes, default values for 5
- command introduction 1
- command scripts, creating 148
- commands
  - arguments
    - lprafp 15
    - mkfntmap 17
    - pdaccount 20
    - pdclean 23
    - pdcreate 27
    - pddelete 31
    - pddisable 35
    - pdenable 38
    - pdls 45
    - pdmod 54
    - pdpause 60
    - pdpr 67
    - pdpromote 73
    - pdq 77

- commands (*continued*)
  - arguments (*continued*)
    - pdreorder 80
    - pdresubmit 83
    - pdresume 86
    - pdrm 89
    - pdset 94
    - pdshutdown 99
    - pdspace 102
  - attributes
    - general description of 8
    - pdclean 23
    - pdcreate 27
    - pddelete 31
    - pddisable 35
    - pdenable 38
    - pdls 42
    - pdmod 53
    - pdpause 58
    - pdpr 66, 67
    - pdpromote 73
    - pdq 76
    - pdreorder 80
    - pdresubmit 82
    - pdresume 86
    - pdrm 89
    - pdset 93
    - pdshutdown 98
    - pdspace 101
  - description
    - lprafp 15
    - mkfntmap 17
    - pdaccount 19
    - pdclean 22
    - pdcreate 25
    - pddelete 30
    - pddisable 34
    - pdenable 37
    - pdls 40
    - pdmod 51
    - pdpause 56
    - pdpr 63
    - pdpromote 72
    - pdq 74
    - pdresubmit 81
    - pdresume 85
    - pdrm 88
    - pdset 91
    - pdshutdown 96
    - pdspace 100
    - preorder 79
  - examples
    - lprafp 16
    - mkfntmap 18
    - of documents, pdcreate 28
    - of jobs, pdcreate 28
    - pdaccount 21
    - pdclean 24
    - pdcreate 28
    - pddelete 32
    - pddisable 36

commands (*continued*)

- pdenable 39
- pdls 46
- pdmod 54
- pdpause 62
- pdpr 68, 70
- pdpromote 73
- pdq 77
- pdreorder 80
- pdresubmit 84
- pdresume 87
- pdrm 89
- pdset 94
- pdshutdown 99
- pdspace 102

flags

- lprafp 15
- pdaccount 19
- pdclean 22
- pdcreate 26
- pddelete 30
- pddisable 34
- pdenable 37
- pdls 41
- pdmod 52
- pdpause 57
- pdpr 64
- pdpromote 72
- pdq 74
- pdreorder 79
- pdresubmit 81
- pdresume 85
- pdrm 88
- pdset 92
- pdshutdown 97
- pdspace 101

flags, general description of 8

lprafp

- description 15

operators, filters

- pdls, filters 42

pdaccount

- description 19

pdclean

- description 22

pdcreate

- description 25

pddelete

- description 30

pddisable

- description 34

pdenable

- description 37

pdls

- description 40

pdmod

- description 51

pdpause

- description 56

pdpr

- description 63

commands (*continued*)

- pdpromote
  - description 72
- pdq
  - description 74
- pdreorder
  - description 79
- pdresubmit
  - description 81
- pdresume
  - description 85
- pdrm
  - description 88
- pdset
  - description 91
- pdshutdown
  - description 96
- pdspace
  - description 100

syntax

- lprafp 15
- mkfntmap 17
- pdaccount 19
- pdclean 22
- pdcreate 25
- pddelete 30
- pddisable 34
- pdenable 37
- pdls 40
- pdmod 51
- pdpause 56
- pdpr 63
- pdpromote 72
- pdq 74, 79
- pdresubmit 81
- pdresume 85
- pdrm 88
- pdset 91
- pdshutdown 96
- pdspace 100

syntax, general description of 8

commands, attributes

object attributes

- pdcreate, documents 27
- pdcreate, jobs 27
- pdpr 67

comment attribute

- default job 536
- job 536

comments in option file 252

completion-time attribute

- job 526, 568

complex attributes

- ascii-font-map attribute, actual destination 335
- attribute-map attribute, actual destination 338
- input-trays-medium attribute, actual destination 377
- job-size-range-ready attribute
  - actual destination 383
- job-size-range-supported attribute
  - actual destination 383
  - logical destination 590

- complex attributes (*continued*)
  - notification-profile attribute
    - actual destination 394
    - default job 558
    - job 558
    - logical destination 593
    - queue 615
    - server 635
  - notify-operator attribute
    - actual destination 396
    - queue 616
  - operators attribute
    - actual destination 396
    - queue 616
  - output-bin-numbers attribute, actual destination 400
  - printer-resolutions-supported, actual destination 413
  - psf-tray-characteristics attribute, actual destination 418
  - results-profile attribute
    - default job 566
    - job 566
  - specifying 6
- components, complex attributes
  - bin name component, output-bin-numbers attribute, actual destination 400
  - bin number component, output-bin-numbers attribute, actual destination 401
  - BSD-flag component, attribute-map attribute, actual destination 338
  - delivery-address component
    - notification-profile attribute, actual destination 395
    - notification-profile attribute, default job 559
    - notification-profile attribute, job 559
    - notification-profile attribute, logical destination 594
    - notification-profile attribute, queue 616
    - notification-profile attribute, server 635
    - notify-operator attribute, actual destination 396
    - notify-operator attribute, queue 617
    - operators attribute, actual destination 396
    - operators attribute, queue 617
    - results-profile attribute, default job 567
    - results-profile attribute, job 567
  - delivery-method component
    - notification-profile attribute, actual destination 395
    - notification-profile attribute, default job 559
    - notification-profile attribute, job 559
    - notification-profile attribute, logical destination 594
    - notification-profile attribute, queue 616
    - notification-profile attribute, server 636
    - notify-operator attribute, actual destination 396
    - notify-operator attribute, queue 617
    - operators attribute, actual destination 396
    - operators attribute, queue 617
    - results-profile attribute, default job 567
    - results-profile attribute, job 567
  - duplex-supported component, psf-tray-characteristics attribute, actual destination 420
- components, complex attributes (*continued*)
  - event-comment component
    - notification-profile attribute, actual destination 395
    - notification-profile attribute, default job 559
    - notification-profile attribute, job 559
    - notification-profile attribute, logical destination 594
    - notification-profile attribute, queue 616
    - notification-profile attribute, server 636
  - event-identifier component
    - notification-profile attribute, actual destination 394
    - notification-profile attribute, default job 558
    - notification-profile attribute, job 558
    - notification-profile attribute, logical destination 593
    - notification-profile attribute, queue 615
    - notification-profile attribute, server 635
  - first-page component
    - page-select attribute, document 502
  - font-escape component, actual destination 335
  - font-name component, actual destination 335
  - Infoprint-attribute component, attribute-map attribute, actual destination 338
  - input-tray component, psf-tray-characteristics attribute, actual destination 418
  - job-bin-number component, psf-tray-characteristics attribute, actual destination 419
  - job-copies component
    - results-profile attribute, default job 567
    - results-profile attribute, job 567
  - last-page component
    - page-select attribute, document 502
  - locale component
    - notification-profile attribute, actual destination 395
    - notification-profile attribute, default job 560
    - notification-profile attribute, job 560
    - notification-profile attribute, logical destination 594
    - notification-profile attribute, queue 616
    - notification-profile attribute, server 636
  - lower-limit component
    - job-size-range-ready attribute, actual destination 383
    - job-size-range-supported attribute, actual destination 384
    - job-size-range-supported attribute, logical destination 590
    - x-image-shift-range-supported attribute, actual destination 441
    - x-image-shift-range-supported attribute, logical destination 602
    - y-image-shift-range-supported attribute, actual destination 442
    - y-image-shift-range-supported attribute, logical destination 602
  - media-loaded component, psf-tray-characteristics attribute, actual destination 419

- components, complex attributes *(continued)*
  - medium-identifier component, input-trays-medium attribute, actual destination 378
  - output-bin component
    - results-profile attribute, default job 567
    - results-profile attribute, job 567
  - results-set-comment component
    - results-profile attribute, default job 567
    - results-profile attribute, job 567
  - tray-identification component, input-trays-medium attribute, actual destination 378
  - tray-number component, psf-tray-characteristics attribute, actual destination 420
  - upper-limit component
    - job-size-range-ready attribute, actual destination 383
    - job-size-range-supported attribute, actual destination 384
    - job-size-range-supported attribute, logical destination 590
    - x-image-shift-range-supported attribute, actual destination 441
    - x-image-shift-range-supported attribute, logical destination 602
    - y-image-shift-range-supported attribute, actual destination 442
    - y-image-shift-range-supported attribute, logical destination 603
  - x-dimension component, medium-dimensions attribute, medium 606
  - y-dimension component, medium-dimensions attribute, medium 606
- compressed-output attribute
  - default document 461
  - document 461
- configuration files
  - barcode.tab 300
  - defcp.tab 302
  - fonts.tab 302
  - for gif2afp transform 213
  - for jpeg2afp transform 227
  - for pcl2afp transform 273
  - for pcl2afpd daemon 273
  - for pdf2afp transform 294
  - for ps2afp transform 294
  - for ps2afpd daemon 294
  - for sap2afp transform 299
  - for tiff2afp transform 315
  - gif2afp.cfg 213
  - image.tab 305
  - jpeg2afp.cfg 227
  - pagedef.tab 306
  - pcl2afp 273
  - pcl2afpd 273
  - printer.tab 307
  - ps2afp 294
  - ps2afpd 294
  - tiff2afp.cfg 315
  - xxxxyyyy.tab 308
- configuring servers 154
- connection-timeout attribute
  - actual destination 345
- content-orientation attribute
  - default document 462
  - document 462
- content-orientations-supported attribute
  - actual destination 345
  - logical destination 581
- context-address attribute
  - resource context 621
- control currently printing sheets 100
- control-strip attribute
  - default document 462
  - document 462
- convert-to-ebcdic attribute
  - default document 463
  - document 463
- convert-to-ebcdic-supported attribute
  - actual destination 346
  - logical destination 582
- copies attribute
  - default document 463
  - document 463
- copy-count attribute
  - default document 463
  - document 463
- creating
  - actual destinations 159
  - commonly used media 156
  - default objects 154
  - Infoprint attributes files 148
  - Infoprint command scripts 148
  - Infoprint directories 153
  - Infoprint objects 25
- current-backlog attribute
  - queue 618
- current-job-state attribute
  - job 526
- current-page-printing attribute
  - job 527
- customer fonts 304

## D

- d-s-s-requested attribute
  - default job 532
  - job 532
- d2afp transform
  - description 206
  - flags 207
  - limitations 206
  - syntax 206
- daemons
  - mvsprsd 186
  - pcl2apfd 188
  - ps2afpd 191
  - startcbd 197
  - startnotd 195
  - stopcbd 199
  - stopnotd 196
- dashes in commands xl
- data-fidelity-problem-reported attribute
  - default document 464

- data-fidelity-problem-reported attribute *(continued)*
  - document 464
- data-fidelity-problem-reported-supported attribute
  - actual destination 346
  - logical destination 583
- db2afp transform
  - description 202
  - files 205
  - flags 202
  - limitations 202
  - syntax 202
- DCE (Distributed Computing Environment)
  - authorize-jobs, logical destination 580
  - pdcrds utility 153
  - protected-attributes, actual destination 417
  - protected-attributes, logical destination 598
  - protected-attributes, queue 618
  - protected-attributes, server 638
- deadline-in-jeopardy attribute
  - job 528
- default-character-mapping attribute
  - default document 464
  - document 464
- default documents, attributes of
  - account-text 453
  - address2-text 454
  - address3-text 455
  - address4-text 455
  - associated-server 456
  - base-printer 456
  - bits-per-spot 457
  - black-overprint 457
  - building-text 458
  - callback-number 458
  - carriage-control-type 458
  - chars 459
  - cms-proclink 460
  - cms-product 460
  - color-mapping-table 461
  - compressed-output 461
  - content-orientation 462
  - control-strip 462
  - convert-to-ebcdic 463
  - copies 463
  - copy-count 463
  - data-fidelity-problem-reported 464
  - default-character-mapping 464
  - default-input-tray 465
  - default-medium 466
  - default-printer-resolution 467
  - department-text 467
  - descriptor 468
  - destination-company-text 468
  - destination-pass-through 469
  - document-comment 469
  - document-finishing 470
  - document-format 471
  - document-type 472
  - dot-shape 474
  - email-from-address 475
  - email-to-address 475

- default documents, attributes of *(continued)*
  - enable-settrap 476
  - fax-number 476
  - font-fidelity-action 477
  - font-processing-messages 477
  - font-resolution 478
  - form-definition 478
  - format 471
  - image-center-x 480, 483
  - image-center-y 481
  - image-fit 481
  - image-length 482
  - image-out-format 483
  - image-width 484
  - initial-value-document-identifier 485
  - input-exit 486
  - input-tray-select 487
  - job-start-wait 552
  - jog-between-job-copies 487
  - list-of-managers 487
  - logical-destinations-ready 488
  - logical-printers-ready 488
  - managers 487
  - maximum-messages-printed 488
  - maximum-transform-pages-ahead 489
  - message 489
  - mvs-class 489
  - mvs-destination 490
  - mvs-forms 490
  - mvs-segment-id 491
  - name-text 491
  - new-line-option 492
  - node-id-text 492
  - object-class 493
  - orientation 462
  - originating-company-text 494
  - other-options 469
  - other-transform options 495
  - other-transform-options 647
  - output-appearance 495
  - output-bin 495
  - output-face-up 496
  - output-format 497
  - overlay 498, 499
  - overprint 500
  - page-clip 500
  - page-definition 501
  - page-media-select 502
  - plex 503
  - print-quality 504
  - printer-pass-through 469
  - programmer-text 504
  - resource-context 505
  - resource-context-font 506
  - resource-context-form-definition 507
  - resource-context-overlay 508
  - resource-context-page-definition 509
  - resource-context-page-segment 509
  - resource-context-user 510
  - resource-exit 511
  - room-text 512

- default documents, attributes of *(continued)*
  - scanner-correction 512
  - screen-frequency 513
  - segment-file-size 513
  - shared-formdef 514
  - shift-out-shift-in 514
  - sides 515
  - start-on-new-sheet 516
  - subject-text 516
  - table-reference-characters 516
  - title-text 517
  - transform-message-file-name 518
  - type 472
  - user-id-text 519
  - x-image-shift 519
  - x-image-shift-back 520
  - y-image-shift 521
  - y-image-shift-back 521
- default-font-fidelity-action attribute
  - actual destination 347
- default-font-resolution attribute
  - actual destination 347
- default-input-tray attribute
  - actual destination 348
  - default document 465
  - document 465
- default jobs, attributes of
  - actual-destinations-requested 524
  - associated-server 525
  - auxiliary-sheet-selection 525
  - comment 536
  - d-s-s-requested 532
  - delete-segment-list 528
  - descriptor 529
  - destination-locations-requested 530
  - destination-models-requested 530
  - device-support-system-requested 532
  - dss-requested 532
  - end-message 539
  - hold 540
  - initial-value-job-identifier 535
  - job-batch 536
  - job-comment 536
  - job-end-message 539
  - job-finishing 539
  - job-hold 540
  - job-message-to-operator 543
  - job-originator 544
  - job-priority 546
  - job-retention-period 547
  - job-rip-action 547
  - job-ripped-by-server 548
  - job-start-message 551
  - list-of-managers 554
  - locations-requested 530
  - logical-destinations-ready 555
  - logical-printers-ready 555
  - managers 554
  - message 556
  - message-to-operator 543
  - models-requested 530
- default jobs, attributes of *(continued)*
  - notification-profile 558
  - object-class 560
  - optimize-for-multiple-copies 561
  - originator 544
  - physical-printers-requested 524
  - printer-locations-requested 530
  - printer-models-requested 530
  - results-profile 566
  - retention-period 547
  - start-message 551
- default-medium attribute
  - default document 466
  - document 466
- default objects, creating 154
- default-printer-resolution attribute
  - default document 467
  - document 467
- default values for command and object attributes 5
- defcp.tab file 302
- defining the attribute values of an object 91
- delete-segment-list attribute
  - default job 528
  - job 528
- deleting Infoprint objects 30
- delivery-address component
  - notification-profile attribute
    - actual destination 395
    - default job 559
    - job 559
    - logical destination 594
    - queue 616
    - server 635
  - notify-operator attribute
    - actual destination 396
    - queue 616
  - operators attribute
    - actual destination 396
    - queue 616
  - results-profile attribute
    - default job 567
    - job 567
- delivery-method component
  - notification-profile attribute
    - actual destination 395
    - default job 559
    - job 559
    - logical destination 594
    - queue 616
    - server 636
  - operators attribute
    - actual destination 396
    - queue 616
  - results-profile attribute
    - default job 567
    - job 567
- department-text attribute
  - default document 467
  - document 467

description

- of commands
  - lprafp 15
  - mkfntmap 17
  - pdaccount 19
  - pdclean 22
  - pdcreate 25
  - pddelete 30
  - pddisable 34
  - pdenable 37
  - pdl 40
  - pdmod 51
  - pdpause 56
  - pdpr 63
  - pdpromote 72
  - pdq 74
  - pdreorder 79
  - pdresubmit 81
  - pdresume 85
  - pdrm 88
  - pdset 91
  - pdshutdown 96
  - pdspace 100
- of transforms
  - d2afp 206
  - db2afp 202
  - gif2afp 209
  - jpeg2afp 223
  - line2afp 237
  - pcl2afp 261
  - pdf2afp 284
  - ps2afp 284
  - sap2afp 299
  - tiff2afp 310
- of utilities
  - admingui 128
  - afpsplit 129
  - ainupod1 130
  - ainupod2 131
  - ainupod3 132
  - ainurpt1 134
  - ainurpt2 135
  - ainurpt3 136
  - ainurpt4 138
  - ainurpt5 139
  - ainurpt6 140
  - cfu 141
  - cmt 143
  - ipguiadv 145
  - ipguiadvadm 146
  - ipguibasic 145
  - ipguibasicadm 146
  - ipguidist 145
  - ipguidistadm 146
  - jsmigr 148
  - mvsprsd 186
  - opergui 151
  - pcl2afpd 188
  - pdadmin 152
  - pdcrds 153
  - pdcrflt 154

description (*continued*)

- of utilities (*continued*)
  - pdcrmed 156
  - pdinitports 157
  - pdmigpp 159
  - pdmincfg 161
  - pdmsg 163
  - ps2afpd 191
  - rc.ipsap 165
  - rc.pd 166
  - setup 172
  - start\_server 176
  - startcbd 197
  - startnotd 195
  - startppo 175
  - startsrv 178
  - stop\_server 180
  - stopcbd 199
  - stopnotd 196
  - t2file 184
  - tdump 181
  - tlist 183
- descriptor attribute
  - actual destination 348
  - auxiliary sheet 444
  - default document 468
  - default job 529
  - log 573
  - logical destination 583
  - medium 605
  - queue 613
  - resource context 621
  - server 625
  - transform 645
- destination-associated-destinations attribute
  - logical destination 584
- destination-command attribute
  - actual destination 349
- destination-company-text attribute
  - default document 468, 494
  - document 468, 494
- destination-data-stream attribute
  - actual destination 350
- destination-initial-value-document attribute
  - logical destination 584
- destination-initial-value-job attribute
  - job 529
  - logical destination 584
- destination-locations attribute
  - actual destination 351
  - logical destination 585
- destination-locations-requested attribute
  - default job 530
  - job 530
- destination-model attribute
  - actual destination 351
  - logical destination 585
- destination-models-requested attribute
  - default job 530
  - job 530



- destination-name attribute
  - actual destination 352
  - logical destination 585
- destination-name-requested attribute
  - job 531
- destination-needs-attention-time attribute
  - actual destination 353
- destination-needs-key-operator-attention-time attribute
  - actual destination 353
- destination-pass-through attribute
  - actual destination 353
  - default document 469
  - document 469
- destination-poll-intervall attribute
  - actual destination 354
- destination-realization attribute
  - actual destination 354
  - logical destination 586
- destination-register-threshold attribute
  - actual destination 355
- destination-release-timer attribute
  - actual destination 355
- destination-state attribute
  - actual destination 356
- destination-states-supported attribute
  - server 626
- destination-support-system attribute
  - actual destination 357
  - logical destination 586
- destination support systems
  - 3170 326
  - AIX 326
  - BSD 326, 327
  - email 326
  - fax 327
  - Infoprint 2000 326
  - IPP 327
  - Passthrough 327
  - PSF 326, 327
- destination-support-systems-supported attribute
  - server 626
- destination-tcpip-internet-address attribute
  - actual destination 358
- destination-tcpip-port-number attribute
  - actual destination 359
- destinations-assigned attribute
  - job 531
- destinations-ready attribute
  - logical destination 587
- destinations-used attribute
  - job 532
- device-name attribute
  - actual destination 360
- device-support-system attribute
  - actual destination 357
  - logical destination 586
- device-support-system-requested attribute
  - default job 532
  - job 532
- directories
  - install\_path*\reslib 424, 427
- directories (*continued*)
  - usr\pp\psf\reslib* 423
  - install\_path\reslib* 425, 426
  - usr/lib/lpd/pio/predef* 352
  - usr/lpd/pio/predef* 365
  - usr/lpp/pd/attr* 329
  - usr/lpp/psf/reslib* 422, 424, 425, 426, 427
  - font 244
  - fonts 244
  - form definition 242
  - overlay 249
  - overlays 249
  - page definition 252
  - page segment 253
  - user 256
- directories, creating 153
- disabling destinations 34
- discard-time attribute
  - job 538
- displaying information about messages 163
- document-attributes-supported attribute
  - actual destination 361
  - server 627
- document-comment attribute
  - default document 469
  - document 469
- document-content attribute
  - document 469
- document-content-list attribute
  - document 470
- document-file-name attribute
  - document 470
- document-finishing attribute
  - default document 470
  - document 470
- document-finishings-supported attribute
  - actual destination 363
- document-format attribute
  - default document 471
  - document 471
- document-formats-ripped-at-destination
  - actual destination 364
- document-formats-supported attribute
  - actual destination 364, 646
  - logical destination 587
- document-number attribute
  - document 472
- document-sequence-number attribute
  - document 472
- document-type attribute
  - default document 472
  - document 472
- document-types-supported attribute
  - actual destination 366
  - logical destination 588
- documents, attributes of
  - account-text 453
  - address1-text 454
  - address2-text 454
  - address3-text 455
  - address4-text 455

documents, attributes of (*continued*)

- base-printer 456
- bits-per-spot 457
- black-overprint 457
- building-text 458
- callback-number 458
- carriage-control-type 458
- chars 459
- cms-proclink 460
- cms-product 460
- color-mapping-table 461
- compressed-output 461
- content-orientation 462
- control-strip 462
- convert-to-ebcdic 463
- copies 463
- copy-count 463
- data-fidelity-problem-reported 464
- default-character-mapping 464
- default-input-tray 465
- default-medium 466
- default-printer-resolution 467
- department-text 467
- destination-company-text 468
- destination-initial-value-document 468
- destination-pass-through 469
- document-comment 469
- document-content 469
- document-content-list 470
- document-file-name 470
- document-finishing 470
- document-format 471
- document-sequence-number 472
- document-type 472
- dot-shape 474
- email-from-address 475
- email-to-address 475
- enable-settrap 476
- fax-number 476
- fax-to-name 476
- file-name 470
- font-fidelity-action 477
- font-processing-messages 477
- font-resolution 478
- form-definition 478
- format 471
- halftone 479
- image-center-x 480
- image-center-y 481
- image-fit 481
- image-length 482
- image-out-format 483
- image-scale 483
- image-width 484
- initial-value-document 485
- input-exit 486
- input-tray-select 487
- jog-between-job-copies 487
- maximum-messages-printed 488
- maximum-transform-pages-ahead 489
- mvs-class 489

documents, attributes of (*continued*)

- mvs-destination 490
- mvs-forms 490
- mvs-segment-id 491
- name-text 491
- new-line-option 492
- node-id-text 492
- number-up 493
- object-class 493
- octet-count 494
- orientation 462
- originating-company-text 494
- other-options 469
- other-transform options 495
- output-appearance 495
- output-bin 495
- output-face-up 496
- output-format 497
- overlay 498
- overlay-back 499
- overlay-front 499
- overprint 500
- page-clip 500
- page-count 501
- page-definition 501
- page-media-select 502
- page-select 502
- plex 503
- print-quality 504
- printer-initial-value-document 468
- printer-pass-through 469
- programmer-text 504
- resource-context 505
- resource-context-font 506
- resource-context-form-definition 507
- resource-context-overlay 508
- resource-context-page-definition 509
- resource-context-page-segment 509
- resource-context-user 510
- resource-exit 511
- room-text 512
- scanner-correction 512
- screen-frequency 513
- segment-file-size 513
- sequence-number 472
- shared-formdef 514
- shift-out-shift-in 514
- sides 515
- start-on-new-sheet 516
- subject-text 516
- table-reference-characters 516
- title-text 517
- transfer-method 518
- transform-message-file-name 518
- transform-output-file-name 518
- type 472
- used for job scheduling 695
- used for job validation 695
- user-id-text 519
- x-image-shift 519, 520
- y-image-shift 521

- documents, attributes of (*continued*)
  - y-image-shift-back 521
- dot-shape attribute
  - default document 474
  - document 474
- double quotation marks in commands xl
- dss-job-message-disposition attribute
  - actual destination 367
- dss-job-message-log-size attribute
  - actual destination 367
- dss-job-message-log-wrap attribute
  - actual destination 368
- dss-requested attribute
  - default job 532
  - job 532
- dummy form definition 247, 251
- duplex-supported component
  - psf-tray-characteristics attribute, actual destination 420

## E

- ebcdic-character-mapping attribute
  - actual destination 368
- ellipsis in commands xxxix
- email destination support system (DSS) 326
- email-from-address attribute
  - default document 475
  - document 475
- email-to-address attribute
  - default document 475
  - document 475
- enable-settrap attribute
  - default document 476
  - document 476
- enabled attribute
  - actual destination 369
  - log 574
  - logical destination 588
- enabling destinations 37
- end-message attribute
  - default job 539
  - job 539
- end-message-supported attribute
  - actual destination 369
  - logical destination 589
- end-sheets-supported attribute
  - actual destination 370
- environment variables
  - GIF2AFP\_option 652
  - IPR\_PREDPROD 652
  - JPEG2AFP\_option 652
  - LANG 654
  - LC\_ALL 654
  - LC\_CTYPE 654
  - LC\_MESSAGES 655
  - LC\_MONETARY 654
  - LC\_NUMERIC 654
  - LC\_TIME 655
  - MANPATH 652
  - NLSPATH 655

- environment variables (*continued*)
  - PATH 651
  - PD\_CONFIRM\_DELETE 22, 30, 88, 651
  - PD\_ENABLE\_TIMEOUT 652
  - PD\_LISTEN\_COUNT 652
  - PD\_SOCKET 652
  - PDBASE 653
  - PDIDTABLE 651
  - PDNAMESP 653
  - PDPATH 11, 651
  - PDPRINTER 63, 74, 651
  - PPO\_CANCEL\_ALL\_OPTION 653
  - PPO\_DEFAULT\_ENV 653
  - PPO\_FORM 653
  - PPO\_JOB\_BATCH 653
  - PPO\_JOB\_DETAILS\_ATTRS 653
  - PPO\_LP 653
  - PPO\_LPS 654
  - PPO\_PP\_ATTRS 654
  - PPO\_PPS 654
  - PPO\_QUEUE 654
  - PPO\_QUEUE\_ATTRS 654
  - PPO\_QUEUE\_INFO\_FILE 654
  - PPO\_SERVER 654
  - PPO\_TRACE\_FILE 654
  - PSFDBLANG 652
  - PSFPATH 652
  - table of 651
  - TIFF2AFP\_option 653
  - TYPESETTER 653
  - XBMLANGPATH 653
- equals signs in commands xl
- estimated-completion-time attribute
  - job 533
- estimated-processing-time attribute
  - job 534
- event-comment component
  - notification-profile attribute
    - actual destination 395
    - default job 559
    - job 559
    - logical destination 594
    - queue 616
    - server 636
- event-identifier component
  - notification-profile attribute
    - actual destination 394
    - default job 558
    - job 558
    - logical destination 593
    - queue 615
    - server 635
- events-supported attribute
  - server 627
- examples
  - of commands
    - lprafp 16
    - mkfntmap 18
    - pdaccount 21
    - pdclean 24
    - pdcreate 28

examples (*continued*)

- pddelete 32
- pddisable 36
- pdenable 39
- pdls 46
- pdmod 54
- pdpause 62
- pdpr 68, 70
- pdpromote 73
- pdq 77
- pdreorder 80
- pdresubmit 84
- pdresume 87
- pdrm 89
- pdset 94
- pdshutdown 99
- pdspace 102
- of transforms
  - line2afp 257
  - pcl2afp 275
  - pdf2afp 296
  - ps2afp 296
  - sap2afp 309
- of utilities
  - admingui 128
  - afpsplit 129
  - ainupod1 130
  - ainupod2 131
  - ainupod3 132
  - ainurpt1 134
  - ainurpt2 135
  - ainurpt3 136
  - ainurpt4 138
  - ainurpt5 139
  - ainurpt6 140
  - cfu 142
  - ipguibasic 145, 146
  - jsmigr 149
  - mvsprsd 187
  - opergui 151
  - pcl2afpd 190
  - pdadmin 152
  - pdcr cds 153
  - pdcrfilt 155
  - pdcrmed 156
  - pdinitports 158
  - pdmigpp 159
  - pdmincfg 161
  - pdmsg 163
  - ps2afpd 193
  - sense 168, 170
  - setup 173
  - start\_server 177
  - startcbd 197
  - startppo 175
  - startsrv 179
  - stop\_server 180
  - stopcbd 199
  - t2file 184
  - tdump 181
  - tlist 183

exits

- input 247
- output 249
- resource 254

## F

- fax destination support system (DSS) 327
- fax-number attribute
  - default document 476
  - document 476
- fax-to-name attribute
  - default document 476
  - document 476
- fdeflib option 242
- file-name attribute
  - document 470
- file names
  - of form definitions 246
  - of input file 248
  - of output file 249
  - of page definitions 250
  - specified with inputdd option 248
  - specified with outputdd option 249
  - specified with pagedef option 250
- file-reference document, definition 470, 473
- fileformat option 243
- files
  - /etc/services 157
  - barcode.tab 300
  - defcp.tab 302
  - fonts.tab 302
  - for transforms
    - db2afp 205
    - gif2afp 213
    - jpeg2afp 227
    - line2afp 259
    - pcl2afp 273, 282
    - pdf2afp 294, 297
    - ps2afp 294, 297
    - sap2afp 299
    - tiff2afp 315
  - for utilities
    - pcl2afpd 190
    - ps2afpd 193
  - gif2afp.cfg 213
  - image.tab 305
  - input
    - for line2afp 248
  - jpeg2afp.cfg 227
  - output
    - for line2afp transform 249
    - for pdf2afp transform 290
    - for ps2afp transform 290
  - pagedef.tab 306
  - pcl2afp 273
  - pcl2afpd 273
  - printer.tab 307
  - ps2afp 294
  - ps2afpd 294
  - readme xxxvi

- files (*continued*)
  - S9148.CPA 304
  - tiff2afp.cfg 315
  - xxxxyyyy.tab 308
- files, MO:DCA-P, extracting pages 129
- filters
  - operators, pdls command 42
- first-page component
  - page-select attribute
    - document 502
- flags
  - general description of 8
  - line2afp 239
  - of commands
    - lprafp 15
    - pdclean 22
    - pdcreate 26
    - pddelete 30
    - pddisable 34
    - pdenable 37
    - pdls 41
    - pdmod 52
    - pdpause 57
    - pdpr 64
    - pdpromote 72
    - pdq 74
    - pdreorder 79
    - pdresubmit 81
    - pdresume 85
    - pdrm 88
    - pdset 92
    - pdshutdown 97
    - pdspace 101
  - of transforms
    - d2afp 207
    - db2afp 202
    - pcl2afp 263
    - pdf2afp 286
    - ps2afp 286
    - sap2afp 299
  - of utilities
    - admingui 128
    - afpsplit 129
    - cfu 141
    - cmt 143
    - mvsprsd 186
    - opergui 151
    - pcl2afpd 188
    - pdcrdfilt 154
    - pdinitports 157
    - pdmincfg 161
    - pdmsg 163
    - ps2afpd 191
    - setup 172
    - start\_server 176
    - startspl 175
    - startsrv 178
    - stop\_server 180
    - t2file 184
    - tdump 181
    - tlist 183
- font-escape component
  - actual destination 335
- font-fidelity-action attribute
  - default document 477
  - document 477
- font map file keyword on ps2afp or pdf2afp
  - transform 287
- font-name component
  - actual destination 335
- font-processing-messages attribute
  - default document 477
  - document 477
- font-resolution attribute
  - default document 478
  - document 478
- font-resolutions-supported attribute
  - actual destination 370
- fontlib option 244
- fonts
  - converting ASCII to EBCDIC 248
  - directory 244
  - search path for line data transform 244
  - specifying with chars 240
- fonts.tab file 302
- force-destination-setup attribute
  - actual destination 371
- force-printer-setup attribute
  - actual destination 371
- form-definition attribute
  - actual destination 372
  - default document 478
  - document 478
- form definitions
  - default 699
  - file name 246
  - for 11 by 17 inch paper 701
  - for envelopes 701
  - for n\_up page positioning 703
  - for pre-punched paper 704
  - general purpose 699
  - inline 247
  - printer-model specific 705
  - search path for line data transform 242
  - specified with formdef option 246
  - supplied with Infoprint 699
  - with a 0,0 offset 702
- format
  - of input file 243
- format attribute
  - default document 471
  - document 471
- formatted-job-ticket-content attribute
  - job 534
- formdef option 246

## G

- gif2afp transform
  - configuration file 213
  - description 209
  - limitations 214
  - options 214

- gif2afp transform (*continued*)
  - syntax 209
- global characters (wildcards) 9
- global-id attribute
  - job 541
- global job identifier
  - global-id, job-attribute 541
  - job-identifier, job-attribute 541
  - new-job-identifier, job-attribute 557
- glossary 709

## H

- halftone attribute
  - default document 479
  - document 479
- halftones-supported attribute
  - actual destination 372
- height
  - PostScript image 289
- highlighting conventions xxxviii
- hostname attribute
  - server 640
- hostname of the server 640
- HRI character 300
- human readable interface (HRI) character 300

## I

- i-p-address attribute
  - server 640
- image-center-x attribute
  - default document 480
  - document 480
- image-center-y attribute
  - default document 481
  - document 481
- image-fit attribute
  - default document 481
  - document 481
- image-fit-supported attribute
  - actual destination 374
- image-length attribute
  - actual destination 374
  - default document 482
  - document 482
- image-out-format
  - default document 483
  - document 483
- image-out-formats-supported
  - actual destination 375
  - logical destination 589
- image output 247
- image-scale attribute
  - default document 483
  - document 483
- image.tab file 305
- image-width attribute
  - actual destination 376
  - default document 484
  - document 484
- imageout option 247

- images
  - resolution 291
- Infoprint 2000 DSS destination support system (DSS) 326
- Infoprint Installer, starting 172
- Infoprint Manager Administration GUI, starting 146
- Infoprint Manager Operations GUI, starting 145
- Infoprint SMIT production print operations interface, starting 175
- initial-value-document attribute
  - document 485
- initial-value-document-identifier attribute
  - default document 485
- initial-value-job attribute
  - job 535
- initial-value-job-identifier attribute
  - default job 535
- initially settable attribute listing
  - actual destination 329
  - document 449
  - job 523
  - log 573
  - logical destination 578
- inline resources
  - for PDF jobs 297
  - for PostScript jobs 297
  - form definition 247
  - page definition 251
- inpexit option 247
- input-data-user-exit attribute
  - actual destination 377
- input exit 247
- input-exit attribute
  - default document 486
  - document 486
- input files
  - specifying file name 248
  - specifying format 243
- input-tray component
  - psf-tray-characteristics attribute, actual destination 418
- input-tray-select attribute
  - default document 487
  - document 487
- input-trays-medium attribute
  - actual destination 377
- input-trays-supported attribute
  - actual destination 379
  - logical destination 590
- inputddd option 248
- installer, starting 172
- internet address of the host processor 640
- intervening-jobs attribute
  - job 535
- intervention-timer attribute
  - actual destination 379
- ip-address attribute
  - server 640
- ipguiadv utility
  - description 145, 146
  - syntax 145, 146

ipguibasic utility  
description 145, 146  
examples 145, 146  
syntax 145, 146  
ipguidist utility  
description 145, 146  
syntax 145, 146  
IPP destination support system (DSS) 327

## J

job-attributes-supported attribute  
actual destination 380  
server 629  
job-batch attribute  
default job 536  
job 536  
job-batches-ready attribute  
actual destination 380  
job-bin-number component  
psf-tray-characteristics attribute, actual  
destination 419  
job-client-id attribute  
job 536  
job-comment attribute  
default job 536  
job 536  
job-complexity attribute  
job 537  
job-copies-completed attribute  
job 537  
job-copies component  
results-profile attribute  
default job 567  
job 567  
job-deadline-time attribute  
job 538  
job-discard-time attribute  
job 538  
job-end-message attribute  
default job 539  
job 539  
job-finishing attribute  
default job 539  
job 539  
job-finishings-supported attribute  
actual destination 381  
job-hold attribute  
default job 540  
job 540  
job-identifier attribute  
job 541  
job-log attribute  
job 541  
job-media-sheet-count attribute  
job 542  
job-message-from-administrator attribute  
job 542  
job-message-to-operator attribute  
default job 543  
job 543  
job-name attribute  
job 543  
job-originator attribute  
default job 544  
job 544  
job-owner attribute  
job 544  
job-page-count  
job 545  
job-print-after attribute  
job 545  
job-priority attribute  
default job 546  
job 546  
job-retain-until attribute  
job 546  
job-retention-period attribute  
default job 547  
job 547  
job-retry-count-limit attribute  
actual destination 381  
job-retry-interval attribute  
actual destination 382  
job-rip-action attribute  
default job 547  
job 547  
job-rip-actions-supported attribute  
actual destination 382  
job-ripped-by-server attribute  
default job 548  
job 548  
job scripts, PSF for AIX, migrating 148  
job-size attribute  
job 571  
job-size-range-ready attribute  
actual destination 383  
job-size-range-supported attribute  
actual destination 384  
logical destination 590  
job-start-message attribute  
default job 551  
job 551  
job-start-wait attribute  
job 552  
job-start-wait-supported attribute  
job 385  
job-state attribute  
job 526  
job-state-reasons attribute  
job 552  
job-states-supported attribute  
server 630  
job-submission-complete attribute  
job 554  
job-submission-timer attribute  
server 630  
job-ticket-content attribute  
job 534  
jobs, attributes of  
actual-destinations-requested 524  
auxiliary-sheet-selection 525  
comment 536  
completion-time 526

jobs, attributes of (*continued*)

- current-job-state 526
- current-page-printing 527
- d-s-s-requested 532
- deadline-in-jeopardy 528
- delete-segment-list 528
- destination-initial-value-job 529
- destination-locations-requested 530
- destination-models-requested 530
- destination-name-requested 531
- destinations-assigned 531
- destinations-used 532
- device-support-system-requested 532
- discard-time 538
- dss-requested 532
- end-message 539
- estimated-completion-time 533
- estimated-processing-time 534
- formatted-job-ticket-content 534
- global-id 541
- hold 540
- initial-value-job 535
- intervening-jobs 535
- job-batch 536
- job-client-id 536
- job-comment 536
- job-complexity 537
- job-copies-completed 537
- job-deadline-time 538
- job-discard-time 538
- job-end-message 539
- job-finishing 539
- job-hold 540
- job-identifier 541
- job-log 541
- job-media-sheet-count 542
- job-message-from-administrator 542
- job-message-to-operator 543
- job-name 543
- job-originator 544
- job-owner 544
- job-page-count 545
- job-print-after 545
- job-priority 546
- job-retain-until 546
- job-retention-period 547
- job-rip-action 547
- job-ripped-by-server 548
- job-size 571
- job-start-message 551
- job-start-wait 552
- job-state 526
- job-state-reasons 552
- job-submission-complete 554
- job-ticket-content 534
- last-accessor 557
- last-modifier 557
- locations-requested 530
- logical-printer-requested 531
- media-sheet-count 542
- media-sheets-completed 556

jobs, attributes of (*continued*)

- message-from-administrator 542
- message-to-operator 543
- models-requested 530
- modification-time 557
- name 543
- name-of-last-accessor 557
- new-job-identifier 557
- notification-profile 558
- number-of-documents 560
- object-class 560
- octets-completed 561
- optimize-for-multiple-copies 561
- originator 544
- owner 544
- pages-completed 562
- physical-printers-requested 524
- position-in-queue 535
- previous-job-state 563
- previous-state 563
- print-after 545
- printer-initial-value-job 529
- printer-locations-requested 530
- printer-models-requested 530
- printer-name-requested 531
- printer-requested 531
- printers-assigned 531
- printers-used 532
- processing-time 564
- queue-assigned 565
- queue-position 535
- reasons 552
- required-resources-not-ready 565
- required-resources-not-supported 566
- results-profile 566
- retained-time 568
- retention-period 547
- start-message 551
- started-printing-time 568
- state-reasons 552
- submission-time 568
- tape-exit 569
- tape-format 569
- tape-labeled 570
- tape-maximum-block-size 570
- tape-rewind-before 570
- tape-rewind-unload 571
- ticket-content 534
- total-job-octets 571
- used for job scheduling 695
- used for job validation 695
- user-locale 572
- user-name 572
- jog-between-job-copies
  - default document 487
  - document 487
- jpeg2afp transform
  - configuration file 227
  - description 223
  - limitations 228
  - options 228



jpeg2afp transform *(continued)*  
syntax 223  
jsmigr utility  
arguments 149  
description 148  
examples 149  
syntax 148

## K

keywords  
pdf2afp transform  
height of image 289  
length of image 289  
maximum memory 290  
output file 290  
port 290  
quiet 291  
resolution 291  
selected pages 290  
server name 291  
server time out 291  
width of image 292  
X offset 292  
Y offset 293  
ps2afp transform  
height of image 289  
length of image 289  
maximum memory 290  
output file 290  
port 290  
resolution 291  
selected pages 290  
server name 291  
server time out 291  
width of image 292  
X offset 292  
Y offset 293

## L

last-accessor attribute  
job 557  
last-modifier attribute  
job 557  
last-page component  
page-select attribute  
document 502  
length  
PostScript image 289  
length keyword  
pdf2afp transform 289  
ps2afp transform 289  
limitations  
of transforms  
d2afp 206  
db2afp 202  
gif2afp 214  
jpeg2afp 228  
pcl2afp 262  
pdf2afp 285

limitations *(continued)*  
of transforms *(continued)*  
ps2afp 285  
tiff2afp 316  
line data  
examples of printing  
S/370 file 257  
unformatted ASCII 257  
search paths for resources  
AFP resources 256  
fonts 244  
form definitions 242  
overlays 249  
page definitions 252  
page segments 253  
system resources 255  
line2afp transform  
examples 257  
files 259  
flags 239  
syntax 236, 237  
list-of-managers attribute  
actual destination 385  
default document 487  
default job 554  
logical destination 591  
queue 614  
server 630  
listing attribute values 40  
listing of attributes used of job validation and  
scheduling 695  
locale attribute  
server 631  
locale component  
notification-profile attribute  
actual destination 395  
default job 560  
job 560  
logical destination 594  
queue 616  
server 636  
locations attribute  
actual destination 351  
logical destination 585  
locations-requested attribute  
default job 530  
job 530  
log-accounting data attribute  
actual destination 386  
server 631  
log-address attribute  
log 574  
log-identifier attribute  
log 574  
log-message attribute  
log 575  
log-severity attribute  
log 575  
log-size attribute  
log 576

- log-trace-groups attribute
  - log 576
- log-type attribute
  - log 576
- log-wrap attribute
  - log 577
- logical destinations, attributes of
  - associated-queue 579
  - associated-server 579
  - authorize-jobs 580
  - auxiliary-sheet-selections-supported 580
  - carriage-control-types-supported 581
  - character-mappings-supported 581
  - content-orientations-supported 581
  - convert-to-ebcdic-supported 582
  - data-fidelity-problem-reported-supported 583
  - descriptor 583
  - destination-associated-destinations 584
  - destination-initial-value-document 584
  - destination-initial-value-job 584
  - destination-locations 585
  - destination-model 585
  - destination-name 585
  - destination-realization 586
  - destination-support-system 586
  - destinations-ready 587
  - device-support-system 586
  - document-formats-supported 587
  - document-types-supported 588
  - enabled 588
  - end-message-supported 589
  - image-out-formats-supported 589
  - input-trays-supported 590
  - job-size-range-supported 590
  - list-of-managers 591
  - locations 585
  - logical-printer 585
  - managers 591
  - maximum-copies-supported 592
  - media-supported 592
  - message 593
  - model 585
  - notification-profile 593
  - nt-drivers 440, 601
  - object-class 595
  - orientations-supported 581
  - os2-driver-names 595
  - os2-drivers 595
  - page-select-supported 596
  - plexes-supported 597
  - print-qualities-supported 597
  - printer 585
  - printer-associated-printers 584
  - printer-initial-value-document 584
  - printer-initial-value-job 584
  - printer-locations 585
  - printer-model 585
  - printer-name 585
  - printer-realization 586
  - printers-ready 587
  - protected-attributes 598
- logical destinations, attributes of (*continued*)
  - qualities-supported 597
  - sides-supported 598
  - start-message-supported 599
  - table-reference-characters-supported 599
  - used for job validation 695
  - windows-driver-names 600
  - windows-drivers 600
  - windows-nt-driver-names 440, 601
  - windows-nt-drivers 440, 601
  - x-image-shift-supported 601
  - y-image-shift-supported 602
- logical-destinations-assigned
  - actual destination 387
- logical-destinations-assigned attribute
  - queue 614
- logical-destinations-ready attribute
  - default document 488
  - default job 555
  - queue 614
  - server 632
- logical-destinations-supported attribute
  - server 632
- logical-printer attribute
  - logical destination 585
- logical-printer-requested attribute
  - job 531
- logical-printers-assigned attribute
  - queue 614
- logical-printers-ready attribute
  - default document 488
  - default job 555
  - queue 614
  - server 632
- logical-printers-supported attribute
  - server 632
- logs, attributes of
  - associated-server 573
  - descriptor 573
  - enabled 574
  - log-address 574
  - log-identifier 574
  - log-messages 575
  - log-severity 575
  - log-size 576
  - log-trace-groups 576
  - log-type 576
  - log-wrap 577
  - object-class 577
- lower-limit component
  - job-size-range-ready attribute
    - actual destination 383
  - job-size-range-supported attribute
    - actual destination 384
    - logical destination 590
  - x-image-shift-range-supported attribute
    - actual destination 441
    - logical destination 602
  - y-image-shift-range-supported attribute
    - actual destination 442
    - logical destination 602

- lprfp command
  - arguments 15
  - examples 16
  - files 16
  - flags 15
  - syntax 15

## M

- machine code carriage-control characters 240
- managers attribute
  - actual destination 385
  - default document 487
  - default job 554
  - logical destination 591
  - queue 614
  - server 630
- margins of PDF images
  - X offset 292
  - Y offset 293
- margins of PostScript images
  - X offset 292
  - Y offset 293
- maximum-barco-rips attribute
  - server 633
- maximum-concurrent-jobs attribute
  - actual destination 387
- maximum-copies-supported attribute
  - actual destination 388
  - logical destination 592
- maximum-fonts-to-keep attribute
  - actual destination 389
- maximum memory keyword
  - pdf2afp transform 290
  - ps2afp transform 290
- maximum-messages-printed attribute
  - default document 488
  - document 488
- maximum-non-raster-rips attribute
  - server 633
- maximum-overlays-to-keep attribute
  - actual destination 389
- maximum-raster-rips attribute
  - server 633
- maximum-segments-to-keep attribute
  - actual destination 390
- maximum-transform-pages-ahead attribute
  - default document 489
  - document 489
- media, attributes of
  - associated-server 604
  - descriptor 605
  - medium-color 605
  - medium-dimensions 605
  - medium-form-parts 606
  - medium-holes-count 606
  - medium-identifier 607
  - medium-sides 607
  - medium-size 608
  - medium-type 608
  - medium-wight 609
- media, attributes of *(continued)*
  - message 609
  - object-class 609
- media, creating commonly used 156
- media-loaded component
  - psf-tray-characteristics attribute, actual destination 419
- media-ready attribute
  - actual destination 390
- media-sheet-count attribute
  - job 542
- media-sheets-completed attribute
  - job 556
- media-supported attribute
  - actual destination 391
  - logical destination 592
- medium-color attribute
  - medium 605
- medium-dimensions attribute
  - medium 605
- medium-form-parts attribute
  - medium 606
- medium-holes-count attribute
  - medium 606
- medium-identifier attribute
  - medium 607
- medium-identifier component
  - input-trays-medium attribute, actual destination 378
- medium-sides attribute
  - medium 607
- medium-size attribute
  - medium 608
- medium-type attribute
  - medium 608
- medium-weight attribute
  - medium-weight 609

- message attribute
  - actual destination 392
  - default document 489
  - default job 556
  - logical destination 593
  - medium 609
  - queue 615
  - server 634
- message-count, command attribute
  - pdl 44
- message-font-type attribute
  - actual destination 393
- message-form-definition attribute
  - actual destination 393
- message-from-administrator attribute
  - job 542
- message-to-operator attribute
  - default job 543
  - job 543
- messages
  - specifying where written 249
- messages, displaying information about 163
- migrating an existing printer 159
- migrating PSF for AIX job scripts 148
- minimum configuration, setting up 161

- mkfntmap command
  - arguments 17
  - description 17
  - examples 18
  - syntax 17
- MO:DCA-P files, extracting pages 129
- model attribute
  - actual destination 351
  - logical destination 585
- models-requested attribute
  - default job 530
  - job 530
- modification-time attribute
  - job 557
- modify-individual-document-supported attribute
  - server 634
- modifying attributes of submitted jobs 51
- ModWidth optional keyword
  - barcode.tab configuration file 300
- msgdd option 249
- multiple-documents-supported attribute
  - spooler 634
- mvs-class attribute
  - default document 489
  - document 489
- mvs-destination attribute
  - default document 490
  - document 490
- mvs-forms attribute
  - default document 490
  - document 490
- mvs-segment-id attribute
  - default document 491
  - document 491
- mvsprsd daemon 186
- mvsprsd utility
  - description 186
  - examples 187
  - flags 186
  - syntax 186

## N

- name attribute
  - job 543
- name-of-last-accessor attribute
  - job 557
- name of server 641
- name-text attribute
  - default document 491
  - document 491
- new-job-identifier attribute
  - job 557
- new-line-option attribute
  - default document 492
  - document 492
- node-id-text attribute
  - default document 492
  - document 492
- non-process-runout-timer attribute
  - actual destination 394

- notational conventions xxxix
- notification client daemon 150
- notification-delivery-methods-supported attribute
  - server 634
- notification events
  - classes 667
  - list of 657
- notification profile 6
- notification-profile attribute
  - actual destination 394
  - default job 558
  - job 558
  - logical destination 593
  - queue 615
  - server 635
- notify-operator attribute
  - actual destination 396
  - queue 616
  - queue example 7
- notifyd daemon 195, 196
- npm-server-ip-address attribute
  - server 636
- npm-server-port-number attribute
  - server 637
- nt-drivers attribute
  - actual destination 440
  - logical destination 601
  - server 644
- number-of-documents attribute
  - job 560
- number-up attribute
  - document 493
- number-up-supported attribute
  - actual destination 396

## O

- object attributes 4
- object attributes, default values for 5
- object attributes of commands
  - pdcreate
    - documents 27
    - jobs 27
  - pdpr 67
- object-class attribute
  - auxiliary sheet 444
  - default document 493
  - default job 560
  - document 493
  - job 560
  - log 577
  - logical destination 595
  - medium 609
  - queue 617
  - resource context 621, 646
  - server 637
- object classes 3
- object classes, general descriptions of 3
- object-classes-supported attribute
  - server 637
- objects, general descriptions of 3

- octet-count attribute
  - document 494
- octets-completed attribute
  - job 561
- offset-stacking-available attribute
  - actual destination 397
- operators attribute
  - queue 616
- opergui utility
  - arguments 151
  - description 151
  - examples 151
  - flags 151
  - syntax 151
- optimize for-multiple-copies attribute
  - actual destination 398
  - default job 561
  - job 561
- options
  - of transforms
    - gif2afp 214
    - jpeg2afp 228
    - tiff2afp 316
- orientation attribute
  - default document 462
  - document 462
- orientations-supported attribute
  - actual destination 345
  - logical destination 581
- originator attribute
  - default job 544
  - job 544
- os2-driver-names attribute 595
  - logical destination 595
- os2-drivers attribute
  - logical destination 595
- other-options attribute
  - actual destination 353
  - default document 469
  - document 469
- other-transform-options attribute
  - default document 495
  - document 495
  - examples 648
  - other-transform-options 647
- outexit option 249
- output-appearance attribute
  - default document 495
  - document 495
- output-appearances-supported attribute
  - actual destination 399
- output-bin attribute
  - actual destination 399
  - default document 495
  - document 495
- output-bin component
  - results-profile attribute
    - default job 567
    - job 567
- output-bin-numbers attribute
  - actual destination 400

- output-bins-supported attribute
  - actual destination 401
- output-data-user-exit attribute
  - actual destination 402
- output exit 249
- output-face-up attribute
  - default document 496
  - document 496
- output files
  - for PostScript 290
  - specifying file name 249
- output-format attribute
  - default document 497
  - document 497
- output-format-supported attribute
  - actual destination 402
- outputdd option 249
- overlay attribute
  - actual destination 403
  - default document 498
  - document 498
- overlay-back attribute
  - default document 499
  - document 499
- overlay-front attribute
  - default document 499
  - document 499
- overlays
  - directory 249
- overprint attribute
  - default document 500
  - document 500
- ovlylib option 249
- owner attribute
  - job 544

## P

- page-clip attribute
  - default document 500
  - document 500
- page-count attribute
  - document 501
- page-definition attribute
  - default document 501
  - document 501
- page definitions
  - directory 250, 251
  - for A4 paper 706
  - for B4 708
  - for legal-sized paper 707
  - for letter-sized paper 706
  - for multiple-up 707
  - inline 251
  - specified with pagedef option 250
  - supplied with Infoprint 699
- page-media-select attribute
  - default document 502
  - document 502
- page segments
  - directory 253

- page-select attribute
  - document 502
- page-select-supported attribute
  - actual destination 403
- pagedef option 250
- pagedef.tab file 306
- pages, extracting from MO:DCA-P files 129
- pages-completed attribute
  - job 562
- parmdd option 252
- Passthrough destination support system (DSS) 327
- paths
  - font directory 244
  - form definition directory 242
  - overlay directory 249
  - page definition directory 252
  - page segment directory 253
  - resource directory 255
  - user directories 256
- pausing jobs, actual destinations, servers, or queues 56
- pcl-server-address attribute
  - actual destination 404
- pcl-server-port attribute
  - actual destination 404
- pcl2afp transform
  - configuration files
    - pcl2afp file 273
    - pcl2afpd file 273
  - description 261
  - examples, complex 276
  - examples, simple 275
  - files 273, 282
  - flags 263
  - limitations 262
  - syntax 261
- pcl2afpd daemon 188, 262
  - configuration file 273
- pcl2afpd utility
  - configuration file 188
  - description 188
  - examples 190
  - files 190
  - flags 188
  - syntax 188
- PD\_CONFIRM\_DELETE environment variable 22, 30, 88
- pdaccount command
  - arguments 20
  - description 19
  - examples 21
  - flags 19
  - syntax 19
- pdadmin utility
  - description 152
  - examples 152
  - syntax 152
- pdclean command
  - arguments 23
  - command attributes 23
  - description 22
- pdclean command (*continued*)
  - examples 24
  - flags 22
  - syntax 22
- pdcrds utility
  - description 153
  - examples 153
  - syntax 153
- pdcrdflt utility
  - arguments 155
  - description 154
  - examples 155
  - flags 154
  - syntax 154
- pdcreate command
  - arguments 27
  - attributes 27
  - command attributes 27
  - description 25
  - examples 28
  - flags 26
  - syntax 25
- pdcrmed utility
  - arguments 156
  - description 156
  - examples 156
  - syntax 156
- pddelete command
  - arguments 31
  - command attributes 31
  - description 30
  - examples 32
  - flags 30
  - syntax 30
- pddisable command
  - arguments 35
  - command attributes 35
  - description 34
  - examples 36
  - flags 34
  - syntax 34
- pdeflib option 252
- pdenable command
  - arguments 38
  - command attributes 38
  - description 37
  - examples 39
  - flags 37
  - syntax 37
- PDF
  - inline resources 297
  - margins
    - X offset 292
    - Y offset 293
  - resolution of output 291
  - transforming and printing 296
  - width of image 292
- pdf2afp transform
  - configuration files
    - ps2afp file 294
    - ps2afpd file 294

pdf2afp transform (*continued*)

- description 284
- examples 296
- files 294, 297
- flags 286
- keywords
  - height of image 289
  - length of image 289
  - maximum memory 290
  - output file 290
  - port 290
  - quiet 291
  - resolution 291
  - selected pages 290
  - server name 291
  - server time out 291
  - width of image 292
  - Y offset 293
- limitations 285
- syntax 284

pdf2fp transform

- keywords
  - X offset 292

pdinitports utility

- arguments 157
- description 157
- examples 158
- flags 157
- syntax 157

pdis command

- arguments 45
- attribute operators for filters 42
- command attributes 42
- description 40
- examples 46
- flags 41
- syntax 40

pdmigpp utility

- arguments 159
- description 159
- examples 159
- syntax 159

pdmincfg utility

- arguments 161
- description 161
- examples 161
- flags 161
- syntax 161

pdmod command

- arguments 54
- command attributes 53
- description 51
- examples 54
- flags 52
- syntax 51

pdmsg utility

- description 163
- examples 163
- flags 163
- syntax 163

PDPATH environment variable 11

pdpause command

- arguments 60
- command attributes 58
- description 56
- examples 62
- flags 57
- syntax 56

pdpr command

- arguments 67
- command attributes 66
- description 63
- examples 68, 70
- flags 64
- object attributes 67
- syntax 63

PDPRINTER environment variable 63, 74

pdpromote command

- arguments 73
- command attributes 73
- description 72
- examples 73
- flags 72
- syntax 72

pdq command

- arguments 77
- command attributes 76
- description 74
- examples 77
- flags 74
- syntax 74, 79

pdreorder command

- arguments 80
- command attributes 80
- description 79
- examples 80
- flags 79

pdresubmit command

- arguments 83
- command attributes 82
- description 81
- examples 84
- flags 81
- syntax 81

pdresume command

- arguments 86
- command attributes 86
- description 85
- examples 87
- flags 85
- syntax 85

pdrm command

- arguments 89
- command attributes 89
- description 88
- examples 89
- flags 88
- syntax 88

pdset command

- arguments 94
- command attributes 93
- description 91

pdset command (*continued*)

- examples 94
- flags 92
- syntax 91

pdshutdown command

- arguments 99
- command attributes 98
- description 96
- examples 99
- flags 97
- syntax 96

pdspace command

- arguments 102
- command attributes 101
- description 100
- examples 102
- flags 101
- syntax 100

pel output

- for PostScript 291
- output for PDF 291

per-document attribute listing 451

physical-printer attribute

- actual destination 352

physical-printers-assigned attribute

- queue 610

physical-printers-ready attribute

- queue 610
- server 624

physical-printers-requested attribute

- default job 524
- job 524

physical-printers-supported attribute

- server 624

plex attribute

- actual destination 405
- default document 503
- document 503

plexes-supported attribute

- actual destination 405
- logical destination 597

port number keyword

- pdf2afp transform 290
- ps2afp transform 290

position-in-queue attribute

- job 535

PostScript

- height of image 289
- inline resources 297
- length of image 289
- margins
  - X offset 292
  - Y offset 293
- resolution of output 291
- transforming and printing 296
- width of image 292

postscript-server-address attribute

- actual destination 406
- logical destination 596

postscript-server-port attribute

- actual destination 407

presentation-fidelity-problem-reported attribute

- actual destination 407

previous-job-state attribute

- job 563

previous-state attribute

- job 563

Print Administration window, opening 128

print-after attribute

- job 545

print-edge-marks attribute

- actual destination 408

Print Management window, opening 151

print-qualities-supported attribute

- actual destination 408
- logical destination 597

print-quality attribute

- default document 504
- document 504

print-queue-name attribute

- actual destination 409

print queues

- migrating 159

printer-associated-printers attribute

- logical destination 584

printer attribute

- actual destination 352
- logical destination 585

printer-command attribute

- actual destination 349

printer-data-stream attribute

- actual destination 350

printer-end-sheet attribute

- actual destination 409

printer-escape-codes attribute

- actual destination 410

printer-initial-value-document attribute

- document 468
- logical destination 584

printer-initial-value-job attribute

- job 529
- logical destination 584

printer-locations attribute

- actual destination 351
- logical destination 585

printer-locations-requested attribute

- default job 530
- job 530

printer-memory attribute

- actual destination 411

printer-model attribute

- actual destination 351
- logical destination 585

printer-models-requested attribute

- default job 530
- job 530

printer-name attribute

- actual destination 352
- logical destination 585

printer-name-requested attribute

- job 531



- printer-needs-attention-time attribute
  - actual destination 353
- printer-needs-key-operator-attention-time attribute
  - actual destination 353
- printer-pass-through attribute
  - actual destination 353
  - default document 469
  - document 469
- printer-realization attribute
  - actual destination 354
  - logical destination 586
- printer-register-threshold attribute
  - actual destination 355
- printer-release-timer attribute
  - actual destination 355
- printer-requested attribute
  - job 531
- printer-resolutions-ready attribute
  - actual destination 412
- printer-resolutions-supported attribute
  - actual destination 413
- printer-s370-channel-device-address attribute
  - actual destination 416
- printer-s370-channel-slot-number attribute
  - actual destination 416
- printer-separator-sheet attribute
  - actual destination 414
- printer-start-sheet attribute
  - actual destination 414
- printer-state attribute
  - actual destination 356
- printer-states-supported attribute
  - server 626
- printer.tab file 307
- printer-tcpip-internet-address attribute
  - actual destination 358
- printer-tcpip-port-number attribute
  - actual destination 359
- printer-timeout-period attribute
  - actual destination 359
- printers, attributes of
  - used for job scheduling 695
  - used for job validation 695
- printers, channel-attached, sensing 167
- printers-assigned attribute
  - job 531
- printers-ready attribute
  - logical destination 587
- printers-used attribute
  - job 532
- prmode option 253
- problem-child attribute
  - server 638
- problem-message attribute
  - actual destination 417
- processing-time attribute
  - job 564
- programmer-text attribute
  - default document 504
  - document 504
- promoting a job to the top of a queue 72
- protected-attributes attribute
  - actual destination 417
  - logical destination 598
  - queue 618
  - server 638
- ps2afp transform
  - configuration files
    - ps2afp file 294
    - ps2afpd file 294
  - description 284
  - examples 296
  - files 294, 297
  - flags 286
  - keywords
    - height of image 289
    - length of image 289
    - maximum memory 290
    - output file 290
    - port 290
    - resolution 291
    - selected pages 290
    - server name 291
    - server time out 291
    - width of image 292
    - X offset 292
    - Y offset 293
  - limitations 285
  - syntax 284
- ps2afpd daemon 191, 285
  - configuration file 294
- ps2afpd utility
  - configuration file 191
  - description 191, 195, 197
  - examples 193, 197, 199
  - files 193
  - flags 191
  - syntax 191, 195
- pseglib option 253
- PSF destination support system (DSS) 326, 327
- psf-exit-form-definition attribute
  - auxiliary sheet 444
- psf-exit-page-mark attribute
  - auxiliary sheet 444
- psf-exit-program-name attribute
  - auxiliary sheet 445
- PSF for AIX job scripts, migrating 148
- psf-tray-characteristics attribute
  - actual destination 418

## Q

- qualities-supported attribute
  - actual destination 408
  - logical destination 597
- querying the status of jobs 74
- queue-assigned attribute
  - job 565
- queue-backlog attribute
  - queue 618
- queue-name attribute
  - queue 618

- queue-position attribute
  - job 535
- queue-state attribute
  - queue 618
- queues, attributes of
  - actual-destinations-assigned 610
  - actual-destinations-ready 610
  - assign-to-destination 611
  - assign-to-printer 611
  - associated-server 611
  - backlog 618
  - backlog-lower-bound 612
  - backlog-update-interval 612
  - backlog-upper-bound 613
  - backlogged 613
  - current-backlog 618
  - descriptor 613
  - list-of-managers 614
  - logical-destinations-assigned 614
  - logical-destinations-ready 614
  - logical-printers-assigned 614
  - logical-printers-ready 614
  - managers 614
  - message 615
  - notification-profile 615
  - notify-operator 616
  - object-class 617
  - operators 616
  - physical-printers-assigned 610
  - physical-printers-ready 610
  - protected-attributes 618
  - queue-backlog 618
  - queue-name 618
  - queue-state 618
  - requeue-failed-jobs 619
- queues-supported attribute
  - server 639
- quiet keyword
  - pdf2afp transform 291

## R

- R/3 output device
  - mapping to a logical destination 307
- Ratio optional keyword
  - barcode.tab configuration file 300
- rc.iprsap utility
  - description 165
  - syntax 165
- rc.pd utility
  - description 166
  - syntax 166
- reasons attribute
  - job 552
- reassigning jobs to actual destination 79
- register-threshold attribute
  - actual destination 355
- registered-with-spooler attribute
  - actual destination 421
- related publications xxxi
- remote printing 15

- remote-queue attribute
  - actual destination 421
- removing jobs
  - pdclean command 22
  - pdrm command 88
- requeue-failed-jobs attribute
  - queue 619
- required-resources-not-ready attribute
  - job 565
- required-resources-not-supported attribute
  - job 566
- resettable attribute listing
  - actual destination 329
  - auxiliary sheet 443
  - default document 449
  - document 449
  - job 523
  - log 573
  - logical destination 578
  - medium 604
  - queue object 610
  - resource context 620
  - server 623
  - transform 645
- resexit option 254
- reslib option 255
- resolution keyword
  - pdf2afp transform 291
  - ps2afp transform 291
- resource-context attribute
  - actual destination 422
  - default document 505
  - document 505
- resource-context-font attribute
  - actual destination 423
  - default document 506
  - document 506
- resource-context-form-definition attribute
  - actual destination 424
  - default document 507
  - document 507
- resource-context-identifier attribute
  - resource context 622
- resource-context-overlay attribute
  - actual destination 425
  - default document 508
  - document 508
- resource-context-page-definition attribute
  - actual destination 426
  - default document 509
  - document 509
- resource-context-page-segment attribute
  - actual destination 427
  - default document 509
  - document 509
- resource-context-user attribute
  - default document 510
  - document 510
- resource contexts, attributes of
  - associated-server 620
  - context-address 621

- resource contexts, attributes of *(continued)*
  - descriptor 621
  - object-class 621, 646
  - resource-context-identifier 622
- resource directory, paths 255
- resource-exit attribute
  - default document 511
  - document 511
- restarting servers 166
- resubmitting jobs 81
- results-profile attribute
  - default job 566
  - job 566
- results-set-comment component
  - results-profile attribute
    - default job 567
    - job 567
- resuming paused objects 85
- retention-period attribute
  - default job 547
  - job 547
- reverse-output attribute
  - actual destination 428
- rip-ini-file attribute
  - actual destination 428
- rip-server attribute
  - actual destination 429
- room-text attribute
  - default document 512
  - document 512

**S**

- SAP Callback daemon 197, 199
- SAP Callback Daemon 197, 199
- SAP callback daemons, starting 165
- sap2afp transform
  - configuration files
    - barcode.tab 300
    - defcp.tab 302
    - fonts.tab 302
    - image.tab 305
    - pagedef.tab 306
    - printer.tab 307
    - xxxxyyyy.tab 308
  - converting ASCII to EBCDIC 302
  - description 299
  - examples 309
  - flags 299
  - mapping bar codes to BCOCA 300
  - syntax 299
- save-rip-files attribute
  - server 639
- scanner-correction attribute
  - default document 512
  - document 512
- scanner-corrections-supported attribute
  - actual destination 429
- scheduler-sort-primary-order attribute
  - actual destination 429
- scheduler-sort-secondary-order attribute
  - actual destination 430
- schedulers-supported attribute
  - actual destination 430
- scheduling of jobs, attributes used for 695
- screen-frequencies-supported attribute
  - actual destination 431
- screen-frequency attribute
  - default document 513
  - document 513
- search order for resources
  - line data 242, 244, 249, 252, 253, 255, 256
- security-level attribute
  - server 639
- segment-file-size attribute
  - default document 513
  - document 513
- selected pages keyword
  - pdf2afp transform 290
  - ps2afp transform 290
- sense utility
  - examples 168, 170
  - flags 167, 169
  - messages 167, 169
  - return codes 167, 169
  - syntax 167, 169
- sensing channel-attached printers, sensing 167
- separator-sheets-supported attribute
  - actual destination 431
- sequence-number attribute
  - document 472
- server
  - port number 290
  - time out keyword 291
- server, shutting down 180
- server, starting 176, 178
- server-hostname attribute
  - server 640
- server-ip-address attribute
  - server 640
- server name 641
- server-name attribute
  - server 641
- server name keyword
  - pdf2afp transform 291
  - ps2afp transform 291
- server state 641
- server-state attribute
  - server 641
- servers, attributes of
  - accept-unsupported-jobs 623
  - actual-destinations-ready 624
  - actual-destinations-supported 624
  - auto-create-shared-printers 625
  - cancel-individual-document-supported 625
  - descriptor 625
  - destination-states-supported 626
  - destination-support-systems-supported 626
  - document-attributes-supported 627
  - events-supported 627
  - hostname 640

- servers, attributes of *(continued)*
  - i-p-address 640
  - ip-address 640
  - job-attributes-supported 629
  - job-states-supported 630
  - job-submission-timer 630
  - list-of-managers 630
  - locale 631
  - log-accounting-data 631
  - logical-destinations-ready 632
  - logical-destinations-supported 632
  - logical-printers-ready 632
  - logical-printers-supported 632
  - managers 630
  - maximum-barco-rips 633
  - maximum-non-raster-rips 633
  - maximum-raster-rips 633
  - message 634
  - modify-individual-document-supported 634
  - multiple-documents-supported 634
  - notification-delivery-methods-supported 634
  - notification-profile 635
  - npm-server-ip-address 636
  - npm-server-port-number 637
  - nt-drivers 644
  - object-class 637
  - object-classes-supported 637
  - physical-printers-ready 624
  - physical-printers-supported 624
  - printer-states-supported 626
  - problem-child 638
  - protected-attributes 638
  - queues-supported 639
  - save-rip-files 639
  - security-level 639
  - server-hostname 640
  - server-ip-address 640
  - server-name 641
  - server-state 641
  - smtp-server-host 641
  - smtp-server-port-number 642
  - snmp-aix-printer-models 642
  - snmp-discovery-during-startup 642
  - snmp-normal-poll-interval 643
  - snmp-problem-poll-interval 643
  - transfer-methods-supported 644
  - windows-nt-driver-names 644
  - windows-nt-drivers 644
- servers, configuring 154
- servers, restarting 166
- Servers window, opening 152
- setting the attribute values of an object 91
- setting up a minimum configuration 161
- setup utility
  - description 172
  - examples 173
  - flags 172
  - syntax 172
- shared-formdef attribute
  - default document 514
  - document 514
- shared-printer-name attribute
  - actual destination 432
- shift-out-shift-in attribute
  - default document 514
  - document 514
- shutting down a server 180
- shutting down destinations 96
- shutting down servers 96
- sides attribute
  - actual destination 433
  - default document 515
  - document 515
- sides-supported attribute 433
  - actual destination 433
  - logical destination 598
- single quotation marks in commands xl
- smtp-server-host
  - server 641
- smtp-server-port-number
  - server 642
- snmp-active attribute
  - actual destination 434
- snmp-aix-printer-models attribute
  - server 642
- snmp-community-name attribute
  - actual destination 434
- SNMP-discovery-during-startup
  - server 642
- snmp-normal-poll-interval attribute
  - server 643
- snmp-problem-poll-interval attribute
  - server 643
- snmp-retry-count attribute
  - actual destination 435
- snmp-timeout attribute
  - actual destination 435
- special characters in commands xl
- start-message attribute
  - default job 551
  - job 551
- start-message-supported attribute
  - actual destination 436
  - logical destination 599
- start-on-new-sheet attribute
  - default document 516
  - document 516
- start\_server utility
  - arguments 177
  - description 176
  - examples 177
  - flags 176
  - syntax 176
- start-sheets-supported
  - actual destination 436
- startcbd utility
  - arguments 197, 199
  - syntax 197
- started-printing-time attribute
  - job 568
- starting a server 176, 178

- starting Infoprint SMIT production print operations
  - interface 175
- starting SAP callback daemons 165
- starting the Infoprint Installer 172
- starting the Infoprint Manager Administration GUI 146
- starting the Infoprint Manager Operations GUI 145
- startppo utility
  - description 175
  - examples 175
  - flags 175
  - syntax 175
- startsrv utility
  - arguments 179
  - description 178
  - examples 179
  - flags 178
  - syntax 178
- state of the server 641
- state-reasons attribute
  - job 552
- stop\_server utility
  - arguments 180
  - description 180
  - examples 180
  - flags 180
  - syntax 180
- stopcbd utility
  - description 199
  - syntax 199
- stopnotd utility
  - description 196
  - syntax 196
- subject-text attribute
  - default document 516
  - document 516
- submission-time attribute
  - job 568
- submitting jobs 63
- syntax
  - of commands
    - lprafp 15
    - mkfntmap 17
    - pdaccount 19
    - pdclean 22
    - pdcreate 25
    - pddelete 30
    - pddisable 34
    - pdenable 37
    - pdls 40
    - pdmod 51
    - pdpause 56
    - pdpr 63
    - pdpromote 72
    - pdq 74, 79
    - pdresubmit 81
    - pdresume 85
    - pdrm 88
    - pdset 91
    - pdshutdown 96
    - pdspace 100

- syntax (*continued*)
  - of transforms
    - d2afp 206
    - db2afp 202
    - gif2afp 209
    - jpeg2afp 223
    - line2afp 236
    - pcl2afp 261
    - pdf2afp 284
    - ps2afp 284
    - sap2afp 299
    - tiff2afp 310
  - of utilities
    - admingui 128
    - afpsplit 129
    - ainupod1 130
    - ainupod2 131
    - ainupod3 132
    - ainurpt1 134
    - ainurpt2 135
    - ainurpt3 136
    - ainurpt4 138
    - ainurpt5 139
    - ainurpt6 140
    - cfu 141
    - cmt 143
    - ipguiadv 145
    - ipguiadvadm 146
    - ipguibasic 145
    - ipguibasicadm 146
    - ipguidist 145
    - ipguidistadm 146
    - jsmigr 148
    - mvsprsd 186
    - opergui 151
    - pcl2afpd 188
    - pdadmin 152
    - pdcrds 153
    - pdcrflt 154
    - pdcrmed 156
    - pdinitports 157
    - pdmigpp 159
    - pdmincfg 161
    - pdmsg 163
    - ps2afpd 191
    - rc.ipsap 165
    - rc.pd 166
    - sense 167, 169
    - setup 172
    - start\_server 176
    - startcbd 197
    - startnotd 195
    - startppo 175
    - startsrv 178
    - stop\_server 180
    - stopcbd 199
    - stopnotd 196
    - t2file 184
    - tdump 181
    - tlist 183

- syntax for attribute values
  - complex 6
  - notification-profile, complex 6
  - overview 5
- system resource directories, paths 255

## T

- t2file utility
  - description 184
  - examples 184
  - flags 184
  - syntax 184
- table reference characters 256
- table-reference-characters attribute
  - default document 516
  - document 516
- table-reference-characters-supported attribute
  - actual destination 437
  - logical destination 599
- tape-exit
  - job 569
- tape-format
  - job 569
- tape-labeled
  - job 570
- tape-max-block-size
  - job 570
- tape-rewind-before
  - job 570
- tape-rewind-unload
  - job 571
- TCP/IP
  - port number 290
- tdump utility
  - description 181
  - examples 181
  - flags 181
  - syntax 181
- terminating-transform attribute 649
- ticket-content attribute
  - job 534
- tiff2afp transform
  - configuration file 315
  - description 310
  - options 316
  - syntax 310
- time outs
  - server 291
- timeout-period attribute
  - actual destination 359
- title-text attribute
  - default document 517
  - document 517
  - examples 649
- tlist utility
  - description 183
  - examples 183
  - flags 183
  - syntax 183
- total-job-octets attribute
  - job 571

- transfer-method attribute
  - document 518
- transfer-methods-supported attribute
  - server 644
- transform, attributes of
  - associated-server 645
  - descriptor 645
  - other-transform-options 647
  - output-document-format 648
  - terminating-transform 649
  - transform-identifier 649
  - transform-library 650
- transform-identifier attribute 649
- transform-message-file-name attribute
  - default document 518
  - document 518
- transform-output-file-name attribute
  - document 518
- transform-sequence attribute
  - actual destination 438
- transforms
  - d2afp 206
  - db2afp 202
  - gif2afp 209
  - jpeg2afp 223
  - line2afp 236
  - pcl2afp 261
  - pdf2afp 284
  - ps2afp 284
  - sap2afp 299
  - tiff2afp 310
- Transmission Control Protocol/Internet Protocol
  - port number 290
- tray-identification component
  - input-trays-medium attribute, actual destination 378
- tray-number component
  - psf-tray-characteristics attribute, actual destination 420
- trc option 256
- type attribute
  - default document 472
  - document 472

## U

- underlines in commands xxxix
- upper-limit component
  - job-size-range-ready attribute
    - actual destination 383
  - job-size-range-supported attribute
    - actual destination 384
    - logical destination 590
- x-image-shift-range-supported attribute
  - actual destination 441
  - logical destination 602
- y-image-shift-range-supported attribute
  - actual destination 442
  - logical destination 603
- use-snmp attribute
  - actual destination 438

- user-exit programs
  - for ACIF 259
- user exits
  - input 247
  - output 249
  - resource 254
- user-id-text attribute
  - default document 519
  - document 519
- user-locale attribute
  - job 572
- user-name attribute
  - job 572
- userlib option 256
- utilities
  - admingui 128
  - afpsplit 129
  - ainupod1 130
  - ainupod2 131
  - ainupod3 132
  - ainurpt1 134
  - ainurpt2 135
  - ainurpt3 136
  - ainurpt4 138
  - ainurpt5 139
  - ainurpt6 140
  - cfu 141
  - cmt 143
  - ipguiadv 145
  - ipguiadvadm 146
  - ipguibasic 145
  - ipguibasicadm 146
  - ipguidist 145
  - ipguidistadm 146
  - jsmigr 148
  - mkfntmap 17
  - mvsprsd 186
  - opergui 151
  - pcl2afpd 188
  - pdadmin 152
  - pdcr cds 153
  - pdcrflt 154
  - pdcrmed 156
  - pdinitports 157
  - pdmigpp 159
  - pdmincfg 161
  - pdmsg 163
  - ps2afpd 191
  - rc.iprsap 165
  - rc.pd 166
  - sense 167
  - setup 172
  - start\_server 176
  - startcbd 197
  - startnotd 195
  - startppo 175
  - startsrv 178
  - stop\_server 180
  - stopcbd 199
  - stopnotd 196
  - t2file 184

- utilities (*continued*)
  - tdump 181
  - tlist 183

## V

- validation of jobs, attributes used for 695
- vertical bars in commands xxxix

## W

- wait-for-job-completion attribute
  - actual destination 439
- warning-message attribute
  - actual destination 439
- width
  - PDF image 292
  - PostScript image 292
- width keyword
  - pdf2afp transform 292
  - ps2afp transform 292
- wildcards (global characters) 9
- windows-driver-names attribute
  - logical destination 600
- windows-drivers attribute
  - logical destination 600
- windows-nt-driver-names 644
- windows-nt-driver-names attribute
  - actual destination 440
  - logical destination 601
  - servers 644
- windows-nt-drivers attribute
  - actual destination 440
  - logical destination 601
  - server 644

## X

- x-dimension component
  - medium-dimensions attribute, medium 606
- x-image-shift attribute
  - default document 519
  - document 519
- x-image-shift-back attribute
  - default document 520
  - document 520
- x-image-shift-range-supported attribute
  - actual destination 440
  - logical destination 601
- X offset keyword on ps2afp or pdf2afp transform 292
- xxxxyyyy.tab file 308

## Y

- y-dimension component
  - medium-dimensions attribute, medium 606
- y-image-shift attribute
  - default document 521
  - document 521
- y-image-shift-back attribute
  - default document 521

y-image-shift-back attribute (*continued*)  
document 521

y-image-shift-range-supported attribute  
actual destination 441  
logical destination 602

Y offset keyword on ps2afp or pdf2afp transform 293



---

# Readers' Comments — We'd Like to Hear from You

Infoprint Manager  
Reference

Publication No. S544-5475-03

Overall, how satisfied are you with the information in this book?

	Very Satisfied	Satisfied	Neutral	Dissatisfied	Very Dissatisfied
Overall satisfaction	<input type="checkbox"/>	<input type="checkbox"/>	<input type="checkbox"/>	<input type="checkbox"/>	<input type="checkbox"/>

How satisfied are you that the information in this book is:

	Very Satisfied	Satisfied	Neutral	Dissatisfied	Very Dissatisfied
Accurate	<input type="checkbox"/>	<input type="checkbox"/>	<input type="checkbox"/>	<input type="checkbox"/>	<input type="checkbox"/>
Complete	<input type="checkbox"/>	<input type="checkbox"/>	<input type="checkbox"/>	<input type="checkbox"/>	<input type="checkbox"/>
Easy to find	<input type="checkbox"/>	<input type="checkbox"/>	<input type="checkbox"/>	<input type="checkbox"/>	<input type="checkbox"/>
Easy to understand	<input type="checkbox"/>	<input type="checkbox"/>	<input type="checkbox"/>	<input type="checkbox"/>	<input type="checkbox"/>
Well organized	<input type="checkbox"/>	<input type="checkbox"/>	<input type="checkbox"/>	<input type="checkbox"/>	<input type="checkbox"/>
Applicable to your tasks	<input type="checkbox"/>	<input type="checkbox"/>	<input type="checkbox"/>	<input type="checkbox"/>	<input type="checkbox"/>

Please tell us how we can improve this book:

Thank you for your responses. May we contact you?  Yes  No

When you send comments to IBM, you grant IBM a nonexclusive right to use or distribute your comments in any way it believes appropriate without incurring any obligation to you.

---

Name

---

Address

---

Company or Organization

---

Phone No.



Fold and Tape

Please do not staple

Fold and Tape



NO POSTAGE  
NECESSARY  
IF MAILED IN THE  
UNITED STATES

# BUSINESS REPLY MAIL

FIRST-CLASS MAIL PERMIT NO. 40 ARMONK, NEW YORK

POSTAGE WILL BE PAID BY ADDRESSEE

IBM Corporation  
Information Development  
IBM Printing Systems  
Department H7FE Building 003G  
PO Box 1900  
Boulder, CO 80301-9817



Fold and Tape

Please do not staple

Fold and Tape





Program Number: 5765-E42  
5639-I27



Printed in the United States of America  
on recycled paper containing 10%  
recovered post-consumer fiber.

S544-5475-03

