


This is the tutorial for the DB2<sup>®</sup> feature of IBM's File Manager for z/OS<sup>®</sup>, one of the IBM zSeries<sup>®</sup> problem determination tools.



File Manager DB2 has a set of options that can be customized with personal preferences. They affect things like the types of information displayed in the browser and editor, and where output is written when a report is generated.

This section will describe many of the options, how to modify them, and some recommendations. As you watch this section, you can update your settings in File Manager DB2. Pause the tutorial as needed to check and customize the options on your system.

	Use the Options pull down –or-
Process	Options Enter ties Help
FM/DB2 ( Command 0 Setti 1 View 2 Edit 3 Utili 4 SQL 5 DB2I 6 Comma X Exit	1.Print settings2.FM/DB2 system options3.Job card specifications4.Compiler language selection5.COBOL compiler specifications6.HLASM compiler specifications7.PL/I compiler specifications8.Temporary Data Set Allocations9.Output Data Set Allocations10.Trace options11.ISPF settings22.2010/03/24
F1=Help	<ul> <li>12. Editor options</li> <li>13. Copy utility options</li> <li>14. Object list utility</li> <li>15. Export utility opti</li> <li>16. DB2 LOAD utility op</li> <li>17. DB2 Utility LISTDEF</li> <li>18. DB2 Utility OPTIONS</li> <li>19. DB2 Utility TEMPLAT</li> <li>20. DB2 Unload utility</li> </ul> Bring down the options menu (put cursor on the word "Options" and press Enter.)
F9=Swap	F10=Left F11=Right
3	IBM File Manager DB2 for z/OS V10 Mentor Workshop W00 © 2010 IBM Corporation

There are two ways to navigate to the options panels. The first way is to use the pull down of the options menu that is available on most panels. Place the cursor on the word "Options" at the top of the screen and press Enter. Then select one of the options categories. This method is useful when changing a single option setting. When the option has been modified, the F3 key will exit the option menu.

Enter 0 (settings) on the command line					
		lities <u>H</u> elp	<u> </u>	on 0 from the	main menu
FM/DB2 (D91F) Command ===>		Primary	Option Menu		
0 Settings 1 View 2 Edit 3 Utilities 4 SQL 5 DB2I 6 Command X Exit	View DB Edit DB Perform Prototy Start D Enter a	cessing optio 2 object 2 object utility func pe, execute a B2 Interactiv nd execute a te FM/DB2	tions nd analyze SQL e	User ID . : System ID : Appl ID . : Version . : Terminal : Screen . : Date : Time : DB2 SSID . SQL ID	STLABF6 FMN2 10.1.0 3278A 1 2010/03/24 02:48 D91F
F1=Help F9=Swap	F2=Split F10=Left	F3=Exit F11=Right	F4=Expand F12=Cancel	F7=Backward	F8=Fo
F9=Swap 4			F12=Cancel or z/OS V10 Mentor Works	hop W00	© 2010 IBM Corporati

The other way is to select option 0 from the File Manager DB2 main menu. In this example, 0 is entered on the command line. Press Enter.

		Select Sys	stem option	6	IBM
<u>P</u> rocess	<u>O</u> ptions	<u>U</u> tilities <u>H</u> elp			
FM/DB2 ( Command		Set Proce	ssing Options		
0 Syste	m	System options			
1 View		View options			
2 Edit		Edit options			
3 Utili 3.1	Print				
	Copy	Print utility o Copy utility op			
	Object List				
	Export	Export utility			
3.L	Load	DB2 LOAD utilit	the second se		
3.UL	LISTDEF	DB2 Utility LIS			
3.UO	OPTIONS	DB2 Utility OPT	IONS options		
3.UT	TEMPLATE	DB2 Utility TEM	PLATE options		
3.UU	Unload	DB2 Unload util	ity options		
F1=Help F12=Canc		t F3=Exit	F7=Backward	F8=Forward	F9=Sw Enter
5		IBM File Manager DB2 fo	or z/OS V10 Mentor Works	NOP W0	0 © 2010 IBM Corporatio

The Set Processing Options panel is displayed. From here select any of the categories shown. Access to any of the options panels is available from this menu. This method is useful if numerous settings are being modified or reviewed First, the print options will be described. Select option 0 System options, on the command line. Press Enter.

	Select Print settings	IBM
Process Opt FM/DB2 (D91F) Command ===> 1	ions <u>U</u> tilities <u>H</u> elp Set System Processing Options	
1 Print 2 System 3 Batch 4 LANG 5 COBOL 6 HLASM 7 PL/I 8 Temporary 9 Output 10 Trace 11 ISPF	Print settings FM/DB2 system options Job card specifications Compiler language selection COBOL compiler specifications HLASM compiler specifications PL/I compiler specifications Temporary Data Set Allocations Output Data Set Allocations Trace options ISPF settings	Enter
6	IBM File Manager DB2 for z/OS V10 Mentor Workshop	W00 © 2010 IBM Corporation

The Set System Processing Options panel is displayed. Select option 1 Print. Press Enter.

		Print op	tions
<u>P</u> rocess <u>O</u> p	tions <u>U</u> ti	lities <u>H</u> elp	Recommended:  Be aware
FM/DB2 (D91F) Command ===>	_	Set Print Proces	sing Options
Print Options Output des 31. SYSP 2. Term 3. Data 4. REXX	tination RINT inal set	Record length <u>2</u> 1.80 2.132	Enter "/" to select option _ Page skip <u>/</u> Wide print <u>/</u> Translate non-printable chars _ Uppercase message text
1. OLD 2. MOD	ISP		This is the print data set
Output cla Lines per	ame TS ss <u>A</u> page <u>bu</u> its <u>(1</u>	_	(n,m) n=begin column, m=end column
F1=Help F8=Forward	F2=Split F9=Swap		4=CRetriev F6=Reset F7=Ba F3 2=Cancel
7	IE	BM File Manager DB2 for z/OS	V10 Mentor Workshop W00 © 2010 IBM Corporation

The "Set Print Processing Options" panel is displayed. Options with a red arrow have suggested values in red circles. Options shown with blue arrows are settings that you should consider, or at least be aware of.

It is strongly suggested that you change the "Print Options, Output destination". The default setting may send the output of reports directly to your terminal. Select option 3, data set. This directs output to the file manager print data set. Anything done online that produces a report will write to the print data set. The name of the print data set is entered in the 'Data set name' field below. When a report is in the print data set, it can easily be viewed and then copied to sysout.

Consider changing the Data set DISP to OLD. The MOD setting will add new reports to the end of the print data set. Print disposition of "old" will clear the contents of the print data set every time a report is generated. The data set will only contain the last generated report.


The File Manager print data set is shown in the "Data set name" field. The value of the default data set will be filled in. Verify the naming pattern will follow your data set naming conventions. Modify the name if necessary.

Change the "Output class" setting to a valid, held sysout class on your system. If you are not sure what output classes are defined on your system, take a look at one of your job cards, and use the same SYSOUT class that is coded on your job card. If you do not have any JCL that you can refer to, ask a colleague. If you are still unsure, take a guess. It is better to guess than to leave it unchanged.

	System Option 1 of 4		TEM
Process Options Ut	tilities Help	Recommend Be awa	
FM/DB2 (D91F) Command ===>	<b>_</b> ·		
Uppercase Translation: Enter "/" to select / Translate DB2 obj / Translate input S Encapsulation of SQL Ic Use double quotes 3 1. For DB2 SQL re	ject names SQL statements dentifiers in Double Qu	uotes:	
<pre>3. Always More Options:    Enter "/" to select</pre>	option statements, time displ	panel	down to the next
F1=Help F11=NxtPage F12=Cancel		ackward F8=Forwa	ard F9=Sw F11
8	IBM File Manager DB2 for z/OS V10 M	entor Workshop	W00 © 2010 IBM Corporation

This is the File Manager DB2 System Options panel. There are enough system options that four panels are needed to show them all. The "Translate DB2 object names" option, if selected, object names entered on panels are converted to upper case. Select this if tables and other objects have all upper case names.

The "Translate input SQL statement" option, if on, will translate input SQL statements to upper case before they run. Press F11 to move to the next page of system options.




Option "Arbitrary SQL select statements" controls how results of running SQL statements are displayed. Select 1 for browse, 2 for view, or 3 for edit.


Also be aware of "External format for time data type columns". Set it to preferred time display. F3 to exit system options.

	Enter a v	alid job card
<u>P</u> rocess <u>O</u> ptic	ons <u>U</u> tilities <u>H</u> elp	Recommended:  Be aware
FM/DB2 (D91F) Command ===>	Set Batch Job	Card Information
→ <u>//TSS13X JOB</u>	n Job Statement Inform (ACCTG),'IBM TOOLS WO MSGCLASS=H,NOTIFY=&SYS	RKSHOP', REGION=4M, CLASS=A,
		This job card is used by all File Manager DB2 utilities that generate JCL Provide a job card that is valid for your system (Do not just copy this example)
	2=Split F3=Exit 9=Swap F10=Actions	F4=CRetriev F6=Reset F7=Ba F3
10	IBM File Manager DB2 f	or z/OS V10 Mentor Workshop W00 © 2010 IBM Corporation

This is the "Batch Job Card Information" panel. This option is used by File Manager to generate JCL. Many utilities, like print and copy, can be run as batch jobs. File Manager will pull the job card information from this panel and insert it into the generated JCL. An easy way to do it is to cut and paste a job card from existing JCL. Provide a valid system job card, do not just copy this example. F3 to exit.



The 'Compiler Language Selection" panel is displayed. These options are only used by the Import and Export utilities. It is possible, although not necessary, to use COBOL or PL/1 copybooks as record layouts for input or output files. For COBOL only, specify 1. For PL/1, specify 2. If both are being used, specify 3, and File Manager will automatically determine the compiler to use when the copybook is specified for the import or export utilities. F3 to exit.



The 'Set COBOL Processing options" panel is now displayed. These options are only used by the import and export utilities, when the layout of input or output files are done using COBOL copybooks. For copybooks that copy other copybooks, provide a list of one or more syslib data sets. Syslib data sets are the libraries where the COBOL compiler looks for copybooks. This is only needed for nested copybooks, which are copybooks that copy other copybooks.

This panel also allows for entry of copybook replacement values. Some copybooks are coded with special characters or tag strings that are intended to be replaced with some other string by the compiler. That happens in a COBOL program when a COPY REPLACING statement is used. In COBOL the syntax is coded so that both the from and to strings have two equal signs on each side. The values would be entered in the COBOL Replacing Options entry fields.

It is a common practice to have the special character "colon" as part of the tags that are intended to be replaced. This is sometimes done purposely by programmers to force compiler errors if the programmer forgets to code a COPY REPLACING. This example removes all colon characters from copybooks, to avoid compiler errors in those cases.

F3 to exit this panel.

HLASM Processing Options	IBM
Process Options Utilities Help	
FM/DB2 (D91F) Set HLASM Processing Options Command ===> This is only used for Export /Impor	rt
Additional SYSLIB data sets  1.  2.  3.  4.  Specify additional SYSLIB c	lata
5 Specify additional 51 SLID c 6 7	
8. 9. 10	
Enter "/" to select option DBCS NOALIGN	
F1=Help F2=Split F3=Exit F7=Backward F8=Forward F9=Sw F12=Cancel	F3
13 IBM File Manager DB2 for z/OS V10 Mentor Workshop W00 © 2010 IBM	Corporation

This is the "HLASM processing options" panel. It is similar to the COBOL options panel. These options are only used by the import or export utilities. Specify additional SYSLIB data sets on this panel. Press F3 to exit this panel.

PL/I Processing Options
Process Options Utilities Help
FM/DB2 (D91F) Set PL/I Processing Options
This is only used for Export /Import
Additional SYSLIB data sets: 1
2
4 Specify additional SYSLIB data
6. 7
8
10.
PL/I Compiler Options for Copybooks:
Enter "/" to select option GRAPHICUNALIGNED
_ 63 bit binary _ 31 digit decimal
F1=Help F2=Split F3=Exit F7=Backward F8=Forward F9=Sw F3 F12=Cancel
14 IBM File Manager DB2 for z/OS V10 Mentor Workshop W00 © 2010 IBM Corporation

This is the "PL/I processing options" panel. It is similar to the COBOL options panel. These options are only used by the import or export utilities, and only if using PL/I copybooks to lay out input or output files. For nested PL/I include members, or include members that %INCLUDE other include members, provide one or more syslib data sets. The PL/I compiler will search these data sets for included copybooks. F3 to exit this panel.

ISP	F Settings
Log/List Function keys Colors	Environ We Be aware
ISP	F Settings
Command ===>	<u> </u>
Options Enter "/" to select option Command line at bottom Panel display CUA mode Long message in pop-up Tab to action bar choices Tab to point-and-shoot fields Restore TEST/TRACE options Session Manager mode Jump from leader dots Edit PRINTDS Command Always show split line Enable EURO sign	More: + Print Graphics Family printer type 2 Device name Aspect ratio 0 General Input field pad <u>B</u> Command delimiter
Member list options Enter "/" to select option <u>/</u> Scroll member list F1=Help F2=Split F3=Exit F10=Actions F12=Cancel	F7=Backward F8=Forward F9=Sw F8
15 IBM File Manager DE	32 for z/OS V10 Mentor Workshop W00 © 2010 IBM Corporation

This is the ISPF settings panel. IBM recommends leaving the command line at the top of panels instead of the bottom. To set that option, leave the "Command line at bottom" option blank. It is also recommended that you turn off "Tab to action bar choices", and "Tab to point-and-shoot fields'. If these are turned on, the tab key will move the cursor to menu selections at the very top of panels, which can be a hindrance. Scroll forward with F8.

ISPF Settings	BM
Log/List <u>Function keys</u> <u>Colors Environ</u> <u>W</u> Be aware	
ISPF Settings         Command ===>	32
There is optimised and the second of the sec	-3
F10=Actions     F12=Cancel       16     IBM File Manager DB2 for z/OS V10 Mentor Workshop     W00     © 2010 IBM Co	orporation

For 3270 terminal emulators that have been configured to display extra lines and columns, use the "screen format" setting to allow expanded panel displays. The emulator settings must be configured to match before the expanded display is activated. F3 to exit.

			Select Edit options	B
<u>P</u>	rocess	<u>O</u> ptions	<u>U</u> tilities <u>H</u> elp	
	/DB2 ( mmand		Set Processing Options	
0	Syste	m	System options	
_	View		View options	
_	Edit Utili		Edit options	
3	3.1	Print	Drint utilitu ontione	
	3.1	Copy	Print utility options Copy utility options	
	3.4	Object List		
	3.7		Export utility options	
	3.L		DB2 LOAD utility options	
	3.UL	LISTDEF	DB2 Utility LISTDEF options	
	3.UO	OPTIONS	DB2 Utility OPTIONS options	
	3.UT	TEMPLATE	DB2 Utility TEMPLATE options	
	3.UU	Unload	DB2 Unload utility options	
	1=Help 2=Canc		t F3=Exit F7=Backward F8=Forward	F9=Sw Enter
-	17		IBM File Manager DB2 for z/OS V10 Mentor Workshop W0	00 © 2010 IBM Corporati

There are many editor options. Select option 2 from the Set Processing Options panel to access these. Press Enter.

<u>Process Options U</u> tilities		aware
FM/DB2 (D91F) Edi Command ===>	tor Options (1 of 7)	Global Settings
Display Format: Initial display format <u>1</u> 1. Previous	Editor CAPS Settin Enter "/" to se _ Initially ON	lect option
2. Table 3. Single	Audit Option: Option fixed at Create audit	
	ble column options cessing options	
F1=Help F2=Split F3= F11=NxtPage F12=Cancel	Exit F7=Backward F8=	Forward F9=Sw <b>F11</b>

This is panel one of the "Editor Options". There are many options. The "initial display" option controls how data is displayed when an edit or view session is started. This is a personal preference. It can be set to either 2 table or 3 single format, or a setting of 1, which means display the same format that was active the last time edit or view was active.

Use F11 to scroll to the next page of editor options.

Editor Options	page 2 – take defaults
<u>Process Options Utilities He</u> r	Recommended: Be aware
FM/DB2 (D91F) Editor Op Command ===>	otions (2 of 7) Global Settings
Optimization Options:	Large Table Options:
Enter "/" to select option	
_ Use row count value	<u>1</u> 1. Insensitive
	2. Sensitive static
Optimize for <u>O</u> Rows	
Data Sampling:	Clustered Sampling:
Sampling type	Initial skip count <u>O</u>
<u>1</u> 1. None	Include count <u>1</u>
<ol><li>Clustered sampling</li></ol>	Skip count <u>0</u>
3. Random sampling	
	Random Sampling:
Sampling limit <u>O</u>	Sampling frequency <u>0.01</u>
	Sampling seed <u>0</u>
F1=Help F2=Split F3=Exit F10=PrvPage F11=NxtPage F12=Cance	
19 IBM File Manager DB	2 for z/OS V10 Mentor Workshop W00 © 2010 IBM Corporat

Editor options page 2, take the defaults on this page. Press F11.


Set prefix are	ea selections
<u>P</u> rocess <u>O</u> ptions <u>U</u> tilities <u>H</u> elp	Recommended:
FM/DB2 (D91F) Editor Option	ns (3 of 7) Global Settings
Enter "/" to select option <u>/</u> Show data type <u>/</u> Show scale line <u>/</u> Show column number Single Display Format: Enter "/" to select option	refix Area: Prefix length <u>A</u> (A,6,7,8,9)
F1=Help F2=Split F3=Exit F10=PrvPage F11=NxtPage F12=Cancel	F7=Backward F8=Forward F9=Sw
20 IBM File Manager DB2 for z/	OS V10 Mentor Workshop W00 © 2010 IBM Corporation

IBM recommends displaying the prefix area, and NOT showing the prefix area on the right. Selecting "Show SQLCODE" is suggested. With this on, if there is a save error when you try to save your changes, the non-zero SQL code is displayed in the prefix area.

In this example, the "Display prefix area" and "Show SQLCODE" options were selected by entering a slash in the input area. The "Show prefix area on the right" field was blanked out, to not select this option. Press F11 to scroll to the next page.

	Key and	Index valu	ues, take the	e defaults	IBM
<u>P</u> rocess <u>O</u>	ptions <u>U</u> til	ities <u>H</u> elp	Reco	ommended: Be aware	<b>+</b> ○
FM/DB2 (D91F Command ===>		Editor Opt	ions (4 of 7)	GI	obal Settings
Enter "/" <u>/</u> Allow <u>/</u> Show p <u>/</u> Show f <u>/</u> Show i Export Comma Enter "/"	Foreign Keys, to select op updates to pr rimary key oreign key ndex indicato nd: to select op xport options	otion Simary Key Ors Otion			
	F2=Split F11=NxtPage		F7=Backward	F8=Forward	F9=Sw <b>F11</b>
21	IB	M File Manager DB2 fo	r z/OS V10 Mentor Works	nop W00	© 2010 IBM Corporation

Editor options page 4, key and index values, take the system defaults. Press F11 to scroll to the next page.



Editor options page 5, string delimiters and null column indicators. String delimiters for input and display are set on this panel. They can be modified. The "End of string delimiter" settings let you select the character that marks the end of varying length strings. Most people use the defaults. The "Null column indicator" settings are similar. They show the character that marks a null column. Press F11 to scroll to the next page.

Se	t key processing an	d commit op	tions IBM
<u>Process Option</u>	s <u>U</u> tilities <u>H</u> elp		ended:
FM/DB2 (D91F) Command ===>	Editor Options	(6 of 7)	Global Settings
Commit Options: Enter "/" to s _ Commit when	e n a a and commit changes		F11
23	IBM File Manager DB2 for z/OS V	/10 Mentor Workshop	W00 © 2010 IBM Corporatio

The "Commit changes when no save errors" option affects what happens when you exit from the editor or use a save command. With this option on, File Manager issues a commit only if there were no errors saving data. Save errors can be caused by things like duplicate keys in your data.


When the option is off, File Manager issues a commit even if there were some save errors, meaning that it will commit the changes that it can. Either way, if you have save errors, you will remain in the editor and you will have a chance to fix the problems. In this example, the "Enter key usage" default value of 1 is entered, and "Commit Options, Commit when no save errors" has been selected with a slash. Press F11 to scroll to the next panel.

		Recomm	ended: 🔸 🔵
<u>P</u> rocess <u>O</u> ptions <u>U</u> til	ities <u>H</u> el	P Be	aware 🔶
FM/DB2 (D91F) Command ===>	Editor Op	tions (7 of 7)	Global Settings
Concurrency Options:		SQL Cursor Concurr	ency Options:
Enter "/" to select op	tion	Concurrency	
_ Read-only access		<u>1</u> 0. Uncommitte	ed read
🖊 Commit after data f	etch	1. No with c	lause
_ Skip locked rows		2. Cursor st	ability
		3. Read stab	ility
Edit Locking Option:			ility keep locks
Locking		5. Repeatabl	
<u>1</u> 1. None		6. Repeatabl	e read keep locks
2. Share mode			
3. Exclusive mode		Keep locks opti	
		<u>1</u> 1. Use/Keep	
		2. Use/Keep	•
		3. Use/Keep	exclusive locks
F1=Help F2=Split F10=PrvPage F12=Cancel	F3=Exit	F7=Backward F8=	Forward F9=Sw

There are options here to control how File Manager performs locking when you use edit or browse. It is typical to take the default values, and it is a good idea to consult with your DBA before you change these, especially if you are not familiar with how DB2 performs locking. Press F3 to exit the editor options.


_	s <u>O</u> ptions	<u>U</u> tilities <u>H</u> elp
FM/DB2 Command	(D91F) ===>( <u>3.3</u>	Set Processing Options
0 Syste	em	System options
1 View		View options
2 Edit		Edit options
3 Utili	ities	
3.1	Print	Print utility options
3.3	Сору	Copy utility options
3.4		Object list utility options
3.7	Export	Export utility options
3.L	Load	DB2 LOAD utility options
3.UL		DB2 Utility LISTDEF options
	OPTIONS	DB2 Utility OPTIONS options
3.UT		DB2 Utility TEMPLATE options
3.UU	Unload	DB2 Unload utility options

From the Set Processing Options panel, specify 3.3 copy utility options. Press Enter.



This is the Copy Options panel. It affects what happens when the Copy utility is used to copy data from one table to another. Notice the "Duplicate key processing" option. If the output table already contains rows, it controls what happens when there are duplicate key values in input rows. "Ignore" means that rows with duplicate keys are ignored and not copied. Update is the opposite, and File Manager will attempt to update the output table with the information from the input row.

Be careful with the "Delete existing rows" option. When this is on, all of the rows in the output table are deleted before the input rows are copied. This can be useful, but make sure this is the desired action before turning it on. "Ignore referential integrity errors" allows copying the rows that do not have RI errors, but the rows that do have RI errors are not copied. If this option is set to off, then the Copy utility fails if it encounters an RI error. If the "Create audit trail" setting is turned on, File Manager automatically creates a new audit log file every time a copy is performed. If there are no plans to print reports from audit logs, then turn this option off. F3 to exit.



There are many File Manager options, but the ones that have been reviewed so far are the most used.

File Manager panels are designed so that underscores should be displayed in the data entry fields. This makes the entry areas much easier to identify. The display at the top shows the display with the underscores turned on. If underscores are not being displayed, an ISPF setting can be used to turn them on.

Issue ISPF command CUAATTR						
	tions <u>U</u> ti	lities <u>H</u> elp				
FM/DB2 (D91F) Command ===>	cuaattr	Primary	Option Menu			
0 Settings 1 View 2 Edit 3 Utilities 4 SQL 5 DB2I 6 Command X Exit	View DB Edit DB Perform Prototy Start D Enter a	cessing optic 2 object 2 object utility func pe, execute a B2 Interactiv nd execute a te FM/DB2	tions Ind analyze SQL Ve	User ID . : System ID : Appl ID . : Version . : Terminal : Screen . : Date : Time : DB2 SSID . SQL ID	STLABF6 FMN2 10.1.0 3278A 1 2010/03/24 03:09 D91F	
F1=Help F9=Swap	F2=Split F10=Left	F3=Exit F11=Right	F4=Expand F12=Cancel	F7=Backward	F8=F0 Enter	
28		BM File Manager DB2 f	or z/OS V10 Mentor Works	hop W00	© 2010 IBM Corporati	

To turn on the underscores, use the ISPF command: CUAATTR. Enter CUAATTR on the command line and press Enter.

			ended: 🔶 🧲
	ISPF Setti		ware 🔶
Command ===>	JA Attribute Chan	ge otririg	Default
Change colors, intensitie	es. or highlights	for panel att	ribute elements.
Enter the EXIT command to		•	
without saving. To restor			
press Enter or select the		and the second	
default settings for all	types.		
Panel Element	Color	Intensity	Highlight
			More:
AB Selected Choice		LOW	NONE
AB Separator Line		<u>LOW</u>	NONE
AB Unselected Choice		<u>HIGH</u>	NONE
Action Message Text		HIGH	NONE
Active Window Frame		HIGH	
		<u>HIGH</u>	NONE
	TUDO	LOW	USCORE
Caution Text			
Choice Entry Field Column Heading	<u>BLUE</u>	HIGH	NONE
Choice Entry Field Column Heading Descriptive Text	<u>BLUE</u> <u>GREEN</u>	LOW	NONE
	<u>BLUE</u> <u>GREEN</u> F3=Exit		NONE

The "CUA attributes change utility" panel has settings that control how ISPF panels are displayed. There are three settings that are important for File Manager. First, on the "Choice Entry Field" line, type USCORE in the highlight field. Then scroll down with the F8 key.


			Recommended:
		— ISPF Settir	Be aware
	CUA A	ttribute Chang	
Command ===>			Defaul
without savi press <mark>Enter</mark>	.ng. To restore tl	he defaults fo faults point-a	enter the CANCEL command to ex or a type, clear the field and and-shoot field to restore all
Panel Elemer	nt	Color	Intensity Highlight More:
List Entru P	ield	. TURO	LOW USCORE
	escription		LOW NONE
List Items .		. WHITE	LOW HONE
Normal Entry	, Field	. TURQ	LOW USCORE
			LOW NONE
	(1,1,1,1,1,1,1,1,1,1,1,1,1,1,1,1,1,1,1,		<u>LOWNONE</u>
	uction		<u>LOWNONE</u>
	· · · · · · · · · ·		<u>LOW</u> NONE
	noot		HIGH NONE
	F2=Split	F3=Exit	F7=Backward F8=Forwa

Make the same changes to the "List Entry Field" and "Normal Entry Field" lines. Type "USCORE" into the Highlight field. Press F3 to save the changes. If this setting is changed while on a panel with underscores, the panel will have to be exited to get the updated settings. F3 to exit the CUAATTR panel.

	-	r stores your option settings in your you exit File Manager	permanent ISPF profile
		e made changes that you want to save	, exit File Manager DB2
		nes out before you exit, your settings wi	
	/DB2 (D91F) mmand ===>	Primary Option Menu	
0	Settings	Set processing options	User ID . : TSS13
1	View	View DB2 object	System ID : STLABF6
2	Edit	Edit DB2 object	Appl ID . : FMN2
3	Utilities	Perform utility functions	Version . : 10.1.0
4	SQL	Prototype, execute and analyze SQL	Terminal : 3278A
5	DB2I	Start DB2 Interactive	Screen . : 1
6	Command	Enter and execute a DB2 Command	Date : 2010/03/26
Х	Exit	Terminate FM/DB2	Time : 22:39
			DB2 SSID . D91F
			SQL ID TSS13

File Manager stores the options settings in the TSO profile data set when File Manager is exited. If changes have been made to any settings, save them by going back to the File Manager main menu, then press F3 to exit. When File Manager is exited, the changes will be written to the ISPF profile data set. If the TSO session times out, the changes to the File Manager settings will not be lost. F3 to exit.

This ends the section on understanding your File Manager DB2 options settings.



You can help improve the quality of IBM Education Assistant content by providing feedback.

					LEM
Trademarks, o	opyrights,	and	disclair	ners	
IBM, the IBM logo, ibm.com, DB2, z/OS, and many jurisdictions worldwide. Other product is available on the web at " <u>Copyright and trac</u>	t and service names might be trade	marks of IBM or	other companies. A cu		
THE INFORMATION CONTAINED IN THIS MADE TO VERIFY THE COMPLETENESS "AS IS" WITHOUT WARRANTY OF ANY KII PRODUCT PLANS AND STRATEGY, WHIC ANY DAMAGES ARISING OUT OF THE US NOTHING CONTAINED IN THIS PRESENT REPRESENTATIONS FROM IBM (OR ITS OR LICENSE GOVERNING THE USE OF IE	AND ACCURACY OF THE INFOR ND, EXPRESS OR IMPLIED. IN AI CH ARE SUBJECT TO CHANGE B SE OF, OR OTHERWISE RELATE! ATION IS INTENDED TO, NOR SI SUPPLIERS OR LICENSORS), OF	MATION CONT DDITION, THIS I Y IBM WITHOU D TO, THIS PRE HALL HAVE THE	AINED IN THIS PRESS INFORMATION IS BAS T NOTICE. IBM SHALL SENTATION OR ANY E EFFECT OF, CREAT	ENTATION, IT SED ON IBM'S NOT BE RE OTHER DOC 'ING ANY WA	IS PROVIDED S CURRENT SPONSIBLE FOR CUMENTATION. RRANTIES OR
© Copyright International Business Machines	s Corporation 2010. All rights reser	ved.			
33	IBM File Manager DB2 for z/O	S V10 Mentor W	/orkshop	W00 (	© 2010 IBM Corporation