

MQSeries®



# Application Programming Guide



MQSeries®



# Application Programming Guide

**Note!**

Before using this information and the product it supports, be sure to read the general information under Appendix J, "Notices" on page 567.

**Tenth edition (January 1999)**

This edition applies to the following products:

- MQSeries for AIX® V5.1
- MQSeries for AS/400® V4R2M1
- MQSeries for AT&T GIS UNIX® V2.2
- MQSeries for Digital OpenVMS V2.2
- MQSeries for HP-UX V5.1
- MQSeries for OS/390® V2.1
- MQSeries for OS/2® Warp V5.1
- MQSeries for SINIX and DC/OSx V2.2
- MQSeries for Sun Solaris V5.1
- MQSeries for Tandem NonStop Kernel V2.2
- MQSeries for VSE/ESA™ V2.1
- MQSeries for Windows® V2.0
- MQSeries for Windows V2.1
- MQSeries for Windows NT® V5.1

and to any subsequent releases and modifications until otherwise indicated in new editions.

Order publications through your IBM® representative or the IBM branch office serving your locality. Publications are not stocked at the address given below.

At the back of this publication is a page titled "Sending your comments to IBM". If you want to make comments, but the methods described are not available to you, please address them to:

IBM United Kingdom Laboratories,  
Information Development,  
Mail Point 095,  
Hursley Park,  
Winchester,  
Hampshire,  
England,  
SO21 2JN

When you send information to IBM, you grant IBM a nonexclusive right to use or distribute the information in any way it believes appropriate without incurring any obligation to you.

© **Copyright International Business Machines Corporation 1993,1999. All rights reserved.**

US Government Users Restricted Rights – Use, duplication or disclosure restricted by GSA ADP Schedule Contract with IBM Corp.

---

# Contents

<b>About this book</b> . . . . .	xv
Who this book is for . . . . .	xvi
What you need to know to understand this book . . . . .	xvi
How to use this book . . . . .	xvi
Appearance of text in this book . . . . .	xvii
Terms used in this book . . . . .	xvii
MQSeries publications . . . . .	xviii
MQSeries cross-platform publications . . . . .	xviii
MQSeries platform-specific publications . . . . .	xxi
MQSeries Level 1 product publications . . . . .	xxii
Softcopy books . . . . .	xxii
MQSeries information available on the Internet . . . . .	xxiv
Related publications . . . . .	xxiv
CICS . . . . .	xxiv
IMS . . . . .	xxv
MVS/ESA . . . . .	xxv
Design . . . . .	xxv
C . . . . .	xxv
C++ . . . . .	xxv
COBOL . . . . .	xxv
LDAP . . . . .	xxvi
<b>Summary of Changes</b> . . . . .	xxvii
Changes for this edition (SC33-0807-09) . . . . .	xxvii
MQSeries for OS/390 V2.1 . . . . .	xxvii
MQSeries V5.1 . . . . .	xxviii
MQSeries for VSE/ESA V2.1 . . . . .	xxxi
MQSeries for AS/400 V4R2M1 . . . . .	xxxii
Changes for the ninth edition (SC33-0807-08) . . . . .	xxxii
Changes for the eighth edition (SC33-0807-07) . . . . .	xxxii

---

## Part 1. Designing applications that use MQSeries . . . . . 1

<b>Chapter 1. Introduction to message queuing</b> . . . . .	3
What is message queuing? . . . . .	3
What is a message? . . . . .	4
What is a message queue? . . . . .	4
What is a queue manager? . . . . .	5
What is a cluster? . . . . .	6
What is an MQSeries client? . . . . .	6
Main features of message queuing . . . . .	7
Benefits of message queuing to the application designer and developer . . . . .	10
What can you do with MQSeries products? . . . . .	10
<b>Chapter 2. Overview of application design</b> . . . . .	13
Planning . . . . .	13
Using MQSeries objects . . . . .	14
Designing your messages . . . . .	15
MQSeries techniques . . . . .	16

Application programming	18
Testing MQSeries applications	21
<b>Chapter 3. MQSeries messages</b>	<b>23</b>
Message descriptor	23
Types of message	24
Format of message control information and message data	29
Message priorities	32
Message groups	33
Message persistence	34
Selecting messages from queues	35
Messages that fail to be delivered	35
Messages that are backed out	35
Reply-to queue and queue manager	36
Message context	37
<b>Chapter 4. MQSeries objects</b>	<b>39</b>
Queue managers	39
Queues	40
Namelists	48
Process definitions	49
Channels	49
Storage classes	49
Rules for naming MQSeries objects	49
<b>Chapter 5. Handling program errors</b>	<b>53</b>
Locally determined errors	53
Using report messages for problem determination	55
Remotely determined errors	56

---

**Part 2. Writing an MQSeries application** . . . . . 61

<b>Chapter 6. Introducing the Message Queue Interface</b>	<b>65</b>
What is in the MQI?	65
Parameters common to all the calls	73
Specifying buffers	74
Programming language considerations	75
OS/390 batch considerations	84
UNIX signal handling on MQSeries Version 5 products	85
<b>Chapter 7. Connecting and disconnecting a queue manager</b>	<b>89</b>
Connecting to a queue manager using the MQCONN call	90
Connecting to a queue manager using the MQCONNX call	92
Disconnecting programs from a queue manager using MQDISC	94
<b>Chapter 8. Opening and closing objects</b>	<b>97</b>
Opening objects using the MQOPEN call	98
Creating dynamic queues	104
Opening remote queues	105
Closing objects using the MQCLOSE call	105
<b>Chapter 9. Putting messages on a queue</b>	<b>107</b>
Putting messages on a local queue using the MQPUT call	107

Putting messages on a remote queue	112
Controlling context information	113
Putting one message on a queue using the MQPUT1 call	114
Distribution lists	116
Some cases where the put calls fail	121
<b>Chapter 10. Getting messages from a queue</b>	123
Getting messages from a queue using the MQGET call	123
The order in which messages are retrieved from a queue	128
Getting a particular message	137
Type of index	139
Handling large messages	140
Waiting for messages	146
Signaling	147
Skipping backout	150
Application data conversion	152
Browsing messages on a queue	154
Browsing messages in logical order	156
Some cases where the MQGET call fails	159
<b>Chapter 11. Writing data-conversion exits</b>	161
Invoking the data-conversion exit	161
Writing a data-conversion exit program	163
Writing a data-conversion exit program for MQSeries for AS/400	167
Writing a data-conversion exit for MQSeries for OS/2 Warp	168
Writing a data-conversion exit program for MQSeries for OS/390	170
Writing a data-conversion exit for MQSeries for Tandem NSK	171
Writing a data-conversion exit for MQSeries on UNIX systems and Digital OpenVMS	172
Writing a data-conversion exit for MQSeries for Windows NT	177
<b>Chapter 12. Inquiring about and setting object attributes</b>	179
Inquiring about the attributes of an object	180
Some cases where the MQINQ call fails	181
Setting queue attributes	182
<b>Chapter 13. Committing and backing out units of work</b>	183
Syncpoint considerations in MQSeries applications	184
Syncpoints in MQSeries for OS/390 applications	185
Syncpoints in MQSeries for AS/400 applications	188
Syncpoints in CICS for AS/400 applications	189
Syncpoints in MQSeries for OS/2 Warp, MQSeries for Windows NT, MQSeries for Digital OpenVMS, and MQSeries on UNIX systems	189
Syncpoints in MQSeries for Tandem NSK applications	194
General XA support	195
<b>Chapter 14. Starting MQSeries applications using triggers</b>	197
What is triggering?	197
Prerequisites for triggering	202
Conditions for a trigger event	204
Controlling trigger events	208
Designing an application that uses triggered queues	210
Trigger monitors	212

Properties of trigger messages	215
When triggering does not work	217
<b>Chapter 15. Using and writing applications on MQSeries for OS/390</b>	219
Environment-dependent MQSeries for OS/390 functions	219
Program debugging facilities	220
Syncpoint support	220
Recovery support	220
The MQSeries for OS/390 interface with the application environment	221
Writing OS/390 OpenEdition® applications	224
The API-crossing exit for OS/390	225
Writing MQSeries-CICS bridge applications	230
Writing MQSeries-IMS bridge applications	239
Writing IMS applications using MQSeries	245
MQSeries Workflow	249
<b>Chapter 16. Object-oriented programming with MQSeries</b>	251
What is in the MQSeries Object Model?	251
Programming language considerations	253
<hr/>	
<b>Part 3. Building an MQSeries application</b>	255
<b>Chapter 17. Building your application on AIX</b>	259
Preparing C programs	259
Preparing COBOL programs	260
Preparing PL/I programs	261
Preparing CICS programs	261
<b>Chapter 18. Building your application on AS/400</b>	265
Preparing C programs	265
Preparing COBOL programs	265
Preparing RPG programs	266
AS/400 programming considerations	266
<b>Chapter 19. Building your application on AT&amp;T GIS UNIX</b>	267
Preparing C programs	267
<b>Chapter 20. Building your application on Digital OpenVMS</b>	269
Preparing C programs	269
Preparing COBOL programs	270
<b>Chapter 21. Building your application on HP-UX</b>	271
Preparing C programs	271
Preparing COBOL programs	272
Preparing CICS programs	273
<b>Chapter 22. Building your application on OS/390</b>	275
Preparing your program to run	275
Dynamically calling the MQSeries stub	279
Debugging your programs	284
<b>Chapter 23. Building your application on OS/2 Warp</b>	289
Preparing C programs	289

Preparing COBOL programs	291
Preparing PL/I programs	292
<b>Chapter 24. Building your application on SINIX or DC/OSx</b>	293
Preparing C programs	293
Preparing COBOL programs	294
Preparing CICS programs	295
Linking libraries	296
<b>Chapter 25. Building your application on Sun Solaris</b>	297
Preparing C programs	297
Preparing COBOL programs	298
Preparing CICS programs	299
<b>Chapter 26. Building your application on Tandem NSK</b>	301
Unit of work (transaction) management	301
Compiling and binding applications	303
Running applications	303
<b>Chapter 27. Building your application on VSE/ESA</b>	305
Linking library	305
Using the batch interface	305
Preparing C programs	305
Preparing COBOL programs	305
Preparing PL/I programs	305
<b>Chapter 28. Building your application on Windows</b>	307
Linking libraries	307
Preparing Visual Basic programs	307
<b>Chapter 29. Building your application on Windows NT</b>	309
Preparing C programs	309
Preparing COBOL programs	311
Preparing PL/I programs	313
Preparing Visual Basic programs	313
<b>Chapter 30. Using lightweight directory access protocol services with MQSeries for Windows NT</b>	315
What is a directory service?	315
What is LDAP?	315
Using LDAP with MQSeries	316
LDAP sample program	317
<b>Part 4. Sample MQSeries programs</b>	323
<b>Chapter 31. Sample programs (all platforms except OS/390)</b>	327
Features demonstrated in the sample programs	327
Preparing and running the sample programs	336
The Put sample programs	342
The Distribution List sample program	345
The Browse sample programs	346
The Browser sample program	347
The Get sample programs	349

## Contents

The Reference Message sample programs	351
The Request sample programs	359
The Inquire sample programs	366
The Set sample programs	367
The Echo sample programs	369
The Data-Conversion sample program	370
The Triggering sample programs	371
Running the samples using remote queues	373
Database coordination samples	373
The CICS transaction sample	379
TUXEDO samples	379
Encina sample program	390
Dead-letter queue handler sample	391
The Connect sample program	391
<b>Chapter 32. Sample programs for MQSeries for OS/390</b>	<b>395</b>
Features demonstrated in the sample applications	395
Preparing and running sample applications for the batch environment	399
Preparing sample applications for the TSO environment	401
Preparing the sample applications for the CICS environment	403
Preparing the sample application for the IMS environment	407
The Put samples	408
The Get samples	411
The Browse sample	414
The Print Message sample	416
The Queue Attributes sample	420
The Mail Manager sample	421
The Credit Check sample	430
The Message Handler sample	443
<b>Part 5. Appendixes</b>	<b>449</b>
<b>Appendix A. Language compilers and assemblers</b>	<b>453</b>
<b>Appendix B. MQI names in RPG</b>	<b>457</b>
<b>Appendix C. C language examples</b>	<b>487</b>
Connecting to a queue manager	488
Disconnecting from a queue manager	488
Creating a dynamic queue	489
Opening an existing queue	489
Closing a queue	490
Putting a message using MQPUT	490
Putting a message using MQPUT1	491
Getting a message	492
Getting a message using the wait option	492
Getting a message using signaling	493
Inquiring about the attributes of an object	494
Setting the attributes of a queue	495
<b>Appendix D. COBOL examples</b>	<b>497</b>
Connecting to a queue manager	498
Disconnecting from a queue manager	498

Creating a dynamic queue	499
Opening an existing queue	500
Closing a queue	501
Putting a message using MQPUT	501
Putting a message using MQPUT1	502
Getting a message	503
Getting a message using the wait option	504
Getting a message using signaling	505
Inquiring about the attributes of an object	506
Setting the attributes of a queue	507
<b>Appendix E. System/390 assembler-language examples</b>	509
Connecting to a queue manager	510
Disconnecting from a queue manager	510
Creating a dynamic queue	511
Opening an existing queue	512
Closing a queue	512
Putting a message using MQPUT	513
Putting a message using MQPUT1	513
Getting a message	514
Getting a message using the wait option	515
Getting a message using signaling	516
Inquiring about and setting the attributes of a queue	517
<b>Appendix F. PL/I examples</b>	519
Connecting to a queue manager	520
Disconnecting from a queue manager	520
Creating a dynamic queue	521
Opening an existing queue	521
Closing a queue	522
Putting a message using MQPUT	522
Putting a message using MQPUT1	523
Getting a message	524
Getting a message using the wait option	525
Getting a message using signaling	526
Inquiring about the attributes of an object	527
Setting the attributes of a queue	528
<b>Appendix G. MQSeries data definition files</b>	529
C language include files	530
Visual Basic module files	531
COBOL copy files	532
System/390 assembler-language macros	535
PL/I include files	536
<b>Appendix H. List of MQSeries products</b>	537
Level 1 products	537
Level 2 products	537
<b>Appendix I. MQSeries platforms - functional comparisons</b>	539
What is included here	539
Syncpoint	540
Triggering	544
Input	547

## Figures

Message properties and protocols	551
Threading	555
Security	556
Object types	560
Administration	562
Programming languages	564
Connection	566
<b>Appendix J. Notices</b>	<b>567</b>
Programming interface information	569
Trademarks	570

---

<b>Part 6. Glossary and Index</b>	<b>571</b>
<b>Glossary of terms and abbreviations</b>	<b>573</b>
<b>Index</b>	<b>585</b>

---

## Figures

1. Message queuing compared with traditional communication	8
2. Representation of a message	23
3. Group of logical messages	33
4. Segmented messages	34
5. How distribution lists work	117
6. Opening a distribution list in C	119
7. Opening a distribution list in COBOL	119
8. Putting a message to a distribution list in C	120
9. Putting a message to a distribution list in COBOL	121
10. Logical order on a queue	130
11. Physical order on a queue	131
12. Skipping backout using MQGMO_MARK_SKIP_BACKOUT	151
13. Sample JCL used to invoke the CSQUCVX utility	165
14. Flow of application and trigger messages	199
15. Relationship of queues within triggering	201
16. Setting of key fields for a single CICS user program in a unit of work, or non-conversational 3270 transaction	235
17. Setting of key fields for many CICS user programs in a unit of work	236
18. Setting of key fields: MQSeries - conversational 3270 transaction	237
19. User program abends (only program in the unit of work)	238
20. Fragments of JCL to link-edit the object module in the batch environment, using single-phase commit	276
21. Fragments of JCL to link-edit the object module in the batch environment, using two-phase commit	276
22. Fragments of JCL to link-edit the object module in the CICS environment	278
23. Fragments of JCL to link-edit the object module in the IMS environment	279
24. Dynamic linking using COBOL in the batch environment	280
25. Dynamic linking using COBOL in the CICS environment	281
26. Dynamic linking using COBOL in the IMS environment	281

27.	Dynamic linking using assembler language in the batch environment	282
28.	Dynamic linking using assembler language in the CICS environment	282
29.	Dynamic linking using assembler language in the IMS environment	282
30.	Dynamic linking using C language in the batch environment	282
31.	Dynamic linking using C language in the CICS environment	283
32.	Dynamic linking using C language in the IMS environment	283
33.	Dynamic linking using PL/I in the batch environment	283
34.	Dynamic linking using PL/I in the IMS environment	284
35.	Running the reference message samples	353
36.	Request and Inquire samples using triggering	362
37.	Sample Client/Server (Echo) program flowchart	365
38.	The database coordination samples	374
39.	Example of ubbstxcx.cfg file for UNIX systems	385
40.	Example of ubbstxcn.cfg file for Windows NT	387
41.	Sample TUXEDO makefile for MQSeries for Windows NT	388
42.	How TUXEDO samples work together	389
43.	Example of a report from the Print Message sample application	417
44.	Programs and panels for the TSO versions of the Mail Manager	425
45.	Programs and panels for the CICS version of the Mail Manager	426
46.	Example of a panel showing a list of waiting messages	428
47.	Example of a panel showing the contents of a message	428
48.	Immediate Inquiry panel for the Credit Check sample application	431
49.	Programs and queues for the Credit Check sample application (COBOL programs only)	433
50.	Initial screen for Message Handler sample	444
51.	Message list screen for Message Handler sample	444
52.	Chosen message is displayed	445
53.	Using the MQCONN call (C language)	488
54.	Using the MQDISC call (C language)	488
55.	Using the MQOPEN call to create a dynamic queue (C language)	489
56.	Using the MQOPEN call to open an existing queue (C language)	489
57.	Using the MQCLOSE call (C language)	490
58.	Using the MQPUT call (C language)	490
59.	Using the MQPUT1 call (C language)	491
60.	Using the MQGET call (C language)	492
61.	Using the MQGET call with the wait option (C language)	492
62.	Using the MQGET call with signaling (C language)	493
63.	Using the MQINQ call (C language)	494
64.	Using the MQSET call (C language)	495
65.	Using the MQCONN call (COBOL)	498
66.	Using the MQDISC call (COBOL)	498
67.	Using the MQOPEN call to create a dynamic queue (COBOL)	499
68.	Using the MQOPEN call to open an existing queue (COBOL)	500
69.	Using the MQCLOSE call (COBOL)	501
70.	Using the MQPUT call (COBOL)	501
71.	Using the MQPUT1 call (COBOL)	502
72.	Using the MQGET call (COBOL)	503
73.	Using the MQGET call with the wait option (COBOL)	504
74.	Using the MQGET call with signaling (COBOL)	505
75.	Using the MQINQ call (COBOL)	506
76.	Using the MQSET call (COBOL)	507
77.	Using the MQCONN call (Assembler language)	510
78.	Using the MQDISC call (Assembler language)	510

## Tables

79. Using the MQOPEN call to create a dynamic queue (Assembler language) . . . . .	511
80. Using the MQOPEN call to open an existing queue (Assembler language) . . . . .	512
81. Using the MQCLOSE call (Assembler language) . . . . .	512
82. Using the MQPUT call (Assembler language) . . . . .	513
83. Using the MQPUT1 call (Assembler language) . . . . .	513
84. Using the MQGET call (Assembler language) . . . . .	514
85. Using the MQGET call with the wait option (Assembler language) . . . . .	515
86. Using the MQGET call with signaling (Assembler language) . . . . .	516
87. Using the MQINQ and MQSET calls (Assembler language) . . . . .	517
88. Using the MQCONN call (PL/I) . . . . .	520
89. Using the MQDISC call (PL/I) . . . . .	520
90. Using the MQOPEN call to create a dynamic queue (PL/I) . . . . .	521
91. Using the MQOPEN call to open an existing queue (PL/I) . . . . .	521
92. Using the MQCLOSE call (PL/I) . . . . .	522
93. Using the MQPUT call (PL/I) . . . . .	522
94. Using the MQPUT1 call (PL/I) . . . . .	523
95. Using the MQGET call (PL/I) . . . . .	524
96. Using the MQGET call with the wait option (PL/I) . . . . .	525
97. Using the MQGET call with signaling (PL/I) . . . . .	526
98. Using the MQINQ call (PL/I) . . . . .	527
99. Using the MQSET call (PL/I) . . . . .	528

---

## Tables

1. Visual Basic equivalents of the C elementary data types . . . . .	69
2. Environment variable . . . . .	94
3. Resolving queue names when using MQOPEN . . . . .	100
4. How queue attributes and options of the MQOPEN call affect access to queues . . . . .	103
5. Using message and correlation identifiers . . . . .	138
6. Using the group identifier . . . . .	138
7. Skeleton source files . . . . .	164
8. Linking MQSeries for OS/2 Warp with CICS Version 3 applications . . . . .	193
9. Essential Code for CICS applications . . . . .	195
10. OS/390 environmental features . . . . .	219
11. Mapping MQSeries messages to IMS transaction types . . . . .	241
12. Essential Code for CICS applications (AIX) . . . . .	261
13. Essential Code for CICS applications (HP-UX) . . . . .	273
14. Call names for dynamic linking . . . . .	280
15. CICS adapter trace entries . . . . .	285
16. Essential Code for CICS applications (SINIX) . . . . .	295
17. Essential Code for CICS applications (Sun Solaris) . . . . .	299
18. MQSeries on UNIX and Digital OpenVMS sample programs demonstrating use of the MQI . . . . .	328
19. MQSeries for OS/2 Warp and Windows NT sample programs demonstrating use of the MQI . . . . .	330
20. MQSeries for AIX, OS/2 Warp, and Windows NT sample programs demonstrating use of the MQI . . . . .	331

21.	MQSeries for Windows NT sample programs demonstrating use of the MQI . . . . .	332
22.	MQSeries for AS/400 sample programs demonstrating use of the MQI . . . . .	333
23.	MQSeries for Tandem NSK C and COBOL sample programs demonstrating use of the MQI . . . . .	334
24.	MQSeries for Tandem NSK TAL sample programs demonstrating use of the MQI . . . . .	334
25.	MQSeries for VSE/ESA COBOL sample programs demonstrating use of the MQI . . . . .	335
26.	Where to find the samples for MQSeries on UNIX systems . . . . .	336
27.	Where to find the samples for MQSeries for Digital OpenVMS . . . . .	337
28.	Where to find the samples for MQSeries for OS/2 Warp and MQSeries for Windows NT . . . . .	338
29.	Client/server sample program details . . . . .	365
30.	Source for the distributed queuing exit samples . . . . .	399
31.	Source for the data conversion exit samples (Assembler language only) . . . . .	399
32.	Source and JCL for the Put and Get samples . . . . .	400
33.	Source and JCL for the Browse sample . . . . .	401
34.	Source for the Print Message sample (C language only) . . . . .	401
35.	Source and JCL for the Mail Manager (TSO) sample . . . . .	402
36.	Source for the Message Handler sample . . . . .	403
37.	Source and JCL for the Put and Get samples . . . . .	404
38.	Source for the Queue Attributes sample . . . . .	405
39.	Source and JCL for the Mail Manager (CICS) sample (COBOL only) . . . . .	405
40.	Source and JCL for the Credit Check CICS sample . . . . .	406
41.	Source and JCL for the Credit Check IMS sample (C only) . . . . .	408
42.	Language compilers and assemblers . . . . .	453
43.	Names of calls . . . . .	457
44.	Names of call parameters . . . . .	457
45.	Data types . . . . .	458
46.	Names of fields in structures . . . . .	458
47.	Names of constants . . . . .	466
48.	C include files for MQSeries . . . . .	530
49.	Visual Basic module files for MQSeries for Windows V2.0 . . . . .	531
50.	Visual Basic module files for MQSeries for Windows V2.1 . . . . .	531
51.	Visual Basic module files for MQSeries for Windows NT V5.1 . . . . .	531
52.	COBOL copy files . . . . .	533
53.	System/390 assembler-language macros . . . . .	535
54.	PL/I include files . . . . .	536
55.	MQSeries products, Level 1 . . . . .	537
56.	MQSeries products, Level 2 . . . . .	537
57.	Syncpoint support - function summary . . . . .	540
58.	Triggering support - function summary . . . . .	544
59.	Input features - function summary . . . . .	547
60.	Message properties - function summary . . . . .	551
61.	Threading - function summary . . . . .	555
62.	Security - function summary . . . . .	556
63.	Object types - function summary . . . . .	560
64.	Administration - function summary . . . . .	562
65.	Programming languages supported - function summary . . . . .	564
66.	Default connection to a queue manager - function summary . . . . .	566

## Tables

---

## About this book

This book introduces the concepts of *messages* and *queues*, and shows you how to design and write applications that use the services that MQSeries provides.

The IBM MQSeries Level 2 products comprise:

- MQSeries for AIX
- MQSeries for AS/400  
(formerly known as MQSeries for OS/400®)
- MQSeries for AT&T GIS UNIX®<sup>1</sup>
- MQSeries for Digital OpenVMS
- MQSeries for HP-UX
- MQSeries for OS/390  
(formerly known as MQSeries for MVS/ESA™)
- MQSeries for OS/2 Warp
- MQSeries for SINIX and DC/OSx
- MQSeries for Sun Solaris
- MQSeries for Tandem NonStop Kernel
- MQSeries for VSE/ESA
- MQSeries for Windows
- MQSeries for Windows NT

They are referred to in this book collectively as MQSeries. They provide application programming services that allow a new style of programming. This style enables you to write applications in which the constituent programs communicate with each other using *message queues*.

For a full description of the MQSeries programming interface, see the *MQSeries Application Programming Reference* manual for your platform. The manuals are:

- *MQSeries Application Programming Reference* manual, SC33-1673
- *MQSeries for AS/400 Application Programming Reference (RPG)*, SC33-1957

For information on the use of C++, see the *MQSeries Using C++* book.

For information on the MQSeries Level 1 products, see the books listed in “MQSeries Level 1 product publications” on page xxii. For a functional comparison of Level 1 and Level 2 MQSeries products, see the *MQSeries Planning Guide*.

In this book, references to “MQSeries on UNIX systems” include:

- IBM MQSeries for AIX Version 5.1
- IBM MQSeries for AT&T GIS UNIX Version 2.2
- IBM MQSeries for HP-UX Version 5.1
- IBM MQSeries for SINIX and DC/OSx Version 2.2
- IBM MQSeries for Sun Solaris Version 5.1

---

<sup>1</sup> This platform has become NCR UNIX SVR4 MP-RAS, R3.0.

## About this book

The term “MQSeries Version 5 products” applies to the following MQSeries products:

- IBM MQSeries for AIX Version 5.1
- IBM MQSeries for HP-UX Version 5.1
- IBM MQSeries for OS/2 Warp Version 5.1
- IBM MQSeries for Sun Solaris Version 5.1
- IBM MQSeries for Windows NT Version 5.1

IBM ships sample programs with IBM MQSeries which are explained in Part 4, “Sample MQSeries programs” on page 323. You may find it useful to refer to these.

---

## Who this book is for

This book is for the designers of applications that use message queuing techniques, and for the programmers who have to implement those designs.

---

## What you need to know to understand this book

To write message queuing applications using MQSeries, you need to know how to write programs in at least one of the programming languages that MQSeries supports. Appendix A, “Language compilers and assemblers” on page 453 contains details of supported compilers and assemblers listed by MQSeries platform.

If the applications you are writing will run within a CICS® or IMS™ system, you must also be familiar with CICS or IMS, and their application programming interfaces.

To understand this book, you do not need to have written message queuing programs before.

---

## How to use this book

This book contains guidance information to help you design an application, and procedural information to help you to write an application.

The book is divided into five parts:

**Part 1, “Designing applications that use MQSeries” on page 1**

Introduces the message queuing style of application design, describes MQSeries messages and queues, and shows how to design a message queuing application.

**Part 2, “Writing an MQSeries application” on page 61**

Describes how to use the IBM Message Queue Interface (MQI) to write the programs that comprise a message queuing application. The chapters guide you through the coding of each MQI call, showing you what information to supply as input and what returns to expect. These chapters first describe simple uses of the MQI calls, then go on to describe how to use all the features of each call.

Read Part 1, “Designing applications that use MQSeries” on page 1 to understand the concepts involved when designing MQSeries

applications. The second part is self-contained: use an individual chapter when you are performing the task described in it.

**Part 3, “Building an MQSeries application” on page 255**

Explains how to build your MQSeries application on each platform.

**Part 4, “Sample MQSeries programs” on page 323**

Lists and explains how the sample programs work, for all platforms.

**Part 5, “Appendixes” on page 449**

Contains examples of how to use the MQI calls in each of the programming languages supported by MQSeries.

## Appearance of text in this book

This book uses the following type style:

*CompCode*                      Example of the name of a parameter of a call, or the attribute of an object

## Terms used in this book

In the body of this book, the following shortened names are used for these products and qualifier:

**CICS**

CICS for AS/400, CICS for MVS/ESA, CICS for VSE/ESA, CICS Transaction Server for OS/2, CICS Transaction Server for OS/390, TXSeries for AIX, TXSeries for HP-UX, TXSeries for Sun Solaris, and TXSeries for Windows NT products.

**IMS**

The IMS/ESA® product.

**MQSeries**

MQSeries for AIX, MQSeries for AS/400, MQSeries for AT&T GIS UNIX, MQSeries for Digital OpenVMS, MQSeries for HP-UX, MQSeries for OS/2 Warp, MQSeries for OS/390, MQSeries for SINIX and DC/OSx, MQSeries for Sun Solaris, MQSeries for Tandem NSK, MQSeries for VSE/ESA, MQSeries for Windows, and MQSeries for Windows NT.

**MQSeries on UNIX systems**

MQSeries for AIX, MQSeries for AT&T GIS UNIX, MQSeries for HP-UX, MQSeries for SINIX and DC/OSx, and MQSeries for Sun Solaris.

**OS/390**

The OS/390 System Product.

**thlqual**

The high-level qualifier of the installation library on OS/390.

### MQSeries publications

This section describes the documentation available for all current MQSeries products.

### MQSeries cross-platform publications

Most of these publications, which are sometimes referred to as the MQSeries “family” books, apply to all MQSeries Level 2 products. The latest MQSeries Level 2 products are:

- MQSeries for AIX V5.1
- MQSeries for AS/400 V4R2M1
- MQSeries for AT&T GIS UNIX V2.2
- MQSeries for Digital OpenVMS V2.2
- MQSeries for HP-UX V5.1
- MQSeries for OS/2 Warp V5.1
- MQSeries for OS/390 V2.1
- MQSeries for SINIX and DC/OSx V2.2
- MQSeries for Sun Solaris V5.1
- MQSeries for Tandem NonStop Kernel V2.2
- MQSeries for VSE/ESA V2.1
- MQSeries for Windows V2.0
- MQSeries for Windows V2.1
- MQSeries for Windows NT V5.1

Any exceptions to this general rule are indicated. (Publications that support the MQSeries Level 1 products are listed in “MQSeries Level 1 product publications” on page xxii. For a functional comparison of the Level 1 and Level 2 MQSeries products, see the *MQSeries Planning Guide*.)

#### **MQSeries Brochure**

The *MQSeries Brochure*, G511-1908, gives a brief introduction to the benefits of MQSeries. It is intended to support the purchasing decision, and describes some authentic customer use of MQSeries.

#### **MQSeries: An Introduction to Messaging and Queuing**

*MQSeries: An Introduction to Messaging and Queuing*, GC33-0805, describes briefly what MQSeries is, how it works, and how it can solve some classic interoperability problems. This book is intended for a more technical audience than the *MQSeries Brochure*.

#### **MQSeries Planning Guide**

The *MQSeries Planning Guide*, GC33-1349, describes some key MQSeries concepts, identifies items that need to be considered before MQSeries is installed, including storage requirements, backup and recovery, security, and migration from earlier releases, and specifies hardware and software requirements for every MQSeries platform.

#### **MQSeries Intercommunication**

The *MQSeries Intercommunication* book, SC33-1872, defines the concepts of distributed queuing and explains how to set up a distributed queuing network in a variety of MQSeries environments. In particular, it demonstrates how to (1) configure communications to and from a representative sample of MQSeries products, (2) create required MQSeries objects, and (3) create and configure MQSeries channels. The use of channel exits is also described.

**MQSeries Clients**

The *MQSeries Clients* book, GC33-1632, describes how to install, configure, use, and manage MQSeries client systems.

**MQSeries System Administration**

The *MQSeries System Administration* book, SC33-1873, supports day-to-day management of local and remote MQSeries objects. It includes topics such as security, recovery and restart, transactional support, problem determination, and the dead-letter queue handler. It also includes the syntax of the MQSeries control commands.

This book applies to the following MQSeries products only:

- MQSeries for AIX V5.1
- MQSeries for HP-UX V5.1
- MQSeries for OS/2 Warp V5.1
- MQSeries for Sun Solaris V5.1
- MQSeries for Windows NT V5.1

**MQSeries Command Reference**

The *MQSeries Command Reference*, SC33-1369, contains the syntax of the MQSC commands, which are used by MQSeries system operators and administrators to manage MQSeries objects.

**MQSeries Programmable System Management**

The *MQSeries Programmable System Management* book, SC33-1482, provides both reference and guidance information for users of MQSeries events, Programmable Command Format (PCF) messages, and installable services.

**MQSeries Messages**

The *MQSeries Messages* book, GC33-1876, which describes “AMQ” messages issued by MQSeries, applies to these MQSeries products only:

- MQSeries for AIX V5.1
- MQSeries for HP-UX V5.1
- MQSeries for OS/2 Warp V5.1
- MQSeries for Sun Solaris V5.1
- MQSeries for Windows NT V5.1
- MQSeries for Windows V2.0
- MQSeries for Windows V2.1

This book is available in softcopy only.

**MQSeries Application Programming Guide**

The *MQSeries Application Programming Guide*, SC33-0807, provides guidance information for users of the message queue interface (MQI). It describes how to design, write, and build an MQSeries application. It also includes full descriptions of the sample programs supplied with MQSeries.

**MQSeries Application Programming Reference**

The *MQSeries Application Programming Reference*, SC33-1673, provides comprehensive reference information for users of the MQI. It includes: data-type descriptions; MQI call syntax; attributes of MQSeries objects; return codes; constants; and code-page conversion tables.

**MQSeries Application Programming Reference Summary**

The *MQSeries Application Programming Reference Summary*, SX33-6095, summarizes the information in the *MQSeries Application Programming Reference* manual.

### **MQSeries Using C++**

*MQSeries Using C++*, SC33-1877, provides both guidance and reference information for users of the MQSeries C++ programming-language binding to the MQI. MQSeries C++ is supported by these MQSeries products:

- MQSeries for AIX V5.1
- MQSeries for AS/400 V4R2M1
- MQSeries for HP-UX V5.1
- MQSeries for OS/2 Warp V5.1
- MQSeries for OS/390 V2.1
- MQSeries for Sun Solaris V5.1
- MQSeries for Windows NT V5.1

MQSeries C++ is also supported by MQSeries clients supplied with these products and installed in the following environments:

- AIX
- HP-UX
- OS/2
- Sun Solaris
- Windows NT
- Windows 3.1
- Windows 95 and Windows 98

### **MQSeries Using Java™**

*MQSeries Using Java*, SC34-5456, provides both guidance and reference information for users of the MQSeries Bindings for Java and the MQSeries Client for Java. MQSeries Java is supported by these MQSeries products:

- MQSeries for AIX V5.1
- MQSeries for HP-UX V5.1
- MQSeries for OS/2 Warp V5.1
- MQSeries for Sun Solaris V5.1
- MQSeries for Windows NT V5.1

### **MQSeries Administration Interface Programming Guide and Reference**

The *MQSeries Administration Interface Programming Guide and Reference*, SC34-5390, provides information for users of the MQAI. The MQAI is a programming interface that simplifies the way in which applications manipulate Programmable Command Format (PCF) messages and their associated data structures.

This book applies to the following MQSeries products only:

- MQSeries for AIX V5.1
- MQSeries for HP-UX V5.1
- MQSeries for OS/2 Warp V5.1
- MQSeries for Sun Solaris V5.1
- MQSeries for Windows NT V5.1

### **MQSeries Queue Manager Clusters**

*MQSeries Queue Manager Clusters*, SC34-5349, describes MQSeries clustering. It explains the concepts and terminology and shows how you can benefit by taking advantage of clustering. It details changes to the MQI, and summarizes the syntax of new and changed MQSeries commands. It shows a number of examples of tasks you can perform to set up and maintain clusters of queue managers.

This book applies to the following MQSeries products only:

MQSeries for AIX V5.1  
 MQSeries for HP-UX V5.1  
 MQSeries for OS/2 Warp V5.1  
 MQSeries for OS/390 V2.1  
 MQSeries for Sun Solaris V5.1  
 MQSeries for Windows NT V5.1

## MQSeries platform-specific publications

Each MQSeries product is documented in at least one platform-specific publication, in addition to the MQSeries family books.

### MQSeries for AIX

*MQSeries for AIX Version 5 Release 1 Quick Beginnings*, GC33-1867

### MQSeries for AS/400

*MQSeries for AS/400 Version 4 Release 2.1 Administration Guide*, GC33-1956

*MQSeries for AS/400 Version 4 Release 2 Application Programming Reference (RPG)*, SC33-1957

### MQSeries for AT&T GIS UNIX

*MQSeries for AT&T GIS UNIX Version 2 Release 2 System Management Guide*, SC33-1642

### MQSeries for Digital OpenVMS

*MQSeries for Digital OpenVMS Version 2 Release 2 System Management Guide*, GC33-1791

### MQSeries for Digital UNIX

*MQSeries for Digital UNIX Version 2 Release 2.1 System Management Guide*, GC34-5483

### MQSeries for HP-UX

*MQSeries for HP-UX Version 5 Release 1 Quick Beginnings*, GC33-1869

### MQSeries for OS/2 Warp

*MQSeries for OS/2 Warp Version 5 Release 1 Quick Beginnings*, GC33-1868

### MQSeries for OS/390

*MQSeries for OS/390 Version 2 Release 1 Licensed Program Specifications*, GC34-5377

*MQSeries for OS/390 Version 2 Release 1 Program Directory*

*MQSeries for OS/390 Version 2 Release 1 System Management Guide*, SC34-5374

*MQSeries for OS/390 Version 2 Release 1 Messages and Codes*, GC34-5375

*MQSeries for OS/390 Version 2 Release 1 Problem Determination Guide*, GC34-5376

### MQSeries link for R/3

*MQSeries link for R/3 Version 1 Release 2 User's Guide*, GC33-1934

## MQSeries publications

### MQSeries for SINIX and DC/OSx

*MQSeries for SINIX and DC/OSx Version 2 Release 2 System Management Guide*, GC33-1768

### MQSeries for Sun Solaris

*MQSeries for Sun Solaris Version 5 Release 1 Quick Beginnings*, GC33-1870

### MQSeries for Tandem NonStop Kernel

*MQSeries for Tandem NonStop Kernel Version 2 Release 2 System Management Guide*, GC33-1893

### MQSeries for VSE/ESA

*MQSeries for VSE/ESA Version 2 Release 1 Licensed Program Specifications*, GC34-5365

*MQSeries for VSE/ESA Version 2 Release 1 System Management Guide*, GC34-5364

### MQSeries for Windows

*MQSeries for Windows Version 2 Release 0 User's Guide*, GC33-1822

*MQSeries for Windows Version 2 Release 1 User's Guide*, GC33-1965

### MQSeries for Windows NT

*MQSeries for Windows NT Version 5 Release 1 Quick Beginnings*, GC34-5389

*MQSeries for Windows NT Using the Component Object Model Interface*, SC34-5387

*MQSeries LotusScript Extension*, SC34-5404

## MQSeries Level 1 product publications

For information about the MQSeries Level 1 products, see the following publications:

*MQSeries: Concepts and Architecture*, GC33-1141

*MQSeries Version 1 Products for UNIX Operating Systems Messages and Codes*, SC33-1754

*MQSeries for UnixWare Version 1 Release 4.1 User's Guide*, SC33-1379

## Softcopy books

Most of the MQSeries books are supplied in both hardcopy and softcopy formats.

### BookManager® format

The MQSeries library is supplied in IBM BookManager format on a variety of online library collection kits, including the *Transaction Processing and Data* collection kit, SK2T-0730. You can view the softcopy books in IBM BookManager format using the following IBM licensed programs:

BookManager READ/2

BookManager READ/6000

BookManager READ/DOS

BookManager READ/MVS

BookManager READ/VM

BookManager READ for Windows

## HTML format

Relevant MQSeries documentation is provided in HTML format with these MQSeries products:

- MQSeries for AIX V5.1
- MQSeries for HP-UX V5.1
- MQSeries for OS/2 Warp V5.1
- MQSeries for Sun Solaris V5.1
- MQSeries for Windows NT V5.1 (compiled HTML)
- MQSeries link for R/3 V1.2

The MQSeries books are also available in HTML format from the MQSeries product family Web site at:

<http://www.software.ibm.com/ts/mqseries/>

## Portable Document Format (PDF)

PDF files can be viewed and printed using the Adobe Acrobat Reader.

If you need to obtain the Adobe Acrobat Reader, or would like up-to-date information about the platforms on which the Acrobat Reader is supported, visit the Adobe Systems Inc. Web site at:

<http://www.adobe.com/>

PDF versions of relevant MQSeries books are supplied with these MQSeries products:

- MQSeries for AIX V5.1
- MQSeries for HP-UX V5.1
- MQSeries for OS/2 Warp V5.1
- MQSeries for Sun Solaris V5.1
- MQSeries for Windows NT V5.1
- MQSeries link for R/3 V1.2

PDF versions of all current MQSeries books are also available from the MQSeries product family Web site at:

<http://www.software.ibm.com/ts/mqseries/>

## PostScript format

The MQSeries library is provided in PostScript (.PS) format with many MQSeries Version 2 products. Books in PostScript format can be printed on a PostScript printer or viewed with a suitable viewer.

## Windows Help format

The *MQSeries for Windows User's Guide* is provided in Windows Help format with MQSeries for Windows Version 2.0 and MQSeries for Windows Version 2.1.

---

## MQSeries information available on the Internet

### MQSeries Web site

The MQSeries product family Web site is at:

<http://www.software.ibm.com/ts/mqseries/>

By following links from this Web site you can:

- Obtain latest information about the MQSeries product family.
- Access the MQSeries books in HTML and PDF formats.
- Download MQSeries SupportPacs™.

---

## Related publications

This section describes the documentation available for some related products and issues mentioned in this book.

### CICS

For information about those aspects of CICS Transaction Server for OS/390 that this book refers to, see the following books:

*CICS Application Programming Reference*, SC33-1688  
*CICS Customization Guide*, SC33-1683  
*CICS-Supplied Transactions*, SC33-1686  
*CICS System Definition Guide*, SC33-1682

For information about those aspects of CICS for MVS/ESA Version 4.1 that this book refers to, see the following books:

*CICS for MVS/ESA V4.1 Application Programming Reference*, SC33-1170  
*CICS for MVS/ESA V4.1 Customization Guide*, SC33-1165  
*CICS for MVS/ESA V4.1 CICS-Supplied Transactions*, SC33-1168  
*CICS for MVS/ESA V4.1 System Definition Guide*, SC33-1164

For information about CICS programming on other platforms, see the following books:

*CICS on Open Systems Application Programming Guide*, SC33-1568-00  
*CICS for OS/2 V2.0.1 Application Programming*, SC33-0883  
*Transaction Server for OS/2 Warp, V4 Application Programming*, SC33-1585  
*CICS for AS/400 Application Programming Guide*, SC33-1386  
*CICS for Windows NT V2.0 Application Programming*, SC33-1425  
*Transaction Server for Windows NT, V4 Application Programming Guide*, SC33-1888

## IMS

For information about those aspects of IMS that this book refers to, see the following books:

*IMS/ESA Version 4 Application Programming: DL/I Calls*, SC26-3062  
*IMS/ESA Version 4 Application Programming: Design Guide*, SC26-3066  
*IMS/ESA Version 5 Application Programming: Database Manager*, SC26-8015  
*IMS/ESA Version 5 Application Programming: Design Guide*, SC26-8016  
*IMS/ESA Version 5 Application Programming: Transaction Manager*, SC26-8017  
*IMS/ESA Version 5 Open Transaction Manager Access Guide*, SC26-8026

## MVS/ESA

For information about those aspects of MVS/ESA that this book refers to, see the following book:

*MVS/ESA Application Development Guide: Assembler Language Programs*, GC28-1644

## Design

For information on how to design panel-driven application interfaces, see the following book:

*Systems Application Architecture, Common User Access: Basic Interface Design Guide*, SC26-4583

## C

For information about C programming, see the following books:

*Guide to Tools for Programming in C*, U6296-J-Z145-2-7600  
*SNI Programmer*, U6401-J-Z145-3-7600  
*OS/390 C/C++ Programming Guide*, SC09-2362

## C++

For information about C++ programming, see the following books:

*C Set++ for AIX: User's Guide*, SC09-1968  
*VisualAge C++ for OS/2 User's Guide*, S25H-6961  
*VisualAge C++ for OS/2 Programming Guide*, S25H-6958  
*VisualAge for C++ for Windows User's Guide*, S33H-5031  
*VisualAge for C++ for Windows Programming Guide*, S33H-5032  
*VisualAge for C++ for AS/400 : C++ User's Guide*, SC09-2416  
*OS/390 C/C++ Programming Guide*, SC09-2362

## COBOL

For information about COBOL programming that this book refers to, see the following books:

*COBOL V3.2 SINIX pocket guide*, U21709-J-Z145-2-7600  
*IBM COBOL Set for AIX Programming Guide*, SC26-8423  
*IBM COBOL for MVS and VM, IBM VisualAge for COBOL for OS/2, IBM COBOL Set for AIX Language Reference*, SC26-4769

## Related publications

### | **LDAP**

| For information about LDAP, see the following redbook:

| *Understanding LDAP*, SG24-4986

---

## Summary of Changes

Changes for this edition are marked with the | character in the left-hand margin.

---

### Changes for this edition (SC33-0807-09)

This edition of *MQSeries Application Programming Guide* applies to these new versions and releases of MQSeries products:

- MQSeries for AIX V5.1
- MQSeries for AS/400 V4R2M1
- MQSeries for HP-UX V5.1
- MQSeries for OS/2 Warp V5.1
- MQSeries for OS/390 V2.1
- MQSeries for Sun Solaris V5.1
- MQSeries for VSE/ESA V2.1
- MQSeries for Windows NT V5.1

Major new function supplied with each of these MQSeries products is summarized here.

### MQSeries for OS/390 V2.1

MQSeries for OS/390 V2.1 is a new product for the OS/390 platform that offers functional enhancements over MQSeries for MVS/ESA V1.2. Those functional enhancements specific to MQSeries for OS/390 are summarized here. As a general rule, other function described in this book as supported by MQSeries for OS/390 is also supported by MQSeries for MVS/ESA V1.2.

#### MQSeries queue manager clusters

MQSeries queue managers can be connected to form a *cluster* of queue managers. Within a cluster, queue managers can make the queues they host available to every other queue manager. Any queue manager can send a message to any other queue manager in the same cluster without the need for explicit channel definitions, remote queue definitions, or transmission queues for each destination. The main benefits of MQSeries clusters are:

- Fewer system administration tasks
- Increased availability
- Workload balancing

Clusters are supported by these MQSeries products:

- MQSeries for AIX V5.1
- MQSeries for HP-UX V5.1
- MQSeries for OS/2 Warp V5.1
- MQSeries for OS/390 V2.1
- MQSeries for Sun Solaris V5.1
- MQSeries for Windows NT V5.1

See the book *MQSeries Queue Manager Clusters*, SC34-5349, for a complete description of this function.

#### OS/390 Automatic Restart Manager (ARM)

If an MQSeries queue manager or channel initiator fails, the OS/390 Automatic Restart Manager (ARM) can restart it automatically on the same OS/390 image.

## Summary of changes

If the OS/390 image itself fails, ARM can restart that image's subsystems and applications automatically on another OS/390 image in the sysplex, provided that the LU 6.2 communication protocol is being used. By removing the need for operator intervention, OS/390 ARM improves the availability of your MQSeries subsystems.

### **OS/390 Resource Recovery Services (RRS)**

MQSeries Batch and TSO applications can participate in two-phase commit protocols with other RRS-enabled products, such as DB2, coordinated by the OS/390 RRS facility.

### **MQSeries Workflow**

MQSeries Workflow allows applications on various network clients to perform business functions through System/390 by driving one or more CICS, IMS, or MQSeries applications. This is achieved through format, rule, and table definition, rather than through application programming.

### **Support for C++**

MQSeries for OS/390 V2.1 applications can be written in C++.

### **Euro support**

MQSeries supports new and changed code pages that use the euro currency symbol. Details of code pages that include the euro symbol are provided in the *MQSeries Application Programming Reference* book.

## MQSeries V5.1

The MQSeries Version 5 Release 1 products are:

- MQSeries for AIX V5.1
- MQSeries for HP-UX V5.1
- MQSeries for OS/2 Warp V5.1
- MQSeries for Sun Solaris V5.1
- MQSeries for Windows NT V5.1

The following new function is provided in all of the V5.1 products:

### **MQSeries queue manager clusters**

MQSeries queue managers can be connected to form a *cluster* of queue managers. Within a cluster, queue managers can make the queues they host available to every other queue manager. Any queue manager can send a message to any other queue manager in the same cluster without the need for explicit channel definitions, remote queue definitions, or transmission queues for each destination. The main benefits of MQSeries clusters are:

- Fewer system administration tasks
- Increased availability
- Workload balancing

Clusters are supported by these MQSeries products:

- MQSeries for AIX V5.1
- MQSeries for HP-UX V5.1
- MQSeries for OS/2 Warp V5.1
- MQSeries for OS/390 V2.1
- MQSeries for Sun Solaris V5.1
- MQSeries for Windows NT V5.1

See the book *MQSeries Queue Manager Clusters*, SC34-5349, for a complete description of this function.

**MQSeries Administration Interface (MQAI)**

The MQSeries Administration Interface is an MQSeries programming interface that simplifies manipulation of MQSeries PCF messages for administrative tasks. It is described in a new book, *MQSeries Administration Interface Programming Guide and Reference*, SC34-5390.

**Support for Windows 98 clients**

A Windows 98 client can connect to any MQSeries V5.1 server.

**Message queue size**

A message queue can be up to 2 GB.

**Controlled, synchronous shutdown of a queue manager**

A new option has been added to the **endmqm** command to allow controlled, synchronous shutdown of a queue manager.

**Java support**

The MQSeries Client for Java and MQSeries Bindings for Java are provided with all MQSeries V5.1 products. The client, bindings, and common files have been packaged into .jar files for ease of installation.

**Euro support**

MQSeries supports new and changed code pages that use the euro currency symbol. Details of code pages that include the euro symbol are provided in the *MQSeries Application Programming Reference* book.

**Conversion of the EBCDIC new-line character**

You can control the conversion of EBCDIC new-line characters to ensure that data transmitted from EBCDIC systems to ASCII systems and back to EBCDIC is unaltered by the ASCII conversion.

**Client connections by way of MQCONN**

A client application can specify the definition of the client-connection channel at run time in the MQCNO structure of the MQCONN call.

**Additional new function in MQSeries for AIX V5.1**

- The UDP transport protocol is supported.
- Sybase databases can participate in global units of work.
- Multithreaded channels are supported.

**Additional new function in MQSeries for HP-UX V5.1**

- MQSeries for HP-UX V5.1 runs on both HP-UX V10.20 and HP-UX V11.0.
- Multithreaded channels are supported.
- Both HP-UX kernel threads and DCE threads are supported.

**Additional new function in MQSeries for OS/2 Warp V5.1**

OS/2 high memory support is provided.

**Additional new function in MQSeries for Sun Solaris V5.1**

- MQSeries for Sun Solaris V5.1 runs on both Sun Solaris V2.6 and Sun Solaris 7.
- Sybase databases can participate in global units of work.
- Multithreaded channels are supported.

### Additional new function in MQSeries for Windows NT V5.1

MQSeries for Windows NT V5.1 is part of the IBM Enterprise Suite for Windows NT. New function in this release includes:

- Close integration with Microsoft® Windows NT Version 4.0, including exploitation of extra function provided by additional Microsoft offerings. The main highlights are:
  - Graphical tools and applications for managing, controlling, and exploring MQSeries:
    - MQSeries Explorer—a snap-in for the Microsoft management console (MMC) that allows you to query, change, and create the local, remote, and cluster objects across an MQSeries network.
    - MQSeries Services—an MMC snap-in that controls the operation of MQSeries components, either locally or remotely within the Windows NT domain. It monitors the operation of MQSeries servers and provides extensive error detection and recovery functions.
    - MQSeries API Exerciser—a graphical application for exploring the messaging and queuing programming functions that MQSeries provides. It can also be used in conjunction with the MQSeries Explorer to gain a deeper understanding of the effects of MQSeries operations on objects and messages.
    - MQSeries Postcard—a sample application that can be used to verify an MQSeries installation, for either local or remote messaging.
  - Support for the following features of Windows NT has been added:
    - Windows NT performance monitor—used to access and display MQSeries information, such as the current depth of a queue and the rate at which message data is put onto and taken off queues.
    - ActiveDirectory—programmable access to MQSeries objects is available through the Active Directory Service Interfaces (ADSI).
    - Windows NT user IDs—previous MQSeries restrictions on the validity of Windows NT user IDs have been removed. All valid Windows NT user IDs are now valid identifiers for MQSeries operations. MQSeries uses the associated Windows NT Security Identifier (SID) and the Security Account Manager (SAM). The SID allows the MQSeries Object Authority Manager (OAM) to identify the specific user for an authorization request.
    - Windows NT registry—now used to hold all configuration and related data. The contents of any configuration (.INI) files from previous MQSeries installations of MQSeries for Windows NT products are migrated into the registry; the .INI files are then deleted.
    - A set of Component Object Model (COM) classes, which allow ActiveX applications to access the MQSeries Message Queue Interface (MQI) and the MQSeries Administration Interface (MQAI).
  - An online Quick Tour of the product concepts and functions.
  - An online Information Center that gives you quick access to task help information, reference information, and Web-based online books and home pages.

- Simplified installation of MQSeries for Windows NT, with default options and automatic configuration.
- Support for web-based administration of an MQSeries network, which provides a simplified way of using the MQSC commands and scripts and allows you to create powerful macros for standard administration tasks.
- Support for MQSeries LotusScript Extension (MQLSX), which allows Lotus Notes applications that are written in LotusScript to communicate with applications that run in non-Notes environments.
- Support for Microsoft Visual Basic® for Windows Version 5.0.
- Performance improvements over the MQSeries for Windows NT Version 5.0 product.
- Information and examples on how MQSeries applications can interface with and exploit the lightweight directory access protocol (LDAP) directories.
- Support for Sybase participation in global units of work.

## MQSeries for VSE/ESA V2.1

MQSeries for VSE/ESA joins the MQSeries Level 2 products. New function in Version 2 Release 1 of MQSeries for VSE/ESA includes:

- Transmission Control Protocol/Internet Protocol (TCP/IP) is supported.
- MQSeries clients can connect to the MQSeries for VSE/ESA server using the TCP/IP protocol. (Note, however, that there is no MQSeries for VSE/ESA client.)
- Messages may be up to 4 MB in size.
- A user-selected, coded character set ID (CCSID) can be specified for all messages written locally.
- Messages sent to remote, non-VSE/ESA systems can be flagged as nonpersistent.
- Confirmation-on-delivery (COD) and confirmation-on-arrival (COA) messages are supported.
- A message priority, in the range 0 through 9, can be specified on MQPUT and MQPUT1 calls.
- Automated reorganization of queue storage is supported.
- Messages can be sent and received in batches of a user-specified size.
- Support has been added for the C and PL/I application-programming languages. Copy books, macros, and include files are provided for each language.
- Messages can be retrieved from queues by message identifier (*MsgID*) and correlation identifier (*CorrelID*).
- Message Channel Agents (MCAs) record more diagnostic information in the SYSTEM.LOG when communications failures occur.

### MQSeries for AS/400 V4R2M1

New function in MQSeries for AS/400 V4R2M1 includes:

- Support for the MQSeries dead-letter queue handler
- Improvements to installation and migration procedures

---

### Changes for the ninth edition (SC33-0807-08)

Changes for edition number SC33-0807-08 include:

- A new release of:
  - MQSeries for AS/400 V4R2
- Inclusion of a new MQSeries product:
  - MQSeries for Tandem NonStop Kernel V2.2

---

### Changes for the eighth edition (SC33-0807-07)

Changes for edition number SC33-0807-07 include:

- New releases of the following MQSeries products:
  - MQSeries for AIX V5.0
  - MQSeries for HP-UX V5.0
  - MQSeries for OS/2 Warp V5.0
  - MQSeries for Sun Solaris V5.0
  - MQSeries for Windows NT V5.0
  - MQSeries for OS/400 V3R7
  - MQSeries for MVS/ESA V1.2
- Inclusion of new MQSeries products:
  - MQSeries for Digital OpenVMS V2.2
  - MQSeries for Windows V2.0
  - MQSeries for Windows V2.1
- Support of programming languages:
  - C++
  - PL/I on MQSeries for AIX, OS/2 Warp, and Windows NT
- New function:
  - Distribution lists
  - Handling large messages
  - External resource managers
  - Report options for application acknowledgement
  - Indexed queues (MQSeries for OS/390 only)
- Enhancement of existing function:
  - Change in triggering rules
  - Lotus Notes® link with AIX
  - Support for Encina by MQSeries on Windows NT
  - Support for signaling on MQSeries for Windows V2.1

---

# Part 1. Designing applications that use MQSeries

<b>Chapter 1. Introduction to message queuing</b>	3
What is message queuing?	3
What is a message?	4
Message descriptor	4
Message channel agent	4
What is a message queue?	4
What is a queue manager?	5
What is a cluster?	6
What is an MQSeries client?	6
Main features of message queuing	7
MQSeries clients and servers	10
Benefits of message queuing to the application designer and developer	10
What can you do with MQSeries products?	10
MQSeries for OS/390	10
MQSeries for non-OS/390 platforms	12
<b>Chapter 2. Overview of application design</b>	13
Planning	13
Using MQSeries objects	14
Designing your messages	15
MQSeries techniques	16
Waiting for messages	16
Correlating replies	16
Setting and using context information	16
Starting MQSeries programs automatically	17
Generating MQSeries reports	17
Clusters and message affinities	17
Application programming	18
Call interface	18
Design for performance - hints and tips	18
Programming platforms	19
Applications for more than one platform	21
Testing MQSeries applications	21
<b>Chapter 3. MQSeries messages</b>	23
Message descriptor	23
Types of message	24
Datagrams	24
Request messages	24
Reply messages	25
Report messages	25
Reports and segmented messages	27
Format of message control information and message data	29
Format of message control information	30
Format of message data	30
Application data conversion	31
Message priorities	32
Message groups	33
Message persistence	34
Selecting messages from queues	35

Messages that fail to be delivered	35
Messages that are backed out	35
Reply-to queue and queue manager	36
Message context	37
Identity context	37
Origin context	38
<b>Chapter 4. MQSeries objects</b>	<b>39</b>
Queue managers	39
Attributes of queue managers	39
Queue managers and workload management	40
Queues	40
Types of queue	41
Attributes of queues	43
Remote queues	43
Alias queues	44
Model queues	45
Dynamic queues	45
Transmission queues	47
Initiation queues	47
Dead-letter (undelivered-message) queues	48
System command queues	48
System default queues	48
Namelist	48
Process definitions	49
Channels	49
Storage classes	49
Rules for naming MQSeries objects	49
Queue names	50
Process definition and namelist names	51
Channel names	51
Reserved object names	51
<b>Chapter 5. Handling program errors</b>	<b>53</b>
Locally determined errors	53
Failure of an MQI call	53
System interruptions	54
Messages containing incorrect data	55
Using report messages for problem determination	55
Remotely determined errors	56
Problems delivering a message	57
Using the dead-letter (undelivered-message) queue	57

---

## Chapter 1. Introduction to message queuing

The MQSeries products enable programs to communicate with one another across a network of unlike components – processors, operating systems, subsystems and communication protocols – using a consistent application programming interface.

Applications designed and written using this interface are known as *message queuing* applications, as they use the *messaging* and *queuing* style:

**Messaging**      Programs communicate by sending each other data in messages rather than calling each other directly.

**Queuing**        Messages are placed on queues in storage, allowing programs to run independently of each other, at different speeds and times, in different locations, and without having a logical connection between them.

---

### What is message queuing?

*Message queuing* has been used in data processing for many years. It is most commonly used today in electronic mail. Without queuing, sending an electronic message over long distances requires every node on the route to be available for forwarding messages, and the addressees to be logged on and conscious of the fact that you are trying to send them a message. In a queuing system, messages are stored at intermediate nodes until the system is ready to forward them. At their final destination they are stored in an electronic mailbox until the addressee is ready to read them.

Even so, many complex business transactions are processed today without queuing. In a large network, the system might be maintaining many thousands of connections in a ready-to-use state. If one part of the system suffers a problem, many parts of the system become unusable.

You can think of message queuing as being electronic mail for programs. In a message queuing environment, each program from the set that makes up an application suite is designed to perform a well-defined, self-contained function in response to a specific request. To communicate with another program, a program must put a message on a predefined queue. The other program retrieves the message from the queue, and processes the requests and information contained in the message. So message queuing is a style of program-to-program communication.

Queuing is the mechanism by which messages are held until an application is ready to process them. Queuing allows you to:

- Communicate between programs (which may each be running in different environments) without having to write the communication code.
- Select the order in which a program processes messages.
- Balance loads on a system by arranging for more than one program to service a queue when the number of messages exceeds a threshold.
- Increase the availability of your applications by arranging for an alternative system to service the queues if your primary system is unavailable.

### What is a message?

In message queuing, a *message* is simply a collection of data sent by one program and intended for another program.

MQSeries defines four types of message:

<b>Datagram</b>	A simple message for which no reply is expected
<b>Request</b>	A message for which a reply is expected
<b>Reply</b>	A reply to a request message
<b>Report</b>	A message that describes an event such as the occurrence of an error

See “Types of message” on page 24 for more information about these messages.

### Message descriptor

An MQSeries message consists of control information and application data. The control information is defined in a *message descriptor* structure (MQMD) and contains such things as:

- The type of the message
- An identifier for the message
- The priority for delivery of the message

The structure and content of the application data is determined by the participating programs, not by MQSeries.

### Message channel agent

A message channel agent moves messages from one queue manager to another. References are made to them in this book when dealing with report messages and you will need to consider them when designing your application. See “Writing your own message channel agents” and Chapter 35, “Channel-exit programs” in the *MQSeries Intercommunication* book for more information.

---

### What is a message queue?

A *message queue*, known simply as a queue, is a named destination to which messages can be sent. Messages accumulate on queues until they are retrieved by programs that service those queues.

Queues reside in, and are managed by, a queue manager (see “What is a queue manager?” on page 5). The physical nature of a queue depends on the operating system on which the queue manager is running. A queue can either be a volatile buffer area in the memory of a computer, or a data set on a permanent storage device (such as a disk). The physical management of queues is the responsibility of the queue manager and is not made apparent to the participating application programs.

Programs access queues only through the external services of the queue manager. They can open a queue, put messages on it, get messages from it, and close the queue. They can also set, and inquire about, the attributes of queues.

---

## What is a queue manager?

A *queue manager* is a system program that provides queuing services to applications. It provides an application programming interface so that programs can put messages on, and get messages from, queues. A queue manager provides additional functions so that administrators can create new queues, alter the properties of existing queues, and control the operation of the queue manager.

For MQSeries message queuing services to be available on a system, there must be a queue manager running:

- On OS/390, OS/2, Windows NT, Digital OpenVMS, and UNIX systems, you can have more than one queue manager running on a single system (for example, to separate a test system from a “live” system). To an application, each queue manager is identified by a *connection handle (Hconn)*.
- On the AS/400, VSE/ESA, and Windows platforms, you can have only one queue manager running on a single system. *Hconn* is still used, but only to give compatibility with other MQSeries platforms.

Many different applications can make use of the queue manager’s services at the same time and these applications can be entirely unrelated. For a program to use the services of a queue manager, it must establish a connection to that queue manager.

For applications to be able to send messages to applications that are connected to other queue managers, the queue managers must be able to communicate among themselves. MQSeries implements a *store-and-forward* protocol to ensure the safe delivery of messages between such applications.

### What is a cluster?

A *cluster* is a network of queue managers that are logically associated in some way. Clustering is available to queue managers on the following platforms:

- MQSeries for AIX V5.1
- MQSeries for HP-UX V5.1
- MQSeries for OS/2 Warp V5.1
- MQSeries for OS/390 V2.1
- MQSeries for Sun Solaris V5.1
- MQSeries for Windows NT V5.1

In a traditional MQSeries network using distributed queuing, every queue manager is independent. If one queue manager needs to send messages to another it must have defined a transmission queue, a channel to the remote queue manager, and a remote queue definition for every queue to which it wants to send messages.

If you group queue managers in a cluster, the queue managers can make the queues that they host available to every other queue manager in the cluster. Then, assuming you have the necessary network infrastructure in place, any queue manager can send a message to any other queue manager in the same cluster without the need for explicit channel definitions, remote queue definitions, or transmission queues.

There are two quite different reasons for using clusters: to reduce system administration and to improve availability and workload balancing.

As soon as you establish even the smallest cluster you will benefit from simplified system administration. Queue managers that are part of a cluster need fewer definitions and so the risk of making an error in your definitions is reduced.

For details of workload balancing see “Queue managers and workload management” on page 40 and Chapter 5, “Using clusters for workload management” in the *MQSeries Queue Manager Clusters* book.

For details of all aspects of clustering, see the *MQSeries Queue Manager Clusters* book, SC34-5349.

---

### What is an MQSeries client?

An *MQSeries client* is an independently installable component of an MQSeries product. It allows you to run MQSeries applications, by means of a communications protocol, to interact with one or more MQI servers on other platforms and to connect to their queue managers.

For full details on how to install the MQSeries client component and use the environment, see Chapter 3, “Installing MQSeries client components from Version 5.1 products” or Chapter 4, “Installing MQSeries clients with non-Version 5 products” in the *MQSeries Clients* book.

---

## Main features of message queuing

The main features of applications that use message queuing techniques are:

- There are no direct connections between programs.
- Communication between programs can be time-independent.
- Work can be carried out by small, self-contained programs.
- Communication can be driven by events.
- Applications can assign a priority to a message.
- Security.
- Syncpoint support.
- Recovery support.

### No direct connections between programs

Message queuing is a technique for indirect program-to-program communication. It can be used within any application where programs communicate with each other. Communication occurs by one program putting messages on a queue (owned by a queue manager) and another program getting the messages from the queue.

Programs can get messages that were put on a queue by other programs. The other programs can be connected to the same queue manager as the receiving program, or to another queue manager. This other queue manager might be on another system, a different computer system, or even within a different business or enterprise.

There are no physical connections between programs that communicate using message queues. A program sends messages to a queue owned by a queue manager, and another program retrieves messages from the queue (see Figure 1 on page 8).




Figure 1. Message queuing compared with traditional communication

As with electronic mail, the individual messages that may be part of a transaction, travel through a network on a store-and-forward basis. If a link between nodes fails, the message is kept until the link is restored, or the operator or program redirects the message.

The mechanism by which a message moves from queue to queue is hidden from the programs. Therefore the programs are simpler.

**Time-independent communication**

Programs requesting others to do work do not have to wait for the reply to a request. They can do other work, and process the reply either when it arrives or at a later time. When writing a messaging application, you need not know (or be concerned) when a program sends a message, or when the target is able to receive the message. The message is not lost; it is retained by the queue manager until the target is ready to process it. The message stays on the queue until it is removed by a program.

### **Small programs**

Message queuing allows you to exploit the advantages of using small, self-contained programs. Instead of a single, large program performing all the parts of a job sequentially, you can spread the job over several smaller, independent programs. The requesting program sends messages to each of the separate programs, asking them to perform their function; when each program is complete, the results are sent back as one or more messages.

### **Event-driven processing**

Programs can be controlled according to the state of queues. For example, you can arrange for a program to start as soon as a message arrives on a queue, or you can specify that the program does not start until there are, for example, 10 messages above a certain priority on the queue, or 10 messages of any priority on the queue.

### **Message priority**

A program can assign a priority to a message when it puts the message on a queue. This determines the position in the queue at which the new message is added.

Programs can get messages from a queue either in the order in which the messages appear in the queue, or by getting a specific message. (A program may want to get a specific message if it is looking for the reply to a request it sent earlier.)

### **Security**

Authorization checks are carried out on each resource, using the tables that are set up and maintained by the MQSeries administrator.

- RACF® or other external security managers may be used within MQSeries for OS/390.
- Native OS/400 is used within MQSeries for AS/400.
- There is no authorization checking within MQSeries for OS/2 Warp; however, an interface is provided to enable you to build and install your own.
- Within MQSeries on UNIX systems, Digital OpenVMS, Tandem NonStop Kernel, and Windows NT, a security manager, the Object Authority Manager (OAM), is provided as an installable service. By default, the OAM is active.
- On VSE/ESA, security is provided by CICS.

### **Syncpoint support**

The synchronization of the start and end of units of work is fully supported as an option on each MQGET/MQPUT, allowing the results of the call to be committed or rolled back. Syncpoint support operates either internally or externally to MQSeries depending on the form of syncpoint coordination selected for the application.

### **Recovery support**

For recovery to be possible, all persistent MQSeries updates are logged. Hence, in the event that recovery is necessary, all persistent messages will be restored, all in-flight transactions will be rolled back and any syncpoint commit and backouts will be handled in the normal way of the syncpoint manager in control. For more information on persistent messages, see "Message persistence" on page 34.

### MQSeries clients and servers

A server application will not have to be changed to be able to support additional MQSeries clients on new platforms.

Similarly, the MQSeries client will, without change, be able to function with additional types of server.

---

### Benefits of message queuing to the application designer and developer

Some of the benefits of message queuing are:

- You can design applications using small programs that you can share between many applications.
- You can quickly build new applications by reusing these building blocks.
- Applications written to use message queuing techniques are not affected by changes in the way queue managers work.
- You do not need to use any communication protocols. The queue manager deals with all aspects of communication for you.
- Programs that receive messages need not be running at the time messages are sent to them. The messages are retained on queues.

Designers can reduce the cost of their applications because development is faster, fewer developers are needed, and demands on programming skill are lower than those for applications that do not use message queuing.

---

### What can you do with MQSeries products?

MQSeries products are queue managers and application enablers. They support the IBM Message Queue Interface (MQI) through which programs can put messages on a queue and get messages from a queue.

### MQSeries for OS/390

With MQSeries for OS/390 you can write applications that:

- Use message queuing within CICS or IMS.
- Send messages between batch, CICS, and IMS applications, selecting the most appropriate environment for each function.
- Send messages to applications that run on other MQSeries platforms.
- Process several messages together as a single unit of work that can be committed or backed out.
- Send messages to and interact with IMS applications by means of the IMS bridge.
- Participate in units of work coordinated by RRS.

See Appendix A, "Language compilers and assemblers" on page 453 for details of the supported programming languages.

Each environment within OS/390 has its own characteristics, advantages, and disadvantages. The advantage of MQSeries for OS/390 is that applications are not tied to any one environment, but can be distributed to take advantage of the benefits of each environment. For example, you can develop end-user interfaces using TSO or CICS, you can run processing-intensive modules in OS/390 batch, and you can run database applications in IMS or CICS. In all cases, the various parts of the application can communicate using messages and queues.

Designers of MQSeries applications must be aware of the differences and limitations imposed by these environments. For example:

- MQSeries provides facilities that allow intercommunication between queue managers (this is known as *distributed queuing*).
- Methods of committing and backing out changes differ between the batch and CICS environments.
- MQSeries for OS/390 provides support in the IMS environment for online message processing programs (MPPs), interactive fast path programs (IFPs), and batch message processing programs (BMPs). If you are writing batch DL/I programs, follow the guidance given in this book for OS/390 batch programs.
- Although multiple instances of MQSeries for OS/390 can exist on a single OS/390 system, a CICS region can connect to only one queue manager at a time. However, more than one CICS region can be connected to the same queue manager. In the IMS and OS/390 batch environments, programs can connect to more than one queue manager.

The differences between the supported environments, and their limitations, are discussed further in Chapter 15, "Using and writing applications on MQSeries for OS/390" on page 219.

### MQSeries for non-OS/390 platforms

With MQSeries for non-OS/390 platforms you can write applications that:

- Send messages to other applications running under the same operating systems. The applications can be on either the same or another system.
- Send messages to applications that run on other MQSeries platforms.
- Use message queuing from within CICS Transaction Server for OS/2, CICS for AS/400, TXSeries for AIX, TXSeries for HP-UX, CICS for Siemens Nixdorf SINIX, TXSeries for Sun Solaris, and TXSeries for Windows NT, DOS, and Windows 3.1 applications.
- Use message queuing from within Encina for AIX, HP-UX, SINIX, Sun Solaris, and Windows NT.
- Use message queuing from within Sybase for AIX, Sun Solaris, and Windows NT.
- Use message queuing from within Tuxedo for AIX, AT&T, HP-UX, SINIX and DC/OSx, Sun Solaris, and Windows NT.
- Process several messages together as a single unit of work that can be committed or backed out.
- Run from a full MQSeries environment, or run from an MQSeries client environment on the following platforms:
  - Digital OpenVMS
  - DOS
  - OS/2
  - UNIX systems
  - VM/ESA®
  - Windows NT
  - Windows 3.1
  - Windows 95 and Windows 98

See Appendix A, “Language compilers and assemblers” on page 453 for details of the supported programming languages.

---

## Chapter 2. Overview of application design

This chapter discusses how to design MQSeries applications. It introduces:

- The decisions you should take during the design process
- The features that MQSeries provides for you to work with
- The programming techniques that you should consider
- The Message Queue Interface (MQI)

These subjects are discussed in greater detail in the remaining chapters of this book.

---

### Planning

When you have decided how your applications are able to take advantage of the platforms and environments available to you, you need to decide how to use the features offered by MQSeries. Some of the key aspects are:

#### What types of queue should you use?

Do you want to create a queue each time you need one, or do you want to use queues that have already been set up? Do you want to delete a queue when you have finished using it, or is it going to be used again? Do you want to use alias queues for application independence? To see what types of queues are supported, refer to “Queues” on page 40.

#### What types of message should you use?

You may want to use datagrams for simple messages, but request messages (for which you expect replies) for other situations. You may want to assign different priorities to some of your messages.

#### How can you control your MQSeries programs?

You may want to start some programs automatically or make programs wait until a particular message arrives on a queue, (using the MQSeries *triggering* feature, see Chapter 14, “Starting MQSeries applications using triggers” on page 197). Alternatively, you may want to start up another instance of an application when the messages on a queue are not getting processed fast enough (using the MQSeries *instrumentation events* feature as described in Chapter 1, “Using instrumentation events to monitor queue managers” in the *MQSeries Programmable System Management* book).

#### Will your application run on an MQSeries client?

The full MQI is supported in the client environment and this enables almost any MQSeries application to be relinked to run on an MQSeries client. Link the application on the MQSeries client to the MQIC library, rather than to the MQI library. The exceptions are:

- An application that needs syncpoint coordination with other resource managers.
- Get(signal) on OS/390 is not supported.

**Note:** An application running on an MQSeries client may connect to more than one queue manager concurrently, or use a queue manager name with an asterisk (\*) on an MQCONN or MQCONNX call. The application will have to be changed if you want to link to the queue

## Using MQSeries objects

manager libraries instead of the client libraries, as this function will not be available.

See the *MQSeries Clients* book for more information.

### How can you secure your data and maintain its integrity?

You can use the context information that is passed with a message to test that the message has been sent from an acceptable source. You can use the syncpointing facilities provided by MQSeries or your operating system to ensure that your data remains consistent with other resources (see Chapter 13, “Committing and backing out units of work” on page 183 for further details). You can use the *persistence* feature of MQSeries messages to assure the delivery of important messages.

### How should you handle exceptions and errors?

You need to consider how to process messages that cannot be delivered, and how to resolve error situations that are reported to you by the queue manager. For some reports, you must set report options on MQPUT.

The remainder of this chapter introduces the features and techniques that MQSeries provides to help you answer questions like these.

---

## Using MQSeries objects

The MQI uses the following types of object:

- Queue managers
- Queues
- Namelists (MQSeries for OS/390 and MQSeries Version 5.1 products only)
- Process definitions
- Channels
- Storage classes (OS/390 only)

These objects are discussed in Chapter 4, “MQSeries objects” on page 39.

Each object is identified by an *object descriptor* (MQOD), which you use when you write MQSeries programs. However, with the exception of dynamic queues, these objects must be defined to the queue manager before you can work with them.

You define objects using:

- The PCF commands described in Chapter 7, “Using Programmable Command Formats” in the *MQSeries Programmable System Management* book (not on OS/390 or VSE/ESA)
- The MQSC commands described in Chapter 2, “The MQSeries commands” in the *MQSeries Command Reference* manual (not on VSE/ESA)
- The MQSeries for OS/390 operations and control panels, described in the *MQSeries for OS/390 System Management Guide*
- The MQSeries Explorer or MQSeries Web Administration (Windows NT only)
- The MQSeries Master Terminal (MQMT) transaction (VSE/ESA only)

You can also display or alter the attributes of objects, or delete the objects.

Alternatively, for sequences of MQSeries for OS/390 commands that you use regularly, you can write administration programs that create messages containing commands and that put these messages on the system-command input queue. The queue manager processes the messages on this queue in the same way that it processes commands entered from the command line or from the operations and control panels. This technique is described in the *MQSeries for OS/390 System Management Guide*, and demonstrated in the Mail Manager sample application delivered with MQSeries for OS/390. For a description of this sample, see Chapter 32, “Sample programs for MQSeries for OS/390” on page 395.

For sequences of MQSeries for AS/400 commands you use regularly, you can write CL programs that contain the commands, as demonstrated in the CL sample program (AMQSDEF4) delivered with MQSeries for AS/400. For a description of this sample, see the *MQSeries for AS/400 Administration Guide*.

For sequences of MQSeries commands on OS/2, Windows NT, and UNIX systems, you can use the MQSC facility to run a series of commands held in a file. For information on how to use this facility, see the *MQSeries Command Reference* manual.

---

## Designing your messages

You create a message when you use an MQI call to put the message on a queue. As input to the call, you supply some control information in a *message descriptor* (MQMD) and the data that you want to send to another program. But at the design stage, you need to consider the following questions, because they affect the way you create your messages:

### What type of message should I use?

Are you designing a simple application in which you can send a message, then take no further action? Or are you asking for a reply to a question? If you are asking a question, you may include in the message descriptor the name of the queue on which you want to receive the reply.

Do you want your request and reply messages to be synchronous? This implies that you set a timeout period for the reply to answer your request, and if you do not receive the reply within that period, it is treated as an error.

Or would you prefer to work asynchronously, so that your processes do not have to depend upon the occurrence of specific events, such as common timing signals?

Another consideration is whether you have all your messages inside a unit of work.

### Should I assign different priorities to some of the messages I create?

You can assign a priority value to each message, and define the queue so that it maintains its messages in order of their priority. If you do this, when another program retrieves a message from the queue, it always gets the message with the highest priority. If the queue does not maintain its messages in priority order, a program that retrieves messages from the queue will retrieve them in the order in which they were added to the queue.

Programs can also select a message using the identifier that the queue manager assigned when the message was put on the queue. Alternatively, you can generate your own identifiers for each of your messages.

### **Will my messages be discarded when the queue manager restarts?**

The queue manager preserves all persistent messages, recovering them when necessary from the MQSeries log files, when it is restarted. Nonpersistent messages and temporary dynamic queues are not preserved. Any messages that you do not want discarded must be defined as persistent at the time they are created. When writing an application for MQSeries for OS/2 Warp, MQSeries for Windows NT, or MQSeries on UNIX systems, make sure that you know how your system has been set up in respect of log file allocation to reduce the risk of designing an application that will run to the log file limits.

### **Do I want to give information about myself to the recipient of my messages?**

Normally, the queue manager sets the user ID, but suitably authorized applications can also set this field, so that you can include your own user ID and other information that the receiving program can use for accounting or security purposes.

---

## MQSeries techniques

For a simple MQSeries application, you need to decide which MQSeries objects to use in your application, and which types of message you want to use. For a more advanced application, you may want to use some of the techniques introduced in the following sections.

### **Waiting for messages**

A program that is serving a queue can await messages by:

- Making periodic calls on the queue to see whether a message has arrived (*polling*).
- Waiting until either a message arrives, or a specified time interval expires (see “Waiting for messages” on page 146).
- Setting a signal so that the program is informed when a message arrives (MQSeries for OS/390 and MQSeries for Windows V2.1 only). For information about this, see “Signaling” on page 147.

### **Correlating replies**

In MQSeries applications, when a program receives a message that asks it to do some work, the program usually sends one or more reply messages to the requester. To help the requester to associate these replies with its original request, an application can set a *correlation identifier* field in the descriptor of each message. Programs should copy the message identifier of the request message into the correlation identifier field of their reply messages.

### **Setting and using context information**

*Context information* is used for associating messages with the user who generated them, and for identifying the application that generated the message. Such information is useful for security, accounting, auditing, and problem determination.

When you create a message, you can specify an option that requests that the queue manager associates default context information with your message.

For more information on using and setting context information, see “Message context” on page 37.

## Starting MQSeries programs automatically

MQSeries *triggering* enables a program to be started automatically when messages arrive on a queue. You can set trigger conditions on a queue so that a program is started to process that queue:

- Every time a message arrives on the queue
- When the first message arrives on the queue
- When the number of messages on the queue reaches a predefined number

For more information on triggering, see Chapter 14, “Starting MQSeries applications using triggers” on page 197.

**Note:** Triggering is just one way of starting a program automatically. For example, you can start a program automatically on a timer using non-MQSeries facilities.

## Generating MQSeries reports

You can request the following reports within an application:

- Exception reports
- Expiry reports
- Confirm-on-arrival (COA) reports
- Confirm-on-delivery (COD) reports
- Positive action notification (PAN) reports
- Negative action notification (NAN) reports

These are described in “Report messages” on page 25.

## Clusters and message affinities

Before starting to use clusters with multiple definitions for the same queue, you must examine your applications to see whether there are any that require an exchange of related messages. Within a cluster, a message may be routed to *any* queue manager that hosts an instance of the appropriate queue. Therefore, the logic of applications with message affinities may be upset.

For example, you may have two applications that rely on a series of messages flowing between them in the form of questions and answers. It may be important that all the questions are sent to the same queue manager and that all the answers are sent back to the other queue manager. In this situation, it is important that the workload management routine does not send the messages to any queue manager that just happens to host an instance of the appropriate queue.

You should attempt, where possible, to remove the affinities. Removing message affinities improves the availability and scalability of applications.

For more information see “Programming considerations” in the *MQSeries Queue Manager Clusters* book.

### Application programming

MQSeries supports the IBM Message Queue Interface (MQI). The MQI includes a set of calls with which you can send and receive messages, and manipulate MQSeries objects.

### Call interface

The MQI calls allow you to:

- Connect programs to, and disconnect programs from, a queue manager
- Open and close objects (such as queues, queue managers, namelists, and processes)
- Put messages on queues
- Receive messages from a queue, or browse them (leaving them on the queue)
- Inquire about the attributes (or properties) of MQSeries objects, and set some of the attributes of queues
- Commit and back out changes made within a unit of work, in environments where there is no natural syncpoint support, for example, OS/2 and UNIX systems
- Coordinate queue manager updates and updates made by other resource managers

The MQI provides *structures* (groups of fields) with which you supply input to, and get output from, the calls. It also provides a large set of named constants to help you supply options in the parameters of the calls. The definitions of the calls, structures, and named constants are supplied in data definition files for each of the supported programming languages. Also, default values are set within the MQI calls.

### Design for performance - hints and tips

Here are a few ideas to help you design efficient applications:

- Design your application so that processing goes on in parallel with a user's thinking time:
  - Display a panel and allow the user to start typing while the application is still initializing.
  - Don't be afraid to get the data you need in parallel from different servers.
- Keep connections and queues open if you are going to reuse them instead of repeatedly opening and closing, connecting and disconnecting.

**Note:** However, a server application which is putting only one message should use MQPUT1.
- Keep your messages within a unit of work, so that they can be committed or backed out simultaneously.
- Use the nonpersistent option for messages that do not need to be recoverable.

## Programming platforms

### MQSeries for OS/390

MQSeries for OS/390 operates under OS/390 Version 2.4 and subsequent compatible releases. You can run MQSeries for OS/390 programs in the CICS Transaction Server for OS/390, CICS for MVS/ESA, IMS/ESA, and OS/390 environments. See Appendix A, “Language compilers and assemblers” on page 453 for details of the programming languages supported by MQSeries for OS/390.

### UNIX systems

MQSeries for AIX operates under AIX Version 4.2, Version 4.3.x, and subsequent compatible releases. You can run MQSeries for AIX programs from within CICS for AIX, TXSeries for AIX, Encina for AIX, and Tuxedo for AIX. Applications using threads are supported by MQSeries for AIX.

MQSeries for AT&T GIS UNIX operates under AT&T GIS UNIX Version 3<sup>2</sup> and subsequent compatible releases. You can run MQSeries for AT&T GIS UNIX programs from within Tuxedo for AT&T.

MQSeries for Digital OpenVMS operates under VMS Version 6.2 and VMS Version 7.1.

MQSeries for HP-UX operates under HP-UX Version 10.20 and Version 11.0. You can run MQSeries for HP-UX programs from within TXSeries, Encina, and Tuxedo for HP-UX. Applications using threads are supported by MQSeries for HP-UX.

MQSeries for SINIX and DC/OSx operates under SINIX and DC/OSx Version 2.1 and subsequent compatible releases. You can run MQSeries for SINIX and DC/OSx programs from within CICS for Siemens Nixdorf SINIX, and Tuxedo for SINIX and DC/OSx. You can also run MQSeries for SINIX programs from within Encina for SINIX.

MQSeries for Sun Solaris operates under Sun Solaris Version 2.6 (with patches 105210-13 and 105568-10), Version 7, and subsequent compatible releases. You can run MQSeries for Sun Solaris programs from within CICS, TXSeries, Encina, and Tuxedo for Sun Solaris. Applications using threads are supported by MQSeries for Sun Solaris.

See Appendix A, “Language compilers and assemblers” on page 453 for details of the programming languages supported by MQSeries on UNIX systems.

### MQSeries for AS/400

MQSeries for AS/400 operates under OS/400 Version 4 Release 2 and subsequent compatible releases. You can run MQSeries for AS/400 programs in the CICS for AS/400 environment. See Appendix A, “Language compilers and assemblers” on page 453 for details of the programming languages supported by MQSeries for AS/400.

### MQSeries for OS/2 Warp

MQSeries for OS/2 Warp operates under OS/2 Warp Version 4.0, OS/2 Warp Server V4.0, OS/2 Warp Server Advanced SMP feature, OS/2 Workspace On-Demand, OS/2 e-business Server, and subsequent compatible releases. You can run MQSeries for OS/2 Warp programs in the CICS and CICS Transaction Server environment. See Appendix A, “Language compilers and

<sup>2</sup> This platform has become NCR UNIX SVR4 MP-RAS, R3.0.

assemblers” on page 453 for details of the programming languages supported by MQSeries for OS/2 Warp.

### **MQSeries for Tandem NonStop Kernel**

MQSeries for Tandem NonStop Kernel V2.2 operates under Tandem NSK operating system version D3x, D4x, or G02 with TMF and PATHWAY, and subsequent compatible releases. See Appendix A, “Language compilers and assemblers” on page 453 for details of the programming languages supported by MQSeries for Tandem NonStop Kernel.

### **MQSeries for VSE/ESA**

MQSeries for VSE/ESA V2.1 operates under VSE/ESA V2.3 and subsequent compatible releases, with CICS for VSE/ESA V2.3. See Appendix A, “Language compilers and assemblers” on page 453 for details of the programming languages supported by MQSeries for VSE/ESA.

### **MQSeries for Windows**

MQSeries for Windows V2.0 operates under Windows Version 3.1, Windows 95, and the WIN-OS/2 environment within OS/2. MQSeries for Windows V2.1 operates under Windows 95, Windows 98, and Windows NT V4. See Appendix A, “Language compilers and assemblers” on page 453 for details of the programming languages supported by MQSeries for Windows.

### **MQSeries for Windows NT**

MQSeries for Windows NT operates under Windows NT Version 4.0 (service pack 4) and subsequent compatible releases. You can run MQSeries for Windows NT programs from within CICS, TXSeries, Encina, and Tuxedo for Windows NT. See Appendix A, “Language compilers and assemblers” on page 453 for details of the programming languages supported by MQSeries for Windows NT.

## Applications for more than one platform

Will your application run on more than one platform? Do you have a strategy to move to a different platform from the one you use today? If the answer to either of these questions is “yes,” you need to make sure that you code your programs for platform independence.

If you are using C, make sure that you code in ANSI standard C. Use a standard C library function rather than an equivalent platform-specific function even if the platform-specific function is faster or more efficient. The exception is when efficiency in the code is paramount, when you should code for both situations using `#ifdef`. For example:

```
#ifdef _OS2
    OS/2 specific code
#else
    generic code
#endif
```

When the time comes to move the code to another platform, you can now search the source for `#ifdef` with the platform specific identifiers, in this example `_OS2`, and add or change code as necessary.

It is worth considering keeping portable code in separate source files from the platform-specific code, and using a simple naming convention to split the categories.

---

## Testing MQSeries applications

The application development environment for MQSeries programs is no different from that for any other application, so you can use the same development tools as well as the MQSeries trace facilities. This is most noticeable on OS/2 and UNIX systems where there is a wide selection.

When testing CICS applications with MQSeries for OS/390, you can use the CICS Execution Diagnostic Facility (CEDF). CEDF traps the entry and exit of every MQI call as well as calls to all CICS services. Also, in the CICS environment, you can write an API-crossing exit program to provide diagnostic information before and after every MQI call. For information on how to do this, see Chapter 15, “Using and writing applications on MQSeries for OS/390” on page 219.

When testing AS/400 applications, you can use the Extended Program Model Debugger. To start this, use the STRDBG command.



## Chapter 3. MQSeries messages

An MQSeries message consists of two parts:

- Message descriptor
- Application data

Figure 2 represents a message and shows how it is logically divided into message data and application data.




Figure 2. Representation of a message

The application data carried in an MQSeries message is not changed by a queue manager unless data conversion is carried out on it. Also, MQSeries does not put any restrictions on the content of this data. The length of the data in each message cannot exceed the value of the *MaxMsgLength* attribute of both the queue and queue manager. In MQSeries for AIX, MQSeries for HP-UX, MQSeries for OS/2 Warp, MQSeries for Sun Solaris, and MQSeries for Windows NT, the *MaxMsgLength* defaults to 100 MB (104 857 600 bytes). In MQSeries for AS/400, MQSeries for AT&T GIS UNIX, MQSeries for Digital OpenVMS, MQSeries for OS/390, MQSeries for SINIX and DC/OSx, MQSeries for Tandem NonStop Kernel, MQSeries for VSE/ESA, 16-bit Windows, and 32-bit Windows, the *MaxMsgLength* defaults to 4 MB (4 194 304 bytes). However, you should make your messages slightly shorter than the value of the *MaxMsgLength* attribute in some circumstances (see “The data in your message” on page 111 for more information).

You create a message when you use the MQPUT or MQPUT1 MQI call. As input to these calls, you supply the control information (such as the priority of the message, and the name of a reply queue) and your data. These calls put the message on a queue. See “MQPUT - Put message” and “MQPUT1 - Put one message” in the *MQSeries Application Programming Reference* manual for more information on these calls.

### Message descriptor

You can access message control information using the MQMD structure, which defines the *message descriptor*. For a full description of the MQMD structure, see “MQMD - Message descriptor” in the *MQSeries Application Programming Reference* manual.

## Types of message

### Note for RPG programmers

The names of MQI calls, call parameters, data types, fields of structures, and constants are shown in this book with long names. When writing RPG programs, use the equivalent names given in Appendix B, “MQI names in RPG” on page 457.

See “Message context” on page 37 for a description of how to use the fields within the MQMD that contain information about the origin of the message.

Additional information for grouping and segmenting messages (see “Message groups” on page 33) is provided in Version 2 of the Message Descriptor (or the MQMDE). This is the same as the Version 1 Message Descriptor but has additional fields as described in “MQMDE - Message descriptor extension” in the *MQSeries Application Programming Reference* manual.

---

## Types of message

There are four types of message defined by MQSeries:

- Datagram
- Request
- Reply
- Report

Applications can use the first three types of messages to pass information between themselves. The fourth type, report, is for applications and queue managers to use to report information about events such as the occurrence of an error.

Each type of message is identified by an MQMT\_★ value. You can also define your own types of message. For the range of values you can use, see the description of the *MsgType* field in “MQMD - Message descriptor” in the *MQSeries Application Programming Reference* manual.

## Datagrams

You should use a *datagram* when you do not require a reply from the application that receives the message (that is, gets the message from the queue).

An example of an application that could use datagrams is one that displays flight information in an airport lounge. A message could contain the data for a whole screen of flight information. Such an application is unlikely to request an acknowledgement for a message because it probably does not matter if a message is not delivered. The application will send an update message after a short period of time.

## Request messages

You should use a *request message* when you want a reply from the application that receives the message.

An example of an application that could use request messages is one that displays the balance of a checking account. The request message could contain the number of the account, and the reply message would contain the account balance.

If you want to link your reply message with your request message, there are two options:

- You can give your application the responsibility of ensuring that it puts information into the reply message that relates to the request message.
- You can use the report field in the message descriptor of your request message to specify the content of the *MsgId* and *CorrelId* fields of the reply message:
  - You can request that either the *MsgId* or the *CorrelId* of the original message is to be copied into the *CorrelId* field of the reply message (the default action is to copy *MsgId*).
  - You can request that either a new *MsgId* is generated for the reply message, or that the *MsgId* of the original message is to be copied into the *MsgId* field of the reply message (the default action is to generate a new message identifier).

## Reply messages

You should use a *reply message* when you reply to another message.

When you create a reply message, you should respect any options that were set in the message descriptor of the message to which you are replying. Report options specify the content of the message identifier (*MsgId*) and correlation identifier (*CorrelId*) fields. These fields allow the application that receives the reply to correlate the reply with its original request.

## Report messages

*Report messages* inform applications about events such as the occurrence of an error when processing a message. They can be generated by:

- A queue manager,
  - A message channel agent (for example, if they cannot deliver the message),
- or
- An application (for example, if it cannot use the data in the message).

Note that report messages can be generated at any time, and they may arrive on a queue when your application is not expecting them.

### Types of report message

When you put a message on a queue, you can select to receive:

- An *exception report message*. This is sent in response to a message that had the exceptions flag set. It is generated by the message channel agent (MCA) or the application.
- An *expiry report message*. This indicates that an application attempted to retrieve a message that had reached its expiry threshold; the message is marked to be discarded. This type of report is generated by the queue manager.
- A *confirmation of arrival (COA) report message*. This indicates that the message has reached its target queue. It is generated by the queue manager.

## Types of message

- A *confirmation of delivery (COD) report message*. This indicates that the message has been retrieved by a receiving application. It is generated by the queue manager.
- A *positive action notification (PAN) report message*. This indicates that a request has been successfully serviced (that is, the action requested in the message has been performed successfully). This type of report is generated by the application.
- A *negative action notification (NAN) report message*. This indicates that a request has **not** been successfully serviced (that is, the action requested in the message has **not** been performed successfully). This type of report is generated by the application.

**Note:** Each type of report message is about this message, containing the original message, the first 100 bytes of data in the original message, or no data from the original message.

You may request more than one type of report message when you put a message on a queue. If you select the delivery confirmation report message and the exception report message options, in the event that the message fails to be delivered, you will receive an exception report message. However, if you select only the delivery confirmation report message option and the message fails to be delivered, you **will not** get an exception report message.

The report messages you request, when the criteria for generating a particular message are met, are the only ones you will receive.

### Report message options

You have the option to **discard** a message after an exception has arisen. If you select the discard option, and have requested an exception report message, the report message goes to the *ReplyToQ* and *ReplyToQMGr*, and the original message is discarded.

**Note:** A benefit of this is you can reduce the number of messages going to the dead-letter queue. However, it does mean that your application, unless it sends only datagram messages, has to deal with returned messages.

When an exception report message is generated, it inherits the persistence of the original message.

If a report message cannot be delivered (if the queue is full, for instance), the report message will be placed on the dead-letter queue.

If you wish to receive a report message, you must specify the name of your reply-to queue in the *ReplyToQ* field; otherwise the MQPUT or MQPUT1 of your original message will fail with MQRC\_MISSING\_REPLY\_TO\_Q.

You can use other report options in the message descriptor (MQMD) of a message to specify the content of the *MsgId* and *CorrelId* fields of any report messages that are created for the message:

- You can request that either the *MsgId* or the *CorrelId* of the original message is to be copied into the *CorrelId* field of the report message (the default action is to copy the message identifier)

- You can request that either a new *MsgId* is generated for the report message, or that the *MsgId* of the original message is to be copied into the *MsgId* field of the report message (the default action is to generate a new message identifier)

When generating a report about a message, server applications should test to see if any of these options have been set.

For more information on how to use report messages, see the description of the *Report* field in “MQMD - Message descriptor” in the *MQSeries Application Programming Reference* manual.

To indicate the nature of the report, queue managers use a range of feedback codes. They put these codes in the *Feedback* field of the message descriptor of a report message. Queue managers can also return MQI reason codes in the *Feedback* field. MQSeries defines a range of feedback codes for applications to use.

For more information on feedback and reason codes, see the description of the *Feedback* field in “MQMD - Message descriptor” in the *MQSeries Application Programming Reference* manual.

An example of a program that could use a feedback code is one that monitors the work loads of other programs serving a queue. If there is more than one instance of a program serving a queue, and the number of messages arriving on the queue no longer justifies this, such a program could send a report message (with the feedback code MQFB\_QUIT) to one of the serving programs to indicate that the program should terminate its activity. (A monitoring program could use the MQINQ call to find out how many programs are serving a queue.)

## Reports and segmented messages

*Segmented messages are supported on MQSeries Version 5 products and the MQSeries for AS/400 product only.*

If a message is segmented (see “Message segmentation” on page 141 for a description of this) and you ask for reports to be generated, you may receive more reports than you would have done had the message not been segmented.

### MQSeries-generated reports

If you segment your messages or allow the queue manager to do so, there is only one case in which you can expect to receive a single report for the entire message. This is when you have requested only COD reports, and you have specified MQGMO\_COMPLETE\_MSG on the getting application.

In other cases your application must be prepared to deal with several reports; usually one for each segment.

**Note:** If you segment your messages, and you need only the first 100 bytes of the original message data to be returned, you must change the setting of the report options to ask for reports with *no* data for segments that have an offset of 100 or more. If you do not do this, and you leave the setting so that each segment requests 100 bytes of data, and you retrieve the report messages with a single MQGET specifying MQGMO\_COMPLETE\_MSG, the reports assemble into a large message containing 100 bytes of read data at each appropriate offset. If this happens, you need a large buffer or you need to specify MQGMO\_ACCEPT\_TRUNCATED\_MSG.

### Application-generated reports

If your application generates reports, you should always copy the MQSeries headers that are present at the start of the original message data to the report message data. Then add none, 100 bytes, or all of the original message data (or whatever other amount you would normally include) to the report message data.

You can recognize the MQSeries headers that must be copied by looking at the successive Format names, starting with the MQMD and continuing through any headers present. The following Format names indicate these MQSeries headers:

- MQMDE
- MQDLH
- MQXQH
- MQIIH
- MQH\*

MQH\* means any name starting with the characters MQH.

The Format name occurs at specific positions for MQDLH and MQXQH, but for the other MQSeries headers it occurs at the same position. The length of the header is contained in a field that also occurs at the same position for MQMDE, MQIMS and all MQH\* headers.

If you are using a Version 1 of the MQMD, and you are reporting on a segment, or a message in a group, or a message for which segmentation is allowed, the report data must start with an MQMDE. You should set the *OriginalLength* field to the length of the original message data **excluding** the lengths of any MQSeries headers that you find.

### Retrieval of reports

If you ask for COA or COD reports, you can ask for them to be reassembled for you with MQGMO\_COMPLETE\_MSG. An MQGET with MQGMO\_COMPLETE\_MSG is satisfied when enough report messages (of a single type, for example COA, and with the same *GroupId*) are present on the queue to represent one complete original message. This is true even if the report messages themselves do not contain the complete original data; the *OriginalLength* field in each report message gives the length of original data **represented** by that report message, even if the data itself is not present.

This technique can be used even if there are several different report types present on the queue (for example, both COA and COD), because an MQGET with MQGMO\_COMPLETE\_MSG reassembles report messages only if they have the same *Feedback* code. Note, however, that you cannot normally use the technique for exception reports, since in general these have different *Feedback* codes.

You can use this technique to get a positive indication that the entire message has arrived. However, in most circumstances you need to cater for the possibility that some segments arrive while others may generate an exception (or expiry, if you have allowed this). You cannot use MQGMO\_COMPLETE\_MSG in this case because in general you may get different *Feedback* codes for different segments and, as noted above, you may get more than one report for a given segment. You can, however, use MQGMO\_ALL\_SEGMENTS\_AVAILABLE.

To allow for this you may need to retrieve reports as they arrive, and build up a picture in your application of what happened to the original message. You can use

the *GroupId* field in the report message to correlate reports with the *GroupId* of the original message, and the *Feedback* field to identify the type of each report message. The way in which you do this depends on your application requirements.

One approach is as follows:

- Ask for COD reports and exception reports.
- After a specific time, check whether a complete set of COD reports has been received using MQGMO\_COMPLETE\_MSG. If so, your application knows that the entire message has been processed.
- If not, and exception reports relating to this message are present, the problem should be handled just as for unsegmented messages, though provision must also be made for 'orphan' segments to be cleaned up at some point.
- If there are segments for which there are no reports of any kind, the original segments (or the reports) may be waiting for a channel to be reconnected, or the network might be overloaded at some point. If no exception reports at all have been received (or if you think that the ones you have may be temporary only), you may decide to let your application wait a little longer.

As before, this is similar to the considerations you have when dealing with unsegmented messages, except that you must also consider the possibility of 'orphan' segments which have to be cleaned up.

If the original message is not critical (for example, if it is a query, or a message that can be repeated later), set an expiry time to ensure that orphan segments are removed.

### Back-level queue managers

When a report is generated by a queue manager that supports segmentation, but is received on a queue manager that does *not* support segmentation, the MQMDE structure (which identifies the *Offset* and *OriginalLength* represented by the report) is always included in the report data, in addition to zero, 100 bytes, or all of the original data in the message.

However, if a segment of a message passes through a queue manager that does not support segmentation, you should be aware that if a report is generated there, the MQMDE structure in the original message will be treated purely as data. It will not therefore be included in the report data if zero bytes of the original data have been requested. Without the MQMDE, the report message may not be useful.

You should therefore request at least 100 bytes of data in reports if there is a possibility that the message might travel through a back-level queue manager.

---

## Format of message control information and message data

The queue manager is only interested in the format of the control information within a message, whereas applications that handle the message are interested in the format of both the control information and the data.

### Format of message control information

Control information in the character-string fields of the message descriptor must be in the character set used by the queue manager. The *CodedCharSetId* attribute of the queue manager object defines this character set. Control information must be in this character set because when applications pass messages from one queue manager to another, message channel agents that transmit the messages use the value of this attribute to determine what data conversion they must perform.

### Format of message data

You can specify any of the following:

- The format of the application data
- The character set of the character data
- The format of numeric data

To do this, use these fields:

#### *Format*

This indicates to the receiver of a message the format of the application data in the message.

When the queue manager creates a message, in some circumstances it uses the *Format* field to identify the format of that message. For example, when a queue manager cannot deliver a message, it puts the message on a dead-letter (undelivered-message) queue. It adds a header (containing more control information) to the message, and changes the *Format* field to show this.

The queue manager has a number of *built-in formats* with names beginning “MQ”, for example MQFMT\_STRING. If these do not meet your needs, you must define your own formats (*user-defined formats*), but you should not use names beginning with “MQ” for these.

When you create and use your own formats, you must write a data-conversion exit to support a program getting the message using MQGMO\_CONVERT.

#### *CodedCharSetId*

This defines the character set of character data in the message. If you want to set this character set to that of the queue manager, you can set this field to the constant MQCCSI\_Q\_MGR.

When you get a message from a queue, you should compare the value of the *CodedCharSetId* field with the value that your application is expecting. If the two values differ, you may need to convert any character data in the message or use a data-conversion message exit if one is available.

#### *Encoding*

This describes the format of numeric message data that contains binary integers, packed-decimal integers, and floating point numbers. It is usually encoded according to the particular machine on which the queue manager is running.

When you put a message on a queue, you should normally specify the constant MQENC\_NATIVE in the *Encoding* field. This means that the encoding of your message data is the same as that of the machine on which your application is running.

When you get a message from a queue, you should compare the value of the *Encoding* field in the message descriptor with the value of the constant

MQENC\_NATIVE on your machine. If the two values differ, you may need to convert any numeric data in the message or use a data-conversion message exit if one is available.

## Application data conversion

Application data may need to be converted to the character set and the encoding required by another application where different platforms are concerned. It may be converted at the sending queue manager, or at the receiving queue manager. If the library of built-in formats does not meet your needs, you must define your own. The type of conversion depends on the message format which is specified in the format field of the message descriptor, MQMD.

### Conversion at the sending queue manager

You must set the CONVERT channel attribute to YES if you need the sending message channel agent (MCA) to convert the application data.

The conversion is performed at the sending queue manager for certain built-in formats and for user-defined formats if a suitable user exit is supplied.

**Built-in formats:** These include:

- Messages that are all characters (using the format name MQFMT\_STRING)
- MQSeries defined messages, for example Programmable Command Formats  
MQSeries uses Programmable Command Format messages for administration messages and events (the format name used is MQFMT\_ADMIN in this case). You can use the same format (using the format name MQFMT\_PCF) for your own messages, and take advantage of the built-in data conversion.

**Note:** Messages with MQFMT\_NONE specified are not converted.

The queue manager built-in formats all have names beginning with MQFMT. They are listed and described in “MQMD - Message descriptor” in the *MQSeries Application Programming Reference* manual under the *Format* field of the Message descriptor (MQMD).

**Application-defined formats:** For user-defined formats, application data conversion must be performed by a data-conversion exit program (for more information, see Chapter 11, “Writing data-conversion exits” on page 161). In a client-server environment, the exit is loaded at the server and conversion takes place there.

### Conversion at the receiving queue manager

Application message data may be converted by the receiving queue manager for the built-in formats and user-defined formats. The conversion is performed during the processing of an MQGET call if the MQGMO\_CONVERT option is specified. For details, see “MQGMO - Get-message options” in the *MQSeries Application Programming Reference* manual.

## Message priorities

### Coded character sets

MQSeries products support the coded character sets that are provided by the underlying operating system.

When you create a queue manager, the queue manager coded character set ID (CCSID) used is based on that of the underlying environment. If this is a mixed code page, MQSeries uses the SBCS part of the mixed code page as the queue manager CCSID.

For general data conversion, if the underlying operating system supports DBCS code pages then MQSeries is able to use it.

See the documentation for your operating system for details of the coded character sets that it supports.

You need to consider application data conversion, format names, and user exits when writing applications that span multiple platforms. For details of the MQGET call, the Convert characters call, the MQGMO\_CONVERT option, and the built-in formats, see “MQGET - Get message,” “MQXCNVC - Convert characters,” “MQGMO - Get-message options,” and “MQMD - Message descriptor” in the *MQSeries Application Programming Reference* manual. See Chapter 11, “Writing data-conversion exits” on page 161 for information about invoking and writing data-conversion exits.

---

## Message priorities

You set the priority of a message (in the *Priority* field of the MQMD structure) when you put the message on a queue. You can set a numeric value for the priority, or you can let the message take the default priority of the queue.

The *MsgDeliverySequence* attribute of the queue determines whether messages on the queue are stored in FIFO (first in, first out) sequence, or in FIFO within priority sequence. If this attribute is set to MQMDS\_PRIORITY, messages are enqueued with the priority specified in the *Priority* field of their message descriptors; but if it is set to MQMDS\_FIFO, messages are enqueued with the default priority of the queue. Messages of equal priority are stored on the queue in order of arrival.

The *DefPriority* attribute of a queue sets the default priority value for messages being put on that queue. This value is set when the queue is created, but it can be changed afterwards. Alias queues, and local definitions of remote queues, may have different default priorities from the base queues to which they resolve. If there is more than one queue definition in the resolution path (see “Name resolution” on page 99), the default priority is taken from the value (at the time of the put operation) of the *DefPriority* attribute of the queue specified in the open command.

The value of the *MaxPriority* attribute of the queue manager is the maximum priority that you can assign to a message processed by that queue manager. You cannot change the value of this attribute. In MQSeries, the attribute has the value 9; you can create messages having priorities between 0 (the lowest) and 9 (the highest).

## Message groups

Message groups are supported on MQSeries Version 5 products and MQSeries for AS/400 only.

Messages can occur within groups. This allows ordering of messages (see “Logical and physical ordering” on page 129), and segmentation of large messages (see “Message segmentation” on page 141) within the same group.

The hierarchy within a group is as follows:

### Group

This is the highest level in the hierarchy and is identified by a *GroupId*. It consists of one or more messages that contain the same *GroupId*. These messages can be stored anywhere on the queue.

**Note:** The term “message” is used here to denote one item on a queue, such as would be returned by a single MQGET that does not specify MQGMO\_COMPLETE\_MSG.

Figure 3 shows a group of logical messages:




Figure 3. Group of logical messages

### Logical message

Logical messages within a group are identified by the *GroupId* and *MsgSeqNumber* fields. The *MsgSeqNumber* starts at 1 for the first message within a group, and if a message is not in a group, the value of the field is 1.

Logical messages within a group can be used to:

- Ensure ordering (if this is not guaranteed under the circumstances in which the message is transmitted).
- Allow applications to group together similar messages (for example, those that must all be processed by the same server instance).

Each message within a group consists of one physical message, unless it is split into segments. Each message is logically a separate message, and only the *GroupId* and *MsgSeqNumber* fields in the MQMD need bear any relationship to other messages in the group. Other fields in the MQMD are independent; some may be identical for all messages in the group whereas others may be different. For example, messages in a group may have different format names, CCSIDs, encodings, and so on.

### Segment

Segments are used to handle messages that are too large for either the putting or getting application or the queue manager (including intervening queue managers through which the message passes). For more information about this, see “Message segmentation” on page 141.

A segment of a message is identified by the *GroupId*, *MsgSeqNumber*, and *Offset* fields. The *Offset* field starts at zero for the first segment within a message.

## Message persistence

Each segment consists of one physical message that may or may not belong to a group (Figure 4 on page 34 shows an example of messages within a group). A segment is logically part of a single message, so only the *MsgId*, *Offset*, and *SegmentFlag* fields in the MQMD should differ between separate segments of the same message.

Figure 4 shows a group of logical messages, some of which are segmented:




Figure 4. Segmented messages

For a description of logical and physical messages, see “Logical and physical ordering” on page 129. For further information about segmenting messages, see “Message segmentation” on page 141.

---

## Message persistence

Persistent messages are written out to logs and queue data files. If a queue manager is restarted after a failure, it recovers these persistent messages as necessary from the logged data. Messages that are not persistent are discarded if a queue manager stops, whether the stoppage is as a result of an operator command or because of the failure of some part of your system.

When you create a message, if you initialize the message descriptor (MQMD) using the defaults, the persistence for the message will be taken from the *DefPersistence* attribute of the queue specified in the MQOPEN command. Alternatively, you may set the persistence of the message using the *Persistence* field of the MQMD structure to define the message as persistent or not persistent.

The performance of your application is affected when you use persistent messages; the extent of the effect depends on the performance characteristics of the machine’s I/O subsystem and how you use the syncpoint options on each platform:

- A persistent message, outside the current unit of work, is written to disk on every put and get operation. See Chapter 13, “Committing and backing out units of work” on page 183.
- In MQSeries on UNIX systems, MQSeries for Digital OpenVMS, MQSeries for OS/390, MQSeries for OS/2 Warp, MQSeries for VSE/ESA, and MQSeries for Windows NT, a persistent message within the current unit of work is logged only when the unit of work is committed (and the unit of work could contain many queue operations).

Nonpersistent messages can be used for fast messaging if retrieved outside syncpoint. See “MQMD - Message descriptor” in the *MQSeries Application Programming Reference* manual and “Fast, nonpersistent messages” in the *MQSeries Intercommunication* book for further information about fast messages.

---

## Selecting messages from queues

To get a particular message from a queue, you need to use the *MsgId* and *CorrelId* fields of the message descriptor. If you specify Version 2 of the MQMD, the *GroupId* can also be used. (See “Getting a particular message” on page 137.)

The message identifier is usually generated by the queue manager when the message is put on a queue. The queue manager tries to ensure that message identifiers are unique. However, an MQSeries application can specify a particular value for the message identifier.

You can use the correlation identifier in any way you like. However, an intended use of this field is for applications to copy the message identifier of a request message into the *CorrelId* field of a reply message.

The group identifier is usually generated by the queue manager when the first message of a group is put onto a queue. The *MsgSeqNumber* field identifies the position of the message within the group and the *Offset* field identifies the segments within the message.

Where more than one message meets the combined selection criteria, the *MsgDeliverySequence* attribute of the queue determines whether messages are selected in FIFO (first in, first out) or priority order. When messages have equal priority, they are selected in FIFO order. For more information, see “The order in which messages are retrieved from a queue” on page 128.

For an example of an application that uses correlation identifiers, see “The Credit Check sample” on page 430.

---

## Messages that fail to be delivered

When a queue manager is unable to put a message on a queue, you have various options. You can:

- Attempt to put the message on the queue again.
- Request that the message is returned to the sender.
- Put the message on the dead-letter queue.

See Chapter 5, “Handling program errors” on page 53 for more information.

---

## Messages that are backed out

When processing messages from a queue under the control of a unit of work, the unit of work could consist of one or more messages. If a backout occurs, the messages which were retrieved from the queue are reinstated on the queue, and they can be processed again in another unit of work. If the processing of a particular message is causing the problem, the unit of work is backed out again. This could cause a processing loop. Messages which were put to a queue are removed from the queue.

An application can detect messages that are caught up in such a loop by testing the *BackoutCount* field of MQMD. The application can either correct the situation, or issue a warning to an operator.

## Message response

In MQSeries for OS/390, to ensure that the back-out count survives restarts of the queue manager, set the *HardenGetBackout* attribute to MQQA\_BACKOUT\_HARDENED; otherwise, if the queue manager has to restart, it does not maintain an accurate back-out count for each message. Setting the attribute this way adds the penalty of extra processing.

In MQSeries for AS/400, MQSeries for OS/2 Warp, MQSeries for Windows NT, MQSeries for Digital OpenVMS, and MQSeries on UNIX systems, the back-out count always survives restarts of the queue manager. Any change to the *HardenGetBackout* attribute is ignored.

**Note:** In MQSeries for VSE/ESA, the BackoutCount field is reserved and so cannot be used as described here.

For more information on committing and backing out messages, see Chapter 13, “Committing and backing out units of work” on page 183.

---

## Reply-to queue and queue manager

There are occasions when you may receive messages in response to a message you send:

- A reply message in response to a request message
- A report message about an unexpected event or expiry
- A report message about a COA (Confirmation Of Arrival) or a COD (Confirmation Of Delivery) event
- A report message about a PAN (Positive Action Notification) or a NAN (Negative Action Notification) event

Using the MQMD structure, specify the name of the queue to which you want reply and report messages sent, in the *ReplyToQ* field. Specify the name of the queue manager that owns the reply-to queue in the *ReplyToQMgr* field.

If you leave the *ReplyToQMgr* field blank, the queue manager sets the contents of the following fields in the message descriptor on the queue:

### *ReplyToQ*

If *ReplyToQ* is a local definition of a remote queue, the *ReplyToQ* field is set to the name of the remote queue; otherwise this field is not changed.

### *ReplyToQMgr*

If *ReplyToQ* is a local definition of a remote queue, the *ReplyToQMgr* field is set to the name of the queue manager that owns the remote queue; otherwise the *ReplyToQMgr* field is set to the name of the queue manager to which your application is connected.

**Note:** You can request that a queue manager makes more than one attempt to deliver a message, and you can request that the message is discarded if it fails. If the message, after failing to be delivered, is not to be discarded, the remote queue manager puts the message on its dead-letter (undelivered-message) queue (see “Using the dead-letter (undelivered-message) queue” on page 57).

## Message context

*Message context* information allows the application that retrieves the message to find out about the originator of the message. The retrieving application may want to:

- Check that the sending application has the correct level of authority
- Perform some accounting function so that it can charge the sending application for any work it has to perform
- Keep an audit trail of all the messages it has worked with

When you use the MQPUT or MQPUT1 call to put a message on a queue, you can specify that the queue manager is to add some default context information to the message descriptor. Applications that have the appropriate level of authority can add extra context information. For more information on how to specify context information, see “Controlling context information” on page 113.

All context information is stored in the eight context fields of the message descriptor. The type of information falls into two categories: identity and origin context information.

## Identity context

*Identity context* information identifies the user of the application that **first** put the message on a queue:

- The queue manager fills the *UserIdentifier* field with a name that identifies the user—the way that the queue manager can do this depends on the environment in which the application is running.
- The queue manager fills the *AccountingToken* field with a token or number that it determined from the application that put the message.
- Applications can use the *AppIdentityData* field for any extra information that they want to include about the user (for example, an encrypted password).

Suitably authorized applications may set the above fields.

A Windows NT security identifier (SID) is stored in the *AccountingToken* field when a message is created under MQSeries for Windows NT. The SID can be used to supplement the *UserIdentifier* field and to establish the credentials of a user.

For information on how the queue manager fills the *UserIdentifier* and *AccountingToken* fields, see the descriptions of these fields in “MQMD - Message descriptor” in the *MQSeries Application Programming Reference* manual.

Applications that pass messages from one queue manager to another should also pass on the identity context information so that other applications know the identity of the originator of the message.

## Message context

### Origin context

*Origin context* information describes the application that put the message on the queue on which the message is **currently** stored. The message descriptor contains the following fields for origin context information:

<i>PutApplType</i>	The type of application that put the message (for example, a CICS transaction).
<i>PutApplName</i>	The name of the application that put the message (for example, the name of a job or transaction).
<i>PutDate</i>	The date on which the message was put on the queue.
<i>PutTime</i>	The time at which the message was put on the queue.
<i>ApplOriginData</i>	Any extra information that an application may want to include about the origin of the message. For example, it could be set by suitably authorized applications to indicate whether the identity data is trusted.

Origin context information is usually supplied by the queue manager. Greenwich Mean Time (GMT) is used for the *PutDate* and *PutTime* fields. See the descriptions of these fields in “MQMD - Message descriptor” in the *MQSeries Application Programming Reference* manual.

Within MQSeries for OS/2 Warp only, the TZ environment variable is used to calculate the GMT *PutDate* and *PutTime* of a message.

An application with enough authority can provide its own context. This allows accounting information to be preserved when a single user has a different user ID on each of the systems that process a message they have originated.

---

## Chapter 4. MQSeries objects

The MQSeries objects are:

- Queue managers
- Queues
- Namelists (MQSeries for OS/390 and MQSeries Version 5.1 products only)
- Process definitions
- Channels
- Storage classes (MQSeries for OS/390 only)

Queue managers define the properties (known as attributes) of these objects. The values of these attributes affect the way in which these objects are processed by MQSeries. From your applications, you use the Message Queue Interface (MQI) to control these objects. Each object is identified by an *object descriptor* (MQOD) when addressed from a program.

When you use MQSeries commands to define, alter, or delete objects, for example, the queue manager checks that you have the required level of authority to perform these operations. Similarly, when an application uses the MQOPEN call to open an object, the queue manager checks that the application has the required level of authority before it allows access to that object. The checks are made on the name of the object being opened.

---

### Queue managers

A *queue manager* supplies an application with MQSeries services. A program must have a connection to a queue manager before it can use the services of that queue manager. A program can make this connection explicitly (using the MQCONN call), or the connection might be made implicitly (this depends on the platform and the environment in which the program is running).

Queues belong to queue managers, but programs can send messages to queues that belong to any queue manager.

### Attributes of queue managers

Associated with each queue manager is a set of attributes (or properties) that define its characteristics. Some of the attributes of a queue manager are fixed when it is created; you can change others using the MQSeries commands. You can inquire about the values of **all** the attributes using the MQINQ call.

The *fixed* attributes include:

- The name of the queue manager
- The platform on which the queue manager runs (for example, AS/400)
- The level of system control commands that the queue manager supports
- The maximum priority that you can assign to messages processed by the queue manager
- The name of the queue to which programs can send MQSeries commands

## Queues

- The identifier of the character set the queue manager uses for character strings when it processes MQI calls (this can be changed in OS/390 using the system parameters)
- The maximum length of messages the queue manager can process
- Whether the queue manager supports syncpointing when programs put and get messages

The *changeable* attributes include:

- A text description of the queue manager
- The time interval that the queue manager uses to restrict the number of trigger messages
- The name of the queue manager's dead-letter (undelivered-message) queue (useful if this queue is full, but is already set to the maximum size allowed, as it allows the queue manager to start using a different one)
- The name of the queue manager's default transmission queue
- The maximum number of open handles for any one connection
- The enabling and disabling of various categories of event reporting
- The maximum number of uncommitted messages within a unit of work

For a full description of all the attributes, see “Attributes for the queue manager” in the *MQSeries Application Programming Reference* manual.

## Queue managers and workload management

You can set up a cluster of queue managers that has more than one definition for the same queue (for example, the queue managers in the cluster could be clones of each other). Messages for a particular queue can be handled by any queue manager which hosts an instance of the queue. A workload-management algorithm decides which queue manager handles the message and so spreads the workload between your queue managers. See Chapter 5, “Using clusters for workload management” in the *MQSeries Queue Manager Clusters* book for further information.

---

## Queues

An MQSeries *queue* is a named object on which applications can put messages, and from which applications can get messages. Messages are stored on a queue, so if the putting application is expecting a reply to its message, it is free to do other work while waiting for that reply. Applications access a queue by using the Message Queue Interface (MQI), described in Chapter 6, “Introducing the Message Queue Interface” on page 65.

Before a message can be put on a queue, the queue must have already been created. A queue is owned by a queue manager, and that queue manager can own many queues. However, each queue must have a name that is unique within that queue manager.

A queue is maintained through a queue manager. Queues are managed physically by their queue managers but this is transparent to an application program.

To create a queue you can use MQSeries commands (MQSC), PCF commands, or platform-specific interfaces such as the MQSeries for OS/390 operations and control panels.

With MQSeries for AS/400, MQSeries for OS/390, MQSeries for OS/2 Warp, MQSeries for Digital OpenVMS, and MQSeries on UNIX systems, you can also create local queues “dynamically” from your application for temporary jobs, such as *reply-to* queues (which are not needed after an application ends). For more information, see “Dynamic queues” on page 45.

Before using a queue, you must open the queue, specifying what you want to do with it. For example, you can open a queue:

- For browsing messages only (not retrieving them)
- For retrieving messages (and either sharing the access with other programs, or with exclusive access)
- For putting messages on the queue
- For inquiring about the attributes of the queue
- For setting the attributes of the queue

For a complete list of the options you can specify when you open a queue, see the description of the MQOPEN call in “MQOPEN - Open object” in the *MQSeries Application Programming Reference* manual.

## Types of queue

The types of queue that MQSeries supports for applications to use are:

### Local and remote queues

A queue is known to a program as *local* if it is owned by the queue manager to which the program is connected; the queue is known as *remote* if it is owned by a different queue manager. The important difference between these two types of queue is that you can get messages only from local queues. (You can put messages on both types of queue.)

The queue definition object, created when you define a local queue, will hold the definition information of the queue as well as the physical messages put on the queue. The queue definition object, created when you ‘define’ a remote queue, will only hold the information necessary for the local queue manager to be able to locate the queue to which you want your message to go. This object is known as the *local definition of a remote queue*. All the attributes of the remote queue are held by the queue manager that owns it, because it is a local queue to that queue manager.

### Alias queues

To your program, an *alias queue* appears to be a queue, but it is really an MQSeries object that you can use to access another queue. This means that more than one program can work with the same queue, accessing it using different names.

### Model and dynamic queues

A model queue is a template of a queue definition used only when you want to create a dynamic local queue.

You can create a local queue dynamically from an MQSeries program, naming the model queue you wish to use as the template for the queue attributes. You

may now, if you wish, change some attributes of the new queue. However, you cannot change the *DefinitionType*. If, for example, you require a permanent queue, you must select a model queue with the definition type set to permanent. Some conversational applications could make use of dynamic queues to hold replies to their queries because they probably would not need to maintain these queues after they have processed the replies.

### Cluster queues

A cluster queue is a queue that is hosted by a cluster queue manager and made available to other queue managers in the cluster.

The cluster queue manager makes a local queue definition for the queue specifying the name of the cluster that the queue is to be available in. This definition has the effect of advertising the queue to the other queue managers in the cluster. The other queue managers in the cluster can put messages to a cluster queue without needing a corresponding remote-queue definition. A cluster queue can be advertised in more than one cluster. See “What is a cluster?” on page 6 and the *MQSeries Queue Manager Clusters* book for further information.

### Types of local queue

Each queue manager can have some local queues that it uses for special purposes:

#### Transmission queues

A *transmission queue* is a local queue which holds messages destined for a remote queue. The messages are forwarded to their destination queue by MQSeries when a communication program and link are available.

#### Initiation queues

An *initiation queue* is a local queue on which the queue manager puts a message for the purpose of automatically starting an application when certain conditions (such as more than 10 messages arriving, for example) are met on a local queue.

#### Dead-letter (undelivered-message) queue

The *dead-letter queue* is a local queue on which the queue manager and applications put messages they cannot deliver. You should plan to process any messages that arrive on this queue.

#### System command queue

The *system command queue* is a queue to which suitably authorized applications can send MQSeries commands.

#### System default queues

When you create a queue (other than a dynamic queue), MQSeries uses the queue definitions stored in the *system default queues*.

#### Channel queues

*Channel queues* are used for distributed queue management.

#### Event queues

*Event queues* hold event messages. These messages are reported by the queue manager or a channel.

These special queues are described in greater detail in the following sections.

## Attributes of queues

Some of the attributes of a queue are specified when the queue is defined, and may not be changed afterwards (for example, the type of the queue). Other attributes of queues can be grouped into those that can be changed:

- By the queue manager during the processing of the queue (for example, the current depth of a queue)
- Only by commands (for example, the text description of the queue)
- By applications, using the MQSET call (for example, whether or not put operations are allowed on the queue)

You can find the values of all the attributes using the MQINQ call.

The attributes that are common to more than one type of queue are:

*QName*

Name of the queue

*QType*

Type of the queue

*QDesc*

Text description of the queue

*InhibitGet*

Whether or not programs are allowed to get messages from the queue (although you can never get messages from remote queues)

*InhibitPut*

Whether or not programs are allowed to put messages on the queue

*DefPriority*

Default priority for messages put on the queue

*DefPersistence*

Default persistence for messages put on the queue

*Scope (not supported on AS/400, VSE/ESA, or OS/390)*

Controls whether an entry for this queue also exists in a cell directory

For a full description of these attributes, see "Attributes for all queues" in the *MQSeries Application Programming Reference* manual.

## Remote queues

To a program, a queue is *remote* if it is owned by a different queue manager to the one to which the program is connected. Where a communication link has been established, it is possible for a program to send a message to a remote queue. A program can never get a message from a remote queue.

When opening a remote queue, to identify the queue you must specify either:

- The name of the local definition that defines the remote queue.

To create a local definition of a remote queue use the DEFINE QREMOTE command; in MQSeries for AS/400, alternatively use the CRTMQMQ command; in MQSeries for Tandem NSK, you can use the MQM screen-based interface; in MQSeries for VSE/ESA, you can use the MQMT transaction.

## Queues

From the viewpoint of an application, this is the same as opening a local queue. An application does not need to know if a queue is local or remote.

- The name of the remote queue manager and the name of the queue as it is known to that remote queue manager.

Local definitions of remote queues have three attributes in addition to the common attributes described in “Attributes of queues” on page 43. These are *RemoteQName* (the name that the queue’s owning queue manager knows it by), *RemoteQMGrName* (the name of the owning queue manager), and *XmitQName* (the name of the local transmission queue that is used when forwarding messages to other queue managers). For a fuller description of these attributes, see “Attributes for local definitions of remote queues” in the *MQSeries Application Programming Reference* manual.

If you use the MQINQ call against the local definition of a remote queue, the queue manager returns the attributes of the local definition only, that is the remote queue name, the remote queue manager name and the transmission queue name, not the attributes of the matching local queue in the remote system.

See also “Transmission queues” on page 47.

## Alias queues

An *alias queue* is an MQSeries object that you can use to access another queue. The queue resulting from the resolution of an alias name (known as the base queue) can be either a local queue or the local definition of a remote queue. It can also be either a predefined queue or a dynamic queue, as supported by the platform.

**Note:** An alias cannot resolve to another alias.

An example of the use of alias queues is for a system administrator to give different access authorities to the base queue name (that is, the queue to which the alias resolves) and to the alias queue name. This would mean that a program or user could be authorized to use the alias queue, but not the base queue.

Alternatively, authorization can be set to inhibit put operations for the alias name, but allow them for the base queue.

In some applications, the use of alias queues means that system administrators can easily change the definition of an alias queue object without having to get the application changed.

MQSeries makes authorization checks against the alias name when programs try to use that name. It does not check that the program is authorized to access the name to which the alias resolves. A program can therefore be authorized to access an alias queue name, but not the resolved queue name.

In addition to the general queue attributes described in “Attributes of queues” on page 43, alias queues have a *BaseQName* attribute. This is the name of the base queue to which the alias name resolves. For a fuller description of this attribute, see “Attributes for alias queues” in the *MQSeries Application Programming Reference* manual.

The *InhibitGet* and *InhibitPut* attributes (see “Attributes of queues” on page 43) of alias queues belong to the alias name. For example, if the alias-queue name ALIAS1 resolves to the base-queue name BASE, inhibitions on ALIAS1 affect ALIAS1 only and BASE is not inhibited. However, inhibitions on BASE also affect ALIAS1.

The *DefPriority* and *DefPersistence* attributes also belong to the alias name. So, for example, you can assign different default priorities to different aliases of the same base queue. Also, you can change these priorities without having to change the applications that use the aliases.

## Model queues

A *model queue* is a template of a queue definition, that you use when creating a dynamic queue. You specify the name of a model queue in the *object descriptor* (MQOD) of your MQOPEN call. Using the attributes of the model queue, the queue manager dynamically creates a local queue for you.

You can specify a name (in full) for the dynamic queue, or the stem of a name (for example, ABC) and let the queue manager add a unique part to this, or you can let the queue manager assign a complete unique name for you. If the queue manager assigns the name, it puts it in the MQOD structure.

You can not issue an MQPUT1 call directly to a model queue, however, once a model queue has been opened, you can issue an MQPUT1 to the dynamic queue.

The attributes of a model queue are a subset of those of a local queue. For a fuller description, see “Attributes for local queues and model queues” in the *MQSeries Application Programming Reference* manual.

## Dynamic queues

When an application program issues an MQOPEN call to open a model queue, the queue manager dynamically creates an instance of a local queue with the same attributes as the model queue. Depending on the value of the *DefinitionType* field of the model queue, the queue manager creates either a temporary or permanent dynamic queue (See “Creating dynamic queues” on page 104).

### Properties of temporary dynamic queues

*Temporary dynamic queues* have the following properties:

- They hold nonpersistent messages only.
- They are non-recoverable.
- They are deleted when the queue manager is started
- They are deleted when the application that issued the MQOPEN call which resulted in the creation of the queue closes the queue or terminates.
  - If there are any committed messages on the queue, they will be deleted.
  - If there are any uncommitted MQGET, MQPUT, or MQPUT1 calls outstanding against the queue at this time, the queue is marked as being logically deleted, and is only physically deleted (after these calls have been committed) as part of close processing, or when the application terminates.

- If the queue happens to be in use at this time (by the creating, or another application), the queue is marked as being logically deleted, and is only physically deleted when closed by the last application using the queue.
- Attempts to access a logically deleted queue (other than to close it) fail with reason code MQRC\_Q\_DELETED.
- MQCO\_NONE, MQCO\_DELETE and MQCO\_DELETE\_PURGE are all treated as MQCO\_NONE when specified on an MQCLOSE call for the corresponding MQOPEN call that created the queue.

### Properties of permanent dynamic queues

*Permanent dynamic queues* have the following properties:

- They hold persistent or nonpersistent messages.
- They are recoverable in the event of system failures.
- They are deleted when an application (not necessarily the one that issued the MQOPEN call which resulted in the creation of the queue) successfully closes the queue using the MQCO\_DELETE, or the MQCO\_DELETE\_PURGE option.
  - A close request with the MQCO\_DELETE option fails if there are any messages (committed or uncommitted) still on the queue. A close request with the MQCO\_DELETE\_PURGE option succeeds even if there are committed messages on the queue (the messages being deleted as part of the close), but fails if there are any uncommitted MQGET, MQPUT, or MQPUT1 calls outstanding against the queue.
  - If the delete request is successful, but the queue happens to be in use (by the creating, or another application), the queue is marked as being logically deleted and is only physically deleted when closed by the last application using the queue.
- They are not deleted if closed by an application (other than the one that issued the MQOPEN call which resulted in the creation of the queue) which is not authorized to delete the queue. Authorization checks are performed against the user identifier (or alternate user identifier if MQOO\_ALTERNATE\_USER\_AUTHORITY was specified) which was used to validate the corresponding MQOPEN call.
- They can be deleted in the same way as a normal queue.

### Uses of dynamic queues

You can use dynamic queues for:

- Applications that do not require queues to be retained after the application has terminated.
- Applications that require replies to messages to be processed by another application can dynamically create a reply-to queue by opening a model queue. For example, a client application could:
  1. Create a dynamic queue.
  2. Supply its name in the *ReplyToQ* field of the message descriptor structure of the request message.
  3. Place the request on a queue being processed by a server.

The server could then place the reply message on the reply-to queue. Finally, the client could process the reply, and close the reply-to queue with the delete option.

### Recommendations for uses of dynamic queues

You should consider the following points when using dynamic queues:

- In a client-server model, each client should create and use its own dynamic reply-to queue. If a dynamic reply-to queue is shared between more than one client, the deletion of the reply-to queue may be delayed because there is uncommitted activity outstanding against the queue, or because the queue is in use by another client. Additionally, the queue might be marked as being logically deleted, and hence inaccessible for subsequent API requests (other than MQCLOSE).
- If your application environment requires that dynamic queues must be shared between applications, you should ensure that the queue is only closed (with the delete option) when all activity against the queue has been committed. This should be by the last user preferably. This ensures that deletion of the queue is not delayed, and should minimize the period that the queue is inaccessible because it has been marked as being logically deleted.

## Transmission queues

When an application sends a message to a remote queue, the local queue manager stores the message in a special local queue, called a *transmission queue*.

A *message channel agent* (channel program) will be associated with the transmission queue and the remote queue manager, and it is this that deals with the transmitting of the message. When the message has been transmitted, it is deleted from the transmission queue.

The message may have to pass through many queue managers (or *nodes*) on its journey to its final destination. There must be a transmission queue defined at each queue manager along the route, each holding messages waiting to be transmitted to the next node. There can be several transmission queues defined at a particular queue manager. A given transmission queue holds messages whose **next** destination is the same queue manager, although the messages may have different eventual destinations. There may also be several transmission queues for the same remote queue manager, with each one being used for a different type of service, for example.

The queue manager must know the attributes of an application if that application is to start automatically. (For information about this, see Chapter 14, “Starting MQSeries applications using triggers” on page 197.) These attributes are defined in the transmission queue definition (for triggered channels) or the process definition object (see “Process definitions” on page 49).

## Initiation queues

An *initiation queue* is a local queue on which the queue manager puts a trigger message when a trigger event occurs on an application queue. A trigger event is an event (for example, more than 10 messages arriving) that an application designer intends the queue manager to use as a cue, or trigger, to start a program that will process the queue. For more information on how triggering works, see Chapter 14, “Starting MQSeries applications using triggers” on page 197.

### Dead-letter (undelivered-message) queues

A *dead-letter (undelivered-message) queue* is a local queue on which the queue manager puts messages it cannot deliver.

When the queue manager puts a message on the dead-letter queue, it adds a header to the message. This includes such information as the intended destination of the original message, the reason the queue manager put the message on the dead-letter queue, and the date and time it did this.

Applications can also use the queue for messages they cannot deliver. For more information, see “Using the dead-letter (undelivered-message) queue” on page 57.

### System command queues

*System command queues are not supported on MQSeries for VSE/ESA.*

These queues receive the PCF, MQSC, and CL commands, as supported on your platform, in readiness for the queue manager to action them. In MQSeries for OS/390 the queue is known as the **SYSTEM.COMMAND.INPUT.QUEUE** and accepts MQSC commands. On other platforms it is known as the **SYSTEM.ADMIN.COMMAND.QUEUE** and the commands accepted vary by platform. See “PCF command messages” in the *MQSeries Programmable System Management* book for details.

### System default queues

The *system default queues* contain the initial definitions of the queues for your system. When you create a new queue, the queue manager copies the definition from the appropriate system default queue.

---

## Namelists

*Namelists are supported on MQSeries for OS/390 and MQSeries Version 5.1 products only.*

A *namelist* is an MQSeries object that contains a list of queue names. The queues in the list can be of any type and the list can contain queues of more than one type.

You can define and modify namelists using only the commands or operations and control panels of MQSeries for OS/390 or the MQSC of MQSeries Version 5.1 products.

Programs can use the MQI to find out which queues are included in these namelists. The organization of the namelists is the responsibility of the application designer and system administrator.

For a full description of the attributes of namelists, see “Attributes for namelists” in the *MQSeries Application Programming Reference* manual.

---

## Process definitions

**Note:** Process definition objects are not supported on VSE/ESA.

To allow an application to be started without the need for operator intervention (described in Chapter 14, “Starting MQSeries applications using triggers” on page 197), the attributes of the application must be known to the queue manager. These attributes are defined in a *process definition object*.

The *ProcessName* attribute is fixed when the object is created; you can change the others using the MQSeries commands or the MQSeries for OS/390 operations and control panels. You can inquire about the values of **all** the attributes using the MQINQ call.

For a full description of the attributes of process definitions, see “Attributes for process definitions” in the *MQSeries Application Programming Reference* manual.

---

## Channels

A *channel* is a communication link used by distributed applications. There are two categories of channel in MQSeries:

- *Message* channels, which are unidirectional, and transfer messages from one queue manager to another.
- *MQI* channels, which are bidirectional, and transfer MQI calls from an MQSeries client to a queue manager, and responses from a queue manager to an MQSeries client.

These need to be considered when designing your application, but a program will be unaware of MQSeries channel objects. For more information, see “Message channels” in the *MQSeries Intercommunication* book and “What is a channel?” in the *MQSeries Clients* book.

---

## Storage classes

*Storage classes are supported on MQSeries for OS/390 only.*

A *storage class* maps one or more queues to a page set. This means that messages for that queue are stored (subject to buffering) on that page set.

For further information about storage classes, see the *MQSeries for OS/390 System Management Guide*.

---

## Rules for naming MQSeries objects

An MQSeries queue, process definition, namelist, and channel can all have the same name. However, an MQSeries object cannot have the same name as any other object of the same type. Names in MQSeries are case sensitive.

The character set that can be used for naming all MQSeries objects is as follows:

- Uppercase A–Z

## Naming objects

- Lowercase a–z (but there are restrictions on the use of lowercase letters for OS/390 console support)

On systems using EBCDIC Katakana you cannot use lowercase characters.

- Numerics 0–9
- Period (.)
- Forward slash (/)
- Underscore (\_)
- Percent sign (%)

### Notes:

1. Leading or embedded blanks are not allowed.
2. You should also avoid using names with leading or trailing underscores, because they cannot be handled by the MQSeries for OS/390 operations and control panels.
3. Any name that is less than the full field length can be padded to the right with blanks. All short names that are returned by the queue manager are always padded to the right with blanks.
4. Any structure to the names (for example, the use of the period or underscore) is not significant to the queue manager.
5. On AS/400 systems lowercase a-z, forward slash (/), and percent (%) are special characters. If you use any of these characters in a name, the name must be enclosed in quotation marks. Lowercase a-z characters are changed to uppercase if the name is not enclosed in quotation marks.

## Queue names

The name of a queue has two parts:

- The name of a queue manager
- The local name of the queue as it is known to that queue manager

Each part of the queue name is 48 characters long.

To refer to a local queue, you can omit the name of the queue manager (by replacing it with blank characters or using a leading null character). However, all queue names returned to a program by MQSeries contain the name of the queue manager.

To refer to a remote queue, a program must include the name of the queue manager in the full queue name, or there must be a local definition of the remote queue.

Note that when an application uses a queue name, that name can be either the name of a local queue (or an alias to one) or the name of a local definition of a remote queue, but the application does not need to know which, unless it needs to get a message from the queue (when the queue must be local). When the application opens the queue object, the MQOPEN call performs a name resolution function to determine on which queue to perform subsequent operations. The significance of this is that the application has no built-in dependency on particular queues being defined at particular locations in a network of queue managers.

Therefore, if a system administrator relocates queues in the network, and changes their definitions, the applications that use those queues do not need to be changed.

### Process definition and namelist names

Process definitions and namelists can have names up to 48 characters long.

### Channel names

Channels can have names up to 20 characters long. See “Message channels” in the *MQSeries Intercommunication* book for further information on channels.

### Reserved object names

Names that start with SYSTEM. are reserved for objects defined by the queue manager.

## Naming objects

---

## Chapter 5. Handling program errors

Your application may encounter errors associated with its MQI calls either when it makes a call or when its message is delivered to its final destination:

- Whenever possible, the queue manager returns any errors as soon as an MQI call is made. These are *locally determined errors*.
- When sending messages to a remote queue, errors may not be apparent when the MQI call is made. In this case, the queue manager that identifies the errors reports them by sending another message to the originating program. These are *remotely determined errors*.

This chapter gives advice on how to handle both types of error.

---

### Locally determined errors

The three most common causes of errors that the queue manager can report immediately are:

- Failure of an MQI call; for example, because a queue is full
- An interruption to the running of some part of the system on which your application is dependent; for example, the queue manager
- Messages containing data that cannot be processed successfully

### Failure of an MQI call

The queue manager can report immediately any errors in the coding of an MQI call. It does this using a set of predefined return codes. These are divided into completion codes and reason codes.

To show whether or not a call is successful, the queue manager returns a *completion code* when the call completes. There are three completion codes, indicating success, partial completion, and failure of the call. The queue manager also returns a *reason code* which indicates the reason for the partial completion or the failure of the call.

The completion and reason codes for each call are listed with the description of that call in the *MQSeries Application Programming Reference* manual. You will also find further information (including some ideas for corrective action) for each completion and reason code, in Chapter 5, "Return codes" in the *MQSeries Application Programming Reference* manual. You should design your programs to handle all the return codes that could arise from each call.

### System interruptions

Your application may be unaware of any interruption if the queue manager to which it is connected has to recover from a system failure. However, you must design your application to ensure that your data is not lost if such an interruption occurs.

The methods you can use to make sure that your data remains consistent depends on the platform on which your queue manager is running:

#### **OS/390**

In the CICS and IMS environments, you can make MQPUT and MQGET calls within units of work that are managed by CICS or IMS. In the batch environment, you can make MQPUT and MQGET calls in the same way, but you must declare syncpoints by using the MQSeries for OS/390 MQCMIT and MQBACK calls (see Chapter 13, “Committing and backing out units of work” on page 183), or you can use the OS/390 Transaction Management and Recoverable Resource Manager Services (RRS) to provide two-phase syncpoint support. RRS allows you to update both MQSeries and other RRS-enabled product resources, such as DB2® stored procedure resources, within a single logical unit of work. For information on RRS syncpoint support see “Transaction management and recoverable resource manager services” on page 187.

#### **AS/400**

You can make your MQPUT and MQGET calls within units of work that are managed by OS/400 commitment control.

#### **Digital OpenVMS, DOS, OS/2, UNIX systems, Windows NT, and Windows 3.1**

In these environments, you can make your MQPUT and MQGET calls in the normal way, but you must declare syncpoints by using the MQCMIT and MQBACK calls (see Chapter 13, “Committing and backing out units of work” on page 183). In the CICS environment, MQCMIT and MQBACK commands are disabled as you can make your MQPUT and MQGET calls within units of work that are managed by CICS.

#### **Tandem NSK**

You can make your MQPUT and MQGET calls within units of work that are managed by Tandem’s TM/MP product.

#### **VSE/ESA**

CICS controls the unit of work in the VSE/ESA environment. If the system fails and is restarted, the logical unit of work rollback occurs automatically.

You should also use persistent messages for carrying all data you cannot afford to lose. Persistent messages are reinstated on queues if the queue manager has to recover from a failure. With MQSeries on UNIX systems, MQSeries for OS/2 Warp, and MQSeries for Windows NT, note that an MQGET or MQPUT call within your application will fail at the point of filling up all the log files, with the message MQRC\_RESOURCE\_PROBLEM. For more information on log files, see “Making sure that messages are not lost (logging)” in the *MQSeries System Administration Guide* for MQSeries for AIX, HP-UX, OS/2, Sun Solaris, and Windows NT; for other platforms, see the appropriate *System Management Guide*.

If the queue manager is stopped by an operator while an application is running, the quiesce option is normally used. The queue manager enters a quiescing state in which applications can continue to do work, but they should terminate as soon as it

is convenient. Small, quick applications can probably ignore the quiescing state and continue until they terminate as normal. Longer running applications, or ones that wait for messages to arrive, should use the *fail if quiescing* option when they use the MQCONN, MQPUT, MQPUT1, and MQGET calls. These options mean that the calls fail when the queue manager quiesces, but the application may still have time to terminate cleanly by issuing calls that ignore the quiescing state. Such applications could also commit, or back out, changes they have made, and then terminate.

If the queue manager is forced to stop (that is, stop without quiescing), applications will receive the MQRC\_CONNECTION\_BROKEN reason code when they make MQI calls. At this point you must exit the application or, alternatively, on MQSeries on UNIX systems, MQSeries for OS/2 Warp, and MQSeries for Windows NT, you can issue an MQDISC call.

## Messages containing incorrect data

When you use units of work in your application, if a program cannot successfully process a message that it retrieves from a queue, the MQGET call is backed out. The queue manager maintains a count (in the *BackoutCount* field of the message descriptor) of the number of times this happens. It maintains this count in the descriptor of each message that is affected. This count can provide valuable information about the efficiency of an application. Messages whose backout counts are increasing over time are being repeatedly rejected—you should design your application so that it analyzes the reasons for this and handles such messages accordingly.

In MQSeries for OS/390, to make the backout count survive restarts of the queue manager, set the *HardenGetBackout* attribute to MQQA\_BACKOUT\_HARDENED; otherwise, if the queue manager has to restart, it does not maintain an accurate backout count for each message. Setting the attribute this way adds the penalty of extra processing.

In MQSeries for AS/400, MQSeries for OS/2 Warp, MQSeries for Windows NT, and MQSeries on UNIX systems, the backout count always survives restarts of the queue manager.

Also, in MQSeries for OS/390, when you remove messages from a queue within a unit of work, you can mark one message so that it is *not* made available again if the unit of work is backed out *by the application*. The marked message is treated as if it has been retrieved under a new unit of work. You mark the message that is to skip backout using the MQGMO\_MARK\_SKIP\_BACKOUT option (in the MQGMO structure) when you use the MQGET call. See “Skipping backout” on page 150 for more information about this technique.

**Note:** In MQSeries for VSE/ESA, *BackoutCount* is a reserved field. It cannot be used as described in this section.

---

## Using report messages for problem determination

The remote queue manager cannot report errors such as failing to put a message on a queue when you make your MQI call, but it can send you a report message to say how it has processed your message.

## Remotely determined errors

Within your application you can create (MQPUT) report messages as well as select the option to receive them (in which case they will be sent by either another application or by a queue manager).

### Creating report messages

Report messages provide a mechanism for an application to inform another application that it is unable to deal with the message that was sent. However, the *Report* field must initially be analyzed to determine whether or not the application that sent the message is interested in being informed of any problems. Having determined that a report message is required, you have to decide:

- Whether you want to include all the original message (not an option on OS/390), just the first 100 bytes of data, or none of the original message.
- What to do with the original message. You can discard it or let it go to the dead-letter queue.
- Whether the contents of the *MsgId* and *CorrelId* fields are needed as well.

Use the *Feedback* field to indicate the reason for the report message being generated. Put your report messages on an application's reply-to queue. Refer to "MQMD - Message descriptor" in the *MQSeries Application Programming Reference* manual for further information.

### Requesting and receiving (MQGET) report messages

When you send a message to another application, you will not be informed of any problems unless you complete the *Report* field to indicate the feedback you require. The options available to you are in "MQMD - Message descriptor" in the *MQSeries Application Programming Reference* manual.

Queue managers always put report messages on an application's reply-to queue and it is recommended that your own applications do the same. When you use the report message facility you must specify the name of your reply-to queue in the message descriptor of your message; otherwise, the MQPUT call fails.

Your application should contain procedures that monitor your reply-to queue and process any messages that arrive on it. Remember that a report message can contain all the original message, the first 100 bytes of the original message, or none of the original message.

The queue manager sets the *Feedback* field of the report message to indicate the reason for the error; for example, the target queue does not exist. Your programs should do the same.

For more information on report messages, see "Report messages" on page 25.

---

## Remotely determined errors

When you send messages to a remote queue, even when the local queue manager has processed your MQI call without finding an error, other factors can influence how your message is handled by a remote queue manager. For example, the queue you are targeting may be full, or may not even exist. If your message has to be handled by other intermediate queue managers on the route to the target queue, any of these could find an error.

## Problems delivering a message

When an MQPUT call fails, you have the choice of attempting to put the message on the queue again, returning it to the sender, or putting it on the dead-letter queue.

Each option has its own merits, but you may not want to retry putting a message if the reason that the MQPUT failed was because the destination queue was full. In this instance, putting it on the dead-letter queue allows you to deliver it to the correct destination queue later on.

### Retry message delivery

Before the message is put on a dead-letter queue, a remote queue manager attempts to put the message on the queue again if the attributes *MsgRetryCount* and *MsgRetryInterval* have been set for the channel, or if there is a retry exit program for it to use (the name of which is held in the channel attribute *MsgRetryExitId* field).

If the *MsgRetryExitId* field is blank, the values in the attributes *MsgRetryCount* and *MsgRetryInterval* are used.

If the *MsgRetryExitId* field is not blank, the exit program of this name runs. For more information on using your own exit programs, see Chapter 35, “Channel-exit programs” in the *MQSeries Intercommunication* book.

### Return message to sender

You return a message to the sender by requesting a report message to be generated to include all of the original message. See “Report messages” on page 25 for details on report message options.

## Using the dead-letter (undelivered-message) queue

When a queue manager cannot deliver a message, it attempts to put the message on its dead-letter queue. This queue should be defined when the queue manager is installed.

Your programs can use the dead-letter queue in the same way that the queue manager uses it. You can find the name of the dead-letter queue by opening the queue manager object (using the MQCONN call) and inquiring about the *DeadLetterQName* attribute (using the MQINQ call).

When the queue manager puts a message on this queue, it adds a header to the message, the format of which is described by the dead-letter header (MQDLH) structure, in “MQDLH - Dead-letter header” in the *MQSeries Application Programming Reference* manual. This header includes the name of the target queue and the reason the message was put on the dead-letter queue. It must be removed and the problem must be resolved before the message is put on the intended queue. Also, the queue manager changes the *Format* field of the message descriptor (MQMD) to indicate that the message contains an MQDLH structure.

### MQDLH structure

You are recommended to add an MQDLH structure to all messages that you put on the dead-letter queue; however, if you intend to use the dead-letter handler provided by certain MQSeries products, you *must* add an MQDLH structure to your messages.

The addition of the header to a message may make the message too long for the dead-letter queue, so you should always make sure that your messages are shorter than the maximum size allowed for the dead-letter queue, by at least the value of the MQ\_MSG\_HEADER\_LENGTH constant. The maximum size of messages allowed on a queue is determined by the value of the *MaxMsgLength* attribute of the queue. For the dead-letter queue, you should make sure that this attribute is set to the maximum allowed by the queue manager. If your application cannot deliver a message, and the message is too long to be put on the dead-letter queue, follow the advice given in the description of the MQDLH structure.

You need to ensure that the dead-letter queue is monitored, and that any messages arriving on it get processed. A dead-letter queue handler is provided by MQSeries on all platforms except OS/390 and VSE/ESA. It runs as a batch utility and can be used to perform various actions on selected messages on the dead-letter queue. If you have a queue manager on one of the platforms that does not provide a dead-letter queue handler, you will need to provide your own. The program could be triggered, or run at regular intervals. For further details, see Chapter 12, “The MQSeries dead-letter queue handler” in the *MQSeries System Administration* Guide for MQSeries for AIX, HP-UX, OS/2, Sun Solaris, and Windows NT; for other platforms, see the appropriate *System Administration Guide*.

If data conversion is necessary, the queue manager converts the header information when you use the MQGMO\_CONVERT option on the MQGET call. If the process putting the message is an MCA, the header is followed by all the text of the original message.

You should be aware that messages put on the dead-letter queue may be truncated if they are too long for this queue. A possible indication of this situation is the messages on the dead-letter queue being the same length as the value of the *MaxMsgLength* attribute of the queue.

### Dead-letter queue processing

#### General-use programming interface

Dead-letter queue processing is dependent on local system requirements, but you should consider the following when you draw up the specification:

- The message can be identified as having a dead-letter queue header because the value of the format field in the MQMD, is MQFMT\_DEAD\_LETTER\_HEADER.
- In MQSeries for OS/390 using CICS, if an MCA puts this message to the dead-letter queue, the *PutApplType* field is MQAT\_CICS, and the *PutApplName* field is the *ApplId* of the CICS system followed by the transaction name of the MCA.

- The reason for the message to be routed to the dead-letter queue is contained in the *Reason* field of the dead-letter queue header.
- The dead-letter queue header contains details of the destination queue name and queue manager name.
- The dead-letter queue header contains fields that have to be reinstated in the message descriptor before the message is put to the destination queue. These are:
  1. *Encoding*
  2. *CodedCharSetId*
  3. *Format*
- The message descriptor is the same as PUT by the original application, except for the three fields shown above.

Your dead-letter queue application should do one or more of the following:

- Examine the *Reason* field. A message may have been put by an MCA for the following reasons:
  - The message was longer than the maximum message size for the channel  
The reason will be MQRC\_MSG\_TOO\_BIG\_FOR\_CHANNEL (or MQRC\_MSG\_TOO\_BIG\_FOR\_Q\_MGR if you are using CICS for distributed queuing on MQSeries for OS/390)
  - The message could not be put to its destination queue  
The reason will be any MQRC\_\* reason code that can be returned by an **MQPUT** operation
  - A user exit has requested this action  
The reason code will be that supplied by the user exit, or the default MQRC\_SUPPRESSED\_BY\_EXIT
- Try to forward the message to its intended destination, where this is possible.
- Retain the message for a certain length of time before discarding when the reason for the diversion is determined, but not immediately correctable.
- Give instructions to administrators for the correction of problems where these have been determined.
- Discard messages that are corrupted or otherwise not processible.

There are two ways that you deal with the messages you have recovered from the dead-letter queue:

1. If the message is for a local queue, you should:
  - Carry out any code translations required to extract the application data
  - Carry out code conversions on that data if this is a local function
  - Put the resulting message on the local queue with all the detail of the message descriptor restored
2. If the message is for a remote queue, put the message on the queue.

\_\_\_\_\_ End of General-use programming interface \_\_\_\_\_

## Remotely determined errors

| For information on how undelivered messages are handled in a distributed queuing  
| environment, see “What happens when a message cannot be delivered?” in the  
| *MQSeries Intercommunication* book.

---

## Part 2. Writing an MQSeries application

<b>Chapter 6. Introducing the Message Queue Interface</b>	65
What is in the MQI?	65
Calls	66
Syncpoint calls	67
Data conversion	68
Structures	68
Elementary data types	68
MQSeries data definitions	69
MQSeries stub programs and library files	69
Parameters common to all the calls	73
Using connection and object handles	74
Understanding return codes	74
Specifying buffers	74
Programming language considerations	75
Coding in C	76
Coding in COBOL	78
Coding in System/390® assembler language	79
Specifying the form of a structure	81
Coding in RPG	82
Coding in PL/I	83
Coding in TAL	84
OS/390 batch considerations	84
UNIX signal handling on MQSeries Version 5 products	85
Unthreaded applications	86
Threaded applications	86
Fastpath (trusted) applications	87
MQI function calls within signal handlers	87
Signals during MQI calls	88
User exits and installable services	88
<b>Chapter 7. Connecting and disconnecting a queue manager</b>	89
Connecting to a queue manager using the MQCONN call	90
Scope of MQCONN	91
Connecting to a queue manager using the MQCONNX call	92
MQCNO_STANDARD_BINDING	92
MQCNO_FASTPATH_BINDING	92
Restrictions	93
Environment variable	94
Disconnecting programs from a queue manager using MQDISC	94
Authority checking	95
<b>Chapter 8. Opening and closing objects</b>	97
Opening objects using the MQOPEN call	98
Scope of an object handle	98
Identifying objects (the MQOD structure)	99
Name resolution	99
Using the options of the MQOPEN call	101
Creating dynamic queues	104
Opening remote queues	105
Closing objects using the MQCLOSE call	105

<b>Chapter 9. Putting messages on a queue</b>	107
Putting messages on a local queue using the MQPUT call	107
Specifying handles	108
Defining messages using the MQMD structure	108
Specifying options using the MQPMO structure	108
The data in your message	111
Putting messages on a remote queue	112
Controlling context information	113
Passing identity context	113
Passing all context	114
Setting identity context	114
Setting all context	114
Putting one message on a queue using the MQPUT1 call	114
Distribution lists	116
Opening distribution lists	116
Putting messages to a distribution list	119
Some cases where the put calls fail	121
<b>Chapter 10. Getting messages from a queue</b>	123
Getting messages from a queue using the MQGET call	123
Specifying connection handles	124
Describing messages using the MQMD structure and the MQGET call	124
Specifying MQGET options using the MQGMO structure	125
Specifying the size of the buffer area	127
The order in which messages are retrieved from a queue	128
Priority	128
Logical and physical ordering	129
Getting a particular message	137
Type of index	139
Handling large messages	140
Increasing the maximum message length	140
Message segmentation	141
Reference messages	144
Waiting for messages	146
Signaling	147
To set a signal	147
When the message arrives	148
Skipping backout	150
Application data conversion	152
Conversion of EBCDIC newline characters	153
Browsing messages on a queue	154
The browse cursor	154
Browsing messages when message length unknown	155
Removing a message you have browsed	156
Browsing messages in logical order	156
Some cases where the MQGET call fails	159
<b>Chapter 11. Writing data-conversion exits</b>	161
Invoking the data-conversion exit	161
Data conversion on OS/390	162
Writing a data-conversion exit program	163
Skeleton source file	164
Convert characters call	164
Utility for creating conversion-exit code	164

Valid syntax	166
Writing a data-conversion exit program for MQSeries for AS/400	167
Writing a data-conversion exit for MQSeries for OS/2 Warp	168
Writing a data-conversion exit program for MQSeries for OS/390	170
Writing a data-conversion exit for MQSeries for Tandem NSK	171
Reusing data-conversion exit programs	172
Writing a data-conversion exit for MQSeries on UNIX systems and Digital OpenVMS	172
UNIX environment	174
Compiling data-conversion exits on Digital OpenVMS	174
Compiling data-conversion exits on UNIX	175
Writing a data-conversion exit for MQSeries for Windows NT	177
<b>Chapter 12. Inquiring about and setting object attributes</b>	179
Inquiring about the attributes of an object	180
Some cases where the MQINQ call fails	181
Setting queue attributes	182
<b>Chapter 13. Committing and backing out units of work</b>	183
Syncpoint considerations in MQSeries applications	184
Syncpoints in MQSeries for OS/390 applications	185
Syncpoints in CICS Transaction Server for OS/390 and CICS for MVS/ESA applications	185
Syncpoints in IMS applications	186
Syncpoints in OS/390 batch applications	186
Syncpoints in MQSeries for AS/400 applications	188
Syncpoints in CICS for AS/400 applications	189
Syncpoints in MQSeries for OS/2 Warp, MQSeries for Windows NT, MQSeries for Digital OpenVMS, and MQSeries on UNIX systems	189
Local units of work	189
Global units of work	190
Interfaces to external syncpoint managers	192
Syncpoints in MQSeries for Tandem NSK applications	194
General XA support	195
<b>Chapter 14. Starting MQSeries applications using triggers</b>	197
What is triggering?	197
Prerequisites for triggering	202
Conditions for a trigger event	204
Controlling trigger events	208
Example of the use of trigger type EVERY	209
Example of the use of trigger type FIRST	209
Example of the use of trigger type DEPTH	209
Special case of trigger type FIRST	210
Designing an application that uses triggered queues	210
Trigger messages and units of work	210
Getting messages from a triggered queue	211
Trigger monitors	212
MQSeries for OS/390 trigger monitors	212
MQSeries for AS/400 trigger monitors	213
MQSeries for OS/2 Warp, Digital OpenVMS, Tandem NSK, UNIX systems, and Windows NT trigger monitors	213
Properties of trigger messages	215

Persistence and priority of trigger messages	215
Queue manager restart and trigger messages	215
Trigger messages and changes to object attributes	216
Format of trigger messages	216
When triggering does not work	217
How CKTI detects errors	217
How CSQQTRMN detects errors	217
How RUNMQTRM detects errors	218

## **Chapter 15. Using and writing applications on MQSeries for OS/390** . . . 219

Environment-dependent MQSeries for OS/390 functions	219
Program debugging facilities	220
Syncpoint support	220
Recovery support	220
The MQSeries for OS/390 interface with the application environment	221
The batch adapter	221
RRS batch adapter	221
The CICS adapter	222
The IMS adapter	224
Writing OS/390 OpenEdition® applications	224
The API-crossing exit for OS/390	225
Using the API-crossing exit	226
Writing your own exit program	227
The sample API-crossing exit program, CSQCAPX	229
Writing MQSeries-CICS bridge applications	230
Structure of the MQSeries message	231
Handling a unit of work	233
Programming considerations for running 3270 transactions	234
Examples	234
Writing MQSeries-IMS bridge applications	239
How the MQSeries-IMS bridge deals with messages	239
Writing your program	243
Writing IMS applications using MQSeries	245
Syncpoints in IMS applications	245
MQI calls in IMS applications	246
MQSeries Workflow	249

## **Chapter 16. Object-oriented programming with MQSeries** . . . 251

What is in the MQSeries Object Model?	251
Classes	251
Object references	252
Return codes	252
Programming language considerations	253
Coding in C++	253
Coding in Java	253
Coding in LotusScript	253
Coding in ActiveX	253

---

## Chapter 6. Introducing the Message Queue Interface

This chapter introduces the features of the Message Queue Interface (MQI).

The remaining chapters in this part of the book describe how to use these features. Detailed descriptions of the calls, structures, data types, return codes, and constants are given in the *MQSeries Application Programming Reference* manual.

---

### What is in the MQI?

The Message Queue Interface comprises the following:

- *Calls* through which programs can access the queue manager and its facilities
- *Structures* that programs use to pass data to, and get data from, the queue manager
- *Elementary data types* for passing data to, and getting data from, the queue manager

MQSeries for OS/390 also supplies:

- Two extra calls through which OS/390 batch programs can commit and back out changes.
- *Data definition files* (sometimes known as copy files, macros, include files, and header files) that define the values of constants supplied with MQSeries for OS/390.
- *Stub programs* to link-edit to your applications.
- A suite of sample programs that demonstrate how to use the MQI on the OS/390 platform. For further information about these samples, see Chapter 32, "Sample programs for MQSeries for OS/390" on page 395.

MQSeries for AS/400 also supplies:

- *Data definition files* (sometimes known as copy files, macros, include files, and header files) that define the values of constants supplied with MQSeries for AS/400.
- A stub program to link-edit to your C/400® applications.
- A suite of sample programs that demonstrate how to use the MQI on the AS/400 platform. For further information about these samples, see Chapter 31, "Sample programs (all platforms except OS/390)" on page 327.

MQSeries for OS/2 Warp, MQSeries for Windows NT, MQSeries for Digital OpenVMS, and MQSeries on UNIX systems also supply:

- Calls through which MQSeries for OS/2 Warp and MQSeries on UNIX systems programs can commit and back out changes.
- *Include files* that define the values of constants supplied on these platforms.
- *Library files* to link your applications.
- A suite of sample programs that demonstrate how to use the MQI on these platforms.

## MQI

- Sample source and executable code for bindings to external transaction managers.

MQSeries for Tandem NSK also supplies:

- *Include files* that define the values of constants supplied with MQSeries for Tandem NSK.
- *Library files* to link your applications.
- A suite of sample programs that demonstrate how to use the MQI on the Tandem NSK platform.

MQSeries for VSE/ESA also supplies:

- *Include files* that define the values of constants supplied with MQSeries for VSE/ESA.
- A suite of sample programs that demonstrate how to use the MQI on the VSE/ESA platform.

MQSeries for Windows provides a subset of the MQI. For more information, see the following:

- *MQSeries for Windows V2.0 User's Guide.*
- *MQSeries for Windows V2.1 User's Guide.*

## Calls

The calls in the MQI can be grouped as follows:

### **MQCONN, MQCONNX, and MQDISC**

Use these calls to connect a program to (with or without options), and disconnect a program from, a queue manager. If you write CICS programs for MQSeries for OS/390, OS/400, or VSE/ESA, you do not need to use these calls. However, you are recommended to use them if you want your application to be portable to other platforms.

### **MQOPEN and MQCLOSE**

Use these calls to open and close an object, such as a queue.

### **MQPUT and MQPUT1**

Use these calls to put a message on a queue.

**MQGET** Use this call to browse messages on a queue, or to remove messages from a queue.

**MQINQ** Use this call to inquire about the attributes of an object.

**MQSET** Use this call to set some of the attributes of a queue. You cannot set the attributes of other types of object.

### **MQBEGIN, MQCMIT, and MQBACK**

Use these calls to start and commit a global unit of work (where coordination is performed by MQSeries) and indicate to the queue manager that all messages put or retrieved as part of a unit of work since the last syncpoint are to be backed out.

The MQI calls are described fully in Chapter 3, "Call descriptions" in the *MQSeries Application Programming Reference* manual.

## Syncpoint calls

Syncpoint calls are available as follows:

### MQSeries for OS/390 calls

MQSeries for OS/390 provides the MQCMIT and MQBACK calls. Use these calls in OS/390 batch programs to tell the queue manager that all the MQGET and MQPUT operations since the last syncpoint are to be made permanent (committed) or are to be backed out. To commit and back out changes in other environments:

CICS	Use commands such as EXEC CICS SYNCPOINT and EXEC CICS SYNCPOINT ROLLBACK.
IMS	Use the IMS syncpoint facilities, such as the GU (get unique) to the IOPCB, CHKP (checkpoint), and ROLB (rollback) calls.
RRS	Use MQCMIT and MQBACK or SRRCMIT and SRRBACK as appropriate. (See “Transaction management and recoverable resource manager services” on page 187.)
	<b>Note:</b> SRRCMIT and SRRBACK are ‘native’ RRS commands, they are not MQI calls.

For backward compatibility, the CSQBCMT and CSQBBAK calls are available as synonyms for MQCMIT and MQBACK. These are described fully in “MQBACK - Back out changes” and “MQCMIT - Commit changes” in the *MQSeries Application Programming Reference* manual.

### OS/400 calls

Use the OS/400 COMMIT and ROLLBACK commands, or any other commands or calls that initiate the OS/400 commitment control facilities (for example, EXEC CICS SYNCPOINT).

### MQSeries for Tandem NSK calls

The default SYNCPOINT option for the MQPUT and MQGET calls is SYNCPOINT, rather than NO\_SYNCPOINT. To use the default (SYNCPOINT) option for MQPUT, MQGET and MQPUT1 operations, the application must have an active TM/MP Transaction that defines the unit of work to be committed.

### MQSeries for VSE/ESA calls

Use CICS commands such as EXEC CICS SYNCPOINT and EXEC CICS SYNCPOINT ROLLBACK. The batch interface and server support the MQCMIT and MQBACK calls which are translated into the CICS commands EXEC CICS SYNCPOINT and EXEC CICS SYNCPOINT ROLLBACK respectively. Use these calls in programs to tell the queue manager that all the MQGET and MQPUT operations since the last syncpoint are to be made permanent (committed) or are to be backed out.

### MQSeries calls on other platforms

The following products provide the MQCMIT and MQBACK calls:

- MQSeries for OS/2 Warp
- MQSeries for Windows
- MQSeries for Windows NT
- MQSeries for Digital OpenVMS
- MQSeries on UNIX systems

## MQI

Use syncpoint calls in programs to tell the queue manager that all the MQGET and MQPUT operations since the last syncpoint are to be made permanent (committed) or are to be backed out. To commit and back out changes in the CICS environment, use commands such as EXEC CICS SYNCPOINT and EXEC CICS SYNCPOINT ROLLBACK.

## Data conversion

The MQXCNVC - convert characters call is used only from a data-conversion exit. This call converts message character data from one character set to another.

See “MQXCNVC - Convert characters” in the *MQSeries Application Programming Reference* manual for the syntax used with the MQXCNVC call, and Chapter 11, “Writing data-conversion exits” on page 161 for guidance on writing and invoking data conversion exits.

## Structures

Structures, used with the MQI calls listed in “Calls” on page 66, are supplied in data definition files for each of the supported programming languages. MQSeries for OS/390 and MQSeries for AS/400 supply files that contain constants for you to use when filling in some of the fields of these structures. For more information on these, see “MQSeries data definitions” on page 69.

All the structures are described fully in Chapter 2, “Data type descriptions - structures” in the *MQSeries Application Programming Reference* manual.

## Elementary data types

For the C language, the MQI provides the following elementary data types or unstructured fields:

MQBYTE	A single byte of data
MQBYTEn	A string of 16, 24, 32, 40, or 64 bytes
MQCHAR	One single-byte character
MQCHARn	A string of 4, 8, 12, 16, 20, 28, 32, 48, 64, 128, or 256 single-byte characters
MQHCONN	A connection handle (this data is 32 bits long)
MQHOBJ	An object handle (this data is 32 bits long)
MQLONG	A 32-bit signed binary integer
PMQLONG	A pointer to data of type MQLONG

These data types are described fully in Chapter 1, “Data type descriptions - elementary” in the *MQSeries Application Programming Reference* manual.

Table 1 on page 69 shows the Visual Basic equivalents of the C elementary data types.

Table 1. Visual Basic equivalents of the C elementary data types

C data type	Visual Basic data type
MQBYTE	String * 1
MQBYTEn	String * n
MQCHAR	String * 1
MQCHARn	String * n
MQHCONN	Long
MQHOBJ	Long
MQLONG	Long
PMQLONG	No equivalent

For COBOL, assembler, PL/I, or RPG, use the equivalent declarations shown in the same manuals.

## MQSeries data definitions

MQSeries for OS/390 supplies data definitions in the form of COBOL copy files, assembler-language macros, a single PL/I include file, a single C language include file, and C++ language include files.

MQSeries for AS/400 supplies data definitions in the form of COBOL copy files, RPG copy files, C language include files, and C++ language include files.

MQSeries for VSE/ESA supplies data definitions in the form of a C language include file, COBOL copy files, and PL/I include files.

The data definition files supplied with MQSeries contain:

- Definitions of all the MQSeries constants and return codes
- Definitions of the MQSeries structures and data types
- Constant definitions for initializing the structures
- Function prototypes for each of the calls (for PL/I and the C language only)

For a full description of MQSeries data definition files, see Appendix G, “MQSeries data definition files” on page 529.

## MQSeries stub programs and library files

The stub programs and library files provided are listed here, for each platform.

For more information about how to use stub programs and library files when you build an executable application, see Part 3, “Building an MQSeries application” on page 255. For information about linking to C++ library files, see the *MQSeries Using C++* book.

### MQSeries for OS/390

Before you can run an MQSeries for OS/390 program, you must link-edit it to the stub program supplied with MQSeries for OS/390 for the environment in which you are running the application. The stub program provides the first stage of the processing of your calls into requests that MQSeries for OS/390 can process.

MQSeries for OS/390 supplies the following stub programs:

<b>CSQBSTUB</b>	Stub program for OS/390 batch programs
<b>CSQBRRSI</b>	Stub program for OS/390 batch programs using RRS by way of the MQI
<b>CSQBRSTB</b>	Stub program for OS/390 batch programs using RRS directly
<b>CSQCSTUB</b>	Stub program for CICS programs
<b>CSQQSTUB</b>	Stub program for IMS programs
<b>CSQXSTUB</b>	Stub program for distributed queuing non-CICS exits
<b>CSQASTUB</b>	Stub program for data-conversion exits

**Note:** If you use the CSQBRSTB stub program you must link-edit with ATRSCSS from SYS1.CSSLIB. (SYS1.CSSLIB is also known as the “Callable Services Library”.) For more information about RRS see “Transaction management and recoverable resource manager services” on page 187.

Alternatively, you can dynamically call the stub from within your program. This technique is described in “Dynamically calling the MQSeries stub” on page 279.

In IMS, you may also need to use a special language interface module that is supplied by MQSeries.

### MQSeries for AS/400

In MQSeries for AS/400, you must bind your ILE C/400 programs and RPG/400® static calls to the supplied AMQZSTUB service program.

If you are using MQSeries for AS/400 you can write your applications in C++. To see how to link your C++ applications, and for full details of all aspects of using C++, see the book *MQSeries Using C++*.

### MQSeries for OS/2 Warp

In MQSeries for OS/2 Warp, you must link your program to the MQI library files supplied for the environment in which you are running your application, in addition to those provided by the operating system:

<b>MQM.LIB</b>	Server for 32-bit C
<b>MQIC.LIB</b>	Client for C
<b>MQMXA.LIB</b>	Static XA interface for C
<b>MQMCICS.LIB</b>	CICS for OS/2 V2 exits for C
<b>MQMCICS3.LIB</b>	CICS Transaction Server for OS/2, V4 exits
<b>MQMZFLIB</b>	Installable services exits for C
<b>MQICCB16.LIB</b>	Client for 16-bit Micro Focus COBOL
<b>MQMCB16.LIB</b>	Server for 16-bit Micro Focus COBOL
<b>MQMCBB.LIB</b>	Server for 32-bit IBM VisualAge® COBOL
<b>MQMCB32.LIB</b>	Server for 32-bit Micro Focus COBOL
<b>MQICCB.LIB</b>	Client for 32-bit IBM VisualAge COBOL
<b>MQICCB32.LIB</b>	Client for 32-bit Micro Focus COBOL
<b>IMQ*.LIB</b>	Server for C++

### MQSeries for Windows

In MQSeries for Windows, you must link your program to the MQI library files supplied for the environment in which you are running your application, in addition to those provided by the operating system:

<b>MQM16.LIB</b>	Server for 16-bit C
<b>MQM.LIB</b>	Server for 32-bit C

## MQSeries for Windows NT

In MQSeries for Windows NT, you must link your program to the MQI library files supplied for the environment in which you are running your application, in addition to those provided by the operating system:

<b>MQM.LIB</b>	Server for 32-bit C
<b>MQIC.LIB</b>	Client for 16-bit C
<b>MQIC32.LIB</b>	Client for 32-bit C
<b>MQMXA.LIB</b>	Static XA interface for C
<b>MQMCICS.LIB</b>	CICS for Windows NT V2 exits for C
<b>MQMCICS4.LIB</b>	TXSeries for Windows NT, V4 exits for C
<b>MQMZF.LIB</b>	Installable services exits for C
<b>MQMCBB.LIB</b>	Server for 32-bit IBM COBOL
<b>MQMCB32</b>	Server for 32-bit Micro Focus COBOL
<b>MQICCB.LIB</b>	Client for 32-bit IBM COBOL
<b>MQICCB32</b>	Client for 32-bit Micro Focus COBOL
<b>IMQ*.LIB</b>	Server for C++
<b>MQMENC.LIB</b>	Dynamic XA interface in C for Encina
<b>MQMTUX.LIB</b>	Dynamic XA interface in C for Tuxedo

## MQSeries for AIX

In MQSeries for AIX, you must link your program to the MQI library files supplied for the environment in which you are running your application, in addition to those provided by the operating system.

In a non-threaded application:

<b>libmqm.a</b>	Server for C
<b>libmqic.a</b>	Client for C
<b>libmqmzf.a</b>	Installable service exits for C
<b>libmqmxa.a</b>	XA interface for C
<b>libmqmcbt.o</b>	MQSeries run-time library for Micro Focus COBOL support
<b>libmqmcb.a</b>	Server for COBOL
<b>libmqicb.a</b>	Client for COBOL
<b>libimq*.a</b>	Client for C++

In a threaded application:

<b>libmqm_r.a</b>	Server for C
<b>libmqmzf_r.a</b>	Installable service exits for C
<b>libmqmxa_r.a</b>	XA interface for C
<b>libimq*_r.a</b>	Client for C++
<b>libmqmxa_r.a</b>	For Encina

## MQSeries for AT&T GIS UNIX

In MQSeries for AT&T GIS UNIX, you must link your program to the MQI library files supplied for the environment in which you are running your application, in addition to those provided by the operating system.

<b>libmqm.so</b>	Server for C
<b>libmqmzse.so</b>	For C
<b>libmqic.so</b>	Client for C
<b>libmqmcs.so</b>	Client for C
<b>libmqmzf.so</b>	Installable service exits for C
<b>libmqmxa.a</b>	XA interface for C

## MQSeries for Digital OpenVMS

In MQSeries for Digital OpenVMS, you must link your program to the MQI library files supplied for the environment in which you are running your application, in addition to those provided by the operating system:

<b>mqm.exe</b>	Server for C
<b>mqjc.exe</b>	Client for C
<b>mqmzf.exe</b>	Installable service exits for C
<b>mqmxa.exe</b>	XA interface for C
<b>mqcbrt.exe</b>	MQSeries COBOL run-time
<b>mqmcb.exe</b>	Server for COBOL
<b>mqicb.exe</b>	Client for COBOL

## MQSeries for HP-UX

In MQSeries for HP-UX, you must link your program to the MQI library files supplied for the environment in which you are running your application, in addition to those provided by the operating system.

In a non-threaded application:

<b>libmqm.sl</b>	Server for C
<b>libmqjc.sl</b>	Client for C
<b>libmqmzf.sl</b>	Installable service exits for C
<b>libmqmxa.sl</b>	XA interface for C
<b>libmqmcbrt.o</b>	MQSeries run-time library for Micro Focus COBOL support
<b>libmqmcb.sl</b>	Server for COBOL
<b>libmqicb.sl</b>	Client for COBOL

In a threaded application:

<b>libmqm_r.sl</b>	Server for C
<b>libmqmzf_r.sl</b>	Installable service exits for C
<b>libmqmxa_r.sl</b>	XA interface for C

## MQSeries for SINIX and DC/OSx

In MQSeries for SINIX and DC/OSx, you must link your program to the MQI library files supplied for the environment in which you are running your application, in addition to those provided by the operating system.

In a non-threaded application:

<b>libmqm.so</b>	Server for C
<b>libmqmzse.so</b>	For C
<b>libmqjc.so</b>	Client for C
<b>libmqmcs.so</b>	Client for C
<b>libmqmzf.so</b>	Installable service exits for C
<b>libmqmxa.a</b>	XA interface for C
<b>libmqmcbrt.o</b>	MQSeries COBOL run-time
<b>libmqmcb.so</b>	Server for COBOL
<b>libmqicb.so</b>	Client for COBOL

In a threaded application:

<b>libmqm_r.so</b>	For C
<b>libmqmcs_r.so</b>	For C
<b>libmqmcics_r.so</b>	For CICS
<b>libmqmxa_r.a</b>	For XA interface in C

**DOS and Windows 3.1 clients**

In DOS and Windows 3.1, you must link your program to the MQIC.LIB library file (or imq\*vw.lib for C++), followed by the protocol libraries, indicating the protocol you do and do not want.

<b>mqicn.lib</b>	NetBIOS required
<b>mqicdn.lib</b>	NetBIOS not required
<b>mqict.lib</b>	TCP/IP required
<b>mqicdt.lib</b>	TCP/IP not required

<b>libmqm.so</b>	Server for C
<b>libmqmzse.so</b>	For C
<b>libmqic.so</b>	Client for C
<b>libmqmcs.so</b>	Client for C
<b>libmqmzf.so</b>	Installable service exits for C
<b>libmqmxa.a</b>	XA interface for C
<b>imq*.so</b>	C++

**MQSeries for Sun Solaris**

In MQSeries for Sun Solaris, you must link your program to the MQI library files supplied for the environment in which you are running your application in addition to those provided by the operating system.

<b>libmqm.so</b>	Server for C
<b>libmqmzse.so</b>	For C
<b>libmqic.so</b>	Client for C
<b>libmqmcs.so</b>	Client for C
<b>libmqmzf.so</b>	Installable service exits for C
<b>libmqmxa.a</b>	XA interface for C
<b>imq*.so</b>	C++

**MQSeries for VSE/ESA**

In MQSeries for VSE/ESA you must link your program to the install sublibrary PRD2.MQSERIES (this is its default name). This sublibrary contains all the required object decks.

**MQSeries for Tandem NSK**

In MQSeries for Tandem NSK, you must link your program to the MQI library files supplied for the environment in which you are running your application in addition to those provided by the operating system.

<b>mqmlibc</b>	For C, nonnative
<b>mqmlibt</b>	For TAL or COBOL, nonnative
<b>mqmlibnc</b>	For native C
<b>mqmlibnt</b>	For native TAL or COBOL

---

**Parameters common to all the calls**

There are two types of parameter common to all the calls: handles and return codes.

### Using connection and object handles

For a program to communicate with a queue manager, the program must have a unique identifier by which it knows that queue manager. This identifier is called a *connection handle*. For CICS and OS/400 programs, the connection handle is always zero. For all other platforms or styles of programs, the connection handle is returned by the MQCONN or MQCONNX call when the program connects to the queue manager. Programs pass the connection handle as an input parameter when they use the other calls.

For a program to work with an MQSeries object, the program must have a unique identifier by which it knows that object. This identifier is called an *object handle*. The handle is returned by the MQOPEN call when the program opens the object to work with it. Programs pass the object handle as an input parameter when they use subsequent MQPUT, MQGET, MQINQ, MQSET, or MQCLOSE calls.

### Understanding return codes

A completion code and a reason code are returned as output parameters by each call. These are known collectively as *return codes*.

To show whether or not a call is successful, each call returns a *completion code* when the call is complete. The completion code is usually either MQCC\_OK or MQCC\_FAILED, showing success and failure, respectively. Some calls can return an intermediate state, MQCC\_WARNING, indicating partial success.

Each call also returns a *reason code* that shows the reason for the failure, or partial success, of the call. There are many reason codes, covering such circumstances as a queue being full, get operations not being allowed for a queue, and a particular queue not being defined for the queue manager. Programs can use the reason code to decide how to proceed. For example, they could prompt the user of the program to make changes to his input data, then make the call again, or they could return an error message to the user.

When the completion code is MQCC\_OK, the reason code is always MQRC\_NONE.

The completion and reason codes for each call are listed with the description of that call in the *MQSeries Application Programming Reference*

You will also find further information (including some ideas for corrective action) for each completion and reason code, in Chapter 5, "Return codes" in the *MQSeries Application Programming Reference* manual.

---

### Specifying buffers

The queue manager refers to buffers only if they are required. If you do not require a buffer on a call or the buffer is zero in length, you can use a null pointer to a buffer.

Always use datalength when specifying the size of the buffer you require.

When you use a buffer to hold the output from a call (for example, to hold the message data for an MQGET call, or the values of attributes queried by the MQINQ call), the queue manager attempts to return a reason code if the buffer you specify

is not valid or is in read-only storage. However, it may not be able to return a reason code in some situations.

---

### Programming language considerations

MQSeries provides support for the following programming languages:

- C.
- C++ (MQSeries for AIX, AS/400, HP-UX, OS/2, OS/390, Sun Solaris, and Windows NT only). See the *MQSeries Using C++* book for information about coding MQSeries programs in C++.
- Visual Basic (MQSeries for Windows and Windows NT only). See the *MQSeries for Windows Version 2.0 User's Guide* and the *MQSeries for Windows Version 2.1 User's Guide* for information about coding MQSeries programs in Visual Basic.
- COBOL.
- Assembler language (MQSeries for OS/390 only).
- RPG (MQSeries for AS/400 only).
- PL/I (MQSeries for OS/390, AIX, OS/2 Warp, VSE/ESA, and Windows NT only).
- TAL (MQSeries for Tandem NSK only).

The call interface, and how you can code the calls in each of these languages, is described in Chapter 3, "Call descriptions" in the *MQSeries Application Programming Reference* manual.

MQSeries provides data definition files to assist you with the writing of your applications. For a full description, see Appendix G, "MQSeries data definition files" on page 529.

If you can choose which language to code your programs in, you should consider the maximum length of the messages that your programs will process. If your programs will process only messages of a known maximum length, you can code them in any of the supported programming languages. But if you do not know the maximum length of the messages the programs will have to process, the language you choose will depend on whether you are writing a CICS, IMS, or batch application:

#### IMS and batch

Code the programs in C, PL/I, or assembler language to use the facilities these languages offer for obtaining and releasing arbitrary amounts of memory. Alternatively, you could code your programs in COBOL, but use assembler language, PL/I, or C subroutines to get and release storage.

#### CICS

Code the programs in any language supported by CICS. The EXEC CICS interface provides the calls for managing memory, if necessary.

### Coding in C

See Appendix A, “Language compilers and assemblers” on page 453 for the compilers that you can use to process your C programs.

Note the information in the following sections when coding MQSeries programs in C.

#### Parameters of the MQI calls

Parameters that are *input-only* and of type MQHCONN, MQHOBJ, or MQLONG are passed by value; for all other parameters, the *address* of the parameter is passed by value.

Not all parameters that are passed by address need to be specified every time a function is invoked. Where a particular parameter is not required, a null pointer can be specified as the parameter on the function invocation, in place of the address of the parameter data. Parameters for which this is possible are identified in the call descriptions.

No parameter is returned as the value of the function; in C terminology, this means that all functions return void.

The attributes of the function are defined by the MQENTRY macro variable; the value of this macro variable depends on the environment.

#### Parameters with undefined data type

The MQGET, MQPUT, and MQPUT1 functions each have one parameter that has an undefined data type, namely the *Buffer* parameter. This parameter is used to send and receive the application’s message data.

Parameters of this sort are shown in the C examples as arrays of MQBYTE. It is valid to declare the parameters in this way, but it is usually more convenient to declare them as the particular structure that describes the layout of the data in the message. The function parameter is declared as a pointer-to-void, and so the address of any sort of data can be specified as the parameter on the function invocation.

#### Data types

All data types are defined by means of the typedef statement. For each data type, the corresponding pointer data type is also defined. The name of the pointer data type is the name of the elementary or structure data type prefixed with the letter “P” to denote a pointer. The attributes of the pointer are defined by the MQPOINTER macro variable; the value of this macro variable depends on the environment. The following illustrates how pointer data types are declared:

```
#define MQPOINTER          /* depends on environment */
...
typedef MQLONG MQPOINTER PMQLONG; /* pointer to MQLONG */
typedef MQMD MQPOINTER PMQMD; /* pointer to MQMD */
```

## Manipulating binary strings

Strings of binary data are declared as one of the MQBYTE $n$  data types. Whenever you copy, compare, or set fields of this type, use the C functions `memcpy`, `memcmp`, or `memset`:

```
#include <string.h>
#include "cmqc.h"

MQMD MyMsgDesc;

memcpy(MyMsgDesc.MsgId,          /* set "MsgId" field to nulls */
       MQMI_NONE,              /* ...using named constant */
       sizeof(MyMsgDesc.MsgId));

memset(MyMsgDesc.CorrelId,      /* set "CorrelId" field to nulls */
       0x00,                  /* ...using a different method */
       sizeof(MQBYTE24));
```

Do not use the string functions `strcpy`, `strcmp`, `strncpy`, or `strncmp` because these do not work correctly with data declared as MQBYTE24.

## Manipulating character strings

When the queue manager returns character data to the application, the queue manager always pads the character data with blanks to the defined length of the field. The queue manager **does not** return null-terminated strings, but you can use them in your input. Therefore, when copying, comparing, or concatenating such strings, use the string functions `strncpy`, `strncmp`, or `strncat`.

Do not use the string functions that require the string to be terminated by a null (`strcpy`, `strcmp`, and `strcat`). Also, do not use the function `strlen` to determine the length of the string; use instead the `sizeof` function to determine the length of the field.

## Initial values for structures

The include file `<cmqc.h>` defines various macro variables that may be used to provide initial values for the structures when instances of those structures are declared. These macro variables have names of the form MQxxx\_DEFAULT, where MQxxx represents the name of the structure. Use them like this:

```
MQMD MyMsgDesc = {MQMD_DEFAULT};
MQPMO MyPutOpts = {MQPMO_DEFAULT};
```

For some character fields, the MQI defines particular values that are valid (for example, for the *StrucId* fields or for the *Format* field in MQMD). For each of the valid values, two macro variables are provided:

- One macro variable defines the value as a string whose length, excluding the implied null, matches exactly the defined length of the field. For example, (the symbol `b` represents a blank character):

```
#define MQMD_STRUC_ID "MDbb"
#define MQFMT_STRING "MQSTRbbb"
```

Use this form with the `memcpy` and `memcmp` functions.

- The other macro variable defines the value as an array of `char`; the name of this macro variable is the name of the string form suffixed with `"_ARRAY"`.

## Programming language considerations

For example:

```
#define MQMD_STRUC_ID_ARRAY 'M','D','b','b'  
#define MQFMT_STRING_ARRAY 'M','Q','S','T','R','b','b','b'
```

Use this form to initialize the field when an instance of the structure is declared with values different from those provided by the MQMD\_DEFAULT macro variable.

### Initial values for dynamic structures

When a variable number of instances of a structure are required, the instances are usually created in main storage obtained dynamically using the calloc or malloc functions. To initialize the fields in such structures, the following technique is recommended:

1. Declare an instance of the structure using the appropriate MQxxx\_DEFAULT macro variable to initialize the structure. This instance becomes the “model” for other instances:

```
MQMD ModelMsgDesc = {MQMD_DEFAULT};  
/* declare model instance */
```

The static or auto keywords can be coded on the declaration in order to give the model instance static or dynamic lifetime, as required.

2. Use the calloc or malloc functions to obtain storage for a dynamic instance of the structure:

```
PMQMD InstancePtr;  
InstancePtr = malloc(sizeof(MQMD));  
/* get storage for dynamic instance */
```

3. Use the memcpy function to copy the model instance to the dynamic instance:

```
memcpy(InstancePtr,&ModelMsgDesc,sizeof(MQMD));  
/* initialize dynamic instance */
```

### Use from C++

For the C++ programming language, the header files contain the following additional statements that are included only when a C++ compiler is used:

```
#ifdef __cplusplus  
extern "C" {  
#endif  
  
/* rest of header file */  
  
#ifdef __cplusplus  
}  
#endif
```

## Coding in COBOL

See Appendix A, “Language compilers and assemblers” on page 453 for the compilers that you can use to process your COBOL programs.

Note the information in the following sections when coding MQSeries programs in COBOL.

## Named constants

In this book, the names of constants are shown containing the underscore character (`_`) as part of the name. In COBOL, you must use the hyphen character (`-`) in place of the underscore.

Constants that have character-string values use the single quotation mark character (`'`) as the string delimiter. To make the compiler accept this character, use the compiler option `APOST`.

The copy file `CMQV` contains declarations of the named constants as level-10 items. To use the constants, declare the level-01 item explicitly, then use the `COPY` statement to copy in the declarations of the constants:

```
WORKING-STORAGE SECTION.
01 MQM-CONSTANTS.
   COPY CMQV.
```

However, this method causes the constants to occupy storage in the program even if they are not referred to. If the constants are included in many separate programs within the same run unit, multiple copies of the constants will exist—this may result in a significant amount of main storage being used. You can avoid this situation by adding the `GLOBAL` clause to the level-01 declaration:

```
* Declare a global structure to hold the constants
01 MQM-CONSTANTS GLOBAL.
   COPY CMQV.
```

This causes storage to be allocated for only **one** set of constants within the run unit; the constants, however, can be referred to by **any** program within the run unit, not just the program that contains the level-01 declaration.

## Coding in System/390® assembler language

*System/390 assembler is supported on OS/390 only.*

See Appendix A, “Language compilers and assemblers” on page 453 for the assemblers that you can use to process your assembler-language programs.

Note the information in the following sections when coding MQSeries for OS/390 programs in assembler language.

### Names

In this book, the names of parameters in the descriptions of calls, and the names of fields in the descriptions of structures are shown in mixed case. In the assembler-language macros supplied with MQSeries, all names are in uppercase.

### Using the MQI calls

The MQI is a call interface, so assembler-language programs must observe the OS linkage convention. In particular, before they issue an MQI call, assembler-language programs must point register R13 at a save area of at least 18 full words. This save area is to provide storage for the called program. It stores the registers of the caller before their contents are destroyed, and restores the contents of the caller’s registers on return.

## Programming language considerations

**Note:** This is of particular importance for CICS assembler-language programs that use the DFHEIENT macro to set up their dynamic storage, but that choose to override the default DATAREG from R13 to other registers. When the CICS Resource Manager Interface receives control from the stub, it saves the current contents of the registers at the address to which R13 is pointing. Failing to reserve a proper save area for this purpose gives unpredictable results, and will probably cause an abend in CICS.

### Declaring constants

Most constants are declared as equates in macro CMQA. However, the following constants cannot be defined as equates, and these are not included when you call the macro using default options:

```
MQACT_NONE
MQCI_NONE
MQFMT_NONE
MQFMT_ADMIN
MQFMT_COMMAND_1
MQFMT_COMMAND_2
MQFMT_DEAD_LETTER_HEADER
MQFMT_EVENT
MQFMT_IMS
MQFMT_IMS_VAR_STRING
MQFMT_PCF
MQFMT_STRING
MQFMT_TRIGGER
MQFMT_XMIT_Q_HEADER
MQMI_NONE
```

To include them, add the keyword EQUONLY=NO when you call the macro.

CMQA is protected against multiple declaration, so you can include it many times. However, the keyword EQUONLY takes effect only the first time the macro is included.

### Specifying the name of a structure

To allow more than one instance of a structure to be declared, the macro that generates the structure prefixes the name of each field with a user-specifiable string and an underscore character (\_). Specify the string when you invoke the macro. If you do not specify a string, the macro uses the name of the structure to construct the prefix:

```
* Declare two object descriptors
           CMQODA           Prefix used="MQOD_" (the default)
MY_MQOD CMQODA           Prefix used="MY_MQOD_"
```

The structure declarations in Chapter 2, "Data type descriptions - structures" in the *MQSeries Application Programming Reference* manual show the default prefix.

## Specifying the form of a structure

The macros can generate structure declarations in one of two forms, controlled by the DSECT parameter:

DSECT=YES	An assembler-language DSECT instruction is used to start a new data section; the structure definition immediately follows the DSECT statement. No storage is allocated, so no initialization is possible. The label on the macro invocation is used as the name of the data section; if no label is specified, the name of the structure is used.
DSECT=NO	Assembler-language DC instructions are used to define the structure at the current position in the routine. The fields are initialized with values, which you can specify by coding the relevant parameters on the macro invocation. Fields for which no values are specified on the macro invocation are initialized with default values.

DSECT=NO is assumed if the DSECT parameter is not specified.

## Controlling the listing

You can control the appearance of the structure declaration in the assembler-language listing by means of the LIST parameter:

LIST=YES	The structure declaration appears in the assembler-language listing.
LIST=NO	The structure declaration does not appear in the assembler-language listing. This is assumed if the LIST parameter is not specified.

## Specifying initial values for fields

You can specify the value to be used to initialize a field in a structure by coding the name of that field (without the prefix) as a parameter on the macro invocation, accompanied by the value required.

For example, to declare a message descriptor structure with the *MsgType* field initialized with MQMT\_REQUEST, and the *ReplyToQ* field initialized with the string MY\_REPLY\_TO\_QUEUE, you could use the following code:

```
MY_MQMD          CMQMDA          MSGTYPE=MQMT_REQUEST,          X
                  REPLYTOQ=MY_REPLY_TO_QUEUE
```

If you specify a named constant (or equate) as a value on the macro invocation, you must use the CMQA macro to define the named constant. You must not enclose in single quotation marks ( ' ') values that are character strings.

## Writing reenterable programs

MQSeries uses its structures for both input and output. If you want your program to remain reenterable, you should:

1. Define working storage versions of the structures as DSECTs, or define the structures inline within an already-defined DSECT. Then copy the DSECT to storage that is obtained using:
  - For batch and TSO programs, the STORAGE or GETMAIN OS/390 assembler macros
  - For CICS, the working storage DSECT (DFHEISTG) or the EXEC CICS GETMAIN command

To correctly initialize these working storage structures, copy a constant version of the corresponding structure to the working storage version.

## Programming language considerations

**Note:** The MQMD and MQXQH structures are each more than 256 bytes long. To copy these structures to storage, you will have to use the MVCL assembler instruction.

2. Reserve space in storage by using the LIST form (MF=L) of the CALL macro. When you use the CALL macro to make an MQI call, use the EXECUTE form (MF=E) of the macro, using the storage reserved earlier, as shown in the example under “Using CEDF.” For more examples of how to do this, see the assembler language sample programs as shipped with MQSeries.

Use the assembler language RENT option to help you determine if your program is reenterable.

For information on writing reenterable programs, see the *MVS/ESA Application Development Guide: Assembler Language Programs*, GC28-1644.

### Using CEDF

If you want to use the CICS-supplied transaction, CEDF (CICS Execution Diagnostic Facility) to help you to debug your program, you must add the ,VL keyword to each CALL statement, for example:

```
CALL MQCONN, (NAME, HCONN, COMPCODE, REASON), MF=(E, PARMAREA), VL
```

The above example is reenterable assembler-language code where PARMAREA is an area in the working storage you specified.

## Coding in RPG

*RPG is supported on OS/400 only.*

See Appendix A, “Language compilers and assemblers” on page 453 for the compilers that you can use to process your RPG programs.

Note the following when coding MQSeries for AS/400 programs in RPG:

- In this book, the MQI calls are described using their individual names. In RPG, you must make all calls to the single name QMQM, and specify the particular function you require by coding an additional parameter that precedes the normal parameters for that call. The names you use for this additional parameter are shown in Appendix B, “MQI names in RPG” on page 457.
- The structure declarations supplied with MQSeries for AS/400 do not contain DS statements. This allows you to declare either a single data structure or a multiple-occurrence data structure. To do the latter, use the DS statement followed by the /COPY statement to copy in the remainder of the declaration. For example:

```
I*..1.....2.....3.....4.....5.....6.....7
I* Declare an MQMD data structure with 5 occurrences
IMYMD      DS              5
I/COPY CMQMDR
```
- The *buffer* field, as declared in the AMQ1GET4 sample program, has a maximum size limit of 256 bytes. This limit can be increased to:
  - 9999 bytes by declaring *buffer* as a structure
  - 32 KB if *buffer* is declared as a physical file

This is explained in the *MQSeries for AS/400 Application Programming Reference (RPG)* manual for the MQPUT, MQPUT1, and MQGET calls.

In this book, the parameters of calls, the names of data types, the fields of structures, and the names of constants are described using their long names. In RPG, these names are abbreviated to six or fewer uppercase characters. For example, the field *MsgType* becomes *MDMT* in RPG. The short RPG names for these names are shown in Appendix B, “MQI names in RPG” on page 457.

## Coding in PL/I

*PL/I is supported on AIX, OS/390, OS/2 Warp, VSE/ESA, and Windows NT only.*

See Appendix A, “Language compilers and assemblers” on page 453 for the compilers that you can use to process your PL/I programs.

Note the information in the following sections when coding MQSeries for OS/390 programs in PL/I.

### Structures

Structures are declared with the `BASED` attribute, and so do not occupy any storage unless the program declares one or more instances of a structure.

An instance of a structure can be declared by using the `like` attribute, for example:

```
dc1 my_mqmd          like MQMD; /* one instance */
dc1 my_other_mqmd   like MQMD; /* another one */
```

The structure fields are declared with the `INITIAL` attribute; when the `like` attribute is used to declare an instance of a structure, that instance inherits the initial values defined for that structure. Thus it is necessary to set only those fields where the value required is different from the initial value.

PL/I is not sensitive to case, and so the names of calls, structure fields, and constants can be coded in lowercase, uppercase, or mixed case.

### Named constants

The named constants are declared as macro variables; as a result, named constants which are not referenced by the program do not occupy any storage in the compiled procedure. However, the compiler option which causes the source to be processed by the macro preprocessor must be specified when the program is compiled.

All of the macro variables are character variables, even the ones which represent numeric values. Although this may seem counter intuitive, it does not result in any data-type conflict after the macro variables have been substituted by the macro processor, for example:

```
%dc1 MQMD_STRUC_ID char;
%MQMD_STRUC_ID = 'MD  ';

%dc1 MQMD_VERSION_1 char;
%MQMD_VERSION_1 = '1';
```

### Coding in TAL

*TAL is supported on Tandem NonStop Kernel only.*

See Appendix A, “Language compilers and assemblers” on page 453 for the compilers that you can use to process your TAL programs.

Note the following when coding MQSeries for Tandem NSK programs in TAL:

- The MQI library (bound into the application process) does not open \$RECEIVE and does not open \$TMP (TM/MP transaction pseudo-file) itself, so you may code your application to use these features.
- The MQI library uses a SERVERCLASS\_SEND\_() call in initial communication with the Queue Manager. While connected, it maintains two process file opens (with the LINKMON process and a Local Queue Manager Agent) and a small number of disk file opens (fewer than 10).

---

### OS/390 batch considerations

OS/390 batch programs that call the MQI can be in either supervisor or problem state. However, they must meet the following conditions:

- They must be in task mode, not service request block (SRB) mode.
- They must be in Primary address space control (ASC) mode (not Access Register ASC mode).
- They must not be in cross-memory mode. The primary address space number (ASN) must be equal to the secondary ASN and the home ASN.
- No OS/390 locks can be held.
- There can be no function recovery routines (FRRs) on the FRR stack.
- Any program status word (PSW) key can be in force for the MQCONN call (provided the key is compatible with using storage that is in the TCB key), but subsequent calls that use the connection handle returned by MQCONN:
  - Must have the same PSW key that was used on the MQCONN call
  - Must have parameters accessible (for write, where appropriate) under the same PSW key
  - Must be issued under the same task (TCB), but not in any subtask of the task
- They can be in either 24-bit or 31-bit addressing mode. However, if 24-bit addressing mode is in force, parameter addresses must be interpreted as valid 31-bit addresses.

If any of these conditions is not met, a program check may occur. In some cases the call will fail and a reason code will be returned.

---

## UNIX signal handling on MQSeries Version 5 products

In general, UNIX systems have moved from a nonthreaded (process) environment to a multithreaded environment. In the nonthreaded environment, some functions could be implemented only by using signals, though most applications did not need to be aware of signals and signal handling. In the multithreaded environment, thread-based primitives support some of the functions that used to be implemented in the nonthreaded environments using signals. In many instances, signals and signal handling, although supported, do not fit well into the multithreaded environment and various restrictions exist. This can be particularly problematic when you are integrating application code with different middleware libraries (running as part of the application) in a multithreaded environment where each is trying to handle signals. The traditional approach of saving and restoring signal handlers (defined per process), which worked when there was only one thread of execution within a process, does not work in a multithreaded environment: many threads of execution could be trying to save and restore a process-wide resource, with unpredictable results.

For a standard application MQSeries supports both nonthreaded and threaded application environments on AIX and HP-UX.

All MQSeries applications in the Sun Solaris environment are threaded. MQSeries for Sun Solaris V2.2 supported only single-threaded applications (though there was no way to enforce this) and, because there was only one thread of execution, was able to make use of the traditional signal handling functions. In MQSeries for Sun Solaris V5.0, and subsequent releases, true multithreaded applications are supported and so the signal behavior has changed.

The library `libmqm` is provided for migration of nonthreaded applications from Version 2 of MQSeries for AIX or MQSeries for HP-UX to Version 5. The goal of this library is to maintain the Version 2 behavior (including signals) for nonthreaded applications. Within an application in this environment there is only one thread of execution, which means that signal handlers can be saved and restored safely across MQSeries API calls (as can any middleware library that is part of the application). Therefore, if you have an application suite on V2 of MQSeries for AIX or MQSeries for HP-UX that uses signals, and you do not want to move to the threaded environment, the suite should run unchanged on V5 using the nonthreaded library, `libmqm`.

The library `libmqm_r` is provided for threaded applications on MQSeries for AIX or MQSeries for HP-UX. However, the behavior, particularly for signals, is different:

- As in the nonthreaded environment, MQSeries still establishes signal handlers for synchronous terminating signals (SIGBUS, SIGFPE, SIGSEGV).
- MQSeries must run some clean-up code during abnormal termination. This is achieved by setting up a `sigwait` thread to handle terminating, asynchronous signals. While this approach is suitable for an application that does not handle signals, it can cause problems when the signals being trapped on the MQSeries `sigwait` thread overlap with signals that an application wishes to intercept.
- Even in the threaded environment MQSeries needs a signal for its internal processing. As was stated earlier, use of signals in a threaded environment may cause problems when you are integrating a middleware stack. (With many threads all independently trying to handle signals, saving and restoring signal

## UNIX signal handling

handlers, results are unpredictable.) MQSeries must use one signal: SIGALRM.

**Note:** Some system functions may use signals internally (for example, SIGALRM in a nonthreaded environment). For a particular operating system, some of these functions may have thread-safe equivalents or it may be stated that they are not multithread safe. Any non-thread-safe operating system call should be replaced if moving to a multithreaded environment.

## Unthreaded applications

Each MQI function sets up its own signal handler for the signals:

SIGALRM  
SIGBUS  
SIGFPE  
SIGSEGV

Users' handlers for these are replaced for the duration of the MQI function call. Other signals can be caught in the normal way by user-written handlers. If you do not install a handler, the default actions (for example, ignore, core dump, or exit) are left in place.

**Note:** On Sun Solaris all applications are threaded even if they use a single thread.

## Threaded applications

A thread is considered to be connected to MQSeries from MQCONN (or MQCONNX) until MQDISC.

### Synchronous signals

Synchronous signals arise in a specific thread. UNIX safely allows the setting up of a signal handler for such signals for the whole process. However, MQSeries sets up its own handler for the following signals, in the application process, while any thread is connected to MQSeries:

SIGBUS  
SIGFPE  
SIGSEGV

If you are writing multithreaded applications, you should note that there is only one process-wide signal handler for each signal. MQSeries alters this signal handler when the application is connected to MQSeries. If one of these signals occurs while not on a thread connected to MQSeries, MQSeries attempts to call the signal handler that was in effect at the time of the first MQSeries connection within the process. Application threads must not establish signal handlers for these signals while there is any possibility that another thread of the same process is also connected to MQSeries.

### Asynchronous signals

Asynchronous signals arise outside the whole process. UNIX does not guarantee predictable behavior for handling asynchronous signals, in certain situations, when running multithreaded. MQSeries must perform clean-up of thread and process resources as part of the termination from these asynchronous signals:

SIGCHLD

SIGHUP  
 SIGINT  
 SIGQUIT  
 SIGTERM

MQSeries establishes a sigwait thread in the application process to intercept these signals.

These signals must not be used by the application when running multithreaded and when any thread is within an MQSeries connection. These signals should not be unmasked within any application thread; be aware of the default status of the signal mask for threads that do not make MQSeries calls.

### **MQSeries use of SIGALRM**

For communication purposes MQSeries needs a signal for its internal use. This signal should not be used by the application while any thread is within an MQSeries connection.

### **Threaded client applications - additional considerations**

MQSeries handles the following signals during I/O to a server. These signals are defined by the communications stack. The application should not establish a signal handler for these signals while a thread of the process is making an MQSeries call:

**SIGPIPE** (for TCP/IP)  
**SIGUSR1** (for LU 6.2)

## **Fastpath (trusted) applications**

Fastpath applications run in the same process as MQSeries and so are running in the multithreaded environment. In this environment the application should not use any signals or timer interrupts. If a Fastpath application intercepts such an event, the queue manager must be stopped and restarted, or it may be left in an undefined state. For a full list of the restrictions for Fastpath applications under MQCONN see "Connecting to a queue manager using the MQCONN call" on page 92.

## **MQI function calls within signal handlers**

While you are in a signal handler, you cannot call an MQI function. If you call an MQI function, while another MQI function is active, MQRC\_CALL\_IN\_PROGRESS is returned. If you call an MQI function, while no other MQI function is active, it is likely to fail because of the operating system restrictions on which calls can be issued from within a handler.

In the case of C++ destructor methods, which may be called automatically during program exit, you may not be able to stop the MQI functions from being called. Therefore, ignore any errors about MQRC\_CALL\_IN\_PROGRESS. If a signal handler calls exit(), MQSeries backs out uncommitted messages in syncpoint as normal and closes any open queues.

### Signals during MQI calls

MQI functions do not return the code EINTR or any equivalent to application programs. If a signal occurs during an MQI call, and the handler calls 'return', the call continues to run as if the signal had not happened. In particular, MQGET cannot be interrupted by a signal to return control immediately to the application. If you want to break out of an MQGET, set the queue to GET\_DISABLED; alternatively, use a loop around a call to MQGET with a finite time expiry (MQGMO\_WAIT with gmo.WaitInterval set), and use your signal handler (in a nonthreaded environment) or equivalent function in a threaded environment to set a flag which breaks the loop.

### User exits and installable services

User exits and installable services that run as part of an MQSeries process (that is, in a multithreaded environment) have the same restrictions as for Fastpath applications. They should be considered as permanently connected to MQSeries and so not use signals or non-threadsafe operating system calls.

## Chapter 7. Connecting and disconnecting a queue manager

To use MQSeries programming services, a program must have a connection to a queue manager. The way this connection is made depends on the platform and the environment in which the program is operating:

### **OS/390 batch, MQSeries on UNIX systems, MQSeries for Digital OpenVMS, MQSeries for OS/2 Warp, MQSeries for Tandem NSK, MQSeries for Windows, and MQSeries for Windows NT**

Programs that run in these environments can use the MQCONN MQI call to connect to, and the MQDISC call to disconnect from, a queue manager. Alternatively, MQSeries on UNIX systems, MQSeries for OS/2 Warp, and MQSeries for Windows NT can use the MQCONNX call. This chapter describes how writers of such programs should use these calls.

### **IMS**

The IMS control region is connected to one or more queue managers when it starts. This connection is controlled by IMS commands. (For information on how to control the IMS adapter of MQSeries for OS/390, see the *MQSeries for OS/390 System Management Guide*.) However, writers of message queuing IMS programs must use the MQCONN MQI call to specify the queue manager to which they want to connect. They can use the MQDISC call to disconnect from that queue manager. This chapter describes how writers of such programs should use these calls. Before the IMS adapter processes a message for another user following a Get Unique call from the IOPCB, or one implied by a checkpoint call, the adapter ensures that the application closes handles and disconnects from the queue manager.

### **CICS Transaction Server for OS/390 and CICS for MVS/ESA**

CICS programs do not need to do any work to connect to a queue manager because the CICS system itself is connected. This connection is usually made automatically at initialization, but you can also use the CKQC transaction, which is supplied with MQSeries for OS/390. CKQC is discussed in the *MQSeries for OS/390 System Management Guide*.

**Note:** CICS programs can also use the MQI connect and disconnect calls (MQCONN and MQDISC). You may want to do this so that you can port these applications to non-CICS environments with a minimum of recoding. Be warned, though, that these calls *always* complete successfully in a CICS environment. This means that the return code may not reflect the true state of the connection to the queue manager.

### **TXSeries for Windows NT and Open Systems**

These programs do not need to do any work to connect to a queue manager because the CICS system itself is connected. Therefore, only one connection at a time is supported. CICS applications must issue an MQCONN call to obtain a connection handle, and should issue an MQDISC call before they exit.

### **AS/400**

The connection to a queue manager can be made explicitly using the MQCONN call, or it can be made implicitly in the first successful MQOPEN or MQPUT1 call. If you want to use your application on other platforms as well as AS/400, it is a good idea to use the MQCONN call. If you do use the MQCONN call, you must also use the MQDISC call.

The performance of your application is better if you connect and disconnect (either explicitly or implicitly) as infrequently as possible.

If you use the MQPUT1 call and rely on an implicit connection, your application is implicitly disconnected when the call completes. When an application connects implicitly using an MQOPEN call, it is disconnected implicitly when it issues the last MQCLOSE call.

### **MQSeries for VSE/ESA**

In your VSE/ESA application, make an explicit call to MQCONN to establish a connection to the VSE/ESA queue manager. Ensure that your application issues an MQDISC call to disconnect. The performance of your application is better if you connect and disconnect as infrequently as possible.

---

## Connecting to a queue manager using the MQCONN call

In general, you can connect either to a specific queue manager, or to the default queue manager:

- For MQSeries for OS/390, in the batch environment, the default queue manager is specified in the CSQBDEFV module.
- For MQSeries for OS/2 Warp, MQSeries for Digital OpenVMS, MQSeries for Tandem NSK, and MQSeries on UNIX systems, the default queue manager is specified in the mqs.ini file.
- For MQSeries for Windows NT, the default queue manager is specified in the registry.
- MQSeries for Windows allows only one queue manager to run at a time; it uses the running queue manager as its default.
- MQSeries for VSE/ESA allows only one queue manager to run at a time; its name is specified in the Global System Definition of the System Management Facility (SMF). Your application can specify the name or use the default value.

The queue manager you connect to must be *local* to the task. This means that it must belong to the same system as the MQSeries application.

On AS/400, there can be only one queue manager on the same system as an application.

In the IMS environment, the queue manager must be connected to the IMS control region and to the dependent region that the program uses. The default queue manager is specified in the CSQQDEFV module when MQSeries for OS/390 is installed.

With the CICS on Open Systems environment, and TXSeries for Windows NT and AIX, the queue manager must be defined as an XA resource to CICS.

To connect to the default queue manager, call MQCONN, specifying a name consisting entirely of blanks or starting with a null (X'00') character.

Within MQSeries on UNIX systems, an application must be authorized for it to successfully connect to a queue manager. For more information, see Chapter 10, "Protecting MQSeries objects" in the *MQSeries System Administration* Guide for

MQSeries for AIX, HP-UX, and Sun Solaris; for other platforms, see the appropriate *System Management Guide*.

The output from MQCONN is:

- A connection handle
- A completion code
- A reason code

You will need to use the connection handle on subsequent MQI calls.

If the reason code indicates that the application is already connected to that queue manager, the connection handle that is returned is the same as the one that was returned when the application first connected. So the application probably should not issue the MQDISC call in this situation because the calling application will expect to remain connected.

The scope of the connection handle is the same as that for the object handle (see “Opening objects using the MQOPEN call” on page 98).

Descriptions of the parameters are given in the description of the MQCONN call in “MQCONN - Connect queue manager” in the *MQSeries Application Programming Reference* manual.

The MQCONN call fails if the queue manager is in a quiescing state when you issue the call, or if the queue manager is shutting down.

## Scope of MQCONN

Within MQSeries on UNIX systems, MQSeries for Digital OpenVMS, MQSeries for OS/2 Warp, MQSeries for Windows, and MQSeries for Windows NT, the scope of an MQCONN call is the thread that issued it. That is, the connection handle returned from an MQCONN call is valid only within the thread which issued the call. Only one call may be made at any one time using the handle. If it is used from a different thread, it will be rejected as invalid. If you have multiple threads in your application that each wish to use MQSeries calls, then they must each individually issue MQCONN.

Each thread can connect to a different queue manager on OS/2 and Windows NT, but not on UNIX.

If your application is running as a client, it may connect to more than one queue manager within a thread. This does not apply if your application is not running as a client.

OS/2 has a limit of 4095 active threads in a system. However, the default is 64. This value may be controlled by the THREADS=xxxx parameter in CONFIG.SYS. Limitations on the number of concurrent MQCONN calls that can be made within a system are dependent on this value, although other factors to consider are disk space availability for the swapper.dat file and shared memory availability.

On MQSeries for Windows, the scope of an MQCONN call is the application process.

On MQSeries for VSE/ESA, there is a maximum of 1000 concurrently-connected tasks. The connection handle is unique to the ID of the transaction that is executing and only valid for the duration of that transaction.

---

## Connecting to a queue manager using the MQCONNX call

*MQCONNX is not supported on AS/400, Digital OpenVMS, OS/390, Tandem NonStop Kernel, and VSE/ESA.*

The MQCONNX call is similar to the MQCONN call, but includes options to control the way that the call actually works.

As input to MQCONNX, you must supply a queue manager name. The output from MQCONNX is:

- A connection handle
- A completion code
- A reason code

You will need to use the connection handle on subsequent MQI calls.

A description of all of the parameters of MQCONNX is given in “MQCONNX - Connect queue manager (extended)” in the *MQSeries Application Programming Reference* manual. The *Options* field allows you to set STANDARD\_BINDING or FASTPATH\_BINDING:

### MQCNO\_STANDARD\_BINDING

By default, MQCONNX (like MQCONN) implies two threads where the MQSeries application and the local queue manager agent run in separate processes. The MQSeries application performs the MQSeries operation and the local queue manager agent performs the application operation. This is defined by the MQCNO\_STANDARD\_BINDING option on the MQCONNX call.

**Note:** This default maintains the integrity of the queue manager (that is, it makes the queue manager immune to errant programs), but impairs the performance of the MQI calls.

### MQCNO\_FASTPATH\_BINDING

*Trusted applications* imply that the MQSeries application and the local queue manager agent become the same process. Since the agent process no longer needs to use an interface to access the queue manager, these applications become an extension of the queue manager. This is defined by the MQCNO\_FASTPATH\_BINDING option on the MQCONNX call.

You need to link trusted applications to the threaded MQSeries libraries. For instructions on how to set up an MQSeries application to run as trusted, see “MQCNO - Connect options” in the *MQSeries Application Programming Reference* manual.

**Note:** This option compromises the integrity of the queue manager as there is no protection from overwriting its storage. This also applies if the application contains errors which can be exposed to messages and other data in the queue manager too. These issues must be considered before using this option.

## Restrictions

The following restrictions apply to trusted applications:

- On MQSeries on UNIX systems, it is necessary to use mqm as the effective userID and groupID for all MQI calls. You may change these IDs before making a non-MQI call requiring authentication (for example, opening a file), but you **must** change it back to mqm before making the next MQI call.
- On MQSeries on UNIX systems, trusted applications must run in threaded processes but only one thread can be connected at a time.
- On MQSeries for OS/2 Warp and MQSeries for Windows NT, a thread within a trusted application cannot connect to a queue manager while another thread in the same process is connected to a different queue manager.
- You must explicitly disconnect trusted applications from the queue manager.
- You must stop trusted applications before ending the queue manager with the endmqm command.
- You must not use asynchronous signals and timer interrupts (such as sigkill) with MQCNO\_FASTPATH\_BINDING.
- On MQSeries for AIX, trusted applications cannot be compiled using the PL/I programming language.
- On MQSeries for AIX, there are restrictions on the use of shared memory segments:

MQSeries uses a single “shmat()” command to connect to shared memory resources. However, on AIX, one process cannot attach to more than 10 memory segments.

MQSeries uses two additional shared memory segments for trusted applications, reducing the amount of shared storage available. Therefore, it is important that your applications do not connect to too many shared segments, causing a failure in the application code.

Here is a breakdown of the memory segments:

Segment	Use	
0	Reserved for AIX	
1	Reserved for AIX	
2	Stack and heap	
3	CICS	MQSeries (trusted applications only)
4	DB2 and DT/6000	
5		
6		
7		MQSeries (trusted applications only)
8		MQSeries
9	CICS	
A	CICS	
B	CICS	
C	DB2	
D	Reserved for AIX	
E	Reserved for AIX	
F	Reserved for AIX	

This also implies that trusted applications cannot use the maxdata binder option to specify a greater user data area: this conflicts with the queue manager use

of shared memory within the application process as it causes the program data to be placed in shared memory segment 3.

## Environment variable

On MQSeries for OS/2 Warp, MQSeries for Windows NT, and MQSeries on UNIX systems, the environment variable, MQ\_CONNECT\_TYPE, can be used in combination with the type of binding specified in the *Options* field. This environment variable allows you to execute the application with the STANDARD\_BINDING if any problems occur with the FASTPATH\_BINDING. If the environment variable is specified, it should have the value FASTPATH or STANDARD to select the type of binding required. However, the FASTPATH binding is used only if the connect option is appropriately specified as shown in Table 2:

Table 2. Environment variable

MQCONN	Environment variable	Result
STANDARD	UNDEFINED	STANDARD
FASTPATH	UNDEFINED	FASTPATH
STANDARD	STANDARD	STANDARD
FASTPATH	STANDARD	STANDARD
STANDARD	FASTPATH	STANDARD
FASTPATH	FASTPATH	FASTPATH

So, to run a trusted application, either:

1. Specify the MQCNO\_FASTPATH\_BINDING option on the MQCONN call and the FASTPATH environment variable,
- or
2. Specify the MQCNO\_FASTPATH\_BINDING option on the MQCONN call and leave the environment variable undefined.

If neither MQCNO\_STANDARD\_BINDING nor MQCNO\_FASTPATH\_BINDING is specified, you can use MQCNO\_NONE, which defaults to MQCNO\_STANDARD\_BINDING.

---

## Disconnecting programs from a queue manager using MQDISC

When a program that has connected to a queue manager using the MQCONN call has finished all interaction with the queue manager, it must break the connection using the MQDISC call.

However, in MQSeries for AS/400, if the connection was made implicitly, the MQDISC call is optional. Also, on CICS Transaction Server for OS/390 applications, the call is optional.

After MQDISC is called, the connection handle (*Hconn*) is no longer valid, and you cannot issue any further MQI calls until you call MQCONN again. MQDISC does an implicit MQCLOSE for any objects that are still open using this handle.

In MQSeries for AS/400, when you sign off from the operating system, an implicit MQDISC call is made.

As input to the MQDISC call, you must supply the connection handle (*Hconn*) that was returned by MQCONN when you connected to the queue manager.

The output from this call is a completion code and a reason code, with the connection handle set to the value MQHC\_UNUSABLE\_HCONN.

| On MQSeries for VSE/ESA, if your application does not issue the MQDISC call  
| explicitly, the MQSeries for VSE/ESA housekeeping routine issues the MQDISC call  
| on its behalf and unwanted messages appear in the SYSTEM.LOG queue.

| Descriptions of the parameters are given in the description of the MQDISC call in  
| "MQDISC - Disconnect queue manager" in the *MQSeries Application Programming*  
| *Reference* manual.

### Authority checking

The MQCLOSE and MQDISC calls usually perform no authority checking. In the normal course of events a job which has the authority to open or connect to an MQSeries object will close or disconnect from that object. Even if the authority of a job that has connected to, or opened an MQSeries object is revoked, the MQCLOSE and MQDISC calls are accepted.



---

## Chapter 8. Opening and closing objects

To perform any of the following operations, you must first *open* the relevant MQSeries object:

- Put messages on a queue
- Get (browse or retrieve) messages from a queue
- Set the attributes of an object
- Inquire about the attributes of any object

Use the MQOPEN call to open the object, using the options of the call to specify what you want to do with the object. The only exception is if you want to put a single message on a queue, then close the queue immediately. In this case, you can bypass the “opening” stage by using the MQPUT1 call (see “Putting one message on a queue using the MQPUT1 call” on page 114).

Before you open an object using the MQOPEN call, you must connect your program to a queue manager. This is explained in detail, for all environments, in Chapter 7, “Connecting and disconnecting a queue manager” on page 89.

There are four types of MQSeries object that can be opened:

- Queue
- Namelist (MQSeries for OS/390 and MQSeries Version 5.1 products only)
- Process definition
- Queue manager

You open all of these objects in a similar way using the MQOPEN call. For more information about MQSeries objects, see Chapter 4, “MQSeries objects” on page 39.

You can open the same object more than once, and each time you get a new object handle. You might want to browse messages on a queue using one handle, and remove messages from the same queue using another handle. This saves using up resources to close and reopen the same object. You can also open a queue for browsing *and* removing messages at the same time.

Moreover, you can open multiple objects with a single MQOPEN and close them using MQCLOSE. See “Distribution lists” on page 116 for information about how to do this.

When you attempt to open an object, the queue manager checks that you are authorized to open that object for the options you specify in the MQOPEN call.

Objects are closed automatically when a program disconnects from the queue manager. In the IMS environment, disconnection is forced when a program starts processing for a new user following a GU (get unique) IMS call. On the AS/400 platform, objects are closed automatically when a job ends.

It is good programming practice to close objects you have opened. Use the MQCLOSE call to do this.

The remaining sections of this chapter describe how to:

- Open objects using the MQOPEN call
- Create dynamic queues using model queues (MQSeries for AS/400, MQSeries for OS/390, MQSeries for OS/2 Warp, MQSeries for Tandem NSK, MQSeries for Windows NT, and MQSeries on UNIX systems only)
- Open remote queues
- Close objects using the MQCLOSE call

---

### Opening objects using the MQOPEN call

As input to the MQOPEN call, you must supply:

- A connection handle. For CICS and AS/400 applications, you can specify the constant MQHC\_DEF\_HCONN (which has the value zero), or use the connection handle returned by the MQCONN call. For other programs, always use the connection handle returned by the MQCONN call.
- A description of the object you want to open, using the object descriptor structure (MQOD).
- One or more options that control the action of the call.

The output from MQOPEN is:

- An object handle that represents your access to the object. Use this on input to any subsequent MQI calls.
- A modified object-descriptor structure, if you are creating a dynamic queue (and it is supported on your platform).
- A completion code.
- A reason code.

Namelists can be opened only on AIX, HP-UX, OS/2 Warp, OS/390, Sun Solaris, and Windows NT.

### Scope of an object handle

The scope of an object handle is the same as the scope of a connection handle, however there are variations between platforms:

#### **CICS**

In a CICS program, you can use the handle only within the same CICS task from which you made the MQOPEN call.

#### **IMS and OS/390 batch**

In the IMS and batch environments, you can use the handle within the same task, but not within any subtasks.

#### **AS/400**

In an AS/400 program, you can use the handle only within the same job from which you made the MQOPEN call.

#### **MQSeries for OS/2 Warp**

In the MQSeries for OS/2 Warp environment, you can use the same handle within the same thread.

**MQSeries for Windows NT**

In the MQSeries for Windows NT environment, you can use the same handle within the same thread.

**MQSeries on UNIX systems**

In these environments, you can use the same handle within the same thread.

**DOS**

In the DOS environment, there are no restrictions on where you can use the handle.

**MQSeries for VSE/ESA**

In the VSE/ESA environment, you can use the handle only within the same application transaction from which you made the MQOPEN call.

**Windows 3.1**

In the Windows 3.1 environment, you can use the handle in the same Windows 3.1 instance.

Descriptions of the parameters of the MQOPEN call are given in “MQOPEN - Open object” in the *MQSeries Application Programming Reference* manual.

The following sections describe the information you must supply as input to MQOPEN.

**Identifying objects (the MQOD structure)**

Use the MQOD structure to identify the object you want to open. This structure is an input parameter for the MQOPEN call. (The structure is modified by the queue manager when you use the MQOPEN call to create a dynamic queue.)

For full details of the MQOD structure see “MQOD - Object descriptor” in the *MQSeries Application Programming Reference* manual.

For information about using the MQOD structure for distribution lists, see Using the MQOD structure under “Distribution lists” on page 116.

**Name resolution**

When you open an MQSeries queue, the MQOPEN call performs a name resolution function on the queue name you specify. This determines on which queue the queue manager performs subsequent operations. This means that when you specify the name of an alias queue or a remote queue in your object descriptor (MQOD), the call resolves the name either to a local queue or to a transmission queue. If a queue is opened for any type of input, browse, or set, it resolves to a local queue if there is one, and fails otherwise. It resolves to a nonlocal queue only if it is opened for output only, inquire only, or output and inquire only. See Table 3 on page 100 for an overview of the name resolution process. Note that the name you supply in *ObjectQMgrName* is resolved **before** that in *ObjectName*.

Table 3 on page 100 also shows how you can use a local definition of a remote queue to define an alias for the name of a queue manager. This allows you to select which transmission queue is used when you put messages on a remote queue, so you could, for example, use a single transmission queue for messages destined for many remote queue managers. This technique is described further in Chapter 4, “MQSeries distributed-messaging techniques” in the *MQSeries Intercommunication* book.

## Using MQOPEN

Table 3 (Page 1 of 2). Resolving queue names when using MQOPEN

Input to MQOD		Resolved names		
<i>ObjectQMgrName</i>	<i>ObjectName</i>	<i>ObjectQMgrName</i>	<i>ObjectName</i>	Transmission queue
Blank or local queue manager	Local queue with no CLUSTER attribute	Local queue manager	Input <i>ObjectName</i>	Not applicable (local queue used)
Blank queue manager	Local queue with CLUSTER attribute	Workload management selected cluster queue manager or specific cluster queue manager selected on PUT	Input <i>ObjectName</i>	SYSTEM.CLUSTER.TRANSMIT.QUEUE and local queue used
Local queue manager	Local queue with CLUSTER attribute	Local queue manager	Input <i>ObjectName</i>	Not applicable (local queue used)
Blank or local queue manager	Model queue	Local queue manager	Generated name	Not applicable (local queue used)
Blank or local queue manager	Alias queue with or without CLUSTER attribute	Perform name resolution again with <i>ObjectQMgrName</i> unchanged, and input <i>ObjectName</i> set to the <i>BaseQName</i> in the alias queue definition object. May not return to alias queues		
Blank or local queue manager	Local definition of a remote queue with or without CLUSTER attribute	Perform name resolution again with <i>ObjectQMgrName</i> set to <i>RemoteQMgrName</i> , and <i>ObjectName</i> set to <i>RemoteQName</i> . May not return to remote queues		Name of <i>XmitQName</i> attribute, if non-blank; otherwise <i>RemoteQMgrName</i> in the remote queue definition object
Blank queue manager	No matching local object; cluster queue found	Workload management selected cluster queue manager or specific cluster queue manager selected on PUT	Input <i>ObjectName</i>	SYSTEM.CLUSTER.TRANSMIT.QUEUE
Blank or local queue manager	No matching local object; cluster queue not found		Error, queue not found	Not applicable
Name of a local transmission queue	(Not resolved)	Input <i>ObjectQMgrName</i>	Input <i>ObjectName</i>	Input <i>ObjectQMgrName</i>
Queue manager alias definition ( <i>RemoteQMgrName</i> may be the local queue manager)	(Not resolved, remote queue)	Perform name resolution again with <i>ObjectQMgrName</i> set to <i>RemoteQMgrName</i> . May not return to remote queues	Input <i>ObjectName</i>	Name of <i>XmitQName</i> attribute, if non-blank; otherwise <i>RemoteQMgrName</i> in the remote queue definition object

Table 3 (Page 2 of 2). Resolving queue names when using MQOPEN

Queue manager is not the name of any local object; cluster queue managers or queue manager alias found	(Not resolved)	<i>ObjectQMgrName</i> or specific cluster queue manager selected on PUT	Input <i>ObjectName</i>	SYSTEM.CLUSTER.TRANSMIT.QUEUE
Queue manager is not the name of any local object; no cluster objects found	(Not resolved)	Input <i>ObjectQMgrName</i>	Input <i>ObjectName</i>	<i>DefXmitQName</i> attribute of the queue manager <sup>3</sup>

**Notes:**

1. *BaseQName* is the name of the base queue from the definition of the alias queue.
2. *RemoteQName* is the name of the remote queue from the local definition of the remote queue.
3. *RemoteQMgrName* is the name of the remote queue manager from the local definition of the remote queue.
4. *XmitQName* is the name of the transmission queue from the local definition of the remote queue.

Opening an alias queue also opens the base queue to which the alias resolves, and opening a remote queue also opens the transmission queue. Therefore you cannot delete either the queue you specify or the queue to which it resolves while the other one is open.

The resolved queue name and the resolved queue manager name are stored in the *ResolvedQName* and *ResolvedQMgrName* fields in the MQOD.

For more information about name resolution in a distributed queuing environment see Appendix C, "Queue name resolution" in the *MQSeries Intercommunication* book.

## Using the options of the MQOPEN call

In the *Options* parameter of the MQOPEN call, you must choose one or more options to control the access you are given to the object you are opening. With these options you can:

- Open a queue and specify that all messages put to that queue must be directed to the same instance of it
- Open a queue to allow you to put messages on it
- Open a queue to allow you to browse messages on it
- Open a queue to allow you to remove messages from it
- Open an object to allow you to inquire about and set its attributes (but you can set the attributes of queues only)
- Associate context information with a message

<sup>3</sup> where *DefXmitQName* is supported

- Nominate an alternate user identifier to be used for security checks
- Control the call if the queue manager is in a quiescing state

### MQOPEN option for cluster queue

To specify that all messages MQPUT to a queue are to be routed to the same queue manager by the same route use the MQOO\_BIND\_ON\_OPEN option on the MQOPEN call. To specify that a destination is to be selected at MQPUT time, that is, on a message-by-message basis, use the MQOO\_BIND\_NOT\_FIXED option on the MQOPEN call. If you specify neither of these options the default, MQOO\_BIND\_AS\_Q\_DEF, is used. In this case the binding used for the queue handle is taken from the *DefBind* queue attribute, which can take the value MQBND\_BIND\_ON\_OPEN or MQBND\_BIND\_NOT\_FIXED. If the queue you open is not a cluster queue the MQOO\_BIND\_\* options are ignored. If you specify the name of the local queue manager in the MQOD the local instance of the cluster queue is selected. If the queue manager name is blank, any instance can be selected. See “MQI and clusters” in the *MQSeries Queue Manager Clusters* book for more information.

### MQOPEN option for putting messages

To open a queue in order to put messages on it, use the MQOO\_OUTPUT option.

### MQOPEN option for browsing messages

To open a queue so that you can *browse* the messages on it, use the MQOPEN call with the MQOO\_BROWSE option. This creates a *browse cursor* that the queue manager uses to identify the next message on the queue. For more information, see “Browsing messages on a queue” on page 154.

#### Notes:

1. You cannot browse messages on a remote queue. Therefore you cannot open a remote queue using the MQOO\_BROWSE option.
2. You cannot specify this option when opening a distribution list. For further information about distribution lists, see “Distribution lists” on page 116.

### MQOPEN options for removing messages

There are three options that control the opening of a queue in order to remove messages from it. You can use only one of them in any MQOPEN call. These options define whether your program has exclusive or shared access to the queue. *Exclusive access* means that, until you close the queue, only you can remove messages from it. If another program attempts to open the queue to remove messages, its MQOPEN call fails. *Shared access* means that more than one program can remove messages from the queue.

The most advisable approach is to accept the type of access that was intended for the queue when the queue was defined. The queue definition involved the setting of the *Shareability* and the *DefInputOpenOption* attributes. To accept this access, use the MQOO\_INPUT\_AS\_Q\_DEF option. Refer to Table 4 to see how the setting of these attributes affects the type of access you will be given when you use this option.

Table 4. How queue attributes and options of the MQOPEN call affect access to queues

Queue attributes		Type of access with MQOPEN options		
<i>Shareability</i>	<i>DefInputOpenOption</i>	AS_Q_DEF	SHARED	EXCLUSIVE
SHAREABLE	SHARED	shared	shared	exclusive
SHAREABLE	EXCLUSIVE	exclusive	shared	exclusive
NOT_SHAREABLE*	SHARED*	exclusive	exclusive	exclusive
NOT_SHAREABLE	EXCLUSIVE	exclusive	exclusive	exclusive

**Note:** \* Although you can define a queue to have this combination of attributes, the default input open option is overridden by the shareability attribute.

Alternatively:

- If you know that your application can work successfully even if other programs can remove messages from the queue at the same time, use the MQOO\_INPUT\_SHARED option. Table 4 shows how, in some cases you will be given exclusive access to the queue, even with this option.
- If you know that your application can work successfully only if other programs are prevented from removing messages from the queue at the same time, use the MQOO\_INPUT\_EXCLUSIVE option.

**Notes:**

1. You cannot remove messages from a remote queue. Therefore you cannot open a remote queue using any of the MQOO\_INPUT\_\* options.
2. You cannot specify this option when opening a distribution list. For further information, see “Distribution lists” on page 116.

**MQOPEN options for setting and inquiring about attributes**

To open a queue so that you can set its attributes, use the MQOO\_SET option. You cannot set the attributes of any other type of object (see Chapter 12, “Inquiring about and setting object attributes” on page 179).

To open an object so that you can inquire about its attributes, use the MQOO\_INQUIRE option.

**Note:** You cannot specify this option when opening a distribution list.

**MQOPEN options relating to message context**

If you want to be able to associate context information with a message when you put it on a queue, you must use one of the message context options when you open the queue.

The options allow you to differentiate between context information that relates to the *user* who originated the message, and that which relates to the *application* that originated the message. Also, you can opt to set the context information when you put the message on the queue, or you can opt to have the context taken automatically from another queue handle.

For more information about the subject of message context, see “Message context” on page 37.

### **MQOPEN option for alternate user authority**

*This is not supported on MQSeries for Windows.*

When you attempt to open an object using the MQOPEN call, the queue manager checks that you have the authority to open that object. If you are not authorized, the call fails.

However, server programs may want the queue manager to check the authorization of the user on whose behalf they are working, rather than the server's own authorization. To do this, they must use the MQOO\_ALTERNATE\_USER\_AUTHORITY option of the MQOPEN call, and specify the alternate user ID in the *AlternateUserId* field of the MQOD structure. Typically, the server would get the user ID from the context information in the message it is processing.

### **MQOPEN option for queue manager quiescing**

*This is not supported on MQSeries for Windows.*

In the CICS environment, if you use the MQOPEN call when the queue manager is in a quiescing state, the call always fails. In other OS/390 environments, AS/400, OS/2, Windows NT, and in UNIX systems environments, the call fails when the queue manager is quiescing only if you use the MQOO\_FAIL\_IF QUIESCING option of the MQOPEN call.

---

## Creating dynamic queues

You should use a dynamic queue for those cases where you do not need the queue after your application ends. For example, you may want to use a dynamic queue for your “reply-to” queue. You specify the name of the reply-to queue in the *ReplyToQ* field of the MQMD structure when you put a message on a queue (see “Defining messages using the MQMD structure” on page 108).

To create a dynamic queue, you use a template known as a model queue, together with the MQOPEN call. You create a model queue using the MQSeries commands or the operations and control panels. The dynamic queue you create takes the attributes of the model queue.

When you call MQOPEN, specify the name of the model queue in the *ObjectName* field of the MQOD structure. When the call completes, the *ObjectName* field is set to the name of the dynamic queue that is created. Also, the *ObjectQMgrName* field is set to the name of the local queue manager.

There are three ways to specify the name of the dynamic queue you create:

- Give the full name you want in the *DynamicQName* field of the MQOD structure.
- Specify a prefix (less than 33 characters) for the name, and allow the queue manager to generate the rest of the name. This means that the queue manager generates a unique name, but you still have some control (for example, you may want each user to use a certain prefix, or you may want to give a special security classification to queues with a certain prefix in their name). To use this method, specify an asterisk (★) for the last non-blank character of the *DynamicQName* field. Do not specify a single asterisk (★) for the dynamic queue name.

- Allow the queue manager to generate the full name. To use this method, specify an asterisk (\*) in the first character position of the *DynamicQName* field.

For more information about these methods, see the description of the *DynamicQName* field in “MQOD - Object descriptor” in the *MQSeries Application Programming Reference* manual.

There is more information on dynamic queues in “Dynamic queues” on page 45.

---

## Opening remote queues

A remote queue is a queue owned by a queue manager other than the one to which the application is connected.

To open a remote queue, use the MQOPEN call as for a local queue, but there are two ways you can specify the name of the queue:

1. In the *ObjectName* field of the MQOD structure, specify the name of the remote queue as known to the *local* queue manager.
2. In the *ObjectName* field of the MQOD structure, specify the name of the remote queue, as known to the *remote* queue manager. In the *ObjectQMGrName* field, specify either:
  - The name of the transmission queue that has the same name as the remote queue manager.
  - The name of an alias queue object that resolves to the transmission queue that has the same name as the remote queue manager.

This tells the queue manager the destination of the message as well as the transmission queue it needs to be put on to get there.

3. If *DefXmitQname* is supported, in the *ObjectName* field of the MQOD structure, specify the name of the remote queue name as known by the *remote* queue manager.

In both methods, only local names are validated when you call MQOPEN; the last check is for the existence of the transmission queue to be used.

These two methods are summarized in Table 3 on page 100.

---

## Closing objects using the MQCLOSE call

To close an object, you use the MQCLOSE call. If the object is a queue, you should note the following:

- There is no need to empty a temporary dynamic queue before you close it. When you close a temporary dynamic queue, the queue is deleted, along with any messages that may still be on it. This is true even if there are uncommitted MQGET, MQPUT, or MQPUT1 calls outstanding against the queue.
- In MQSeries for OS/390, if you have any MQGET requests with an MQGMO\_SET\_SIGNAL option outstanding for that queue, they are canceled.
- If you opened the queue using the MQOO\_BROWSE option, your browse cursor is destroyed.

## Using MQCLOSE

Namelists can be closed only on AIX, HP-UX, OS/2 Warp, OS/390, Sun Solaris, and Windows NT.

In MQSeries for AS/400, if the first MQOPEN call made an implicit connection to the queue manager, the final MQCLOSE call makes an implicit disconnection.

In MQSeries for VSE/ESA, ensure that your application issues a matching MQCLOSE call for each MQOPEN call. If your application does not issue the MQCLOSE call, the MQSeries for VSE/ESA housekeeping routine issues the MQCLOSE call on its behalf and unwanted messages appear in the SYSTEM.LOG queue.

Closure is unrelated to syncpoint, so you can close queues before or after syncpoint.

As input to the MQCLOSE call, you must supply:

- A connection handle. Use the same connection handle used to open it, or alternatively, for CICS and AS/400 applications, you can specify the constant MQHC\_DEF\_HCONN (which has the value zero).
- The handle of the object you want to close. Get this from the output of the MQOPEN call.
- MQCO\_NONE in the *Options* field (unless you are closing a permanent dynamic queue).
- The control option to determine whether the queue manager should delete the queue even if there are still messages on it (when closing a permanent dynamic queue).

The output from MQCLOSE is:

- A completion code
- A reason code
- The object handle, reset to the value MQHO\_UNUSABLE\_HOBJ

Descriptions of the parameters of the MQCLOSE call are given in “MQCLOSE - Close object” in the *MQSeries Application Programming Reference* manual.

---

## Chapter 9. Putting messages on a queue

Use the MQPUT call to put messages on the queue. You can use MQPUT repeatedly to put many messages on the same queue, following the initial MQOPEN call. Call MQCLOSE when you have finished putting all your messages on the queue.

If you want to put a single message on a queue and close the queue immediately afterwards, you can use the MQPUT1 call. MQPUT1 performs the same functions as the following sequence of calls:

- MQOPEN
- MQPUT
- MQCLOSE

Generally however, if you have more than one message to put on the queue, it is more efficient to use the MQPUT call. This depends on the size of the message and the platform you are working on.

The sections in this chapter describe how to:

- Put messages on a local queue
- Put messages on a remote queue
- Control context information
- Put a single message on a queue using the MQPUT1 call
- Put a single message to multiple destinations using a single MQPUT call

The final section mentions some cases where put calls might fail.

---

### Putting messages on a local queue using the MQPUT call

As input to the MQPUT call, you must supply:

- A connection handle (HCONN).
- A queue handle (HObj).
- A description of the message you want to put on the queue. This is in the form of a message descriptor structure (MQMD).
- Control information, in the form of a put-message options structure (MQPMO).
- The length of the data contained within the message (MQLONG).
- The message data itself.

The output from the MQPUT call is

- A reason code (MQLONG)
- A completion code (MQLONG)

## MQPUT to local queue

If the call completes successfully, it also returns your options structure and your message descriptor structure. The call modifies your options structure to show the name of the queue and the queue manager to which the message was sent. If you request that the queue manager generates a unique value for the identifier of the message you are putting (by specifying binary zero in the *MsgId* field of the MQMD structure), the call inserts the value in the *MsgId* field before returning this structure to you. This value must be reset before you issue another MQPUT.

There is a description of the MQPUT call in “MQPUT - Put message” in the *MQSeries Application Programming Reference* manual.

The following section describe the information you must supply as input to the MQPUT call.

### Specifying handles

For the connection handle (*Hconn*) in CICS on OS/390 and AS/400 applications, you can specify the constant MQHC\_DEF\_HCONN (which has the value zero), or you can use the connection handle returned by the MQCONN call. For other applications, always use the connection handle returned by the MQCONN call.

Whatever environment you are working in, use the same queue handle (*Hobj*) that is returned by the MQOPEN call.

### Defining messages using the MQMD structure

The message descriptor structure (MQMD) is an input/output parameter for the MQPUT and MQPUT1 calls. You use it to define the message you are putting on a queue.

If MQPRI\_PRIORITY\_AS\_Q\_DEF or MQPER\_PERSISTENCE\_AS\_Q\_DEF is specified for the message and the queue is a cluster queue the values used will be those of the queue the MQPUT resolves to. If that queue is disabled for MQPUT the call will fail. See “MQI and clusters” in the *MQSeries Queue Manager Clusters* book for more information.

**Note:** You must reset the *MsgId* and *CorrelId* to null prior to putting a new message in order to ensure they are unique. The values in these fields are returned on a successful MQPUT. However, if you set the *Version* field of the MQMD structure to 2, you can use the MQMO\_MATCH\_MSG\_ID and MQMO\_MATCH\_CORREL\_ID flags instead of resetting.

There is an introduction to the message properties that MQMD describes in Chapter 3, “MQSeries messages” on page 23, and there is a description of the structure itself in “MQMD - Message descriptor” in the *MQSeries Application Programming Reference* manual.

### Specifying options using the MQPMO structure

You use the MQPMO (Put Message Option) structure to pass options to the MQPUT and MQPUT1 calls.

The following sections give you help on filling in the fields of this structure. There is a description of the structure in “MQPMO - Put message options” in the *MQSeries Application Programming Reference* manual.

The fields of the structure include:

- *StrucId*
- *Version*
- *Options*
- *Context*
- *ResolvedQName*
- *ResolvedQMgrName*

These fields are described below.

#### *StrucId*

This identifies the structure as a put-message options structure. This is a 4-character field. Always specify MQPMO\_STRUC\_ID.

#### *Version*

This describes the version number of the structure. The default is MQPMO\_VERSION\_1. If you enter MQPMO\_VERSION\_2, you can use distribution lists (see “Distribution lists” on page 116). If you enter MQPMO\_CURRENT\_VERSION, your application is set always to use the most recent level.

#### *Options*

This controls the following:

- Whether the put operation is included in a unit of work
- How much context information is associated with a message
- Where the context information is taken from
- Whether the call fails if the queue manager is in a quiescing state
- Generation of a new message identifier and correlation identifier
- The order in which messages and segments are put on a queue

If you leave the *Options* field set to the default value (MQPMO\_NONE), the message you put has default context information associated with it.

Also, the way that the call operates with syncpoints is determined by the platform. The syncpoint control default is ‘yes’ in OS/390; for other platforms, it is ‘no’.

#### *Context*

This states the name of the queue handle that you want context information to be copied from (if requested in the *Options* field).

For an introduction to message context, see “Message context” on page 37.

For information about using the MQPMO structure to control the context information in a message, see “Controlling context information” on page 113.

#### *ResolvedQName*

This contains the name (after resolution of any alias name) of the queue that was opened to receive the message. This is an output field.

#### *ResolvedQMgrName*

This contains the name (after resolution of any alias name) of the queue manager that owns the queue in *ResolvedQName*. This is an output field.

The MQPMO can also accommodate fields required for distribution lists (see “Distribution lists” on page 116). If you wish to use this facility, Version 2 of the MQPMO structure is used.

## MQPUT to local queue

This includes the following fields:

### *Version*

This field describes the version number of the structure. For distribution lists, you are required to specify MQPMO\_VERSION\_2.

### *RecsPresent*

This field contains the number of Put Message Records (MQPMR) and Response Records (MQRR) present.

The value you enter can be the same as the number of Object Records provided at MQOPEN. However, if the value is less than the number of Object Records provided on the MQOPEN call (or if no Put Message Records are provided), the values of the queues that are not defined are taken from the default values provided by the message descriptor. Also, if the value is greater than the number of Object Records provided, the excess Put Message Records are ignored.

You are recommended to do one of the following:

- If you want to receive a report or reply from each destination, enter the same value as appears in the MQOR structure and use MQPMRs containing *MsgId* fields. Either initialize these *MsgId* fields to zeros or specify MQPMO\_NEW\_MSG\_ID.

When you have put the message to the queue, *MsgId* values that the queue manager has created become available in the MQPMRs; you can use these to identify which destination is associated with each report or reply.

- If you do not want to receive reports or replies, choose one of the following:
  1. If you want to identify destinations that fail immediately, you may still want to enter the same value in the *RecsPresent* field as appears in the MQOR structure and provide MQRRs to identify these destinations. Do not specify any MQPMRs.
  2. If you do not want to identify failed destinations, enter zero in the *RecsPresent* field and do not provide MQPMRs nor MQRRs.

**Note:** If you are using MQPUT1, the number of Response Record Pointers and Response Record Offsets must be zero.

For a full description of Put Message Records (MQPMR) and Response Records (MQRR), see “MQPMR - Put message record” and “MQRR - Response record” in the *MQSeries Application Programming Reference* manual.

### *PutMsgRecFields*

This indicates which fields are present in each Put Message Record (MQPMR). For a list of these fields, see “Using the MQPMR structure” on page 120.

### *PutMsgRecOffset* and *PutMsgRecPtr*

Pointers (typically in C) and offsets (typically in COBOL) are used to address the Put Message Records (see “Using the MQPMR structure” on page 120 for an overview of the MQPMR structure).

Use the *PutMsgRecPtr* field to specify a pointer to the first Put Message Record, or the *PutMsgRecOffset* field to specify the offset of the first Put Message Record. This is the offset from the start of the MQPMO. Depending on the *PutMsgRecFields* field, enter a nonnull value for either *PutMsgRecOffset* or *PutMsgRecPtr*.

*ResponseRecOffset and ResponseRecPtr*

You also use pointers and offsets to address the Response Records (see “Using the MQRR structure” on page 119 for further information about Response Records).

Use the *ResponseRecPtr* field to specify a pointer to the first Response Record, or the *ResponseRecOffset* field to specify the offset of the first Response Record. This is the offset from the start of the MQPMO structure. Enter a nonnull value for either *ResponseRecOffset* or *ResponseRecPtr*.

**Note:** If you are using MQPUT1 to put messages to a distribution list, *ResponseRecPtr* must be null or zero and *ResponseRecOffset* must be zero.

Additional information for putting to a distribution list (see “Distribution lists” on page 116) is provided in Version 2 of the Put Message Option structure (MQPMR). This is described in “MQPMR - Put message record” in the *MQSeries Application Programming Reference* manual.

## The data in your message

Give the address of the buffer that contains your data in the *Buffer* parameter of the MQPUT call. You can include anything in the data in your messages. The amount of data in the messages, however, affects the performance of the application that is processing them.

The maximum size of the data is determined by:

- The *MaxMsgLength* attribute of the queue manager
- The *MaxMsgLength* attribute of the queue on which you are putting the message
- The size of any message header added by MQSeries (including the Dead-letter header, MQDLH and the Distribution list header, MQDH)

The *MaxMsgLength* attribute of the queue manager holds the size of message that the queue manager can process. This has a default of 4 MB (1 MB=1048576 bytes). To determine the value of this attribute, use the MQINQ call on the queue manager object. For large messages, you can change this value (not on AS/400).

The *MaxMsgLength* attribute of a queue determines the maximum size of message you can put on the queue. If you attempt to put a message with a size larger than the value of this attribute, your MQPUT call fails. If you are putting a message on a remote queue, the maximum size of message that you can successfully put is determined by the *MaxMsgLength* attribute of the remote queue, of any intermediate transmission queues that the message is put on along the route to its destination, and of the channels used.

For an MQPUT operation, the size of the message must be smaller than or equal to the *MaxMsgLength* attribute of both the queue and the queue manager. The values of these attributes are independent, but you are recommended to set the *MaxMsgLength* of the queue to a value less than or equal to that of the queue manager.

MQSeries adds header information to messages in the following circumstances:

- When you put a message on a remote queue, MQSeries adds an MQXQH structure to the message. This structure includes the name of the destination queue and its owning queue manager.

## MQPUT to remote queue

- If MQSeries cannot deliver a message to a remote queue, it attempts to put the message on the dead-letter (undelivered-message) queue. It adds an MQDLH structure to the message. This structure includes the name of the destination queue and the reason the message was put on the dead-letter (undelivered-message) queue.
- If you want to send a message to multiple destination queues, MQSeries adds an MQDH header to the message. This describes the data that is present in a message, belonging to a distribution list, on a transmission queue. This point should be considered when choosing an optimum value for the maximum message length.

These structures are described in “MQXQH - Transmission queue header,” “MQDLH - Dead-letter header,” and “MQDH - Distribution header” in the *MQSeries Application Programming Reference* manual.

If your messages are of the maximum size allowed for these queues, the addition of these headers means that the put operations fail because the messages are now too big. To reduce the possibility of the put operations failing:

- Make the size of your messages smaller than the *MaxMsgLength* attribute of the transmission and dead-letter (undelivered-message) queues. Allow at least the value of the MQ\_MSG\_HEADER\_LENGTH constant (more for large distribution lists).
- Make sure that the *MaxMsgLength* attribute of the dead-letter (undelivered-message) queue is set to the same as the *MaxMsgLength* of the queue manager that owns the dead-letter queue.

The attributes for the queue manager and the message queuing constants are described in “Attributes for the queue manager,” and Chapter 6, “MQSeries constants,” in the *MQSeries Application Programming Reference* manual.

For information on how undelivered messages are handled in a distributed queuing environment, see “What happens when a message cannot be delivered?” in the *MQSeries Intercommunication* book.

---

## Putting messages on a remote queue

When you want to put a message on a remote queue (that is, a queue owned by a queue manager other than the one to which your application is connected) rather than a local queue, the only extra consideration is how you specify the name of the queue when you open it. This is described in “Opening remote queues” on page 105. There is no change to how you use the MQPUT or MQPUT1 call for a local queue.

For more information on using remote and transmission queues, see the *MQSeries Intercommunication* book.

---

## Controlling context information

To control context information, you use the *Options* field in the MQPMO structure.

If you don't, the queue manager will overwrite context information that may already be in the message descriptor with the identity and context information it has generated for your message. This is the same as specifying the MQPMO\_DEFAULT\_CONTEXT option. You may want this default context information when you create a new message (for example, when processing user input from an inquiry screen).

If you want no context information associated with your message, use the MQPMO\_NO\_CONTEXT option.

## Passing identity context

In general, programs should pass identity context information from message to message around an application until the data reaches its final destination. Programs should change the origin context information each time they change the data. However, applications that want to change or set any context information must have the appropriate level of authority. The queue manager checks this authority when the applications open the queues; they must have authority to use the appropriate context options for the MQOPEN call.

If your application gets a message, processes the data from the message, then puts the changed data into another message (possibly for processing by another application), the application should pass the identity context information from the original message to the new message. You can allow the queue manager to create the origin context information.

To save the context information from the original message, you must use the MQOO\_SAVE\_ALL\_CONTEXT option when you open the queue for getting the message. This is in addition to any other options you use with the MQOPEN call. Note, however, that you cannot save context information if you only browse the message.

When you create the second message, you must:

- Open the queue using the MQOO\_PASS\_IDENTITY\_CONTEXT option (in addition to the MQOO\_OUTPUT option).
- In the *Context* field of the put-message options structure, give the handle of the queue from which you saved the context information.
- In the *Options* field of the put-message options structure, specify the MQPMO\_PASS\_IDENTITY\_CONTEXT option.

### Passing all context

If your application gets a message, and puts the message data (unchanged) into another message, the application should pass both the identity and the origin context information from the original message to the new message. An example of an application that might do this is a message mover, which moves messages from one queue to another.

Follow the same procedure as for passing identity context, except you use the MQOPEN option MQOO\_PASS\_ALL\_CONTEXT and the put-message option MQPMO\_PASS\_ALL\_CONTEXT.

### Setting identity context

If you want to set the identity context information for a message, leaving the queue manager to set the origin context information:

- Open the queue using the MQOO\_SET\_IDENTITY\_CONTEXT option.
- Put the message on the queue, specifying the MQPMO\_SET\_IDENTITY\_CONTEXT option. In the message descriptor, specify whatever identity context information you require.

### Setting all context

If you want to set both the identity and the origin context information for a message:

- Open the queue using the MQOO\_SET\_ALL\_CONTEXT option.
- Put the message on the queue, specifying the MQPMO\_SET\_ALL\_CONTEXT option. In the message descriptor, specify whatever identity and origin context information you require.

Appropriate authority is needed for each type of context setting.

---

## Putting one message on a queue using the MQPUT1 call

Use the MQPUT1 call when you want to close the queue immediately after you have put a single message on it. For example, a server application is likely to use the MQPUT1 call when it is sending a reply to each of the different queues.

MQPUT1 is functionally equivalent to calling MQOPEN followed by MQPUT, followed by MQCLOSE. The only difference in the syntax for the MQPUT and MQPUT1 calls is that for MQPUT you must specify an object handle, whereas for MQPUT1 you must specify an object descriptor structure (MQOD) as defined in MQOPEN (see “Identifying objects (the MQOD structure)” on page 99). This is because you need to give information to the MQPUT1 call about the queue it has to open, whereas when you call MQPUT, the queue must already be open.

As input to the MQPUT1 call, you must supply:

- A connection handle.
- A description of the object you want to open. This is in the form of an object descriptor structure (MQOD).
- A description of the message you want to put on the queue. This is in the form of a message descriptor structure (MQMD).

- Control information in the form of a put-message options structure (MQPMO).
- The length of the data contained within the message (MQLONG).
- The address of the message data.

The output from MQPUT1 is:

- A completion code
- A reason code

If the call completes successfully, it also returns your options structure and your message descriptor structure. The call modifies your options structure to show the name of the queue and the queue manager to which the message was sent. If you request that the queue manager generate a unique value for the identifier of the message you are putting (by specifying binary zero in the *MsgId* field of the MQMD structure), the call inserts the value in the *MsgId* field before returning this structure to you.

**Note:** You cannot use MQPUT1 with a model queue name; however, once a model queue has been opened, you can issue an MQPUT1 to the dynamic queue.

The six input parameters for MQPUT1 are:

#### *Hconn*

This is a connection handle. For CICS and AS/400 applications, you can specify the constant MQHC\_DEF\_HCONN (which has the value zero), or use the connection handle returned by the MQCONN call. For other programs, always use the connection handle returned by the MQCONN call.

#### *ObjDesc*

This is an object descriptor structure (MQOD).

In the *ObjectName* and *ObjectQMgrName* fields, give the name of the queue on which you want to put a message, and the name of the queue manager that owns this queue.

The *DynamicQName* field is ignored for the MQPUT1 call because it cannot use model queues.

Use the *AlternateUserId* field only if you want to nominate an alternate user identifier that is to be used to test authority to open the queue.

#### *MsgDesc*

This is a message descriptor structure (MQMD). As with the MQPUT call, use this structure to define the message you are putting on the queue.

#### *PutMsgOpts*

This is a put-message options structure (MQPMO). Use it as you would for the MQPUT call (see “Specifying options using the MQPMO structure” on page 108).

When the *Options* field is set to zero, the queue manager uses your own user ID when it performs tests for authority to access the queue. Also, the queue manager ignores any alternate user identifier given in the *AlternateUserId* field of the MQOD structure.

#### *BufferLength*

This is the length of your message.

#### *Buffer*

This is the buffer area that contains the text of your message.

## Distribution lists

When you use clusters, MQPUT1 operates as though MQOO\_BIND\_NOT\_FIXED is in effect. Applications must use the resolved fields in the MQPMO structure rather than the MQOD structure to determine where the message was sent. See “MQI and clusters” in the *MQSeries Queue Manager Clusters* book for more information.

There is a description of the MQPUT1 call in “MQPUT1 - Put one message” in the *MQSeries Application Programming Reference* manual.

---

## Distribution lists

*These are supported on MQSeries Version 5 products and MQSeries for AS/400.*

Distribution lists allow you to put a message to multiple destinations in a single MQPUT or MQPUT1 call. Multiple queues can be opened using a single MQOPEN and a message can then be put to each of those queues using a single MQPUT. Some generic information from the MQI structures used for this process can be superseded by specific information relating to the individual destinations included in the distribution list.

When an MQOPEN call is issued, generic information is taken from the Object Descriptor (MQOD). If you specify MQOD\_VERSION\_2 in the *Version* field and a value greater than zero in the *RecsPresent* field, the *Hobj* can be defined as a handle of a list (of one or more queues) rather than of a queue. In this case, specific information is given through the object records (MQORs), which give details of destination (that is, *ObjectName* and *ObjectQMgrName*).

The object handle (*Hobj*) is passed to the MQPUT call, allowing you to put to a list rather than to a single queue.

When a message is put on the queues (MQPUT), generic information is taken from the Put Message Option structure (MQPMO) and the Message Descriptor (MQMD). Specific information is given in the form of Put Message Records (MQPMRs).

Response Records (MQRR) can receive a completion code and reason code specific to each destination queue.

**Note:** There may be an impact on portability if pointers are used in these languages on the following platforms:

Language	Platform
COBOL	AS/400
RPG	AS/400

Figure 5 on page 117 shows how distribution lists work:

## Opening distribution lists

Use the MQOPEN call to open a distribution list, and use the options of the call to specify what you want to do with the list.

As input to MQOPEN, you must supply:

- A connection handle (see Chapter 9, “Putting messages on a queue” on page 107 for a description)




Figure 5. How distribution lists work. This diagram shows that **one** message is transmitted through the channel and can be put on more than one remote queue.

- Generic information in the Object Descriptor structure (MQOD)
- The name of each queue you want to open, using the Object Record structure (MQOR)

The output from MQOPEN is:

- An object handle that represents your access to the distribution list
- A generic completion code
- A generic reason code
- Response Records (optional), containing a completion code and reason for each destination

### Using the MQOD structure

Use the MQOD structure to identify the queues you want to open. To define a distribution list, you must specify MQOD\_VERSION\_2 in the *Version* field, a value greater than zero in the *RecsPresent* field, and MQOT\_Q in the *ObjectType* field. See “MQOD - Object descriptor” in the *MQSeries Application Programming Reference* manual for a description of all the fields of the MQOD structure.

### Using the MQOR structure

An MQOR structure must be provided for each destination. The structure contains the destination queue and queue manager names. The *ObjectName* and *ObjectQMGRName* fields in the MQOD are not used for distribution lists. There must be one or more object records. If the *ObjectQMGRName* is left blank, the local queue manager is used. See “MQOR - Object record” in the *MQSeries Application Programming Reference* manual for further information about these fields.

You can specify the destination queues in two ways:

- By using the offset field *ObjectRecOffset*.

In this case, the application should declare its own structure containing an MQOD structure, followed by the array of MQOR records (with as many array elements as are needed), and set *ObjectRecOffset* to the offset of the first element in the array from the start of the MQOD. Care must be taken to ensure that this offset is correct.

Use of built-in facilities provided by the programming language is recommended, if these are available in all of the environments in which the application must run. The following illustrates this technique for the COBOL programming language:

```
01 MY-OPEN-DATA.  
  02 MY-MQOD.  
    COPY CMQODV.  
  02 MY-MQOR-TABLE OCCURS 100 TIMES.  
    COPY CMQORV.  
  MOVE LENGTH OF MY-MQOD TO MQOD-OBJECTRECOFFSET.
```

Alternatively, the constant MQOD\_CURRENT\_LENGTH can be used if the programming language does not support the necessary built-in facilities in all of the environments concerned. The following illustrates this technique:

```
01 MY-MQ-CONSTANTS.  
  COPY CMQV.  
01 MY-OPEN-DATA.  
  02 MY-MQOD.  
    COPY CMQODV.  
  02 MY-MQOR-TABLE OCCURS 100 TIMES.  
    COPY CMQORV.  
  MOVE MQOD-CURRENT-LENGTH TO MQOD-OBJECTRECOFFSET.
```

However, this will work correctly only if the MQOD structure and the array of MQOR records are contiguous; if the compiler inserts skip bytes between the MQOD and the MQOR array, these must be added to the value stored in *ObjectRecOffset*.

Using *ObjectRecOffset* is recommended for programming languages that do not support the pointer data type, or that implement the pointer data type in a way that is not portable to different environments (for example, the COBOL programming language).

- By using the pointer field *ObjectRecPtr*.

In this case, the application can declare the array of MQOR structures separately from the MQOD structure, and set *ObjectRecPtr* to the address of the array. The following illustrates this technique for the C programming language:

```
MQOD MyMqod;  
MQOR MyMqor[100];  
MyMqod.ObjectRecPtr = MyMqor;
```

Using *ObjectRecPtr* is recommended for programming languages that support the pointer data type in a way that is portable to different environments (for example, the C programming language).

Whichever technique is chosen, one of *ObjectRecOffset* and *ObjectRecPtr* must be used; the call fails with reason code MQRC\_OBJECT\_RECORDS\_ERROR if both are zero, or both are nonzero.

### Using the MQRR structure

These structures are destination specific as each Response Record contains a *CompCode* and *Reason* field for each queue of a distribution list. You must use this structure to enable you to distinguish where any problems lie.

For example, if you receive a reason code of MQRC\_MULTIPLE\_REASONS and your distribution list contains five destination queues, you will not know which queues the problems apply to if you do not use this structure. However, if you have a completion code and reason code for each destination, you can locate the errors more easily.

See “MQRR - Response record” in the *MQSeries Application Programming Reference* manual for further information about the MQRR structure.

Figure 6 shows how you can open a distribution list in C:




Figure 6. Opening a distribution list in C. The MQOD uses pointers to the MQOR and MQRR structures.

Figure 7 shows how you can open a distribution list in COBOL:




Figure 7. Opening a distribution list in COBOL. The MQOD uses offsets in COBOL.

### Using the MQOPEN options

The following options can be specified when opening a distribution list:

- MQOO\_OUTPUT
- MQOO\_FAIL\_IF QUIESCING (optional)
- MQOO\_ALTERNATE\_USER\_AUTHORITY (optional)
- MQOO\_\*\_CONTEXT (optional)

See Chapter 8, “Opening and closing objects” on page 97 for a description of these options.

## Putting messages to a distribution list

To put messages to a distribution list, you can use MQPUT or MQPUT1. As input, you must supply:

- A connection handle (see Chapter 9, “Putting messages on a queue” on page 107 for a description).
- An object handle. If a distribution list is opened using MQOPEN, the *Hobj* allows you only to put to the list.

## Putting messages to a distribution list

- A message descriptor structure (MQMD). See “MQMD - Message descriptor” in the *MQSeries Application Programming Reference* manual for a description of this structure.
- Control information in the form of a put-message option structure (MQPMO). See “Specifying options using the MQPMO structure” on page 108 for information about filling in the fields of the MQPMO structure.
- Control information in the form of Put Message Records (MQPMR).
- The length of the data contained within the message (MQLONG).
- The message data itself.

The output is:

- A completion code
- A reason code
- Response Records (optional)

### Using the MQPMR structure

This structure is optional and gives destination-specific information for some fields that you may want to identify differently from those already identified in the MQMD. For a description of these fields, see “MQMD - Message descriptor” in the *MQSeries Application Programming Reference* manual.

The content of each record depends on the information given in the *PutMsgRecFields* field of the MQPMO. For example, in the sample program AMQSPTL0.C (see “The Distribution List sample program” on page 345 for a description) showing the use of distribution lists, the sample chooses to provide values for *MsgId* and *CorrelId* in the MQPMR.

This section of the sample program looks like this:

```
typedef struct
{
  MQBYTE24 MsgId;
  MQBYTE24 CorrelId;
} PutMsgRec;...
/*****
MQLONG PutMsgRecFields=MQPMRF_MSG_ID | MQPMRF_CORREL_ID;
```

This implies that *MsgId* and *CorrelId* are provided for each destination of a distribution list. The Put Message Records are provided as an array.

Figure 8 shows how you can put a message to a distribution list in C:




Figure 8. Putting a message to a distribution list in C. The MQPMO uses pointers to the MQPMR and MQRR structures.

Figure 9 on page 121 shows how you can put a message to a distribution list in COBOL:




Figure 9. Putting a message to a distribution list in COBOL. The MQPMO uses offsets in COBOL.

### Using MQPUT1

If you are using MQPUT1, consider the following:

1. The values of the *ResponseRecOffset* and *ResponseRecPtr* fields must be null or zero.
2. The Response Records, if required, must be addressed from the MQOD.

---

## Some cases where the put calls fail

If certain attributes of a queue are changed using the FORCE option on a command during the interval between you issuing an MQOPEN and an MQPUT call, the MQPUT call fails and returns the MQRC\_OBJECT\_CHANGED reason code. The queue manager marks the object handle as being no longer valid. This also happens if the changes are made while an MQPUT1 call is being processed, or if the changes apply to any queue to which the queue name resolves. The attributes that affect the handle in this way are listed in the description of the MQOPEN call in "MQOPEN - Open object" in the *MQSeries Application Programming Reference* manual. If your call returns the MQRC\_OBJECT\_CHANGED reason code, close the queue, reopen it, then try to put a message again.

If put operations are inhibited for a queue on which you are attempting to put messages (or any queue to which the queue name resolves), the MQPUT or MQPUT1 call fails and returns the MQRC\_PUT\_INHIBITED reason code. You may be able to put a message successfully if you attempt the call at a later time, if the design of the application is such that other programs change the attributes of queues regularly.

Further, if the queue that you are trying to put your message on is full, the MQPUT or MQPUT1 call fails and returns MQRC\_Q\_FULL.

If a dynamic queue (either temporary or permanent) has been deleted, MQPUT calls using a previously acquired object handle fail and return the MQRC\_Q\_DELETED reason code. In this situation, it is good practice to close the object handle as it is no longer of any use to you.

In the case of distribution lists, multiple completion codes and reason codes can occur in a single request. These cannot be handled using only the *CompCode* and *Reason* output fields on MQOPEN and MQPUT.

When distribution lists are used to put messages to multiple destinations, the Response Records contain the specific *CompCode* and *Reason* for each destination. If you receive a completion code of MQCC\_FAILED, no message is put on any destination queue successfully. If the completion code is MQCC\_WARNING, the

## Put call failure

message is successfully put on one or more of the destination queues. If you receive a return code of `MQRC_MULTIPLE_REASONS`, the reason codes are not all the same for every destination. Therefore, it is recommended to use the `MQRR` structure so that you can determine which queue or queues caused an error and the reasons for each.

---

## Chapter 10. Getting messages from a queue

You can get messages from a queue in two ways:

1. You can **remove** a message from the queue so that other programs can no longer see it.
2. You can **copy** a message, leaving the original message on the queue. This is known as *browsing*. You can easily remove the message once you have browsed it.

In both cases, you use the MQGET call, but first your application must be connected to the queue manager, and you must use the MQOPEN call to open the queue (for input, browse, or both). These operations are described in Chapter 7, “Connecting and disconnecting a queue manager” on page 89 and Chapter 8, “Opening and closing objects” on page 97.

When you have opened the queue, you can use the MQGET call repeatedly to browse or remove messages on the same queue. Call MQCLOSE when you have finished getting all the messages you want from the queue.

This chapter tells you how to get messages from a queue using the MQGET call, and includes:

- Information on the MQGET call itself
- The order in which messages are retrieved
- Getting a particular message
- Waiting for messages
- Handling large messages
- Getting notification when a message arrives (signaling)
- Avoiding loops by skipping backout
- Converting messages from different systems
- Browsing messages
- Why MQGET might fail

---

### Getting messages from a queue using the MQGET call

The MQGET call gets a message from an open local queue. It cannot get a message from a queue on another system.

As input to the MQGET call, you must supply:

- A connection handle.
- A queue handle.
- A description of the message you want to get from the queue. This is in the form of a message descriptor (MQMD) structure.
- Control information in the form of a Get Message Options (MQGMO) structure.
- The size of the buffer you have assigned to hold the message (MQLONG).
- The address of the storage in which the message must be put.

The output from MQGET is:

- A reason code

- A completion code
- The message in the buffer area you specified, if the call completes successfully
- Your options structure, modified to show the name of the queue from which the message was retrieved
- Your message descriptor structure, with the contents of the fields modified to describe the message that was retrieved
- The length of the message (MQLONG)

There is a description of the MQGET call in “MQGET - Get message” in the *MQSeries Application Programming Reference* manual.

The following sections describe the information you must supply as input to the MQGET call.

### Specifying connection handles

For CICS on OS/390, VSE/ESA, and AS/400 applications, you can specify the constant MQHC\_DEF\_HCONN (which has the value zero), or use the connection handle returned by the MQCONN call. For other applications, always use the connection handle returned by the MQCONN call.

Use the queue handle (*Hobj*) that is returned when you call MQOPEN.

### Describing messages using the MQMD structure and the MQGET call

To identify the message you want to get from a queue, use the message descriptor structure (MQMD). This is an input/output parameter for the MQGET call. There is an introduction to the message properties that MQMD describes in Chapter 3, “MQSeries messages” on page 23, and there is a description of the structure itself in “MQMD - Message descriptor” in the *MQSeries Application Programming Reference* manual.

If you know which message you want to get from the queue, see “Getting a particular message” on page 137.

If you do not specify a particular message, MQGET retrieves the **first** message in the queue. “The order in which messages are retrieved from a queue” on page 128 describes how the priority of a message, the *MsgDeliverySequence* attribute of the queue, and the MQGMO\_LOGICAL\_ORDER option determine the order of the messages in the queue.

**Note:** If you want to use MQGET more than once (for example, to step through the messages in the queue), you can set the *MsgId* and *CorrelId* fields of this structure to null after each call. This prevents the the call from filling these fields with the identifiers of the message that was retrieved, and therefore having messages with the same identifiers as the previous message.

However, if you want to group your messages, the *GroupId* should be the same for messages in the same group, so that the call will look for a message having the same identifiers as the previous message in order to make up the whole group.

## Specifying MQGET options using the MQGMO structure

The MQGMO structure is an input/output variable for passing options to the MQGET call.

The following sections give you help on filling in some of the fields of this structure. There is a description of the structure in “MQGMO - Get-message options” in the *MQSeries Application Programming Reference* manual.

### *StrucId*

*StrucId* is a 4-character field used to identify the structure as a get-message options structure. Always specify MQGMO\_STRUC\_ID.

### *Version*

*Version* describes the version number of the structure. MQGMO\_VERSION\_1 is the default. If you wish to use the Version 2 fields or retrieve messages in logical order, specify MQGMO\_VERSION\_2. If you wish to use the Version 3 fields or retrieve messages in logical order, specify MQGMO\_VERSION\_3. MQGMO\_CURRENT\_VERSION sets your application to use the most recent level.

### *Options*

Within your code, you can select the options in any order as each option is represented by a bit in the *Options* field.

The *Options* field controls:

- Whether the MQGET call waits for a message to arrive on the queue before it completes (see “Waiting for messages” on page 146)
- Whether the get operation is included in a unit of work
- Whether a nonpersistent message is retrieved outside syncpoint, allowing fast messaging
- In MQSeries for OS/390, whether the message retrieved is marked as skipping backout (see “Skipping backout” on page 150)
- Whether the message is removed from the queue, or merely browsed
- Whether to select a message by using a browse cursor or by other selection criteria
- Whether the call succeeds even if the message is longer than your buffer
- In MQSeries for OS/390, whether to allow the call to complete, but set a signal to indicate that you want to be notified when a message arrives
- Whether the call fails if the queue manager is in a quiescing state
- On OS/390, whether the call fails if the connection is in a quiescing state
- Whether application message data conversion is required (see “Application data conversion” on page 152)
- On MQSeries Version 5 products and MQSeries for AS/400, the order in which messages and segments are retrieved from a queue
- On MQSeries Version 5 products and MQSeries for AS/400, whether complete, logical messages only are retrievable
- On MQSeries Version 5 products and MQSeries for AS/400, whether messages in a group can be retrieved only when **all** messages in the group are available

- On MQSeries Version 5 products and MQSeries for AS/400, whether segments in a logical message can be retrieved only when **all** segments in the logical message are available

If you leave the *Options* field set to the default value (MQGMO\_NO\_WAIT), the MQGET call operates this way:

- If there is no message matching your selection criteria on the queue, the call does not wait for a message to arrive, but completes immediately. Also, in MQSeries for OS/390, the call does not set a signal requesting notification when such a message arrives.
- The way that the call operates with syncpoints is determined by the platform:

Platform	Under syncpoint control
AS/400	No
UNIX systems	No
OS/390	Yes
OS/2	No
Tandem NSK	Yes
VSE/ESA	Yes
Windows NT	No
Windows	No

- In MQSeries for OS/390, the message retrieved is not marked as skipping backout.
- The selected message is removed from the queue (not browsed).
- No application message data conversion is required.
- The call fails if the message is longer than your buffer.

### *WaitInterval*

The *WaitInterval* field specifies the maximum time (in milliseconds) that the MQGET call waits for a message to arrive on the queue when you use the MQGMO\_WAIT option. If no message arrives within the time specified in *WaitInterval*, the call completes and returns a reason code showing that there was no message that matched your selection criteria on the queue.

In MQSeries for OS/390, if you use the MQGMO\_SET\_SIGNAL option, the *WaitInterval* field specifies the time for which the signal is set.

For more information on these options, see “Waiting for messages” on page 146 and “Signaling” on page 147.

### *Signal1*

*Signal1* is supported on MQSeries for OS/390, MQSeries for Tandem NSK, and MQSeries for Windows Version 2.1 only.

If you have chosen to use the MQGMO\_SET\_SIGNAL option to request that your application is notified when a suitable message arrives, you must specify the type of signal in the *Signal1* field. In MQSeries on all other platforms, the *Signal1* field is reserved and its value is not significant.

For more information, see “Signaling” on page 147.

*Signal2*

On MQSeries for Windows Version 2.1 this specifies an identifier for the signal message. The *Signal2* field is reserved on all other platforms and its value is not significant.

For more information, see “Signaling” on page 147.

*ResolvedQName*

*ResolvedQName* is an output field in which the queue manager returns the name of the queue (after resolution of any alias) from which the message was retrieved.

*MatchOptions*

*MatchOptions* controls the selection criteria for MQGET.

*GroupStatus*

*GroupStatus* indicates whether the message you have retrieved is in a group.

*SegmentStatus*

*SegmentStatus* indicates whether the item you have retrieved is a segment of a logical message.

*Segmentation*

*Segmentation* indicates whether segmentation is allowed for the message retrieved.

*MsgToken*

*MsgToken* is supported on MQSeries for OS/390 only.

*MsgToken* uniquely identifies a message.

For more information, see “MQSeries Workflow” on page 249.

*ReturnedLength*

*ReturnedLength* is an output field in which the queue manager returns the length of message data returned (in bytes).

## Specifying the size of the buffer area

In the *BufferLength* parameter of the MQGET call, specify the size of the buffer area you want to use to hold the message data that you retrieve. There are three ways to decide how big this should be:

1. You may already know what length of messages to expect from this program. If so, specify a buffer of this size.

However, you can use the MQGMO\_ACCEPT\_TRUNCATED\_MSG option in the MQGMO structure if you want the MQGET call to complete even if the message is too big for the buffer. In this case:

- The buffer is filled with as much of the message as it can hold
- The call returns a warning completion code
- The message is removed from the queue (discarding the remainder of the message), or the browse cursor is advanced (if you are browsing the queue)
- The real length of the message is returned in *DataLength*

Without this option, the call still completes with a warning, but it does not remove the message from the queue (or advance the browse cursor).

## MQGET retrieval sequence

2. Estimate a size for the buffer (or even specify a size of zero bytes) and **do not** use the `MQGMO_ACCEPT_TRUNCATED_MSG` option. If the MQGET call fails (for example, because the buffer is too small), the length of the message is returned in the *DataLength* parameter of the call. (The buffer is still filled with as much of the message as it can hold, but the processing of the call is not completed.) Store the *MsgId* of this message, then repeat the MQGET call, specifying a buffer area of the correct size, and the *MsgId* you noted from the first call.

If your program is serving a queue that is also being served by other programs, one of those other programs may remove the message you want before your program can issue another MQGET call. Your program could waste time searching for a message that no longer exists. To avoid this, first browse the queue until you find the message you want, specifying a *BufferLength* of zero and using the `MQGMO_ACCEPT_TRUNCATED_MSG` option. This positions the browse cursor under the message you want. You can then retrieve the message by calling MQGET again, specifying the `MQGMO_MSG_UNDER_CURSOR` option. If another program removes the message between your browse and removal calls, your second MQGET fails immediately (without searching the whole queue), because there is no message under your browse cursor.

3. The *MaxMsgLength* queue attribute determines the maximum length of messages accepted for that queue and the *MaxMsgLength* queue manager attribute determines the maximum length of messages accepted for that queue manager. If you do not know what length of message to expect, you can inquire about the *MaxMsgLength* attribute (using the MQINQ call), then specify a buffer of this size.

For further information about the *MaxMsgLength* attribute, see “Increasing the maximum message length” on page 140.

---

## The order in which messages are retrieved from a queue

You have control over the order in which you retrieve messages from a queue. This section looks at the options.

### Priority

A program can assign a priority to a message when it puts the message on a queue (see “Message priorities” on page 32). Messages of equal priority are stored in a queue in order of arrival, not the order in which they are committed.

The queue manager maintains queues either in strict FIFO (first in, first out) sequence, or in FIFO within priority sequence. This depends on the setting of the *MsgDeliverySequence* attribute of the queue. When a message arrives on a queue, it is inserted immediately following the last message that has the same priority.

Programs can either get the first message from a queue, or they can get a particular message from a queue, ignoring the priority of those messages. For example, a program may want to process the reply to a particular message that it sent earlier. For more information, see “Getting a particular message” on page 137.

If an application puts a sequence of messages on a queue, another application can retrieve those messages in the same order that they were put, provided:

- The messages all have the same priority
- The messages were all put within the same unit of work, or all put outside a unit of work
- The queue is local to the putting application

If these conditions are not met, and the applications depend on the messages being retrieved in a certain order, the applications must either include sequencing information in the message data, or establish a means of acknowledging receipt of a message before the next one is sent.

On MQSeries for OS/390, the queue attribute, *IndexType*, can be used to increase the speed of MQGET operations on the queue. For more information, see “Type of index” on page 139.

## Logical and physical ordering

*Logical and physical ordering is supported on MQSeries Version 5 products only.*

Messages on queues can occur (within each priority level) in *physical* or *logical* order:

<b>Order</b>	<b>Meaning</b>
<b>Physical</b>	This is the order in which messages arrive on a queue.
<b>Logical</b>	This is when all of the messages and segments within a group are in their logical sequence, adjacent to each other, in the position determined by the physical position of the first item belonging to the group.

For a description of groups, messages, and segments, see “Message groups” on page 33. These physical and logical orders may differ because:

- Groups can arrive at a destination at similar times from different applications, therefore losing any distinct physical order.
- Even within a single group, messages may get out of order due to rerouting or delay of some of the messages in the group.

For example, the logical order might look like Figure 10 on page 130:

## MQGET retrieval sequence




Figure 10. Logical order on a queue

These messages would appear in the following order on a queue:

1. Message A (not in a group)
2. Logical message 1 of group Y
3. Logical message 2 of group Y
4. Segment 1 of (last) logical message 3 of group Y
5. (Last) segment 2 of (last) logical message 3 of group Y
6. Logical message 1 of group Z
7. (Last) logical message 2 of group Z
8. Message B (not in a group)

The physical order, however, might be entirely different. As stated on page 129, the physical position of the **first** item within each group determines the logical position of the whole group. For example, if groups Y and Z arrived at similar times, and message 2 of group Z overtook message 1 of the same group, the physical order would look like Figure 11 on page 131:




Figure 11. Physical order on a queue

These messages appear in the following order on the queue:

1. Message A (not in a group)
2. Logical message 1 of group Y
3. Logical message 2 of group Z
4. Logical message 2 of group Y
5. Segment 1 of (last) logical message 3 of group Y
6. (Last) segment 2 of (last) logical message 3 of group Y
7. Logical message 1 of group Z
8. Message B (not in a group)

When getting messages, you can specify `MQGMO_LOGICAL_ORDER` to retrieve messages in logical rather than physical order.

If you issue an `MQGET` call with `MQGMO_BROWSE_FIRST` and `MQGMO_LOGICAL_ORDER`, subsequent `MQGET` calls with `MQGMO_BROWSE_NEXT` must also specify this option. Conversely, if the `MQGET` with `MQGMO_BROWSE_FIRST` does not specify `MQGMO_LOGICAL_ORDER`, neither must the following `MQGET`s with `MQGMO_BROWSE_NEXT`.

The group and segment information that the queue manager retains for `MQGET` calls that browse messages on the queue is separate from the group and segment information that the queue manager retains for `MQGET` calls that remove

## MQGET retrieval sequence

messages from the queue. When MQGMO\_BROWSE\_FIRST is specified, the queue manager ignores the group and segment information for browsing, and scans the queue as though there were no current group and no current logical message.

**Note:** Special care is needed if an MQGET call is used to browse *beyond the end* of a message group (or logical message not in a group) when MQGMO\_LOGICAL\_ORDER is not specified. For example, if the last message in the group happens to *precede* the first message in the group on the queue, using MQGMO\_BROWSE\_NEXT to browse beyond the end of the group, specifying MQMO\_MATCH\_MSG\_SEQ\_NUMBER with *MsgSeqNumber* set to 1 (to find the first message of the next group) would return again the first message in the group already browsed. This could happen immediately, or a number of MQGET calls later (if there are intervening groups).

The possibility of an infinite loop can be avoided by opening the queue *twice* for browse:

- Use the first handle to browse only the first message in each group.
- Use the second handle to browse only the messages within a specific group.
- Use the MQMO\_\* options to move the second browse cursor to the position of the first browse cursor, before browsing the messages in the group.
- Do not use the MQGMO\_BROWSE\_NEXT browse beyond the end of a group.

For further information about this, see “MQGMO - Get-message options” in the *MQSeries Application Programming Reference* manual.

For most applications you will probably choose either logical or physical ordering when browsing. However, if you want to switch between these modes, remember that when you first issue a browse with MQGMO\_LOGICAL\_ORDER, your position within the logical sequence is established.

If the first item within the group is not present at this time, the group you are in is not considered to be part of the logical sequence.

Once the browse cursor is within a group, it can continue within the same group, even if the first message is removed. Initially though, you can never move into a group using MQGMO\_LOGICAL\_ORDER where the first item is not present.

### Grouping logical messages

There are two main reasons for using logical messages in a group:

- The messages may need to be processed in the correct order
- Each of the messages in a group may need to be processed in a related way.

In either case, retrieval of the entire group must be carried out by the same getting application instance.

For example, assume that the group consists of four logical messages. The putting application looks like this:

```
PMO.Options = MQPMO_LOGICAL_ORDER | MQPMO_SYNCPOINT

MQPUT MD.MsgFlags = MQMF_MSG_IN_GROUP
MQPUT MD.MsgFlags = MQMF_MSG_IN_GROUP
MQPUT MD.MsgFlags = MQMF_MSG_IN_GROUP
MQPUT MD.MsgFlags = MQMF_LAST_MSG_IN_GROUP

MQCMIT
```

The getting application chooses not to start processing any group until all of the messages within it have arrived. MQGMO\_ALL\_MSGS\_AVAILABLE is therefore specified for the first message in the group; the option is ignored for subsequent messages within the group.

Once the first logical message of the group is retrieved, MQGMO\_LOGICAL\_ORDER is used to ensure that the remaining logical messages of the group are retrieved in order.

So, the getting application looks like this:

```
/* Wait for the first message in a group, or a message not in a group */
GMO.Options = MQGMO_SYNCPOINT | MQGMO_WAIT
              | MQGMO_ALL_MSGS_AVAILABLE | MQGMO_LOGICAL_ORDER
do while ( GroupStatus == MQGS_MSG_IN_GROUP )
    MQGET
    /* Process each remaining message in the group */
    ...

MQCMIT
```

For further examples of grouping messages, see “Application segmentation of logical messages” on page 143 and “Putting and getting a group that spans units of work.”

### Putting and getting a group that spans units of work

In the previous case, messages or segments cannot start to leave the node (if its destination is remote) or start to be retrieved until all of the group has been put and the unit of work is committed. This may not be what you want if it takes a long time to put the whole group, or if queue space is limited on the node. To overcome this, the group can be put in several units of work.

If the group is put within multiple units of work, it is possible for some of the group to commit even when a failure of the putting application occurs. The application must therefore save status information, committed with each unit of work, which it can use after a restart to resume an incomplete group. The simplest place to record this information is in a STATUS queue. If a complete group has been successfully put, the STATUS queue is empty.

If segmentation is involved, the logic is similar. In this case, the StatusInfo must include the *Offset*.

## MQGET retrieval sequence

Here is an example of putting the group in several units of work:

```
PMO.Options = MQPMO_LOGICAL_ORDER | MQPMO_SYNCPOINT

/* First UOW */

MQPUT MD.MsgFlags = MQMF_MSG_IN_GROUP
MQPUT MD.MsgFlags = MQMF_MSG_IN_GROUP
MQPUT MD.MsgFlags = MQMF_MSG_IN_GROUP
StatusInfo = GroupId,MsgSeqNumber from MQMD
MQPUT (StatusInfo to STATUS queue) PMO.Options = MQPMO_SYNCPOINT
MQCMIT

/* Next and subsequent UOWs */
MQPUT MD.MsgFlags = MQMF_MSG_IN_GROUP
MQPUT MD.MsgFlags = MQMF_MSG_IN_GROUP
MQPUT MD.MsgFlags = MQMF_MSG_IN_GROUP
MQGET (from STATUS queue) GMO.Options = MQGMO_SYNCPOINT
StatusInfo = GroupId,MsgSeqNumber from MQMD
MQPUT (StatusInfo to STATUS queue) PMO.Options = MQPMO_SYNCPOINT
MQCMIT

/* Last UOW */
MQPUT MD.MsgFlags = MQMF_MSG_IN_GROUP
MQPUT MD.MsgFlags = MQMF_MSG_IN_GROUP
MQPUT MD.MsgFlags = MQMF_LAST_MSG_IN_GROUP
MQGET (from STATUS queue) GMO.Options = MQGMO_SYNCPOINT
MQCMIT
```

If all the units of work have been committed, the entire group has been put successfully, and the STATUS queue is empty. If not, the group must be resumed at the point indicated by the status information. MQPMO\_LOGICAL\_ORDER cannot be used for the first put, but can thereafter.

Restart processing looks like this:

```
MQGET (StatusInfo from STATUS queue) GMO.Options = MQGMO_SYNCPOINT
if (Reason == MQRC_NO_MSG_AVAILABLE)
  /* Proceed to normal processing */
  ...
else
  /* Group was terminated prematurely */
  Set GroupId, MsgSeqNumber in MQMD to values from Status message
  PMO.Options = MQPMO_SYNCPOINT
  MQPUT MD.MsgFlags = MQMF_MSG_IN_GROUP

  /* Now normal processing is resumed.
   Assume this is not the last message */
  PMO.Options = MQPMO_LOGICAL_ORDER | MQPMO_SYNCPOINT
  MQPUT MD.MsgFlags = MQMF_MSG_IN_GROUP
  MQPUT MD.MsgFlags = MQMF_MSG_IN_GROUP
  StatusInfo = GroupId,MsgSeqNumber from MQMD
  MQPUT (StatusInfo to STATUS queue) PMO.Options = MQPMO_SYNCPOINT
  MQCMIT
```

From the getting application, you may want to start processing the messages in a group before the whole group has arrived. This improves response times on the

messages within the group, and also means that storage is not required for the entire group.

For recovery reasons, each message must be retrieved within a unit of work. However, in order to realize the above benefits, several units of work must be used for each group of messages.

As with the corresponding putting application, this requires status information to be recorded somewhere atomically as each unit of work is committed. Again, the simplest place to record this information is on a STATUS queue. If a complete group has been successfully processed, the STATUS queue is empty.

**Note:** For intermediate units of work, you can avoid the MQGET calls from the STATUS queue by specifying that each MQPUT to the status queue is a segment of a message (that is, by setting the MQMF\_SEGMENT flag), instead of putting a complete new message for each unit of work. In the last unit of work, a final segment is put to the status queue specifying MQMF\_LAST\_SEGMENT, and then the status information is cleared with an MQGET specifying MQGMO\_COMPLETE\_MSG.

During restart processing, instead of using a single MQGET to get a possible status message, browse the status queue with MQGMO\_LOGICAL\_ORDER until you reach the last segment (that is, until no further segments are returned). In the first unit of work after restart, also specify the offset explicitly when putting the status segment.

In the following example, we consider only messages within a group. It is assumed that the application's buffer is always large enough to hold the entire message, whether or not the message has been segmented. MQGMO\_COMPLETE\_MSG is therefore specified on each MQGET. The same principles apply if segmentation is involved (in this case, the StatusInfo must include the *Offset*).

## MQGET retrieval sequence

For simplicity, we assume that a maximum of 4 messages should be retrieved within a single UOW:

```
msgs = 0    /* Counts messages retrieved within UOW */
/* Should be no status message at this point */

/* Retrieve remaining messages in the group */
do while ( GroupStatus == MQGS_MSG_IN_GROUP )

    /* Process up to 4 messages in the group */
    GMO.Options = MQGMO_SYNCPOINT | MQGMO_WAIT
                 | MQGMO_LOGICAL_ORDER
    do while ( (GroupStatus == MQGS_MSG_IN_GROUP) && (msgs < 4) )
        MQGET
        msgs = msgs + 1
        /* Process this message */
        ...
    /* end while

    /* Have retrieved last message or 4 messages */
    /* Update status message if not last in group */
    MQGET (from STATUS queue) GMO.Options = MQGMO_SYNCPOINT
    if ( GroupStatus == MQGS_MSG_IN_GROUP )
        StatusInfo = GroupId,MsgSeqNumber from MQMD
        MQPUT (StatusInfo to STATUS queue) PMO.Options = MQPMO_SYNCPOINT
    MQCMIT
    msgs = 0
/* end while

if ( msgs > 0 )
    /* Come here if there was only 1 message in the group */
    MQCMIT
```

If all of the units of work have been committed, then the entire group has been retrieved successfully, and the STATUS queue is empty. If not, then the group must be resumed at the point indicated by the status information. MQGMO\_LOGICAL\_ORDER cannot be used for the first retrieve, but can thereafter.

Restart processing looks like this:

```

MQGET (from STATUS queue) GMO.Options = MQGMO_SYNCPOINT
if (Reason == MQRC_NO_MSG_AVAILABLE)
    /* Proceed to normal processing */
    ...
else
    /* Group was terminated prematurely */
    /* The next message on the group must be retrieved by matching
       the sequence number and group id with those retrieved from the
       status information. */
    GMO.Options = MQGMO_COMPLETE_MSG | MQGMO_SYNCPOINT | MQGMO_WAIT
    MQGET GMO.MatchOptions = MQMO_MATCH_GROUP_ID | MQMO_MATCH_MSG_SEQ_NUMBER,
        MQMD.GroupId      = value from Status message,
        MQMD.MsgSeqNumber = value from Status message plus 1
    msgs = 1
    /* Process this message */
    ...

    /* Now normal processing is resumed */
    /* Retrieve remaining messages in the group */
    do while ( GroupStatus == MQGS_MSG_IN_GROUP )

        /* Process up to 4 messages in the group */
        GMO.Options = MQGMO_COMPLETE_MSG | MQGMO_SYNCPOINT | MQGMO_WAIT
                    | MQGMO_LOGICAL_ORDER
        do while ( (GroupStatus == MQGS_MSG_IN_GROUP) && (msgs < 4) )
            MQGET
            msgs = msgs + 1
            /* Process this message */
            ...

        /* Have retrieved last message or 4 messages */
        /* Update status message if not last in group */
        MQGET (from STATUS queue) GMO.Options = MQGMO_SYNCPOINT
        if ( GroupStatus == MQGS_MSG_IN_GROUP )
            StatusInfo = GroupId,MsgSeqNumber from MQMD
            MQPUT (StatusInfo to STATUS queue) PMO.Options = MQPMO_SYNCPOINT
        MQCMIT
        msgs = 0

```

---

## Getting a particular message

To get a particular message from a queue, use the *MsgId* and *CorrelId* fields of the MQMD structure. Note, however, that applications can explicitly set these fields, so the values you specify may not identify a unique message. Table 5 on page 138 shows which message is retrieved for the possible settings of these fields. These fields are ignored on input if you specify `MQGMO_MSG_UNDER_CURSOR` in the *GetMsgOpts* parameter of the MQGET call.

## Getting specific message

To retrieve ...	<i>MsgId</i>	<i>CorrelId</i>
First message in the queue	MQMI_NONE	MQCI_NONE
First message that matches <i>MsgId</i>	Nonzero	MQCI_NONE
First message that matches <i>CorrelId</i>	MQMI_NONE	Nonzero
First message that matches both <i>MsgId</i> and <i>CorrelId</i>	Nonzero	Nonzero

In each case, **first** means the first message that satisfies the selection criteria (unless MQGMO\_BROWSE\_NEXT is specified, when it means the **next** message in the sequence satisfying the selection criteria).

On return, the MQGET call sets the *MsgId* and *CorrelId* fields to the message and correlation identifiers (respectively) of the message returned (if any).

If you set the *Version* field of the MQMD structure to 2 or 3, you can use the *GroupId*, *MsgSeqNumber*, and *Offset* fields. Table 6 shows which message is retrieved for the possible settings of these fields.

To retrieve ...	Match options
First message in the queue	MQMO_NONE
First message that matches <i>MsgId</i>	MQMO_MATCH_MSG_ID
First message that matches <i>CorrelId</i>	MQMO_MATCH_CORREL_ID
First message that matches <i>GroupId</i>	MQMO_MATCH_GROUP_ID
First message that matches <i>MsgSeqNumber</i>	MQMO_MATCH_MSG_SEQ_NUMBER
First message that matches <i>MsgToken</i>	MQMO_MATCH_MSG_TOKEN
First message that matches <i>Offset</i>	MQMO_MATCH_OFFSET
<b>Notes:</b>	
<ol style="list-style-type: none"> <li>1. MQMO_XXX implies that the XXX field in the MQMD structure is set to the value to be matched.</li> <li>2. The MQMO flags can be used in combination. For example, MQMO_MATCH_GROUP_ID, MQMO_MATCH_MSG_SEQ_NUMBER, and MQMO_MATCH_OFFSET can be used together to give the segment identified by the <i>GroupId</i>, <i>MsgSeqNumber</i>, and <i>Offset</i> fields.</li> <li>3. If you specify MQGMO_LOGICAL_ORDER, the message you are trying to retrieve is affected because the option depends on state information controlled for the queue handle. For information about this, see “Logical and physical ordering” on page 129 and “MQGMO - Get-message options” in the <i>MQSeries Application Programming Reference</i> manual.</li> <li>4. MQMO_MATCH_MSG_TOKEN is used only on queues managed by the OS/390 workload manager.</li> <li>5. MQSeries for OS/390 does not support MQMO_MATCH_GROUP_ID, MQMO_MATCH_MSG_SEQ_NUMBER, or MQMO_MATCH_OFFSET.</li> </ol>	

**Notes:**

1. The MQGET call usually retrieves the first message from a queue. If you specify a particular message when you use the MQGET call, the queue manager has to search the queue until it finds that message. This can affect the performance of your application.
2. If you are using Version 2 or 3 of the MQMD structure, you can use the MQMO\_MATCH\_MSG\_ID and MQMO\_MATCH\_CORREL\_ID flags. This avoids having to reset the *MsgId* and *CorrelId* fields between MQGETs.

On MQSeries for OS/390, the queue attribute, *IndexType*, can be used to increase the speed of MQGET operations on the queue. For more information, see “Type of index.”

---

## Type of index

*This is supported on MQSeries for OS/390 only.*

The queue attribute, *IndexType*, specifies the type of index that the queue manager maintains in order to increase the speed of MQGET operations on the queue.

You have four options:

Value	Description
<b>NONE</b>	No index is maintained. Use this when messages are retrieved sequentially (see “Priority” on page 128).
<b>MSGID</b>	An index of message identifiers is maintained. Use this when messages are retrieved using the <i>MsgId</i> field as a selection criterion on the MQGET call (see “Getting a particular message” on page 137).
<b>MSGTOKEN</b>	An index of message tokens is maintained. Use this when messages are retrieved using the <i>MsgToken</i> field as a selection criterion on the MQGET call (see “MQSeries Workflow” on page 249).
<b>CORRELID</b>	An index of correlation identifiers is maintained. Use this when messages are retrieved using the <i>CorrelId</i> field as a selection criterion on the MQGET call (see “Getting a particular message” on page 137).

**Notes:**

1. If you are indexing using the MSGID option or CORRELID option, set the relative *MsgId* or *CorrelId* parameters in the MQMD. It is **not** beneficial to set both.
2. Indexes are ignored when browsing messages on a queue (see “Browsing messages on a queue” on page 154 for more information).
3. Avoid queues (indexed by *MsgId* or *CorrelId*) containing thousands of messages because this affects restart time. (This does not apply to nonpersistent messages as they are deleted at restart.)
4. MSGTOKEN is used to define queues managed by the OS/390 workload manager.

For a full description of the *IndexType* attribute, see “Attributes for local queues and model queues” in the *MQSeries Application Programming Reference* manual. For

## Handling large messages

conditions needed to change the *IndexType* attribute, see “ALTER QLOCAL” in the *MQSeries Command Reference* manual.

---

## Handling large messages

*This is supported on MQSeries Version 5 products and MQSeries for AS/400 only.*

Messages can be too large for the application, queue, or queue manager. MQSeries provides three ways of dealing with large messages:

1. Increase the queue and queue manager *MaxMsgLength* attributes (not AS/400).
2. Use segmented messages. (Messages can be segmented by either the application or the queue manager.)
3. Use reference messages.

Each of these approaches is described in the remainder of this section.

### Increasing the maximum message length

The *MaxMsgLength* queue manager attribute defines the maximum length of a message that can be handled by a queue manager. Similarly, the *MaxMsgLength* queue attribute is the maximum length of a message that can be handled by a queue. The **default** maximum message length supported depends on the environment you are working in, as shown under “Message properties and protocols” on page 551.

If you are handling large messages, you can alter these attributes independently (not AS/400). The attribute value can be set between 32768 bytes and 100 MB.

After changing one or both of the *MaxMsgLength* attributes, restart your applications and channels to ensure that the changes take effect. When these changes are made, the message length must be less than or equal to both the queue and the queue manager *MaxMsgLength* attributes. However, existing messages may be longer than either attribute.

If the message is too big for the queue, MQRC\_MSG\_TOO\_BIG\_FOR\_Q is returned. Similarly, if the message is too big for the queue manager, MQRC\_MSG\_TOO\_BIG\_FOR\_Q\_MGR is returned. However, these return codes can be avoided by segmenting your messages (see “Message segmentation” on page 141 for full details of this).

This method of handling large messages is easy and convenient. However, consider the following factors before using it:

- Uniformity among queue managers is reduced. The maximum size of message data is determined by the *MaxMsgLength* for each queue (including transmission queues) on which the message will be put. This value is often defaulted to the queue manager’s *MaxMsgLength*, especially for transmission queues. This makes it difficult to predict whether a message is too large when it is to travel to a remote queue manager.
- Usage of system resources is increased. For example, applications need larger buffers, and on some platforms, there may be increased usage of shared storage. Note that queue storage should be affected only if actually required for larger messages.

- Channel batching is affected. A large message still counts as just one message towards the batch count but needs longer to transmit, thereby increasing response times for other messages.

## Message segmentation

Increasing the maximum message length as discussed on page 140 has some negative implications. Also, it could still result in the message being too large for the queue or queue manager. In these cases, a message can be segmented. For information about segments, see “Message groups” on page 33.

The next sections look at common uses for segmenting messages. For putting and destructively getting, it is assumed that the MQPUT or MQGET calls *always* operate within a unit of work. It is strongly recommended that this technique is always used, to reduce the possibility of incomplete groups being present in the network. Single-phase commit by the queue manager is assumed, but of course other coordination techniques are equally valid.

Also, in the getting applications, it is assumed that if multiple servers are processing the same queue, each server executes similar code, so that one server never fails to find a message or segment that it expects to be there (because it had specified MQGMO\_ALL\_MSGS\_AVAILABLE or MQGMO\_ALL\_SEGMENTS\_AVAILABLE earlier).

### Segmentation and reassembly by queue manager

This is the simplest scenario, in which one application puts a message to be retrieved by another. The message may be large: not too large for either the putting or the getting application to handle in a single buffer, but possibly too large for the queue manager or a queue on which the message is to be put.

The only changes necessary for these applications are for the putting application to authorize the queue manager to perform segmentation if necessary,

```
PMO.Options = (existing options)
MQPUT MD.MsgFlags = MQMF_SEGMENTATION_ALLOWED
```

and for the getting application to ask the queue manager to reassemble the message if it has been segmented:

```
GMO.Options = MQGMO_COMPLETE_MSG | (existing options)
MQGET
```

The application buffer must be large enough to contain the reassembled message (unless the MQGMO\_ACCEPT\_TRUNCATED\_MSG option is included).

If data conversion is necessary, it may have to be done by the getting application specifying MQGMO\_CONVERT. This should be straightforward because the data conversion exit is presented with the complete message. Attempting to do data conversion in a sender channel will not be successful if the message is segmented, and the format of the data is such that the data-conversion exit cannot carry out the conversion on incomplete data.

### Application segmentation

This example shows how to segment a single large message

Application segmentation is used for two main reasons:

1. Queue-manager segmentation alone is not adequate because the message is too large to be handled in a single buffer by the applications.
2. Data conversion must be performed by sender channels, and the format is such that the putting application needs to stipulate where the segment boundaries are to be in order for conversion of an individual segment to be possible.

However, if data conversion is not an issue, or if the getting application always uses `MQGMO_COMPLETE_MSG`, queue-manager segmentation can also be allowed by specifying `MQMF_SEGMENTATION_ALLOWED`. In our example, the application segments the message into four segments:

```
PMO.Options = MQPMO_LOGICAL_ORDER | MQPMO_SYNCPOINT

MQPUT MD.MsgFlags = MQMF_SEGMENT
MQPUT MD.MsgFlags = MQMF_SEGMENT
MQPUT MD.MsgFlags = MQMF_SEGMENT
MQPUT MD.MsgFlags = MQMF_LAST_SEGMENT

MQCMIT
```

If you do not use `MQPMO_LOGICAL_ORDER`, the application must set the *Offset* and the length of each segment. In this case, logical state is not maintained automatically.

The getting application cannot, or chooses not to, guarantee to have a buffer that will hold any reassembled message. It must therefore be prepared to process segments individually.

For messages that are segmented, this application does not want to start processing one segment until all of the segments that constitute the logical message are present. `MQGMO_ALL_SEGMENTS_AVAILABLE` is therefore specified for the first segment. If you specify `MQGMO_LOGICAL_ORDER` and there is a current logical message, `MQGMO_ALL_SEGMENTS_AVAILABLE` is ignored.

Once the first segment of a logical message has been retrieved, `MQGMO_LOGICAL_ORDER` is used to ensure that the remaining segments of the logical message are retrieved in order.

No consideration is given to messages within different groups. If such messages do occur, they are processed in the order in which the first segment of each message appears on the queue.

```
GMO.Options = MQGMO_SYNCPOINT | MQGMO_LOGICAL_ORDER
              | MQGMO_ALL_SEGMENTS_AVAILABLE | MQGMO_WAIT
do while ( SegmentStatus == MQSS_SEGMENT )
  MQGET
  /* Process each remaining segment of the logical message */
  ...

MQCMIT
```

## Application segmentation of logical messages

The messages must be maintained in logical order in a group, and some or all of them may be so large that they require application segmentation.

In our example, a group of four logical messages is to be put. All but the third message are large, and require segmentation which is performed by the putting application:

```
PMO.Options = MQPMO_LOGICAL_ORDER | MQPMO_SYNCPOINT

MQPUT MD.MsgFlags = MQMF_MSG_IN_GROUP      | MQMF_SEGMENT
MQPUT MD.MsgFlags = MQMF_MSG_IN_GROUP      | MQMF_SEGMENT
MQPUT MD.MsgFlags = MQMF_MSG_IN_GROUP      | MQMF_LAST_SEGMENT

MQPUT MD.MsgFlags = MQMF_MSG_IN_GROUP      | MQMF_SEGMENT
MQPUT MD.MsgFlags = MQMF_MSG_IN_GROUP      | MQMF_LAST_SEGMENT

MQPUT MD.MsgFlags = MQMF_MSG_IN_GROUP

MQPUT MD.MsgFlags = MQMF_LAST_MSG_IN_GROUP | MQMF_SEGMENT
MQPUT MD.MsgFlags = MQMF_LAST_MSG_IN_GROUP | MQMF_SEGMENT
MQPUT MD.MsgFlags = MQMF_LAST_MSG_IN_GROUP | MQMF_LAST_SEGMENT

MQCMIT
```

In the getting application, MQGMO\_ALL\_MSGS\_AVAILABLE is specified on the first MQGET. This means that no messages or segments of a group are retrieved until the entire group is available. When the first physical message of a group has been retrieved, MQGMO\_LOGICAL\_ORDER is used to ensure that the segments and messages of the group are retrieved in order:

```
GMO.Options = MQGMO_SYNCPOINT | MQGMO_LOGICAL_ORDER
              | MQGMO_ALL_MESSAGES_AVAILABLE | MQGMO_WAIT

do while ( (GroupStatus  != MQGS_LAST_MSG_IN_GROUP) ||
           (SegmentStatus != MQGS_LAST_SEGMENT) )
  MQGET
  /* Process a segment or complete logical message. Use the GroupStatus
     and SegmentStatus information to see what has been returned */
  ...

MQCMIT
```

**Note:** If you specify MQGMO\_LOGICAL\_ORDER and there is a current group, MQGMO\_ALL\_MESSAGES\_AVAILABLE is ignored.

## Putting and getting a segmented message that spans units of work

You can put and get a segmented message that spans a unit of work in a similar way to “Putting and getting a group that spans units of work” on page 133.

### Reference messages

This method allows a large object to be transferred from one node to another without the need for the object to be stored on MQSeries queues at either the source or the destination nodes. This is of particular benefit where the data already exists in another form, for example, for mail applications.

To do this, you need to specify a message exit at both ends of a channel. For information on how to do this, see Chapter 35, “Channel-exit programs” in the *MQSeries Intercommunication* book.

MQSeries defines the format of a reference message header (MQRMH). See “MQRMH - Message reference header” in the *MQSeries Application Programming Reference* manual for a description of this. This is recognized by means of a defined format name and may or may not be followed by actual data.

To initiate transfer of a large object, an application can put a message consisting of a reference message header with no data following it. As this message leaves the node, the message exit retrieves the object in an appropriate way and appends it to the reference message. It then returns the message (now larger than before) to the sending Message Channel Agent for transmission to the receiving MCA.

Another message exit is configured at the receiving MCA. When this message exit sees one of these messages, it creates the object using the object data that was appended and passes on the reference message **without** it. The reference message can now be received by an application and this application knows that the object (or at least the portion of it represented by this reference message) has been created at this node.

The maximum amount of object data that a sending message exit can append to the reference message is limited by the negotiated maximum message length for the channel. The exit can only return a single message to the MCA for each message that it is passed, so the putting application can put several messages to cause one object to be transferred. Each message must identify the **logical** length and offset of the object that is to be appended to it. However, in cases where it is not possible to know the total size of the object or the maximum size allowed by the channel, the sending message exit can be designed so that the putting application just puts a single message, and the exit itself puts the next message on the transmission queue when it has appended as much data as it can to the message it has been passed.

Before using this method of dealing with large messages, consider the following:

- The MCA and the message exit run under an MQSeries user ID. The message exit (and therefore, the user ID) needs to access the object to either retrieve it at the sending end or create it at the receiving end; this may only be feasible in cases where the object is universally accessible. This raises a security issue.
- If the reference message with bulk data appended to it must travel through several queue managers before reaching its destination, the bulk data **is** present on MQSeries queues at the intervening nodes. However, no special support or exits need to be provided in these cases.
- Designing your message exit is made difficult if rerouting or dead-letter queuing is allowed. In these cases, the portions of the object may arrive out of order.

- When a reference message arrives at its destination, the receiving message exit creates the object. However, this is not synchronized with the MCA's unit of work, so if the batch is backed out, another reference message containing this same portion of the object will arrive in a later batch, and the message exit may attempt to recreate the same portion of the object. If the object is, for example, a series of database updates, this might be unacceptable. If so, the message exit must keep a log of which updates have been applied; this may require the use of an MQSeries queue.
- Depending on the characteristics of the object type, the message exits and applications may need to cooperate in maintaining use counts, so that the object can be deleted when it is no longer needed. An instance identifier may also be required; a field is provided for this in the reference message header (see "MQRMH - Message reference header" in the *MQSeries Application Programming Reference* manual).
- If a reference message is put as a distribution list, the object must be retrievable for each resulting distribution list or individual destination at that node. You may need to maintain use counts. Also consider the possibility that a given node may be the final node for some of the destinations in the list, but an intermediate node for others.
- Bulk data is not normally converted. This is because conversion takes place **before** the message exit is invoked. For this reason, conversion should not be requested on the originating sender channel. If the reference message passes through an intermediate node, the bulk data is converted when sent from the intermediate node, if requested.
- Reference messages cannot be segmented.

### Using the MQRMH and MQMD structures

See "MQRMH - Message reference header" and "MQMD - Message descriptor" in the *MQSeries Application Programming Reference* manual for a description of the fields in the reference message header and the message descriptor.

In the MQMD structure, the *Format* field must be set to MQFMT\_REF\_MSG\_HEADER. The MQHREF format, when requested on MQGET, is converted automatically by MQSeries along with any bulk data that follows.

Here is an example of the use of the *DataLogicalOffset* and *DataLogicalLength* fields of the MQRMH:

A putting application might put a reference message with:

- No physical data
- *DataLogicalLength* = 0 (this message represents the entire object)
- *DataLogicalOffset* = 0.

Assuming that the object is 70,000 bytes long, the sending message exit sends the first 40,000 bytes along the channel in a reference message containing:

- 40,000 bytes of physical data following the MQRMH
- *DataLogicalLength* = 40,000
- *DataLogicalOffset* = 0 (from the start of the object).

## Waiting for messages

It then places another message on the transmission queue containing:

- No physical data
- *DataLogicalLength* = 0 (to the end of the object). You could specify a value of 30,000 here.
- *DataLogicalOffset* = 40,000 (starting from this point).

When this message exit is seen by the sending message exit, the remaining 30,000 bytes of data is appended, and the fields are set to:

- 30,000 bytes of physical data following the MQRMH
- *DataLogicalLength* = 30,000
- *DataLogicalOffset* = 40,000 (starting from this point).

The MQRMHF\_LAST flag is also set.

For a description of the sample programs provided for the use of reference messages, see Chapter 31, "Sample programs (all platforms except OS/390)" on page 327.

---

## Waiting for messages

If you want a program to wait until a message arrives on a queue, specify the MQGMO\_WAIT option in the *Options* field of the MQGMO structure. Use the *WaitInterval* field of the MQGMO structure to specify the maximum time (in milliseconds) that you want an MQGET call to wait for a message to arrive on a queue.

If the message does not arrive within this time, the MQGET call completes with the MQRC\_NO\_MSG\_AVAILABLE reason code.

You can specify an unlimited wait interval using the constant MQWI\_UNLIMITED in the *WaitInterval* field. However, events outside your control could cause your program to wait for a long time, so use this constant with caution. IMS applications should not specify an unlimited wait interval because this would prevent the IMS system terminating. (When IMS terminates, it requires all dependent regions to end.) Instead, IMS applications should specify a finite wait interval; then, if the call completes without retrieving a message after that interval, issue another MQGET call with the wait option.

In the Windows 3.1 environment, while your application is waiting for an MQGET to return, MQSeries will still recover Windows messages to allow the application and the rest of Windows to function normally. You must ensure that your code that processes Windows program messages does not assume that the MQGET call returns data to the application immediately. If it attempts to access data that is not yet available, errors can easily occur. Also, if you attempt to make other MQI calls while the MQGET call is waiting, MQRC\_CALL\_IN\_PROGRESS is returned to show that another call is busy.

**Note:** If more than one program is waiting on the same shared queue to **remove** a message, only one program is activated by a message arriving. However, if more than one program is waiting to browse a message, all the programs can be activated. For more information, see the description of the *Options* field of the MQGMO structure in "MQGMO - Get-message options" in the *MQSeries Application Programming Reference* manual.

If the state of the queue or the queue manager changes before the wait interval expires, the following actions occur:

- If the queue manager enters the quiescing state, and you used the `MQGMO_FAIL_IF QUIESCING` option, the wait is canceled and the `MQGET` call completes with the `MQRC_Q_MGR QUIESCING` reason code. Without this option, the call remains waiting.
- On OS/390, if the connection (for a CICS or IMS application) enters the quiescing state, and you used the `MQGMO_FAIL_IF QUIESCING` option, the wait is canceled and the `MQGET` call completes with the `MQRC_CONN QUIESCING` reason code. Without this option, the call remains waiting.
- If the queue manager is forced to stop, or is canceled, the `MQGET` call completes with either the `MQRC_Q_MGR STOPPING` or the `MQRC_CONNECTION_BROKEN` reason code.
- If the attributes of the queue (or a queue to which the queue name resolves) are changed so that get requests are now inhibited, the wait is canceled and the `MQGET` call completes with the `MQRC_GET_INHIBITED` reason code.
- If the attributes of the queue (or a queue to which the queue name resolves) are changed in such a way that the `FORCE` option is required, the wait is canceled and the `MQGET` call completes with the `MQRC_OBJECT_CHANGED` reason code.

If you want your application to wait on more than one queue, use the signal facility of MQSeries for OS/390 (see “Signaling”). For more information about the circumstances in which these actions occur, see “MQGMO - Get-message options” in the *MQSeries Application Programming Reference* manual.

---

## Signaling

*Signaling is supported only on MQSeries for OS/390, MQSeries for Tandem NSK, and MQSeries for Windows Version 2.1.*

Signaling is an option on the `MQGET` call to allow the operating system to notify (or *signal*) a program when an expected message arrives on a queue. This is similar to the “get with wait” function described on page 146 because it allows your program to continue with other work while waiting for the signal. However, if you use signaling, you can free the application thread and rely on the operating system to notify the program when a message arrives.

### To set a signal

To set a signal, do the following in the `MQGMO` structure that you use on your `MQGET` call:

1. Set the `MQGMO_SET_SIGNAL` option in the *Options* field.
2. Set the maximum life of the signal in the *WaitInterval* field. This sets the length of time (in milliseconds) for which you want MQSeries to monitor the queue. Use the `MQWI_UNLIMITED` value to specify an unlimited life.

**Note:** IMS applications should not specify an unlimited wait interval because this would prevent the IMS system from terminating. (When IMS terminates, it

requires all dependent regions to end.) Instead, IMS applications should examine the state of the ECB at regular intervals (see step 3).

A program can have signals set on several queue handles at the same time:

3. On MQSeries for Tandem NSK, specify an application tag in the *Signal1* field. This can be used by an application to associate the IPC notification message with a particular MQGET call (see “When the message arrives”).

On MQSeries for Windows Version 2.1, specify the handle of the window to which you want the signal sent in the *Signal1* field.

On MQSeries for OS/390, specify the address of the *Event Control Block* (ECB) in the *Signal1* field. This notifies you of the result of your signal. The ECB storage must remain available until the queue is closed.

4. On MQSeries for Windows Version 2.1, specify an identifier for the signal message in the *Signal2* field. This specifies the Windows message that you receive when a suitable message arrives. Use a RegisterWindow message to find a suitable identifier.

**Note:** You cannot use the MQGMO\_SET\_SIGNAL option in conjunction with the MQGMO\_WAIT option.

## When the message arrives

When a suitable message arrives, the following occurs:

- On MQSeries for Tandem NSK An Inter-Process Communication (IPC) message is sent to the \$RECEIVE queue of the process that made the MQGET call.
- On MQSeries for Windows Version 2.1, MQSeries sends a Windows message (identified in step 4) to the window you specified in your *Signal1* field. It also puts a completion code in the WPARAM field of the Windows message.
- On MQSeries for OS/390, a completion code is returned to the ECB.

The completion code describes one of the following:

- The message you set the signal for has arrived on the queue. The message is not reserved for the program that requested a signal, so the program must issue an MQGET call again to get the message.  
**Note:** Another application could get the message in the time between you receiving the signal and you issuing another MQGET call.
- The wait interval you set has expired and the message you set the signal for did not arrive on the queue. MQSeries has canceled the signal.
- The signal has been canceled. This happens, for example, if the queue manager stops or the attribute of the queue is changed so that MQGET calls are no longer allowed.

When a suitable message is already on the queue, the MQGET call completes in the same way as an MQGET call without signaling. Also, if an error is detected immediately, the call completes and the return codes are set.

When the call is accepted and no message is immediately available, control is returned to the program so that it can continue with other work. None of the output fields in the message descriptor are set, but the *CompCode* and *Reason* parameters

are set to MQCC\_WARNING and MQRC\_SIGNAL\_REQUEST\_ACCEPTED, respectively.

For information on what MQSeries can return to your application when it makes an MQGET call using signaling, see “MQGMO - Get-message options” in the *MQSeries Application Programming Reference* manual.

On MQSeries for OS/390, if the program has no other work to do while it is waiting for the ECB to be posted, it can wait for the ECB using:

- For a CICS Transaction Server for OS/390 program, the EXEC CICS WAIT EXTERNAL command
- For batch and IMS programs, the OS/390 WAIT macro

If the state of the queue or the queue manager changes while the signal is set (that is, the ECB has not yet been posted), the following actions occur:

- If the queue manager enters the quiescing state, and you used the MQGMO\_FAIL\_IF\_QUIESCING option, the signal is canceled. The ECB is posted with the MQEC\_Q\_MGR\_QUIESCING completion code. Without this option, the signal remains set.
- If the queue manager is forced to stop, or is canceled, the signal is canceled. The signal is delivered with the MQEC\_WAIT\_CANCELED completion code.
- If the attributes of the queue (or a queue to which the queue name resolves) are changed so that get requests are now inhibited, the signal is canceled. The signal is delivered with the MQEC\_WAIT\_CANCELED completion code.

### Notes:

1. If more than one program has set a signal on the same shared queue to remove a message, only one program is activated by a message arriving. However, if more than one program is waiting to browse a message, all the programs can be activated. The rules that the queue manager follows when deciding which applications to activate are the same as those for waiting applications: for more information, see the description of the *Options* field of the MQGMO structure in the *MQSeries Application Programming Reference* manual.
2. If there is more than one MQGET call waiting for the same message, with a mixture of wait and signal options, each waiting call is considered equally. For more information, see the description of the *Options* field of the MQGMO structure in “MQGMO - Get-message options” in the *MQSeries Application Programming Reference* manual.
3. Under some conditions, it is possible both for an MQGET call to retrieve a message and for a signal (resulting from the arrival of the same message) to be delivered. This means that when your program issues another MQGET call (because the signal was delivered), there could be no message available. You should design your program to test for this situation.

For information about how to set a signal, see the description of the MQGMO\_SET\_SIGNAL option and the *Signal1* field in “MQGMO - Get-message options” in the *MQSeries Application Programming Reference* manual.

---

### Skipping backout

*Skipping backout is supported only on MQSeries for OS/390.*

As part of a unit of work, an application program can issue one or more MQGET calls to get messages from a queue. If the application program detects an error, it can back out the unit of work. This restores all the resources updated during that unit of work to the state they were in before the unit of work started, and reinstates the messages retrieved by the MQGET calls.

Once reinstated, these messages are available to subsequent MQGET calls issued by the application program. In many cases, this does not cause a problem for the application program. However, in cases where the error leading to the backout cannot be circumvented, having the message reinstated on the queue can cause the application program to enter an 'MQGET-error-backout' loop.

To avoid this problem, specify the MQGMO\_MARK\_SKIP\_BACKOUT option on the MQGET call. This marks the MQGET request as not being involved in application-initiated backout; that is, it should not be backed out. Use of this option means that when a backout occurs, updates to other resources are backed out as required, but the marked message is treated as if it had been retrieved under a new unit of work. The application program can then perform exception handling, such as informing the originator that the message has been discarded, and then commit the new unit of work, causing the message to be removed from the queue. If the new unit of work is backed out (for any reason) the message is reinstated on the queue.

Within a unit of work, there can be only one MQGET request marked as skipping backout; however, there can be several other messages that are not marked as skipping backout. Once a message has been marked as skipping backout, any further MQGET calls within the unit of work that specify MQGMO\_MARK\_SKIP\_BACKOUT will fail with reason code MQRC\_SECOND\_MARK\_NOT\_ALLOWED.

#### Notes:

1. The marked message only skips backout if the unit of work containing it is terminated by an application request to back it out. If the unit of work is backed out for any other reason, the message is backed out on to the queue in the same way that it would be if it was not marked to skip backout.
2. Skip backout is not supported within DB2 stored procedures participating in units of work controlled by RRS. For example, an MQGET call with the MQGMO\_MARK\_SKIP\_BACKOUT option will fail with the reason code MQRC\_OPTION\_ENVIRONMENT\_ERROR.




Figure 12. Skipping backout using MQGMO\_MARK\_SKIP\_BACKOUT

Figure 12 illustrates a typical sequence of steps that an application program might contain when an MQGET request is required to skip backout:

- Step 1 Initial processing occurs within the transaction, including an MQOPEN call to open the queue (specifying one of the MQOO\_INPUT\_\* options in order to get messages from the queue in Step 2).
- Step 2 MQGET is called, with MQGMO\_SYNCPOINT and MQGMO\_MARK\_SKIP\_BACKOUT. MQGMO\_SYNCPOINT is required because MQGET must be within a unit of work for

## MQGET data conversion

MQGMO\_MARK\_SKIP\_BACKOUT to be effective. In Figure 12 this unit of work is referred to as UOW1.

- Step 3 Other resource updates are made as part of UOW1. These may include further MQGET calls (issued without MQGMO\_MARK\_SKIP\_BACKOUT).
- Step 4 All updates from Steps 2 and 3 complete as required. The application program commits the updates and UOW1 ends. The message retrieved in Step 2 is removed from the queue.
- Step 5 Some of the updates from Steps 2 and 3 do not complete as required. The application program requests that the updates made during these steps are backed out.
- Step 6 The updates made in Step 3 are backed out.
- Step 7 The MQGET request made in Step 2 skips backout and becomes part of a new unit of work, UOW2.
- Step 8 UOW2 performs exception handling in response to UOW1 being backed out. (For example, an MQPUT call to another queue, indicating that a problem occurred that caused UOW1 to be backed out.)
- Step 9 Step 8 completes as required, the application program commits the activity, and UOW2 ends. As the MQGET request is part of UOW2 (see Step 7), this commit causes the message to be removed from the queue.
- Step 10 Step 8 does not complete as required and the application program backs out UOW2. Because the get message request is part of UOW2 (see Step 7), it too is backed out and reinstated on the queue. It is now available to further MQGET calls issued by this or another application program (in the same way as any other message on the queue).

---

## Application data conversion

When necessary, MCAs convert the message descriptor data into the required character set and encoding. Either end of the link (that is, the local MCA or the remote MCA) may do the conversion.

When an application puts messages on a queue, the local queue manager adds control information to the message descriptors to facilitate the control of the messages when they are processed by queue managers and MCAs. Depending on the environment, the message header data fields will be created in the character set and encoding of the local system.

When you move messages between systems, it is necessary, on some occasions, to convert the application data into the character set and encoding required by the receiving system. This can be done either from within application programs on the receiving system or by the MCAs on the sending system. If data conversion is supported on the receiving system, it is recommended to use application programs to convert the application data, rather than depending on the conversion having already occurred at the sending system.

Application data is converted within an application program when the MQGMO\_CONVERT option is specified in the *Options* field of the MQGMO structure passed to an MQGET call, and **all** of the following are true:

- The *CodedCharSetId* or *Encoding* fields set in the MQMD structure associated with the message on the queue differ from the *CodedCharSetId* or *Encoding* fields set in the MQMD structure specified on the MQGET call.
- The *Format* field in the MQMD structure associated with the message is not MQFMT\_NONE.
- The *BufferLength* specified on the MQGET call is not zero.
- The message data length is not zero.
- The queue manager supports conversion between the *CodedCharSetId* and *Encoding* fields specified in the MQMD structures associated with the message and the MQGET call. See “MQMD - Message descriptor” in the *MQSeries Application Programming Reference* manual for details of the coded character set identifiers and machine encodings supported.
- The queue manager supports conversion of the message format. If the *Format* field of the MQMD structure associated with the message is one of the built-in formats, the queue manager is able to convert the message. If the *Format* is not one of the built-in formats, you need to write a data-conversion exit to convert the message.

If the sending MCA is to convert the data, the CONVERT(YES) keyword must be specified on the definition of each sender or server channel for which conversion is required. If the data conversion fails, the message is sent to the DLQ at the sending queue manager and the *Feedback* field of the MQDLH structure indicates the reason. If the message cannot be put on the DLQ, the channel will close and the unconverted message will remain on the transmission queue. Data conversion within applications rather than at sending MCAs avoids this situation.

As a general rule, data in the message that is described as “character” data by the built-in format or data-conversion exit is converted from the coded character set used by the message to that requested, and “numeric” fields are converted to the encoding requested.

For further details of the conversion processing conventions used when converting the built-in formats, and for information about writing your own data-conversion exits, see Chapter 11, “Writing data-conversion exits” on page 161. See also Appendix F, “Code page conversion tables” in the *MQSeries Application Programming Reference* manual for information about the language support tables and about the supported machine encodings.

## Conversion of EBCDIC newline characters

If you need to ensure that the data you send from an EBCDIC platform to an ASCII one is identical to the data you receive back again, you must control the conversion of EBCDIC newline characters. This can be done using a platform-dependent switch that forces MQSeries to use the unmodified conversion tables but you must be aware of the inconsistent behavior that may result.

The problem arises because the EBCDIC newline character is not converted consistently across platforms or conversion tables. As a result, if the data is displayed on an ASCII platform, the formatting may be incorrect. This would make

## Browsing messages

it difficult, for example, to administer an AS/400 remotely from an ASCII platform using RUNMQSC.

See “The AllQueueManagers stanza” in the *MQSeries System Administration* book for further information about converting EBCDIC-format data to ASCII format.

---

## Browsing messages on a queue

To use the MQGET call to browse the messages on a queue:

1. Call MQOPEN to open the queue for browsing, specifying the MQOO\_BROWSE option.
2. To browse the first message on the queue, call MQGET with the MQGMO\_BROWSE\_FIRST option. To find the message you want, you can call MQGET repeatedly with the MQGMO\_BROWSE\_NEXT option to step through many messages.

You **must** set the *MsgId* and *CorrelId* fields of the MQMD structure to null after each MQGET call in order to see all messages.

3. Call MQCLOSE to close the queue.

## The browse cursor

When you open (MQOPEN) a queue for browsing, the call establishes a browse cursor for use with MQGET calls that use one of the browse options. You can think of the browse cursor as a logical pointer that is positioned before the first message on the queue.

You can have more than one browse cursor active (from a single program) by issuing several MQOPEN requests for the same queue.

When you call MQGET for browsing, use one of the following options in your MQGMO structure:

MQGMO_BROWSE_FIRST	Gets a copy of the first message that satisfies the conditions specified in your MQMD structure.
MQGMO_BROWSE_NEXT	Gets a copy of the next message that satisfies the conditions specified in your MQMD structure.

In both cases, the message remains on the queue.

When you open a queue, the browse cursor is positioned logically just before the first message on the queue. This means that if you make your MQGET call immediately after your MQOPEN call, you can use the MQGMO\_BROWSE\_NEXT option to browse the first message; you do not have to use the MQGMO\_BROWSE\_FIRST option.

The order in which messages are copied from the queue is determined by the *MsgDeliverySequence* attribute of the queue. (For more information, see “The order in which messages are retrieved from a queue” on page 128.)

### Queues in FIFO (first in, first out) sequence

The first message in a queue in this sequence is the message that has been on the queue the longest.

Use MQGMO\_BROWSE\_NEXT to read the messages sequentially in the queue. You will see any messages put to the queue while you are browsing, as a queue in this sequence will have messages placed at the end. When the cursor has recognized that it has reached the end of the queue, the browse cursor will stay where it is and return with MQRC\_NO\_MSG\_AVAILABLE. You may then either leave it there waiting for further messages or reset it to the beginning of the queue with a MQGMO\_BROWSE\_FIRST call.

### Queues in priority sequence

The first message in a queue in this sequence is the message that has been on the queue the longest and has the highest priority at the time the MQOPEN call is issued.

Use MQGMO\_BROWSE\_NEXT to read the messages in the queue.

The browse cursor will point to the next message, working from the priority of the first message to finish with the message at the lowest priority. It will browse any messages put to the queue during this time as long as they are of equal or lower priority to the message identified by the current browse cursor.

Any messages put to the queue of higher priority can only be browsed by:

- Opening the queue for browse again, at which point a new browse cursor is established
- Using the MQGMO\_BROWSE\_FIRST option

### Uncommitted messages

An uncommitted message is never visible to a browse, the browse cursor skips past it. Messages within a unit-of-work cannot be browsed until the unit-of-work is committed.

### Change to queue sequence

If the message delivery sequence is changed from priority to FIFO while there are messages on the queue, the order of the messages that are already queued is not changed. Messages added to the queue subsequently take the default priority of the queue.

## Browsing messages when message length unknown

To browse a message when you do not know the size of the message, and you do not wish to use the *MsgId*, *CorrelId*, or *GroupId* fields to locate the message, you can use the MQGMO\_BROWSE\_MSG\_UNDER\_CURSOR option (not supported on OS/390):

1. Issue an MQGET with:
  - Either the MQGMO\_BROWSE\_FIRST or MQGMO\_BROWSE\_NEXT option
  - The MQGMO\_ACCEPT\_TRUNCATED\_MSG option
  - Buffer length zero

## Browsing messages in logical order

**Note:** If another program is likely to get the same message, consider using the MQGMO\_LOCK option as well. MQRC\_TRUNCATED\_MSG\_ACCEPTED should be returned.

2. Use the returned *DataLength* to allocate the storage needed.
3. Issue an MQGET with the MQGMO\_BROWSE\_MSG\_UNDER\_CURSOR.

The message pointed to is the last one that was retrieved; the browse cursor will not have moved. You can choose either to lock the message using the MQGMO\_LOCK option, or to unlock a locked message using MQGMO\_UNLOCK option.

The call fails if no MQGET with either the MQGMO\_BROWSE\_FIRST or MQGMO\_BROWSE\_NEXT options has been issued successfully since the queue was opened.

### Restriction

MQGMO\_LOCK and MQGMO\_UNLOCK are not available on MQSeries for Tandem NSK and MQSeries for OS/390.

## Removing a message you have browsed

You can remove from the queue a message you have already browsed provided you have opened the queue for removing messages as well as for browsing. (You must specify one of the MQOO\_INPUT\_\* options, as well as the MQOO\_BROWSE option, on your MQOPEN call.)

To remove the message, call MQGET again, but in the *Options* field of the MQGMO structure, specify MQGMO\_MSG\_UNDER\_CURSOR. In this case, the MQGET call ignores the *MsgId*, *CorrelId*, and *GroupId* fields of the MQMD structure.

In the time between your browsing and removal steps, another program may have removed messages from the queue, including the message under your browse cursor. In this case, your MQGET call returns a reason code to say that the message is not available.

---

## Browsing messages in logical order

*Browsing messages in logical order is supported on MQSeries Version 5 products and MQSeries for AS/400 only.*

“Logical and physical ordering” on page 129 discusses the difference between the logical and physical order of messages on a queue. This distinction is particularly important when browsing a queue, because, in general, messages are not being deleted and browse operations do not necessarily start at the beginning of the queue. If an application browses through the various messages of one group (using logical order), it is important that logical order should be followed to reach the start of the next group, since the last message of one group may occur physically **after** the first message of the next group. The MQGMO\_LOGICAL\_ORDER option ensures that logical order is followed when scanning a queue.

MQGMO\_ALL\_MSGS\_AVAILABLE (or MQGMO\_ALL\_SEGMENTS\_AVAILABLE) needs to be used with care for browse operations. Consider the case of logical messages with MQGMO\_ALL\_MSGS\_AVAILABLE. The effect of this is that a logical message is available only if all of the remaining messages in the group are also present. If they are not, the message is passed over. This can mean that when the missing messages arrive subsequently, they will not be noticed by a browse-next operation.

For example, if the following logical messages are present,

```
Logical message 1 (not last) of group 123
Logical message 1 (not last) of group 456
Logical message 2 (last)      of group 456
```

and a browse function is issued with MQGMO\_ALL\_MSGS\_AVAILABLE, the first logical message of group 456 is returned, leaving the browse cursor on this logical message. If the second (last) message of group 123 now arrives,

```
Logical message 1 (not last) of group 123
Logical message 2 (last)      of group 123
Logical message 1 (not last) of group 456 <=== browse cursor
Logical message 2 (last)      of group 456
```

and the same browse-next function is issued, it will not be noticed that group 123 is now complete, because the first message of this group is *before* the browse cursor.

In some cases (for example, if messages are retrieved destructively when the group is present in its entirety), it may be acceptable to use MQGMO\_ALL\_MSGS\_AVAILABLE together with MQGMO\_BROWSE\_FIRST. Otherwise, the browse scan must be repeated in order to take note of newly arrived messages that have been missed; just issuing MQGMO\_WAIT together with MQGMO\_BROWSE\_NEXT and MQGMO\_ALL\_MSGS\_AVAILABLE does not take account of them. (This also happens to higher-priority messages that might arrive after scanning the messages is complete.)

The next sections look at browsing examples that deal with unsegmented messages; segmented messages follow similar principles.

### Browsing messages in groups

In this example, the application browses through each message on the queue, in logical order.

Messages on the queue may either be grouped or not. For grouped messages, the application does not want to start processing any group until all of the messages within it have arrived. MQGMO\_ALL\_MSGS\_AVAILABLE is therefore specified for the first message in the group; for subsequent messages in the group, this option is unnecessary.

MQGMO\_WAIT is used in this example. However, although the wait can be satisfied if a new group arrives, for the reasons in “Browsing messages in logical order” on page 156, it will not be satisfied if the browse cursor has already passed the first logical message in a group, and the remaining messages now arrive. Nevertheless, waiting for a suitable interval ensures that the application does not constantly loop while waiting for new messages or segments.

## Browsing messages in logical order

MQGMO\_LOGICAL\_ORDER is used throughout, to ensure that the scan is in logical order. This contrasts with the destructive MQGET example, where because each group is being removed, MQGMO\_LOGICAL\_ORDER is not used when looking for the first (or only) message in a group.

It is assumed that the application's buffer is always large enough to hold the entire message, whether or not the message has been segmented. MQGMO\_COMPLETE\_MSG is therefore specified on each MQGET.

The following gives an example of browsing logical messages in a group:

```
/* Browse the first message in a group, or a message not in a group */
GMO.Options = MQGMO_BROWSE_NEXT | MQGMO_COMPLETE_MSG | MQGMO_LOGICAL_ORDER
              | MQGMO_ALL_MSGS_AVAILABLE | MQGMO_WAIT
MQGET GMO.MatchOptions = MQMO_MATCH_MSG_SEQ_NUMBER, MD.MsgSeqNumber = 1
/* Examine first or only message */
...

GMO.Options = MQGMO_BROWSE_NEXT | MQGMO_COMPLETE_MSG | MQGMO_LOGICAL_ORDER
do while ( GroupStatus == MQGS_MSG_IN_GROUP )
    MQGET
    /* Examine each remaining message in the group */
    ...
```

The above group is repeated until MQRC\_NO\_MSG\_AVAILABLE is returned.

### Browsing and retrieving destructively

In this example, the application browses each of the logical messages within a group, before deciding whether to retrieve that group destructively.

The first part of this example is similar to the previous one. However in this case, having browsed an entire group, we may decide to go back and retrieve it destructively.

As each group is removed in this example, MQGMO\_LOGICAL\_ORDER is not used when looking for the first or only message in a group.

The following gives an example of browsing and then retrieving destructively:

```

GMO.Options = MQGMO_BROWSE_NEXT | MQGMO_COMPLETE_MSG | MQGMO_LOGICAL_ORDER
              | MQGMO_ALL_MESSAGES_AVAILABLE | MQGMO_WAIT
do while ( GroupStatus == MQGS_MSG_IN_GROUP )
    MQGET
    /* Examine each remaining message in the group (or as many as
       necessary to decide whether or not to get it destructively) */
    ...

if ( we want to retrieve the group destructively )

    if ( GroupStatus == ' ' )
        /* We retrieved an ungrouped message */
        GMO.Options = MQGMO_MSG_UNDER_CURSOR | MQGMO_SYNCPOINT
        MQGET GMO.MatchOptions = 0
        /* Process the message */
        ...

    else
        /* We retrieved one or more messages in a group. The browse cursor */
        /* will not normally be still on the first in the group, so we have */
        /* to match on the GroupId and MsgSeqNumber = 1. */
        /* Another way, which works for both grouped and ungrouped messages, */
        /* would be to remember the MsgId of the first message when it was */
        /* browsed, and match on that. */
        GMO.Options = MQGMO_COMPLETE_MSG | MQGMO_SYNCPOINT
        MQGET GMO.MatchOptions = MQMO_MATCH_GROUP_ID
                | MQMO_MATCH_MSG_SEQ_NUMBER,
                (MQMD.GroupId      = value already in the MD)
                MQMD.MsgSeqNumber = 1
        /* Process first or only message */
        ...

        GMO.Options = MQGMO_COMPLETE_MSG | MQGMO_SYNCPOINT
                    | MQGMO_LOGICAL_ORDER
do while ( GroupStatus == MQGS_MSG_IN_GROUP )
    MQGET
    /* Process each remaining message in the group */
    ...

```

---

## Some cases where the MQGET call fails

If certain attributes of a queue are changed using the FORCE option on a command between issuing an MQOPEN and an MQGET call, the MQGET call fails and returns the MQRC\_OBJECT\_CHANGED reason code. The queue manager marks the object handle as being no longer valid. This also happens if the changes apply to any queue to which the queue name resolves. The attributes that affect the handle in this way are listed in the description of the MQOPEN call in “MQOPEN - Open object” in the *MQSeries Application Programming Reference* manual. If your call returns the MQRC\_OBJECT\_CHANGED reason code, close the queue, reopen it, then try to get a message again.

If get operations are inhibited for a queue from which you are attempting to get messages (or any queue to which the queue name resolves), the MQGET call fails and returns the MQRC\_GET\_INHIBITED reason code. This happens even if you are using the MQGET call for browsing. You may be able to get a message

## MQGET failure

successfully if you attempt the MQGET call at a later time, if the design of the application is such that other programs change the attributes of queues regularly.

If a dynamic queue (either temporary or permanent) has been deleted, MQGET calls using a previously acquired object handle fail and return the MQRC\_Q\_DELETED reason code.

---

## Chapter 11. Writing data-conversion exits

*Data-conversion exits are not supported on MQSeries for Windows or VSE/ESA.*

The Message Descriptor of a message is created by your application when you do an MQPUT. As MQSeries needs to be able to understand the contents of the MQMD regardless of the platform it is created on, it is converted automatically by the system.

Application data, however, is not converted automatically. If character data is being exchanged between platforms where the *CodedCharSetId* and *Encoding* fields differ, for example, between ASCII and EBCDIC, it is the responsibility of the application to arrange for conversion of the message. Application data conversion may be performed by the queue manager itself or by a user exit program, referred to as a *data-conversion exit*. This chapter discusses the data-conversion exit facility that MQSeries provides.

Control may be passed to the data-conversion exit during an MQGET call. This avoids converting across different platforms before reaching the final destination. However, if the final destination is a platform that does not support data conversion on the MQGET, you must specify CONVERT(YES) on the sender channel that sends the data to its final destination. This ensures that MQSeries converts the data during transmission. In this case, your data-conversion exit must reside on the system where the sender channel is defined.

The MQGET call can be issued directly by an application. Set the *CodedCharSetId* field of the MQMD to MQCCSI\_DEFAULT to pick up the default CCSID of the queue manager. This ensures that MQSeries knows the correct target CCSID.

The conditions required for the data-conversion exit to be called are defined for the MQGET call in "MQGET - Get message" in the *MQSeries Application Programming Reference* manual.

For a description of the parameters that are passed to the data-conversion exit, and detailed usage notes, see "MQ\_DATA\_CONV\_EXIT - Data conversion exit" for the MQ\_DATA\_CONV\_EXIT call and "MQDXP - Data-conversion exit parameter structure" for the MQDXP structure in the *MQSeries Application Programming Reference* manual.

Programs that convert application data between different machine encodings and CCSIDs must conform to the MQSeries data conversion interface (DCI).

---

### Invoking the data-conversion exit

A data-conversion exit is a user-written exit that receives control during the processing of an MQGET call. The exit is invoked if the following are true:

- The MQGMO\_CONVERT option is specified on the MQGET call.
- The *CodedCharSetId* or *Encoding* fields in the MQMD structure associated with the message on the queue differ from the *CodedCharSetId* or *Encoding* fields in the MQMD structure specified on the MQGET call (see the code page support tables in Appendix F, "Code page conversion tables" in the *MQSeries Application Programming Reference* manual).

## Data-conversion exits

- The *Format* field in the MQMD structure associated with the message is not MQFMT\_NONE (MQFMT\_STRING indicates that the message consists entirely of character data).
- The *BufferLength* specified on the MQGET call is not zero.
- The message data length is not zero.
- Either the message format is not one that can be handled by one of the built-in conversion routines, or its format can be handled by one of the built-in conversion routines but the routine is unable to convert the message itself. The conversion routines supplied with the product **always** attempt to convert the built-in format messages first; user-written routines are called only if these product-supplied routines fail to convert.

There are some other conditions, described fully in the usage notes of the MQ\_DATA\_CONV\_EXIT call in “MQ\_DATA\_CONV\_EXIT - Data conversion exit” in the *MQSeries Application Programming Reference* manual.

See “MQGET - Get message” in the *MQSeries Application Programming Reference* manual for details of the MQGET call. Data-conversion exits cannot use MQI calls, other than MQXCNCV.

A new copy of the exit is loaded when an application attempts to retrieve the first message that uses that *Format* since the application connected to the queue manager. A new copy may also be loaded at other times if the queue manager has discarded a previously-loaded copy.

The data-conversion exit runs in an environment similar to that of the program which issued the MQGET call. As well as user applications, the program can be an MCA (message channel agent) sending messages to a destination queue manager that does not support message conversion. The environment includes address space and user profile, where applicable. The exit cannot compromise the queue manager's integrity, since it does not run in the queue manager's environment.

In a client-server environment, the exit is loaded at the server, and conversion takes place there.

## Data conversion on OS/390

On OS/390, you must also be aware of the following:

- Exit programs can be written in assembler language only.
- Exit programs must be reentrant, and capable of running anywhere in storage.
- Exit programs must restore the environment on exit to that at entry, and must free any storage obtained.
- Exit programs must not WAIT, or issue ESTAEs or SPIEs.
- Exit programs are normally invoked as if by OS/390 LINK in:
  - Non-authorized problem program state
  - Primary address space control mode
  - Non cross-memory mode
  - Non access-register mode
  - 31 bit addressing mode
  - TCB-PRB mode

- When used by a CICS application, the exit is invoked by EXEC CICS LINK, and should conform to the CICS programming conventions. The parameters are passed by pointers (addresses) in the CICS communication area (COMMAREA).

Although not recommended, user exit programs can also make use of CICS API calls, with the following caution:

- Do not issue syncpoints, as the results could influence units of work declared by the MCA.
  - Do not update any resources controlled by a resource manager other than MQSeries for OS/390, including those controlled by CICS Transaction Server for OS/390.
- For distributed queuing without CICS, the exit is loaded from the data set referenced by the CSQXLIB DD statement. In other environments, the exit is loaded from the same place as application programs.
  - For distributed queuing using CICS, data-conversion exits are not supported.

---

## Writing a data-conversion exit program

For OS/390, you must write data-conversion exits in assembler language. For other platforms, it is recommended that you use the C programming language.

To help you create a data-conversion exit program, the following are supplied:

- A skeleton source file
- A convert characters call
- A utility that creates a fragment of code that performs data conversion on data type structures

This utility takes C input only. On OS/390, it produces assembler code.

These are described in subsequent sections.

For the procedure for writing the programs see:

- “Writing a data-conversion exit program for MQSeries for AS/400” on page 167
- “Writing a data-conversion exit for MQSeries for OS/2 Warp” on page 168
- “Writing a data-conversion exit program for MQSeries for OS/390” on page 170
- “Writing a data-conversion exit for MQSeries for Tandem NSK” on page 171
- “Writing a data-conversion exit for MQSeries on UNIX systems and Digital OpenVMS” on page 172
- “Writing a data-conversion exit for MQSeries for Windows NT” on page 177

## Skeleton source file

These can be used as your starting point when writing a data-conversion exit program. The files supplied are listed in Table 7:

<i>Table 7. Skeleton source files</i>	
<b>Platform</b>	<b>File</b>
AIX	amqsvfc0.c
AS/400	QMOMSAMP/QCSRC(AMQSVFC4)
AT&T GIS UNIX	amqsvfcx.c
Digital OpenVMS	AMQSVFCX.C
HP-UX	amqsvfc0.c
OS/2	AMQSVFC0.C
OS/390	CSQ4BAX8 (1) CSQ4BAX9 (2) CSQ4CAX9 (3)
SINIX and DC/OSx	amqsvfcx.c
Sun Solaris	amqsvfc0.c
Tandem NSK	amqsvfcn
Windows NT	amqsvfc0.c
<b>Notes:</b>	
<ol style="list-style-type: none"> <li>1. Illustrates the MQXCVNC call.</li> <li>2. A wrapper for the code fragments generated by the utility for use in all environments except CICS.</li> <li>3. A wrapper for the code fragments generated by the utility for use in the CICS environment.</li> </ol>	

## Convert characters call

The MQXCNVN (Convert characters) call may be used from within a data-conversion exit program to convert character message data from one character set to another. For certain multibyte character sets (for example, UCS2 character sets), the appropriate options must be used.

No other MQI calls can be made from within the exit; an attempt to make such a call fails with reason code MQRC\_CALL\_IN\_PROGRESS.

See “MQXCNVN - Convert characters” in the *MQSeries Application Programming Reference* manual for further information on the MQXCNVN call and appropriate options.

## Utility for creating conversion-exit code

The commands for creating conversion-exit code are:

AS/400

CVTMQMDTA (Convert MQSeries Data Type)

OS/2, Digital OpenVMS, Tandem NSK, Windows NT, and UNIX systems

**crtmqcvx** (Create MQSeries conversion-exit)

OS/390

CSQUCVX

The command for your platform produces a fragment of code that performs data conversion on data type structures, for use in your data-conversion exit program. The command takes a file containing one or more C language structure definitions. On OS/390, it then generates a data set containing assembler code fragments and conversion functions. On other platforms, it generates a file with a C function to convert each structure definition. The utility requires access to the LE/370 run-time library SCEERUN.

### Invoking the CSQUCVX utility on OS/390

Figure 13 shows an example of the JCL used to invoke the CSQUCVX utility.

```
//CVX      EXEC PGM=CSQUCVX
//STEPLIB DD DISP=SHR,DSN=th1qua1.SCSQANLE
//          DD DISP=SHR,DSN=th1qua1.SCSQLOAD
//          DD DISP=SHR,DSN=1e370qua1.SCEERUN
//SYSPRINT DD SYSOUT=*
//CSQUINP DD DISP=SHR,DSN=MY.MQSERIES.FORMATS(MSG1)
//CSQUOUT DD DISP=OLD,DSN=MY.MQSERIES.EXIT1(MSG1)
```

Figure 13. Sample JCL used to invoke the CSQUCVX utility

### Data definition statements

The CSQUCVX utility requires DD statements with the following DDnames:

#### SYSPRINT

This specifies a data set or print spool class for reports and error messages.

#### CSQUINP

This specifies the sequential data set containing the definitions of the data structures to be converted.

#### CSQUOUT

This specifies the sequential data set where the conversion code fragments are to be written. The logical record length (LRECL) must be 80 and the record format (RECFM) must be FB.

### Error messages in OS/2, Windows NT, and UNIX systems

The `crtmqcvx` command returns messages in the range AMQ7953 through AMQ7970. For other platforms, see the appropriate *System Management Guide* for your platform.

There are two main types of error:

- Major errors, such as syntax errors, when processing cannot continue.

A message is displayed on the screen giving the line number of the error in the input file. The output file may have been partially created.

- Other errors when a message is displayed stating that a problem has been found but parsing of the structure can continue.

The output file has been created and contains error information on the problems that have occurred. This error information is prefixed by #error so that the code produced will not be accepted by any compiler without intervention to rectify the problems.

### Valid syntax

Your input file for the utility must conform to the C language syntax. If you are unfamiliar with C, refer to “Example of valid syntax for the input data set.”

In addition, you must be aware of the following rules:

- typedef is recognized only before the struct keyword.
- A structure tag is required on your structure declarations.
- Empty square brackets [ ] may be used to denote a variable length array or string at the end of a message.
- Multidimensional arrays and arrays of strings are not supported.
- The following additional data types are recognized:

```
MQBYTE
MQCHAR
MQSHORT
MQLONG
```

MQCHAR fields are code page converted, but MQBYTE is left untouched. If the encoding is different, MQSHORT and MQLONG are converted accordingly.

- The following should **not** be used:

```
float
double
pointers
bit-fields
```

This is because the utility for creating conversion-exit code does not provide the facility to convert these data types. To overcome this, you can write your own routines and call them from the exit.

Other points to note:

- Do not use sequence numbers in the input data set.
- If there are fields for which you want to provide your own conversion routines, declare them as MQBYTE, and then replace the generated CMQXCFBA macros with your own conversion code.

#### Example of valid syntax for the input data set

```
struct TEST { MQLONG    SERIAL_NUMBER;
              MQCHAR    ID[5];
              MQSHORT   VERSION;
              MQBYTE    CODE[4];
              MQLONG    DIMENSIONS[3];
              MQCHAR    NAME[24];
              } ;
```

This corresponds to the following declarations in the other programming languages:

### COBOL

```

10 TEST.
   15 SERIAL-NUMBER PIC S9(9) BINARY.
   15 ID             PIC X(5).
   15 VERSION       PIC S9(4) BINARY.
* CODE IS NOT TO BE CONVERTED
   15 CODE          PIC X(4).
   15 DIMENSIONS   PIC S9(9) BINARY OCCURS 3 TIMES.
   15 NAME          PIC X(24).

```

### System/390 assembler: Supported on OS/390 only

```

TEST          EQU *
SERIAL_NUMBER DS F
ID            DS CL5
VERSION       DS H
CODE          DS XL4
DIMENSIONS    DS 3F
NAME          DS CL24

```

### PL/I: Supported on AIX, OS/390, OS/2 Warp, and Windows NT only

```

DCL 1 TEST,
     2 SERIAL_NUMBER FIXED BIN(31),
     2 ID             CHAR(5),
     2 VERSION        FIXED BIN(15),
     2 CODE           CHAR(4),      /* not to be converted */
     2 DIMENSIONS(3)  FIXED BIN(31),
     2 NAME           CHAR(24);

```

---

## Writing a data-conversion exit program for MQSeries for AS/400

Follow these steps:

1. Name your message format. The name must fit in the *Format* field of the MQMD. The *Format* name should not have leading embedded blanks, and trailing blanks are ignored. The object's name must have no more than eight non-blank characters, because the *Format* is only eight characters long. Remember to use this name each time you send a message (our example uses the name *Format*).
2. Create a structure to represent your message. See "Valid syntax" on page 166 for an example.
3. Run this structure through the CVTMQMMDTA command to create a code fragment for your data-conversion exit.

The functions generated by the CVTMQMMDTA command use macros that are shipped in the file QMQM/H(AMQSVMDHA). These macros are written assuming that all structures are packed; they should be amended if this is not the case.

4. Take a copy of the supplied skeleton source file, QMQMSAMP/QCSRC(AMQSVFC4) and rename it. (Our example uses the name EXIT\_MOD.)

5. Find the following comment boxes in the source file and insert code as described:
  - a. Towards the bottom of the source file, a comment box starts with:

```
/* Insert the functions produced by the data-conversion exit */
```

Here, insert the code fragment generated in step 3.
  - b. Near the middle of the source file, a comment box starts with:

```
/* Insert calls to the code fragments to convert the format's */
```

This is followed by a commented-out call to the function `ConverttagSTRUCT`. Change the name of the function to the name of the function you added in step 5a above. Remove the comment characters to activate the function. If there are several functions, create calls for each of them.
  - c. Near the top of the source file, a comment box starts with:

```
/* Insert the function prototypes for the functions produced by */
```

Here, insert the function prototype statements for the functions added in step 5a above.

If the message contains character data, the generated code will call `MQXCNVC`; this can be resolved by binding the service programs `AMQVSTUB` and `AMQZSTUB`.
6. Compile the source module, `EXIT_MOD`, using the `CRTCMOD` command.

7. Create/link the program:

```
CRTPGM PGM(library/Format) +  
      MODULE(library/EXIT_MOD) +  
      BNDSRVPGM(QMQM/AMQVSTUB) +  
      BNDSRVPGM(QMQM/AMQZSTUB) +  
      ACTGRP(QMQM) +  
      USRPRF(*USER)
```

8. Place the output in the library list for the MQSeries job. It is recommended that, for production, data-conversion exit programs be stored in `QSYS`.

### Notes:

1. If `CVTMQMMDTA` uses packed structures, all MQSeries applications must use the `_Packed` qualifier.
2. Data-conversion exit programs must be re-entrant.
3. `MQXCNVC` is the **only** MQI call that may be issued from a data-conversion exit.
4. The exit program should be compiled with the user profile compiler option set to `*USER`, so that the exit runs with the authority of the user.

---

## Writing a data-conversion exit for MQSeries for OS/2 Warp

Follow these steps:

1. Name your message format. The name must fit in the `Format` field of the `MQMD`. The `Format` name should not have leading blanks. Trailing blanks are ignored. The object's name must have no more than eight non-blank characters, because the `Format` is only eight characters long.

A .DEF file called AMQSVFC2.DEF is also supplied in the samples directory, <drive:\directory>\MQM\TOOLS\C\SAMPLES. Take a copy of this file and rename it, for example, to MYFORMAT.DEF. Make sure that the name of the DLL being created and the name specified in MYFORMAT.DEF are the same. Overwrite the name F0RMAT1 in MYFORMAT.DEF with the new format name.

Remember to use this name each time you send a message.

2. Create a structure to represent your message. See “Valid syntax” on page 166 for an example.
3. Run this structure through the CRTMQCVX command to create a code fragment for your data-conversion exit.

The functions generated by the CRTMQCVX command use macros which are written assuming that all structures are packed; they should be amended if this is not the case.

4. Take a copy of the supplied skeleton source file, AMQSVFC0.C, renaming it to the name of your message format that you decided on in step 1 (that is, MYFORMAT.C in this example).

AMQSVFC0.C is in <drive:\directory>\MQM\TOOLS\C\SAMPLES (where <drive:\directory> was specified at installation).

The skeleton includes a sample header file AMQSVMHA.H in the same directory. Make sure that your include path points to this directory to pick up this file.

The AMQSVMHA.H file contains macros that are used by the code generated by the CRTMQCVX command. If the structure to be converted contains character data, then these macros call MQXCNCV.

5. Find the following comment boxes in the source file and insert code as described:

- a. Towards the bottom of the source file, a comment box starts with:

```
/* Insert the functions produced by the data-conversion exit */
```

Here, insert the code fragment generated in step 3.

- b. Near the middle of the source file, a comment box starts with:

```
/* Insert calls to the code fragments to convert the format's */
```

This is followed by a commented-out call to the function ConverttagSTRUCT.

Change the name of the function to the name of the function you added in step 5a above. Remove the comment characters to activate the function. If there are several functions, create calls for each of them.

- c. Near the top of the source file, a comment box starts with:

```
/* Insert the function prototypes for the functions produced by */
```

Here, insert the function prototype statements for the functions added in step 5a above.

6. Resolve this call by linking the routine with the library MQMVX.LIB, in the directory <drive:\directory>\MQM\TOOLS\LIB.

7. Create the following command file:

```
icc /Ge- \
/I<drive:\directory>\mqm\tools\c\include MYFORMAT.C \
<drive:\directory>\mqm\tools\lib\mqm.lib MYFORMAT.DEF \
<drive:\directory>\mqm\tools\lib\mqmvx.lib
```

where <drive:\directory> is specified at installation.

Issue the command file to compile your exit as a DLL file.

8. Place the output in the \mqm\exits subdirectory. The path used to look for the data-conversion exits is given in the qm.ini file as DefaultExitPath. This path is set for each queue manager and the exit will only be looked for in that path or paths.

### Notes:

1. If CVTMQCVX uses packed structures, all MQSeries applications must be compiled in this way.
2. Data-conversion exit programs must be re-entrant.
3. MQXCNVC is the **only** MQI call that may be issued from a data-conversion exit.

---

## Writing a data-conversion exit program for MQSeries for OS/390

Follow these steps:

1. Take the supplied source skeleton CSQ4BAX9 (for non-CICS environments) or CSQ4CAX9 (for CICS) as your starting point.
2. Run the CSQUCVX utility.
3. Follow the instructions in the prolog of CSQ4BAX9 or CSQ4CAX9 to incorporate the routines generated by the CSQUCVX utility, in the order that the structures occur in the message you want to convert.
4. The utility assumes that the data structures are not packed, that the implied alignment of the data is honored, and that the structures start on a full-word boundary, with bytes being skipped as required (as between ID and VERSION in the "Example of valid syntax for the input data set" on page 166). If the structures are packed, you will need to omit the CMQXCALA macros that are generated. You are therefore strongly recommended to declare your structures in such a way that all fields are named and no bytes are skipped; in the "Example of valid syntax for the input data set" on page 166, you would add a field "MQBYTE DUMMY;" between ID and VERSION.
5. The supplied exit returns an error if the input buffer is shorter than the message format to be converted. Although the exit converts as many complete fields as possible, the error causes an unconverted message to be returned to the application. If you want to allow short input buffers to be converted as far as possible, including partial fields, change the TRUNC= value on the CSQXCDF macro to YES: no error is returned, so the application receives a converted message. The application is responsible for handling the truncation.
6. Add any other special processing code that you need.
7. Rename the program to your data format name.

8. Compile and link-edit your program like a batch application program (unless it is for use with CICS applications). The macros in the code generated by the utility are in the library, **thlqual.SCSQMACS**.

If the message contains character data, the generated code will call MQXCNV. If your exit uses this call, link-edit it with the exit stub program CSQASTUB. The stub is language-independent and environment-independent. Alternatively, you can load the stub dynamically using the dynamic call name CSQXCNV. See “Dynamically calling the MQSeries stub” on page 279 for more information.

Place the link-edited module in your application load library, and in a data set that is referenced by the CSQXLIB DD statement of your task procedure started by your channel initiator.

9. If the exit is for use by CICS applications, compile and link-edit it like a CICS application program, including CSQASTUB if required. Place it in your CICS application program library. Define the program to CICS in the usual way, specifying EXECKEY(CICS) in the definition.

**Note:** Although the LE/370 run-time libraries are needed for running the CSQUCVX utility (see step 2 on page 170), they are not needed for link-editing or running the data-conversion exit itself (see steps 8 and 9).

See “Writing MQSeries-IMS bridge applications” on page 239 for information about data conversion within the MQSeries-IMS bridge.

---

## Writing a data-conversion exit for MQSeries for Tandem NSK

Dynamically bound libraries are not supported by MQSeries for Tandem NSK. Data conversion exits (and channel exits) are implemented by including statically bound stub functions in the MQSeries libraries and executables that can be replaced using the REPLACE bind option.

A data conversion exit **must** be called DATACONVEXIT (see sample AMQSVFCN), and can be bound into the chosen executable (or library) using the TACL macro BEXITE.

**Note:** This procedure modifies the target executable; you are recommended to make a back-up copy of the target executable or library before using the macro.

Exit functions, once compiled, must be bound directly into the target executable or library to be accessible by MQSeries. The following TACL macro is used for this purpose:

**BEXITE** Usage: BEXITE *target-executable-or-library*  
*source-exit-file-or-library*

For example, to bind the sample data conversion exit into the sample MQSGETA, follow these steps:

1. Compile the exit function DATACONVEXIT (CSAMP AMQSVFCN).
2. Compile the get application (CSAMP AMQSGET0).
3. Bind the get application (BSAMP AMQSGET).
4. Bind the exit function into the get application (BEXITE AMQSGET AMQSVFCO).

## Data-conversion exits

Alternatively, if all applications are to have this data conversion exit, the following steps would create both a user library and an application with the exit bound in:

1. Compile the exit function DATACONVEXIT (CSAMP AMQSVFCN).
2. Compile the get application (CSAMP AMQSGET0).
3. Bind the exit function into the user library (BEXITE ZMQSLIB.MQMLIBC AMQSVFCO).
4. Bind the get application with the modified library (BSAMP AMQSGET).

If the data conversion exit is to be used by channels processing within MQSeries, it must also be bound into the caller executable by the system administrator. For example:

```
BEXITE ZMQSEXE.MQMCACAL AMQSVFCO
```

Use the TACL macro BDCXALL to bind the data conversion exit into all required MQSeries processes. For example:

```
BDCXALL source-exit-file-or-library
```

## Reusing data-conversion exit programs

In other MQSeries Version 2 products, a data-conversion exit is required for each application-defined format to be supported. The data-conversion exit programs are named according to the *Format* value (from MQMD) of the message to be converted. The format for which conversion is being requested can be determined from the *Format* field of the *MsgDesc* parameter. The appropriate data-conversion exit program can therefore be invoked from MQDATA CONVEXIT(). The parameters supplied to MQDATA CONVEXIT() can be supplied to the invoked data-conversion function.

---

## Writing a data-conversion exit for MQSeries on UNIX systems and Digital OpenVMS

*For SINIX and DC/OSx, data-conversion exits must not use DCE.*

Follow these steps:

1. Name your message format. The name must fit in the *Format* field of the MQMD, and be in uppercase, for example, MYFORMAT. The *Format* name should not have leading blanks. Trailing blanks are ignored. The object's name must have no more than eight non-blank characters because the *Format* is only eight characters long. Remember to use this name each time you send a message.
2. Create a structure to represent your message. See "Valid syntax" on page 166 for an example.
3. Run this structure through the **crtmqcvx** command to create a code fragment for your data-conversion exit.

The functions generated by the **crtmqcvx** command use macros which are written assuming that all structures are packed; they should be amended if this is not the case.

4. Take a copy of the supplied skeleton source file renaming it to the name of your message format that you decided on in step 1 (that is, MYFORMAT.C).

**Note:** On MQSeries for AIX, HP-UX, and Sun Solaris the skeleton source file is called amqsvfc0.c. On MQSeries for Digital OpenVMS, AT&T GIS UNIX, and SINIX and DC/OSx the skeleton source file is called amqsvfcx.c.

The skeleton includes a sample header file amqsvmha.h in the directory /usr/mqm/inc (on AIX) or /opt/mqm/inc (on other UNIX systems). Make sure that your include path points to this directory to pick up this file.

The amqsvmha.h file contains macros that are used by the code generated by the **crtmqcvx** command. If the structure to be converted contains character data, then these macros call MQXCNVC.

5. Find the following comment boxes in the source file and insert code as described:
  - a. Towards the bottom of the source file, a comment box starts with:
 

```
/* Insert the functions produced by the data-conversion exit */
```

 Here, insert the code fragment generated in step 3.
  - b. Near the middle of the source file, a comment box starts with:
 

```
/* Insert calls to the code fragments to convert the format's */
```

 This is followed by a commented-out call to the function ConverttagSTRUCT. Change the name of the function to the name of the function you added in step 5a above. Remove the comment characters to activate the function. If there are several functions, create calls for each of them.
  - c. Near the top of the source file, a comment box starts with:
 

```
/* Insert the function prototypes for the functions produced by */
```

 Here, insert the function prototype statements for the functions added in step 5a above.
6. Resolve this call by linking the routine with the library libmqm. For threaded programs, the routine must be linked with the library libmqm\_r (AIX and HP-UX only).
7. Compile your exit as a shared library, using MQStart as the entry point. To do this, see "Compiling data-conversion exits on UNIX" on page 175, or "Compiling data-conversion exits on Digital OpenVMS" on page 174.
8. Place the output in the default system directory, /var/mqm/exits, to ensure that it can be loaded when required. The path used to look for the data-conversion exits is given in the qm.ini file. This path can be set for each queue manager and the exit is only looked for in that path or paths.

#### Notes:

1. If **crtmqcvx** uses packed structures, all MQSeries applications must be compiled in this way.
2. Data-conversion exit programs must be re-entrant.
3. MQXCNVC is the **only** MQI call that may be issued from a data-conversion exit.

### UNIX environment

There are two environments to consider: non threaded and threaded.

#### Non-threaded environment

The loadable object must have its name in upper case, for example MYFORMAT. The libmqm library should be used to resolve the calls to MQXCNVC.

#### Threaded environment

In addition to creating the data-conversion exit for the basic environment, another is required in the threaded environment. This loadable object must be followed by `_r` (on AIX and HP-UX) and `_d` (on Sun Solaris) to indicate that it is a DCE-threaded version. The `libmqm_r` library (on AIX and HP-UX) and the `lmqmcs_d` library (on Sun Solaris) should be used to resolve the calls to MQXCNVC. Note that both loadable objects (non-threaded and threaded) are required for a threading environment.

**Note:** If the data-conversion exits are in a mixed non-threaded and threaded environment, the calling environment is detected and the appropriate object loaded. The shared object should be placed in `/var/mqm/exits` to ensure it can be loaded when required.

### Compiling data-conversion exits on Digital OpenVMS

The names of the routines which are called by the data-conversion exit must be made universal.

```
$ CC /INCLUDE_DIRECTORY=MQS_INCLUDE AMQSVFCX.C  
$ LINK /SYS$SHARE:[SYSLIB]MYFORMAT AMQSVFCX.OBJ,MYFORMAT/OPTIONS
```

The contents of MYFORMAT.OPT vary depending on which platform you are working on.

On Alpha:

```
SYS$SHARE:MQM/SHAREABLE  
SYS$SHARE:MQMCS/SHAREABLE  
SYMBOL_VECTOR=(MQSTART=PROCEDURE)
```

On VAX:

```
SYS$SHARE:MQM/SHAREABLE  
SYS$SHARE:MQMCS/SHAREABLE  
UNIVERSAL=MQSTART
```

If you are using threaded applications linked with the pthread library, you must also build a second copy of the data-conversion exit with the thread options and libraries:

```
$ CC /INCLUDE_DIRECTORY=MQS_INCLUDE AMQSVFCX.C  
$ LINK /SYS$SHARE:[SYSLIB]MYFORMAT AMQSVFCX.OBJ,MYFORMAT/OPTIONS
```

Again, the contents of MYFORMAT.OPT vary depending on which platform you are working on.

On Alpha:

```
SYS$SHARE:MQM_R/SHAREABLE
SYS$SHARE:MQMCS_R/SHAREABLE
SYS$SHARE:CMA$OPEN_RTL.EXE/SHAREABLE
SYMBOL_VECTOR-(MQSTART=PROCEDURE)
```

On VAX:

```
SYS$SHARE:MQM_R/SHAREABLE
SYS$SHARE:MQMCS_R/SHAREABLE
SYS$SHARE:CMA$OPEN_RTL.EXE/SHAREABLE
UNIVERSAL=MQSTART
```

## Compiling data-conversion exits on UNIX

The following sections give examples of how to compile a data conversion exit on the UNIX platforms.

On all platforms, the entry point to the module is MQStart.

### On AIX 4.2

```
$ cc -c -I/usr/mqm/inc MYFORMAT.C
$ ld MYFORMAT.o -e MQStart -o MYFORMAT -bM:SRE -H512 -T512 -lmqm -lc
$ cp MYFORMAT /var/mqm/exits
```

If you are using threaded application linked with the pthreads library, you must build a second copy of the conversion exit with the thread options and libraries.

```
$ cc_r -c -I/usr/mqm/inc MYFORMAT.C
$ ld MYFORMAT.o -e MQStart -o MYFORMAT_r -bM:SRE -H512 \
-T512 -lmqm_r -lpthreads -lc_r
$ cp MYFORMAT_r /var/mqm/exits
```

### On AIX 4.3

```
$ cc -c -I/usr/mqm/inc MYFORMAT.C
$ ld MYFORMAT.o -e MQStart -o MYFORMAT -bM:SRE -H512 -T512 -lmqm -lc
$ cp MYFORMAT /var/mqm/exits
```

You must build conversion exits for the threaded environment using the draft 7 Posix threads interface rather than the draft 10 interface which is the AIX 4.3 default.

```
$ xlc_r7 -c -I/usr/mqm/inc MYFORMAT.C
$ ld MYFORMAT.o -eMQStart -o MYFORMAT_r -bM:SRE -H512 -T512 \
-lmqm_r -lpthreads_compat -lpthreads -lc_r
$ cp MYFORMAT_r /var/mqm/exits
```

### On AT&T GIS UNIX

```
$ cc -c -K PIC -I/opt/mqm/inc MYFORMAT.C
$ ld -G MYFORMAT.O -o MYFORMAT
$ cp MYFORMAT /opt/mqm/lib
```

### On HP-UX

```
$ CC -c -Aa +z -I/opt/mqm/inc MYFORMAT.C
$ ld -b MYFORMAT.o -o MYFORMAT -L /opt/mqm/lib -lmqm +IMQStart
$ cp MYFORMAT /var/mqm/exits
```

If you are using threaded applications linked with the pthreads library, you must build a second copy of the conversion exit with the thread options and libraries.

```
$ CC -c -Aa +z -I/opt/mqm/inc -D_REENTRANT MYFORMAT.C
$ ld -b MYFORMAT.o -o MYFORMAT_r -L /opt/mqm/lib \
-lmqm_r -lcma -lc_r +IMQStart
$ cp MYFORMAT_r /var/mqm/exits
```

### On SINIX

```
$ cc -c -K PIC -I/opt/mqm/inc -lmproc -lxt MYFORMAT.C
$ ld -G MYFORMAT.O -o MYFORMAT
$ cp MYFORMAT /opt/mqm/lib
```

### On DC/OSx

```
$ cc -c -K PIC -I/opt/mqm/inc -liconv -lmproc -lxt MYFORMAT.C
$ ld -G MYFORMAT.O -o MYFORMAT
$ cp MYFORMAT /opt/mqm/lib
```

### On Sun Solaris

If your application uses no threading calls or Posix V10 threading calls:

```
cc -c -KPIC -I/opt/mqm/inc MYFORMAT.C

ld -G /opt/SUNWspro/SC4.0/lib/crt1.o
/opt/SUNWspro/SC4.0/lib/crti.o
/opt/SUNWspro/SC4.0/lib/crtn.o
/opt/SUNWspro/SC4.0/lib/values-xt.o
MYFORMAT.o -o MYFORMAT -lmqm -lthread -lsocket -lc -lnsl -ldl

cp MYFORMAT /var/mqm/exits
```

If your application requires DCE threading (for example, if it is a CICS application):

```
cc -c -KPIC -I/opt/mqm/inc MYFORMAT.C

ld -G /opt/SUNWspro/SC4.0/lib/crt1.o
/opt/SUNWspro/SC4.0/lib/crti.o
/opt/SUNWspro/SC4.0/lib/crtn.o
/opt/SUNWspro/SC4.0/lib/values-xt.o
MYFORMAT.o -o MYFORMAT_d -ldce -lnsl -lthread -lm -lsocket
-lmqmcs_d -lmqm -lc -ldl

cp MYFORMAT /var/mqm/exits
```

**Note:** The SC4.0 directory name varies depending on the release of compiler.

If you want to run applications using both the Posix V10-threaded and the DCE-threaded variants on a single queue manager:

1. Build a Posix V10 type of data-conversion exit. Name it MYFORMAT and place it in the appropriate exit directory.
2. Build a DCE-threaded type of data-conversion exit. Name it MYFORMAT\_d and place it in the appropriate exit directory.

Two object files are generated; one of which loads the MYFORMAT data-conversion exit, and the other of which loads the MYFORMAT\_d data-conversion exit.

---

## Writing a data-conversion exit for MQSeries for Windows NT

Follow these steps:

1. Name your message format. The name must fit in the *Format* field of the MQMD. The *Format* name should not have leading blanks. Trailing blanks are ignored. The object's name must have no more than eight non-blank characters, because the *Format* is only eight characters long.

A .DEF file called amqsvfcn.def is also supplied in the samples directory, <drive:\directory>\Program Files\MQSeries\Tools\C\Samples. Take a copy of this file and rename it, for example, to MYFORMAT.DEF. Make sure that the name of the DLL being created and the name specified in MYFORMAT.DEF are the same. Overwrite the name FORMAT1 in MYFORMAT.DEF with the new format name.

Remember to use this name each time you send a message.

2. Create a structure to represent your message. See "Valid syntax" on page 166 for an example.
3. Run this structure through the CRTMQCVX command to create a code fragment for your data-conversion exit.

The functions generated by the CVTMQCVX command use macros which are written assuming that all structures are packed; they should be amended if this is not the case.

4. Take a copy of the supplied skeleton source file, amqsvfc0.c, renaming it to the name of your message format that you decided on in step 1 (that is, MYFORMAT).

amqsvfc0.c is in <drive:\directory>\Program Files\MQSeries\Tools\C\Samples (where <drive:\directory> was specified at installation).

The skeleton includes a sample header file amqsvmha.h in the same directory. Make sure that your include path points to this directory to pick up this file.

The amqsvmha.h file contains macros that are used by the code generated by the CRTMQCVX command. If the structure to be converted contains character data, then these macros call MQXCNCV.

5. Find the following comment boxes in the source file and insert code as described:

- a. Towards the bottom of the source file, a comment box starts with:

```
/* Insert the functions produced by the data-conversion exit */
```

Here, insert the code fragment generated in step 3.

- b. Near the middle of the source file, a comment box starts with:

```
/* Insert calls to the code fragments to convert the format's */
```

This is followed by a commented-out call to the function ConverttagSTRUCT.

## Data-conversion exits

Change the name of the function to the name of the function you added in step 5a above. Remove the comment characters to activate the function. If there are several functions, create calls for each of them.

- c. Near the top of the source file, a comment box starts with:

```
/* Insert the function prototypes for the functions produced by */
```

Here, insert the function prototype statements for the functions added in step 5a above.

6. Resolve this call by linking the routine with the library MQMVX.LIB, in the directory <drive:\directory>\Program Files\MQSeries\Tools\Lib.

7. Create the following command file:

```
cl -I <drive:\directory>\Program Files\MQSeries\Tools\C\Include -Tp \
MYFORMAT.C -LD -DEFAULTLIB \
<drive:\directory>\Program Files\MQSeries\Tools\Lib\mqm.lib \
<drive:\directory>\Program Files\MQSeries\Tools\Lib\mqmvx.lib \
MYFORMAT.DEF
```

where <drive:\directory> is specified at installation,

Issue the command file to compile your exit as a DLL file.

8. Place the output in the C:\WINNT\Profiles\All Users\Application Data\MQSeries\EXITS subdirectory. The path used to look for the data-conversion exits is given in the registry. This path can be set for each queue manager and the exit is only looked for in that path or paths.

### Notes:

1. If CVTMQCVX uses packed structures, all MQSeries applications must be compiled in this way.
2. Data-conversion exit programs must be re-entrant.
3. MQXCNVC is the **only** MQI call that may be issued from a data-conversion exit.

## Chapter 12. Inquiring about and setting object attributes

Attributes are the properties that define the characteristics of an MQSeries object. They affect the way that an object is processed by a queue manager. The attributes of each type of MQSeries object are described in detail in Chapter 4, "Attributes of MQSeries objects" in the *MQSeries Application Programming Reference* manual.

Some attributes are set when the object is defined, and can be changed only by using the MQSeries commands; an example of such an attribute is the default priority for messages put on a queue. Other attributes are affected by the operation of the queue manager and may change over time; an example is the current depth of a queue.

You can inquire about the current values of all these attributes using the MQINQ call. The MQI also provides an MQSET call with which you can change some queue attributes. You cannot use the MQI calls to change the attributes of any other type of object; instead you must use:

### For MQSeries for OS/390

The ALTER operator commands (or the DEFINE commands with the REPLACE option), which are described in the *MQSeries Command Reference*.

### For MQSeries for AS/400

The CHGMQMx CL commands, which are described in the *MQSeries for AS/400 Administration Guide*, or you can use the MQSC facility.

### For MQSeries for Tandem NSK

The MQM screen-based interface, which is described in the *MQSeries for Tandem NonStop Kernel System Management Guide*, or you can use the MQSC facility.

### For MQSeries for VSE/ESA

The panel interface, which is described in the *MQSeries for VSE/ESA System Management Guide*.

### For MQSeries for all other platforms

The MQSC facility, described in Chapter 2, "The MQSeries commands" in the *MQSeries Command Reference*.

**Note:** The names of the attributes of objects are shown in this book in the form that you use them with the MQINQ and MQSET calls. When you use MQSeries commands to define, alter, or display the attributes, you must identify the attributes using the keywords shown in the descriptions of the commands in the above books.

Both the MQINQ and the MQSET calls use arrays of selectors to identify those attributes you want to inquire about or set. There is a selector for each attribute you can work with. The selector name has a prefix, determined by the nature of the attribute:

MQCA\_ These selectors refer to attributes that contain character data (for example, the name of a queue).

**MQIA\_** These selectors refer to attributes that contain either numeric values (such as *CurrentQueueDepth*, the number of messages on a queue) or a constant value (such as *SyncPoint*, whether or not the queue manager supports syncpoints).

Before you use the MQINQ or MQSET calls your application must be connected to the queue manager, and you must use the MQOPEN call to open the object for setting or inquiring about attributes. These operations are described in Chapter 7, “Connecting and disconnecting a queue manager” on page 89 and Chapter 8, “Opening and closing objects” on page 97.

---

### Inquiring about the attributes of an object

Use the MQINQ call to inquire about the attributes of any type of MQSeries object.

As input to this call, you must supply:

- A connection handle.
- An object handle.
- The number of selectors.
- An array of attribute selectors, each selector having the form MQCA\_★ or MQIA\_★. Each selector represents an attribute whose value you want to inquire about, and each selector must be valid for the type of object that the object handle represents. You can specify selectors in any order.
- The number of integer attributes that you are inquiring about. Specify zero if you are not inquiring about integer attributes.
- The length of the character attributes buffer in *CharAttrLength*. This must be at least the sum of the lengths required to hold each character attribute string. Specify zero if you are not inquiring about character attributes.

The output from MQINQ is:

- A set of integer attribute values copied into the array. The number of values is determined by *IntAttrCount*. If either *IntAttrCount* or *SelectorCount* is zero, this parameter is not used.
- The buffer in which character attributes are returned. The length of the buffer is given by the *CharAttrLength* parameter. If either *CharAttrLength* or *SelectorCount* is zero, this parameter is not used.
- A completion code. If the completion code gives a warning, this means that the call completed only partially. In this case, you should examine the reason code.
- A reason code. There are three partial-completion situations:
  - The selector does not apply to the queue type
  - There is not enough space allowed for integer attributes
  - There is not enough space allowed for character attributes

If more than one of these situations arise, the first one that applies is returned.

Namelist can be inquired only on AIX, HP-UX, OS/2 Warp, OS/390, Sun Solaris, and Windows NT.

If you open a queue for output or inquire and it resolves to a non-local cluster queue you can only inquire the queue name, queue type, and common attributes. The values of the common attributes are those of the chosen queue if MQOO\_BIND\_ON\_OPEN was used. The values are those of an arbitrary one of the possible cluster queues if either MQOO\_BIND\_NOT\_FIXED was used or MQOO\_BIND\_AS\_Q\_DEF was used and the *DefBind* queue attribute was MQBND\_BIND\_NOT\_FIXED. See “MQI and clusters” in the *MQSeries Queue Manager Clusters* book for more information.

**Note:** The values returned by the call are a snapshot of the selected attributes. The attributes can change before your program acts on the returned values.

There is a description of the MQINQ call in “MQINQ - Inquire about object attributes” in the *MQSeries Application Programming Reference* manual.

---

## Some cases where the MQINQ call fails

If you open an alias to inquire about its attributes, you are returned the attributes of the alias queue (the MQSeries object used to access another queue) only, not those of the base queue. However, the definition of the base queue to which the alias resolves is also opened by the queue manager, and if another program changes the usage of the base queue in the interval between your MQOPEN and MQINQ calls, your MQINQ call fails and returns the MQRC\_OBJECT\_CHANGED reason code. The call also fails if the attributes of the alias queue object are changed.

Similarly, when you open a remote queue to inquire about its attributes, you are returned the attributes of the local definition of the remote queue only.

If you specify one or more selectors that are not valid for the type of queue about whose attributes you are inquiring, the MQINQ call completes with a warning and sets the output as follows:

- For integer attributes, the corresponding elements of *IntAttrs* are set to MQIAV\_NOT\_APPLICABLE.
- For character attributes, the corresponding portions of the *CharAttrs* string are set to asterisks.

If you specify one or more selectors that are not valid for the type of object about whose attributes you are inquiring, the MQINQ call fails and returns the MQRC\_SELECTOR\_ERROR reason code.

It is not possible to call MQINQ to look at a model queue. You will have to use either the MQSC facility or use the commands available on your platform.

---

### Setting queue attributes

You can set only the following queue attributes using the MQSET call:

- *InhibitGet* (but not for remote queues)
- *DistList*
- *InhibitPut*
- *TriggerControl*
- *TriggerType*
- *TriggerDepth*
- *TriggerMsgPriority*
- *TriggerData*

The MQSET call has the same parameters as the MQINQ call. However for MQSET, all parameters except the completion code and reason code are input parameters. There are no partial-completion situations.

**Note:** You cannot use the MQI to set the attributes of MQSeries objects other than locally-defined queues.

There is a description of the MQSET call in “MQSET - Set object attributes” in the *MQSeries Application Programming Reference* manual.

---

## Chapter 13. Committing and backing out units of work

This chapter describes how to commit and back out any recoverable get and put operations that have occurred in a unit of work. The following terms, described below, are used in this topic:

- Commit
- Back out
- Syncpoint coordination
- Syncpoint
- Unit of work
- Single-phase commit
- Two-phase commit

If you are familiar with these transaction processing terms, you can skip to “Syncpoint considerations in MQSeries applications” on page 184.

### Commit and back out

When a program puts a message on a queue within a unit of work, that message is made visible to other programs only when the program *commits* the unit of work. To commit a unit of work, *all* updates must be successful to preserve data integrity. If the program detects an error and decides that the put operation should not be made permanent, it can *back out* the unit of work. When a program performs a back out, MQSeries restores the message on the queue. The way in which the program performs the commit and back out operations depends on the environment in which the program is running.

Similarly, when a program gets a message from a queue within a unit of work, that message remains on the queue until the program commits the unit of work, but the message is not available to be retrieved by other programs. The message is permanently deleted from the queue when the program commits the unit of work. If the program backs out the unit of work, MQSeries restores the queue to the state it was in before the program performed the get operation.

Changes to queue attributes (either by the MQSET call or by commands) are not affected by the committing or backing out of units of work.

### Syncpoint coordination, syncpoint, unit of work

*Syncpoint coordination* is the process by which units of work are either committed or backed out with data integrity.

The decision to commit or back out the changes is taken, in the simplest case, at the end of a transaction. However, it can be more useful for an application to synchronize data changes at other logical points within a transaction. These logical points are called *syncpoints* (or *synchronization points*) and the period of processing a set of updates between two syncpoints is called a *unit of work*. Several MQGET calls and MQPUT calls can be part of a single unit of work.

### Single-phase commit

A *single-phase commit* process is one in which a program can commit updates to a queue without coordinating its changes with other resource managers.

### Two-phase commit

A *two-phase commit* process is one in which updates that a program has made to MQSeries queues can be coordinated with updates to other resources (for example, databases under the control of DB2). Under such a process, updates to **all** resources are committed or backed out together.

To help handle units of work, MQSeries provides the *BackoutCount* attribute. This is incremented each time a message, within a unit of work, is backed out. If the message repeatedly causes the unit of work to abend, the value of the *BackoutCount* finally exceeds that of the *BackoutThreshold*. This value is set when the queue is defined. In this situation, the application can choose to remove the message from the unit of work and put it onto another queue, as defined in *BackoutRequeueQName*. When the message is moved, the unit of work can commit.

---

## Syncpoint considerations in MQSeries applications

Two-phase commit is supported under:

- MQSeries for AIX
- MQSeries for HP-UX
- MQSeries for OS/2 Warp
- MQSeries for Sun Solaris
- MQSeries for Tandem NSK
- MQSeries for Windows NT
- CICS for MVS/ESA 4.1
- CICS Transaction Server for OS/390
- CICS on Open Systems
- TXSeries for Windows NT
- IMS/ESA
- OS/390 batch with RRS
- Other external coordinators using the X/Open XA interface

Single-phase commit is supported under:

- MQSeries for AS/400
- MQSeries for Digital OpenVMS
- MQSeries for OS/2 Warp
- MQSeries for Tandem NSK
- MQSeries on UNIX systems
- MQSeries for VSE/ESA
- MQSeries for Windows
- MQSeries for Windows NT
- CICS for OS/2
- CICS for Windows NT V2.0
- OS/390 batch

**Note:** For further details on external interfaces see “Interfaces to external syncpoint managers” on page 192, and the XA documentation *X/Open CAE Specifications Distributed Transaction Processing: The XA Specification*.

Transaction managers (such as CICS, IMS, Encina, and Tuxedo) can participate in two-phase commit, coordinated with other recoverable resources. This means that

the queuing functions provided by MQSeries can be brought within the scope of a unit of work, managed by the transaction manager.

Samples shipped with MQSeries show MQSeries coordinating XA-compliant databases. For further information about these samples, see Chapter 31, “Sample programs (all platforms except OS/390)” on page 327.

In your MQSeries application, you can specify on every put and get call whether you want the call to be under syncpoint control. To make a put operation operate under syncpoint control, use the MQPMO\_SYNCPOINT value in the *Options* field of the MQPMO structure when you call MQPUT. For a get operation, use the MQGMO\_SYNCPOINT value in the *Options* field of the MQGMO structure. If you do not explicitly choose an option, the default action depends on the platform. The syncpoint control default on OS/390 and Tandem NSK is ‘yes’; for all other platforms, it is ‘no’.

If a program issues the MQDISC call while there are uncommitted requests, an implicit syncpoint occurs. If the program ends abnormally, an implicit backout occurs. On OS/390, an implicit syncpoint occurs if the program ends normally without first calling MQDISC.

For MQSeries for OS/390 programs, you can use the MQGMO\_MARK\_SKIP\_BACKOUT option to specify that a message should not be backed out if backout occurs (in order to avoid an ‘MQGET-error-backout’ loop). For information about using this option, see “Skipping backout” on page 150.

For information on committing and backing out units of work in MQSeries for VSE/ESA, see the *MQSeries for VSE/ESA V2R1 System Management Guide*.

---

### Syncpoints in MQSeries for OS/390 applications

This section explains how to use syncpoints in transaction manager (CICS and IMS) and batch applications.

### Syncpoints in CICS Transaction Server for OS/390 and CICS for MVS/ESA applications

In a CICS application you establish a syncpoint by using the EXEC CICS SYNCPOINT command. To back out all changes to the previous syncpoint, you can use the EXEC CICS SYNCPOINT ROLLBACK command. For more information, see the *CICS Application Programming Reference* manual.

If other recoverable resources are also involved in the unit of work, the queue manager (in conjunction with the CICS syncpoint manager) participates in a two-phase commit protocol; otherwise, the queue manager performs a single-phase commit process.

If a CICS application issues the MQDISC call, no implicit syncpoint is taken. If the application closes down normally, any open queues are closed and an implicit commit occurs. If the application closes down abnormally, any open queues are closed and an implicit backout occurs.

### Syncpoints in IMS applications

In an IMS application, you establish a syncpoint by using IMS calls such as GU (get unique) to the IOPCB and CHKP (checkpoint). To back out all changes since the previous checkpoint, you can use the IMS ROLB (rollback) call. For more information, see the following books:

- *IMS/ESA Version 4 Application Programming: DLI Calls*
- *IMS/ESA Version 4 Application Programming: Design Guide*
- *IMS/ESA Version 5 Application Programming: Database Manager*
- *IMS/ESA Version 5 Application Programming: Design Guide*

The queue manager (in conjunction with the IMS syncpoint manager) participates in a two-phase commit protocol if other recoverable resources are also involved in the unit of work.

All open handles are closed by the IMS adapter at a syncpoint (except in a nonmessage batch-oriented BMP). This is because a different user could initiate the next unit of work and MQSeries security checking is performed when the MQCONN and MQOPEN calls are made, not when the MQPUT or MQGET calls are made. The handles are closed at the beginning of the MQI call following the IMS call which initiated the syncpoint.

If you have not installed IMS APAR PN83757, handles are also closed after a ROLB call unless you are running IMS Version 3 or are running a nonmessage BMP.

If an IMS application (either a BMP or an MPP) issues the MQDISC call, open queues are closed but no implicit syncpoint is taken. If the application closes down normally, any open queues are closed and an implicit commit occurs. If the application closes down abnormally, any open queues are closed and an implicit backout occurs.

### Syncpoints in OS/390 batch applications

For batch applications, you can use the MQSeries syncpoint management calls: MQCMIT and MQBACK. For backward compatibility, CSQBCMT and CSQBBAK are available as synonyms.

**Note:** If you need to commit or back out updates to resources managed by different resource managers, such as MQSeries and DB2, within a single unit of work you should use RRS. For further information see "Transaction management and recoverable resource manager services" on page 187.

#### Committing changes using the MQCMIT call

As input, you must supply the connection handle (*Hconn*), which is returned by the MQCONN call.

The output from MQCMIT is a completion code and a reason code. The call completes with a warning if the syncpoint was completed but the queue manager backed out the put and get operations since the previous syncpoint.

Successful completion of the MQCMIT call indicates to the queue manager that the application has reached a syncpoint and that all put and get operations made since the previous syncpoint are to be made permanent.

There is a description of the MQCMIT call in “MQCMIT - Commit changes” in the *MQSeries Application Programming Reference* manual.

### Backing out changes using the MQBACK call

As input, you must supply a connection handle (*Hconn*). Use the handle that is returned by the MQCONN call.

The output from MQBACK is a completion code and a reason code.

It indicates to the queue manager that the application has reached a syncpoint and that all gets and puts that have been made since the last syncpoint are to be backed out.

There is a description of the MQBACK call in “MQBACK - Back out changes” in the *MQSeries Application Programming Reference* manual.

### Transaction management and recoverable resource manager services

Transaction management and recoverable resource manager services (RRS) is an OS/390 facility to provide two-phase syncpoint support across participating resource managers. An application can update recoverable resources managed by various OS/390 resource managers such as MQSeries and DB2, and then commit or back out these updates as a single unit of work. RRS provides the necessary unit-of-work status logging during normal execution, coordinates the syncpoint processing, and provides appropriate unit-of-work status information during subsystem restart.

MQSeries for OS/390 RRS participant support enables MQSeries applications in the batch, TSO, and DB2 stored procedure environments to update both MQSeries and non-MQSeries resources (for example, DB2) within a single logical unit of work.

Your MQSeries application can use either MQCMIT and MQBACK or the equivalent RRS calls, SRRCMIT and SRRBACK. See “RRS batch adapter” on page 221 for more information.

**RRS availability:** If RRS is not active on your OS/390 system, any MQSeries call issued from a program linked with either RRS stub (CSQBRSTB or CSQBRRSI) returns MQRC\_ENVIRONMENT\_ERROR.

**DB2 stored procedures:** If you use DB2 stored procedures with RRS you must be aware of the following guidelines:

- DB2 stored procedures that use RRS must be WLM-managed.
- If a DB2-managed stored procedure contains MQSeries calls, and it is linked with either RRS stub (CSQBRSTB or CSQBRRSI), the MQCONN call returns MQRC\_ENVIRONMENT\_ERROR.
- If a WLM-managed stored procedure contains MQSeries calls, and is linked with a non-RRS stub, the MQCONN call returns MQRC\_ENVIRONMENT\_ERROR, unless it is the first MQSeries call executed since the stored procedure address space started.
- If your DB2 stored procedure contains MQSeries calls and is linked with a non-RRS stub, MQSeries resources updated in that stored procedure are not

committed until the stored procedure address space ends, or until a subsequent stored procedure does an MQCMIT (using an MQSeries Batch/TSO stub).

- Multiple copies of the same stored procedure can execute concurrently in the same address space. You should ensure that your program is coded in a reentrant manner if you want DB2 to use a single copy of your stored procedure. Otherwise you may receive MQRC\_HCONN\_ERROR on any MQSeries call in your program.
- You must not code MQCMIT or MQBACK in a WLM-managed DB2 stored procedure.
- All programs must be designed to run in Language Environment® (LE).

---

## Syncpoints in MQSeries for AS/400 applications

To start the AS/400 commitment control facilities, use the STRCMTCTL command.

**Note:** The default value of *Commitment definition scope* is \*ACTGRP. This must be defined as \*JOB for MQSeries for AS/400.

All MQSeries for AS/400 code runs in a single, named activation group: QMQM.

If you call MQPUT, MQPUT1 or MQGET, specifying MQPMO\_SYNCPOINT or MQGMO\_SYNCPOINT, when MQSeries for AS/400 is not registered as an API commitment resource inside your commitment definition, MQSeries for AS/400 adds itself to the definition. This is typically the first such call in a job. While there are any API commitment resources registered under a particular commitment definition, you cannot end commitment control for that definition.

MQSeries for AS/400 removes its registration, as an API commitment resource, when you disconnect from the queue manager, provided there are no pending MQI operations in the current unit of work. The precise mechanism used depends on how you connected to the queue manager:

- If you connected to the queue manager explicitly, using the CCTMQM command, you must issue the DSCMQM command to disconnect from the queue manager.
- If you connected to the queue manager explicitly, using the MQCONN call, you must issue an MQDISC call to disconnect from the queue manager.
- If you connected to the queue manager implicitly, by opening an object using the MQOPEN call without a previous MQCONN call, you must use the MQCLOSE call for each of the opened objects, to disconnect from the queue manager.

If you disconnect from the queue manager while there are pending MQPUT, MQPUT1 or MQGET operations in the current unit of work, MQSeries for AS/400 remains registered as an API commitment resource in order that it is notified of the next commit or rollback. When the next syncpoint is reached, MQSeries for AS/400 commits or rolls back the changes as required.

If you attempt to issue an ENDCMTCTL command for that commitment definition, message CPF8355 is issued, indicating that pending changes were active. This message also appears in the job log when the job ends. In order to avoid this situation, ensure that you commit or rollback all pending MQSeries for AS/400

operations, and that you disconnect from the queue manager. Thus, using commands COMMIT or ROLLBACK and DSCMQM before command ENDCMTCTL, should enable end-commitment-control to complete successfully.

To commit or rollback (otherwise backout) your unit of work, use one of the programming languages that supports the commitment control:

- CL commands: COMMIT and ROLLBACK
- ILE C Programming Functions: \_Rcommit and \_Rrollback

---

## Syncpoints in CICS for AS/400 applications

MQSeries for AS/400 participates in CICS for AS/400 units of work. You can use the MQI within a CICS for AS/400 application to put and get messages inside the current unit of work.

You can use the EXEC CICS SYNCPOINT command to establish a syncpoint that includes the MQSeries for AS/400 operations. To back out all changes up to the previous syncpoint, you can use the EXEC CICS SYNCPOINT ROLLBACK command.

If you use MQPUT, MQPUT1, or MQGET with the MQPMO\_SYNCPOINT, or MQGMO\_SYNCPOINT, option set in a CICS for AS/400 application, you cannot log off CICS for AS/400 until MQSeries for AS/400 has removed its registration as an API commitment resource. Therefore, you should commit or back out any pending put or get operations before you disconnect from the queue manager. This will allow you to log off CICS for AS/400.

---

## Syncpoints in MQSeries for OS/2 Warp, MQSeries for Windows NT, MQSeries for Digital OpenVMS, and MQSeries on UNIX systems

Syncpoint support operates on two types of units of work: local and global.

A *local* unit of work is one in which the only resources updated are those of the MQSeries queue manager. Here syncpoint coordination is provided by the queue manager itself using a single-phase commit procedure.

A *global* unit of work is one in which resources belonging to other resource managers, such as XA-compliant databases, are also updated. For full integrity, a two-phase commit procedure must be used. MQSeries can either coordinate such units of work itself or it can be coordinated by another XA-compliant transaction manager such as IBM CICS. CICS for OS/2, CICS Transaction Server for OS/2, and TXSeries for Windows NT all provide a single-phase commit procedure in which MQSeries can participate.

### Local units of work

Units of work that involve only the queue manager are called *local* units of work. Syncpoint coordination is provided by the queue manager itself (internal coordination) using a single-phase commit process.

To start a local unit of work, the application issues MQGET, MQPUT, or MQPUT1 requests specifying the appropriate syncpoint option. The unit of work is committed using MQCMIT or rolled back using MQBACK. However, the unit of work also

## Syncpointing

ends when the connection between the application and the queue manager is broken, whether intentionally or unintentionally.

If an application disconnects (MQDISC) from a queue manager while a unit of work is still active, the unit of work is committed. If, however, the application terminates without disconnecting, the unit of work is rolled back as the application is deemed to have terminated abnormally.

## Global units of work

Use global units of work when you also need to include updates to resources belonging to other resource managers. Here the coordination may be internal or external to the queue manager:

### Internal syncpoint coordination

*Queue manager coordination of global units of work is supported only on MQSeries Version 5 products. It is not supported in an MQSeries client environment.*

Here, the coordination is performed by MQSeries. To start a global unit of work, the application issues the MQBEGIN call. This allows the queue manager to coordinate its own updates in addition to those made by other resource managers.

As input to the MQBEGIN call, you must supply the connection handle (*Hconn*), which is returned by the MQCONN call. This represents the connection to the MQSeries queue manager.

Again, the application issues MQGET, MQPUT, or MQPUT1 requests specifying the appropriate 'syncpoint' option. This means that MQBEGIN can be used to initiate a global unit of work that updates local resources, resources belonging to other resource managers, or both. Updates made to resources belonging to other resource managers are made using the API of that resource manager. However, it is not possible to use the MQI to update queues that belong to other queue managers. MQCMIT or MQBACK must be issued before starting further units of work (local or global).

The global unit of work is committed using MQCMIT; this initiates a two-phase commit of all the resource managers involved in the unit of work. A two-phase commit process is used whereby resource managers (for example, XA-compliant database managers such as DB2, Oracle, and Sybase) are firstly all asked to prepare to commit. Only if all are prepared are they asked to commit. If any resource manager signals that it cannot commit, each is asked to back out instead. Alternatively, MQBACK can be used to roll back the updates of all the resource managers.

If an application disconnects (MQDISC) while a global unit of work is still active, the unit of work is committed. If, however, the application terminates without disconnecting, the unit of work is rolled back as the application is deemed to have terminated abnormally.

The output from MQBEGIN is a completion code and a reason code.

When MQBEGIN is used to start a global unit of work, all the external resource managers that have been configured with the queue manager are included.

However, the call starts a unit of work but completes with a warning if:

- There are no participating resource managers (that is, no resource managers have been configured with the queue manager)

or

- One or more resource managers are not available.

In these cases, the unit of work can include updates to only those resource managers that were available when the unit of work was started.

If one of the resource managers is unable to commit its updates, all of the resource managers are instructed to roll back their updates, and MQCMIT completes with a warning. In unusual circumstances (typically, operator intervention), an MQCMIT call may fail if some resource managers commit their updates but others roll them back; the work is deemed to have completed with a 'mixed' outcome. Such occurrences are diagnosed in the error log of the queue manager so remedial action may be taken.

An MQCMIT of a global unit of work succeeds if all of the resource managers involved commit their updates.

For a description of the MQBEGIN call, see "MQBEGIN - Begin unit of work" in the *MQSeries Application Programming Reference* manual.

### External syncpoint coordination

This is when a syncpoint coordinator other than MQSeries has been selected, for example CICS, Encina, or Tuxedo. In this situation, MQSeries for OS/2 Warp, MQSeries for Windows NT, and MQSeries on UNIX systems register their interest in the outcome of the unit of work with the syncpoint coordinator in order that they can commit or roll back any uncommitted get or put operations as required. The external syncpoint coordinator determines whether one- or two-phase commitment protocols are provided.

You can also use the Transaction Monitor supplied with the Version 5 products for external syncpoint coordination. You cannot use a transaction monitor with a client application.

When an external coordinator is used (that is, when you are in XA mode), MQCMIT, MQBACK, and MQBEGIN may not be issued. Calls to these functions fail with the reason code MQRC\_ENVIRONMENT\_ERROR.

The way in which an externally coordinated unit of work is started is dependent on the interface provided by the syncpoint coordinator. There may or may not be an explicit call required. If an explicit call is required, and you issue an MQPUT call specifying the MQPMO\_SYNCPOINT option when a unit of work is not started, the completion code MQRC\_SYNCPOINT\_NOT\_AVAILABLE is returned.

The scope of the unit of work is determined by the syncpoint coordinator. The state of the connection between the application and the queue manager affects the success or failure of MQI calls that an application issues, not the state of the unit of work. It is, for example, possible for an application to disconnect and reconnect to a queue manager during an active unit of work and perform further MQGET and MQPUT operations inside the same unit of work (a *pending disconnect*).

### Interfaces to external syncpoint managers

MQSeries on UNIX systems, MQSeries for OS/2 Warp, and MQSeries for Windows NT support coordination of transactions by external syncpoint managers which utilize the X/Open XA interface. This support is available only on server configurations. The interface is not available to client applications.

Some XA transaction managers (not CICS on Open Systems or Encina) require that each XA resource manager supplies its name. This is the string called name in the XA switch structure. The resource manager for MQSeries on UNIX systems is named "MQSeries\_XA\_RMI". For further details on XA interfaces refer to XA documentation *X/Open CAE Specifications Distributed Transaction Processing: The XA Specification*.

In an XA configuration, MQSeries on UNIX systems, MQSeries for OS/2 Warp, and MQSeries for Windows NT fulfil the role of an XA Resource Manager. An XA syncpoint coordinator can manage a set of XA Resource Managers, and synchronize the commit or backout of transactions in both Resource Managers. This is how it works for a statically-registered resource manager:

1. An application notifies the syncpoint coordinator that it wishes to start a transaction.
2. The syncpoint coordinator issues a call to any resource managers that it knows of, to notify them of the current transaction.
3. The application issues a call (for example MQGET in syncpoint) to the resource manager that is associated with the current transaction.
4. The application requests that the syncpoint coordinator either commit or roll back the transaction.
5. The syncpoint coordinator issues a call to each resource manager using two-phase commit protocols to complete the transaction as requested.

XA requires each Resource Manager to provide a structure called an *XA Switch*. This structure declares the capabilities of the Resource Manager, and the functions that are to be called by the syncpoint coordinator.

There are two versions of this structure:

<b>MQRMIASwitch</b>	Static XA resource management
<b>MQRMIASwitchDynamic</b>	Dynamic XA resource management

The structure is found in the following libraries:

<b>mqmxa.lib</b>	OS/2 and Windows NT XA library for Static resource management
<b>mqmenc.lib</b>	AIX, HP-UX, Sun Solaris, and Windows NT Encina XA library for Dynamic resource management
<b>libmqmxa.a</b>	UNIX systems XA library (non-threaded) for both Static and Dynamic resource management
<b>libmqmxa_r.a</b>	UNIX systems XA library (threaded) for both Static and Dynamic resource management

The method that must be used to link them to an XA syncpoint coordinator is defined by the coordinator, and you will need to consult the documentation provided

by that coordinator to determine how to enable MQSeries to cooperate with your XA syncpoint coordinator.

The *xa\_info* structure that is passed on any *xa\_open* call by the syncpoint coordinator should be the name of the queue manager that is to be administered. This takes the same form as the queue manager name passed to MQCONN, and may be blank if the default queue manager is to be used.

**Restrictions**

- On OS/2, all functions declared in the XA switch are declared as `_System` functions.
- On Windows NT, all functions declared in the XA switch are declared as `_cdecl` functions.
- Only one queue manager may be administered by an external syncpoint coordinator at a time. This is due to the fact that the coordinator has an effective connection to each queue manager, and is therefore subject to the rule that only one connection is allowed at a time.
- All applications that are run using the syncpoint coordinator can connect only to the queue manager that is administered by the coordinator because they are already effectively connected to that queue manager. They must issue MQCONN to obtain a connection handle and must issue MQDISC before they exit. Alternatively, they can use the CICS user exit 15 for CICS for OS/2 V2 and V3, and CICS for Windows NT V2, or the exit UE014015 for TXSeries for Windows NT V4 and CICS on Open Systems.

The features not implemented are:

- Association migration
- Asynchronous calls

Because CICS Transaction Server V4 is 32-bit, changes are required to the source of CICS user exits. The supplied samples have been updated to work with CICS Transaction Server V4 as shown in Table 8.

*Table 8. Linking MQSeries for OS/2 Warp with CICS Version 3 applications*

User exit	CICS V2 source	CICS V2 dll	TS V4 source	TS V4 dll
exit 15	amqzsc52.c	faaexp15.dll	amqzsc53.c	faaex315.dll
exit 17	amqzsc72.c	faaexp17.dll	amqzsc73.c	faaex317.dll

For CICS Transaction Server V4, the supplied user exits `faaex315.dll` and `faaex317.dll` should be renamed to the standard names `faaexp15.dll` and `faaexp17.dll`.

---

### Syncpoints in MQSeries for Tandem NSK applications

When using MQSeries for Tandem NSK transaction management is performed under the control of the Tandem TM/MP product, rather than by MQSeries itself.

The effects of this difference are:

- The default SYNCPOINT option for the MQPUT and MQGET calls is SYNCPOINT, rather than NO\_SYNCPOINT.
- To use the default (SYNCPOINT) option for MQPUT, MQGET, and MQPUT1 operations, the application must have an active TM/MP Transaction that defines the unit of work to be committed. An application initiates a TM/MP transaction by calling the BEGINTRANSACTION() function. All MQPUT, MQPUT1, and MQGET operations performed by the application while this transaction is active are within the same unit of work (transaction). Any other database operations performed by the application are also within this UOW. Note that there are system-imposed limits on the number and size of messages that can be written and deleted within a single TM/MP transaction. When the application has completed the UOW, the TM/MP transaction is ended (the UOW is committed) using the ENDTRANSACTION() function. If any error is encountered, the application can cancel the TM/MP transaction (backout the UOW) using the ABORTTRANSACTION() function. Consequently, the standard Version 2 functions MQCMIT() and MQBACK() are not supported on this product. If they are called, an error is returned.
- If an application uses the NO\_SYNCPOINT option for MQPUT, MQGET, and MQPUT1 operations, MQSeries starts a TM/MP transaction itself, performs the queuing operation, and commits the transaction before returning to the application. Each operation is therefore performed in its own UOW and, once complete, cannot be backed out by the application using TM/MP.
- A TM/MP transaction does not need to be active for MQI calls other than MQGET, MQPUT, and MQPUT1.
- Because TM/MP can cause previously performed MQGET, MQPUT, and MQPUT1 operations to be backed out without notification, the current queue-depth and input-and-output-open counts of queues can become inaccurate. The **cleanq** control command runs in the background to correct such inaccuracies, and each MQOPEN call corrects the value of these attributes on a queue if necessary. However, applications should be coded to be resilient to inaccuracies in these quantities, especially in an environment that may involve backed-out transactions.
- The back-out count attribute cannot be maintained in the same way as on standard Version 2 implementations. Also, the harden backout count attribute is not used.
- The MQRC\_SYNCPOINT\_LIMIT\_REACHED reason code is used by MQSeries for Tandem NSK V2.2 to inform an application that the system-imposed limit on the number of I/O operations within a single TM/MP transaction has been reached. If the application specified the SYNCPOINT option, it should cancel the transaction (back out the UOW) and retry with a smaller number of operations in that UOW.
- The MQRC\_UOW\_CANCELED reason code informs the application that the UOW (TM/MP transaction) has been canceled, either by the system itself

(TM/MP imposes some system-wide resource-usage thresholds that will cause this), by user action, or by the initiator of the transaction itself.

## General XA support

*This is not supported on Digital OpenVMS or Tandem NSK*

An XA switch load module is provided to enable you to link CICS with MQSeries on UNIX systems. Additionally, sample source code files are provided to enable you to develop the XA switches for other transaction messages. The names of the switch load modules provided are:

*Table 9. Essential Code for CICS applications*

Description	C (source)	C (exec) - add one of the following to your XAD.Stanza
XA initialization routine	amqzscix.c	amqzsc - CICS for AIX Version 2.1, amqzsc - TXSeries for AIX, Version 4.2, amqzsc - TXSeries for HP-UX, Version 4.2, amqzsc - CICS for Siemens Nixdorf SINIX Version 2.2, amqzsc - TXSeries for Sun Solaris, Version 4.2,
	amqzscin.c	mqmc4swi - TXSeries for Windows NT, Version 4.2



---

## Chapter 14. Starting MQSeries applications using triggers

*Triggering is not supported on MQSeries for Windows.*

Some MQSeries applications that serve queues run continuously, so they are always available to retrieve messages that arrive on the queues. However, this may not be desirable when the number of messages arriving on the queues is unpredictable. In this case, applications could be consuming system resources even when there are no messages to retrieve.

MQSeries provides a facility that enables an application to be started automatically when there are messages available to retrieve. This facility is known as *triggering*.

This chapter describes:

- What triggering is
- The prerequisites for using triggering
- The conditions that must exist for a trigger event to occur
- How to control trigger events
- How to design an application that uses triggered queues
- The properties of trigger messages
- What happens when triggering does not work

For information about triggering channels see “Triggering channels” in the *MQSeries Intercommunication* book.

---

### What is triggering?

The queue manager defines certain conditions as constituting “trigger events”. If triggering is enabled for a queue and a trigger event occurs, the queue manager sends a *trigger message* to a queue called an *initiation queue*. The presence of the trigger message on the initiation queue indicates that a trigger event has occurred.

Trigger messages generated by the queue manager are not persistent. This has the effect of reducing logging (thereby improving performance), and minimizing duplicates during restart, so improving restart time.

The program which processes the initiation queue is called a *trigger-monitor application*, and its function is to read the trigger message and take appropriate action, based on the information contained in the trigger message. Normally this action would be to start some other application to process the queue which caused the trigger message to be generated. From the point of view of the queue manager, there is nothing special about the trigger-monitor application—it is simply another application that reads messages from a queue (the initiation queue).

If triggering is enabled for a queue, you have the option to create a *process-definition object* associated with it. This object contains information about the application that processes the message which caused the trigger event. If the process definition object is created, the queue manager extracts this information and places it in the trigger message, for use by the trigger-monitor application. The name of the process definition associated with a queue is given by the *ProcessName*

local-queue attribute. Each queue can specify a different process definition, or several queues can share the same process definition.

On MQSeries Version 5 products, and MQSeries for AS/400 in the case of triggering a channel, you do not need to create a process definition object; the transmission queue definition is used instead. When a trigger event occurs, the transmission queue definition contains information about the application that processes the message which caused the event. Again, when the queue manager generates the trigger message, it extracts this information and places it in the trigger message.

On MQSeries for VSE/ESA, a trigger event is defined to activate the MQSeries trigger API Handler, that is, the MQ02 CICS Transaction. The trigger API handler executes a CICS LINK to the application program or a CICS START to the application transaction depending on whether you defined a program name or a transaction name in the queue definition. For more information, see the *MQSeries for VSE/ESA V2R1 System Management Guide*.

### Support in an MQSeries client environment

Triggering is supported by MQSeries clients in the UNIX systems, Digital OpenVMS, OS/2, Windows 3.1, Windows 95, and Windows NT environments. An application running in a client environment is the same as one running in a full MQSeries environment, only you link it with the client libraries. However the trigger monitor and the application to be started must both be in the same environment as one another.

Triggering involves:

#### Application queue

An *application queue* is a local queue, which, when it has triggering set on and when the conditions are met, requires that trigger messages are written.

#### Process Definition

An application queue can have a *process definition object* associated with it that holds details of the application that will get messages from the application queue. (See "Process definitions" on page 49 for a list of attributes.)

*On MQSeries Version 5 products, the process definition object is optional in the case of triggering channels.*

#### Transmission queue

The transmission queue holds the name of the channel to be triggered. This can replace the process definition for triggering channels, but is used only when a process definition is not created.

#### Trigger event

A *trigger event* is an event that causes a trigger message to be generated by the queue manager. This is usually a message arriving on an application queue, but it can also occur at other times (see "Conditions for a trigger event" on page 204). MQSeries has a range of options to allow you to control the conditions that cause a trigger event (see "Controlling trigger events" on page 208).

#### Trigger message

The queue manager creates a *trigger message* when it recognizes a trigger event (see "Conditions for a trigger event" on page 204). It copies into the

trigger message information about the application to be started. This information comes from the application queue and the process definition object associated with the application queue. Trigger messages have a fixed format (see “Format of trigger messages” on page 216).

**Initiation queue**

An *initiation queue* is a local queue on which the queue manager puts trigger messages. A queue manager can own more than one initiation queue, and each one is associated with one or more application queues.

**Trigger monitor**

A *trigger monitor* is a continuously-running program that serves one or more initiation queues. When a trigger message arrives on an initiation queue, the trigger monitor retrieves the message. The trigger monitor uses the information in the trigger message. It issues a command to start the application that is to retrieve the messages arriving on the application queue, passing it information contained in the trigger message header, which includes the name of the application queue. (For more information, see “Trigger monitors” on page 212.)

To understand how triggering works, consider Figure 14, which is an example of trigger type FIRST, (MQTT\_FIRST).




Figure 14. Flow of application and trigger messages

## Triggering

In Figure 14 on page 199, the sequence of events is:

1. Application A, which can be either local or remote to the queue manager, puts a message on the application queue. Note that no application has this queue open for input. However, this fact is relevant only to trigger type FIRST and DEPTH.
2. The queue manager checks to see if the conditions are met under which it has to generate a trigger event. They are, and a trigger event is generated, passing on information held within the associated process definition object.
3. The queue manager creates a trigger message and puts it on the initiation queue associated with this application queue, but only if an application (trigger monitor) has the initiation queue open for input.
4. The trigger monitor retrieves the trigger message from the initiation queue.
5. The trigger monitor issues a command to start program B (the server application).
6. Application B opens the application queue and retrieves the message.

### Notes:

1. If the application queue is open for input, by any program, and has triggering set for FIRST or DEPTH, no trigger event will occur - it's not needed.
2. If the initiation queue is not open for input, the queue manager will not generate any trigger messages, it will wait until an application opens the initiation queue for input.
3. Only use type FIRST or DEPTH when using triggering for channels.

So far, the relationship between the queues within triggering has been only on a one to one basis. Consider Figure 15 on page 201.




Figure 15. Relationship of queues within triggering

An application queue has a process definition object associated with it that holds details of the application that will process the message. The queue manager places the information in the trigger message, so only one initiation queue is necessary. The trigger monitor extracts this information from the trigger message and starts the relevant application to deal with the message on each application queue.

On MQSeries Version 5 products, in the case of triggering a channel, the process definition object is optional. The transmission queue definition can determine the channel to be triggered.

---

### Prerequisites for triggering

Before your application can take advantage of triggering, follow the steps below:

1. Either:

a. Create an initiation queue for your application queue. For example:

```
DEFINE QLOCAL (initiation.queue) REPLACE +
      LIKE (SYSTEM.DEFAULT.LOCAL.QUEUE) +
      DESCR ('initiation queue description')
```

or

b. Determine the name of a local queue that already exists and can be used by your application, and specify its name in the *InitiationQName* field of the application queue.

You can think of this task as associating the initiation queue with the application queue. A queue manager can own more than one initiation queue—you may want some of your application queues to be served by different programs, in which case you could use one initiation queue for each serving program, although you do not have to. Here is an example of how to create an application queue:

```
DEFINE QLOCAL (application.queue) REPLACE +
      LIKE (SYSTEM.DEFAULT.LOCAL.QUEUE) +
      DESCR ('appl queue description') +
      INITQ ('initiation.queue') +
      PROCESS ('process.name') +
      TRIGGER +
      TRIGTYPE (FIRST)
```

2. If you are triggering an application, create a process definition object to contain information relating to the application that is to serve your application queue.

For example:

```
DEFINE PROCESS (process.name) +
      REPLACE +
      DESCR ('process description') +
      APPLTYPE ('CICS') +
      APPLICID ('CKSG') +
      USERDATA ('EXAMPLE.CHANNEL')
```

Here is an extract from an MQSeries for AS/400 CL program that creates a process definition object:

```

/* Queue used by AMQSINQA */
      CRTMQMQ      QNAME('SYSTEM.SAMPLE.INQ')
                  QTYPE(*LCL) REPLACE(*YES)

                  TEXT('queue for AMQSINQA')
                  SHARE(*YES) /* Shareable */+
                  DFTMSGPST(*YES)/* Persistent messages OK */+

                  TRGENBL(*YES) /* Trigger control on */+
                  TRGTYPE(*FIRST)/* Trigger on first message*/+
                  PRCNAME('SYSTEM.SAMPLE.INQPROCESS')
                  INITQNAME('SYSTEM.SAMPLE.TRIGGER')

/* Process definition */
      CRTMQMPCRC  PRCNAME('SYSTEM.SAMPLE.INQPROCESS')
                  REPLACE(*YES)

                  TEXT('trigger process for AMQSINQA')
                  ENVDATA('JOBPTY(3)') /* Submit parameter */+
                  APPID('AMQSINQA') /* Program name */

```

When the queue manager creates a trigger message, it copies information from the attributes of the process definition object into the trigger message. This step is optional in the case of triggering channels.

Platform	To create a process definition object
UNIX systems, Digital OpenVMS, OS/2, Windows NT	Use DEFINE PROCESS or use SYSTEM.DEFAULT.PROCESS and modify using ALTER PROCESS
OS/390	Use DEFINE PROCESS (see sample code in step 2), or use the operations and control panels.
OS/400	Use a CL program like the extract from AMQSDEF4 in step 2.

3. If you are triggering a channel on a release other than MQSeries Version 5 products, MQSeries for AS/400, or MQSeries for VSE/ESA you need to create a process definition. Create a transmission queue definition and specify the *ProcessName* attribute as blanks. The *TrigData* attribute can contain the name of the channel to be triggered or it can be left blank. When the queue manager creates a trigger message, it copies information from the *TrigData* attribute of the transmission queue definition into the trigger message.
4. If you have created a process definition object, associate your application queue with the application that is to serve that queue by naming the process definition object in the *ProcessName* attribute of the queue.

Platform	Use commands
UNIX systems, Digital OpenVMS, OS/2, Windows NT	ALTER QLOCAL
OS/390	ALTER QLOCAL
AS/400	CHGMQMQ

5. Start instances of the trigger monitors (or trigger servers in MQSeries for AS/400) that are to serve the initiation queues you have defined. See “Trigger monitors” on page 212 for more information.

If you wish to be aware of any undelivered trigger messages, make sure your queue manager has a dead-letter (undelivered-message) queue defined. Specify the name of the queue in the *DeadLetterQName* queue manager field.

You can then set the trigger conditions you require, using the attributes of the queue object that defines your application queue. For more information on this, see “Controlling trigger events” on page 208.

---

### Conditions for a trigger event

The queue manager creates a trigger message when the following conditions are satisfied:

1. A message is **put** on a queue.
2. The message has a priority greater than or equal to the threshold trigger priority of the queue. This priority is set in the *TriggerMsgPriority* local queue attribute—if it is set to zero, any message qualifies.
3. The number of messages on the queue with priority greater than or equal to *TriggerMsgPriority* was previously, depending on *TriggerType*:
  - Zero (for trigger type MQTT\_FIRST)
  - Any number (for trigger type MQTT\_EVERY)
  - *TriggerDepth* minus 1 (for trigger type MQTT\_DEPTH)

**Note:** The queue manager counts both committed and uncommitted messages when it assesses whether the conditions for a trigger event exist. Consequently an application may be started when there are no messages for it to retrieve because the messages on the queue have not been committed. In this situation, you are strongly recommended to consider using the wait option, and relating the *WaitInterval* to the number of messages in the unit of work.

4. For triggering of type FIRST or DEPTH, no program has the application queue open for removing messages (that is, the *OpenInputCount* local queue attribute is zero).
5. On MQSeries for OS/390, if the application queue is one with a *Usage* attribute of MQUS\_NORMAL, get requests for it are not inhibited (that is, the *InhibitGet* queue attribute is MQQA\_GET\_ALLOWED). Also, on MQSeries for non-OS/390 platforms, if the application queue is one with a *Usage* attribute of MQUS\_XMITQ, get requests for it are not inhibited.

6. Either:

- The *ProcessName* local queue attribute for the queue is not blank, and the process definition object identified by that attribute has been created.

or

- The *ProcessName* local queue attribute for the queue is all blank, but the queue is a transmission queue. In this case, the trigger message contains attributes with the following values:

*ProcessName*: blanks

*TriggerData*: trigger data

*ApplType*: MQAT\_UNKNOWN  
*ApplId*: blanks  
*EnvData*: blanks  
*UserData*: blanks

**Note:** As the process definition is optional, the *TriggerData* attribute may also contain the name of the channel to be started. This option is available only on MQSeries for AS/400, OS/2, HP-UX, AIX, Sun Solaris, and Windows NT.

7. An initiation queue has been created, and has been specified in the *InitiationQName* local queue attribute. Also:
    - Get requests are not inhibited for the initiation queue (that is, the *InhibitGet* queue attribute is MQQA\_GET\_ALLOWED).
    - Put requests must not be inhibited for the initiation queue (that is, the *InhibitPut* queue attribute must be MQQA\_PUT\_ALLOWED).
    - The *Usage* attribute of the initiation queue must be MQUS\_NORMAL.
    - In environments where dynamic queues are supported, the initiation queue must not be a dynamic queue that has been marked as logically deleted.
  8. A trigger monitor currently has the initiation queue open for removing messages (that is, the *OpenInputCount* local queue attribute is greater than zero).
  9. The trigger control (*TriggerControl* local queue attribute) for the application queue is set to MQTC\_ON. To do this, set the *trigger* attribute when you define your queue, or use the ALTER QLOCAL command.
  10. The trigger type (*TriggerType* local queue attribute) is not MQTT\_NONE.
- If all of the above required conditions are met, and the message that caused the trigger condition is put as part of a unit of work, the trigger message does not become available for retrieval by the trigger monitor application until the unit of work completes, whether the unit of work is committed **or** backed out.
11. A suitable message is placed on the queue, for a *TriggerType* of MQTT\_FIRST or MQTT\_DEPTH, and the queue:
    - Was not previously empty (MQTT\_FIRST)

or

- Had *TriggerDepth* or more messages (MQTT\_DEPTH)

and conditions 2 through 10 (excluding 3) are satisfied, if in the case of MQTT\_FIRST a sufficient interval (*TriggerInterval* queue-manager attribute) has elapsed since the last trigger message was written for this queue.

This is to allow for a queue server that ends before processing all of the messages on the queue. The purpose of the trigger interval is to reduce the number of duplicate trigger messages that are generated.

**Note:** If you stop and restart the queue manager, the *TriggerInterval* “timer” is reset. There is a small window during which it is possible to produce two trigger messages. The window exists when the queue’s trigger attribute is set to enabled at the same time as a message arrives and the queue was not previously empty (MQTT\_FIRST) or had *TriggerDepth* or more messages (MQTT\_DEPTH).

## Trigger events

12. The only application serving a queue issues an MQCLOSE call, for a *TriggerType* of MQTT\_FIRST or MQTT\_DEPTH, and there is at least:

- One (MQTT\_FIRST)

or

- *TriggerDepth* (MQTT\_DEPTH)

messages on the queue of sufficient priority (condition 2 on page 204), and conditions 6 through 10 on page 205 are also satisfied.

This is to allow for a queue server that issues an MQGET call, finds the queue empty, and so ends; however, in the interval between the MQGET and the MQCLOSE calls, one or more messages arrive.

### Notes:

- a. If the program serving the application queue does not want to retrieve all the messages, this can cause a closed loop. Each time the program closes the queue, the queue manager creates another trigger message which causes the trigger monitor to start the server program again.
  - b. If the program serving the application queue backs out its get request (or if the program abends) before it closes the queue, the same happens.
  - c. To prevent such a loop occurring, you could use the *BackoutCount* field of MQMD to detect messages that are repeatedly backed out. For more information, see “Messages that are backed out” on page 35.
13. The following conditions are satisfied using MQSET or a command:

a.

- *TriggerControl* is changed to MQTC\_ON

or

- *TriggerControl* is already MQTC\_ON and the value of either *TriggerType*, *TriggerMsgPriority*, or *TriggerDepth* (if relevant) is changed,

and there is at least:

- One (MQTT\_FIRST or MQTT EVERY)

or

- *TriggerDepth* (MQTT\_DEPTH)

messages on the queue of sufficient priority (condition 2 on page 204), and conditions 4 through 10 on page 205 (excluding 8) are also satisfied.

This is to allow for an application or operator changing the triggering criteria, when the conditions for a trigger to occur are already satisfied.

- b. The *InhibitPut* queue attribute of an initiation queue changes from MQQA\_PUT\_INHIBITED to MQQA\_PUT\_ALLOWED, and there is at least:

- One (MQTT\_FIRST or MQTT EVERY)

or

- *TriggerDepth* (MQTT\_DEPTH)

messages of sufficient priority (condition 2 on page 204) on any of the queues for which this is the initiation queue, and conditions 4 through 10 on

page 205 are also satisfied. (One trigger message is generated for each such queue satisfying the conditions.)

This is to allow for trigger messages not being generated because of the MQQA\_PUT\_INHIBITED condition on the initiation queue, but this condition now having been changed.

- c. The *InhibitGet* queue attribute of an application queue changes from MQQA\_GET\_INHIBITED to MQQA\_GET\_ALLOWED, and there is at least:

- One (MQTT\_FIRST or MQTT EVERY)

or

- *TriggerDepth* (MQTT\_DEPTH)

messages of sufficient priority (condition 2 on page 204) on the queue, and conditions 4 through 10 on page 205, excluding 5, are also satisfied.

This allows applications to be triggered only when they are able to retrieve messages from the application queue.

- d. A trigger-monitor application issues an MQOPEN call for input from an initiation queue, and there is at least:

- One (MQTT\_FIRST or MQTT EVERY)

or

- *TriggerDepth* (MQTT\_DEPTH)

messages of sufficient priority (condition 2 on page 204) on any of the application queues for which this is the initiation queue, and conditions 4 through 10 on page 205 (excluding 8) are also satisfied, and no other application has the initiation queue open for input (one trigger message is generated for each such queue satisfying the conditions).

This is to allow for messages arriving on queues while the trigger monitor is not running, and for the queue manager restarting and trigger messages (which are nonpersistent) being lost.

**Note:** From step 12 (where trigger messages are generated as a result of some event other than a message arriving on the application queue), the trigger message is not put as part of a unit of work. Also, if the *TriggerType* is MQTT EVERY, and if there are one or more messages on the application queue, only one trigger message is generated.

14. MSGDLVSQ is set correctly.

If you set MSGDLVSQ=FIFO, messages are delivered to the queue in a First In First Out basis. The priority of the message is ignored and the default priority of the queue is assigned to the message. If *TriggerMsgPriority* is set to a higher value than the default priority of the queue, no messages are triggered. If *TriggerMsgPriority* is set equal to or lower than the default priority of the queue, triggering occurs for type FIRST, EVERY, and DEPTH. For information about these types, see the description of the *TriggerType* field under “Controlling trigger events” on page 208.

If you set MSGDLVSQ=PRIORITY and the message priority is equal to or greater than the *TriggerMsgPriority* field, messages only **count** towards a trigger event. In this case, again triggering occurs for type FIRST, EVERY, and DEPTH.

## Trigger events

As an example, if you put 100 messages of lower priority than the *TriggerMsgPriority*, the effective queue depth for triggering purposes is still zero. If you then put another message on the queue, but this time the priority is greater than or equal to the *TriggerMsgPriority*, the effective queue depth increases from zero to one and the condition for *TriggerType* FIRST is satisfied.

---

## Controlling trigger events

You control trigger events using some of the attributes that define your application queue. You can enable and disable triggering, and you can select the number or priority of the messages that count toward a trigger event. There is a full description of these attributes in “Attributes for local queues and model queues” in the *MQSeries Application Programming Reference* manual.

The relevant attributes are:

### *TriggerControl*

Use this attribute to enable and disable triggering for an application queue.

### *TriggerMsgPriority*

The minimum priority that a message must have for it to count toward a trigger event. If a message of priority less than *TriggerMsgPriority* arrives on the application queue, the queue manager ignores the message when it determines whether to create a trigger message. If *TriggerMsgPriority* is set to zero, all messages count toward a trigger event.

### *TriggerType*

In addition to the trigger type NONE (which disables triggering just like setting the *TriggerControl* to OFF), you can use the following trigger types to set the sensitivity of a queue to trigger events:

- |       |  |
|-------|--|
| EVERY | A trigger event occurs every time a message arrives on the application queue. Use this type of trigger if you want a serving program to process only one message, then end.  |
| FIRST | A trigger event occurs only when the number of messages on the application queue changes from zero to one. Use this type of trigger if you want a serving program to start when the first message arrives on a queue, continue until there are no more messages to process, then end. Also see “Special case of trigger type FIRST” on page 210. |
| DEPTH | A trigger event occurs only when the number of messages on the application queue reaches the value of the <i>TriggerDepth</i> attribute. A typical use of this type of triggering is for starting a program when all the replies to a set of requests are received.  |

**Triggering by depth**

With triggering by depth, the queue manager disables triggering (using the *TriggerControl* attribute) after it creates a trigger message. Your application must reenables triggering itself (by using the MQSET call) after this has happened.

The action of disabling triggering is not under syncpoint control, so triggering cannot be reenables simply by backing out a unit of work. If a program backs out a put request that caused a trigger event, or if the program abends, you must reenables triggering by using the MQSET call or the ALTER QLOCAL command.

*TriggerDepth*

The number of messages on a queue that causes a trigger event when using triggering by depth.

The conditions that must be satisfied for a queue manager to create a trigger message are described in “Conditions for a trigger event” on page 204.

**Example of the use of trigger type EVERY**

Consider an application that generates requests for motor insurance. The application might send request messages to a number of insurance companies, specifying the same reply-to queue each time. It could set a trigger of type EVERY on this reply-to queue so that each time a reply arrives, the reply could trigger an instance of the server to process the reply.

**Example of the use of trigger type FIRST**

Consider an organization with a number of branch offices that each transmit details of the day's business to the head office. They all do this at the same time, at the end of the working day, and at the head office there is an application that processes the details from all the branch offices. The first message to arrive at the head office could cause a trigger event which starts this application. This application would continue processing until there are no more messages on its queue.

**Example of the use of trigger type DEPTH**

Consider a travel agency application that creates a single request to confirm a flight reservation, to confirm a reservation for a hotel room, to rent a car, and to order some travelers' checks. The application could separate these items into four request messages, sending each to a separate destination. It could set a trigger of type DEPTH on its reply-to queue (with the depth set to the value 4), so that it is restarted only when all four replies have arrived.

If another message (possibly from a different request) arrives on the reply-to queue before the last of the four replies, the requesting application is triggered early. To avoid this, when DEPTH triggering is being used to collect multiple replies to a request, you should always use a new reply-to queue for each request.

### Special case of trigger type FIRST

With trigger type FIRST, if there is already a message on the application queue when another message arrives, the queue manager does not usually create another trigger message. However, the application serving the queue might not actually open the queue (for example, the application might end, possibly because of a system problem). If an incorrect application name has been put into the process definition object, the application serving the queue will not pick up any of the messages. In these situations, if another message arrives on the application queue, there is no server running to process this message (and any other messages on the queue).

To deal with this, the queue manager creates another trigger message if another message arrives on the application queue, but only if a predefined time interval has elapsed since the queue manager created the last trigger message for that queue. This time interval is defined in the queue manager attribute *TriggerInterval*. Its default value is 999 999 999 milliseconds.

You should consider the following points when deciding on a value for the trigger interval to be used in your application:

- If *TriggerInterval* is set to a low value, trigger type FIRST might behave like trigger type EVERY (this depends on the rate that messages are being put onto the application queue, which in turn may depend on other system activity). This is because, if the trigger interval is very small, another trigger message is generated each time a message is put onto the application queue, even though the trigger type is FIRST, not EVERY. (Trigger type FIRST with a trigger interval of zero is equivalent to trigger type EVERY.)
- If a unit of work is backed out (see “Trigger messages and units of work”) and the trigger interval has been set to a high value (or the default value), one trigger message is generated when the unit of work is backed out. However, if you have set the trigger interval to a low value or to zero (causing trigger type FIRST to behave like trigger type EVERY) many trigger messages can be generated. If the unit of work is backed out, all the trigger messages are still made available. The number of trigger messages generated depends on the trigger interval, the maximum number being reached when trigger interval has been set to zero.

---

## Designing an application that uses triggered queues

You have seen how to set up, and control, triggering for your applications. Here are some tips you should consider when you design your application.

### Trigger messages and units of work

Trigger messages created because of trigger events that are not part of a unit of work are put on the initiation queue, outside any unit of work, with no dependence on any other messages, and are available for retrieval by the trigger monitor immediately.

Trigger messages created because of trigger events that **are** part of a unit of work are put on the initiation queue as part of the same unit of work. Trigger monitors cannot retrieve these trigger messages until the unit of work completes. This applies whether the unit of work is committed or backed out.

If the queue manager fails to put a trigger message on an initiation queue, it will be put on the dead-letter (undelivered-message) queue.

**Note:** The queue manager counts both committed and uncommitted messages when it assesses whether the conditions for a trigger event exist.

With triggering of type FIRST or DEPTH, trigger messages are made available even if the unit of work is backed out so that a trigger message is always available when the required conditions are met. For example, consider a put request within a unit of work for a queue that is triggered with trigger type FIRST. This causes the queue manager to create a trigger message. If another put request occurs, from another unit of work, this does not cause another trigger event because the number of messages on the application queue has now changed from one to two, which does not satisfy the conditions for a trigger event. Now if the first unit of work is backed out, but the second is committed, a trigger message is still created.

However, this does mean that trigger messages are sometimes created when the conditions for a trigger event are *not* satisfied. Applications that use triggering must always be prepared to handle this situation. It is recommended that you use the wait option with the MQGET call, setting the *WaitInterval* to a suitable value.

## Getting messages from a triggered queue

When you design applications that use triggering, you must be aware that there may be a delay between a program being started by a trigger monitor, and other messages becoming available on the application queue. This can happen when the message that causes the trigger event is committed before the others.

To allow time for messages to arrive, always use the wait option when you use the MQGET call to remove messages from a queue for which trigger conditions are set. The *WaitInterval* should be sufficient to allow for the longest reasonable time between a message being put and that put call being committed. If the message is arriving from a remote queue manager, this time is affected by:

- The number of messages that are put before being committed
- The speed and availability of the communication link
- The sizes of the messages

For an example of a situation where you should use the MQGET call with the wait option, consider the same example we used when describing units of work. This was a put request within a unit of work for a queue that is triggered with trigger type FIRST. This event causes the queue manager to create a trigger message. If another put request occurs, from another unit of work, this does not cause another trigger event because the number of messages on the application queue has not changed from zero to one. Now if the first unit of work is backed out, but the second is committed, a trigger message is still created. So the trigger message is created at the time the first unit of work is backed out. If there is a significant delay before the second message is committed, the triggered application may need to wait for it.

With triggering of type DEPTH, a delay can occur even if all relevant messages are eventually committed. Suppose that the *TriggerDepth* queue attribute has the value 2. When two messages arrive on the queue, the second causes a trigger message to be created. However, if the second message is the first to be committed, it is at that time the trigger message becomes available. The trigger monitor starts the server program, but the program can retrieve only the second

## Trigger monitors

message until the first one is committed. So the program may need to wait for the first message to be made available.

You should design your application so that it terminates if no messages are available for retrieval when your wait interval expires. If one or more messages arrive subsequently, you should rely on your application being retriggered to process them. This method prevents applications being idle, and unnecessarily using resources.

---

## Trigger monitors

To a queue manager, a trigger monitor is like any other application that serves a queue. However, a trigger monitor serves initiation queues.

A trigger monitor is usually a continuously-running program. When a trigger message arrives on an initiation queue, the trigger monitor retrieves that message. It uses information in the message to issue a command to start the application that is to process the messages on the application queue.

The trigger monitor must pass sufficient information to the program it is starting so that the program can perform the right actions on the right application queue.

A channel initiator is an example of a special type of trigger monitor for message channel agents. In this situation however, you must use either trigger type FIRST or DEPTH.

## MQSeries for OS/390 trigger monitors

The following trigger monitor is provided for CICS Transaction Server for OS/390 and CICS for MVS/ESA:

**CKTI** You need to start one instance of CKTI for each initiation queue (see the *MQSeries for OS/390 System Management Guide* for information on how to do this). CKTI passes the MQTM structure of the trigger message to the program it starts by EXEC CICS START TRANSID. The started program gets this information by using the EXEC CICS RETRIEVE command. A program can use the EXEC CICS RETRIEVE command with the RTRANSID option to determine how the program was started; if the value returned is CKTI, the program was started by MQSeries for OS/390. For an example of how to use CKTI, see the source code supplied for module CSQ4CVB2 in the Credit Check sample application supplied with MQSeries for OS/390. See “The Credit Check sample” on page 430 for a full description.

The following trigger monitor is provided for IMS/ESA:

**CSQQTRMN** You need to start one instance of CSQQTRMN for each initiation queue (see the *MQSeries for OS/390 System Management Guide* for information on how to do this). CSQQTRMN passes the MQTMC2 structure of the trigger message to the programs it starts.

## MQSeries for AS/400 trigger monitors

The following are provided:

- AMQSTRG4** This is a trigger monitor that submits an OS/400 job for the process that is to be started, but this means there is a processing overhead associated with each trigger message.
- AMQSERV4** This is a trigger server. For each trigger message, this server runs the command for the process in its own job, and can call CICS transactions.

Both the trigger monitor and the trigger server pass an MQTMC structure to the programs they start. For a description of this structure, see “MQTMC2 - Trigger message 2 (character format)” in the *MQSeries Application Programming Reference* manual. Both of these samples are delivered in both source and executable forms.

## MQSeries for OS/2 Warp, Digital OpenVMS, Tandem NSK, UNIX systems, and Windows NT trigger monitors

The following trigger monitors are provided for the server environment:

- amqstrg0** This is a sample trigger monitor that provides a subset of the function provided by **runmqtrm**. See Chapter 31, “Sample programs (all platforms except OS/390)” on page 327 for more information on **amqstrg0**.
- runmqtrm** **runmqtrm** [-m *QMgrName*] [-q *InitQ*] is the command. The default is SYSTEM.DEFAULT.INITIATION.QUEUE on the default queue manager. It calls programs for the appropriate trigger messages. This trigger monitor supports the default application type.

The command string passed by the trigger monitor to the operating system is built as follows:

1. The *AppId* from the relevant PROCESS definition (if created)
2. The MQTMC2 structure, enclosed in quotation marks
3. The *EnvData* from the relevant PROCESS definition (if created)

where *AppId* is the name of the program to run - as it would be entered on the command line.

The parameter passed is the MQTMC2 character structure. A command string is invoked which has this string, exactly as provided, in ‘quotation marks’, in order that the system command will accept it as one parameter.

The trigger monitor will not look to see if there is another message on the initiation queue until the completion of the application it has just started. If the application has a lot of processing to do, this may mean that the trigger monitor cannot keep up with the number of trigger messages arriving. You have two options:

- Have more trigger monitors running
- Run the started applications in the background

If you choose to have more trigger monitors running you have control over the maximum number of applications that can run at

## Trigger monitors

any one time. If you choose to run applications in the background, there is no restriction imposed by MQSeries on the number of applications that can run.

To run the started application in the background under OS/2, or Windows NT, within the *AppId* field you must prefix the name of your application with a START command. For example:

```
START AMQSECHA /B
```

To run the started application in the background on UNIX systems, you must put an '&' at the end of the *EnvData* of the PROCESS definition.

The following trigger monitors are provided for the MQSeries client:

**runmqmtmc** This is the same as **runmqtrm** except that it links with the MQSeries client libraries.

### For CICS:

The following trigger monitor is provided for CICS:

**amqltmc0** The CICS Trigger monitor works in the same fashion as the standard trigger monitor, **runmqtrm**, but you run it in a different way and it triggers CICS transactions.

It is supplied as a CICS program and you must define it with a 4-character transaction name. Enter the 4-character name to start the trigger monitor. It uses the default queue manager (as named in the qm.ini file or, on MQSeries for Windows NT, the registry), and the SYSTEM.CICS.INITIATION.QUEUE.

If you want to use a different queue manager or queue, you must build the trigger monitor the MQTMC2 structure: this requires you to write a program using the EXEC CICS START call, because the structure is too long to add as a parameter. Then, pass the MQTMC2 structure as data to the START request for the trigger monitor.

When you use the MQTMC2 structure, you only need to supply the *StrucId*, *Version*, *QName*, and *QMgrName* parameters to the trigger monitor as it does not reference any other fields.

Messages are read from the initiation queue and used to start CICS transactions, using EXEC CICS START, assuming the APPL\_TYPE in the trigger message is MQAT\_CICS. The reading of messages from the initiation queue is performed under CICS syncpoint control.

Messages are generated when the monitor has started and stopped as well as when an error occurs. These messages are sent to the CSMT transient data queue.

Here are the available versions and appropriate use of the trigger monitor:

Version	Use
<b>amqltmc0</b>	CICS for OS/2 Version 2
	CICS for Windows NT Version 2

TXSeries for AIX, Version 4

**amqltmc3** CICS Transaction Server for OS/2, Version 4

**amqltmc4** TXSeries for Windows NT, Version 4

If you need a trigger monitor for other environments, you need to write a program that can process the trigger messages that the queue manager puts on the initiation queues. Such a program should:

1. Use the MQGET call to wait for a message to arrive on the initiation queue.
2. Examine the fields of the MQTM structure of the trigger message to find the name of the application to start and the environment in which it runs.
3. Issue an environment-specific start command. For example, in OS/390 batch, submit a job to the internal reader.
4. Convert the MQTM structure to the MQTMC2 structure if required.
5. Pass either the MQTMC2 or MQTM structure to the started application. This may contain user data.
6. Associate with your application queue the application that is to serve that queue. You do this by naming the process definition object (if created) in the *ProcessName* attribute of the queue.

Use DEFINE QLOCAL or ALTER QLOCAL. On AS/400 you can also use CRTMQMQ or CHGMQMQ.

For more information on the trigger monitor interface, see “MQTM - Trigger message” and “MQTMC2 - Trigger message 2 (character format)” in the *MQSeries Application Programming Reference* manual.

---

## Properties of trigger messages

The following sections describe some other properties of trigger messages.

### Persistence and priority of trigger messages

Trigger messages are not persistent as there is no requirement for them to be so. The conditions for generating triggering events are persistent, hence trigger messages will be generated whenever these conditions are met. In the event that a trigger message is lost, the continued existence of the application message on the application queue will guarantee that the queue manager will generate a trigger message as soon as all the conditions are met.

If a unit of work is rolled-back, any trigger messages it generated will always be delivered.

Trigger messages take the default priority of the initiation queue.

### Queue manager restart and trigger messages

Following the restart of a queue manager, when an initiation queue is next opened for input, a trigger message may be put to this initiation queue if an application queue associated with it has messages on it, and is defined for triggering.

### Trigger messages and changes to object attributes

Trigger messages are created according to the values of the trigger attributes in force at the time of the trigger event. If the trigger message is not made available to a trigger monitor until later (because the message that caused it to be generated was put within a unit of work), any changes to the trigger attributes in the meantime have no effect on the trigger message. In particular, disabling triggering does not prevent a trigger message being made available once it has been created. Also, the application queue may no longer exist at the time the trigger message is made available.

### Format of trigger messages

The format of a trigger message is defined by the MQTM structure. This has the following fields, which the queue manager fills when it creates the trigger message, using information in the object definitions of the application queue and of the process associated with that queue:

<i>StrucId</i>	The structure identifier.
<i>Version</i>	The version of the structure.
<i>QName</i>	The name of the application queue on which the trigger event occurred. When the queue manager creates a trigger message, it fills this field using the <i>QName</i> attribute of the application queue.
<i>ProcessName</i>	The name of the process definition object that is associated with the application queue. When the queue manager creates a trigger message, it fills this field using the <i>ProcessName</i> attribute of the application queue.
<i>TriggerData</i>	A free-format field for use by the trigger monitor. When the queue manager creates a trigger message, it fills this field using the <i>TriggerData</i> attribute of the application queue.
<i>ApplType</i>	The type of the application that the trigger monitor is to start. When the queue manager creates a trigger message, it fills this field using the <i>ApplType</i> attribute of the process definition object identified in <i>ProcessName</i> .
<i>ApplId</i>	A character string that identifies the application that the trigger monitor is to start. When the queue manager creates a trigger message, it fills this field using the <i>ApplId</i> attribute of the process definition object identified in <i>ProcessName</i> . When you use an MQSeries for OS/390-supplied trigger monitor (CKTI or CSQQTRMN) the <i>ApplId</i> attribute of the process definition object is a CICS or IMS transaction identifier.
<i>EnvData</i>	A character field containing environment-related data for use by the trigger monitor. When the queue manager creates a trigger message, it fills this field using the <i>EnvData</i> attribute of the process definition object identified in <i>ProcessName</i> . The MQSeries for OS/390-supplied trigger monitors (CKTI or CSQQTRMN) do not use this field, but other trigger monitors may choose to use it.
<i>UserData</i>	A character field containing user data for use by the trigger monitor. When the queue manager creates a trigger message, it fills this field using the <i>UserData</i> attribute of the process definition object identified in <i>ProcessName</i> .

There is a full description of the trigger monitor structures in “MQTM - Trigger message” and “MQTMC2 - Trigger message 2 (character format)” in the *MQSeries Application Programming Reference* manual.

---

## When triggering does not work

A program is not triggered if the trigger monitor cannot start the program or the queue manager cannot deliver the trigger message.

If a trigger message is created but cannot be put on the initiation queue (for example, because the queue is full or the length of the trigger message is greater than the maximum message length specified for the initiation queue), the trigger message is put instead on the dead-letter (undelivered-message) queue.

If the put operation to the dead-letter queue cannot complete successfully, the trigger message is discarded and a warning message is sent to the console (OS/390) or to the system operator (AS/400), or put on the error log. Note that putting these messages to the dead-letter (undelivered-message) queue does not cause trigger events for the DLQ on OS/400.

Putting the trigger message on the dead-letter queue may generate a trigger message for that queue. This second trigger message is discarded if it adds a message to the dead-letter queue.

If the program is triggered successfully but abends before it gets the message from the queue, use a trace utility (for example, CICS AUXTRACE if the program is running under CICS) to find out the cause of the failure.

## How CKTI detects errors

If the CKTI trigger monitor in MQSeries for OS/390 detects an error in the structure of a trigger message, or if it cannot start a program, it puts the trigger message on the dead-letter (undelivered-message) queue. CKTI adds a dead-letter header structure (MQDLH) to the trigger message. It uses a feedback code in the *Reason* field of this structure to explain why it put the message on the dead-letter (undelivered-message) queue.

An instance of CKTI stops serving an initiation queue if it attempts to get a trigger message from the queue and finds that the attributes of the queue have changed since it last accessed that queue. The attributes could have been changed by another program, or by an operator using the commands or operations and control panels of MQSeries. CKTI produces an error message, which includes a reason code, explaining the action it has taken.

## How CSQQTRMN detects errors

If the CSQQTRMN trigger monitor in MQSeries for OS/390 detects an error in the structure of a trigger message, or if it cannot start a program, it puts the trigger message on the dead-letter (undelivered-message) queue and sends a diagnostic message to a user specified LTERM (the default is MASTER). CSQQTRMN adds a dead-letter header structure (MQDLH) to the trigger message. It uses a feedback code in the *Reason* field of this structure to explain why it put the message on the dead-letter (undelivered-message) queue. If any other errors are detected, CSQQTRMN sends a diagnostic message to the specified LTERM, and then terminates.

### How RUNMQTRM detects errors

If the RUNMQTRM trigger monitor in MQSeries for OS/2 Warp and MQSeries on UNIX systems detects an error in either the:

- Structure of a trigger message
- Application type is unsupported

or it either:

- Cannot start a program
- Detects a data-conversion error

it puts the trigger message on the dead-letter (undelivered-message) queue, having added a dead-letter header structure (MQDLH) to the message. It uses a feedback code in the *Reason* field of this structure to explain why it put the message on the dead-letter (undelivered-message) queue.

## Chapter 15. Using and writing applications on MQSeries for OS/390

MQSeries for OS/390 applications can be made up from programs that run in many different environments. This means they can take advantage of the facilities available in more than one environment. This chapter explains the MQSeries facilities available to programs running in each of the supported environments.

### Environment-dependent MQSeries for OS/390 functions

The main differences to be considered between MQSeries functions in the environments in which MQSeries for OS/390 runs are:

- MQSeries for OS/390 supplies the following trigger monitors:
  - CKTI for use in the CICS environment
  - CSQQTRMN for use in the IMS environment

You must write your own module to start applications in other environments.

- Syncpointing using two-phase commit is supported in the CICS and IMS environments. It is also supported in the OS/390 batch environment using transaction management and recoverable resource manager services (RRS). Single-phase commit is supported in the OS/390 environment by MQSeries itself.
- For the batch and IMS environments, the MQI provides calls to connect programs to, and to disconnect them from, a queue manager. Programs can connect to more than one queue manager.
- A CICS system can connect to only one queue manager. This can be made to happen when CICS is initiated if the subsystem name is defined in the CICS system startup job. The MQI connect and disconnect calls are tolerated, but have no effect, in the CICS environment.
- The API-crossing exit allows a program to intervene in the processing of all MQI calls. This exit is available in the CICS environment only.
- In CICS on multiprocessor systems, some performance advantage is gained because MQI calls can be executed under multiple OS/390 TCBs. For more information, see the *MQSeries for OS/390 System Management Guide*.

These features are summarized in Table 10.

Table 10. OS/390 environmental features

	CICS	IMS	Batch/TSO
Trigger monitor supplied	Yes	Yes	No
Two-phase commit	Yes	Yes	Yes
Single-phase commit	Yes	No	Yes
Connect/disconnect MQI calls	Tolerated	Yes	Yes
API-crossing exit	Yes	No	No
<b>Note:</b> Two-phase commit is supported in the Batch/TSO environment using RRS.			

## Program debugging facilities

MQSeries for OS/390 provides a trace facility that you can use to debug your programs in all environments. Additionally, in the CICS environment you can use:

- The CICS Execution Diagnostic Facility (CEDF)
- The CICS Trace Control Transaction (CETR)
- The MQSeries for OS/390 API-crossing exit

On the OS/390 platform, you can use any available interactive debugging tool that is supported by the programming language you are using.

All these tools are discussed further in the *MQSeries for OS/390 System Management Guide*.

---

## Syncpoint support

The synchronization of the start and end of units of work is necessary in a transaction processing environment so that transaction processing can be used safely. This is fully supported by MQSeries for OS/390 in the CICS and IMS environments. Full support means cooperation between resource managers so that units of work can be committed or backed out in unison, under control of CICS or IMS. Examples of resource managers are DB2, CICS File Control, IMS, and MQSeries for OS/390.

OS/390 batch applications can use MQSeries for OS/390 calls to give a single-phase commit facility. This means that an application-defined set of queue operations can be committed, or backed out, without reference to other resource managers.

Two-phase commit is also supported in the OS/390 batch environment using transaction management and recoverable resource manager services (RRS). For further information see “Transaction management and recoverable resource manager services” on page 187.

---

## Recovery support

If the connection between a queue manager and a CICS or IMS system is broken during a transaction, some units of work may not be backed out successfully. However, these units of work are resolved by the queue manager (under the control of the syncpoint manager) when its connection with the CICS or IMS system is reestablished.

## The MQSeries for OS/390 interface with the application environment

To allow applications running in different environments to send and receive messages through a message queuing network, MQSeries for OS/390 provides an *adapter* for each of the environments it supports. These adapters are the interface between the application programs and an MQSeries for OS/390 subsystem. They allow the programs to use the MQI.

### The batch adapter

The *batch adapter* provides access to MQSeries for OS/390 resources for programs running in:

- Task (TCB) mode
- Problem or Supervisor state
- Primary address space control mode

The programs must not be in cross-memory mode.

Connections between application programs and MQSeries for OS/390 are at the task level. The adapter provides a single connection thread from an application task control block (TCB) to MQSeries for OS/390.

The adapter supports a single-phase commit protocol for changes made to resources owned by MQSeries for OS/390; it does not support multiphase-commit protocols.

### RRS batch adapter

The transaction management and recoverable resource manager services (RRS) adapter:

- Uses OS/390 RRS for commit control.
- Supports simultaneous connections to multiple MQSeries subsystems running on a single OS/390 instance from a single task.
- Provides OS/390-wide coordinated commitment control (using OS/390 RRS) for recoverable resources accessed by way of OS/390 RRS compliant recoverable managers for:
  - Applications that connect to MQSeries using the RRS batch adapter.
  - DB2 stored procedures executing in a DB2 stored procedures address space that is managed by an OS/390 workload manager (WLM).
- Supports the ability to switch an MQSeries batch thread between TCBs.

MQSeries for OS/390 V2.1 provides two RRS batch adapters:

#### **CSQBRSTB**

This adapter requires you to change any MQCMIT and MQBACK statements in your MQSeries application to SRRCMIT and SRRBACK respectively. (If you code MQCMIT or MQBACK in an application linked with CSQBRSTB, you will receive MQRC\_ENVIRONMENT\_ERROR.)

#### **CSQBRSI**

This adapter allows your MQSeries application to use either MQCMIT and MQBACK or SRRCMIT and SRRBACK.

## Migration

**Note:** CSQBRSTB and CSQBRRSI are shipped with linkage attributes AMODE(31) RMODE(ANY). If your application loads either stub below the 16 MB line, you must first relink the stub with RMODE(24).

### Migration

It is possible to migrate existing Batch/TSO MQSeries applications to exploit RRS coordination with few or no changes. If you link-edit your MQSeries application with the CSQBRRSI adapter, MQCMIT and MQBACK syncpoint your unit of work across MQSeries and all other RRS-enabled resource managers. If you link-edit your MQSeries application with the CSQBRSTB adapter you must change MQCMIT and MQBACK to SRRCMIT and SRRBACK respectively. The latter approach may be preferable as it clearly indicates that the syncpoint is not restricted to MQSeries resources only.

## The CICS adapter

A CICS system can have only one connection to an MQSeries for OS/390 queue manager, and this connection is managed by the MQSeries for OS/390 *CICS adapter*. The CICS adapter provides access to MQSeries for OS/390 resources for CICS programs. In addition to providing access to the MQI calls, the adapter provides:

- A trigger monitor (or task initiator) program that can start programs automatically when certain trigger conditions on a queue are met. For more information, see Chapter 14, “Starting MQSeries applications using triggers” on page 197.
- An API-crossing exit that can be invoked before and after each MQI call. For more information, see “The API-crossing exit for OS/390” on page 225.
- A trace facility to help you when debugging programs.
- Facilities that allow the MQI calls to be executed under multiple OS/390 TCBS. For more information, see the *MQSeries for OS/390 System Management Guide*.

The adapter supports a two-phase commit protocol for changes made to resources owned by MQSeries for OS/390, with CICS acting as the syncpoint coordinator.

The CICS adapter also supplies facilities (for use by system programmers and administrators) for managing the CICS-MQSeries for OS/390 connection, and for collecting task and connection statistics. These facilities are described in the *MQSeries for OS/390 System Management Guide*.

### Adapter trace points

Application programmers can use trace points related to the MQI calls—for example, CSQCGMGD (GET Message Data)—for debugging CICS application programs. System programmers can use trace points related to system events, such as recovery and task switching, for diagnosing system-related problems. For full details of trace points in the CICS adapter, see the *MQSeries for OS/390 Problem Determination Guide*.

Some trace data addresses are passed by applications. If the address of the trace data is in the private storage area of the CICS region, the contents of the area are traced when necessary. For example, this would be done for the trace entries CSQCGMGD (GET Message Data) or CSQCPMGD (PUT Message Data). If the

address is not in the private storage area, message CSQC416I is written to the CICS trace—this contains the address in error.

### Abends

This section describes some of the things you must consider with regard to CICS AEY9 and QLOP abends. For information about all other abends, see the *MQSeries for OS/390 Messages and Codes* manual.

**CICS AEY9 abends:** A transaction does *not* abend with a CICS AEY9 code if it issues an MQI call before the adapter is enabled. Instead, it receives return code MQCC\_FAILED and reason code MQRC\_ADAPTER\_NOT\_AVAILABLE.

For more information about CICS AEY9 abends, see the *CICS Messages and Codes* manual.

**QLOP abends:** Tasks abend with the abend code QLOP if a second MQI call is made after a call has been returned with completion code MQCC\_FAILED and one of these reason codes:

```
MQRC_CONNECTION_BROKEN
MQRC_Q_MGR_NAME_ERROR
MQRC_Q_MGR_NOT_AVAILABLE
MQRC_Q_MGR_STOPPING
MQRC_CONNECTION_STOPPING
MQRC_CONNECTION_NOT_AUTHORIZED
```

This runaway mechanism can be activated only after the adapter has been enabled once. Before the adapter has been enabled, such a task will loop with reason code set to MQRC\_ADAPTER\_NOT\_AVAILABLE. To avoid this, ensure that your applications respond to the above reason codes either by terminating abnormally or by issuing an EXEC CICS SYNCPOINT ROLLBACK and terminating normally.

If the application does not terminate at this point, it might not issue any further MQSeries calls even if the connection between MQSeries and CICS is re-established. Once MQSeries is reconnected to CICS, new transactions can use MQI calls as before.

### Using the CICS Execution Diagnostic Facility

You can use the CICS execution diagnostic facility (CEDF) to monitor applications that use the CICS adapter. For details of how to use CEDF, see the *CICS Application Programming Guide*.

CEDF uses standard formatting to display MQI calls.

- Before the MQI call is executed:
  - CEDF displays the addresses of the call parameters
  - You can use the Working Storage key to verify or modify their contents
  - You can skip the call by overtyping the command with NOOP
- After the call has completed:
  - The results are returned in the program's storage
  - The return code and reason code are displayed in the call parameter list
  - You can modify them before returning to the application program

See the *MQSeries for OS/390 Problem Determination Guide* for examples of the output produced by this facility.

## The IMS adapter

The *IMS adapter* provides access to MQSeries for OS/390 resources for

- On-line message processing programs (MPPs)
- Interactive Fast Path programs (IFPs)
- Batch message processing programs (BMPs)

To use these resources, the programs must be running in task (TCB) mode and problem state; they must not be in cross-memory mode or access-register mode.

The adapter provides a connection thread from an application task control block (TCB) to MQSeries. The adapter supports a two-phase commit protocol for changes made to resources owned by MQSeries for OS/390, with IMS acting as the syncpoint coordinator.

The adapter also provides a trigger monitor program that can start programs automatically when certain trigger conditions on a queue are met. For more information, see Chapter 14, “Starting MQSeries applications using triggers” on page 197.

If you are writing batch DL/I programs, follow the guidance given in this book for OS/390 batch programs.

---

## Writing OS/390 OpenEdition® applications

The batch adapter supports queue manager connections from Batch and TSO address spaces:

If we consider a Batch address space, the adapter supports connections from multiple TCBS within that address space as follows:

- Each TCB can connect to multiple queue managers using the MQCONN call (but a TCB can only have one instance of a connection to a particular queue manager at any one time).
- Multiple TCBS can connect to the same queue manager (but the queue manager handle returned on any MQCONN call is bound to the issuing TCB and cannot be used by any other TCB).

OS/390 OpenEdition supports two types of pthread\_create call:

1. Heavyweight threads, run one per TCB, that are ATTACHED and DETACHED at thread start and end by OS/390.
2. Mediumweight threads, run one per TCB, but the TCB can be one of a pool of long-running TCBS. The onus is on the application to perform all necessary application clean up, since, if it is connected to a server, the default thread termination that may be provided by the server at Task (TCB) termination, will **not** always be driven.

Lightweight threads are not supported. (If an application creates permanent threads which do their own dispatching of work requests, then the **application** is responsible for cleaning up any resources before starting the next work request.)

MQSeries for OS/390 supports OS/390 OpenEdition threads by way of the Batch Adapter as follows:

1. Heavyweight threads are fully supported as Batch connections.

Each thread runs in its own TCB which is ATTACHed and DETACHed at thread start and end. Should the thread end before issuing an MQDISC call, then MQSeries for OS/390 performs its standard task clean up which includes committing any outstanding unit of work if the thread terminated normally, or backing it out if the thread terminated abnormally.

2. Mediumweight threads are fully supported but if the TCB is going to be reused by another thread, then the application must ensure that an MQDISC call, preceded by either MQCMIT or MQBACK, is issued prior to the next thread start. This implies that if the application has established a Program Interrupt Handler, and the application then abends, then the Interrupt Handler should issue MQCMIT and MQDISC calls before reusing the TCB for another thread.

Again, lightweight threads are not supported.

**Note:** Threading models do *not* support access to common MQSeries resources from multiple threads.

---

## The API-crossing exit for OS/390

### Product-sensitive programming interface

An exit is a point in IBM-supplied code where you can run your own code. MQSeries for OS/390 provides an *API-crossing exit* that you can use to intercept calls to the MQI, and to monitor or modify the function of the MQI calls. This section describes how to use the API-crossing exit, and describes the sample exit program that is supplied with MQSeries for OS/390.

#### Note

The API-crossing exit is invoked only by the CICS adapter of MQSeries for OS/390. The exit program runs in the CICS address space.

### Using the API-crossing exit

You could use the API-crossing exit to:

- Operate additional security checks by examining the contents of each message before and after each MQI call
- Replace the queue name supplied in the message with another queue name
- Cancel the call and either issue a return code of 0 to simulate a successful call, or another value to indicate that the call was not performed
- Monitor the use of MQI calls in an application
- Gather statistics
- Modify input parameters on specific calls
- Modify the results of specific calls

### Defining the exit program

Before the exit can be used, an exit program load module must be available when the CICS adapter connects to MQSeries for OS/390. The exit program is a CICS program that must be named CSQCAPX and reside in a library in the DFHRPL concatenation. CSQCAPX must be defined in the CICS system definition file (CSD), and the program must be enabled.

When CSQCAPX is loaded, a confirmation message is written to the CKQC adapter control panel or to the console. If the program cannot be loaded, a diagnostic message is displayed.

### How the exit is invoked

When enabled, the API-crossing exit is invoked:

- By **all** applications that use the CICS adapter of MQSeries for OS/390
- For the following MQI calls:
  - MQCLOSE
  - MQGET
  - MQINQ
  - MQOPEN
  - MQPUT
  - MQPUT1
  - MQSET
- Every time one of these MQI calls is made
- Both before **and** after a call

This means that using the API-crossing exit degrades the performance of MQSeries for OS/390, so plan your use of it carefully.

The exit program can be invoked once **before** a call is executed, and once **after** the call is executed. On the before type of exit call, the exit program can modify any of the parameters on the MQI call, suppress the call completely, or allow the call to be processed. If the call is processed, the exit is invoked again after the call has completed.

**Note:** The exit program is not recursive. Any MQI calls made inside the exit do not invoke the exit program for a second time.

## Communicating with the exit program

After it has been invoked, the exit program is passed a parameter list in the CICS communication area pointed to by a field called DFHEICAP. The CICS Exec Interface Block field EIBCALEN shows the length of this area. The structure of this communication area is defined in the CMQXPA assembler-language macro that is supplied with MQSeries for OS/390 :

```

*
MQXP_COPYPLIST      DSECT
                    DS  0D          Force doubleword alignment
MQXP_PXPB           DS  AL4        Pointer to exit parameter block
MQXP_PCOPYPARAM     DS 11AL4      Copy of original plist
*
                    ORG  MQXP_PCOPYPARAM
MQXP_PCOPYPARAM1    DS  AL4        Copy of 1st parameter
MQXP_PCOPYPARAM2    DS  AL4        Copy of 2nd parameter
MQXP_PCOPYPARAM3    DS  AL4        Copy of 3rd parameter
MQXP_PCOPYPARAM4    DS  AL4        Copy of 4th parameter
MQXP_PCOPYPARAM5    DS  AL4        Copy of 5th parameter
MQXP_PCOPYPARAM6    DS  AL4        Copy of 6th parameter
MQXP_PCOPYPARAM7    DS  AL4        Copy of 7th parameter
MQXP_PCOPYPARAM8    DS  AL4        Copy of 8th parameter
MQXP_PCOPYPARAM9    DS  AL4        Copy of 9th parameter
MQXP_PCOPYPARAM10   DS  AL4        Copy of 10th parameter
MQXP_PCOPYPARAM11   DS  AL4        Copy of 11th parameter
*
MQXP_COPYPLIST_LENGTH EQU *-MQXP_PXPB
                    ORG  MQXP_PXPB
MQXP_COPYPLIST_AREA  DS  CL(MQXP_COPYPLIST_LENGTH)
*

```

Field *MQXP\_PXPB* points to the exit parameter block, MQXP.

Field *MQXP\_PCOPYPARAM* is an array of addresses of the call parameters. For example, if the application issues an MQI call with parameters P1,P2,or P3, the communication area contains:

```
PXPB,PP1,PP2,PP3
```

where *P* denotes a pointer (address) and XPB is the exit parameter block.

## Writing your own exit program

You can use the sample API-crossing exit program (CSQCAPX) that is supplied with MQSeries for OS/390 as a framework for your own program. This is described on page 229.

When writing an exit program, to find the name of an MQI call issued by an application, examine the *ExitCommand* field of the MQXP structure. To find the number of parameters on the call, examine the *ExitParmCount* field. You can use the 16-byte *ExitUserArea* field to store the address of any dynamic storage that the application obtains. This field is retained across invocations of the exit and has the same life time as a CICS task.

Your exit program can suppress execution of an MQI call by returning `MQXCC_SUPPRESS_FUNCTION` or `MQXCC_SKIP_FUNCTION` in the *ExitResponse* field. To allow the call to be executed (and the exit program to be reinvoked after the call has completed), your exit program must return `MQXCC_OK`.

When invoked after an MQI call, an exit program can inspect and modify the completion and reason codes set by the call.

### Usage notes

Here are some general points you should bear in mind when writing your exit program:

- For performance reasons, you should write your program in assembler language. If you write it in any of the other languages supported by MQSeries for OS/390, you must provide your own data definition file.
- Link-edit your program as `AMODE(31)` and `RMODE(ANY)`.
- To define the exit parameter block to your program, use the assembler-language macro, `CMQXPA`.
- If you are using the CICS Transaction Server for OS/390 storage protection feature, your program must run in CICS execution key. That is, you must specify `EXECKEY(CICS)` when defining both your exit program and any programs to which it passes control. For information about CICS exit programs and the CICS storage protection facility, see the *CICS Customization Guide*.
- Your program can use all the APIs (for example, IMS, DB2, and CICS) that a CICS task-related user exit program can use. It can also use any of the MQI calls except `MQCONN` and `MQDISC`. However, any MQI calls within the exit program do not invoke the exit program a second time.
- Your program can issue `EXEC CICS SYNCPOINT` or `EXEC CICS SYNCPOINT ROLLBACK` commands. However, these commands commit or roll back **all** the updates done by the task up to the point that the exit was used, and so their use is not recommended.
- Your program must end by issuing an `EXEC CICS RETURN` command. It must not transfer control with an `XCTL` command.
- Exits are written as extensions to the MQSeries for OS/390 code. You must take great care that your exit does not disrupt any MQSeries for OS/390 programs or transactions that use the MQI. These are usually indicated with a prefix of "CSQ" or "CK".
- If `CSQCAPX` is defined to CICS, the CICS system will attempt to load the exit program when CICS connects to MQSeries for OS/390. If this attempt is successful, message `CSQC301I` is sent to the `CKQC` panel or to the system console. If the load is unsuccessful (for example, if the load module does not exist in any of the libraries in the `DFHRPL` concatenation), message `CSQC315` is sent to the `CKQC` panel or to the system console.
- Because the parameters in the communication area are addresses, the exit program must be defined as local to the CICS system (that is, not as a remote program).

## The sample API-crossing exit program, CSQCAPX

The sample exit program is supplied as an assembler-language program. The source file (CSQCAPX) is supplied in the library **thlqual**.SCSQASMS (where **thlqual** is the high-level qualifier used by your installation). This source file includes pseudocode that describes the program logic.

The sample program contains initialization code and a layout that you can use when writing your own exit programs.

The sample shows how to:

- Set up the exit parameter block
- Address the call and exit parameter blocks
- Determine for which MQI call the exit is being invoked
- Determine whether the exit is being invoked before or after processing of the MQI call
- Put a message on a CICS temporary storage queue
- Use the macro DFHEIENT for dynamic storage acquisition to maintain reentrancy
- Use DFHEIBLK for the CICS exec interface control block
- Trap error conditions
- Return control to the caller

### Design of the sample exit program

The sample exit program writes messages to a CICS temporary storage queue (CSQ1EXIT) to show the operation of the exit. The messages show whether the exit is being invoked before or after the MQI call. If the exit is invoked after the call, the message contains the completion code and reason code returned by the call. The sample uses named constants from the CMQXPA macro to check on the type of entry (that is, before or after the call).

The sample does not perform any monitoring function, but simply places time-stamped messages into a CICS queue indicating the type of call it is processing. This provides an indication of the performance of the MQI, as well as the proper functioning of the exit program.

**Note:** The sample exit program issues six EXEC CICS calls for each MQI call that is made while the program is running. If you use this exit program, MQSeries for OS/390 performance is degraded.

### Preparing and using the sample exit

The sample exit is supplied in source form only.

- For CICS Transaction Server for OS/390 and CICS for MVS/ESA, when you update the CICS system definition (CSD) data set, the definitions you need are in the member **thlqual**.SCSQPROC(CSQ4B100).

## Writing CICS bridge applications

**Note:** The definitions use a suffix of MQ. If this suffix is already used in your enterprise, this must be changed before the assembly stage.

If you use the default CICS program definitions supplied, the exit program CSQCAPX is installed in a **disabled** state. This is because using the exit program can produce a significant reduction in performance.

To activate the API-crossing exit temporarily:

1. Issue the command CEMT S PROGRAM(CSQCAPX) ENABLED from the CICS master terminal.
2. Run the CKQC transaction, and use option 3 in the Connection pull-down to alter the status of the API-crossing exit to 'Enabled'.

If you want to run MQSeries for OS/390 with the API-crossing exit permanently enabled, do one of the following:

- For CICS Transaction Server for OS/390 and CICS for MVS/ESA do one of the following:
  - Alter the CSQCAPX definition in member CSQ4B100, changing STATUS(DISABLED) to STATUS(ENABLED). You can update the CICS CSD definition using the CICS-supplied batch program DFHCSDUP.
  - Alter the CSQCAPX definition in the CSQCAT1 group by changing the status from DISABLED to ENABLED.

In both cases you must reinstall the group. You can do this by cold-starting your CICS system or by using the CICS CEDA transaction to reinstall the group while CICS is running.

**Note:** Using CEDA may cause an error if any of the entries in the group are currently in use.

\_\_\_\_\_ End of Product-sensitive programming interface \_\_\_\_\_

---

## Writing MQSeries-CICS bridge applications

The CICS bridge is accessed by putting an MQSeries message on the request queue. The message can originate from any application running in an MQSeries environment, but it must be forwarded to a request queue on MQSeries for OS/390, defined for the sole use of the CICS bridge.

Within your request message you include the name of the user program or transaction that is to be run, and whether or not a response is needed. A response message can be put on a local or remote queue. One or more request messages make up a unit of work. The key attributes in a message used to identify and subsequently control a unit of work are *MsgId* and *CorrelId* in the MQSeries message descriptor (MQMD) and the *UOWControl* in the MQCIH header.

If your message originates from an application running in an MQSeries environment other than OS/390, you will need the appropriate header files and copybooks on that platform. These are shipped as part of SupportPac MA1E, and are available from the MQSeries product family Web site at:

<http://www.software.ibm.com/ts/mqseries/>

The files you need are:

- \include\cmqcbc.h – C header
- \include\cmqcihl.cbc – COBOL copybook
- \include\cmqcihv.cbc – COBOL copybook
- \include\cmqcbv.cbc – COBOL copybook

## Structure of the MQSeries message

The structure a DPL bridge message must take is:

1. MQMD (MQSeries message descriptor).
2. MQCIH (CICS bridge header). This is optional; see “Using the MQCIH header” on page 232 for more information about when the MQCIH header is mandatory.
3. Program name (8-character name of the CICS program to be started by the CICS bridge task).
4. Your own data (COMMAREA).

The structure a 3270 bridge message must take is:

1. MQMD (MQSeries message descriptor).
2. MQCIH (CICS bridge header).
3. BRMQ vectors. These contain any data required to run the application. For information about these vectors, see the *CICS Internet and External Interface Guide*.

The reply message has the same structure, although the BRMQ vectors are different.

### MQMD attributes

The message identifier (*MsgId*) and correlation identifier (*CorrelId*) attributes are used by the CICS bridge to identify a unit of work. The first request message must have a unique *MsgId* (unique to the request queue for a unit of work) and a *CorrelId* of MQCI\_NEW\_SESSION. It is important that each request within a unit of work, after the first message, has the same *CorrelId* and that this *CorrelId* is the same as the *MsgId* of the first request message.

When sending a response, the CICS bridge:

- Sets the *MsgId* field, in every message, to the value in the *MsgId* of the first message in a unit of work.
- Sets the *CorrelId* field to the value in the *MsgId* of the message it has just taken off the queue.

The setting of *MsgId* and *CorrelId* is shown in Figure 17 on page 236.

When the message includes an MQCIH header, you must set the *Format* field in the MQMD to MQFMT\_CICS. If you do not set it to this value, the CICS bridge assumes the message does not include the MQCIH header, hence expects the first 8 bytes of the *Userdata* to contain the name of the program to be run.

It is important that you specify a reply-to queue (*ReplyToQ*) if you want response messages from the CICS bridge.

When returning messages to the reply-to queue, the CICS bridge sets the *MsgType* field (in the MQMD) to MQMT\_REQUEST until it is the last message in a unit of work, when it is set to MQMT\_REPLY.

### Attention

MQMT\_REQUEST messages from the CICS bridge refer to the results of intermediate processing within a unit of work which could be backed out after the message is sent.

### Using the MQCIH header

The MQCIH is required if you want to do one of the following:

- Run a 3270 transaction
- Run the bridge with AUTH=VERIFY\_\*
- Include more than one program within a single unit of work

It is not required if you want to run a single DPL program where AUTH is set to LOCAL or IDENTIFY.

### Messages returned from the CICS bridge

The CICS bridge puts response messages to the reply-to queue specified in the MQMD of the request message. All replies within a unit of work will go to the first reply-to queue specified in a request message for that unit of work, even if subsequent request messages within the unit of work specify different reply-to queues. If a message does not specify a reply-to queue, no reply message is sent unless a previous request message within the unit of work specified a reply-to queue. Reply messages are not sent for any messages within a unit of work that occur before the first message that specifies a reply-to queue name.

The response message contains the following:

- For normal responses to DPL requests:
  - An MQCIH (if one was present in the request message)
  - The program name
  - The return COMMAREA
- For error responses to DPL requests:
  - An MQCIH (even if one was not present in the request message)
  - Error text
- For responses to 3270 requests:
  - An MQCIH
  - Zero or more BRMQ vectors

As error replies sent by the monitor always have a *CorrelId* set from the *MsgId* from the first request message, when your application gets a response message it should issue an MQGET by *MsgId* call, and check the *CorrelId* where the order is important, to ensure you pick up the correct message.

## Error handling by the CICS bridge

Errors detected by the CICS bridge task cause the bridge to:

- Back out the unit of work.
- Copy the request message(s) to the dead-letter queue.
- Send an error reply message back to the client if a reply-to queue is specified.
- Write a CSQC7nn message to the CICS CSMT transient data queue or issue a transaction abend. Where it is possible to put a message on the reply-to queue, the message will contain this abend code.

Any further request messages in the same unit of work are removed from the request queue and copied to the dead-letter queue, either during error processing for this unit of work or at the next initialization of the monitor; no further error reply messages are generated.

Unexpected messages are removed from the request queue during monitor initialization and put on the dead-letter queue passing all context. No error reply messages are generated.

If the sending of a reply message fails, the CICS bridge puts the reply on the dead-letter queue passing identity context from the CICS bridge request queue. A unit of work is not backed out if the reply message is successfully put on the dead-letter queue. Failure to put a reply message on the dead-letter queue is treated as a request error, and the unit of work is backed out.

If the CICS bridge fails to put a request message on the dead-letter queue, the CICS bridge task abends and leaves the CICS bridge monitor to process the error. If the monitor fails to copy the request to the dead-letter queue, the monitor abends.

Failure to put an error reply is ignored by the CICS bridge; the request message has already been copied to the dead-letter queue and the unit of work has been backed out by MQSeries.

CICS bridge specific abend codes are described in *MQSeries for OS/390 Messages and Codes*.

## Handling a unit of work

You can request the bridge to run a single transaction or program, by setting `UOWControl=MQCUOWC_ONLY` in the request message, or allowing it to default.

To run multiple user programs within a unit of work, set `UOWControl=MQCUOWC_FIRST` in the first request, `MQCUOWC_MIDDLE` in any intermediate requests and `MQCUOWC_LAST` in the last request. Your application can send multiple request messages within a unit of work before receiving any response messages. At any time after the first message you can terminate the unit of work by sending an `MQCUOWC_COMMIT` or `MQCUOWC_BACKOUT` message.

A transaction can split itself into multiple units of work by issuing EXEC CICS SYNCPOINT, but you cannot group transactions into a single unit of work. Set `UOWControl=MQCUOWC_ONLY` in the first request message. Messages supplying additional data to the transaction should be set to `MQCUOWC_CONTINUE`, with an appropriate `CancelCode` if you want to terminate the transaction.

A unit of work must only use **one** request queue.

### Programming considerations for running 3270 transactions

This section describes the MQSeries specific aspects of programming for 3270 transactions. See the *CICS Internet and External Interfaces Guide* for a description of the programming interface.

If the MQSeries application is on a platform other than OS/390, it will be necessary for the BRMQ vectors to be translated between the CCSID and encoding used on OS/390 and that used on the local platform. This causes a problem for the bridge because the BMS application data structure (ADS) consists of binary values that are not fullword values. To overcome this problem, the CICS bridge exit (CSQCBE00) converts its various ADSs into long formats which are fullword values. The MQSeries application can use either the normal variables or the long formats as appropriate. BMS vectors can be converted to the long format, but 3270 data stream vectors cannot.

The BRMQ BMS vectors contain the application data structure (ADS). The format of the ADS can be determined in one of two ways:

1. Using the BMS copybooks

If the long form of the ADS is required, it will be necessary to generate a special version of the BMS copybook. This is done by adding the parameter DSECT=ADSL to the DFHMSD statement on the BMS map. The copybook can then be used in exactly the same way as a normal copybook, except that the fields are fullwords. Currently, only the C headers are supported.

2. Using the application data structure descriptors (ADSDs)

If application data structures are referred to using ADSDs, note that there are two forms of ADS variables in the DFHBRMQx copybook:

- BRMQ\_ADSI\_\* and BRMQ\_ADSO\_\* refer to the ADS contents in the normal form of the ADS
- BRMQ\_ADSLI\_\* and BRMQ\_ADSLO\_\* refer to the ADS contents in the long form of the ADS


The following MQCIH values must be set when using cross platform conversion:

- *Format* must be set to "CSQCBDCI"
- *Adsdescriptor* must be set to:  
MQCADSD\_SEND+MQCADSD\_RECV+MQCADSD\_MSGFORMAT

### Examples

The following examples show the setting of key fields in different scenarios, and what happens in the event of a failure.

In Figure 16 on page 235, running one user program or transaction, the *MsgId* of the request message is set by the queue manager (to M1), and subsequently copied to the *CorrelId* in the reply message.



| Figure 16. Setting of key fields for a single CICS user program in a unit of work, or non-conversational 3270  
 | transaction

## Examples

In Figure 17, running more than one user program, the *MsgId* of the request message is set by the queue manager (to M1), and subsequently copied to the *CorrelId*.




Figure 17. Setting of key fields for many CICS user programs in a unit of work

Figure 18 shows a conversational 3270 transaction.




Figure 18. Setting of key fields: MQSeries - conversational 3270 transaction

## Examples

The following example shows what happens when an error occurs in a unit of work.




Figure 19. User program abends (only program in the unit of work)

In this example:

- The client application sends a request message to run a CICS program named P1.

The queue manager used by the client receives the message. If the queue is not on OS/390, the queue needs to be defined as a remote queue with transmission queue. The final destination queue must be on OS/390 in the same image as the CICS bridge.

The monitor task browses the request queue awaiting the arrival of a message:

- Gets the request message with browse
- Checks for any problems with the request message
- Starts a CICS bridge task
- Continues browsing the request queue

The CICS bridge task:

- Gets the request message, under syncpoint control, from the request queue
- Takes the information in the request message and builds a COMMAREA for program P1

- Issues an EXEC CICS LINK call to program P1
- Waits for program P1 to complete

When these tasks are complete, the user program abends.

The CICS bridge task abend handler, CSQCBP10, is driven which:

- Issues an EXEC CICS SYNCPOINT ROLLBACK which:
  - Backs out all the changes made by P1
  - Reinstates the request message on the request queue
- Gets the request message a second time, under syncpoint control, from the request queue
- Copies the request to the dead-letter queue
- Puts an error reply to the reply-to queue

If the request message includes the name of a reply-to queue:

- Writes a CSQC7nn message to the CICS transient data queue

For information on feedback codes, including those specific to the CICS bridge, see “MQMD - Message descriptor” in the *MQSeries Application Programming Reference* manual.

---

## Writing MQSeries-IMS bridge applications

This section discusses writing applications to exploit the MQSeries-IMS bridge. The following topics are discussed:

- “How the MQSeries-IMS bridge deals with messages”
- “Writing your program” on page 243
- “Triggering” on page 245

For information about the MQSeries-IMS bridge, see the *MQSeries for OS/390 System Management Guide*.

## How the MQSeries-IMS bridge deals with messages

When you use the MQSeries-IMS bridge to send messages to an IMS application, you need to construct your messages in a special format. You must also put your messages on MQSeries queues that have been defined with a storage class that specifies the XCF group and member name of the target IMS system.

A user does not need to sign on to IMS before sending messages to an IMS application. The user ID in the *UserIdentifier* field of the MQMD structure is used for security checking. The level of checking is determined when MQSeries connects to IMS, and is described in the security section of the *MQSeries for OS/390 System Management Guide*.

The MQSeries-IMS bridge accepts the following types of message:

- Messages containing IMS transaction data and an MQIIH structure (described in “MQIIH - IMS bridge header” in the *MQSeries Application Programming Reference* manual):

```
MQIIH LLZZ<trancode><data>[LLZZ<data>][LLZZ<data>]
```

### Notes:

1. The square brackets, [ ], represent optional multi-segments.
  2. The *Format* field of the MQMD structure must be set to MQFMT\_IMS to use the MQIIH structure.
- Messages containing IMS transaction data but no MQIIH structure:

```
LLZZ<trancode><data> \
[LLZZ<data>] [LLZZ<data>]
```

MQSeries validates the message data to ensure that the sum of the LL bytes is equal to the message length after the MQIIH structure (if it is present).

When the MQSeries-IMS bridge gets messages from the OTMA queues, it processes them as follows:

- If the message contains IMS transaction data and an MQIIH structure the bridge verifies the MQIIH (see “MQIIH - IMS bridge header” in the *MQSeries Application Programming Reference* manual) and puts the message on to the appropriate IMS queue. The transaction code is specified in the input message. If this is an LTERM, IMS replies with a DFS1288E message. If the transaction code represents a command, IMS executes the command.
- If the message contains IMS transaction data, but no MQIIH structure, the IMS bridge makes the following assumptions:
  - The transaction code is in bytes 5 through 12 of the user data
  - The transaction is in non-conversational mode
  - The transaction is in commit mode 0 (commit-then-send)
  - The *Format* in the MQMD is used as the *MFSMapName* (on input)
  - The security mode is MQISS\_CHECK

The reply message is also built without an MQIIH structure, taking the *Format* for the MQMD from the *MFSMapName* of the IMS output.

The MQSeries-IMS bridge uses one or two Tpipes for each MQSeries queue:

- A synchronous Tpipe is used for all messages using Commit mode 0 (COMMIT\_THEN\_SEND) (these show with SYN in the status field of the IMS /DIS TMEMBER client TPIPE xxxx command)
- An asynchronous Tpipe is used for all messages using Commit mode 1 (SEND\_THEN\_COMMIT)

The Tpipes are created by MQSeries when they are first used. An asynchronous Tpipe exists until IMS is restarted. Synchronous Tpipes exist until IMS is cold started.

## Mapping MQSeries messages to IMS transaction types

MQSeries message type	Commit-then-send (mode 0) - uses synchronous IMS Tpipes	Send-then-commit (mode 1) - uses asynchronous IMS Tpipes
Persistent MQSeries messages	<ul style="list-style-type: none"> <li>Recoverable full function transactions</li> <li>Irrecoverable transactions are rejected by IMS</li> </ul>	<ul style="list-style-type: none"> <li>Fastpath transactions</li> <li>Conversational transactions</li> <li>Full function transactions</li> </ul>
Nonpersistent MQSeries messages	<ul style="list-style-type: none"> <li>Irrecoverable full function transactions</li> <li>Recoverable transactions are rejected by IMS</li> </ul>	<ul style="list-style-type: none"> <li>Fastpath transactions</li> <li>Conversational transactions</li> <li>Full function transactions</li> </ul>

**Note:** IMS commands cannot use persistent MQSeries messages with commit mode 0. See the *IMS/ESA Open Transaction Manager Access User's Guide* for more information.

### If the message cannot be put to the IMS queue

If the message cannot be put to the IMS queue, the following action is taken by MQSeries:

- If a message cannot be put to the IMS queue because the message is invalid, the message is put to the dead-letter queue and a message is sent to the system console.
- If the message is valid, but is rejected by IMS with a sense code of 001A and a DFS message, MQSeries puts the original message to the dead-letter queue, and puts the DFS message to the reply-to queue. If MQSeries is unable to put the DFS message to the reply-to queue, it is put to the dead-letter queue.
- If the negative acknowledgement (NAK) from IMS represents a message error, an error message is sent to the system console, and the MQSeries message is put to the dead-letter queue.

**Note:** In the circumstances listed above, if MQSeries is unable to put the message to the dead-letter queue for any reason, the message is returned to the originating MQSeries queue. An error message is sent to the system console, and no further messages are sent using the Tpipe associated with that queue until the problem with the dead-letter queue has been resolved.

To resend the messages, do **one** of the following:

1. Stop and restart the Tpipes in IMS corresponding to the queue
2. Alter the queue to GET(DISABLED), and again to GET(ENABLED)
3. Stop and restart the IMS OTMA
4. Stop and restart your MQSeries subsystem

If the NAK received from IMS represents anything else, the MQSeries message is returned to the originating queue, MQSeries stops processing the queue, and an error message is sent to the system console.

If an exception report message is required, the bridge puts it to the reply-to queue with the authority of the originator. If the message cannot be put to the queue, the report message is put to the dead-letter queue with the authority of the bridge. If it cannot be put to the DLQ, it is discarded.

### IMS bridge feedback codes

The IMS bridge feedback codes are in the range 301 through 399. They are mapped from the IMS-OTMA sense codes as follows:

1. The IMS-OTMA sense code is converted from a hexadecimal number to a decimal number.
2. 300 is added to the number resulting from the calculation in 1, giving the MQSeries *Feedback* code.

Refer to the *IMS/ESA Open Transaction Manager Access Guide* for information about IMS-OTMA sense codes.

### Reply messages from IMS

Reply messages from IMS are put onto the reply-to queue specified in the original message. If the message cannot be put onto the reply-to queue, it is put onto the dead-letter queue using the authority of the bridge. If the message cannot be put onto the dead-letter queue, a negative acknowledgement is sent to IMS to say that the message cannot be received. Responsibility for the message is then returned to IMS. If you are using commit mode 0, messages from that Tpipe are not sent to the bridge, and remain on the IMS queue; that is, no further messages are sent until restart. If you are using commit mode 1, other work can continue.

If the reply has an MQIIH structure, its format type is MQFMT\_IMS; if not, its format type is specified by the IMS MOD name used when inserting the message.

**Using alternate response PCBs:** If your IMS application uses alternate response PCBs, invoking these applications through the MQSeries-IMS bridge will cause the IMS pre-routing and destination resolution exits to be called. See the *MQSeries for OS/390 System Management Guide* for information about these exit programs.

### Message segmentation

IMS transactions may be defined as expecting single- or multi-segment input. The originating MQSeries application must construct the user input following the MQIIH structure as one or more LLZZ-data segments. All segments of an IMS message must be contained in a single MQSeries message sent with a single MQPUT.

The maximum length of any one LLZZ-data segment is defined by IMS/OTMA (32764 bytes). The total MQSeries message length is the sum of the LL bytes, plus the length of the MQIIH structure.

All the segments of the reply are contained in a single MQSeries message.

### Data conversion

The MQSeries-IMS bridge converts messages to the coded character set and encoding of the local queue manager as required, using both *built-in* formats and user exit programs. This means that you can send messages to an IMS application using the MQSeries-IMS bridge from any MQSeries platform.

The conversion (including the calling of any necessary exits) is performed by the distributed queuing facility when it puts a message to a destination queue that has XCF information defined for its storage class. Any exits needed must be available to the distributed queuing facility in the data set referenced by the CSQXLIB DD statement.

**Note:** Messages arriving through the CICS distributed queuing facility are not converted.

If there are conversion errors, the message is put to the queue unconverted; this results eventually in it being treated as an error by the MQSeries-IMS bridge, because the bridge cannot recognize the header format. If a conversion error occurs, an error message is sent to the OS/390 console.

See Chapter 11, “Writing data-conversion exits” on page 161 for detailed information about data conversion in general.

**Sending messages to the MQSeries-IMS bridge:** To ensure that conversion is performed correctly, you must tell the queue manager what the format of the message is. If the message has an MQIIH structure, the *Format* in the MQMD must be set to the built-in format MQFMT\_IMS, and the *Format* in the MQIIH must be set to the name of the format that describes your message data. If there is no MQIIH, set the *Format* in the MQMD to your format name.

If your data (other than the LLZZs) is all character data (MQCHAR), use as your format name (in the MQIIH or MQMD, as appropriate) the built-in format MQFMT\_IMS\_VAR\_STRING. Otherwise, use your own format name, in which case you must also provide a data-conversion exit for your format. The exit must handle the conversion of the LLZZs in your message, in addition to the data itself (but it does not have to handle any MQIIH at the start of the message).

If you use this format, the *MFSMapName* passed to IMS is MQFMT\_IMS\_VAR\_STRING. If your application makes use of *MFSMapName*, you are recommended to use messages with the MQFMT\_IMS instead.

**Receiving messages from the MQSeries-IMS bridge:** If an MQIIH structure is present on the original message that you are sending to IMS, one is also present on the reply message.

To ensure your reply is converted correctly, follow these steps:

- If you have an MQIIH structure on your original message, specify the format you want for your reply message in the MQIIH *ReplytoFormat* field of the original message. This value is placed in the MQIIH *Format* field of the reply message.
- If you do not have an MQIIH structure on your original message, specify the format you want for the reply message as the MFS MOD name in the IMS application’s ISRT to the IOPCB.
- Specify CONVERT(YES) on the sender channel between your MQSeries for OS/390 system and your destination MQSeries system.

## Writing your program

The coding required to handle IMS transactions through MQSeries is platform-specific. However, there are several points to be borne in mind when your application handles IMS screen formatting information.

In IMS, your application can modify certain 3270 screen behavior, for example, highlighting a field which has had invalid data entered. This type of information is communicated by adding a two byte attribute field to the IMS message for each screen field needing to be modified by the program.

Thus, if you are coding an application to mimic a 3270, you need to take account of these fields when building or receiving messages.

You may need to code information in your program to process:

- Which key is pressed (Enter, PF1....)
- Where the cursor is when the message is passed to your application
- Whether the attribute fields have been set by the IMS application
  - High/normal/zero intensity
  - Color
  - Whether IMS is expecting the field back the next time enter is pressed
- Whether the IMS application has used null characters (X'3F') in any fields.

If your IMS message contains only character data (apart from the LLZZ-data segment), and you are using an MQIIH structure, set the MQMD format to MQFMT\_IMS and the MQIIH format to MQFMT\_IMS\_VAR\_STRING.

If your IMS message contains only character data (apart from the LLZZ-data segment), and you are *not* using an MQIIH structure, set the MQMD format to MQFMT\_IMS\_VAR\_STRING and ensure that your IMS application specifies MODname MQFMT\_IMS\_VAR\_STRING when replying.

If your IMS message contains binary, packed, or floating point data (apart from the LLZZ-data segment), you will need to code your own data-conversion routines. Refer to the *IMS/ESA Application Programming: Transaction Manager* manual for information about IMS screen formatting.

### Dealing with unsolicited messages from IMS

You need to write pre-routing and destination resolution exits to handle unsolicited messages from IMS. See the *MQSeries for OS/390 System Management Guide* for information about these exit programs.

Unsolicited messages can create new Tpipes. For example if an existing IMS transaction switched to a new LTERM (for example PRINT01) but the implementation required that the output be delivered through OTMA; a new Tpipe (called PRINT01 in this example) would be created. By default this will be an asynchronous Tpipe. If the implementation requires the message to be recoverable the destination resolution exit Output flag must be set. See the *IMS Customization Guide* for more information.

### Writing MQSeries applications to invoke IMS conversational transactions

When you write an application which will invoke an IMS conversation, you should bear the following in mind:

- You must include an MQIIH structure with your application message.
- You must set the *CommitMode* in MQIIH to MQICM\_SEND\_THEN\_COMMIT.
- To invoke a new conversation, set *TranState* in MQIIH to MQITS\_NOT\_IN\_CONVERSATION.
- To invoke second and subsequent steps of a conversation, set *TranState* to MQITS\_IN\_CONVERSATION, and set *TranInstanceId* to the value of that field returned in the previous step of the conversation.

- There is no easy way in IMS to find the value of a *TranInstanceId*, should you lose the original message sent from IMS.
- The application must check the *TranState* of messages from IMS to check whether the IMS transaction has terminated the conversation.
- You can use /EXIT to end a conversation. You must also quote the *TranInstanceId*, set *TranState* to MQITS\_IN\_CONVERSATION, and use the MQSeries queue on which the conversation is being carried out.
- You cannot use /HOLD or /REL to hold or release a conversation.
- Conversations invoked through the MQSeries-IMS bridge are terminated if IMS is restarted.

### Triggering

The MQSeries-IMS bridge does not support trigger messages.

If you define an initiation queue that uses a storage class with XCF parameters, messages put to that queue are rejected when they get to the bridge.

---

## Writing IMS applications using MQSeries

This section discusses the following subjects that you should consider when using MQSeries in IMS applications:

- “Syncpoints in IMS applications”
- “MQI calls in IMS applications” on page 246

### Syncpoints in IMS applications

In an IMS application, you establish a syncpoint by using IMS calls such as GU (get unique) to the IOPCB and CHKP (checkpoint). To back out all changes since the previous checkpoint, you can use the IMS ROLB (rollback) call. For more information, see the following books:

- *IMS/ESA Application Programming: Transaction Manager*
- *IMS/ESA Application Programming: Design Guide*

The queue manager is a participant in a two-phase commit protocol; the IMS syncpoint manager is the coordinator.

All open handles are closed by the IMS adapter at a syncpoint (except in a batch-oriented BMP). This is because a different user could initiate the next unit of work and MQSeries security checking is performed when the MQCONN and MQOPEN calls are made, not when the MQPUT or MQGET calls are made.

Handles are also closed after a ROLB call unless you are running IMS Version 3 or are running a batch-oriented BMP.

If an IMS application (either a BMP or an MPP) issues the MQDISC call, open queues are closed but no implicit syncpoint is taken. If the application closes down normally, any open queues are closed and an implicit commit occurs. If the application closes down abnormally, any open queues are closed and an implicit backout occurs.

### MQI calls in IMS applications

This section covers the use of MQI calls in the following types of IMS applications:

- “Server applications”
- “Enquiry applications” on page 249

#### Server applications

Here is an outline of the MQI server application model:

```
Initialize/Connect
.
Open queue for input shared
.
Get message from MQSeries queue
.
Do while Get does not fail
.
    If expected message received
        Process the message
    Else
        Process unexpected message
    End if
.
    Commit
.
    Get next message from MQSeries queue
.
End do
.
Close queue/Disconnect
.
END
```

Sample program CSQ4ICB3 shows the implementation, in C/370™, of a BMP using this model. The program establishes communication with IMS first, and then with MQSeries:

```
main()
----
    Call InitIMS
    If IMS initialization successful
        Call InitMQM
        If MQSeries initialization successful
            Call ProcessRequests
            Call EndMQM
        End-if
    End-if
Return
```

The IMS initialization determines whether the program has been called as a message-driven or a batch-oriented BMP and controls MQSeries queue manager connection and queue handles accordingly:

```

InitIMS
-----
Get the IO, Alternate and Database PCBs
Set MessageOriented to true

Call ctdli to handle status codes rather than abend
If call is successful (status code is zero)
  While status code is zero
    Call ctdli to get next message from IMS message queue
    If message received
      Do nothing
    Else if no IOPBC
      Set MessageOriented to false
      Initialize error message
      Build 'Started as batch oriented BMP' message
      Call ReportCallError to output the message
    End-if
    Else if response is not 'no message available'
      Initialize error message
      Build 'GU failed' message
      Call ReportCallError to output the message
      Set return code to error
    End-if
  End-if
End-while
Else
  Initialize error message
  Build 'INIT failed' message
  Call ReportCallError to output the message
  Set return code to error
End-if

Return to calling function

```

The MQSeries initialization performs queue manager connection opens the queues. In a Message-driven BMP this is called after each IMS syncpoint is taken; in a batch-oriented BMP, this is only called during program start-up:

```

InitMQM
-----
  Connect to the queue manager
  If connect is successful
    Initialize variables for the open call
    Open the request queue
    If open is not successful
      Initialize error message
      Build 'open failed' message
      Call ReportCallError to output the message
      Set return code to error
    End-if
  Else
    Initialize error message
    Build 'connect failed' message
    Call ReportCallError to output the message
    Set return code to error
  End-if

Return to calling function

```

The implementation of the server model in an MPP is influenced by the fact that the MPP processes a single unit of work per invocation. This is because, when a syncpoint (GU) is taken, the connection and queue handles are closed and the next IMS message is delivered. This limitation can be partially overcome by one of the following:

- **Processing many messages within a single unit-of-work**

This involves:

- Reading a message
- Processing the required updates
- Putting the reply

in a loop until all messages have been processed or until a set maximum number of messages has been processed, at which time a syncpoint is taken.

Only certain types of application (for example, a simple database update or inquiry) can be approached in this way. Although the MQI reply messages can be put with the authority of the originator of the MQI message being handled, the security implications of any IMS resource updates need to be addressed carefully.

- **Processing one message per invocation of the MPP and ensuring multiple scheduling of the MPP to process all available messages.**

Use the MQSeries IMS trigger monitor program (CSQQTRMN) to schedule the MPP transaction when there are messages on the MQSeries queue and no applications serving it.

If the MPP is started by the trigger monitor the queue manager name and queue name are passed to the program, as shown in the following COBOL code extract:

```
* Data definition extract
01 WS-INPUT-MSG.
   05 IN-LL1                PIC S9(3) COMP.
   05 IN-ZZ1                PIC S9(3) COMP.
   05 WS-STRINGPARM        PIC X(1000).
01 TRIGGER-MESSAGE.
   COPY CMQTMCL.

*
* Code extract
GU-IOPCB SECTION.
   MOVE SPACES TO WS-STRINGPARM.
   CALL 'CBLTDLI' USING GU,
                               IOPCB,
                               WS-INPUT-MSG.
   IF IOPCB-STATUS = SPACES
       MOVE WS-STRINGPARM TO MQTMC.
*   ELSE handle error
*
* Now use the queue manager and queue names passed
   DISPLAY 'MQTMC-QMGRNAME      ='
           MQTMC-QMGRNAME OF MQTMC '='.
   DISPLAY 'MQTMC-QNAME        ='
           MQTMC-QNAME   OF MQTMC '='.
```

The server model, which is expected to be a long running task, is better supported in a batch processing region, although the BMP cannot be triggered using CSQQTRMN.

## Enquiry applications

A typical MQSeries application initiating an inquiry or update works as follows:

- Gather data from the user
- Put one or more MQSeries messages
- Get the reply messages (you might have to wait for them)
- Provide a response to the user

Because messages put on to MQSeries queues do not become available to other MQSeries applications until they are committed, they must either be put out of syncpoint, or the IMS application must be split into two transactions.

If the inquiry involves putting a single message, it is acceptable to use the “no syncpoint” option; however, if the inquiry is more complex, or resource updates are involved, you might get consistency problems if failure occurs and you don’t use syncpointing.

To overcome this, IMS MPP transactions using MQI calls could be split using a program-to-program message switch; see the *IMS/ESA Application Programming: Data Communication* manual for information about this. This would allow an inquiry program to be implemented in an MPP :

```

Initialize first program/Connect
.
Open queue for output
.
Put inquiry to MQSeries queue
.
Switch to second MQSeries program, passing necessary data in save
pack area (this commits the put)
.
END
.
Initialize second program/Connect
.
Open queue for input shared
.
Get results of inquiry from MQSeries queue
.
Return results to originator
.
END

```

---

## MQSeries Workflow

MQSeries Workflow on OS/390 is a tool which helps companies improve their business processes. OS/390 workload manager (WLM) addresses the need for:

- Managing workload distribution
- Load balancing
- Distribution of computing resources to competing workloads

MQSeries support for OS/390 workload manager introduces a new type of local queue: a WLM-managed queue. It is recognized by a new value of the INDXTYPE attribute called MSGTOKEN. The initiation queue associated with a WLM-managed

## Workflow

queue should have TRIGTYPE defined as NONE and no ordinary local queues should be associated with this initiation queue.

If an MQSeries Workflow server application has the initiation queue open for input, MQSeries updates a WLM worklist as part of commit processing of MQPUTs to the WLM-managed queue. The setting of TRIGGER or NOTRIGGER on the WLM-managed queue has no effect on the updating of this WLM worklist.

The PROCESS definition is used to provide the name of the application\_environment associated with a WLM-managed queue. This is passed in the APPLICID attribute. You should ensure that a WLM-managed queue uniquely references an associated process and that two processes do not specify the same APPLICID value.

Messages are retrieved from a WLM-managed queue using a unique message\_token which must be passed to MQGET. To do this, a new message\_token value (MQGMO\_MSGTOKEN) and a new get message match option (MQMO\_MATCH\_MSG\_TOKEN) are used.

There are new MQRC values for MQGET (MQRC\_MSG\_TOKEN\_ERROR) and MQPUT (MQRC\_MISSING\_WIH and MQRC\_WIH\_ERROR). MQRC\_MISSING\_WIH is returned if a message, MQPUT to a WLM-managed queue, does not include the new work information header (MQWIH). MQRC\_WIH\_ERROR is returned if the message data does not conform to an MQWIH. MQGET does not remove this header from the message.

**Note:** You may experience excessive CPU usage if your OS/390 system is at Version 2.5 or earlier and the number of messages on WLM-managed queues exceeds 500.

For further information see *IBM MQSeries Workflow: Concepts and Architecture*, GH12-6285 and *IBM MQSeries Workflow for OS/390: Customization and Administration*, SC33-7030.

---

## Chapter 16. Object-oriented programming with MQSeries

The preceding chapters have described the procedural Message Queue Interface (MQI), which may be used from programming languages such as COBOL, PL/I, C, and C++. The MQI comprises calls, structures, and elementary data types to allow an application programmer to create MQSeries applications.

MQSeries provides an alternative way of programming MQSeries applications, that can be used from object-oriented programming languages. It is called the *MQSeries Object Model*. Instead of calls and structures, the MQSeries Object Model provides *classes* that provide the same functionality, but which are a more natural way of programming in an object-oriented environment.

---

### What is in the MQSeries Object Model?

The MQSeries Object Model comprises the following:

- *Classes* representing familiar MQSeries concepts such as queue managers, queues, and messages.
- *Methods* on each class corresponding to MQI calls.
- *Properties* on each class corresponding to attributes of MQSeries objects.

When creating an MQSeries application using the MQSeries Object Model, you create instances of these classes in the program. An instance of a class in object-oriented programming is called an *object*. When an object has been created, you interact with the object by examining or setting the values of the object's properties (the equivalent of issuing an MQINQ or MQSET call), and by making method calls against the object (the equivalent of issuing the other MQI calls).

### Classes

The MQSeries Object Model provides the following base set of classes. Note that the actual implementation of the model varies slightly between the different supported object-oriented environments.

#### **MQQueueManager**

An object of the MQQueueManager class represents a connection to a queue manager. It has methods to Connect(), Disconnect(), Commit(), and Backout() (the equivalent of MQCONN, MQDISC, MQCMIT, and MQBACK). It has properties corresponding to the attributes of a queue manager. Note that accessing a queue manager attribute property implicitly connects to the queue manager if not already connected. Destroying an MQQueueManager object implicitly disconnects from the queue manager.

#### **MQQueue**

An object of the MQQueue class represents a queue. It has methods to Put() and Get() messages to and from the queue (the equivalent of MQPUT and MQGET). It has properties corresponding to the attributes of a queue. Note that accessing a queue attribute property, or issuing a Put() or Get() method call, implicitly opens the queue (the equivalent of MQOPEN). Destroying an MQQueue object implicitly closes the queue (the equivalent of MQCLOSE).

### **MQMessage**

An object of the MQMessage class represents a message to be put on a queue or got from a queue. It comprises a buffer, and encapsulates both application data and MQMD. It has properties corresponding to MQMD fields, and methods that allow you to write and read user data of different types (for example, strings, long integers, short integers, single bytes) to and from the buffer.

### **MQPutMessageOptions**

An object of the MQPutMessageOptions class represents the MQPMO structure. It has properties corresponding to MQPMO fields.

### **MQGetMessageOptions**

An object of the MQGetMessageOptions class represents the MQGMO structure. It has properties corresponding to MQGMO fields.

### **MQProcess**

An object of the MQProcess class represents a process definition (used with triggering). It has properties that represent the attributes of a process definition.

### **MQDistributionList**

MQSeries Version 5 products and MQSeries for AS/400 only. An object of the MQDistributionList class represents a distribution list (used to send multiple messages with a single MQPUT). It comprises a list of MQDistributionListItem objects.

### **MQDistributionListItem**

MQSeries Version 5 products and MQSeries for AS/400 only. An object of the MQDistributionListItem class represents a single distribution list destination. It encapsulates the MQOR, MQRR, and MQPMR structures, and has properties corresponding to the fields of these structures.

## Object references

In an MQSeries program that uses the MQI, MQSeries returns connection handles and object handles to the program. These handles must be passed as parameters on subsequent MQSeries calls. With the MQSeries Object Model, these handles are hidden from the application program. Instead, the creation of an object from a class results in an object reference being returned to the application program. It is this object reference that is used when making method calls and property accesses against the object.

## Return codes

Issuing a method call or setting a property value results in return codes being set. These return codes are a completion code and a reason code, and are themselves properties of the object. The values of completion code and reason code are exactly the same as those defined for the MQI, with some extra values specific to the object-oriented environment.

---

## Programming language considerations

The MQSeries Object Model is implemented in C++, Java, LotusScript®, and ActiveX®.

### Coding in C++

Refer to the *MQSeries Using C++* book for information about coding programs using the MQSeries Object Model in C++.

### Coding in Java

Refer to the *MQSeries Using Java* book for information about coding programs using the MQSeries Object Model in Java.

### Coding in LotusScript

Refer to the *MQSeries LotusScript Extension* book for information about coding programs using the MQSeries Object Model in LotusScript.

The MQSeries link LotusScript Extension is commonly known as the MQLSX. For Windows NT the MQLSX is included as part of MQSeries for Windows NT V5.1. For other platforms, or for earlier releases of MQSeries, the MQLSX and its documentation may be downloaded from the MQSeries Web site as a SupportPac.

### Coding in ActiveX

Refer to the *MQSeries for Windows NT Using the Component Object Model Interface* for information about coding programs using the MQSeries Object Model in ActiveX.

The MQSeries ActiveX is commonly known as the MQAX. The MQAX is included as part of MQSeries for Windows NT V5.1. For earlier releases of MQSeries for Windows NT, the MQAX and its documentation may be downloaded from the MQSeries Web site as a SupportPac.



---

## Part 3. Building an MQSeries application

<b>Chapter 17. Building your application on AIX</b> .....	259
Preparing C programs .....	259
Linking libraries .....	259
Preparing COBOL programs .....	260
Preparing COBOL programs using IBM COBOL SET for AIX .....	261
Preparing COBOL programs using Micro Focus COBOL .....	261
Preparing PL/I programs .....	261
Preparing CICS programs .....	261
CICS on Open Systems support .....	262
<b>Chapter 18. Building your application on AS/400</b> .....	265
Preparing C programs .....	265
Preparing COBOL programs .....	265
Preparing RPG programs .....	266
AS/400 programming considerations .....	266
QMQM activation group .....	266
<b>Chapter 19. Building your application on AT&amp;T GIS UNIX</b> .....	267
Preparing C programs .....	267
C compiler flags .....	267
Linking libraries .....	268
<b>Chapter 20. Building your application on Digital OpenVMS</b> .....	269
Preparing C programs .....	269
C compiler version .....	269
C compiler flags .....	269
Linking libraries .....	269
Preparing COBOL programs .....	270
COBOL compiler flags .....	270
Linking libraries .....	270
<b>Chapter 21. Building your application on HP-UX</b> .....	271
Preparing C programs .....	271
Linking libraries .....	271
Preparing COBOL programs .....	272
Programs to run in the MQSeries client environment .....	272
Preparing CICS programs .....	273
CICS on Open Systems support .....	273
<b>Chapter 22. Building your application on OS/390</b> .....	275
Preparing your program to run .....	275
Building OS/390 batch applications .....	275
Building CICS applications .....	277
Building IMS (BMP or MPP) applications .....	278
Dynamically calling the MQSeries stub .....	279
Debugging your programs .....	284
Debugging CICS programs .....	284
Debugging TSO programs .....	287

<b>Chapter 23. Building your application on OS/2 Warp</b>	289
Preparing C programs	289
Preparing CICS and Transaction Server programs	290
Preparing COBOL programs	291
Preparing Transaction Server programs	292
Preparing PL/I programs	292
<b>Chapter 24. Building your application on SINIX or DC/OSx</b>	293
Preparing C programs	293
C compiler flags	293
Preparing COBOL programs	294
Compiling COBOL programs	294
Preparing CICS programs	295
CICS on Open Systems support	295
CICS sample transaction	295
Linking libraries	296
<b>Chapter 25. Building your application on Sun Solaris</b>	297
Preparing C programs	297
Linking libraries	298
Preparing COBOL programs	298
Preparing CICS programs	299
CICS on Open Systems support	299
<b>Chapter 26. Building your application on Tandem NSK</b>	301
Unit of work (transaction) management	301
General design considerations	301
MQGMO_BROWSE_* with MQGMO_LOCK	301
Triggered applications	301
Compiling and binding applications	303
Running applications	303
<b>Chapter 27. Building your application on VSE/ESA</b>	305
Linking library	305
Using the batch interface	305
Preparing C programs	305
Preparing COBOL programs	305
Preparing PL/I programs	305
<b>Chapter 28. Building your application on Windows</b>	307
Linking libraries	307
Preparing Visual Basic programs	307
<b>Chapter 29. Building your application on Windows NT</b>	309
Preparing C programs	309
Preparing CICS and Transaction Server programs	310
Preparing COBOL programs	311
Preparing CICS and Transaction Server programs	312
Preparing PL/I programs	313
Preparing Visual Basic programs	313
<b>Chapter 30. Using lightweight directory access protocol services with MQSeries for Windows NT</b>	315
What is a directory service?	315

	What is LDAP? . . . . .	315
	Using LDAP with MQSeries . . . . .	316
	LDAP sample program . . . . .	317
	Building the sample program . . . . .	317
	Configuring the directory . . . . .	317
	Configuring the IBM eNetwork LDAP server . . . . .	318
	Configuring the Netscape directory server . . . . .	319
	Running the sample program . . . . .	320
	Program design . . . . .	320



## Chapter 17. Building your application on AIX

The AIX publications describe how to build executable applications from the programs you write. This chapter describes the additional tasks, and the changes to the standard tasks, you must perform when building MQSeries for AIX applications to run under AIX. C, C++, and COBOL are supported. For information about preparing your C++ programs, see the *MQSeries Using C++* book.

The tasks you must perform to create an executable application using MQSeries for AIX vary with the programming language your source code is written in. In addition to coding the MQI calls in your source code, you must add the appropriate language statements to include the MQSeries for AIX include files for the language you are using. You should make yourself familiar with the contents of these files. See Appendix G, "MQSeries data definition files" on page 529 for a full description.

### Preparing C programs

Precompiled C programs are supplied in the `/usr/mqm/samp/bin` directory. Use the ANSI compiler and run the following command:

```
$ cc -o <amqsput> <amqsput>.c -lmqm
```

where `amqsput` is a sample program.

If you want to use the programs on a machine which has only the MQSeries client for AIX installed, recompile the programs to link them with the client library (`-lmqic`) instead.

### Linking libraries

You will need the following libraries:

- If your application is running in a DCE client environment you will need to copy the DCE library, `libxdsom.a`, on to your machine.
- You need to link your programs with the appropriate library provided by MQSeries.

In a non-threaded environment you must link to one of the following libraries:

Library file	Program/exit type
<code>libmqm.a</code>	Server for C
<code>libmqic.a</code>	Client for C

In a threaded environment, you must link to one of the following libraries:

Library file	Program/exit type
<code>libmqm_r.a</code>	Server for C
<code>libmqic_r.a</code>	Client for C

For example, to build a simple threaded MQSeries application from a single compilation unit on AIX 4.3 run the following command:

```
$ xlc_r7 -o myapp myapp.c -lmqm_r
```

where `myapp` is the name of your program.

## Preparing COBOL programs

### Notes:

1. If you are writing an installable service (see Chapter 11, “Installable services and components” in the *MQSeries Programmable System Management* book for further information), you need to link to the `libmqmzf.a` library in a non-threaded application and to the `libmqmzf_r.a` library in a threaded application.
2. If you are producing an XA switch load file for external coordination by an XA-compliant transaction manager such as IBM CICS, Transarc Encina, or Novell Tuxedo, you need to link to the `libmqmxa.a` library in a non-threaded application and to the `libmqmxa_r.a` library in a threaded application.
3. You need to link trusted applications to the threaded MQSeries libraries. However, only one thread in an MQSeries on UNIX systems trusted application can be connected at a time.
4. To run the sample Encina program, link against the following libraries:
  - `libmqmxa_r.a`
  - `libmqm_r.a`

Also, link to the Encina and DCE libraries:

- `libEncServer.a`
- `libEncina.a`
- `libdce.a`

The sample must be compiled and linked using `xlc_r4`.

5. You must link MQSeries libraries before any other product libraries (in this case, DCE and Encina). For example:

```
cc -o put put.c -lmqm_r -ldce
```

This ensures that any operating system functions that have been redefined by DCE are also used by MQSeries.

---

## Preparing COBOL programs

You need to link your program with one of the following:

**libmqmcb.a** Server for COBOL  
**libmqicb.a** Client for COBOL  
**libmqmcb\_r.a** Server for COBOL (in a threaded application)

You can use the IBM COBOL Set compiler or Micro Focus COBOL compiler depending on the program:

- Programs beginning `amqi` are suitable for the IBM COBOL Set compiler,
  - programs beginning `amqm` are suitable for the Micro Focus COBOL compiler,
- and
- programs beginning `amq0` are suitable for either compiler.

## Preparing COBOL programs using IBM COBOL SET for AIX

Sample COBOL programs are supplied with MQSeries. To compile such a program, enter:

```
cob2 -o amq0put0 amq0put0.cb1
-L/usr/mqm/lib
-lmqmcb -qLIB
-I/usr/mqm/inc
```

**Note:** For threaded applications, `cob2_r` is used with the `libmqmcb_r.a` library.

## Preparing COBOL programs using Micro Focus COBOL

Set environment variables before compiling your program as follows:

```
export COBCPY=/usr/mqm/inc
export LIB=/usr/mqm/lib;$LIB
```

To compile a COBOL program using Micro Focus COBOL, enter:

```
cob -xvP amq0put0.cb1 -lmqmcb
```

See the Micro Focus COBOL documentation for a description of the environment variables that need to be set up.

---

## Preparing PL/I programs

Sample PL/I programs are supplied with MQSeries. PL/I include files are also provided so that the C entry points in the MQSeries libraries can be invoked directly.

To prepare a PL/I program:

1. Link your program with one of the libraries listed in “Linking libraries” on page 259.
2. Compile your program:

```
pli amqpput0.pli -I/usr/mqm/inc /usr/mqm/lib/libmqm.a
```

---

## Preparing CICS programs

XA switch modules are provided to enable you to link CICS with MQSeries:

<i>Table 12. Essential Code for CICS applications (AIX)</i>		
Description	C (source)	C (exec) - add to your XAD.Stanza
XA initialization routine	amqzscix.c	amqzsc21 - CICS for AIX

Always link your transactions with the thread safe MQSeries library `libmqm_r.a`.

**Note:** On AIX Version 4, the `libmqm_r.a` library works with both native and DCE libraries.

## Preparing CICS programs

Compile the program by typing:

```
xlc_r4 /usr/mqm/samp/amqzscix.c -I/usr/lpp/encina/include \  
-e amqzscix -o amqzscix /usr/lpp/cics/lib/regxa_swxa.o \  
-L/usr/lpp/cics/lib -L/usr/lpp/encina/lib -lmqmcics_r -lmqmx_r -lmqm_r \  
-lcicsrt -lEncina -lEncServer -ldce
```

You can find more information about supporting CICS transactions in “Using CICS” in the *MQSeries System Administration* book.

## CICS on Open Systems support

MQSeries on UNIX systems support CICS on Open Systems by way of the XA interface.

You must ensure that CICS COBOL applications are linked to the threaded version of the library. CICS on Open Systems MQSeries transactions must link with `libmqm_r`, except on Sun Solaris, where you must link with `lmqmc_d`.

You can run CICS programs using IBM COBOL SET for AIX or Micro Focus COBOL. The following sections describe the difference between these.

### Preparing CICS COBOL programs using IBM COBOL SET for AIX

To use IBM COBOL, follow these steps:

1. Export the following environment variable:

```
export LDFLAGS="-qLIB -bI:/usr/lpp/cics/lib/cicsprIBMCOB.exp \  
-I/usr/mqm/inc -I/usr/lpp/cics/include \  
-e _iwz_cobol_main \  
-L/usr/lib/dce -lmqmc_b_r -ldcelibc_r -ldcepthreads"
```

where LIB is a compiler directive.

2. Translate, compile, and link the program by typing:

```
cicstcl -l IBMCOB <yourprog>.ccp
```

### Preparing CICS COBOL programs using Micro Focus COBOL

To use Micro Focus COBOL, follow these steps:

1. Add the MQSeries COBOL run-time library module to the run-time library using the following command:

```
cicsmkcobol -L/usr/lib/dce -L/usr/mqm/lib \  
/usr/mqm/lib/libmqmcbrt.0 -lmqm_r
```

This creates the Micro Focus COBOL language method file and enables the CICS run-time COBOL library to call MQSeries on UNIX systems.

**Note:** `cicsmkcobol` must be run only when one of the following is installed:

- New version or release of Micro Focus COBOL
- New version or release of CICS for AIX
- New version or release of any supported database product (for COBOL transactions only)
- CICS for AIX

2. Export the following environment variables:

```
COBCPY=/usr/mqm/inc export COBCPY  
LDFLAGS="-L/usr/mqm/lib -lmqm_r" export LDFLAGS
```

3. Translate, compile, and link the program by typing:

```
cicstcl -l COBOL -e <yourprog>.ccp
```

### Preparing CICS C programs

You build CICS C programs using the standard CICS facilities:

1. Export **one** of the following environment variables:

- LDFLAGS = "-L/usr/mqm/lib -lmqm\_r" export LDFLAGS
- USERLIB = "-L/usr/mqm/lib -lmqm\_r" export USERLIB

2. Translate, compile, and link the program by typing:

```
cicstcl -l C amqscic0.ccs
```

**CICS C sample transaction:** Sample C source for a CICS MQSeries transaction is provided by AMQSCIC0.CCS. The transaction reads messages from the transmission queue SYSTEM.SAMPLE.CICS.WORKQUEUE on the default queue manager and places them onto the local queue whose name is contained in the transmission header of the message. Any failures will be sent to the queue SYSTEM.SAMPLE.CICS.DLQ. The sample MQSC script AMQSCIC0.TST may be used to create these queues and sample input queues.



---

## Chapter 18. Building your application on AS/400

The AS/400 publications describe how to build executable applications from the programs you write. This chapter describes the additional tasks, and the changes to the standard tasks, you must perform when building MQSeries for AS/400 applications to run on AS/400 systems. COBOL, C, C++, and RPG programming languages are supported. For information about preparing your C++ programs, see the *MQSeries Using C++* book.

The tasks you must perform to create an executable MQSeries for AS/400 application depend on the programming language the source code is written in. In addition to coding the MQI calls in your source code, you must add the appropriate language statements to include the MQSeries for AS/400 data definition files for the language you are using. You should make yourself familiar with the contents of these files. See Appendix G, "MQSeries data definition files" on page 529 for a full description.

---

### Preparing C programs

To compile a C program, you can use the OS/400 command, CRTCMOD. Make sure that the library containing the data definition files (QMQM) is in the library list when you perform the compilation.

You must then bind the output of the compiler with the service program AMQZSTUB using the CRTPGM command. An example of the command is:

```
CRTPGM PGM(pgmname) MODULE(pgmname)
BNDSRVPGM(QMQM/AMQZSTUB)
```

where *pgmname* is the name of your program.

---

### Preparing COBOL programs

To compile a COBOL program in the OPM environment, use the OS/400 command, CRTCLPGM. To compile an ILE COBOL program, use the OS/400 command, CRTBNDCBL, or the two commands CRTCLMOD, and CRTPGM.

See the *ILE COBOL/400 Programmer's Guide* and *ILE COBOL/400 Reference* for further information.

To make the compiler accept the single quotation mark character (') as the string delimiter in the COBOL copy files, use the compiler option \*APOST. Make sure that the library containing the data definition files (QMQM) is in the library list when you perform the compilation.

**Note:** For more information on compiling a CICS application, see the *CICS for AS/400 Application Programming Guide*, SC33-1386.

When you run a compiled COBOL MQSeries for AS/400 program, make sure the library QMQM is in the library list.

### Preparing RPG programs

If you are using MQSeries for AS/400, you can write your applications in RPG. For more information see “Coding in RPG” on page 82, and refer to the *MQSeries for AS/400 Application Programming Reference (RPG)* manual.

---

### AS/400 programming considerations

In MQSeries for AS/400 V4R2, the system behavior for activation group termination was altered. In previous releases, calling an entry point (by function pointer or bound call) in an activation group which had been terminated would normally cause a MCH3402 error. In MQSeries for AS/400 V4R2, and subsequent releases, the system terminates the process, unless the activation group was explicitly added to the program stack.

If you issue an ENDMQM \*IMMED whilst a program is running which is bound to the AMQZSTUB and/or AMQVSTUB service programs, this change causes the following behavior:

- If the program has been called from a QCMD prompt your program is terminated and you are logged off the system.
- If the program has been called from within an MQSeries panel, for example WRKMQMCHL, the program is terminated but you are not logged off the system.

### QMQM activation group

When creating your program on AS/400, the QMQM activation group should not be used. The QMQM activation group is for the use of MQSeries only.

---

## Chapter 19. Building your application on AT&T GIS UNIX

This chapter describes the additional tasks, and the changes to the standard tasks, you must perform when building MQSeries for AT&T GIS UNIX applications to run under AT&T GIS UNIX<sup>4</sup>. C and C++ programming languages are supported.

In addition to coding the MQI calls in your source code, you must add the appropriate include files. You should make yourself familiar with the contents of these files. See Appendix G, "MQSeries data definition files" on page 529 for a full description.

---

### Preparing C programs

Precompiled C programs are found in the /opt/mqm/samp/bin directory. To build a sample from source code, use the C compiler in /bin/cc, for example:

```
$ /bin/cc -o <yourprog> <yourprog>.c -lmqm -lmqmcs -lmqmzse \
-lnet -lnsl -lsocket -ldl
```

**Note:** The backslash (\) represents the continuation of the line.

### C compiler flags

The order of the libraries specified is important. The following is an example of how to build the sample program amqsput0:

```
/bin/cc -o <amqsput0> <amqsput0>.c -lmqic -lmqmcs -lmqmzse \
-lnet -lnsl -lsocket -ldl
```

This links with the client library -lmqic, so allows you to use the programs on a machine which has only the MQSeries client for GIS installed.

If you use the other version of the compiler (/usr/ucb/cc), your application may compile and link successfully. However when you run it, it will fail when it attempts to connect to the queue manager.

---

<sup>4</sup> This platform has become NCR UNIX SVR4 MP-RAS, R3.0.

### Linking libraries

You need to link your programs with the appropriate library provided by MQSeries.

You must link to one or more of the following libraries:

<b>Library file</b>	<b>Program/exit type</b>
<i>libmqm.so</i>	Server for C
<i>libmqmzse.so</i>	For C
<i>libmqic.so</i>	Client for C
<i>libmqmcs.so</i>	Client for C

**Notes:**

1. If you are writing an installable service (see Chapter 11, "Installable services and components" in the *MQSeries Programmable System Management* book for further information), you need to link to the *libmqmzf.so* library.
2. If you are producing an XA switch load file for external coordination by an XA-compliant transaction manager such as IBM CICS, Transarc Encina, or Novell Tuxedo, you need to link to the *libmqmxa.a* library.

---

## Chapter 20. Building your application on Digital OpenVMS

This chapter describes the additional tasks, and the changes to the standard tasks, you must perform when building MQSeries for Digital OpenVMS applications to run under Digital OpenVMS. C and COBOL are supported.

In addition to coding the MQI calls in your source code, you must add the appropriate include files. You should make yourself familiar with the contents of these files. See Appendix G, "MQSeries data definition files" on page 529 for a full description.

---

### Preparing C programs

This section explains the compiler and libraries you need to prepare your C programs.

#### C compiler version

You must use the DEC C compiler. To invoke the compiler, enter:

```
$ CC/DECC
```

This is the default.

#### C compiler flags

The include files for MQSeries for Digital OpenVMS are located in the MQS\_INCLUDE directory. The following is an example of how to build the sample program AMQSPUTO:

```
$ CC/INCLUDE_DIRECTORY=MQS_INCLUDE AMQSPUTO
$ LINK AMQSPUTO.OBJ,SYS$INPUT/OPTIONS
SYS$SHARE: MQM/SHAREABLE
Ctrl + Z
```

#### Linking libraries

You need to link your programs with the appropriate library provided by MQSeries. The libraries are found in SYS\$SHARE.

You must link to one or more of the following libraries:

<b>Library file</b>	<b>Program/exit type</b>
<i>mqm.exe</i>	Server for C
<i>mqic.exe</i>	Client for C
<i>mqmzf.exe</i>	Installable service exits for C

### Preparing COBOL programs

This section explains the compiler and libraries you need to prepare your COBOL programs.

#### COBOL compiler flags

You must compile the programs in ANSI mode using the /ANSI switch to the DEC COBOL compiler. The following is an example of how to build the sample program AMQ0PUT0:

```
$ COBOL/ANSI AMQ0PUT0.COB  
$ LINK AMQ0PUT0.OBJ,SYS$INPUT/OPTIONS  
SYS$SHARE: MQMCB/SHAREABLE  
Ctrl + Z
```

#### Linking libraries

You need to link your program with one of the following:

```
MQMCB.EXE   COBOL  
MQICB.EXE   COBOL MQSeries client
```

## Chapter 21. Building your application on HP-UX

This chapter describes the additional tasks, and the changes to the standard tasks, you must perform when building MQSeries for HP-UX applications to run under HP-UX. C, C++, and COBOL are supported. For information about preparing your C++ programs, see the *MQSeries Using C++* book.

The tasks you must perform to create an executable application using MQSeries for HP-UX vary with the programming language your source code is written in. In addition to coding the MQI calls in your source code, you must add the appropriate language statements to include the MQSeries for HP-UX include files for the language you are using. You should make yourself familiar with the contents of these files. See Appendix G, "MQSeries data definition files" on page 529 for a full description.

### Preparing C programs

Work in your normal environment. Precompiled C programs are supplied in the `/opt/mqm/samp/bin` directory. The following is an example of how to build the sample program `amqsput0` in a non-threaded environment:

```
cc -Aa -D_HPUX_SOURCE -o amqsput0 amqsput0.c -lmqm
```

The following is an example of how to build the sample program `amqsput0` in a threaded environment:

```
cc -Aa -D_HPUX_SOURCE -o amqsput0 amqsput0.c -lmqm_r -lcma
```

If you want to use the programs on a machine which has only the MQSeries client for HP-UX installed, recompile the programs to link them with the client library instead. The following is an example of how to build a non-threaded client:

```
cc -Aa -D_HPUX_SOURCE -o amqsput0 amqsput0.c -lmqic
```

The following is an example of how to build a threaded client:

```
cc -Aa -D_HPUX_SOURCE -o amqsput0 amqsput0.c -lmqic_r
```

### Linking libraries

The following lists the libraries you will need.

- You need to link your programs with the appropriate library provided by MQSeries.

In a non-threaded environment, you must link to one of the following libraries:

Library file	Program/exit type
<code>libmqm.sl</code>	Server for C
<code>libmqic.sl</code>	Client for C

In a threaded environment, you must link to one of the following libraries:

Library file	Program/exit type
<code>libmqm_r.sl</code>	Server for C
<code>libmqic_r.sl</code>	Client for C

## Preparing COBOL programs

### Notes:

1. If you are writing an installable service (see Chapter 11, “Installable services and components” in the *MQSeries Programmable System Management* book for further information), you need to link to the `libmqmzf.sl` library.
2. If you are producing an XA switch load file for external coordination by an XA-compliant transaction manager such as IBM CICS, Transarc Encina, or Novell Tuxedo, you need to link to the `libmqmxa.a` library in a non-threaded application and to the `libmqmxa_r.a` library in a threaded application.
3. You must link MQSeries libraries before any other product libraries (in this case, DCE and Encina). This ensures that any operating system functions that have been redefined by DCE are also used by MQSeries.

---

## Preparing COBOL programs

Compile the programs using the Micro Focus compiler. The copy files which declare the structures are in `/opt/mqm/inc`:

```
$ export LIB=/usr/mqm/lib;$LIB
$ export COBCPY="/opt/mqm/inc"
$ cob -vxP <amqsput>.cbl -lmqmc
```

where `amqsput` is a sample program.

You must ensure that you have specified adequate run-time stack sizes; 16 KB is the recommended minimum.

You need to link your program with one of the following:

<b>libmqmcb.sl</b>	Server for COBOL
<b>libmqicb.sl</b>	Client for COBOL
<b>amqmc_r.sl</b>	Threaded applications

## Programs to run in the MQSeries client environment

If you are using LU 6.2 to connect your MQI client to a server, you must link your application to `libsna.a`, part of the SNAPplusAPI product. Use the `-lV3` and `-lstr` options on your compile and link command.

- The `-lV3` option gives your program access to the AT&T signaling library (the SNAPplusAPI uses AT&T signals)
- The `-lstr` option links your program to the streams component

**Note:** The `-lstr` option is not needed on HP-UX Version 10.

If you are not using LU 6.2, consider linking to `libsna.a` (in `/opt/mqm/lib`) to fully resolve function names. The need to link to this library varies with how you are using the `-B` flag during the linking stage.

## Preparing CICS programs

To build the sample CICS transaction, amqscic0.ccs, run the following command:

```
$ export USERLIB="-lmqm_r"
$ cicstcl -l C amqscic0.ccs
```

An XA switch module is provided to enable you to link CICS with MQSeries:

<i>Table 13. Essential Code for CICS applications (HP-UX)</i>		
Description	C (source)	C (exec)
XA initialization routine	amqzscix.c	amqzsc

You can find more information about supporting CICS transactions in “Using CICS” in the *MQSeries System Administration* book.

## CICS on Open Systems support

MQSeries on UNIX systems supports CICS on Open Systems by way of the XA interface.

It is very important to ensure that CICS COBOL applications are linked to the threaded version of the library. CICS on Open Systems MQSeries transactions must link with libmqm\_r, except on Sun Solaris, where you must link with lmqmcs\_d.

**CICS C sample transaction:** Sample C source for a CICS MQSeries transaction is provided by AMQSCIC0.CCS. The transaction reads messages from the transmission queue SYSTEM.SAMPLE.CICS.WORKQUEUE on the default queue manager and places them onto the local queue whose name is contained in the transmission header of the message. Any failures will be sent to the queue SYSTEM.SAMPLE.CICS.DLQ. The sample MQSC script AMQSCIC0.TST may be used to create these queues and sample input queues.



---

## Chapter 22. Building your application on OS/390

The CICS, IMS, and OS/390 publications describe how to build applications that run in these environments. This chapter describes the additional tasks, and the changes to the standard tasks, you must perform when building MQSeries for OS/390 applications for these environments. COBOL, C, C++, Assembler, and PL/I programming languages are supported. (For information on building C++ applications see the *MQSeries Using C++* book.)

The tasks you must perform to create an executable MQSeries for OS/390 application depend on both the programming language the program is written in, and the environment in which the application will run.

In addition to coding the MQI calls in your program, you must add the appropriate language statements to include the MQSeries for OS/390 data definition file for the language you are using. You should make yourself familiar with the contents of these files. See Appendix G, “MQSeries data definition files” on page 529 for a full description.

### Note

The name **thlqual** is the high-level qualifier of the installation library on OS/390.

---

## Preparing your program to run

After you have written the program for your MQSeries application, to create an executable application you have to compile or assemble it, then link-edit the resulting object code with the stub program that MQSeries for OS/390 supplies for each environment it supports. How you prepare your program depends on both the environment (batch, CICS, or IMS(BMP or MPP)) in which the application will run, and the structure of the data sets on your OS/390 installation. The details are described in the following sections.

“Dynamically calling the MQSeries stub” on page 279 describes an alternative method of making MQI calls in your programs so that you do not need to link-edit an MQSeries stub. This method is not available for all languages and environments.

Do not link-edit a higher level of stub program than that of the version of MQSeries for OS/390 on which your program is running. For example, a program running on MQSeries for MVS/ESA V1.2 must not be link-edited with a stub program supplied with MQSeries for OS/390 V2.1.

## Building OS/390 batch applications

To build an MQSeries for OS/390 application that runs under OS/390 batch, create job control language (JCL) that performs these tasks:

1. Compile (or assemble) the program to produce object code. The JCL for your compilation must include SYSLIB statements that make the product data definition files available to the compiler.

## Preparing your programs

The data definitions are supplied in the following MQSeries for OS/390 libraries:

- For COBOL, **thlqual.SCSQCOBC**
- For assembler language, **thlqual.SCSQMACS**
- For C, **thlqual.SCSQC370**
- For PL/I, **thlqual.SCSQPLIC**

2. For a C application, prelink the object code created in step 1 on page 275.
3. Link-edit the object code created in step 1 on page 275 (or step 2 for a C application) to produce a load module. When you link-edit the code, you must include one of the MQSeries for OS/390 batch stub programs (CSQBSTUB or one of the RRS stub programs: CSQBRRSI or CSQBRSTB).

**CSQBSTUB** single-phase commit provided by MQSeries for OS/390

**CSQBRRSI** two-phase commit provided by RRS using the MQI

**CSQBRSTB** two-phase commit provided by RRS directly

**Note:** If you use CSQBRSTB then you must also link-edit your application with ATRSCSS from SYS1.CSSLIB. Figure 20 and Figure 21 show fragments of JCL to do this. The stubs are language-independent and are supplied in library **thlqual.SCSQLOAD**.

4. Store the load module in an application load library.

```

:
/*
/* MQSERIES FOR OS/390 LIBRARY CONTAINING BATCH STUB
/*
//CSQSTUB DD DSN=++HLQ.MQM100++.SCSQLOAD,DISP=SHR
/*
:
//SYSIN DD *
INCLUDE CSQSTUB(CSQBSTUB)
:
/*
```

Figure 20. Fragments of JCL to link-edit the object module in the batch environment, using single-phase commit

```

:
/*
/* MQSERIES FOR OS/390 LIBRARY CONTAINING BATCH STUB
/*
//CSQSTUB DD DSN=++HLQ.MQM100++.SCSQLOAD,DISP=SHR
//CSSLIB DD DSN=SYS1.CSSLIB,DISP=SHR
/*
:
//SYSIN DD *
INCLUDE CSQSTUB(CSQBRSTB)
INCLUDE CSSLIB(ATRSCSS)
:
/*
```

Figure 21. Fragments of JCL to link-edit the object module in the batch environment, using two-phase commit

To run a batch or RRS program, you must include the libraries **thlqual.SCSQAUTH** and **thlqual.SCSQLOAD** in the STEPLIB or JOBLIB data set concatenation.

To run a TSO program, you must include the libraries **thlqual.SCSQAUTH** and **thlqual.SCSQLOAD** in the STEPLIB used by the TSO session.

To run an OpenEdition batch program from the OpenEdition shell, add the libraries **thlqual.SCSQAUTH** and **thlqual.SCSQLOAD** to the STEPLIB specification in your \$HOME/.profile like this:

```
STEPLIB=thlqual.SCSQAUTH:thlqual.SCSQLOAD
export STEPLIB
```

## Building CICS applications

To build an MQSeries for OS/390 application that runs under CICS, you must:

- Translate the CICS commands in your program into the language in which the rest of your program is written
- Compile or assemble the output from the translator to produce object code
- Link-edit the object code to create a load module

CICS provides a procedure to execute these steps in sequence for each of the programming languages it supports.

- For CICS Transaction Server for OS/390, the *CICS Transaction Server for OS/390 System Definition Guide* describes how to use these procedures and the *CICS/ESA Application Programming Guide* gives more information on the translation process.

You must include:

- In the SYSLIB statement of the compilation (or assembly) stage, statements that make the product data definition files available to the compiler. The data definitions are supplied in the following MQSeries for OS/390 libraries:

```
For COBOL, thlqual.SCSQCOBC
For assembler language, thlqual.SCSQMACS
For C, thlqual.SCSQC370
For PL/I, thlqual.SCSQPLIC
```

- In your link-edit JCL, the MQSeries for OS/390 CICS stub program (CSQCSTUB). Figure 22 on page 278 shows fragments of JCL code to do this. The stub is language-independent and is supplied in library **thlqual.SCSQLOAD**.

When you have completed these steps, store the load module in an application load library and define the program to CICS in the usual way.

## Preparing your programs

```
      :  
      /*  
      /* MQSERIES FOR OS/390 LIBRARY CONTAINING CICS STUB  
      /*  
      /*CSQSTUB DD DSN=++HLQ.MQM100++.SCSQLOAD,DISP=SHR  
      /*  
      :  
      /*LKED.SYSIN DD *  
      INCLUDE CSQSTUB(CSQCSTUB)  
      :  
      /*
```

Figure 22. Fragments of JCL to link-edit the object module in the CICS environment

Before you run a CICS program, your system administrator must define it to CICS as an MQSeries program and transaction: you can then run it in the usual way.

## Building IMS (BMP or MPP) applications

If you are building batch DL/I programs, see “Building OS/390 batch applications” on page 275. To build other applications that run under IMS (either as a BMP or an MPP), create JCL that performs these tasks:

1. Compile (or assemble) the program to produce object code. The JCL for your compilation must include SYSLIB statements that make the product data definition files available to the compiler. The data definitions are supplied in the following MQSeries for OS/390 libraries:

- For COBOL, **thlqual.SCSQCOBC**
- For assembler language, **thlqual.SCSQMACS**
- For C, **thlqual.SCSQC370**
- For PL/I, **thlqual.SCSQPLIC**

2. For a C application, prelink the object module created in step 1.
3. Link-edit the object code created in step 1 (or step 2 for a C/370 application) to produce a load module:
  - a. Include the IMS language interface module (DFSLI000).
  - b. Include the MQSeries for OS/390 IMS stub program (CSQQSTUB).  
Figure 23 on page 279 shows fragments of JCL to do this. The stub is language independent and is supplied in library **thlqual.SCSQLOAD**.

**Note:** If you are using COBOL, you should select the NODYNAM compiler option to enable the linkage editor to resolve references to CSQQSTUB unless you intend to use dynamic linking as described in “Dynamically calling the MQSeries stub” on page 279.

4. Store the load module in an application load library.

```

:
/*
/* MQSERIES FOR OS/390 LIBRARY CONTAINING IMS STUB
/*
//CSQSTUB DD DSN=++HLQ.MQM100++.SCSQLOAD,DISP=SHR
/*
:
//LKED.SYSIN DD *
  INCLUDE CSQSTUB(CSQSTUB)
:
/*

```

Figure 23. Fragments of JCL to link-edit the object module in the IMS environment

Before you run an IMS program, your system administrator must define it to IMS as an MQSeries program and transaction: you can then run it in the usual way.

## Dynamically calling the MQSeries stub

Instead of link-editing the MQSeries stub program with your object code, you can dynamically call the stub from within your program. You can do this in the batch, IMS, and CICS environments. This facility is not supported by programs using PL/I in the CICS environment and it is not supported in the RRS environment.

However, this method:

- Increases the complexity of your programs
- Increases the storage required by your programs at execution time
- Reduces the performance of your programs
- Means that you cannot use the same programs in other environments

If you call the stub dynamically, the appropriate stub program and its aliases must be available at execution time. To ensure this, include the MQSeries for OS/390 data set SCSQLOAD:

<b>For batch and IMS</b>	In the STEPLIB concatenation of the JCL
<b>For CICS</b>	In the CICS DFHRPL concatenation

For IMS, you must ensure that the library containing the dynamic stub (built as described in the information about installing the IMS adapter in the *MQSeries for OS/390 System Management Guide*) is ahead of the data set SCSQLOAD in the STEPLIB concatenation of the region JCL.

Use the names shown in Table 14 when you call the stub dynamically. In PL/I, only declare the call names used in your program.

*Table 14. Call names for dynamic linking*

MQI call	Dynamic call name		
	Batch (non-RRS)	CICS	IMS
MQBACK	CSQBBACK	not supported	not supported
MQCMIT	CSQBCOMM	not supported	not supported
MQCLOSE	CSQBCLOS	CSQCCLOS	MQCLOSE
MQCONN	CSQBCONN	CSQCCONN	MQCONN
MQDISC	CSQBDISC	CSQCDISC	MQDISC
MQGET	CSQBGET	CSQCGET	MQGET
MQINQ	CSQBINQ	CSQCINQ	MQINQ
MQOPEN	CSQBOPEN	CSQCOPEN	MQOPEN
MQPUT	CSQBPUT	CSQCPUT	MQPUT
MQPUT1	CSQBPUT1	CSQCPUT1	MQPUT1
MQSET	CSQBSET	CSQCSET	MQSET

For examples of how to use this technique, see the following figures:

- Batch and COBOL**                      Figure 24
- CICS and COBOL**                    Figure 25 on page 281
- IMS and COBOL**                     Figure 26 on page 281
- Batch and assembler**              Figure 27 on page 282
- CICS and assembler**                Figure 28 on page 282
- IMS and assembler**                Figure 29 on page 282
- Batch and C**                         Figure 30 on page 282
- CICS and C**                          Figure 31 on page 283
- IMS and C**                            Figure 32 on page 283
- Batch and PL/I**                      Figure 33 on page 283
- IMS and PL/I**                        Figure 34 on page 284

```

:
:   WORKING-STORAGE SECTION.
:
:       05 WS-MQOPEN                PIC X(8) VALUE 'CSQBOPEN'.
:
:   PROCEDURE DIVISION.
:
:       CALL WS-MQOPEN WS-HCONN
:           MQOD
:           WS-OPTIONS
:           WS-HOBJ
:           WS-COMPCODE
:           WS-REASON.
:
:

```

Figure 24. Dynamic linking using COBOL in the batch environment

```

:
:   WORKING-STORAGE SECTION.
:
:       05 WS-MQOPEN                PIC X(8) VALUE 'CSQCOPEN'.
:
:   PROCEDURE DIVISION.
:
:       CALL WS-MQOPEN WS-HCONN
:           MQOD
:           WS-OPTIONS
:           WS-HOBJ
:           WS-COMPCODE
:           WS-REASON.
:
:

```

Figure 25. Dynamic linking using COBOL in the CICS environment

```

:
:   WORKING-STORAGE SECTION.
:
:       05 WS-MQOPEN                PIC X(8) VALUE 'MQOPEN'.
:
:   PROCEDURE DIVISION.
:
:       CALL WS-MQOPEN WS-HCONN
:           MQOD
:           WS-OPTIONS
:           WS-HOBJ
:           WS-COMPCODE
:           WS-REASON.
:
:
:   * ----- *
:   *
:   *   If the compile option 'DYNAM' is specified
:   *   then you may code the MQ calls as follows
:   *
:   * ----- *
:
:       CALL 'MQOPEN' WS-HCONN
:           MQOD
:           WS-OPTIONS
:           WS-HOBJ
:           WS-COMPCODE
:           WS-REASON.
:
:

```

Figure 26. Dynamic linking using COBOL in the IMS environment

```

:
:   LOAD   EP=CSQBOPEN
:
:   CALL  (15), (HCONN, MQOD, OPTIONS, HOBJ, COMPCODE, REASON), VL
:
:   DELETE EP=CSQBOPEN
:

```

Figure 27. Dynamic linking using assembler language in the batch environment

```

:
:   EXEC CICS LOAD PROGRAM('CSQCOPEN') ENTRY(R15)
:
:   CALL  (15), (HCONN, MQOD, OPTIONS, HOBJ, COMPCODE, REASON), VL
:
:   EXEC CICS RELEASE PROGRAM('CSQCOPEN')
:

```

Figure 28. Dynamic linking using assembler language in the CICS environment

```

:
:   LOAD   EP=MQOPEN
:
:   CALL  (15), (HCONN, MQOD, OPTIONS, HOBJ, COMPCODE, REASON), VL
:
:   DELETE EP=MQOPEN
:

```

Figure 29. Dynamic linking using assembler language in the IMS environment

```

:
typedef void CALL_ME();
#pragma linkage(CALL_ME, OS)
:
main()
{
CALL_ME * csqbopen;
:
csqbopen = (CALL_ME *) fetch("CSQBOPEN");
(*csqbopen)(Hconn, &ObjDesc, Options, &Hobj, &CompCode, &Reason);
:

```

Figure 30. Dynamic linking using C language in the batch environment

```

:
typedef void CALL_ME();
#pragma linkage(CALL_ME, OS)
:
main()
{
CALL_ME * csqopen;
:
EXEC CICS LOAD PROGRAM("CSQCOPEN") ENTRY(csqopen);
(*csqopen)(Hconn,&ObjDesc,Options,&Hobj,&CompCode,&Reason);
:

```

Figure 31. Dynamic linking using C language in the CICS environment

```

:
typedef void CALL_ME();
#pragma linkage(CALL_ME, OS)
:
main()
{
CALL_ME * mqopen;
:
mqopen = (CALL_ME *) fetch("MQOPEN");
(*mqopen)(Hconn,&ObjDesc,Options,&Hobj,&CompCode,&Reason);
:

```

Figure 32. Dynamic linking using C language in the IMS environment

```

:
DCL CSQBOPEN ENTRY EXT OPTIONS(ASSEMBLER INTER);
:
FETCH CSQBOPEN;

CALL CSQBOPEN(HQM,
              MQOD,
              OPTIONS,
              HOBJ,
              COMPCODE,
              REASON);

RELEASE CSQBOPEN;

```

Figure 33. Dynamic linking using PL/I in the batch environment

## Debugging programs

```
      :  
      DCL MQOPEN  ENTRY EXT OPTIONS(ASSEMBLER INTER);  
      :  
      FETCH MQOPEN;  
  
      CALL  MQOPEN(HQM,  
                  MQOD,  
                  OPTIONS,  
                  HOBJ,  
                  COMPCODE,  
                  REASON);  
  
      RELEASE  MQOPEN;
```

Figure 34. Dynamic linking using PL/I in the IMS environment

---

## Debugging your programs

The main aids to debugging MQSeries for OS/390 application programs are the reason codes returned by each API call. See Chapter 5, “Return codes” in the *MQSeries Application Programming Reference* manual for a list of these and for more information, including suggestions for corrective action.

This chapter also suggests other debugging tools that you may want to use in particular environments.

## Debugging CICS programs

You can use the CICS Execution Diagnostic Facility (CEDF) to test your CICS programs interactively without having to modify the program or program-preparation procedure. For more information about EDF, see the *CICS Transaction Server for OS/390 CICS Application Programming Guide*.

### CICS trace

You will probably also find it helpful to use the CICS Trace Control transaction (CETR) to control CICS trace activity. For more information about CETR, see the *CICS Transaction Server for OS/390 CICS-Supplied Transactions* manual.

To determine whether CICS trace is active, display connection status using the CKQC panel. This panel also shows the trace number.

To interpret CICS trace entries, see Table 15 on page 285.

The CICS trace entry for these values is AP0xxx (where xxx is the trace number specified when the CICS adapter was enabled). All trace entries except CSQCTEST are issued by CSQCTRUE. CSQCTEST is issued by CSQCRST and CSQCDSP.

Table 15 (Page 1 of 2). CICS adapter trace entries

Name	Description	Trace sequence	Trace data
CSQCABNT	Abnormal termination	Before issuing END_THREAD ABNORMAL to MQSeries. This is due to the end of the task and therefore an implicit backout could be performed by the application. A ROLLBACK request is included in the END_THREAD call in this case.	Unit of work information. You can use this information when finding out about the status of work. (For example, it can be verified against the output produced by the DISPLAY THREAD command, or the MQSeries for OS/390 log print utility.)
CSQCBACK	Syncpoint backout	Before issuing BACKOUT to MQSeries for OS/390. This is due to an explicit backout request from the application.	Unit of work information.
CSQCCRC	Completion code and reason code	After unsuccessful return from API call.	Completion code and reason code.
CSQCCOMM	Syncpoint commit	Before issuing COMMIT to MQSeries for OS/390. This can be due to a single-phase commit request or the second phase of a two-phase commit request. The request is due to a explicit syncpoint request from the application.	Unit of work information.
CSQCEXER	Execute resolve	Before issuing EXECUTE_RESOLVE to MQSeries for OS/390.	The unit of work information of the unit of work issuing the EXECUTE_RESOLVE. This is the last indoubt unit of work in the resynchronization process.
CSQCGETW	GET wait	Before issuing CICS wait.	Address of the ECB to be waited on.
CSQCGMGD	GET message data	After successful return from MQGET.	Up to 40 bytes of the message data.
CSQCGMGH	GET message handle	Before issuing MQGET to MQSeries for OS/390.	Object handle.
CSQCGMGI	Get message ID	After successful return from MQGET.	Message ID and correlation ID of the message.
CSQCINDL	Indoubt list	After successful return from the second INQUIRE_INDOUBT.	The indoubt units of work list.
CSQCINDO	IBM use only		
CSQCINDS	Indoubt list size	After successful return from the first INQUIRE_INDOUBT and the indoubt list is not empty.	Length of the list. Divided by 64 gives the number of indoubt units of work.
CSQCINQH	INQ handle	Before issuing MQINQ to MQSeries for OS/390.	Object handle.
CSQCLOSH	CLOSE handle	Before issuing MQCLOSE to MQSeries for OS/390.	Object handle.
CSQCLOST	Disposition lost	During the resynchronization process, CICS informs the adapter that it has been cold started so no disposition information regarding the unit of work being resynchronized is available.	Unit of work ID known to CICS for the unit of work being resynchronized.
CSQCNIND	Disposition not indoubt	During the resynchronization process, CICS informs the adapter that the unit of work being resynchronized should not have been indoubt (that is, perhaps it is still running).	Unit of work ID known to CICS for the unit of work being resynchronized.

## Debugging programs

<i>Table 15 (Page 2 of 2). CICS adapter trace entries</i>			
<b>Name</b>	<b>Description</b>	<b>Trace sequence</b>	<b>Trace data</b>
CSQCNORT	Normal termination	Before issuing END_THREAD NORMAL to MQSeries for OS/390. This is due to the end of the task and therefore an implicit syncpoint commit may be performed by the application. A COMMIT request is included in the END_THREAD call in this case.	Unit of work information.
CSQCOPNH	OPEN handle	After successful return from MQOPEN.	Object handle.
CSQCOPNO	OPEN object	Before issuing MQOPEN to MQSeries for OS/390.	Object name.
CSQCPMGD	PUT message data	Before issuing MQPUT to MQSeries for OS/390.	Up to 40 bytes of the message data.
CSQCPMGH	PUT message handle	Before issuing MQPUT to MQSeries for OS/390.	Object handle.
CSQCPMGI	PUT message ID	After successful MQPUT from MQSeries for OS/390.	Message ID and Correlation ID of the message.
CSQCPREP	Syncpoint prepare	Before issuing PREPARE to MQSeries for OS/390 in the first phase of two-phase commit processing. This call can also be issued from the distributed queuing component as an API call.	Unit of work information.
CSQCP1MD	PUTONE message data	Before issuing MQPUT1 to MQSeries for OS/390.	Up to 40 bytes of data of the message.
CSQCP1MI	PUTONE message ID	After successful return from MQPUT1.	Message ID and correlation ID of the message.
CSQCP1ON	PUTONE object name	Before issuing MQPUT1 to MQSeries for OS/390.	Object name.
CSQCRBAK	Resolved backout	Before issuing RESOLVE_ROLLBACK to MQSeries for OS/390.	Unit of work information.
CSQCRGMT	Resolved commit	Before issuing RESOLVE_COMMIT to MQSeries for OS/390.	Unit of work information.
CSQCRMIR	RMI response	Before returning to the CICS RMI (resource manager interface) from a specific invocation.	Architected RMI response value. Its meaning depends of the type of the invocation. These values are documented in the <i>CICS Transaction Server for OS/390 Customization Guide</i> . To determine the type of invocation, look at previous trace entries produced by the CICS RMI component.
CSQCRSYN	Resynchronization	Before the resynchronization process starts for the task.	Unit of work ID known to CICS for the unit of work being resynchronized.
CSQCSETH	SET handle	Before issuing MQSET to MQSeries for OS/390.	Object handle.
CSQCTASE	IBM use only		
CSQCTEST	Trace test	Used in EXEC CICS ENTER TRACE call to verify the trace number supplied by the user or the trace status of the connection.	No data.
CSQCDCFF	IBM use only		

## Debugging TSO programs

The following interactive debugging tools are available for TSO programs:

- TEST tool
- VS COBOL II interactive debugging tool
- INSPECT interactive debugging tool for C and PL/I programs



## Chapter 23. Building your application on OS/2 Warp

The OS/2 publications describe how to build executable applications from the programs you write. This chapter describes the additional tasks, and the changes to the standard tasks, you must perform when building MQSeries for OS/2 Warp applications to run under OS/2 Warp. C, C++, and COBOL programming languages are supported. For information about preparing your C++ programs, see the *MQSeries Using C++* book.

The tasks you must perform to create an executable application using MQSeries for OS/2 Warp vary with the programming language your source code is written in. In addition to coding the MQI calls in your source code, you must add the appropriate language statements to include the MQSeries for OS/2 Warp include files for the language you are using. You should make yourself familiar with the contents of these files. See Appendix G, “MQSeries data definition files” on page 529 for a full description.

### Preparing C programs

#### For DOS and Windows 3.1 only

Applications must be built using the large memory model.

Work in your normal environment; MQSeries for OS/2 Warp requires nothing special.

- You need to link your programs with the appropriate libraries provided by MQSeries:

Library file	Program/exit type
<b>MQM.LIB</b>	server for 32-bit C
<b>MQIC.LIB</b>	client for C

The following command gives an example of compiling the sample program `amqsget0`:

```
icc amqsget0.c /Gm /Gd /B "/pmtyp:vio" /Fe"amqsget0.exe" mqm.lib
```

#### Notes:

- If you are writing an installable service (see Chapter 11, “Installable services and components” in the *MQSeries Programmable System Management* book for further information), link to the `MQMZFLIB` library.
  - If you are producing an XA switch load file for external coordination by an XA-compliant transaction manager such as IBM CICS, Transarc Encina, or Novell Tuxedo, use the `MQRMIASwitch` structure and link to the `MQMXA.LIB` library.
  - If you are writing a CICS exit for use with CICS for OS/2 Version 2.0.1, link to the `MQMCICS.LIB` library. If you are writing a CICS exit for use with CICS Transaction Server for OS/2, Version 4, link to the `MQMCICS3.LIB` library.
- For DOS only:** Your application must also be linked with two of the following libraries, one for each protocol, indicating whether you do or do not require it.

## Preparing C programs

If you require TCP/IP you must also link to SOCKETL from the DOS TCP/IP product.

Library file	Protocol
<b>MQICN.LIB</b>	NetBIOS required
<b>MQICDN.LIB</b>	NetBIOS not required
<b>MQICT.LIB</b>	TCP/IP required
<b>MQICDT.LIB</b>	TCP/IP not required

- You must ensure that you have specified adequate run-time stack and heap sizes:
  - You must link a trusted application with more stack than a normal application. Therefore, a stack size of 200 KB is the recommended minimum.
  - A heap size of 8 KB is the recommended minimum.
- The DLLs must be in the library path (LIBPATH) you have specified.
- If you use lowercase characters whenever possible, you can move from MQSeries for OS/2 Warp to MQSeries on UNIX systems, where use of lowercase is necessary.

## Preparing CICS and Transaction Server programs

Sample C source for a CICS MQSeries transaction is provided by AMQSCIC0.CCS. You build it using the standard CICS facilities.

For CICS for OS/2 Version 2:

1. Add the following lines to the CICSENV.CMD file:

```
UserWrk = 'c:\mqm\d11'  
UserInclude = 'c:\mqm\tools\c\include;c:\mqm\tools\c\samples'
```

If necessary replace c:\mqm with the path on which you installed the sample code.

2. Compile using the command:

```
CICS32TC AMQSCIC0.CCS LIBS(MQM)
```

This is described in the *CICS for OS/2 V2.0.1 Application Programming Guide*.

For CICS Transaction Server for OS/2, Version 4:

1. Add the following lines to the CICSENV.CMD file:

```
UserWrk = 'c:\mqm\d11'  
UserInclude = 'c:\mqm\tools\c\include;c:\mqm\tools\c\samples'
```

If necessary replace c:\mqm with the path on which you installed the sample code.

2. Compile using the command:

```
CICSCTCL AMQSCIC0.CCS LIBS(MQM)
```

This is described in the *Transaction Server for OS/2 Warp, V4 Application Programming Guide*.

You can find more information about supporting CICS transactions in "Using CICS" in the *MQSeries System Administration* book.

## Preparing COBOL programs

To prepare COBOL programs on OS/2, link your programs with one of the following libraries provided by MQSeries:

Library file	Program/exit type
<b>MQMCB16</b>	Server for 16-bit Micro Focus COBOL
<b>MQICCB16</b>	Client for 16-bit Micro Focus COBOL
<b>MQMCBB</b>	Server for 32-bit IBM VisualAge COBOL
<b>MQMCB32</b>	Server for 32-bit Micro Focus COBOL
<b>MQICCB</b>	Client for 32-bit IBM VisualAge COBOL
<b>MQICCB32</b>	Client for 32-bit Micro Focus COBOL

To compile, for example, the sample program amq0put0, using IBM VisualAge COBOL:

1. Set the SYSLIB environment variable to include the path to the MQSeries VisualAge COBOL copybooks:

```
set SYSLIB=<drive>:\mqm\tools\cobol\copybook\VAcobol;%SYSLIB%
```

2. Compile and link the program:

```
cob2 amq0put0.cbl -qlib <drive>:\mqm\tools\lib\mqmcbb.lib
```

(for use on the MQSeries server)

```
cob2 amq0put0.cbl -qlib <drive>:\mqm\tools\lib\mqicccb.lib
```

(for use on the MQSeries client)

**Note:** Although the compiler option CALLINT(SYSTEM) must be used, this is the default for cob2.

To prepare Micro Focus COBOL programs, follow these steps:

1. Compile your applications with the LITLINK directive.
2. Specify adequate run-time stack sizes. You must link a trusted application with more stack than a normal application, so a stack size of 200 KB is the recommended minimum. To do this, use:

```
set cobsw=xxxx
```

3. Link the object file to the run-time system.

Set the LIB environment variable to point to the compiler COBOL libraries.

Link the object file for use on the MQSeries server:

```
cbllink amq0put0.obj mqmcb32.lib
```

or

Link the object file for use on the MQSeries client:

```
cbllink amq0put0.obj mqiccb32.lib
```

4. Add the MQSeries copybook directory (\mqm\tools\cobol\copybook) to the cobcpy environment variable.

```
set cobcpy=c:\mqm\tools\cobol\copybook;%COBCPY%
```

### Preparing Transaction Server programs

To prepare CICS Transaction Server for OS/2, V4 programs using IBM VisualAge COBOL:

1. Add the following lines to the CICSENV.CMD file:

```
UserWrk='c:\mqm\d11'  
UserCobol='IBM'  
UserCobcopy='c:\mqm\tools\cobol\copybook'  
UserCobWork='c:\mq-cics\wrk'
```

Where \mq-cics\wrk is the name of a work directory for output from CICSTRAN and CICSCOMP commands (see steps 2 and 3).

2. Translate your program:

```
CICSTRAN MYPROG.CPP
```

This translates your program to a .CBL program.

3. Compile your program:

```
CICSCOMP MYPROG.CBL
```

4. Link your program:

```
CICSLINK MYPROG.OBJ LIBS(MQMCBB)
```

For further information about this, see the *CICS for OS/2 Customization V3.0, SC33-1581-00* and the *Transaction Server for OS/2 Warp, V4 Application Programming Guide*.

---

### Preparing PL/I programs

Sample PL/I programs are supplied with MQSeries. PL/I include files are also provided so that the C entry points in the MQSeries libraries can be invoked directly.

To prepare a PL/I program:

1. Link your program with one of the libraries listed in "Preparing C programs" on page 289.
2. Ensure that \mqm\tools\pli\include is in your INCLUDE environment variable.
3. Compile your program:

```
pli amqpput0.pli  
ilink amqpput0.obj mqm.lib
```

---

## Chapter 24. Building your application on SINIX or DC/OSx

This chapter describes the additional tasks, and the changes to the standard tasks, you must perform when building MQSeries for SINIX and DC/OSx applications to run under SINIX or DC/OSx. COBOL and C programming languages are supported.

In addition to coding the MQI calls in your source code, you must add the appropriate include files. You should make yourself familiar with the contents of these files. See Appendix G, “MQSeries data definition files” on page 529 for a full description.

---

### Preparing C programs

You need to link your programs with the appropriate library provided by MQSeries.

If you are *not* working in a DCE-threaded environment or using CICS, you must link to one of the following libraries:

Library file	Program/exit type
<i>libmqm.so</i>	server for C
<i>libmqic.so</i>	client for C

If you *are* working in a DCE-threaded environment or using CICS, you must link to the C library, *libmqm\_r.so*.

#### Notes:

1. If you are writing an installable service (see Chapter 11, “Installable services and components” in the *MQSeries Programmable System Management* book for further information), you need to link to the *libmqmzf.so* library. Installable services must not use DCE.
2. If you are producing an XA switch load file for external coordination by an XA-compliant transaction manager such as IBM CICS, Transarc Encina, or Novell Tuxedo, link to the *libmqmxa.so* library in a non-DCE threaded environment and to the *libmqmxa\_r.so* library in a DCE threaded environment.

### C compiler flags

When you compile dynamic libraries, or shared objects, for use with MQSeries for SINIX and DC/OSx, you *must* use the `cc` command in the final step that creates the library or object, and not merely the `ld` command. This is because the `cc` command automatically links various initialization data that is needed for proper dynamic linking and loading.

The order of the libraries specified is important. The following is an example of how to build the sample program `amqsput0` for SINIX:

```
cc -o amqsput0 -lmqm -lmqmcs -lmqzse -lnsl \
-lsocket -ldl -lproc -ltext amqsput0.c
```

## Preparing COBOL programs

For DC/OSx Version cd087, include `-liconv -lresolv` on the above command, as shown below:

```
cc -o amqspu0 -lmqm -lmqmcs -lmqzse -lnsl \
-lsocket -ldl -liconv -lresolv -lmproc -ltext amqspu0.c
```

In the same way, for versions preceding cd087 of DC/OSx, include `-liconv`.

**Note:** If you are using an additional product such as ENCINA, you need to find the appropriate header files. You can do this in two ways:

1. Use the `-I` option to scan the extra include directory, for example:

```
cc -c -I/opt/encina/include amqxaex.c
```

2. Symbolically link the header files into `/usr/include`, for example:

```
ln -s /opt/encina/include/* /usr/include
```

---

## Preparing COBOL programs

You must compile your COBOL programs using the Micro Focus Cobol compiler for SINIX with the LITLINK directive.

You must ensure that you have specified adequate run-time stack sizes; 16 KB is the recommended minimum.

You need to link your program with one of the following:

**libmqmcbprt.o** MQSeries COBOL run-time  
**libmqmcb.so** server for COBOL  
**libmqicb.so** client for COBOL

Export the following variables:

```
COBDIR=/usr/opt/lib/cobol export COBDIR
COBLIB=$COBDIR/coblib export COBLIB
COBCPY=/opt/mqm/inc export COBCPY
LD_LIBRARY_PATH=/opt/lib/cobol/coblib export LD_LIBRARY_PATH
```

## Compiling COBOL programs

To compile a COBOL program like `amq0gbr0.cbl` on MQSeries for SINIX and DC/OSx, enter:

```
$ cob -xU -C warning=2 amq0gbr0.cbl -lmqmb -lmqm \
-lmqmcs -lmqzse -lmproc
```

For DC/OSx Version cd087, include `-liconv -lresolv` on the above command. In the same way, for versions preceding cd087 of DC/OSx, include `-liconv`.

If you want to use the programs on a machine which only has MQSeries client connections, recompile the programs and link them with the `mqicb` library instead of the `mqmcb` library.

**Note:** The `mqicb` and `mqmcb` libraries *must* come before the `mqm` library on the above command line.

If you have DCE, you can link your COBOL batch programs with either DCE threaded libraries or non-DCE threaded libraries.

**Notes:**

1. A single program cannot contain both DCE threaded and non-DCE threaded modules.
2. Programs running under CICS must always be DCE threaded.
3. DCE threaded libraries are referred to as *reentrant*.

If you do not choose to use DCE threaded libraries, remove /opt/dcelocal/bin from your PATH environment variable before calling the COBOL compiler.

If you do choose to use DCE threaded libraries, export the following:

```
$ export COBLIBLIST="/opt/lib/cobol/coblib/liblist_r"
```

**Note:** COBLIBLIST is used only in the Micro Focus Compiler for SINIX. It is the same as the Micro Focus Compiler expression LIBLIST.

## Preparing CICS programs

An XA switch module is provided to enable you to link CICS with MQSeries:

<i>Table 16. Essential Code for CICS applications (SINIX)</i>		
Description	C (source)	C (exec) - add one of the following to your XAD.Stanza
XA initialization routine	amqzscix.c	amqzsc - CICS for Siemens Nixdorf SINIX V2.2

Always link your transactions with the thread safe MQSeries library libmqm\_r.so.

You can find more information about supporting CICS transactions in the *MQSeries for SINIX and DC/OSx System Management Guide*.

## CICS on Open Systems support

MQSeries for SINIX supports CICS on Open Systems by way of the XA interface.

**Note:** MQSeries for DC/OSx does not support CICS.

In order to enable the CICS run-time COBOL library to call MQSeries on UNIX systems, you must add the MQSeries COBOL run-time library module to the run-time library using the following command:

```
cicsmkcobol libmqmcbt.o -lmqm_r
```

It is important to ensure that the COBOL run-time library and CICS are linked to the same (DCE) version of the library. All CICS on Open Systems MQSeries transactions **must** link with libmqm\_r.

## CICS sample transaction

Sample C source for a CICS MQSeries transaction is provided by AMQSCIC0.CCS. You build it using the standard CICS facilities. Compile it using the following commands.

## Linking libraries

Export the following environment variables:

```
export CCFLAGS="-I/opt/mqm/inc -I/opt/mqm/samp"  
export USERLIB="-L/opt/mqm/lib -L/opt/cics/lib -lmqm_r -lmqmcs_r"
```

Unset the lib path.

Then, use the command:

```
cicstcl -l C amqscic0.ccs
```

The transaction reads messages from the transmission queue SYSTEM.SAMPLE.CICS.WORKQUEUE on the default queue manager and places them onto the local queue whose name is contained in the transmission header of the message. Any failures will be sent to the queue SYSTEM.SAMPLE.CICS.DLQ. The sample MQSC script AMQSCIC0.TST may be used to create these queues and sample input queues.

---

## Linking libraries

You need to link your programs with the appropriate library provided by MQSeries.

You must link to one or more of the following libraries:

Library file	Program/exit type
<i>libmqm.so</i>	Server for C
<i>libmqmzse.so</i>	For C
<i>libmqic.so</i>	Client for C
<i>libmqmcs.so</i>	Client for C
<i>libmqmzf.so</i>	Installable service exits for C
<i>libmqmxa.a</i>	XA interface for C

If you are using an additional product such as ENCINA, you need to find the run-time libraries. There are three ways (the first two are preferred, especially if the module is an exit or trigger monitor):

1. Link the libraries into `/usr/lib/`, for example:

```
ln -s /opt/encina/lib/*.so /usr/lib
```

**Note:** You need to check these symbolic links when you install a newer version of ENCINA.

2. Set `LD_LIBRARY_PATH` to include the ENCINA library directory (this is in the environment when you run the programs), for example:

```
LD_LIBRARY_PATH=/opt/encina/lib export LD_LIBRARY_PATH
```

3. Set `LD_RUN_PATH` to include `/opt/encina/lib` when you compile the programs.

To compile an ENCINA program on SINIX which uses the MQI:

```
LD_RUN_PATH=/opt/encina/lib export LD_RUN_PATH  
cc -o amqsaex -I/opt/encina/include amqsaex.c -lmqm -lmqmcs \\  
-lmqmcs -lmqmzse -lnsl -lsocket -lencina -ldl -lmproc -lxt
```

For DC/OSx, include `-liconv` on the above command line.

---

## Chapter 25. Building your application on Sun Solaris

This chapter describes the additional tasks, and the changes to the standard tasks, you must perform when building MQSeries for Sun Solaris applications to run under Sun Solaris. COBOL, C, and C++ programming languages are supported. For information about preparing your C++ programs, see the *MQSeries Using C++* book.

In addition to coding the MQI calls in your source code, you must add the appropriate include files. You should make yourself familiar with the contents of these files. See Appendix G, “MQSeries data definition files” on page 529 for a full description.

---

### Preparing C programs

Precompiled C programs are supplied in the `/opt/mqm/samp/bin` directory. To build a sample from source code, use a supported compiler (see Appendix A, “Language compilers and assemblers” on page 453 for more information).

To compile, for example, the sample program `amqsput0`:

1. `export LIB=/opt/mqm/lib;$LIB`
2. Ensure the environment is set to use the correct versions of the compiler software and man pages:

```
export PATH=/opt/SUNWspro/bin:$PATH
export MANPATH=/opt/SUNWspro/man:/usr/man:$MANPATH
export LD_LIBRARY_PATH= \
/opt/SUNWspro/lib:$OPENWINHOME/lib:$LD_LIBRARY_PATH
```

3. Compile the program (the order of the libraries specified is important):

```
cc -o <amqsput0> <amqsput0>.c -mt -lmqm -lmqmcs -lmqmzse \
-lsocket -lnsl -ldl
```

If you wish to compile a DCE application, use the following:

```
cc -o <amqsput0> <amqsput0>.c -mt -lmqm -lmqmcs_d -lmqmzse \
-ldce -lthread -lsocket -lnsl -ldl
```

If you use the unsupported compiler `/usr/ucb/cc`, your application may compile and link successfully. However when you run it, it will fail when it attempts to connect to the queue manager.

If you want to use the programs on a machine which has only the MQSeries client for Sun Solaris installed, recompile the programs to link them with the client library instead:

```
cc -o <amqsput0> <amqsput0>.c -lmqic -lmqmcs -lsocket
```

To build an MQSeries client application that uses DCE, enter:

```
cc -o <amqsput0> <amqsput0>.c -mt -lmqic -lmqmcs_d -lmqmzse \
-ldce -lm -lpthread -lsocket -lc -lnsl -ldl
```

### Linking libraries

You must link with the MQSeries libraries that are appropriate for your application type:

Program/exit type	Library files
Server for C	libmqm.so, libmqmcs.so, and libmqmzse.so
Client for C	libmqic.so, libmqmcs.so, and libmqmzse.so
Server for C with DCE	libmqm.so, libmqmcs_d.so, and libmqmzse.so
Client for C with DCE	libmqic.so, libmqmcs_d.so, and libmqmzse.so

#### Notes:

1. If you are writing an installable service (see Chapter 11, "Installable services and components" in the *MQSeries Programmable System Management* book for further information), link to the libmqmzf.so library.
2. If you are producing an XA switch load file for external coordination by an XA-compliant transaction manager such as IBM CICS, Transarc Encina, or Novell Tuxedo, link to the libmqmxa.a library.
3. To run the sample Encina program, link against the following libraries in addition to the libraries listed above.

- libmqmxa.a

Also, link against libmqmcs\_d.so instead of libmqmcs.so, in addition to the Encina and DCE libraries:

- libEncServer.so
- libEncina.so
- libdce.so

---

## Preparing COBOL programs

Before preparing your COBOL programs, you should check with your system administrator that the COBOL compiler is set up to link with the correct C libraries. By default, the COBOL compiler Version 3.2 links to 3.0 SPARCompiler C libraries. For example, to update the compiler to link with SPARCompiler Version 4.0, ensure that your system administrator has completed the following:

1. Change directory to \$COBDIR/coblib:

```
cd $COBDIR/coblib
```

**Note:** By default, COBDIR is /opt/lib/cobol.

2. Make a backup copy of liblist:

```
cp liblist liblist.saved
```

3. Edit the liblist file using a standard UNIX editor like vi:

```
vi liblist
```

4. Change all references from SC3.0 to SC4.0.

The COBOL compiler is now set up for you to compile COBOL programs.

Precompiled COBOL programs are supplied in the /opt/mqm/samp/bin directory. Use the Micro Focus compiler from the directory /opt/bin to build a sample from source code.

To compile, for example, the sample program amq0put0:

1. Ensure that the environment is set:

```
export COBDIR=/opt/lib/cobol
export PATH=/opt/bin:$PATH
export LD_LIBRARY_PATH=$COBDIR/coblib:$LD_LIBRARY_PATH
```

**Note:** The above assumes that COBOL is installed in the default directories.

2. Define the location of the copybooks which declare the MQI structures:

```
export COBCPY="/opt/mqm/inc"
```

3. Link your program with one of the following libraries when building the application:

**libmqmcb.so** Server for COBOL  
**libmqicb.so** Client for COBOL

4. Compile the program:

```
cob -vxP amq0put0.cbl -lmqmcb -lmqm -lmqmcs -lmqmzse
```

## Preparing CICS programs

XA switch modules are provided to enable you to link CICS with MQSeries:

Table 17. Essential Code for CICS applications (Sun Solaris)

Description	C (source)	C (exec) - add one of the following to your XAD.Stanza
XA initialization routine	amqzscix.c	amqzsc - TXSeries for Sun Solaris

Always link your transactions with the thread safe MQSeries library libmqm\_so.

You can find more information about supporting CICS transactions in "Using CICS" in the *MQSeries System Administration* book.

## CICS on Open Systems support

MQSeries on UNIX systems supports CICS on Open Systems by way of the XA interface.

You must ensure that CICS COBOL applications are linked to the threaded version of the library. CICS on Open Systems MQSeries transactions must link with libmqm\_r, except on Sun Solaris, where you must link with lmqmcs\_d.

### Preparing CICS COBOL programs using Micro Focus COBOL

To use Micro Focus COBOL, follow these steps:

1. Add the MQSeries COBOL run-time library module to the run-time library using the following command:

```
cicsmkcobol /opt/mqm/lib/libmqmcbprt.o -lmqmcs_d
```

This creates the Micro Focus COBOL language method file and enables the CICS run-time COBOL library to call MQSeries on UNIX systems.

**Note:** cicsmkcobol must be run only when one of the following is installed:

New version or release of Micro Focus COBOL

## Preparing CICS programs

```
|           New version or release of TXSeries for Sun Solaris
|           New version or release of any supported database product (for COBOL
|           transactions only)
|           TXSeries for Sun Solaris
|
| 2. Export the following environment variables:
|           COBCPY=/opt/mqm/inc export COBCPY
|           LDFLAGS="-L/usr/mqm/lib -lmqmc_d" export LDFLAGS
|
| 3. Translate, compile, and link the program by typing:
|           cicstcl -l COBOL -e <yourprog>.ccp
```

## Preparing CICS C programs

You build CICS C programs using the standard CICS facilities:

```
| 1. Export one of the following environment variables:
|           • LDFLAGS = "-L/opt/mqm/lib -L/opt/cics/lib -lmqmc_d -lmqm -lmqzse
|             -lsocket -lnsl -ldl"
|
| 2. Translate, compile, and link the program by typing:
|           cicstcl -l C amqscic0.ccs
```

**CICS C sample transaction:** Sample C source for a CICS MQSeries transaction is provided by AMQSCIC0.CCS. The transaction reads messages from the transmission queue SYSTEM.SAMPLE.CICS.WORKQUEUE on the default queue manager and places them onto the local queue whose name is contained in the transmission header of the message. Any failures are sent to the queue SYSTEM.SAMPLE.CICS.DLQ. The sample MQSC script AMQSCIC0.TST may be used to create these queues and sample input queues.

---

## Chapter 26. Building your application on Tandem NSK

The sample programs and the sample compilation and binding scripts, provided in subvolume ZMQSSMPL, illustrate the main features of the MQI in MQSeries for Tandem NSK, and demonstrate how to compile and bind an application.

This chapter describes some minor differences between the standard Version 2 MQI interface, as documented in the *MQSeries Application Programming Reference* manual, and the MQI interface for MQSeries for Tandem NSK.

---

### Unit of work (transaction) management

Transaction management is performed under the control of Tandem's TM/MP product, rather than by MQSeries itself. See "Syncpoints in MQSeries for Tandem NSK applications" on page 194 for details.

### General design considerations

Please note that:

- The MQI library (bound into the application process) does not open \$RECEIVE and does not open \$TMP (TM/MP transaction pseudo-file) itself, so you may code your application to use these features.
- The MQI library uses a SERVERCLASS\_SEND\_() call in initial communication with the Queue Manager. While connected, it maintains two process file opens (with the LINKMON process and a Local Queue Manager Agent) and a small number of disk file opens (fewer than 10).

### MQGMO\_BROWSE\_\* with MQGMO\_LOCK

As a consequence of the use of TM/MP, MQGMO\_BROWSE\_\* with MQGMO\_LOCK is not supported.

### Triggered applications

Triggered MQSeries applications in the Tandem NSK environment receive user data through environment variables set up in the TAACL process that is running. This is because there is a limit to the length of the argument list that can be passed to a Tandem C process.

## Building applications on Tandem NSK

In order to access this information, triggered applications should contain code similar to the following (see sample amqsinqa for more details):

```
MQTMC2 *trig;                /* trigger message structure */
MQTMC2 trigdata;            /* trigger message structure */
char    *applId;
char    *envData;
char    *usrData;
char    *qmName;

/*****
/*
/*  Set the program argument into the trigger message
/*
/*
/*****
trig = (MQTMC2*)argv[1];      /* -> trigger message */

/* get the environment variables and load the rest of the trigger */
memcpy(&trigdata, trig, sizeof(trigdata));

memset(trigdata.ApplId, ' ', sizeof(trigdata.ApplId));
memset(trigdata.EnvData, ' ', sizeof(trigdata.EnvData));
memset(trigdata.UserData, ' ', sizeof(trigdata.UserData));
memset(trigdata.QMgrName, ' ', sizeof(trigdata.QMgrName));

if( (applId = getenv("TRIGAPPLID")) != 0)
{
    strncpy( trigdata.ApplId ,applId, strlen(applId) );
}

if ( (envData = getenv("TRIGENVDATA")) != 0)
{
    strncpy( trigdata.EnvData , envData, strlen(envData) );
}

if ( (usrData = getenv("TRIGUSERDATA")) != 0)
{
    strncpy( trigdata.UserData, usrData, strlen(usrData) );
}

if ( (qmName = getenv("TRIGQMGRNAME")) != 0)
{
    strncpy( trigdata.QMgrName, qmName, strlen(qmName) );
}

trig = &trigdata;
```

---

## Compiling and binding applications

The MQSeries for Tandem NSK V2.2 MQI is implemented using the Tandem wide memory model (the int datatype is 4 bytes) and the Common Run-time Environment (CRE). Applications must be compatible with this environment in order to work correctly. Refer to the sample build files for the correct options for each compiler in order to ensure compatibility.

In particular, TAL and COBOL applications must follow the rules that are required for compatibility with the CRE, documented in the Tandem manuals relating to the CRE.

Four versions of the MQI library are delivered with MQSeries for Tandem NSK V2.2, contained in ZMQSLIB. You must ensure that you use the correct library, as follows:

<b>mqmlibc</b>	for C, nonnative
<b>mqmlibt</b>	for TAL or COBOL, nonnative
<b>mqmlibnc</b>	for native C
<b>mqmlibtnt</b>	for native TAL or COBOL

---

## Running applications

In order to be able to connect to a queue manager, the environment of an application program must be correctly defined:

- The PARAM MQDEFAULTPREFIX is mandatory in the environment of all applications.
- If you have chosen an alternative (nondefault) location for your MQSINI file, an application will not be able to connect to the queue manager if the PARAM MQMACHINIFILE is not set correctly.
- TAL and COBOL applications must have the PARAM SAVE-ENVIRONMENT ON defined in their environment, or they will not be able to connect to the queue manager.

An application may run as either low-pin or high-pin. MQSeries executables themselves are configured to run as high-pin.

MQSeries applications are supported in the NSK environment only. No support for OSS applications is provided.

An MQSeries application may run under PATHWAY, from TACL, or as a child process of another process. Applications can even be added to the queue manager PATHWAY configuration itself, provided they behave correctly on queue manager shutdown.



---

## Chapter 27. Building your application on VSE/ESA

This chapter describes the additional tasks, and the changes to the standard tasks, you must perform when building MQSeries for VSE/ESA applications to run under MQSeries for VSE/ESA. C, COBOL, and PL/I programming languages are supported.

---

### Linking library

The object decks required by MQSeries for VSE/ESA applications are held in the install sublibrary PRD2.MQSERIES (this is its default name). Reference the sublibrary in a LIBDEF statement in the compile JCL:

```
// LIBDEF SEARCH=(PRD2.MQSERIES,PRD2.SCEECICS,PRD2.SCEEBASE)
```

The MQSeries object code is autolinked into the application.

---

### Using the batch interface

If you invoke the MQSeries API from a VSE/ESA batch application, you must link-edit a special object module, which intercepts and handles the MQSeries calls, with the usercode by specifying:

```
INCLUDE MQBIBTCH
```

as part of the link-edit JCL.

---

### Preparing C programs

You must meet the requirements of the COBOL language interface when you write C programs. There are no sample programs provided but an include file, equivalent to the COBOL copybooks, is supplied. It is called CMQC.H, and it declares everything required.

---

### Preparing COBOL programs

Sample programs and copybooks are provided in COBOL for VSE/ESA.

---

### Preparing PL/I programs

You must meet the requirements of the COBOL language interface when you write PL/I programs. There are no sample programs provided but two include files, equivalent to the COBOL copybooks, are supplied:

**CMQEPP.P** Declares the MQI calls and structures

**CMQP.P** Declares the MQI constants



---

## Chapter 28. Building your application on Windows

This chapter describes the additional tasks, and the changes to the standard tasks, you must perform when building MQSeries for Windows applications to run under Windows. C and Visual Basic programming languages are supported.

The tasks you must perform to create an executable application using MQSeries for Windows depend on the language in which your source code is written. In addition to coding the MQI calls in your source code, you must add the appropriate language statements to include the MQSeries for Windows data definition files for the language you are using. You should be aware of the contents of these files. See Appendix G, "MQSeries data definition files" on page 529 for a full description.

---

### Linking libraries

You need to link your programs with the appropriate libraries provided by MQSeries:

Library file	Program
<b>MQM.LIB</b>	server for 32-bit C
<b>MQM16.LIB</b>	server for 16-bit C

---

### Preparing Visual Basic programs

To prepare Visual Basic programs on Windows client:

1. Create a new project.
2. Add the supplied module file, CMQB.BAS, to the project.
3. Add other supplied module files if you need them:
  - CMQBB.BAS** MQAI support.
  - CMQCFB.BAS** PCF support.
  - CMQXB.BAS** Channel exits support.

Call the procedure MQ\_SETDEFAULTS before making any MQI calls in the project code. This procedure sets up default structures that the MQI calls require.

Specify that you are creating an MQSeries client, before you compile or run the project, by setting the conditional compilation variable *MqType* to 2 as follows:

- In a Visual Basic version 4 project:
  1. Select the Tools menu.
  2. Select Options.
  3. Select the Advanced tab in the dialog box.
  4. In the Conditional Compilation Arguments field, enter this:
 

```
MqType=2
```
- In a Visual Basic version 5 project:
  1. Select the Project menu.
  2. Select *Name* Properties (where *Name* is the name of the current project).
  3. Select the Make tab in the dialog box.
  4. In the Conditional Compilation Arguments field, enter this:
 

```
MqType=2
```



## Chapter 29. Building your application on Windows NT

The Windows NT publications describe how to build executable applications from the programs you write. This chapter describes the additional tasks, and the changes to the standard tasks, you must perform when building MQSeries for Windows NT applications to run under Windows NT. ActiveX, C, C++, COBOL, PL/I, and Visual Basic programming languages are supported. For information about preparing your ActiveX programs, see the *MQSeries for Windows NT Using the Component Object Model Interface* book. For information about preparing your C++ programs, see the *MQSeries Using C++* book.

The tasks you must perform to create an executable application using MQSeries for Windows NT vary with the programming language your source code is written in. In addition to coding the MQI calls in your source code, you must add the appropriate language statements to include the MQSeries for Windows NT include files for the language you are using. You should make yourself familiar with the contents of these files. See Appendix G, "MQSeries data definition files" on page 529 for a full description.

### Preparing C programs

#### For DOS and Windows 3.1 only

Applications must be built using the large memory model.

Work in your normal environment; MQSeries for Windows NT requires nothing special.

- You need to link your programs with the appropriate libraries provided by MQSeries:

Library file	Program/exit type
<b>MQM.LIB</b>	server for 32-bit C
<b>MQIC32.LIB</b>	client for 32-bit C

The following command gives an example of compiling the sample program `amqsget0` (using the Microsoft Visual C++® compiler):

```
cl amqsget0.c /link mqm.lib
```

#### Notes:

- If you are writing an installable service (see Chapter 11, "Installable services and components" in the *MQSeries Programmable System Management* book for further information), you need to link to the `MQMZF.LIB` library.
- If you are producing an XA switch load file for external coordination by an XA-compliant transaction manager such as IBM TXSeries, Transarc Encina, or Novell Tuxedo, use the `MQRMIXASwitch` structure and link to the `MQMXA.LIB` library.
- If you are producing an XA switch load file using the `MQRMIXASwitchDynamic` structure, link to the Encina `MQMENC.LIB` library.

## Preparing C programs

4. To build the Encina sample, link against the following libraries:

- MQM.LIB
- MQMENC.LIB

Also, link against the Encina and DCE libraries:

- libEncServer.lib
- libEncina.lib
- libdce.lib

5. If you are writing a CICS exit, link to the MQMCICS.LIB library.

6. If an application is to make changes to environment variables, such as MQSERVER, you must link it to the same C run-time libraries as those used by MQSeries. Use the '-MD' compile switch to accomplish this.

- **For DOS only:** Your application must also be linked with two of the following libraries, one for each protocol, indicating whether you do or do not require it. If you require TCP/IP you must also link to SOCKETL from the DOS TCP/IP product.

Library file	Protocol
<b>MQICN.LIB</b>	NetBIOS required
<b>MQICDN.LIB</b>	NetBIOS not required
<b>MQICT.LIB</b>	TCP/IP required
<b>MQICDT.LIB</b>	TCP/IP not required

- You must ensure that you have specified adequate run-time heap and stack sizes. A heap size of 8 KB and stack size of 16 KB are the recommended minimum size.
- The DLLs must be in the path (PATH) you have specified.
- If you use lowercase characters whenever possible, you can move from MQSeries for Windows NT to MQSeries on UNIX systems, where use of lowercase is necessary.

## Preparing CICS and Transaction Server programs

Sample C source for a CICS MQSeries transaction is provided by AMQSCIC0.CCS. You build it using the standard CICS facilities:

For CICS for Windows NT V2:

1. Add the following lines to the CICSENV.CMD file:

```
UserWork = 'c:\mqm\dll'  
UserIncl = 'c:\mqm\tools\c\include;c:\mqm\tools\c\samples'
```

If necessary replace c:\mqm with the path on which you installed the sample code.

2. Edit the CICSCCL.CMD file (found in <drive>:\CNT200\UTIL) and add the library mqm.lib to the set of libraries.

3. To the LIB environment variable add:

```
<drive>:\MQM\TOOLS\LIB
```

4. To the INCLUDE environment variable add:

```
<drive>:\MQM\TOOLS\C\INCLUDE  
<drive>:\CNT200\INCLUDE
```

5. Compile using the command:

```
CICSCTCL AMQSCIC0
```

This is described in the *CICS for Windows NT V2.0 Application Programming Guide*.

For TXSeries for Windows NT, V4:

1. Set the environment variable (enter the following on one line):

```
set CICS_IBMC_FLAGS=-IC:\Program Files\MQSeries\Tools\C\Include;
%CICS_IBMC_FLAGS%
```

2. Set the USERLIB environment variable:

```
set USERLIB=MQM.LIB;%USERLIB%
```

3. Translate, compile, and link the sample program:

```
cicstcl -l IBMC amqscic0.ccs
```

This is described in the *Transaction Server for Windows NT Application Programming Guide (CICS) V4*.

You can find more information about supporting CICS transactions in “Using CICS” in the *MQSeries System Administration* book.

## Preparing COBOL programs

To prepare COBOL programs on Windows NT, link your program to one of the following libraries provided by MQSeries:

Library file	Program/exit type
<b>MQMCBB</b>	server for 32-bit IBM COBOL
<b>MQMCB32</b>	server for 32-bit Micro Focus COBOL
<b>MQICBB</b>	client for 32-bit IBM COBOL
<b>MQICCB32</b>	client for 32-bit Micro Focus COBOL
<b>MQMCB16</b>	server for 16-bit Micro Focus COBOL
<b>MQICCB16</b>	client for 16-bit Micro Focus COBOL

When you are running a program in the MQI client environment, ensure the DOSCALLS library appears before any COBOL or MQSeries library.

### Micro Focus

You must relink any existing MQSeries Micro Focus COBOL programs using either mqmcb3.lib or mqiccb32.lib rather than the mqmcbb and mqicbb libraries.

To compile, for example, the sample program amq0put0, using IBM VisualAge COBOL:

1. Set the SYSLIB environment variable to include the path to the MQSeries VisualAge COBOL copybooks (enter the following on one line):

```
set SYSLIB=<drive>:\Program Files\MQSeries\
Tools\Cobol\COPYBOOK\VAcobol;%SYSLIB%
```

## Preparing COBOL programs

2. Compile and link the program (enter the following examples on one line):

```
cob2 amq0put0.cbl -qlib <drive>:\Program Files\MQSeries\  
Tools\Lib\mqmccb.lib
```

(for use on the MQSeries server)

```
cob2 amq0put0.cbl -qlib <drive>:\Program Files\MQSeries\  
Tools\Lib\mqicccb.lib
```

(for use on the MQSeries client)

**Note:** Although the compiler option CALLINT(SYSTEM) must be used, this is the default for cob2.

To compile, for example, the sample program amq0put0, using Micro Focus COBOL:

1. Set the COBCPY environment variable to point to the MQSeries COBOL copybooks (enter the following on one line):

```
set COBCPY=<drive>:\Program Files\MQSeries\  
Tools\Cobol\Copybook
```

2. Compile the program to give you an object file:

```
cobol amq0put0 LITLINK
```

3. Link the object file to the run-time system.

Set the LIB environment variable to point to the compiler COBOL libraries.

Link the object file for use on the MQSeries server:

```
cbllink amq0put0.obj mqmcb32.lib
```

or

Link the object file for use on the MQSeries client:

```
cbllink amq0put0.obj mqiccb32.lib
```

## Preparing CICS and Transaction Server programs

To compile and link a TXSeries for Windows NT, V4 program using IBM VisualAge COBOL:

1. Set the environment variable (enter the following on one line):

```
set CICS_IBMCOB_FLAGS=c:\Program Files\MQSeries\Tools\  
Cobol\Copybook\VAcobol;%CICS_IBMCOB_FLAGS%
```

2. Set the USERLIB environment variable:

```
set USERLIB=MQMCBB.LIB
```

3. Translate, compile, and link your program:

```
cicstcl -l IBMCOB myprog.ccp
```

This is described in the *Transaction Server for Windows NT, V4 Application Programming Guide*.

To compile and link a CICS for Windows NT V2 program using Micro Focus COBOL:

- Edit the CICS LINK.CMD file and add the library mqmccb.lib to the set of libraries. (This file is called by the CICSTCL.CMD utility.)

- Set the COBCPY environment variable:

```
set
cobcpy=<drive>:\mqm\tools\cobo1\copybook;<drive>:\cnt200\copybook
```

- To the LIB environment variable add:

```
<drive.>:\mqm\tools\lib
<drive.>:\cobo132\lib
```

- Edit the CICSCOMP.COMD file, change LITLINK(2) to LITLINK to enable link-time, not run-time resolution of the MQI calls.

- Compile using the command:

```
CICSTCL MQMXADC
```

Where MQMXADC.CCP (not actually provided as a sample program) is the name of the program. This creates a MQMXADC.DLL.

This is described in the *CICS for Windows NT V2.0 Application Programming Guide*.

---

## Preparing PL/I programs

Sample PL/I programs are supplied with MQSeries. PL/I include files are also provided so that the C entry points in the MQSeries libraries can be invoked directly.

To prepare a PL/I program:

1. Link your program with one of the libraries listed in “Preparing C programs” on page 309.
2. Ensure that \mqm\tools\pli\include is in your INCLUDE environment variable.
3. Compile your program:

```
pli amqpput0.pli
ilink amqpput0.obj mqm.lib
```

---

## Preparing Visual Basic programs

To prepare Visual Basic programs on Windows NT:

1. Create a new project.
2. Add the supplied module file, CMQB.BAS, to the project.
3. Add other supplied module files if you need them:

```
CMQBB.BAS  MQAI support.
CMQCFB.BAS PCF support.
CMQXB.BAS Channel exits support.
```

Call the procedure MQ\_SETDEFAULTS before making any MQI calls in the project code. This procedure sets up default structures that the MQI calls require.

Specify whether you are creating an MQSeries server or client, before you compile or run the project, by setting the conditional compilation variable *MqType*.

## Preparing Visual Basic programs

Set *MqType* to 1 for a server or 2 for a client as follows:

- In a Visual Basic version 4 project:
  1. Select the Tools menu.
  2. Select Options.
  3. Select the Advanced tab in the dialog box.
  4. In the Conditional Compilation Arguments field, enter this for a server:  
MqType=1  
or this for a client:  
MqType=2
  
- In a Visual Basic version 5 project:
  1. Select the Project menu.
  2. Select *Name* Properties (where *Name* is the name of the current project).
  3. Select the Make tab in the dialog box.
  4. In the Conditional Compilation Arguments field, enter this for a server:  
MqType=1  
or this for a client:  
MqType=2

---

## Chapter 30. Using lightweight directory access protocol services with MQSeries for Windows NT

This chapter explains what a directory service is and the part played by a directory access protocol (DAP). It also explains how MQSeries applications can use a lightweight directory access protocol (LDAP) directory using a sample program as a guide.

**Note:** The sample program is designed for someone who is already familiar with LDAP.

---

### What is a directory service?

A directory is a repository of information about objects, which is organized in such a way that it is easy to find the information on a specific object. A common example is a telephone directory, where information (address and telephone number) is stored about people and companies. Another example is an address book for an e-mail system, where e-mail addresses, and optionally other information such as telephone numbers, are stored for people.

On computer systems, directories can store information about computer resources, such as printers or shared disks. For example you could use a directory to find out where the nearest color printer is located. In an MQSeries application a directory can be used to provide the association between an application service (such as accounts-receivable processing) and the queue to be used for messages requiring that service (possibly identified through the queue name and its host queue manager name).

Directories are implemented as client-server systems, where the directory server holds all the information and answers requests from clients. The clients could be user-interface programs, which provide the information directly to the user, or application programs which need to locate resources to complete their work. A Directory Service comprises the directory server, administrative programs, and the client libraries and programs which are needed to configure, update, and read the directory.

---

### What is LDAP?

Many directory services exist, such as Novell Directory Services, DCE Cell Directory Service, Banyan StreetTalk, Windows NT Directory Services, X.500, and the address book services associated with e-mail products. X.500 was proposed as a standard for global directory services by the International Standards Organization (ISO). It requires an OSI protocol stack for its communications, and largely because of this, its use has been restricted to large organizations and academic institutions. An X.500 directory server communicates with its clients using the Directory Access Protocol (DAP).

LDAP (Lightweight Directory Access Protocol) was created as a simplified version of DAP. It is easier to implement, omits some of the lesser-used features of DAP, and runs over TCP/IP. As a result of these changes it is rapidly being adopted as the directory access protocol for most purposes, replacing the multitude of proprietary protocols previously used. LDAP clients can still access an X.500

server through a gateway (X.500 still requires the OSI protocol stack), or increasingly X.500 implementations typically include native support for LDAP as well as DAP access.

LDAP directories can be distributed and can use replication to enable efficient access to their contents.

For a more complete description of LDAP, please see the IBM Redbook *Understanding LDAP*.

---

## Using LDAP with MQSeries

In MQSeries configurations, the information that defines message and transmission queues is stored locally. This means that in an MQSeries network the various definitions are distributed, with no central directory of this information being available for browsing. Remote messaging between MQSeries applications is commonly achieved through the use of local definitions of remote queues. The application first issues an MQOPEN call using the name specified in the local definition of the remote queue. To put the message on the remote queue, the application then issues MQPUT, specifying the handle returned from the MQOPEN call. The remote queue definition supplies the name of the destination queue, the destination queue manager, and optionally, a transmission queue. In this technique the application has to know at run-time the name specified in the local queue definition.

A variation on the above avoids the use of local definitions of remote queues. The application can specify the full destination queue name, which includes the remote queue manager name as part of the MQOPEN. The application therefore has to know these two names at run-time. Again the local queue manager must be correctly configured with the local queue definition, and with a suitably named (or default) transmission queue and an associated channel that delivers to the target.

In the case where both the source and target queue managers are defined as being members of the same cluster, then the transmission queue and channel aspects of the above two scenarios can be ignored. If the target transmission queue is a cluster queue then a local definition of a remote queue is also not required. However, similarly to the previous cases described, the application must still know the name of the destination queue.

A directory service can be used to remove this application dependency on queue names (or the combination of queue and queue manager names). The mapping between application criteria and MQSeries object names can be held in a directory and be updated dynamically, and independently of applications. At run-time the MQSeries application wishing to send a message first queries the directory using application-based criteria, for example where: `service_name = "accounts receivable"`, retrieves the relevant MQSeries object names, and then uses these returned values in the MQOPEN call.

Another example of the use of a directory is for a company that has many small depots or offices, MQSeries clients may be used to send messages to MQSeries servers located in the larger offices. The clients need to know the name of the host machine, MQI channel, and queue name for each server they send messages to. Occasionally it may be necessary to move an MQSeries server to another machine; every client that communicates with the server would need to know about the

change. An LDAP directory service could be used to store the names of the host machines (and the channel and queue names) and the client programs could retrieve the information from the directory whenever they want to send a message to a server. In this case only the directory needs to be updated if a host name (or channel or queue name) changed.

Multiple destinations for an application message could be stored in a directory, with the one chosen being dependent on availability or load-sharing considerations.

---

### LDAP sample program

The sample program is designed for someone who is familiar with LDAP and probably already uses it. It is intended to show how MQSeries applications can use an LDAP directory.

### Building the sample program

This program has been built and tested only on Windows NT using TCP/IP. As well as the general considerations mentioned in "Preparing C programs" on page 309 the following points must be observed:

- This program is designed to run as a client program, so it should be linked with the MQIC32.LIB library.
- As well as the MQSeries header files and libraries, this program must be built using LDAP client header files and libraries. These are available from several locations, including the IBM eNetwork™ Web site at:

<http://www.software.ibm.com/enetwork>

For example, using the IBM eNetwork client, the program should be linked with the LIBLDAPSTATICE.LIB and LIBLBERSTATICSSL.LIB libraries.

### Configuring the directory

Before the sample program can be run, an LDAP Directory Server must be configured with sample data. The file MQuser.ldif contains some sample data in LDIF (LDAP Data Interchange Format). You can edit this file to suit your needs. It contains data for a fictitious company called MQuser that has a Transport Department comprising three offices. Each of these offices has a machine that runs an MQSeries server.

As a minimum you must edit the three lines that contain the host names of the machines running the MQSeries servers - these are lines 18, 27, and 36:

```
host: LondonHost
...
host: SydneyHost
...
host: WashingtonHost
```

You must change "LondonHost", "SydneyHost", and "WashingtonHost" to the names of three of your machines which run MQSeries servers. You may also change the channel and queue names if you wish (the sample uses names of the system defaults). You may also wish to increase or decrease the number of offices in the sample data.

### Configuring the IBM eNetwork LDAP server

Refer to the eNetwork LDAP Directory Administrator's Guide for information about installing the directory. In the chapter "Installing and Configuring Server", work through the sections "Installing Server" and "Basic Server Configuration". If necessary, read through the chapter "Administrator Interface" to familiarize yourself with how the interface works.

In the chapter "Configuring - How Do I", follow the instructions for starting up the administrator, then work through the section "Configure Database" and create a default database. Skip the section "Configure replica" and using the section "Work with Suffixes", add a suffix "o=MQuser".

Before adding any entries to the database, you must extend the directory schema by adding some attribute definitions and an objectclass definition. This is described in the eNetwork LDAP Directory Administrator's Guide in the chapter "Reference Information" under the section "Directory Schema". Two sample files are included to help you with this. The file "mq.at.conf" includes the attribute definitions which you must add to the file "/etc/slapd.at.conf". Do this by including the sample file by editing slapd.at.conf and adding a line:

```
include <pathname>/mq.at.conf
```

Alternatively you can edit the file slapd.at.conf and add the contents of the sample file directly to it, that is, add the lines:

```
# MQ attribute definitions
attribute mqChannel          ces    mqChannel          1000    normal
attribute mqQueueManager    ces    mqQueueManager    1000    normal
attribute mqQueue            ces    mqQueue            1000    normal
attribute mqPort             cis    mqPort             64      normal
```

Similarly for the objectclass definition, you can either include the sample file by editing "etc/slapd.oc.conf" and add the line:

```
include <pathname>/mq.oc.conf
```

or you can add the contents of the sample file directly to slapd.oc.conf, that is, add the lines:

```
# MQ object classdefinition
objectclass mqApplication
    requires
        objectClass,
        cn,
        host,
        mqChannel,
        mqQueue
    allows
        mqQueueManager,
        mqPort,
        description,
        l,
        ou,
        seeAlso
```

You can now start the directory server (Administration, Server, Startup) and add the sample entries to it. To add the sample entries, go to the Administration, Add

Entries page of the administrator, type in the full pathname of the sample file "MQuser.ldif" and click the Submit button.

The directory server is now running and loaded with data suitable for running the sample program.

## Configuring the Netscape directory server

Using the Netscape Server Administration page, click on "Create New Netscape Directory Server". You should now be presented with a form containing configuration information. Change the Directory Suffix to "o=MQuser" and add a password for the Unrestricted User. You may also, if you wish, change any other information to suit your installation. Click on the OK button, and the directory should be created successfully. Click on "Return to Server Administration" and start the directory server. Click on the directory name to start the Directory Server Administration server for the new directory.

Before adding any entries to the database, you must extend the directory schema by adding some attribute definitions and an objectclass definition. Click on the "Schema" tab of the Directory Server page. You are now presented with a form that allows you to add new attributes. Add the following attributes (the Attribute OID can be left blank for all of them):

Attribute Name	Syntax
-----	-----
mqChannel	Case Exact String
mqQueueManager	Case Exact String
mqQueue	Case Exact String
mqPort	Integer

Add a new objectClass by clicking "Create ObjectClass" in the side panel. Enter "mqApplication" as the ObjectClass Name, select "applicationProcess" as the parent ObjectClass and leave the ObjectClass OID blank. Now add some attributes to the objectClass. Select "host", "mqChannel", and "mqQueue" as Required Attributes, and select "mqQueueManager" and "mqPort" as Allowed attributes. Press the "Create New ObjectClass" button to create the objectClass.

To add the sample data, click on the "Database Management" tab and select "Add Entries" from the side panel. You must enter the pathname of the sample data file <pathname>\MQuser.ldif, enter the password, and click on the OK button.

The sample program runs as an unauthorized user, and by default the Netscape Directory does not allow unauthorized users to search the directory. You must change this by clicking the "Access Control" tab. Enter the password for the Unrestricted User and click the OK button to load in the access control entries for the directory. These should currently be empty. Press the "New ACI" button to create a new access control entry. In the entry box which appears, click on the word "Deny" (which is underlined) and in the resultant dialog box, change it to "Allow". Add a name, for example, "MQuser-access", and click on "choose a suffix" to select "o=MQuser". Enter "o=MQuser" as the target, enter the password for the Unrestricted User, and click on the "Submit" button.

The directory server is now running and loaded with data suitable for running the sample program.

### Running the sample program

You should now have an LDAP Directory Server running and populated with the sample data. The data specifies three host machines all of which should be running MQSeries servers. You should ensure that the default queue manager is running on each machine (unless you changed the sample data to specify a different queue manager). You should also start the MQSeries listener program on each machine; the sample uses TCP/IP with the default MQSeries port number, so you can start the listener with the command:

```
runmqlsr -t tcp
```

To test the sample, you might also wish to run a program to read the messages arriving at each MQSeries server, for example you could use the “amqstrg” sample program:

```
amqstrg SYSTEM.DEFAULT.LOCAL.QUEUE
```

The sample program uses three environment variables, one required and two optional. The required variable is LDAP\_BASEDN, which specifies the base Distinguished Name for the directory search. To work with the sample data, you should set this to “ou=Transport, o=MQuser”, for example in a Windows NT Command Window type:

```
set LDAP_BASEDN=ou=Transport, o=MQuser
```

The optional variables are LDAP\_HOST and LDAP\_VERSION. The LDAP\_HOST variable specifies the name of the host where the LDAP server is running, it defaults to the local host if it is not specified. The LDAP\_VERSION variable specifies the version of the LDAP protocol to be used, and can be either 2 or 3. Most LDAP servers now support version 3 of the protocol; they all support the older version 2. This sample works equally well with either version of the protocol, and if it is not specified it defaults to version 2.

You can now run the sample by typing the program name followed by the name of the MQSeries application you wish to send messages to, in the case of the sample data the application names are “London”, “Sydney”, and “Washington”. For example, to send messages to the London application:

```
amqs1dpc London
```

If the program fails to connect to the MQSeries server, an appropriate error message will appear. If it connects successfully you can start typing messages, each line you type (terminated by <return> or <enter>) is sent as a separate message, an empty line ends the program.

### Program design

The program has two distinct parts: the first part uses the environment variables and command line value to query an LDAP directory server; the second part establishes the MQSeries connection using the information returned from the directory and sends the messages.

The LDAP calls used in the first part of the program differ slightly depending on whether LDAP version 2 or 3 is being used, and they are described in detail by the documentation which comes with the LDAP client libraries. This section gives a brief description.

The first part of the program checks that it has been called correctly and reads the environment variables. It then establishes a connection with the LDAP directory server at the specified host:

```

if (ldapVersion == LDAP_VERSION3)
{
    if ((ld = ldap_init(ldapHost, LDAP_PORT)) == NULL)
        ...
}
else
{
    if ((ld = ldap_open(ldapHost, LDAP_PORT)) == NULL )
        ...
}

```

When a connection has been established, the program sets some options on the server with the "ldap\_set\_option" call, and then authenticates itself to the server by binding to it:

```

if (ldapVersion == LDAP_VERSION3)
{
    if (ldap_simple_bind_s(ld, bindDN, password) != LDAP_SUCCESS)
        ...
}
else
{
    if (ldap_bind_s(ld, bindDN, password, LDAP_AUTH_SIMPLE) !=
        LDAP_SUCCESS)
        ...
}

```

In the sample program "bindDN" and "password" are set to NULL, which means that the program authenticates itself as an anonymous user, that is, it does not have any special access rights and can access only information which is publicly available. In practice most organizations would restrict access to the information they store in directories so that only authorized users can access it.

The first parameter to the bind call "ld" is a handle which is used to identify this particular LDAP session throughout the rest of the program. After authenticating, the program searches the directory for entries which match the application name:

```

rc = ldap_search_s(ld,          /* LDAP Handle          */
                  baseDN,      /* base distinguished name */
                  LDAP_SCOPE_ONELEVEL, /* one-level search    */
                  filterPattern, /* filter search pattern */
                  attrs,        /* attributes required  */
                  FALSE,        /* NOT attributes only  */
                  &ldapResult); /* search result        */

```

This is a simple synchronous call to the server which returns the results directly. There are other types of search which are more appropriate for complex queries or when a large number of results is expected. The first parameter to the search is the handle "ld" which identifies the session. The second parameter is the base distinguished name, which specifies where in the directory the search is to begin, and the third parameter is the scope of the search, that is, which entries relative to the starting point are searched. These two parameters together define which entries in the directory are searched. The next parameter, "filterPattern" specifies what we are searching for. The "attrs" parameter lists the attributes which we want

to get back from the object when we have found it. The next attribute says whether we want just the attributes or their values as well, setting this to FALSE means that we want the attribute values. The final parameter is used to return the result.

The result could contain many directory entries, each with the specified attributes and their values. We have to extract the values we want from the result. In this sample program we only expect one entry to be found, so we only look at the first entry in the result:

```
ldapEntry = ldap_first_entry(ld, ldapResult);
```

This call returns a handle which represents the first entry, and we set up a for loop to extract all the attributes from the entry:

```
for (attribute = ldap_first_attribute(ld, ldapEntry, &ber);
     attribute != NULL;
     attribute = ldap_next_attribute(ld, ldapEntry, ber ))
{
```

For each of these attributes, we extract the values associated with it. Again we only expect one value per attribute, so we only use the first value; we determine which attribute we have and store the value in the appropriate program variable:

```
values = ldap_get_values(ld, ldapEntry, attribute);
if (values != NULL && values[0] != NULL)
{
    if (strcmp(attribute, MQ_HOST_ATTR) == 0)
    {
        mqHost = strdup(values[0]);
        ...
    }
}
```

Finally we tidy up by freeing memory (ldap\_value\_free, ldap\_memfree, ldap\_msgfree) and close the session by “unbinding” from the server:

```
ldap_unbind(ld);
```

We check that we have found all the MQSeries values we need from the directory, and if so we call sendMessages() to connect to the MQSeries server and send the MQSeries messages.

The second part of the sample program is the sendMessages() routine which contains all of the MQSeries calls. This is modelled on the amqsput0 sample program, the differences being that the parameters to the program have been extended and MQCONN is used instead of the MQCONN call.

---

## Part 4. Sample MQSeries programs

<b>Chapter 31. Sample programs (all platforms except OS/390)</b>	327
Features demonstrated in the sample programs	327
Samples for Digital OpenVMS and UNIX systems	328
Samples for OS/2 Warp and Windows NT	330
PL/I samples for AIX, OS/2 Warp, and Windows NT	331
Visual Basic samples for Windows NT	332
Samples for AS/400	333
Samples for Tandem NSK	334
Samples for VSE/ESA	335
Preparing and running the sample programs	336
AS/400	336
UNIX systems	336
Digital OpenVMS	337
OS/2 and Windows NT	338
Tandem NSK	339
Windows	340
Running the sample programs	340
The Put sample programs	342
Running the amqsput and amqsputc samples	342
Running the amqsputw sample	343
Running the amq0put sample	344
Running the AMQSPUT4 C sample	344
Running the AMQ0PUT4 COBOL sample	344
Design of the Put sample program	345
The Distribution List sample program	345
Running the Distribution List sample, amqsptl0	345
Design of the Distribution List sample	345
The Browse sample programs	346
OS/2, UNIX systems, Digital OpenVMS, and Windows NT	346
AS/400	346
Design of the Browse sample program	347
The Browser sample program	347
The Get sample programs	349
Running the amqsget and amqsgetc samples	349
Running the amqsgetw sample	349
Running the amq0get sample	350
Running the AMQSGET4 and the AMQ0GET4 samples	350
Design of the Get sample program	351
The Reference Message sample programs	351
Notes for AS/400 users	352
Running the Reference Message samples	352
Design of the Put Reference Message sample (amqsprma.c)	357
Design of the Reference Message Exit sample (amqsxrma.c, AMQSXRM4)	358
Design of the Get Reference Message sample (amqsgrma.c)	359
The Request sample programs	359
Running the amqsreq0.c, amqsreq, and amqsreqc samples	360
Running the amq0req0.cbl sample	360
Running the AMQSREQ4 sample	360
Running the AMQ0REQ4 sample	361
Running the Request sample using triggering	361

Design of the Request sample program	364
The Inquire sample programs	366
Design of the Inquire sample program	366
The Set sample programs	367
Design of the Set sample program	368
The Echo sample programs	369
Design of the Echo sample programs	369
The Data-Conversion sample program	370
Design of the data-conversion sample	370
The Triggering sample programs	371
Running the amqstrg0.c, amqstrg, and amqstrgc samples	371
Running the AMQSTRG4 sample	371
Design of the triggering sample	371
Running the AMQSERV4 sample	372
Design of the trigger server	372
Ending the triggering sample programs on AS/400	372
Running the samples using remote queues	373
Database coordination samples	373
Creating the databases and tables	375
Preparing, compiling, and linking the samples	376
Running the samples	377
The CICS transaction sample	379
TUXEDO samples	379
Building the server environment	379
Server sample program for TUXEDO	388
Put sample program for TUXEDO	389
Get sample for TUXEDO	390
Encina sample program	390
Building the AMQSXAE0.C sample	390
Dead-letter queue handler sample	391
The Connect sample program	391
Running the amqscnxc sample	392
<b>Chapter 32. Sample programs for MQSeries for OS/390</b>	395
Features demonstrated in the sample applications	395
Put samples	395
Get samples	396
Browse sample	396
Print Message sample	396
Queue Attributes sample	397
Mail Manager sample	397
Credit Check sample	398
The Message Handler sample	398
Distributed queuing exit samples	399
Data-conversion exit samples	399
Preparing and running sample applications for the batch environment	399
Names of the sample batch applications	400
Preparing sample applications for the TSO environment	401
Names of the sample TSO applications	401
Preparing the sample applications for the CICS environment	403
QLOP abend	404
Names of the sample CICS applications	404
Preparing the sample application for the IMS environment	407
Names of the sample IMS application	408

The Put samples	408
Design of the Put sample	408
The Put samples for the batch environment	409
The Put samples for the CICS environment	410
The Get samples	411
Design of the Get sample	411
The Get samples for the CICS environment	413
The Browse sample	414
Design of the Browse sample	414
Language-dependent design considerations	416
The Print Message sample	416
Design of the sample	418
The Queue Attributes sample	420
Design of the sample	420
The Mail Manager sample	421
Preparing the sample	422
Running the sample	422
Design of the sample	424
The Credit Check sample	430
Preparing and running the Credit Check sample	430
Design of the sample	432
Design considerations	439
The Credit Check sample with multiple queue managers	442
The IMS extension to the Credit Check sample	442
The Message Handler sample	443
Preparing and running the sample	443
Using the sample	444
Design of the sample	446



---

## Chapter 31. Sample programs (all platforms except OS/390)

This chapter describes the sample programs delivered with MQSeries, written in C, COBOL, PL/I, and TAL. The samples demonstrate typical uses of the Message Queue Interface (MQI).

The samples are not intended to demonstrate general programming techniques, so some error checking that you may want to include in a production program has been omitted. However, these samples are suitable for use as a base for your own message queuing programs.

The source code for all the samples is provided with the product; this source includes comments that explain the message queuing techniques demonstrated in the programs.

**DCE sample exit:** For information on compiling and linking the DCE sample exit (amqsdc0.c) see “Supplied channel-exit programs using DCE security services” in the *MQSeries Intercommunication* book.

**C++ sample programs:** See the *MQSeries Using C++* book for a description of the sample programs available in C++.

**RPG sample programs:** See the *MQSeries for AS/400 Application Programming Reference (RPG)* manual for a description of the sample programs available in RPG.

The names of the samples start with the prefix amq, except for TAL programs that start zmq. The fourth character indicates the programming language, and the compiler where necessary.

s	C language
o	COBOL language on both IBM and Micro Focus compilers
i	COBOL language on IBM compilers only
m	COBOL language on Micro Focus compilers only
v	COBOL language on DEC COBOL V2.3 and subsequent releases
p	PL/I language

---

### Features demonstrated in the sample programs

The following tables show the techniques demonstrated by the MQSeries sample programs on all systems except OS/390 (see Chapter 32, “Sample programs for MQSeries for OS/390” on page 395). All the samples open and close queues using the MQOPEN and MQCLOSE calls, so these techniques are not listed separately in the tables. See the heading that includes the platform you are interested in:

- “Samples for Digital OpenVMS and UNIX systems” on page 328
- “Samples for OS/2 Warp and Windows NT” on page 330
- “PL/I samples for AIX, OS/2 Warp, and Windows NT” on page 331
- “Samples for AS/400” on page 333
- “Samples for Tandem NSK” on page 334

## Samples for Digital OpenVMS and UNIX systems

Table 18 shows the techniques demonstrated by the sample programs for MQSeries on UNIX systems and MQSeries for Digital OpenVMS.

<i>Table 18 (Page 1 of 2). MQSeries on UNIX and Digital OpenVMS sample programs demonstrating use of the MQI</i>				
<b>Technique</b>	<b>C (source) (1)</b>	<b>COBOL (source) (2)</b>	<b>C (executable)</b>	<b>Client (3) (executable)</b>
Putting messages using the MQPUT call	amqsput0 amqsputw	amq0put0	amqsput	amqsputc amqsputw
Putting a single message using the MQPUT1 call	amqsinqa amqsecha	amqminqx amqmechx amqiinqx amqiechx amqvinqx amqviechx	amqsinq amqsech	no sample
Putting messages to a distribution list (4)	amqsptl0	no sample	amqsptl	amqsptlc
Replying to a request message	amqsinq0	amqminqx amqiinqx amqvinqx	amqsinq	no sample
Getting messages (no wait)	amqsgbr0	amq0gbr0	amqsgbr	no sample
Getting messages (wait with a time limit)	amqsget0 amqsgetw	amq0get0	amqsget	amqsgetc amqsgetw
Getting messages (unlimited wait)	amqstrg0	no sample	amqstrg	amqstrgc
Getting messages (with data conversion)	amqsecha	no sample	amqsech	no sample
Putting reference messages to a queue (4)	amqsprma	no sample	amqsprm	amqsprmc
Getting reference messages from a queue (4)	amqrgma	no sample	amqsgrm	amqsgrmc
Reference message channel exit (4)	amqsqrma amqsxrma	no sample	amqsxrm	no sample
Browsing first 20 characters of a message	amqsgbr0	amq0gbr0	amqsgbr	no sample
Browsing complete messages	amqsbcg0	no sample	amqsbcg	no sample
Using a shared input queue	amqsinq0	amqminqx amqiinqx amqvinqx	amqsinq	no sample
Using an exclusive input queue	amqstrg0	amq0req0	amqstrg	amqstrgc
Using the MQINQ call	amqsinqa	amqminqx amqiinqx amqvinqx	amqsinq	no sample
Using the MQSET call	amqsseta	amqmsetx amqisetx amqvsetx	amqsset	no sample
Using a reply-to queue	amqsreq0	amq0req0	amqsreq	no sample
Requesting message exceptions	amqsreq0	amq0req0	amqsreq	no sample
Accepting a truncated message	amqsgbr0	amq0gbr0	amqsgbr	no sample
Using a resolved queue name	amqsgbr0	amq0gbr0	amqsgbr	no sample
Triggering a process	amqstrg0	no sample	amqstrg	amqstrgc
Using data conversion	(5)	no sample	no sample	no sample

Table 18 (Page 2 of 2). MQSeries on UNIX and Digital OpenVMS sample programs demonstrating use of the MQI

Technique	C (source) (1)	COBOL (source) (2)	C (executable)	Client (3) (executable)
MQSeries (coordinating XA-compliant database managers) accessing a single database using SQL (4)	amqsxas0.sqc	amq0xas0.sqb	no sample	no sample
MQSeries (coordinating XA-compliant database managers) accessing two databases using SQL (4)	amqsxag0.c amqsxab0.sqc amqsxaf0.sqc	amq0xag0.cbl amq0xab0.sqb amq0xaf0.sqb	no sample	no sample
CICS transaction (6)	amqscic0.ccs	no sample	amqscic0	no sample
Encina transaction (4)	amqsxae0	no sample	amqsxae0	no sample
TUXEDO transaction to put messages (7)	amqstpx	no sample	no sample	no sample
TUXEDO transaction to get messages (7)	amqstxgx	no sample	no sample	no sample
Server for TUXEDO (7)	amqstxsx	no sample	no sample	no sample
Dead-letter queue handler	(8)	no sample	amqsdldq	no sample
From an MQI client, putting a message	amqsputw	no sample	no sample	amqsputc amqsputw
From an MQI client, getting a message	amqsgetw	no sample	no sample	amqsgetc amqsgetw
Connecting to the queue manager using MQCONN	amqscnxc	no sample	no sample	amqscnxc

**Notes:**

1. The executable version of the MQSeries client samples share the same source as the samples that run in a server environment.
2. COBOL is not supported by MQSeries for AT&T GIS UNIX. Compile programs beginning 'amqm' with the Micro Focus COBOL compiler, beginning 'amqi' with the IBM COBOL compiler, and beginning 'amq0' with either.
3. The executable versions of the MQSeries client samples are not available on MQSeries for HP-UX or MQSeries for Digital OpenVMS.
4. Supported on MQSeries for AIX, HP-UX, and Sun Solaris only.
5. On MQSeries for AIX, HP-UX, and Sun Solaris this program is called amqsvfc0.c. On MQSeries for Digital OpenVMS, AT&T GIS UNIX, and SINIX and DC/OSx this program is called amqsvfcx.c.
6. CICS is supported by MQSeries for AIX and MQSeries for HP-UX only.
7. TUXEDO is not supported by MQSeries for Digital OpenVMS, AS/400, and Windows.
8. The source for the dead-letter queue handler is made up of several files and provided in a separate directory.

## Samples for OS/2 Warp and Windows NT

Table 19 shows the techniques demonstrated by the sample programs for MQSeries for OS/2 Warp and Windows NT.

<i>Table 19 (Page 1 of 2). MQSeries for OS/2 Warp and Windows NT sample programs demonstrating use of the MQI</i>				
<b>Technique</b>	<b>C (source)</b>	<b>COBOL (source)</b>	<b>C (executable)</b>	<b>Client (executable)</b>
Putting messages using the MQPUT call	amqsput0	amq0put0	amqsput	amqsputc amqsputw
Putting a single message using the MQPUT1 call	amqsinqa amqsecha	amqminq2 amqmehc2 amqiinq2 amqiech2	amqsinq amqsech	amqsinqc amqsechc
Putting messages to a distribution list	amqsptl0	no sample	amqsptl	amqsptlc
Replying to a request message	amqsinq0	amqminq2 amqiinq2	amqsinq	amqsinqc
Getting messages (no wait)	amqsgbr0	amq0gbr0	amqsgbr	amqsgbrc
Getting messages (wait with a time limit)	amqsget0 amqsgetw	amq0get0	amqsget	amqsgetc amqsgetw
Getting messages (unlimited wait)	amqstrg0	no sample	amqstrg	amqstrgc
Getting messages (with data conversion)	amqsecha	no sample	amqsech	amqsechc
Putting reference messages to a queue	amqsprma	no sample	amqsprm	amqsprmc
Getting reference messages from a queue	amqsgрма	no sample	amqsgrm	amqsgrmc
Reference message channel exit	amqsqrma amqsxrma	no sample	amqsxrm	no sample
Browsing first 20 characters of a message	amqsgbr0	amq0gbr0	amqsgbr	amqsgbrc
Browsing complete messages	amqsbcg0	no sample	amqsbcg	amqsbcgc
Using a shared input queue	amqsinq0	amqminq2 amqiinq2	amqsinq	amqsinqc
Using an exclusive input queue	amqstrg0	amq0req0	amqstrg	amqstrgc
Using the MQINQ call	amqsinqa	amqminq2 amqiinq2	amqsinq	amqsinqc
Using the MQSET call	amqsseta	amqmset2 amqiset2	amqsset	amqssetc
Using a reply-to queue	amqsreq0	amq0req0	amqsreq	amqsreqc
Requesting message exceptions	amqsreq0	amq0req0	amqsreq	amqsreqc
Accepting a truncated message	amqsgbr0	amq0gbr0	amqsgbr	amqsgbrc
Using a resolved queue name	amqsgbr0	amq0gbr0	amqsgbr	amqsgbrc
Triggering a process	amqstrg0	no sample	amqstrg	amqstrgc
Using data conversion	amqsvfc0	no sample	no sample	no sample
CICS transaction	amqscic0.ccs	no sample	amqscic0 (1)	no sample
TUXEDO transaction to put messages (Windows NT only)	amqstxpx	no sample	no sample	no sample

Table 19 (Page 2 of 2). MQSeries for OS/2 Warp and Windows NT sample programs demonstrating use of the MQI

Technique	C (source)	COBOL (source)	C (executable)	Client (executable)
TUXEDO transaction to get messages (Windows NT only)	amqstxgx	no sample	no sample	no sample
Server for TUXEDO (Windows NT only)	amqstxsx	no sample	no sample	no sample
Encina transaction	amqsxae0	no sample	amqsxae0	no sample
Dead-letter queue handler	(2)	no sample	amqsdldq	no sample
From an MQSeries client, putting a message	amqsputw	no sample	no sample	amqsputc amqsputw
From an MQSeries client, getting a message	amqsgetw	no sample	no sample	amqsgetc amqsgetw
Connecting to the queue manager using MQCONN	amqscnxc	no sample	no sample	amqscnxc
<b>Notes:</b>				
1. The executable version on OS/2 is for CICS Transaction Server for OS/2, Version 4; the version on Windows NT is for TXSeries for Windows NT, Version 4.				
2. The source for the dead-letter queue handler is made up of several files and provided in a separate directory.				

The following list shows the techniques demonstrated by the MQSeries for Windows sample programs:

Sample program	Technique
<b>AMQSPUTW</b>	Putting a message on a specified queue
<b>AMQSGETW</b>	Getting a message from a specified queue
<b>AMQSBCGW</b>	Browsing a message and its header

For further information about these sample programs, see the following:

- *MQSeries for Windows V2.0 User's Guide.*
- *MQSeries for Windows V2.1 User's Guide.*

## PL/I samples for AIX, OS/2 Warp, and Windows NT

Table 20 shows the techniques demonstrated by the MQSeries for AIX, MQSeries for OS/2 Warp, and MQSeries for Windows NT sample programs.

Table 20. MQSeries for AIX, OS/2 Warp, and Windows NT sample programs demonstrating use of the MQI

Technique	PL/I (source)	PL/I (executable)
Putting messages using the MQPUT call	amqpput0	no sample
Getting messages (wait with a time limit)	amqpget0	no sample

## Visual Basic samples for Windows NT

Table 21 shows the techniques demonstrated by the MQSeries for Windows NT sample programs.

A project may contain several files. When you open a project within Visual Basic the other files will be loaded automatically. No executable programs are provided.

All the sample projects, except mqtrivc.vbp, are set up to work with the MQSeries server. To find out how to change the sample projects to work with the MQSeries clients see "Preparing Visual Basic programs" on page 313.

*Table 21. MQSeries for Windows NT sample programs demonstrating use of the MQI*

<b>Technique</b>	<b>Project file name</b>
Putting messages using the MQPUT call	amqsputb.vbp
Getting messages using the MQGET call	amqsgetb.vbp
Browsing a queue using the MQGET call	amqsbcbg.vbp
Simple MQGET and MQPUT sample (client)	mqtrivc.vbp
Simple MQGET and MQPUT sample (server)	mqtrivs.vbp
Putting and getting strings and user-defined structures using MQPUT and MQGET	strings.vbp
Using PCF structures to start and stop a channel	pcfsamp.vbp
Creating a queue using the MQAI	amqsaicq.vbp
Listing a queue manager's queues using the MQAI	amqsailq.vbp
Monitoring events using the MQAI	amqsaiem.vbp

## Samples for AS/400

Table 22 shows the techniques demonstrated by the MQSeries for AS/400 sample programs. Some techniques occur in more than one sample program, but only one program is listed in the table.

Technique	C (source)	COBOL (source)
Using the MQCONN and MQDISC calls	AMQSECHA, AMQSINQA	AMQ0ECHA, AMQ0INQA
Implicitly connecting and disconnecting	AMQSPUT4	AMQ0PUT4
Putting messages using the MQPUT call	AMQSPUT4	AMQ0PUT4
Putting a single message using the MQPUT1 call	AMQSINQA, AMQSECHA	AMQ0INQA, AMQ0ECHA
Putting messages to a distribution list	AMQSPTL0	no sample
Replying to a request message	AMQSINQA	AMQ0INQA
Getting messages (no wait)	AMQSGBR4	AMQ0GBR4
Getting messages (wait with a time limit)	AMQSGET4	AMQ0GET4
Getting messages (unlimited wait)	AMQSTRG4	no sample
Getting messages (with data conversion)	AMQSECHA	AMQ0ECHA
Putting reference messages to a queue	AMQSPRMA	no sample
Getting reference messages from a queue	AMQSGRMA	no sample
Reference message channel exit	AMQSQRM4, AMQSXRM4	no sample
Message exit	AMQSCMX4	no sample
Browsing first 20 characters of a message	AMQSGBR4	AMQ0GBR4
Browsing complete messages	AMQSBCG0	no sample
Using a shared input queue	AMQSINQA	AMQ0INQA
Using an exclusive input queue	AMQSREQ4	AMQ0REQ4
Using the MQINQ call	AMQSINQA	AMQ0INQA
Using the MQSET call	AMQSSETA	AMQ0SETA
Using a reply-to queue	AMQSREQ4	AMQ0REQ4
Requesting message exceptions	AMQSREQ4	AMQ0REQ4
Accepting a truncated message	AMQSGBR4	AMQ0GBR4
Using a resolved queue name	AMQSGBR4	AMQ0GBR4
Triggering a process	AMQSTRG4	no sample
Trigger server	AMQSERV4	no sample
Using a trigger server (including CICS transactions)	AMQSERV4	no sample
Using data conversion	AMQSVFC4	no sample

In addition to these, the MQSeries for AS/400 sample option includes a sample data file which can be used as input to the sample programs, AMQSDATA and sample CL programs that demonstrate administration tasks. The CL samples are described in the *MQSeries for AS/400 Administration Guide*. You could use the

## Features demonstrated

sample CL program amqsamp4 to create queues to use with the sample programs described in this chapter.

## Samples for Tandem NSK

The following C and COBOL sample programs are supplied with MQSeries for Tandem NSK, Version 2.2:

Description	C (source)	C (executable)	COBOL85 (source)	COBOL85 (executable)
Putting messages using the MQPUT call	amqsput0	amqsput	amq0put0	amq0put
Putting a single message using the MQPUT1 call	amqsinqa	amqsinq	No sample	No sample
Getting messages (no wait)	amqsgbr0	amqsgbr	amq0gbr0	amq0gbr
Getting messages (wait with a time limit)	amqsget0	amqsget	amq0get0	amq0get
Getting messages (unlimited wait)	amqstrg0	amqstrg	No sample	No sample
Getting messages (with data conversion)	amqsecha	amqsech	amq0ech0	amq0ech
Browsing complete messages	amqsbcg0	amqsbcg	No sample	No sample
Use a shared input queue	No sample	No sample	amq0inq0	amq0inq
Using the MQSET call	amqsseta	amqsset	amq0set0	amq0set
Using a reply-to queue	amqsreq0	amqsreq	amq0req0	amq0req
Using data conversion	amqsvfcn	No sample	No sample	No sample
Sample skeleton for channel exit	amqsvchn	No sample	No sample	No sample

The following TAL sample programs are supplied with MQSeries for Tandem NSK Version 2.2:

Description	TAL (source)	TAL (executable)
Read <i>n</i> messages from a queue	zmqreadt	zmqread
Write <i>n</i> messages of <i>n</i> length to a queue	zmqwritt	zmqwrit

## Samples for VSE/ESA

Table 25 shows the techniques demonstrated by the MQSeries for VSE/ESA COBOL sample programs.

<i>Table 25. MQSeries for VSE/ESA COBOL sample programs demonstrating use of the MQI</i>		
<b>Description</b>	<b>COBOL (source)</b>	<b>COBOL (executable)</b>
Transaction that demonstrates MQI calls (1)	TTPTST2.Z	TTPTST2
Test facility that starts the sample transaction TTPTST2 (2)	TTPTST3.Z	TTPTST3
Triggered test program that echoes a message from a queue to a reply-to queue	MQPECHO.Z	MQPECHO
<b>Notes:</b> <ol style="list-style-type: none"> <li>1. Demonstrates MQGET, MQINQ, MQPUT, MQPUT1, both MQPUT and MQGET, MQGET and delete, MQPUT and reply.</li> <li>2. Each TTPTST2 that is started is a task.</li> </ol>		

---

### Preparing and running the sample programs

The following sections help you find the samples that you need to run on the different platforms.

#### AS/400

The MQSeries for AS/400 sample programs are provided in library QMQMSAMP as members of QCSRC, QLBLSRC, QCBLLSRC. Before you can run the samples, you must compile them as you would any other MQSeries for AS/400 applications.

For more details see Chapter 18, “Building your application on AS/400” on page 265.

#### UNIX systems

Table 26. Where to find the samples for MQSeries on UNIX systems

Content	Directory
source files	/mqmtop/samp
C source file for Windows 3.1 sample	/mqmtop/win_client/samp
dead-letter queue handler source files	/mqmtop/samp/dlq
executable files	/mqmtop/samp/bin
Other MQSeries client executable files	/mqmtop/dos_client/samp/bin /mqmtop/os2_client/samp/bin /mqmtop/win_client/samp/bin
<b>Note:</b> For MQSeries for AIX <b>mqmtop</b> is usr/mqm, for MQSeries for other UNIX systems <b>mqmtop</b> is opt/mqm.	

The MQSeries on UNIX systems sample files will be in the directories listed in Table 26 if the defaults were used at installation time. To run the samples, either use the executable versions supplied or compile the source versions as you would any other applications, using an ANSI compiler. For information on how to do this, see “Running the sample programs” on page 340.

## Digital OpenVMS

*Table 27. Where to find the samples for MQSeries for Digital OpenVMS*

<b>Content</b>	<b>Directory</b>
source files	MQS_EXAMPLES
C source file for Windows 3.1 sample	[.WIN_CLIENT.SAMP] under MQS_EXAMPLES
dead-letter queue handler source files	[.DLQ] under MQS_EXAMPLES
executable files	[.BIN] under MQS_EXAMPLES
Other MQSeries client executable files	[.DOS_CLIENT.SAMP.BIN] under MQS_EXAMPLES [OS2_CLIENT.SAMP.BIN] under MQS_EXAMPLES [WIN_CLIENT.SAMP.BIN] under MQS_EXAMPLES

The MQSeries for Digital OpenVMS sample files are in the directories listed in Table 27 if the defaults were used at installation time. To run the samples, either use the executable versions supplied or compile the source versions as you would any other applications, using an ANSI compiler. For information on how to do this, see “Running the sample programs” on page 340.

## OS/2 and Windows NT

Table 28. Where to find the samples for MQSeries for OS/2 Warp and MQSeries for Windows NT

Content	Directory
C source code	<drive:directory>\MQM\TOOLS\C\SAMPLES <drive:directory>\Program Files\MQSeries\ Tools\C\Samples
Source code for dead-letter handler sample	<drive:directory>\MQM\TOOLS\C\SAMPLES\DLQ <drive:directory>\Program Files\MQSeries\ Tools\C\Samples\DLQ
C source code for Windows 3.1 sample	<drive:directory>\MQM\WIN
COBOL source code	<drive:directory>\MQM\TOOLS\COBOL\SAMPLES <drive:directory>\Program Files\MQSeries\ Tools\Cobol\Samples
C executable files	<drive:directory>\MQM\TOOLS\C\SAMPLES\BIN <drive:directory>\Program Files\MQSeries\ Tools\C\Samples\Bin
Other MQSeries client executable files	<drive:directory>\MQM\DOS <drive:directory>\MQM\AIX <drive:directory>\MQM\WIN
Sample MQSC files	<drive:directory>\MQM\TOOLS\MQSC\SAMPLES <drive:directory>\Program Files\MQSeries\ Tools\MQSC\Samples
PL/I source code	<drive:directory>\MQM\TOOLS\PLI\SAMPLES <drive:directory>\Program Files\MQSeries\ Tools\PLI\Samples
Visual Basic Version 4 source code	<drive:directory>\Program Files\MQSeries\ Tools\Samples\VB\Sampvb4
Visual Basic Version 5 source code	<drive:directory>\Program Files\MQSeries\ Tools\Samples\VB\Sampvb5
<b>Note:</b> The Visual Basic samples are not available for OS/2.	

**Note:** MQSeries for Windows NT samples are in the directories that begin <drive:directory>\Program Files.

The MQSeries for OS/2 Warp and MQSeries for Windows NT sample files will be in the directories listed in Table 28 if the defaults were used at installation time, the <drive:directory> will default to <c:>. To run the samples, either use the executable versions supplied or compile the source versions as you would any other MQSeries for OS/2 Warp or MQSeries for Windows NT applications. For information on how to do this, see "Running the sample programs" on page 340.

## Tandem NSK

See the section for the programming language you are using.

### Building C sample programs

The subvolume ZMQSSMPL contains the following TACL macro files to be used for building sample C applications:

**CSAMP** Usage: CSAMP *source-code-file-name*

This is a basic macro for compiling a source file using the include files contained in subvolume ZMQSLIB. For example, to compile the sample AMQSBCG0, use CSAMP AMQSBCG0. If the compilation is successful, the macro produces an object file with the last character of the file name replaced by the letter O; for example, AMQSBCGO.

**BSAMP** Usage: BSAMP *exe-file-name*

This is a basic macro used to bind an object file with the user libraries in ZMQSLIB. For example, to bind the compiled sample AMQSBCG0, use BSAMP AMQSBCG. The macro produces an executable file called *exe-filenameE*; for example, AMQSBCGE.

**COMPALL** Usage: COMPALL

This TACL macro compiles each of the sample source code files using the CSAMP macro.

**BINDALL** Usage: BINDALL

This TACL macro binds each of the sample object files into executables using the BSAMP macro.

**BUILDC** Usage: BUILDC

This TACL macro compiles and binds all of the C sample files using the macros COMPALL and BINDALL.

### Building COBOL sample programs

The subvolume ZMQSSMPL contains the following files to be used for building sample COBOL applications.

**CCBSMPLS** Usage: CCBSMPLS

This TACL macro compiles each of the COBOL sample source code files.

**BCBSMPLS** Usage: BIND /IN BCBSMPLS/

This bind input file binds each of the COBOL sample object files into executables.

**BUILDCOB** Usage: BUILDCOB

This TACL macro compiles and binds all of the COBOL sample files using the macros CCBSMPLS and BCBSMPLS.

## Preparing and running samples

### Building TAL sample programs

The subvolume ZMQSSMPL contains the following files to be used for building sample TAL programs.

**CTLSMPLS** Usage: CTLSMPLS

This TACL macro compiles each of the TAL sample source code files.

**BTLSMPLS** Usage: BIND /IN BTLSMPLS/

This bind input file binds each of the TAL sample object files into executables.

**BUILD COB** Usage: BUILD COB

This TACL macro compiles and binds all of the TAL sample files using the macros CTLSMPLS and BTLSMPLS.

## Windows

For information about MQSeries for Windows, see the following:

- *MQSeries for Windows V2.0 User's Guide.*
- *MQSeries for Windows V2.1 User's Guide.*

## Running the sample programs

Before you can run any of the sample programs, a queue manager must be created and the default definitions set up. This is explained in "Creating a queue manager" in the *MQSeries System Administration* book for MQSeries for AIX, HP-UX, OS/2, Sun Solaris, and Windows NT; for other platforms, see the appropriate *System Management Guide*.

### On all platforms except AS/400

The samples need a set of queues to work with. Either use your own queues or run the sample MQSC file amqscos0.tst to create a set.

To do this on UNIX systems and Digital OpenVMS, enter:

```
runmqsc QManagerName <amqscos0.tst >/tmp/sampobj.out
```

Check the sampobj.out file to ensure that there are no errors.

To do this on OS/2 and Windows NT enter:

```
runmqsc QManagerName <amqscos0.tst > sampobj.out
```

Check the sampobj.out file to ensure that there are no errors. This file will be found in your current directory.

To do this on Tandem NSK enter:

```
runmqsc -i $SYSTEM.ZMQSSMPL.AMQSCOMA
```

Check the sampobj.out file to ensure that there are no errors. This file will be found in your current directory.

The sample applications can now be run. Enter the name of the sample application followed by any parameters, for example:

```
amqsput myqueue qmanagername
```

where `myqueue` is the name of the queue on which the messages are going to be put, and `qmanagername` is the queue manager that owns `myqueue`.

See the description of the individual samples for information on the parameters that each of them expects.

### On AS/400

You can use your own queues when you run the samples, or you can run the sample program `amqsamp4` to create some sample queues. The source for this program is shipped in file `QCLSRC` in library `QMOMSAMP`. It can be compiled using the `CRTCLPGM` command.

To call one of the sample programs using data from member `PUT` in file `AMQSDATA` of library `QMOMSAMP`, use a command like:

```
CALL PGM(QMOMSAMP/AMQSPUT4) PARM('QMOMSAMP/AMQSDATA(PUT)')
```

The sample data only applies to the C/400 sample programs.

### Length of queue name

For the COBOL sample programs, when you pass queue names as parameters, you must provide 48 characters, padding with blank characters if necessary. Anything other than 48 characters causes the program to fail with reason code 2085.

### Inquire, Set, and Echo examples

For the Inquire, Set, and Echo examples, the sample definitions cause the C versions of these samples to be triggered. If you want the COBOL versions you must change the process definitions:

```
SYSTEM.SAMPLE.INQPROCESS  
SYSTEM.SAMPLE.SETPROCESS  
SYSTEM.SAMPLE.ECHOPROCESS
```

On OS/2, Windows NT, and UNIX do this by editing the `amqscos0.tst` file and changing the C executable file names to the COBOL executable file names before using the `runmqsc` command above.

On AS/400, you can use the `CHGMQMPCR` command (described in the *MQSeries for AS/400 Administration Guide*), or edit and run `AMQSAMP4` with the alternative definition.

### The Put sample programs

The Put sample programs put messages on a queue using the MQPUT call. See “Features demonstrated in the sample programs” on page 327 for the names of these programs.

### Running the amqsput and amqsputc samples

These programs each take 2 parameters:

1. The name of the target queue (required)
2. The name of the queue manager (optional)

If a queue manager is not specified, amqsput connects to the default queue manager and amqsputc connects to the queue manager identified by an environment variable or the client channel definition file. To run these programs, enter one of the following:

```
amqsput myqueue qmanagername
```

```
amqsputc myqueue qmanagername
```

where myqueue is the name of the queue on which the messages are going to be put, and qmanagername is the queue manager that owns myqueue.

## Running the amqspuw sample

This program has no visible interface; all messages are put in the output file.

This program takes 4 parameters:

1. The name of the output file (required)
2. The name of the input file (required)
3. The name of the queue manager (required)
4. The name of the target queue (optional)

To run amqspuw from the Windows program manager:

1. Select File and click on Run...
2. On the run dialog, enter into the command line entry field the program name followed by the parameters.

For example:

```
amqspuw outfile.out infile.in qmanagername myqueue
```

where:

outfile.out is used to hold the messages generated when the program runs.

infile.in contains the data to be put onto the target queue. Each line of data is put as a message. This must be an ASCII file.

qmanagername is the queue manager that owns myqueue.

myqueue is the name of the target queue on which the messages are going to be put. If you don't enter a queue name, the default queue for the queue manager is used.

Here is an example of what you would see in the output file if you supplied a target queue name:

```
Sample AMQSPUTW start
Output file "OUTFILE.OUT" opened
Input file "INFILE.IN" opened
Queue Manager name "QMANAGERNAME" will be used
target queue is MYQUEUE
MQPUT OK - message contents: <AMQSPUTW: Windows Client Test Message 1>
MQPUT OK - message contents: <AMQSPUTW: Windows Client Test Message 2>
MQPUT OK - message contents: <AMQSPUTW: Windows Client Test Message 3>
Sample AMQSPUTW end
```

Here is an example of what you would see in the output file if you did not enter a target queue name (for example, amqspuw outfil2.out c:\infil2.in qmanagem2):

```
Sample AMQSPUTW start
Output file "OUTFIL2.OUT" opened
Input file "C:\INFIL2.IN" opened
Queue Manager name "QMANAGERNAM2" will be used
No parameter for Queue Name. Default Queue Name will be used
target queue is QDEF2.Q
MQPUT OK - message contents: <AMQSPUTW: Windows Client Test Message 1>
MQPUT OK - message contents: <AMQSPUTW: Windows Client Test Message 2>
MQPUT OK - message contents: <AMQSPUTW: Windows Client Test Message 3>
Sample AMQSPUTW end
```

## Put samples

where QDEF2.Q is the name of the default queue for the queue manager.

It is important **always** to look in the output file to see what has happened as there is no visible indication of success or failure when you run this program.

### Running the amq0put sample

The COBOL version does not have any parameters. It connects to the default queue manager and when you run it you are prompted:

Please enter the name of the target queue

It takes input from StdIn and adds each line of input to the target queue. A blank line indicates there is no more data.

### Running the AMQSPUT4 C sample

The C program creates messages by reading data from a member of a source file. You must specify the name of the file as a parameter when you start the program.

The structure of the file must be:

```
queue name
text of message 1
text of message 2

:
text of message n
blank line
```

A sample of input for the put samples is supplied in library QMQMSAMP file AMQSDATA member PUT.

**Note:** Remember that queue names are case sensitive. All the queues created by the sample file create program AMQSAMP4 have names created in uppercase characters.

The C program puts messages on the queue named in the first line of the file—you could use the supplied queue SYSTEM.SAMPLE.LOCAL. The program puts the text of each of the following lines of the file into separate datagram messages, and stops when it reads a blank line at the end of the file.

Using the example data file the command is:

```
CALL PGM(QMQMSAMP/AMQSPUT4) PARM('QMQMSAMP/AMQSDATA(PUT)')
```

### Running the AMQ0PUT4 COBOL sample

The COBOL program creates messages by accepting data from the keyboard. To start the program, call the program and give the name of your target queue as a program parameter. The program accepts input from the keyboard into a buffer and creates a datagram message for each line of text. The program stops when you enter a blank line at the keyboard.

## Design of the Put sample program

The program uses the MQOPEN call with the MQOO\_OUTPUT option to open the target queue for putting messages. If it cannot open the queue, the program outputs an error message containing the reason code returned by the MQOPEN call. To keep the program simple, on this and on subsequent MQI calls, the program uses default values for many of the options.

For each line of input, the program reads the text into a buffer and uses the MQPUT call to create a datagram message containing the text of that line. The program continues until either it reaches the end of the input or the MQPUT call fails. If the program reaches the end of the input, it closes the queue using the MQCLOSE call.

---

## The Distribution List sample program

The Distribution List sample `amqsptl0` gives an example of putting a message on several message queues. It is based on the MQPUT sample, `amqsput0`.

## Running the Distribution List sample, `amqsptl0`

The Distribution List sample runs in a similar way to the Put samples. It takes the following parameters:

- The names of the queues
- The names of the queue managers

These values are entered as pairs. For example:

```
amqsptl0 queue1 qmanagename1 queue2 qmanagename2
```

The queues are opened using MQOPEN and messages are put to the queues using MQPUT. Reason codes are returned if any of the queue or queue manager names are not recognized.

## Design of the Distribution List sample

Put Message Records (MQPMRs) specify message attributes on a per destination basis. The sample chooses to provide values for *MsgId* and *CorrelId*, and these override the values specified in the MQMD structure. The *PutMsgRecFields* field in the MQPMO structure indicates which fields are present in the MQPMRs:

```
MQLONG PutMsgRecFields=MQPMRF_MSG_ID + MQPMRF_CORREL_ID;
```

Next, the sample allocates the response records and object records. The object records (MQORs) require at least one pair of names and an even number of names, that is, *ObjectName* and *ObjectQMgrName*.

The next stage involves connecting to the queue managers using MQCONN. The sample attempts to connect to the queue manager associated with the first queue in the MQOR; if this fails, it goes through the object records in turn. You are informed if it is not possible to connect to any queue manager and the program exits.

The target queues are opened using MQOPEN and the message is put to these queues using MQPUT. Any problems and failures are reported in the response records (MQRRs).

## Browse sample

Finally, the target queues are closed using MQCLOSE and the program disconnects from the queue manager using MQDISC. The same response records are used for each call stating the *CompCode* and *Reason*.

---

## The Browse sample programs

The Browse sample programs browse messages on a queue using the MQGET call. See “Features demonstrated in the sample programs” on page 327 for the names of these programs.

## OS/2, UNIX systems, Digital OpenVMS, and Windows NT

The C version of the program takes 2 parameters

1. The name of the source queue (necessary)
2. The name of the queue manager (optional)

If a queue manager is not specified, it will connect to the default one. For example, enter one of the following:

```
amqsgbr myqueue qmanagername
amqsgbrc myqueue qmanagername
amq0gbr0 myqueue
```

where *myqueue* is the name of the queue that the messages will be viewed from, and *qmanagername* is the queue manager that owns *myqueue*.

If you omit the *qmanagername*, when running the C sample, it will assume that the default queue manager owns the queue.

The COBOL version does not have any parameters. It connects to the default queue manager and when you run it you are prompted:

```
Please enter the name of the target queue
```

Each program retrieves copies of all the messages on the queue you specify when you call the program; the messages remain on the queue. You could use the supplied queue SYSTEM.SAMPLE.LOCAL; run the Put sample program first to put some messages on the queue. You could use the queue SYSTEM.SAMPLE.ALIAS, which is an alias name for the same local queue. The program continues until it reaches the end of the queue or an MQI call fails.

Only the first 20 characters of each message are displayed, followed by - - - truncated when this is the case.

## AS/400

Each program retrieves copies of all the messages on the queue you specify when you call the program; the messages remain on the queue. You could use the supplied queue SYSTEM.SAMPLE.LOCAL; run the Put sample program first to put some messages on the queue. You could use the queue SYSTEM.SAMPLE.ALIAS, which is an alias name for the same local queue. The program continues until it reaches the end of the queue or an MQI call fails.

An example of a command to call the C program is:

```
CALL PGM(QMQMSAMP/AMQSGBR4) PARM('SYSTEM.SAMPLE.LOCAL')
```

## Design of the Browse sample program

The program opens the target queue using the MQOPEN call with the MQOO\_BROWSE option. If it cannot open the queue, the program outputs an error message containing the reason code returned by the MQOPEN call.

For each message on the queue, the program uses the MQGET call to copy the message from the queue, then displays the data contained in the message. The MQGET call uses these options:

### MQGMO\_BROWSE\_NEXT

After the MQOPEN call, the browse cursor is positioned logically before the first message in the queue, so this option causes the *first* message to be returned when the call is first made.

### MQGMO\_NO\_WAIT

The program does not wait if there are no messages on the queue.

### MQGMO\_ACCEPT\_TRUNCATED\_MSG

The MQGET call specifies a buffer of fixed size. If a message is longer than this buffer, the program displays the truncated message, together with a warning that the message has been truncated.

The program demonstrates how you must clear the *MsgId* and *CorrelId* fields of the MQMD structure after each MQGET call, because the call sets these fields to the values contained in the message it retrieves. Clearing these fields means that successive MQGET calls retrieve messages in the order in which the messages are held in the queue.

The program continues to the end of the queue; at this point the MQGET call returns the MQRC\_NO\_MSG\_AVAILABLE reason code and the program displays a warning message. If the MQGET call fails, the program displays an error message that contains the reason code.

The program then closes the queue using the MQCLOSE call.

---

## The Browser sample program

*This sample is not available on AS/400.*

The Browser sample program is written as a utility not just to demonstrate a technique. It reads and outputs both the message descriptor and the message content fields of all the messages on a queue. See “Features demonstrated in the sample programs” on page 327 for the names of these programs.

This program takes 2 parameters:

1. The name of the source queue
2. The name of the queue manager

Both input parameters for this program are mandatory. For example, enter one of the following:

```
amqsbcg myqueue qmanagername
amqsbcgc myqueue qmanagername
```

## Browser sample

where `myqueue` is the name of the queue on which the messages are going to be browsed, and `qmanagername` is the queue manager that owns `myqueue`.

It reads each message from the queue and outputs the following to the stdout:

Formatted message descriptor fields

Message data (dumped in hex and, where possible, character format)

The program is restricted to printing the first 32767 characters of the message, and will fail with the reason 'truncated msg' if a longer message is read.

See the *System Management Guide* for your platform, for examples of the output from this utility.

---

## The Get sample programs

The Get sample programs get messages from a queue using the MQGET call. See “Features demonstrated in the sample programs” on page 327 for the names of these programs.

### Running the amqsget and amqsgetc samples

These programs each take two parameters:

1. The name of the source queue (required)
2. The name of the queue manager (optional)

If a queue manager is not specified, amqsget connects to the default queue manager, and amqsgetc connects to the queue manager identified by an environment variable or the client channel definition file.

To run these programs, enter one of the following:

```
amqsget myqueue qmanagername  
amqsgetc myqueue qmanagername
```

where myqueue is the name of the queue from which the program will get messages, and qmanagername is the queue manager that owns myqueue.

If you omit the qmanagername, the programs assume the default, or, in the case of the MQI client, the queue manager identified by an environment variable or the client channel definition file.

### Running the amqsgetw sample

This program has no visible interface, all messages are put in the output file, not to stdout.

This program takes 3 parameters:

1. The name of the output file (required)
2. The name of the queue manager (required)
3. The name of the target queue (optional)

To run amqsgetw from the Windows 3.1 program manager:

1. Select File and click on Run...
2. On the run dialog, enter into the command line entry field the program name followed by the parameters.

## Get sample

For example:

```
amqsgetw outfile.out qmanagername myqueue
```

where:

outfile.out is used to hold the messages generated when the program runs.

qmanagername is the queue manager that owns myqueue.

myqueue is the name of the target queue from which the program will get messages. If you do not enter a queue name, the default queue for the queue manager is used.

Here is an example of the contents of the output file:

```
Sample AMQSGETW start
Output file "OUTFILE.OUT" opened
Queue Manager name "QMANAGERNAME" will be used
Queue Name "MYQUEUE" will be used
MQGET OK - message contents: <AMQSPUTW: Windows Client Test Message 1>
MQGET OK - message contents: <AMQSPUTW: Windows Client Test Message 2>
MQGET OK - message contents: <AMQSPUTW: Windows Client Test Message 3>
no more messages
Sample AMQSGETW end
```

It is important *always* to look in the output file to see what has happened as there is no visible indication of success or failure when you run this program.

## Running the amq0get sample

The COBOL version does not have any parameters. It connects to the default queue manager and when you run it you are prompted:

```
Please enter the name of the source queue
```

Each program removes messages from the queue you specify when you call the program. You could use the supplied queue SYSTEM.SAMPLE.LOCAL; run the Put sample program first to put some messages on the queue. You could use the queue SYSTEM.SAMPLE.ALIAS, which is an alias name for the same local queue. The program continues until the queue is empty or an MQI call fails.

## Running the AMQSGET4 and the AMQ0GET4 samples

The Get sample programs get messages from a queue using the MQGET call. The programs are named:

<b>C language</b>	AMQSGET4
<b>COBOL language</b>	AMQ0GET4

Each program removes messages from the queue you specify when you call the program. You could use the supplied queue SYSTEM.SAMPLE.LOCAL; run the Put sample program first to put some messages on the queue. You could use the queue SYSTEM.SAMPLE.ALIAS, which is an alias name for the same local queue. The program continues until the queue is empty or an MQI call fails.

An example of a command to call the C program is:

```
CALL PGM(QMQMSAMP/AMQSGT4) PARM('SYSTEM.SAMPLE.LOCAL')
```

## Design of the Get sample program

The program opens the target queue using the MQOPEN call with the MQOO\_INPUT\_AS\_Q\_DEF option. If it cannot open the queue, the program displays an error message containing the reason code returned by the MQOPEN call.

For each message on the queue, the program uses the MQGET call to remove the message from the queue, then displays the data contained in the message. The MQGET call uses the MQGMO\_WAIT option, specifying a *WaitInterval* of 15 seconds, so that the program waits for this period if there is no message on the queue. If no message arrives before this interval expires, the call fails and returns the MQRC\_NO\_MSG\_AVAILABLE reason code.

The program demonstrates how you must clear the *MsgId* and *CorrelId* fields of the MQMD structure after each MQGET call because the call sets these fields to the values contained in the message it retrieves. Clearing these fields means that successive MQGET calls retrieve messages in the order in which the messages are held in the queue.

The MQGET call specifies a buffer of fixed size. If a message is longer than this buffer, the call fails and the program stops.

The program continues until either the MQGET call returns the MQRC\_NO\_MSG\_AVAILABLE reason code or the MQGET call fails. If the call fails, the program displays an error message that contains the reason code.

The program then closes the queue using the MQCLOSE call.

---

## The Reference Message sample programs

The reference message samples allow a large object to be transferred from one node to another (usually on different systems) without the need for the object to be stored on MQSeries queues at either the source or the destination nodes.

A set of sample programs is provided to demonstrate how reference messages can be 1) put to a queue, 2) received by message exits, and 3) taken from a queue. The sample programs use reference messages to move files. If you want to move other objects such as databases, or if you want to perform security checks, you must define your own exit, based on our sample, amqsxrm. The following sections describe the Reference Message sample programs.

There are four versions of the reference message exit sample program. The one to use depends on the platform on which the channel is running. If the sender channel is running on:

### MQSeries Version 5 products

Use amqsxrma at the sending end. Use amqsxrma at the receiving end if running under MQSeries Version 5 products or amqsxrm4 if running under MQSeries for AS/400.

## Reference message samples

### MQSeries for AS/400

Use amqsqrm4 at the sending end. Use amqsqrma at the receiving end if running under MQSeries Version 5 products or amqsqrm4 if running under MQSeries for AS/400.

### MQSeries for Windows (not MQSeries for Windows NT)

Use amqsqrma at the receiving end if running under MQSeries Version 5 products or amqsqrm4 if running under MQSeries for AS/400.

If you use amqsqrma or amqsqrm4 a model queue with the name SYSTEM.DEFAULT.MODEL.PERMDYN.QUEUE and queue definition type of PERMDYN must exist at the receiving end. You can create this queue using the MQSC command:

```
def qm(system.default.model.permdyn.queue) deftype(permdyn)
```

**Note:** In the following sections references to amqsxrma also apply to amqsqrma and references to AMQSXRM4 also apply to AMQSQRM4.

## Notes for AS/400 users

To receive a reference message using the sample message exit, specify a file in the root file system of IFS or any sub-directory so that a stream file can be created. The sample message exit on AS/400 creates the file, converts the data to EBCDIC, and sets the code page to your system code page. You then have the option of copying this file to the QSYS.LIB file system using the CPYFRMSTMF command. For example:

```
CPYFRMSTMF FROMSTMF('JANEP/TEST.TXT')
           TOMBR('qsys.lib.janep.lib/test.fie/test.mbr') MBROPT(*REPLACE)
           CVTDTA(*NONE)
```

Note that the CPYFRMSTMF command does not create the file, it must be created before running this command.

If you send a file from QSYS.LIB no changes are required to the samples. For any other file system ensure that the CCSID specified in the CodedCharSetId field in the MQRMH structure matches the bulk data you are sending.

When using the integrated file system, create program modules with the SYSIFCOPT(\*IFSIO) option set. If you want to move database or fixed-length record files, define your own exit based on the supplied sample AMQSXRM4.

## Running the Reference Message samples

The reference message samples run as follows:




Figure 35. Running the reference message samples

1. Set up the environment to start the listeners, channels, and trigger monitors, and define your channels and queues.

For the purposes of describing how to set-up the reference message example this refers to the sending machine as MACHINE1 with a queue manager called QMGR1 and the receiving machine as MACHINE2 with a queue manager called QMGR2.

**For AS/400 users:** On the AS/400 the sample programs must be created, this can be done by issuing the following commands. You may wish to put the modules and programs into a different library but for this example they are kept in QMQMSAMP. It is important to note that the activation group QMQM must not be used for any exit programs - this activation group is for the use of MQSeries only.

## Reference message samples

```
CRTCMOD MODULE(QMQMSAMP/AMQSPRMA) SRCFILE(QMQMSAMP/QCSRC)
CRTPGM PGM(QMQMSAMP/AMQSPRMA) BNDSRVPGM(QMQM/AMQZSTUB)
```

```
CRTCMOD MODULE(QMQMSAMP/AMQSGRMA) SRCFILE(QMQMSAMP/QCSRC)
CRTPGM PGM(QMQMSAMP/AMQSGRMA) BNDSRVPGM(QMQM/AMQZSTUB)
```

```
CRTCMOD MODULE(QMQMSAMP/AMQSXRMA) SRCFILE(QMQMSAMP/QCSRC)
CRTPGM PGM(QMQMSAMP/AMQSXRMA) BNDSRVPGM(QMQM/AMQZSTUB) QMQM/AMQVSTUB)
```

**For all users:** The following definitions allow a reference message to be built to send a file with an object type of FLATFILE from queue manager QMGR1 to QMGR2 and to recreate the file as defined in the call to AMQSPRM (or AMQSPRMA on AS/400). The reference message (including the file data) is sent using channel CHL1 and transmission queue XMITQ and placed on queue DQ. Exception and COA reports are sent back to QMGR1 using the channel REPORT and transmission queue QMGR1.

The application that receives the reference message (AMQSGRM or AMQSGRMA on the AS/400) is triggered using the initiation queue INITQ and process PROC. You need to ensure the CONNAME fields are set correctly and the MSGEXIT field reflects your directory structure, depending on machine type and where the MQSeries product is installed.

The MQSC definitions have used an OS/2 style for defining the exits, if you are using MQSC on the AS/400 you will need to modify these accordingly. It is important to note that the message data FLATFILE is case sensitive and the sample will not work unless it is in uppercase.

On machine MACHINE1, queue manager QMGR1

### MQSC syntax:

```
define chl(chl1) chltype(sdr) trptype(tcp) conname('machine2') xmitq(xmitq)
msgdata(FLATFILE) msgexit('d:\mqm\tools\c\samples\bin\amqsxrm.dll(MsgExit)')
```

```
define ql(xmitq) usage(xmitq)
```

```
define chl(report) chltype(rcvr) trptype(tcp) replace
```

```
define qr(qr) rname(dq) rqnname(qmgr2) xmitq(xmitq) replace
```

### AS/400 command syntax:

```
CRTMQMCHL CHLNAME(CHL1) CHLTYPE(*SDR) CONNAME(MACHINE2) TMQNAME(XMITQ)
MSGEXIT(QMQMSAMP/AMQSXRMA) MSGUSRDATA(FLATFILE)
```

```
CRTMQMQ QNAME(XMITQ) QTYPE(*LCL) USAGE(*TMQ)
```

```
CRTMQMCHL CHLNAME(REPORT) CHLTYPE(*RCVR)
```

```
CRTMQMQ QNAME(QR) QTYPE(*RMT) RMTQNAME(DQ) RMTMQMNAME(QMGR2) TMQNAME(XMITQ)
```

On machine MACHINE2, queue manager QMGR2

**MQSC syntax:**

```
define chl(chl1) chltype(rcvr) trptype(tcp)
msgexit('d:\mqm\tools\c\samples\bin\amqsxrm.dll(MsgExit)')
    msgdata(flatfile)

define chl(report) chltype(sdr) trptype(tcp) conname('MACHINE1')
    xmitq(qmgr1)

define ql(initq)

define ql(qmgr1) usage(xmitq)

define pro(proc) applicid('d:\mqm\tools\c\samples\bin\amqsgrm')

define ql(dq) initq(initq) process(proc) trigger trigtype(first)
```

**AS/400 command syntax:**

```
CRTMQMCHL CHLNAME(CHL1) CHLTYPE(*RCVR) MSGEXIT(QMQMSAMP/AMQSXRMA)
    MSGUSRDATA(FLATFILE)

CRTMQMCHL CHLNAME(REPORT) CHLTYPE(*SDR) CONNAME(MQCHINE1) TMQNAME(QMGR1)

CRTMQMQ QNAME(INITQ) QTYPE(*LCL) USAGE(*NORMAL)

CRTMQMQ QNAME(QMGR1) QTYPE(*LCL) USAGE(*TMQ)

CRTMQMPCRC PRCNAME(PROC) APPID('QMMSAMP/AMQSGRMA')

CRTMQMQ QNAME(DQ) QTYPE(*LCL) PRCNAME(PROC) TRGENBL(*YES)
    INITQNAME(INITQ)
```

2. Once the above MQSeries objects have been created:
  - a. Where applicable to the platform, start the listener for the sending and receiving queue managers
  - b. Start the channels CHL1 and REPORT
  - c. On the receiving queue manager start the trigger monitor for the initiation queue INITQ
3. Invoke the put reference message sample AMQSPRM (AMQSPRMA on the AS/400) from the command line using the following parameters:

```
-m      Name of the local queue manager, this defaults to the default queue manager.
-i      Name and location of source file.
-o      Name and location of destination file.
-q      Name of queue.
-g      Name of queue manager where the queue, defined in the -q parameter exists. This
        defaults to the queue manager specified in the -m parameter.
-t      Object type.
-w      Wait interval, that is, the waiting time for exception and COA reports from the
        receiving queue manager.
```

For example, to use the sample with the objects defined above you would use the following parameters:

```
-mQMGR1 -iInput File -oOutput File -qQR -tFLATFILE -w120
```

## Reference message samples

Increasing the waiting time will allow time for a large file to be sent across a network before the putting program times out.

```
amqsprmq -q QR -m QMGR1 -i d:\x\file.in -o d:\y\file.out -t FLATFILE
```

**AS/400 users:** On the AS/400 use the following command:

```
CALL PGM(QMQMSAMP/AMQSPRMA) PARM('-mQMGR1' '-iLIBRARY/FILEIN'  
'-oLIBRARY/FILEOUT' '-qDQ' '-tFLATFILE')
```

To use the IFS, use the following commands:

```
CRTCMOD MODULE(QMQMSAMP/AMQSXRMA) SRCFILE(QMQMSAMP/QCSRC) SYSIFCOPT(*IFSIO)  
CRTCMOD MODULE(QMQMSAMP/AMQSGRMA) SRCFILE(QMQMSAMP/QCSRC) SYSIFCOPT(*IFSIO)
```

You may use the root directory, but it is recommended you create one using the CRTDIR command.

When calling the putting program the output file name will need to reflect the IFS naming convention, for instance /TEST/FILENAME will create a file called FILENAME in the directory TEST.

**Note:** You can use either a forward slash (/) or a dash (-) when specifying parameters.

For example:

```
amqsprmq /i d:\files\infile.dat /o e:\files\outfile.dat /q QR  
/m QMGR1 /w 30 /t FLATFILE
```

**Note:** For UNIX platforms, you must use two slashes (\\) instead of one to denote the destination file directory. Therefore, the above command looks like this:

```
amqsprmq -i /files/infile.dat -o e:\\files\\outfile.dat -q QR  
-m QMGR1 -w 30 -t FLATFILE
```

This demonstrates the following:

- The reference message will be put to queue QR on queue manager QMGR1.
  - The source file and path is d:\files\infile.dat and exists on the system where the example command is issued.
  - If the queue QR is a remote queue, the reference message is sent to another queue manager, on a different system, where a file is created with the name and path e:\files\outfile.dat. The contents of this file are the same as the source file.
  - amqsprmq waits for 30 seconds for a COA report from the destination queue manager.
  - The object type is flatfile, so the channel used to move messages from the queue QR must specify this in the *MsgData* field.
4. When you define your channels, select the message exit at both the sending and receiving ends to be amqsxrm. This is defined on MQSeries for OS/2 Warp, and Windows NT as follows:

```
msgexit('<pathname>\amqsxrm.dll(MsgExit)')
```

This is defined on MQSeries for AIX, HP-UX, and Sun Solaris as follows:

```
msgexit('<pathname>/amqsxrm(MsgExit)')
```

If a pathname is specified, the complete name must be specified (with .dll on OS/2). If a pathname is not specified, it is assumed that the program is in the path specified in the qm.ini file (or, on MQSeries for Windows NT, the path specified in the registry). This is explained fully in “Writing and compiling channel-exit programs” in the *MQSeries Intercommunication* book.

5. The channel exit reads the reference message header and finds the file that it is referring to.
6. It can then choose to segment the file before sending it down the channel along with the header. On MQSeries for AIX, HP-UX, and Sun Solaris, you must change the group owner of the target directory to ‘mqm’ so that the sample message exit can create the file in that directory. Also, change the permissions of the target directory to allow mqm group members to write to it. The file data is not stored on the MQSeries queues.
7. When the last segment of the file is processed by the receiving message exit, the reference message is put to the destination queue specified by amqsprm. If this queue is triggered (that is, the definition specifies *Trigger*, *InitQ*, and *Process* queue attributes), the program specified by the PROC parameter of the destination queue is triggered. The program to be triggered must be defined in the *ApplId* field of the *Process* attribute.
8. When the reference message reaches the destination queue (DQ), a COA report is sent back to the putting application (amqsprm).
9. The get reference message sample, amqsgrm, gets messages from the queue specified in the input trigger message and checks the existence of the file.

## Design of the Put Reference Message sample (amqsprma.c)

This sample creates a reference message that refers to a file and puts it on a specified queue:

1. The sample connects to a local queue manager using MQCONN.
2. It then opens (MQOPEN) a model queue which is used to receive report messages.
3. The sample builds a reference message containing the values required to move the file, for example, the source and destination file names and the object type.

As an example, the sample shipped with MQSeries builds a reference message to send the file `d:\x\file.in` from QMGR1 to QMGR2 and to recreate the file as `d:\y\file.out` using the following parameters:

```
amqsprm -q QR -m QMGR1 -i d:\x\file.in -o d:\y\file.out -t FLATFILE
```

Where QR is a remote queue definition that refers to a target queue on QMGR2.

**Note:** For UNIX platforms, you must use two slashes (\\) instead of one to denote the destination file directory. Therefore, the above command looks like this:

```
amqsprm -q QR -m QMGR1 -i /x/file.in -o d:\\y\\file.out -t FLATFILE
```

4. The reference message is put (without any file data) to the queue specified by the /q parameter. If this is a remote queue, the message is put to the corresponding transmission queue.
5. The sample waits, for the duration of time specified in the /w parameter (which defaults to 15 seconds), for COA reports, which, along with exception reports,

## Reference message samples

are sent back to the dynamic queue created on the local queue manager (QMGR1).

### Design of the Reference Message Exit sample (amqsxrma.c, AMQSXRM4)

This sample recognizes reference messages with an object type that matches the object type in the message exit user data field of the channel definition. For these messages, the following happens:

- At the sender or server channel, the specified length of data is copied from the specified offset of the specified file into the space remaining in the agent buffer after the reference message. If the end of the file is not reached, the reference message is put back on the transmission queue after updating the *DataLogicalOffset* field.
- At the requester or receiver channel, if the *DataLogicalOffset* field is zero and the specified file does not exist, it is created. The data following the reference message is added to the end of the specified file. If the reference message is not the last one for the specified file, it is discarded. Otherwise, it is returned to the channel exit, without the appended data, to be put on the target queue.

For sender and server channels, if the *DataLogicalLength* field in the input reference message is zero, the remaining part of the file, from *DataLogicalOffset* to the end of the file, is to be sent along the channel. If it is not zero, only the length specified is sent.

If an error occurs (for example, if the sample is unable to open a file), *MQCXP.ExitResponse* is set to *MQXCC\_SUPPRESS\_FUNCTION* so that the message being processed is put to the dead-letter queue instead of continuing to the destination queue. A feedback code is returned in *MQCXP.Feedback* and returned to the application that put the message in the *Feedback* field of the message descriptor of a report message. This is because the putting application requested exception reports by setting *MQRO\_EXCEPTION* in the *Report* field of the *MQMD*.

If the encoding or *CodedCharacterSetId* (CCSID) of the reference message is different from that of the queue manager, the reference message is converted to the local encoding and CCSID. In our sample, *amqsprm*, the format of the object is *MQFMT\_STRING*, so *amqsxrm* converts the object data to the local CCSID at the receiving end before the data is written to the file.

The format of the file being transferred should not be specified as *MQFMT\_STRING* if the file contains multibyte characters (for example, DBCS or Unicode). This is because a multibyte character could be split when the file is segmented at the sending end. To transfer and convert such a file, the format should be specified as something other than *MQFMT\_STRING* so that the reference message exit does not convert it and the file should be converted at the receiving end when the transfer is complete.

## Compiling the Reference Message Exit sample

To compile amqsxrma, use the following commands:

### On AIX:

```
| $cc -d -I/usr/mqm/inc amqsxrma.c
| $ ld -o amqsxrm amqsxrma.o -bE:amqsxrm.exp -H512 -T512 \
| -e MQStart -bM:SRE -lc -ls -lmqm
```

### On HP-UX:

```
| $ cc -c -Aa +z -I/opt/mqm/inc amqsxrma.c
| $ ld -b -o amqsxrm amqsxrma.o -z +b : -lmqm -lc
```

### On Sun Solaris:

```
| $ cc -c -KPIC -I/opt/mqm/inc amqsxrma.c
| $ ld -G -o amqsxrm amqsxrma.o -dy -lmqm -lc -lnsl -ldl
```

## Design of the Get Reference Message sample (amqsgrma.c)

The program logic is as follows:

1. The sample is triggered and extracts the queue and queue manager names from the input trigger message.
2. It then connects to the specified queue manager using MQCONN and opens the specified queue using MQOPEN.
3. The sample issues MQGET with a wait interval of 15 seconds within a loop to get messages from the queue.
4. If a message is a reference message, the sample checks the existence of the file that has been transferred.
5. It then closes the queue and disconnects from the queue manager.

---

## The Request sample programs

The Request sample programs demonstrate client/server processing. The samples are the clients that put request messages on a target server queue that is processed by a server program. They wait for the server program to put a reply message on a reply-to queue.

The Request samples put a series of request messages on target server queue using the MQPUT call. These messages specify the local queue, SYSTEM.SAMPLE.REPLY as the reply-to queue, which can be a local or remote queue. The programs wait for reply messages, then display them. Replies are sent only if the target server queue is being processed by a server application, or if an application is triggered for that purpose (the Inquire, Set, and Echo sample programs are designed to be triggered). The C sample waits 1 minute (the COBOL sample waits 5 minutes), for the first reply to arrive (to allow time for a server application to be triggered), and 15 seconds for subsequent replies, but both samples can end without getting any replies. See "Features demonstrated in the sample programs" on page 327 for the names of the Request sample programs.

### Running the amqsreq0.c, amqsreq, and amqsreqc samples

The C version of the program takes 2 parameters:

1. The name of the target server queue (necessary)
2. The name of the queue manager (optional)

If a queue manager is not specified, it will connect to the default one. For example, enter one of the following:

```
amqsreq myqueue qmanagername
amqsreqc myqueue qmanagername
amq0req0 myqueue
```

where `myqueue` is the name of the target server queue, and `qmanagername` is the queue manager that owns `myqueue`.

If you omit the `qmanagername`, when running the C sample, it will assume that the default queue manager owns the queue.

### Running the amq0req0.cbl sample

The COBOL version does not have any parameters. It connects to the default queue manager and when you run it you are prompted:

```
Please enter the name of the target server queue
```

The program takes its input from `StdIn` and adds each line to the target server queue, taking each line of text as the content of a request message. The program ends when a null line is read.

### Running the AMQSREQ4 sample

The C program creates messages by reading data from a member of a source file. You must specify the name of the file as a parameter when you start the program. The structure of the file must be:

```
queue name
text of message 1
text of message 2

:
text of message n
blank line
```

Samples of input for the request samples are supplied in library `QMMSAMP` file `AMQSDATA` members `ECHO`, `INQ`, and `SET`.

**Note:** Remember that queue names are case sensitive. All the queues created by the sample file create program `AMQSAMP4` have names created in uppercase characters.

The C program puts messages on the queue named in the first line of the file—you could use the supplied queue `SYSTEM.SAMPLE.TRIGGER`. The program puts the text of each of the following lines of the file into separate request messages, and stops when it reads a blank line at the end of the file.

## Running the AMQ0REQ4 sample

The COBOL program creates messages by accepting data from the keyboard. To start the program, call the program and specify the name of your target queue as a parameter. The program accepts input from the keyboard into a buffer and creates a request message for each line of text. The program stops when you enter a blank line at the keyboard.

## Running the Request sample using triggering

If the sample is used with triggering and one of the Inquire, Set, or Echo sample programs, the line of input must be the queue name of the queue that you want the triggered program to access.

### OS/2, UNIX systems, and Windows NT

To run the samples using triggering:

1. Start the trigger monitor program RUNMQTRM in one session (the initiation queue SYSTEM.SAMPLE.TRIGGER is available for you to use).
2. Start the amqsreq program in another session.
3. Make sure you have defined a target server queue.

The sample queues available to you to use as the target server queue for the request sample to put messages are:

- SYSTEM.SAMPLE.INQ - for the Inquire sample program
- SYSTEM.SAMPLE.SET - for the Set sample program
- SYSTEM.SAMPLE.ECHO - for the Echo sample program

These queues have a trigger type of FIRST, so if there are already messages on the queues before you run the Request sample, server applications are not triggered by the messages you send.

4. Make sure you have defined a queue for the Inquire, Set or Echo sample program to use.

This means that the trigger monitor is ready when the request sample sends a message.

**Note:** The sample process definitions created using RUNMQSC and the amqscos0.tst file cause the C samples to be triggered. Change the process definitions in amqscos0.tst and use RUNMQSC with this updated file if the COBOL versions are required.

Figure 36 on page 362 demonstrates how the Request and Inquire samples can be used together.

## Request samples




Figure 36. Request and Inquire samples using triggering

In Figure 36 the Request sample puts messages on to the target server queue, SYSTEM.SAMPLE.INQ, and the Inquire sample queries the queue, MYQUEUE. Alternatively, you can use one of the sample queues defined when you ran amqscos0.tst, or any other queue you have defined, for the Inquire sample.

**Note:** The numbers in Figure 36 show the sequence of events.

To run the Request and Inquire samples, using triggering:

1. Check that the queues you want to use are defined. Run amqscos0.tst, to define the sample queues, and define a queue MYQUEUE.
2. Run the trigger monitor command RUNMQTRM:
 

```
RUNMQTRM -m qmanagername -q SYSTEM.SAMPLE.TRIGGER
```
3. Run the request sample
 

```
amqsreq SYSTEM.SAMPLE.INQ
```

**Note:** The process object defines what is to be triggered. If the client and server are not running on the same platform, any processes started by the trigger monitor must define *AppType*, otherwise the server takes its

default definitions (that is, the type of application that is normally associated with the server machine) and causes a failure.

For example, if the trigger monitor is running on a Windows NT client and wants to send a request to an OS/2 server, MQAT\_WINDOWS\_NT must be defined otherwise OS/2 uses its default definitions (that is, MQAT\_OS2) and the process fails.

For a list of application types, see “Attributes for process definitions” in the *MQSeries Application Programming Reference* manual.

4. Enter the name of the queue you want the Inquire sample to use:  
MYQUEUE
5. Enter a blank line (to end the Request program).
6. The request sample will then display a message, containing the data the Inquire program obtained from MYQUEUE.

If you wish, you can use more than one queue. In this case, you enter the names of the other queues at step 4.

For more information on triggering see Chapter 14, “Starting MQSeries applications using triggers” on page 197.

### AS/400

To try the samples using triggering on AS/400, start the sample trigger server, AMQSERV4, in one job, then start AMQSREQ4 in another. This means that the trigger server is ready when the Request sample program sends a message.

#### Notes:

1. The sample definitions created by AMQSAMP4 cause the C versions of the samples to be triggered. If you want to trigger the COBOL versions, you must change the process definitions SYSTEM.SAMPLE.ECHOPROCESS, SYSTEM.SAMPLE.INQPROCESS and SYSTEM.SAMPLE.SETPROCESS; you can use the CHGMQMPCRC command (described in the *MQSeries for AS/400 Administration Guide*) to do this, or edit and run your own version of AMQSAMP4.
2. Source code for AMQSERV4 is supplied for the C language only. However, a compiled version (that you can use with the COBOL samples) is supplied in library QMQM.

You could put your request messages on these sample server queues:

- SYSTEM.SAMPLE.ECHO (for the Echo sample programs)
- SYSTEM.SAMPLE.INQ (for the Inquire sample programs)
- SYSTEM.SAMPLE.SET (for the Set sample programs)

A flow chart for the SYSTEM.SAMPLE.ECHO program is shown in Figure 37 on page 365. Using the example data file the command to issue the C program request to this server is:

```
CALL PGM(QMQMSAMP/AMQSREQ4) PARM('QMQMSAMP/AMQSDATA(ECHO)')
```

**Note:** This sample queue has a trigger type of FIRST, so if there are already messages on the queue before you run the Request sample, server applications are not triggered by the messages you send.

## Request samples

If you want to attempt further examples, you can try the following variations:

- Use AMQSTRG4 instead of AMQSERV4 to submit the job instead, but potential job submission delays could make it less easy to follow what is happening.
- Run the SYSTEM.SAMPLE.INQUIRE and SYSTEM.SAMPLE.SET sample programs. Using the example data file the commands to issue the C program requests to these servers are, respectively:

```
CALL PGM(QMQMSAMP/AMQSREQ4) PARM('QMMSAMP/AMQSDATA(INQ)')
CALL PGM(QMQMSAMP/AMQSREQ4) PARM('QMMSAMP/AMQSDATA(SET)')
```

These sample queues also have a trigger type of FIRST.

## Design of the Request sample program

The program opens the target server queue so that it can put messages. It uses the MQOPEN call with the MQOO\_OUTPUT option. If it cannot open the queue, the program displays an error message containing the reason code returned by the MQOPEN call.

The program then opens the reply-to queue called SYSTEM.SAMPLE.REPLY so that it can get reply messages. For this, the program uses the MQOPEN call with the MQOO\_INPUT\_EXCLUSIVE option. If it cannot open the queue, the program displays an error message containing the reason code returned by the MQOPEN call.

For each line of input, the program then reads the text into a buffer and uses the MQPUT call to create a request message containing the text of that line. On this call the program uses the MQRO\_EXCEPTION\_WITH\_DATA report option to request that any report messages sent about the request message will include the first 100 bytes of the message data. The program continues until either it reaches the end of the input or the MQPUT call fails.

The program then uses the MQGET call to remove reply messages from the queue, and displays the data contained in the replies. The MQGET call uses the MQGMO\_WAIT, MQGMO\_CONVERT, and MQGMO\_ACCEPT\_TRUNCATED options. The *WaitInterval* is 5 minutes in the COBOL version, and 1 minute in the C version, for the first reply (to allow time for a server application to be triggered), and 15 seconds for subsequent replies. The program waits for these periods if there is no message on the queue. If no message arrives before this interval expires, the call fails and returns the MQRC\_NO\_MSG\_AVAILABLE reason code. The call also uses the MQGMO\_ACCEPT\_TRUNCATED\_MSG option, so messages longer than the declared buffer size are truncated.

The program demonstrates how you must clear the *MsgId* and *CorrelId* fields of the MQMD structure after each MQGET call because the call sets these fields to the values contained in the message it retrieves. Clearing these fields means that successive MQGET calls retrieve messages in the order in which the messages are held in the queue.

The program continues until either the MQGET call returns the MQRC\_NO\_MSG\_AVAILABLE reason code or the MQGET call fails. If the call fails, the program displays an error message that contains the reason code.

The program then closes both the target server queue and the reply-to queue using the MQCLOSE call. Figure 29 shows the changes to the Echo sample program that are necessary to run the Inquire and Set sample programs on AS/400.

**Note:** The details for the Echo sample program are included as a reference.

Program name	AMQSAMP/ AMQSDATA data file	SYSTEM/SAMPLE queue	Program started
Echo	ECHO	ECHO	AMQSECHA
Inquire	INQ	INQ	AMQSINQA
Set	SET	SET	AMQSSETA




Figure 37. Sample Client/Server (Echo) program flowchart

---

### The Inquire sample programs

The Inquire sample programs inquire about some of the attributes of a queue using the MQINQ call. See “Features demonstrated in the sample programs” on page 327 for the names of these programs.

These programs are intended to run as triggered programs, so their only input is an MQTMC2 (trigger message) structure for OS/2, Windows NT, Digital OpenVMS, and UNIX, and an MQTMC structure for AS/400. These structures contain the name of a target queue whose attributes are to be inquired. The C version also uses the queue manager name. The COBOL version uses the default queue manager.

For the triggering process to work, you must ensure that the Inquire sample program you want to use is triggered by messages arriving on queue SYSTEM.SAMPLE.INQ. To do this, specify the name of the Inquire sample program you want to use in the *ApplicId* field of the process definition SYSTEM.SAMPLE.INQPROCESS. For AS/400, you can use the CHGMQMPCR command described in the *MQSeries for AS/400 Administration Guide* for this. The sample queue has a trigger type of FIRST; if there are already messages on the queue before you run the request sample, the inquire sample is not triggered by the messages you send.

When you have set the definition correctly:

- For OS/2, UNIX systems, Digital OpenVMS, and Windows NT, start the **runmqtrm** program in one session, then start the amqsreq program in another.
- For AS/400, start the AMQSERV4 program in one session, then start the AMQSREQ4 program in another. You could use AMQSTRG4 instead of AMQSERV4, but potential job submission delays could make it less easy to follow what is happening.

Use the Request sample programs to send request messages, each containing just a queue name, to queue SYSTEM.SAMPLE.INQ. For each request message, the Inquire sample programs send a reply message containing information about the queue specified in the request message. The replies are sent to the reply-to queue specified in the request message.

On AS/400, if the sample input file member QMQMSAMP.AMQSDATA(INQ) is used, the last queue named does not exist, so the sample returns a report message with a reason code for the failure.

### Design of the Inquire sample program

The program opens the queue named in the trigger message structure it was passed when it started. (For clarity, we will call this the *request queue*.) The program uses the MQOPEN call to open this queue for shared input.

The program uses the MQGET call to remove messages from this queue. This call uses the MQGMO\_ACCEPT\_TRUNCATED\_MSG and MQGMO\_WAIT options, with a wait interval of 5 seconds. The program tests the descriptor of each message to see if it is a request message; if it is not, the program discards the message and displays a warning message.

For each request message removed from the request queue, the program reads the name of the queue (which we will call the *target queue*) contained in the data and opens that queue using the MQOPEN call with the MQOO\_INQ option. The program then uses the MQINQ call to inquire about the values of the *InhibitGet*, *CurrentQDepth*, and *OpenInputCount* attributes of the target queue.

If the MQINQ call is successful, the program uses the MQPUT1 call to put a reply message on the reply-to queue. This message contains the values of the 3 attributes.

If the MQOPEN or MQINQ call is unsuccessful, the program uses the MQPUT1 call to put a report message on the reply-to queue. In the *Feedback* field of the message descriptor of this report message is the reason code returned by either the MQOPEN or MQINQ call, depending on which one failed.

After the MQINQ call, the program closes the target queue using the MQCLOSE call.

When there are no messages remaining on the request queue, the program closes that queue and disconnects from the queue manager.

---

## The Set sample programs

The Set sample programs inhibit put operations on a queue by using the MQSET call to change the queue's *InhibitPut* attribute. See "Features demonstrated in the sample programs" on page 327 for the names of these programs.

The programs are intended to run as triggered programs, so their only input is an MQTMC2 (trigger message) structure that contains the name of a target queue whose attributes are to be inquired. The C version also uses the queue manager name. The COBOL version uses the default queue manager.

For the triggering process to work, you must ensure that the Set sample program you want to use is triggered by messages arriving on queue SYSTEM.SAMPLE.SET. To do this, specify the name of the Set sample program you want to use in the *ApplicId* field of the process definition SYSTEM.SAMPLE.SETPROCESS. The sample queue has a trigger type of FIRST; if there are already messages on the queue before you run the Request sample, the Set sample is not triggered by the messages you send.

When you have set the definition correctly:

- For OS/2, UNIX systems, Digital OpenVMS, and Windows NT, start the **runmqtrm** program in one session, then start the amqsreq program in another.
- For AS/400, start the AMQSERV4 program in one session, then start the AMQSREQ4 program in another. You could use AMQSTRG4 instead of AMQSERV4, but potential job submission delays could make it less easy to follow what is happening.

Use the Request sample programs to send request messages, each containing just a queue name, to queue SYSTEM.SAMPLE.SET. For each request message, the Set sample programs send a reply message containing a confirmation that put operations have been inhibited on the specified queue. The replies are sent to the reply-to queue specified in the request message.

## Set samples

On AS/400, if the sample input file member QMQMSAMP.AMQSDATA(SET) is used, one queue, SYSTEM.SAMPLE.LOCAL has put inhibited.

### Design of the Set sample program

The program opens the queue named in the trigger message structure it was passed when it started. (For clarity, we will call this the request queue.) The program uses the MQOPEN call to open this queue for shared input.

The program uses the MQGET call to remove messages from this queue. This call uses the MQGMO\_ACCEPT\_TRUNCATED\_MSG and MQGMO\_WAIT options, with a wait interval of 5 seconds. The program tests the descriptor of each message to see if it is a request message; if it is not, the program discards the message and displays a warning message.

For each request message removed from the request queue, the program reads the name of the queue (which we will call the target queue) contained in the data and opens that queue using the MQOPEN call with the MQOO\_SET option. The program then uses the MQSET call to set the value of the *InhibitPut* attribute of the target queue to MQQA\_PUT\_INHIBITED.

If the MQSET call is successful, the program uses the MQPUT1 call to put a reply message on the reply-to queue. This message contains the string PUT inhibited.

If the MQOPEN or MQSET call is unsuccessful, the program uses the MQPUT1 call to put a report message on the reply-to queue. In the *Feedback* field of the message descriptor of this report message is the reason code returned by either the MQOPEN or MQSET call, depending on which one failed.

After the MQSET call, the program closes the target queue using the MQCLOSE call.

When there are no messages remaining on the request queue, the program closes that queue and disconnects from the queue manager.

---

## The Echo sample programs

The Echo sample programs echo a message from a message queue to the reply queue. See “Features demonstrated in the sample programs” on page 327 for the names of these programs.

The programs are intended to run as triggered programs.

On OS/2, UNIX systems, and Windows NT, their only input is an MQTMC2 (trigger message) structure that contains the name of a target queue and the queue manager. The COBOL version uses the default queue manager.

On AS/400, for the triggering process to work, you must ensure that the Echo sample program you want to use is triggered by messages arriving on queue SYSTEM.SAMPLE.ECHO. To do this, specify the name of the Echo sample program you want to use in the *AppLId* field of the process definition SYSTEM.SAMPLE.ECHOPROCESS. (For this, you can use the CHGMQMPCRC command, described in the *MQSeries for AS/400 Administration Guide*.) The sample queue has a trigger type of FIRST, so if there are already messages on the queue before you run the Request sample, the Echo sample is not triggered by the messages you send.

When you have set the definition correctly, first start AMQSERV4 in one job, then start AMQSREQ4 in another. You could use AMQSTRG4 instead of AMQSERV4, but potential job submission delays could make it less easy to follow what is happening.

Use the Request sample programs to send messages to queue SYSTEM.SAMPLE.ECHO. The Echo sample programs send a reply message containing the data in the request message to the reply-to queue specified in the request message.

## Design of the Echo sample programs

The program opens the queue named in the trigger message structure it was passed when it started. (For clarity, we will call this the *request queue*.) The program uses the MQOPEN call to open this queue for shared input.

The program uses the MQGET call to remove messages from this queue. This call uses the MQGMO\_ACCEPT\_TRUNCATED\_MSG, MQGMO\_CONVERT, and MQGMO\_WAIT options, with a wait interval of 5 seconds. The program tests the descriptor of each message to see if it is a request message; if it is not, the program discards the message and displays a warning message.

For each line of input, the program then reads the text into a buffer and uses the MQPUT1 call to put a request message, containing the text of that line, on to the reply-to queue.

If the MQGET call fails, the program puts a report message on the reply-to queue, setting the *Feedback* field of the message descriptor to the reason code returned by the MQGET.

When there are no messages remaining on the request queue, the program closes that queue and disconnects from the queue manager.

## Data-conversion sample

On AS/400, the program can also respond to messages sent to the queue from platforms other than MQSeries for AS/400, although no sample is supplied for this situation. To make the ECHO program work, you:

- Write a program, correctly specifying the *Format*, *Encoding*, and *CCSID* parameters, to send text request messages.

The ECHO program requests the queue manager to perform message data conversion, if this is needed.

- Specify CONVERT(\*YES) on the MQSeries for AS/400 sending channel, if the program you have written does not provide similar conversion for the reply.

---

## The Data-Conversion sample program

The data-conversion sample program is a skeleton of a data conversion exit routine. See “Features demonstrated in the sample programs” on page 327 for the names of these programs.

## Design of the data-conversion sample

Each data-conversion exit routine converts a single named message format. This skeleton is intended as a wrapper for code fragments generated by the data-conversion exit generation utility program.

The utility produces one code fragment for each data structure; several such structures make up a format, so several code fragments are added to this skeleton to produce a routine to do data conversion of the entire format.

The program then checks whether the conversion is a success or failure, and returns the values required to the caller.

## The Triggering sample programs

The function provided in the triggering sample is a subset of that provided in the trigger monitor in the `runmqtrm` program. See “Features demonstrated in the sample programs” on page 327 for the names of these programs.

### Running the `amqstrg0.c`, `amqstrg`, and `amqstrgc` samples

The program takes 2 parameters:

1. The name of the initiation queue (necessary)
2. The name of the queue manager (optional)

If a queue manager is not specified, it will connect to the default one. A sample initiation queue will have been defined when you ran `amqscos0.tst`. The name of that queue is `SYSTEM.SAMPLE.TRIGGER`, and you can use it when you run this program.

**Note:** The function in this sample is a subset of the full triggering function that is supplied in the `runmqtrm` program.

### Running the `AMQSTRG4` sample

This is a trigger monitor for the AS/400 environment. It submits an AS/400 job for the application to be started, but this means there is a processing overhead associated with each trigger message.

`AMQSTRG4` takes one parameter: the name of the initiation queue it is to serve. `AMQSAMP4` defines a sample initiation queue, `SYSTEM.SAMPLE.TRIGGER`, that you can use when you try the sample programs.

Using the example trigger queue the command to issue is:

```
CALL PGM(QMQM/AMQSTRG4) PARM('SYSTEM.SAMPLE.TRIGGER')
```

### Design of the triggering sample

The triggering sample program opens the initiation queue using the `MQOPEN` call with the `MQOO_INPUT_AS_Q_DEF` option. It gets messages from the initiation queue using the `MQGET` call with the `MQGMO_ACCEPT_TRUNCATED_MSG` and `MQGMO_WAIT` options, specifying an unlimited wait interval. The program clears the `MsgId` and `CorrelId` fields before each `MQGET` call to get messages in sequence.

When it has retrieved a message from the initiation queue, the program tests the message:

- It checks the size of the message to make sure it is the same size as an MQTM structure.
- It checks the `ApplType` field to make sure it contains the value `MQAT_UNIX`.

If either of these tests fail, the program displays a warning.

For valid trigger messages, the triggering sample copies data from these fields: `ApplicId`, `EnvrData`, `Version`, and `ApplType`. The last two of these fields are numeric, so the program creates character replacements to use in an `MQTMC2` structure for OS/2, UNIX, and Windows NT, and in an `MQTMC` structure for AS/400.

## Triggering samples

The triggering sample issues a start command to the application specified in the *ApplicId* field of the trigger message, and passes an MQTMC2 or MQTMC (a character version of the trigger message) structure. In OS/2, UNIX systems, and Windows NT, the *EnvData* field is used as an extension to the invoking command string. In AS/400, it is used as job submission parameters, for example, the job priority.

Finally, the program closes the initiation queue.

## Running the AMQSERV4 sample

This is a trigger server for the AS/400 environment. For each trigger message, this server runs the start command in its own job to start the specified application. The trigger server can call CICS transactions.

AMQSERV4 takes one parameter: the name of the initiation queue it is to serve. AMQSAMP4 defines a sample initiation queue, SYSTEM.SAMPLE.TRIGGER, that you can use when you try the sample programs.

Using the example trigger queue the command to issue is:

```
CALL PGM(QMQM/AMQSERV4) PARM('SYSTEM.SAMPLE.TRIGGER')
```

## Design of the trigger server

The design of the trigger server is similar to that of the trigger monitor, except the trigger server:

- Allows MQAT\_CICS as well as MQAT\_OS400 applications
- Calls AS/400 applications in its own job (or uses STRCICSUSR to start CICS applications) rather than submitting an AS/400 job
- For CICS applications, substitutes the *EnvData*, for example, to specify the CICS region, from the trigger message in the STRCICSUSR command
- Opens the initiation queue for shared input, so many trigger servers can run at the same time

**Note:** Programs started by AMQSERV4 must not use the MQDISC call because this will stop the trigger server. If programs started by AMQSERV4 use the MQCONN call, they will get the MQRC\_ALREADY\_CONNECTED reason code.

## Ending the triggering sample programs on AS/400

A trigger monitor program can be ended by the sysrequest option 2 (ENDRQS) or by inhibiting gets from the trigger queue. If the sample trigger queue is used the command is:

```
CHGMQM QNAME('SYSTEM.SAMPLE.TRIGGER') GETENBL(*NO)
```

**Note:** To start triggering again on this queue, you **must** enter the command:

```
CHGMQM QNAME('SYSTEM.SAMPLE.TRIGGER') GETENBL(*YES)
```

---

## Running the samples using remote queues

You can demonstrate remote queuing by running the samples on connected queue managers.

Program amqscos0.tst provides a local definition of a remote queue (SYSTEM.SAMPLE.REMOTE) that uses a remote queue manager named OTHER. To use this sample definition, change OTHER to the name of the second queue manager you want to use. You must also set up a message channel between your two queue managers; for information on how to do this, see the *MQSeries Intercommunication* book.

The Request sample programs put their own local queue manager name in the *ReplyToQMgr* field of messages they send. The Inquire and Set samples send reply messages to the queue and message queue manager named in the *ReplyToQ* and *ReplyToQMgr* fields of the request messages they process.

---

## Database coordination samples

Two samples are provided which demonstrate how MQSeries can coordinate both MQSeries updates and database updates within the same unit of work:

1. AMQSXAS0 (in C) or AMQ0XAS0 (in COBOL), which updates a single database within an MQSeries unit of work.
2. AMQSXAG0 (in C) or AMQ0XAG0 (in COBOL), AMQSXAB0 (in C) or AMQ0XAB0 (in COBOL), and AMQSXAF0 (in C) or AMQ0XAF0 (in COBOL), which together update two databases within an MQSeries unit of work, showing how multiple databases can be accessed.

These samples are provided to show the use of the MQBEGIN call, mixed SQL and MQSeries calls, and where and when to connect to a database.

Figure 38 on page 374 shows how the samples provided are used to update databases.

## Database coordination samples




Figure 38. The database coordination samples

The programs read a message from a queue (under syncpoint), then, using the information in the message, obtain the relevant information from the database and update it. The new status of the database is then printed.

The program logic is as follows:

1. Use name of input queue from program argument
2. Connect to default queue manager (or optionally supplied name in C) using MQCONN
3. Open queue (using MQOPEN) for input while no failures
4. Start a unit of work using MQBEGIN
5. Get next message (using MQGET) from queue under syncpoint
6. Get information from databases
7. Update information from databases
8. Commit changes using MQCMIT
9. Print updated information (no message available counts as failure, and loop ends)
10. Close queue using MQCLOSE
11. Disconnect from queue using MQDISC

SQL cursors are used in the samples, so that reads from the databases (that is, multiple instances) are locked whilst a message is being processed, thus multiple instances of these programs can be run simultaneously. The cursors are explicitly opened, but implicitly closed by the MQCMIT call.

The single database sample (AMQXSAS0 or AMQ0XAS0) has no SQL CONNECT statements and the connection to the database is implicitly made by MQSeries with the MQBEGIN call. The multiple database sample (AMQXSAG0 or AMQ0XAG0, AMQXSAB0 or AMQ0XAB0, and AMQXSAF0 or AMQ0XAF0) has SQL CONNECT statements, as some database products allow only one active connection. If this is not the case for your database product, or if you are accessing a single database in multiple database products, the SQL CONNECT statements can be removed.

The samples are prepared with IBM's DB2 database product, so they may need some modification to work with other database products.

The SQL error checking uses routines in UTIL.C and CHECKERR.CBL supplied by DB2. These must be compiled or replaced before compiling and linking.

**Note:** If you are using the Micro Focus COBOL source CHECKERR.MFC for SQL error checking, you must change the program ID to uppercase, that is CHECKERR, for AMQ0XAS0 to link correctly.

## Creating the databases and tables

The databases and tables must be created before the samples can be compiled. To create the databases, use the normal method for your database product, for example:

```
DB2 CREATE DB MQBankDB
DB2 CREATE DB MQFeeDB
```

Create the tables using SQL statements as follows:

In C:

```
EXEC SQL CREATE TABLE MQBankT(Name          VARCHAR(40) NOT NULL,
                                Account      INTEGER   NOT NULL,
                                Balance      INTEGER   NOT NULL,
                                PRIMARY KEY (Account));
```

```
EXEC SQL CREATE TABLE MQBankTB(Name          VARCHAR(40) NOT NULL,
                                Account      INTEGER   NOT NULL,
                                Balance      INTEGER   NOT NULL,
                                Transactions  INTEGER,
                                PRIMARY KEY (Account));
```

```
EXEC SQL CREATE TABLE MQFeeTB(Account      INTEGER   NOT NULL,
                                FeeDue      INTEGER   NOT NULL,
                                TranFee     INTEGER   NOT NULL,
                                Transactions  INTEGER,
                                PRIMARY KEY (Account));
```

## Database coordination samples

In COBOL:

```
EXEC SQL CREATE TABLE
  MQBankT(Name      VARCHAR(40) NOT NULL,
          Account   INTEGER     NOT NULL,
          Balance   INTEGER     NOT NULL,
          PRIMARY KEY (Account))
END-EXEC.
```

```
EXEC SQL CREATE TABLE
  MQBankTB(Name      VARCHAR(40) NOT NULL,
            Account   INTEGER     NOT NULL,
            Balance   INTEGER     NOT NULL,
            Transactions INTEGER,
            PRIMARY KEY (Account))
END-EXEC.
```

```
EXEC SQL CREATE TABLE
  MQFeeTB(Account   INTEGER     NOT NULL,
            FeeDue   INTEGER     NOT NULL,
            TranFee  INTEGER     NOT NULL,
            Transactions INTEGER,
            PRIMARY KEY (Account))
END-EXEC.
```

Fill in the tables using SQL statements as follows:

```
EXEC SQL INSERT INTO MQBankT VALUES ('Mr Fred Bloggs',1,0);
EXEC SQL INSERT INTO MQBankT VALUES ('Mrs S Smith',2,0);
EXEC SQL INSERT INTO MQBankT VALUES ('Ms Mary Brown',3,0);
:
EXEC SQL INSERT INTO MQBankTB VALUES ('Mr Fred Bloggs',1,0,0);
EXEC SQL INSERT INTO MQBankTB VALUES ('Mrs S Smith',2,0,0);
EXEC SQL INSERT INTO MQBankTB VALUES ('Ms Mary Brown',3,0,0);
:
EXEC SQL INSERT INTO MQFeeTB VALUES (1,0,50,0);
EXEC SQL INSERT INTO MQFeeTB VALUES (2,0,50,0);
EXEC SQL INSERT INTO MQFeeTB VALUES (3,0,50,0);
:
```

**Note:** For COBOL, use the same SQL statements but add END\_EXEC at the end of each line.

## Preparing, compiling, and linking the samples

The .SQC files (in C) and .SQB files (in COBOL) must be prepared and bound against the appropriate database to produce the .C or .CBL files. To do this, use the normal method for your database product, for example:

In C:

```
SQLPREP AMQSXAS0.SQC MQBankDB
SQLPREP AMQSXAB0.SQC MQBankDB
SQLPREP AMQSXAFO.SQC MQFeeDB
```

In COBOL:

```
db2 connect to MQBankDB
db2 prep AMQ0XAS0.SQB bindfile target ibmcob
db2 bind AMQ0XAS0.BND
db2 connect reset
```

```
db2 connect to MQBankDB
db2 prep AMQ0XAB0.SQB bindfile target ibmcob
db2 bind AMQ0XAB0.BND
db2 connect reset
```

```
db2 connect to MQFeeDB
db2 prep AMQ0XAF0.SQB bindfile target ibmcob
db2 bind AMQ0XAF0.BND
db2 connect reset
```

Compile the files in the normal way to produce the object files. The samples must be linked against both your database libraries and the appropriate MQSeries libraries. For more information about compiling and linking, see Part 3, "Building an MQSeries application" on page 255 and your database documentation.

The following lists extra points to consider when compiling and linking:

- If you are working on HP-UX and wish to access DB2, add the following link flags:
 

```
-E -u allow_unaligned_data_access
```
- If you are working on AIX and wish to access Oracle, use the xlc\_r compiler and link to libmqm\_r.a.

## Running the samples

Before the samples can be run, the queue manager must be configured with the database product you are using. For information about how to do this, see Chapter 14, "Transactional support" in the *MQSeries System Administration* book.

### C samples

Messages must be in the following format to be read from a queue:

```
UPDATE Balance change=nnn WHERE Account=nnn
```

AMQSPUT can be used to put the messages on the queue.

The database coordination samples take two parameters:

1. Queue name (required)
2. Queue manager name (optional)

Assuming that you have created and configured a queue manager for the single database sample called singDBQM, with a queue called singDBQ, you increment Mr Fred Bloggs' account by 50 as follows:

```
AMQSPUT singDBQ singDBQM
```

Then key in the following message:

```
UPDATE Balance change=50 WHERE Account=1
```

## Database coordination samples

You can put multiple messages on the queue.

```
AMQXSAS0 singDBQ singDBQM
```

The updated status of Mr Fred Bloggs's account is then printed.

Assuming that you have created and configured a queue manager for the multiple-database sample called multDBQM, with a queue called multDBQ, you decrement Ms Mary Brown's account by 75 as follows:

```
AMQSPUT multDBQ multDBQM
```

Then key in the following message:

```
UPDATE Balance change=-75 WHERE Account=3
```

You can put multiple messages on the queue.

```
AMQSXAG0 multDBQ multDBQM
```

The updated status of Ms Mary Brown's account is then printed.

## COBOL samples

Messages must be in the following format to be read from a queue:

```
UPDATE Balance change=snnnnnnnn WHERE Account=nnnnnnnn
```

For simplicity, the Balance change must be a signed eight-character number and the Account must be an eight-character number.

The sample AMQSPUT can be used to put the messages on the queue.

The samples take no parameters and use the default queue manager. It can be configured to run only one of the samples at any time. Assuming that you have configured the default queue manager for the single database sample, with a queue called singDBQ, you increment Mr Fred Bloggs's account by 50 as follows:

```
AMQSPUT singDBQ
```

Then key in the following message:

```
UPDATE Balance change=+00000050 WHERE Account=00000001
```

You can put multiple messages on the queue.

```
AMQ0XAS0
```

Type in the name of the queue:

```
singDBQ
```

The updated status of Mr Fred Bloggs's account is then printed.

Assuming that you have configured the default queue manager for the multiple database sample, with a queue called multDBQ, you decrement Ms Mary Brown's account by 75 as follows:

```
AMQSPUT multDBQ
```

Then key in the following message:

```
UPDATE Balance change=-00000075 WHERE Account=00000003
```

You can put multiple messages on the queue.

```
AMQ0XAG0
```

Type in the name of the queue:

```
multDBQ
```

The updated status of Ms Mary Brown's account is then printed.

---

## The CICS transaction sample

A sample CICS transaction program is provided, named `amqscic0.ccs` for source code and `amqscic0` for the executable version. Transactions may be built using the standard CICS facilities. See Part 3, "Building an MQSeries application" on page 255 for details on the commands needed for your platform.

The transaction reads messages from the transmission queue `SYSTEM.SAMPLE.CICS.WORKQUEUE` on the default queue manager and places them on to the local queue, the name of which is contained in the transmission header of the message. Any failures will be sent to the queue `SYSTEM.SAMPLE.CICS.DLQ`.

**Note:** A sample MQSC script `amqscic0.tst` may be used to create these queues and sample input queues.

---

## TUXEDO samples

Before running these samples, you must build the server environment.

### Building the server environment

It is assumed that you have a working TUXEDO environment.

#### To build the server environment for MQSeries for AIX:

1. Create a directory (for example, `<APPDIR>`) in which the server environment is built and execute all commands in this directory.
2. Export the following environment variables, where `TUXDIR` is the root directory for TUXEDO:

```
$ export CFLAGS="-I /usr/mqm/inc -I /<APPDIR> -L /usr/mqm/lib"
$ export LDOPTS="-lmqm -lmqmzse -lnet -insl -lsocket -lc -ldl"
$ export FIELDTBLS=/usr/mqm/samp/amqstvx.flds
$ export VIEWFILES=/<APPDIR>/amqstvx.V
$ export LIBPATH_PATH=$(TUXDIR)/lib:/usr/mqm/lib:/lib
```

3. Add the following to the TUXEDO file `udataobj/RM`

```
MQSeries_XA_RMI:MQRMIXASwitchDynamic: \
/usr/mqm/lib/libmqmxa.a /usr/mqm/lib/libmqm.a
```

## 4. Run the commands:

```

$ mkfldhdr /usr/mqm/samp/amqstxvx.flds
$ viewc /usr/mqm/samp/amqstxvx.v
$ buildtms -o MQXA -r MQSeries_XA_RMI
$ buildserver -o MQSERV1 -f /usr/mqm/samp/amqstxsx.c \
-f /usr/mqm/lib/libmqm.a \
-r MQSeries_XA_RMI -s MPUT1:MPUT \
-s MGET1:MGET \
-v -bshm
$ buildserver -o MQSERV2 -f /usr/mqm/samp/amqstxsx.c \
-f /usr/mqm/lib/libmqm.a \
-r MQSeries_XA_RMI -s MPUT2:MPUT
-s MGET2:MGET \
-v -bshm
$ buildclient -o doputs -f /usr/mqm/samp/amqstxpx.c \
-f /usr/mqm/lib/libmqm.a
$ buildclient -o dogets -f /usr/mqm/samp/amqstxgx.c \
-f /usr/mqm/lib/libmqm.a

```

## 5. Edit ubbstxcx.cfg (see Figure 39 on page 385), and add details of the machine name, working directories, and queue manager as necessary:

```
$ tmloadcf -y /usr/mqm/samp/ubbstxcx.cfg
```

## 6. Create the TLOGDEVICE:

```
$tmadmin -c
```

A prompt then appears. At this prompt, enter:

```
> crd1 -z /<APPDIR>/TLOG1
```

## 7. Start the queue manager:

```
$ strmqm
```

## 8. Start Tuxedo:

```
$ tmboot -y
```

You can now use the doputs and dogets programs to put messages to a queue and retrieve them from a queue.

### To build the server environment for MQSeries for AT&T GIS UNIX and MQSeries for Sun Solaris:

1. Create a directory (for example, <APPDIR>) in which the server environment is built and execute all commands in this directory.
2. Export the following environment variables, where TUXDIR is the root directory for TUXEDO:

```

$ export CFLAGS="-I /<APPDIR>"
$ export FIELDTBLS=amqstxvx.flds
$ export VIEWFILES=amqstxvx.V
$ export SHLIB_PATH=$TUXDIR/lib:/opt/mqm/lib:lib
$ export LD_LIBRARY_PATH=$(TUXDIR)/lib:/opt/mqm/lib:lib

```

3. Add the following to the TUXEDO file udataobj/RM (RM must include /opt/mqm/lib/libmqmcs and /opt/mqm/lib/libmqmzse).

**Note:** The \ characters should not be entered into the file; they are line continuations.

```
MQSeries_XA_RMI:MQRMIXASwitchDynamic: \
/opt/mqm/lib/libmqmxa.a /opt/mqm/lib/libmqm.so \
/opt/tuxedo/lib/libtux.so /opt/mqm/lib/libmqm.so \
/opt/mqm/lib/libmqmzse.so
```

#### 4. Run the commands:

```
$ mkfldhdr    amqstvx.flds
$ viewc      amqstvx.v
$ buildtms   -o MQXA -r MQSeries_XA_RMI
$ buildserver -o MQSERV1 -f amqstxsx.c \
             -f /opt/mqm/lib/libmqm.so \
             -r MQSeries_XA_RMI -s MPUT1:MPUT \
             -s MGET1:MGET \
             -v -bshm
             -l -ldl
$ buildserver -o MQSERV2 -f amqstxsx.c \
             -f /opt/mqm/lib/libmqm.so \
             -r MQSeries_XA_RMI -s MPUT2:MPUT \
             -s MGET2:MGET \
             -v -bshm
             -l -ldl
$ buildclient -o doputs -f amqstxpx.c \
             -f /opt/mqm/lib/libmqm.so \
             -f /opt/mqm/lib/mqmzse.so \
             -f /opt/mqm/lib/mqmcs.so
$ buildclient -o dogets -f amqstxgx.c \
             -f /opt/mqm/lib/libmqm.so \
             -f /opt/mqm/lib/mqmzse.so \
             -f /opt/mqm/lib/mqmcs.so
```

#### 5. Edit ubbstxcx.cfg (see Figure 39 on page 385), and add details of the machine name, working directories, and Queue Manager as necessary:

```
$ tmloadcf -y ubbstxcx.cfg
```

#### 6. Create the TLOGDEVICE:

```
$tmadmin -c
```

A prompt then appears. At this prompt, enter:

```
> crdl -z /<APPDIR>/TLOG1
```

#### 7. Start the queue manager:

```
$ strmqm
```

#### 8. Start Tuxedo:

```
$ tmboot -y
```

You can now use the doputs and dogets programs to put messages to a queue and retrieve them from a queue.

**To build the server environment for MQSeries for HP-UX:**

1. Create a directory (for example, <APPDIR>) in which the server environment is built and execute all commands in this directory.
2. Export the following environment variables, where TUXDIR is the root directory for TUXEDO:

```

$ export CFLAGS="-Aa -D_HPUX_SOURCE"
$ export LDOPTS="-lmqm"
$ export FIELDTBLS=/opt/mqm/samp/amqstxvx.flds
$ export VIEWFILES=<APPDIR>/amqstxvx.V
$ export SHLIB_PATH=$SHLIB/lib:/opt/mqm/lib:lib
$ export LPATH=$TUXDIR/lib:/opt/mqm/lib:lib

```

3. Add the following to the TUXEDO file udataobj/RM

```

MQSeries_XA_RMI:MQRMIXASwitchDynamic: \
/opt/mqm/lib/libmqmxa.a /opt/mqm/lib/libmqm.sl \
/opt/tuxedo/lib/libtux.sl

```

4. Run the commands:

```

$ mkfldhdr /opt/mqm/samp/amqstxvx.flds
$ viewc /opt/mqm/samp/amqstxvx.v
$ buildtms -o MQXA -r MQSeries_XA_RMI
$ buildserver -o MQSERV1 -f /opt/mqm/samp/amqstxsx.c \
-f /opt/mqm/lib/libmqm.sl \
-r MQSeries_XA_RMI -s MPUT1:MPUT \
-s MGET1:MGET \
-v -bshm
$ buildserver -o MQSERV2 -f /opt/mqm/samp/amqstxsx.c \
-f /opt/mqm/lib/libmqm.sl \
-r MQSeries_XA_RMI -s MPUT2:MPUT \
-s MGET2:MGET \
-v -bshm
$ buildclient -o doputs -f /opt/mqm/samp/amqstxpx.c \
-f /opt/mqm/lib/libmqm.sl
$ buildclient -o dogets -f /opt/mqm/samp/amqstxgx.c \
-f /opt/mqm/lib/libmqm.sl

```

5. Edit ubbstxcx.cfg (see Figure 39 on page 385), and add details of the machine name, working directories, and Queue Manager as necessary:

```

$ tmloadcf -y /opt/mqm/samp/ubbstxcx.cfg

```

6. Create the TLOGDEVICE:

```

$tmadmin -c

```

A prompt then appears. At this prompt, enter:

```

> crd1 -z /<APPDIR>/TLOG1

```

7. Start the queue manager:

```

$ strmqm

```

8. Start Tuxedo:

```

$ tmboot -y

```

You can now use the doputs and dogets programs to put messages to a queue and retrieve them from a queue.

## To build the server environment for MQSeries for SINIX and DC/OSx

1. Export the following environment variables where TUXDIR is the root directory for TUXEDO:

```
$ export CFLAGS="-lmqm -lmqmcs -lmqzse -lmqmx \
-lns1 -lsocket -ldl -lproc -lxt"
```

**Note:** For DC/OSx, add "-liconv" to the above.

```
$ export FIELDTBLS=amqstvx.flds
$ export VIEWFILES=amqstvx.V
$ export VIEWDIR=The path to the directory where the views
are held
$ export TUXDIR=The path to the directory where TUXEDO
is installed (/opt/tuxedo).
$ export CFLAGS="-lmqm -lmqmcs -lmqzse -lmqmx \
-lns1 -lsocket -ldl -lproc -lxt"
```

2. Add the following to the TUXEDO file udataobj/RM

```
MQSeries_XA_RMI:MQRMIXASwitchDynamic: \
/opt/mqm/lib/libmqmx.so
/opt/mqm/lib/libmqm.so /opt/mqm/lib/libmqmcs.s
```

3. Ensure that your LD\_LIBRARY\_PATH contains the path to the Tuxedo libraries (/opt/tuxedo/lib), and that it is exported.
4. Ensure that your PATH contains the path to the Tuxedo bin directory (/opt/tuxedo/bin), and that it is exported.
5. Run the commands:

```
$ mkfldhdr    amqstvx.flds
$ viewc      amqstvx.v
```

6. Alter the value of the CFLAGS variable:

```
export CFLAGS="$CFLAGS -LDuMQRMIXASwitchDynamic -lmqmx"
```

7. Run the commands:

```
$ buildtms    -o MQXA -r MQSeries_XA_RMI
$ buildserver -o MQSERV1 -f amqstxsx.c \
-f /opt/mqm/lib/libmqm.so i \
-r MQSeries_XA_RMI -s MPUT1:MPUT \
-s MGET1:MGET \
-v -bshm
$ buildserver -o MQSERV2 -f amqstxsx.c \
-f /opt/mqm/lib/libmqm.so \
-r MQSeries_XA_RMI -s MPUT2:MPUT \
-s MGET2:MGET \
-v -bshm
$ buildclient -o doputs -f amqstxpx.c \
-f /opt/mqm/lib/libmqm.so
$ buildclient -o dogets -f amqstxgx.c \
-f /opt/mqm/lib/libmqm.so
```

8. Ensure that your NLS\_PATH contains the path to the Tuxedo messages (/opt/tuxedo/locale/C/%N), and that it is exported.
9. Edit ubbstxcx.cfg (see Figure 39 on page 385), and add details of the machine name, working directories, and Queue Manager as necessary.

## TUXEDO samples

10. Set the environment variable TUXCONFIG to the value specified in the MACHINES section of the ubbstxcx.cfg file.

11. If you are using the Tuxedo main machine, run the following commands:

```
tmadmin -c
```

At the prompt (>), enter:

```
crdl -z filename
```

where *filename* is the path to the Tuxedo TLOG file.

12. Run the following command:

```
$ tmloadcf -y ubbstxcx.cfg
```

13. Start the queue manager:

```
$ strmqm
```

14. Start Tuxedo:

```
$ tmboot -y
```

You can now use the doputs and dogets programs to put messages to a queue and retrieve them from a queue.

| For further information on building the TUXEDO server environment, see the  
| README file in the MQSeries sample directory, /opt/mqm/samp.

```

*RESOURCES
IPCKEY          <IPCKey>

#Example:
#IPCKEY        123456

MASTER         <MachineName>
MAXACCESSERS   20
MAXSERVERS     20
MAXSERVICES    50
MODEL          SHM
LDBAL          N

*MACHINES
DEFAULT:
                APPDIR="<WorkDirectory>"
                TUXCONFIG="<WorkDirectory>/tuxconfig"
                ROOTDIR="<RootDirectory>"

<MachineName> LMID=<MachineName>
                TLOGDEVICE="<WorkDirectory>/TLOG1"
                TLOGNAME=TLOG

*GROUPS
GROUP1
                LMID=<MachineName> GRPNO=1
                TMSNAME=MQXA
                OPENINFO="MQSeries_XA_RMI:MYQUEUEMANAGER"

*SERVERS
DEFAULT:
                CLOPT="--A -- -m MYQUEUEMANAGER

MQSERV1        SRVGRP=GROUP1 SRVID=1
MQSERV2        SRVGRP=GROUP1 SRVID=2

*SERVICES
MPUT1
MGET1
MPUT2
MGET2

```

Figure 39. Example of ubbstxcx.cfg file for UNIX systems

**Note:** Other information that you need to add is identified by <> characters. In this file, the queue manager name has been changed to MYQUEUEMANAGER:

### To build the server environment for MQSeries for Windows NT:

**Note:** Change the fields identified by <> in the following, to the directory paths:

<MQMDIR> the directory path specified when MQSeries was installed, for example g:\Program Files\MQSeries

<TUXDIR> the directory path specified when TUXEDO was installed, for example f:\tuxedo

<APPDIR> the directory path to be used for the sample application, for example f:\tuxedo\apps\mqapp

To build the server environment and samples:

1. Create an application directory in which to build the sample application, for example:

```
f:\tuxedo\apps\mqapp
```

2. Copy the following sample files from the MQSeries sample directory to the application directory:

```
amqstxmn.mak
amqstxen.env
ubbstxcn.cfg
```

3. Edit each of these files to set the directory names and directory paths used on your installation.
4. Edit ubbstxcn.cfg (see Figure 40 on page 387) to add details of the machine name and the Queue Manager that you wish to connect to.
5. Add the following line to the TUXEDO file <TUXDIR>udataobj\rm

```
MQSeries_XA_RMI;MQRMIXASwitchDynamic;
<MQMDIR>\tools\lib\mqmtux.lib <MQMDIR>\tools\lib\mqm.lib
```

where <MQMDIR> is replaced as above. Although shown here as two lines, the new entry must be one line in the file.

6. Set the following environment variables:

```
TUXDIR=<TUXDIR>
TUXCONFIG=<APPDIR>\tuxconfig
FIELDTBLS=<MQMDIR>\tools\c\samples\amqstxvx.fld
LANG=C
```

7. Create a TLOG device for TUXEDO. To do this, invoke `tmadmin -c`, and enter the command:

```
crdl -z <APPDIR>\TLOG
```

where <APPDIR> is replaced as above.

8. Set the current directory to <APPDIR>, and invoke the sample makefile (amqstxmn.mak) as an external project makefile. For example, with Microsoft Visual C++ Version 2.0, issue the command:

```
msvc amqstxmn.mak
```

Select **build** to build all the sample programs.

```

*RESOURCES
IPCKEY      99999
UID         0
GID         0
MAXACCESSERS 20
MAXSERVERS  20
MAXSERVICES 50
MASTER     SITE1
MODEL       SHM
LDBAL       N

*MACHINES
<MachineName> LMID=SITE1
                TUXDIR="f:\tuxedo"
                APPDIR="f:\tuxedo\apps\mqapp;g:\Program Files\MQSeries\bin"
                ENVFILE="f:\tuxedo\apps\mqapp\amqstxen.env"
                TUXCONFIG="f:\tuxedo\apps\mqapp\tuxconfig"
                ULOGPFX="f:\tuxedo\apps\mqapp\ULOG"
                TLOGDEVICE="f:\tuxedo\apps\mqapp\TLOG"
                TLOGNAME=TLOG
                TYPE="i386NT"
                UID=0
                GID=0

*GROUPS
GROUP1
                LMID=SITE1  GRPNO=1
                TMSNAME=MQXA
                OPENINFO="MQSeries_XA_RMI:MYQUEUEMANAGER"

*SERVERS
DEFAULT: CLOPT="--A -- -m MYQUEUEMANAGER"

MQSERV1    SRVGRP=GROUP1 SRVID=1
MQSERV2    SRVGRP=GROUP1 SRVID=2

*SERVICES
MPUT1
MGET1
MPUT2
MGET2

```

Figure 40. Example of ubbstxcn.cfg file for Windows NT

**Note:** The directory names and directory paths must be changed to match your installation. The queue manager name MYQUEUEMANAGER should also be changed to the name of the queue manager you wish to connect to. Other information that you need to add is identified by <> characters.

The sample ubbconfig file for MQSeries for Windows NT is listed in Figure 40. It is supplied as ubbstxcn.cfg in the MQSeries samples directory.

The sample makefile (see Figure 41 on page 388) supplied for MQSeries for Windows NT is called ubbstxmn.mak, and is held in the MQSeries samples directory.

```

TUXDIR = f:\tuxedo
MQMDIR = g:\Program Files\MQSeries
APPDIR = f:\tuxedo\apps\mqapp
MQMLIB = $(MQMDIR)\tools\lib
MQMINC = $(MQMDIR)\tools\c\include
MQMSAMP = $(MQMDIR)\tools\c\samples
INC = -f "-I$(MQMINC) -I$(APPDIR)"
DBG = -f "/Zi"

amqstx.exe:
$(TUXDIR)\bin\mkfldhdr -d$(APPDIR) $(MQMSAMP)\amqstxvx.fld
$(TUXDIR)\bin\viewc -d$(APPDIR) $(MQMSAMP)\amqstxvx.v
$(TUXDIR)\bin\builtdtms -o MQXA -r MQSeries_XA_RMI
$(TUXDIR)\bin\buildserver -o MQSERV1 -f $(MQMSAMP)\amqstxsx.c \
-f $(MQMLIB)\mqm.lib -v $(INC) $(DBG) \
-r MQSeries_XA_RMI \
-s MPUT1:MPUT -s MGET1:MGET
$(TUXDIR)\bin\buildserver -o MQSERV2 -f $(MQMSAMP)\amqstxsx.c \
-f $(MQMLIB)\mqm.lib -v $(INC) $(DBG) \
-r MQSeries_XA_RMI \
-s MPUT2:MPUT -s MGET2:MGET
$(TUXDIR)\bin\buildclient -o doputs -f $(MQMSAMP)\amqstxpx.c \
-f $(MQMLIB)\mqm.lib -v $(INC) $(DBG)
$(TUXDIR)\bin\buildclient -o dogets -f $(MQMSAMP)\amqstxgx.c \
-f $(MQMLIB)\mqm.lib $(INC) -v $(DBG)
$(TUXDIR)\bin\tmloadcf -y $(APPDIR)\ubbstxcn.cfg

```

Figure 41. Sample TUXEDO makefile for MQSeries for Windows NT

## Server sample program for TUXEDO

This program is designed to run with the Put (amqstxpx.c) and the Get (amqstxgx.c) sample programs. The sample server program runs automatically when TUXEDO is started.

**Note:** You must start your queue manager *before* you start TUXEDO.

The sample server provides two TUXEDO services, MPUT1 and MGET1.

The MPUT1 service is driven by the PUT sample and uses MQPUT1 in syncpoint to put a message in a unit of work controlled by TUXEDO. It takes the parameters QName and Message Text, which are supplied by the PUT sample.

The MGET1 service opens and closes the queue each time it gets a message. It takes the parameters QName and Message Text, which are supplied by the GET sample.

Any error messages, reason codes, and status messages are written to the TUXEDO log file.




Figure 42. How TUXEDO samples work together

## Put sample program for TUXEDO

This sample allows you to put a message on a queue multiple times, in batches, demonstrating syncpointing using TUXEDO as the resource manager. The sample server program `amqstxsx` must be running for the put sample to succeed - the server sample program makes the connection to the queue manager and uses the XA interface. To run the sample enter:

- `doputs -n queuename -b batchsize -c tranccount -t message`

For example:

- `doputs -n myqueue -b 5 -c 6 -t "Hello World"`

This puts 30 messages on to the queue named `myqueue`, in 6 batches each with 5 messages in them. If there are any problems it will back a batch of messages out, otherwise it will commit them.

Any error messages are written to the TUXEDO log file and to `stderr`. Any reason codes are written to `stderr`.

### Get sample for TUXEDO

This sample allows you to get messages from a queue in batches. The sample server program `amqstxsx` must be running for the put sample to succeed - the server sample program makes the connection to the queue manager and uses the XA interface. To run the sample enter:

- `dogets -n queueName -b batchSize -c trancount`

For example:

- `dogets -n myqueue -b 6 -c 4`

This takes 24 messages off the queue named `myqueue`, in 6 batches each with 4 messages in them. If you ran this after the put example, which put 30 messages on `myqueue`, you would now have only 6 messages on `myqueue`. Note that the number of batches and the batch size can vary between the putting of messages and the getting of them.

Any error messages are written to the TUXEDO log file and to `stderr`. Any reason codes are written to `stderr`.

---

### Encina sample program

This program puts 10 messages to the queue, backing out the odd numbered messages and committing the even numbered messages. The message is a 4-byte number.

The queue used by this sample is the `SYSTEM.DEFAULT.MODEL.QUEUE`, so a temporary dynamic queue is created each time the program is run. You will need to run `trace` to see what happens when the program runs.

### Building the AMQSXAE0.C sample

When compiling for a UNIX or OS/2 platform, ensure that the symbolic constant, `WIN32` is not defined. This constant is used in the preprocessor statements for processing specific to Windows NT:

```
#if defined(WIN32)
```

#### Compiling and linking on Windows NT

When compiling, specify the following options (in addition to those usually specified for an MQSeries application) to the C compiler:

```
-MD -DWIN32 -DDEC_DCE -Gz
```

The sample contains references to the Encina header files:

```
#include <tc/tc.h>  
#include <tmxa/tmxa_status.h>  
#include <tmxa/tmxa.h>
```

At compile time, also include the parent directory path name containing these files, using the compiler `-I` option with a value which names the directory. For example:

```
-Ic:\opt\encina\include
```

At link time, the directory path names containing the Encina and DCE library files must also be specified to the linker, by setting the LIB environment variable. For example:

```
SET LIB=C:\OPT\ENCINA\LIB;C:\OPT\DCE\LIB;%LIB%
```

When linking, specify the following library files:

- mqm.lib
- mqmenc.lib
- libEncServer.lib
- libEncina.lib
- msvcrt.lib
- pthreads.lib
- libdce.lib

### Compiling and linking on Sun Solaris

Use the following invocation:

```
cc -I/opt/encina/include -c amqsxae0.c && cc -mt -o amqsxae0 amqsxae0.o \
-L/opt/encina/lib -L/opt/mqm/lib -lmqm -lmqmcs_d -lmqzse -lmqmx \
-lsocket -lnsl -ldce -lthread -lEncServer -lEncina -lc -lm
```

## Dead-letter queue handler sample

A sample dead-letter queue handler is provided, the name of the executable version is amqsdlq. If you want a dead-letter queue handler that is different to RUNMQDLQ, the source of the sample is available for you to use your base.

The sample is similar to the dead-letter handler provided within the product but trace and error reporting are different. There are two environment variables available to you:

ODQ\_TRACE set to YES or yes to switch tracing on

ODQ\_MSG set to the name of the file containing error and information messages. The file provided is called amqsdlq.msg.

These need to be made known to your environment using either the **export** or **set** commands, depending on your platform; trace is turned off using the **unset** command.

You can modify the error message file, amqsdlq.msg, to suit your own requirements. The sample puts messages out to stdout, **not** to the MQSeries error log file.

The *System Management Guide* for your platform explains how the dead-letter handler works, and how you run it.

## The Connect sample program

The Connect sample program allows you to explore the MQCONNX call and its options from a client. The sample connects to the queue manager using the MQCONNX call, inquires about the name of the queue manager using the MQINQ call, and displays it.

## Connect sample program

**Note:** The Connect sample program is a client sample. You can compile and run it on a server but the function is meaningful only on a client, and only client executables are supplied.

### Running the amqscnxc sample

The command-line syntax of the Connect sample program is:

```
amqscnxc [-x ConnName [-c SvrconnChannelName]] [QMgrName]
```

The parameters are optional and their order is not important with the exception that QMgrName, if it is specified, must come last. The parameters are:

<b>ConnName</b>	The TCP/IP connection name of the server queue manager
<b>SvrconnChannelName</b>	The name of the server connection channel
<b>QMgrName</b>	The name of the target queue manager

If you do not specify the TCP/IP connection name, MQCONN is issued with the *ClientConnPtr* set to NULL. If you specify the TCP/IP connection name but not the server connection channel (the reverse is not allowed) the sample uses the name SYSTEM.DEF.SVRCONN. If you do not specify the target queue manager the sample connects to whichever queue manager is listening at the given TCP/IP connection name.

**Note:** If you enter a question mark as the only parameter or if you enter incorrect parameters you will see a message explaining how to use the program.

If you run the sample with no command-line options the contents of the MQSERVER environment variable are used to determine the connection information. (In this example MQSERVER is set to "SYSTEM.DEF.SVRCONN/TCP/machine.site.company.com".) You see output like this:

```
Sample AMQSCNXC start
Connecting to the default queue manager
with no client connection information specified.
Connection established to queue manager machine
```

```
Sample AMQSCNXC end
```

If you run the sample and provide a TCP/IP connection name and a server connection channel name but no target queue manager name, like this:

```
amqscnxc -x machine.site.company.com -c SYSTEM.ADMIN.SVRCONN
```

the default queue manager name is used and you see output like this:

```
Sample AMQSCNXC start
Connecting to the default queue manager
using the server connection channel SYSTEM.ADMIN.SVRCONN
on connection name machine.site.company.com.
Connection established to queue manager MACHINE
```

```
Sample AMQSCNXC end
```

If you run the sample and provide a TCP/IP connection name and a target queue manager name, like this:

```
amqscnxc -x machine.site.company.com MACHINE
```

```
|          you see output like this:  
|          Sample AMQSCNXC start  
|          Connecting to queue manager MACHINE  
|          using the server connection channel SYSTEM.DEF.SVRCONN  
|          on connection name machine.site.company.com.  
|          Connection established to queue manager MACHINE  
  
|          Sample AMQSCNXC end
```

## Connect sample program

---

## Chapter 32. Sample programs for MQSeries for OS/390

This chapter describes the sample applications that are delivered with MQSeries for OS/390. These samples demonstrate typical uses of the Message Queue Interface (MQI).

MQSeries for OS/390 also provides a sample API-crossing exit program, described in the “The API-crossing exit for OS/390” on page 225, and sample data-conversion exits, described in Chapter 11, “Writing data-conversion exits” on page 161.

The sample applications are supplied in source form only. The source modules include pseudocode that describes the program logic. If you want to run the samples, follow the instructions given in:

- “Preparing and running sample applications for the batch environment” on page 399
- “Preparing the sample applications for the CICS environment” on page 403
- “Preparing the sample application for the IMS environment” on page 407

**Note:** Although some of the sample applications have basic panel-driven interfaces, they do not aim to demonstrate how to design the “look and feel” of your applications. For more information on how to design panel-driven interfaces for nonprogrammable terminals, see the *SAA Common User Access: Basic Interface Design Guide* (SC26-4583) and its addendum (GG22-9508). These provide guidelines to help you design applications that are consistent both within the application and across other applications.

---

### Features demonstrated in the sample applications

This section summarizes the MQI features demonstrated in each of the sample applications, shows the programming languages that each sample is written in, and the environment in which each sample runs. Descriptions of the design of each sample are given in:

- “The Put samples” on page 408
- “The Get samples” on page 411
- “The Browse sample” on page 414
- “The Print Message sample” on page 416
- “The Queue Attributes sample” on page 420
- “The Mail Manager sample” on page 421
- “The Credit Check sample” on page 430
- “The Message Handler sample” on page 443

### Put samples

The Put samples demonstrate how to put messages on a queue using the MQPUT call.

The application uses these MQI calls:

- MQCONN
- MQOPEN

## Features demonstrated

- MQPUT
- MQCLOSE
- MQDISC

The program is delivered in COBOL and C, and runs in the batch and CICS environment. See Table 32 on page 400 for the batch application and Table 37 on page 404 for the CICS application.

## Get samples

The Get samples demonstrate how to get messages from a queue using the MQGET call.

The application uses these MQI calls:

- MQCONN
- MQOPEN
- MQGET
- MQCLOSE
- MQDISC

The program is delivered in COBOL and C, and runs in the batch and CICS environment. See Table 32 on page 400 for the batch application and Table 37 on page 404 for the CICS application.

## Browse sample

The Browse sample demonstrates how to browse a message, print it, then step through the messages on a queue.

The application uses these MQI calls:

- MQCONN
- MQOPEN
- MQGET for browsing messages
- MQCLOSE
- MQDISC

The program is delivered in the COBOL, assembler, PL/I, and C languages. The application runs in the batch environment. See Table 33 on page 401 for the batch application.

## Print Message sample

The Print Message sample demonstrates how to remove a message from a queue and print the data in the message, together with all the fields of its message descriptor. By removing comment characters from two lines in the source module, you can change the program so that it browses, rather than removes, the messages on a queue. This program can usefully be used for diagnosing problems with an application that is putting messages on a queue.

The application uses these MQI calls:

- MQCONN
- MQOPEN
- MQGET for removing messages from a queue (with an option to browse)
- MQCLOSE

- MQDISC

The program is delivered in the C language. The application runs in the batch environment. See Table 34 on page 401 for the batch application.

## Queue Attributes sample

The Queue Attributes sample demonstrates how to inquire about and set the values of MQSeries for OS/390 object attributes.

The application uses these MQI calls:

- MQOPEN
- MQINQ
- MQSET
- MQCLOSE

The program is delivered in the COBOL, assembler, and C languages. The application runs in the CICS environment. See Table 38 on page 405 for the CICS application.

## Mail Manager sample

The Mail Manager sample demonstrates these techniques:

- Using alias queues
- Using a model queue to create a temporary dynamic queue
- Using reply-to queues
- Using syncpoints in the CICS and batch environments
- Sending commands to the system-command input queue
- Testing return codes
- Sending messages to remote queue managers, both by using a local definition of a remote queue and by putting messages directly on a named queue at a remote queue manager

The application uses these MQI calls:

- MQCONN
- MQOPEN
- MQPUT1
- MQGET
- MQINQ
- MQCMIT
- MQCLOSE
- MQDISC

Three versions of the application are provided:

- A CICS application written in COBOL
- A TSO application written in COBOL
- A TSO application written in C

The TSO applications use the MQSeries for OS/390 batch adapter and include some ISPF panels.

See Table 35 on page 402 for the TSO application, and Table 39 on page 405 for the CICS application.

### Credit Check sample

The Credit Check sample is a suite of programs that demonstrates these techniques:

- Developing an application that runs in more than one environment
- Using a model queue to create a temporary dynamic queue
- Using a correlation identifier
- The setting and passing of context information
- Using message priority and persistence
- Starting programs by using triggering
- Using reply-to queues
- Using alias queues
- Using a dead-letter queue
- Using a namelist
- Testing return codes

The application uses these MQI calls:

- MQOPEN
- MQPUT
- MQPUT1
- MQGET for browsing and getting messages, using the wait and signal options, and for getting a specific message
- MQINQ
- MQSET
- MQCLOSE

The sample can run as a stand-alone CICS application. However, to demonstrate how to design a message queuing application that uses the facilities provided by both the CICS and IMS environments, one module is also supplied as an IMS batch message processing program.

The CICS programs are delivered in C and COBOL. The single IMS program is delivered in C.

See Table 40 on page 406 for the CICS application, and Table 41 on page 408 for the IMS application.

### The Message Handler sample

The Message Handler sample allows you to browse, forward, and delete messages on a queue.

The application uses these MQI calls:

- MQCONN
- MQOPEN
- MQINQ
- MQPUT1
- MQCMIT
- MQBACK
- MQGET
- MQCLOSE

- MQDISC

The program is delivered in C and COBOL programming languages. The application runs under TSO. See Table 36 on page 403 for the TSO application.

## Distributed queuing exit samples

The names of the source programs of the distributed queuing exit samples are listed in the following table:

Member name	For language	Description	Supplied in library
CSQ4BAX0	Assembler	Source program	SCSQASMS
CSQ4BCX1	C	Source program	SCSQC37S
CSQ4BCX2	C	Source program	SCSQC37S

**Note:** The source programs are link-edited with CSQXSTUB.

See Chapter 35, “Channel-exit programs” in the *MQSeries Intercommunication* book for a description of the distributed queuing exit samples.

## Data-conversion exit samples

A skeleton is provided for a data-conversion exit routine, and a sample is shipped with MQSeries illustrating the MQXCNVC call. The names of the source programs of the data-conversion exit samples are listed in the following table:

Member name	Description	Supplied in library
CSQ4BAX8	Source program	SCSQASMS
CSQ4BAX9	Source program	SCSQASMS
CSQ4CAX9	Source program	SCSQASMS

**Note:** The source programs are link-edited with CSQASTUB.

See Chapter 11, “Writing data-conversion exits” on page 161 for more information.

## Preparing and running sample applications for the batch environment

To prepare a sample application that runs in the batch environment, perform the same steps that you would when building any batch MQSeries for OS/390 application. These steps are listed in “Building OS/390 batch applications” on page 275.

**Note:** The assembler language version of the Browse sample uses data control blocks (DCBs), so you must link-edit it using RMODE(24).

The library members that you will use are listed in Table 32, Table 33, and Table 34 on page 401.

## Preparing and running samples

You must edit the run JCL supplied for the samples that you want to use (see Table 32, Table 33, and Table 34 on page 401).

The PARM statement in the supplied JCL contains a number of parameters that you need to modify. To run the C sample programs, separate the parameters by spaces; to run the Assembler, COBOL, and PL/I sample programs, separate them by commas. For example, if the name of your queue manager is CSQ1 and you want to run the application with a queue named LOCALQ1, in the COBOL, PL/I, and assembler-language JCL, your PARM statement should look like this:

```
PARM=(CSQ1,LOCALQ1)
```

In the C language JCL, your PARM statement should look like this:

```
PARM=('CSQ1 LOCALQ1')
```

You are now ready to submit the jobs.

## Names of the sample batch applications

The names of the source programs and JCL that are supplied for each of the sample batch applications are listed in the following tables:

<b>Put and Get samples</b>	Table 32
<b>Browse sample</b>	Table 33 on page 401
<b>Print message sample</b>	Table 34 on page 401

*Table 32. Source and JCL for the Put and Get samples*

<b>Member name</b>	<b>For language</b>	<b>Description</b>	<b>Supplied in library</b>
CSQ4BCJ1	C	Get source program	SCSQC37S
CSQ4BCK1	C	Put source program	SCSQC37S
CSQ4BVJ1	COBOL	Get source program	SCSQCOBS
CSQ4BVK1	COBOL	Put source program	SCSQCOBS
CSQ4BCJR	C	Sample run JCL	SCSQPROC
CSQ4BVJR	COBOL	Sample run JCL	SCSQPROC

*Table 33. Source and JCL for the Browse sample*

Member name	For language	Description	Supplied in library
CSQ4BVA1	COBOL	Source program	SCSQCOBS
CSQ4BVAR	COBOL	Sample run JCL	SCSQPROC
CSQ4BAA1	Assembler	Source program	SCSQASMS
CSQ4BAAR	Assembler	Sample run JCL	SCSQPROC
CSQ4BCA1	C	Source program	SCSQC37S
CSQ4BCAR	C	Sample run JCL	SCSQPROC
CSQ4BPA1	PL/I	Source program	SCSQPLIS
CSQ4BPAR	PL/I	Sample run JCL	SCSQPROC

*Table 34. Source for the Print Message sample (C language only)*

Member name	Description	Supplied in library
CSQ4BCG1	Source program	SCSQC37S
CSQ4BCGR	Sample run JCL	SCSQPROC

## Preparing sample applications for the TSO environment

To prepare a sample application that runs in the TSO environment, perform the same steps that you would when building any batch MQSeries for OS/390 application—these steps are listed in “Building OS/390 batch applications” on page 275. The library members you will use are listed in Table 35 on page 402.

For the Mail Manager sample application, ensure that the queues it uses are available on your system. They are defined in the member **thlqual.SCSQPROC(CSQ4CVD)**. To ensure that these queues are always available, you could add these members to your CSQINP2 initialization input data set, or use the CSQUTIL program to load these queue definitions.

## Names of the sample TSO applications

The names of the source programs that are supplied for each of the sample TSO applications are listed in the following tables:

<b>Mail manager sample</b>	Table 35 on page 402
<b>Message handler sample</b>	Table 36 on page 403

These samples use ISPF panels. You must therefore include the ISPF stub, ISPLINK, when you link-edit the programs.

## Preparing and running samples

<i>Table 35. Source and JCL for the Mail Manager (TSO) sample</i>			
<b>Member name</b>	<b>For language</b>	<b>Description</b>	<b>Supplied in library</b>
CSQ4CVD	independent	MQSeries for OS/390 object definitions	SCSQPROC
CSQ40	independent	ISPF messages	SCSQMSGE
CSQ4RVD1	COBOL	CLIST to initiate CSQ4TVD1	SCSQCLST
CSQ4TVD1	COBOL	Source program for Menu program	SCSQCOBS
CSQ4TVD2	COBOL	Source program for Get Mail program	SCSQCOBS
CSQ4TVD4	COBOL	Source program for Send Mail program	SCSQCOBS
CSQ4TVD5	COBOL	Source program for Nickname program	SCSQCOBS
CSQ4VDP1-6	COBOL	Panel definitions	SCSQPNLA
CSQ4VD0	COBOL	Data definition	SCSQCOBC
CSQ4VD1	COBOL	Data definition	SCSQCOBC
CSQ4VD2	COBOL	Data definition	SCSQCOBC
CSQ4VD4	COBOL	Data definition	SCSQCOBC
CSQ4RCD1	C	CLIST to initiate CSQ4TCD1	SCSQCLST
CSQ4TCD1	C	Source program for Menu program	SCSQ37S
CSQ4TCD2	C	Source program for Get Mail program	SCSQ37S
CSQ4TCD4	C	Source program for Send Mail program	SCSQ37S
CSQ4TCD5	C	Source program for Nickname program	SCSQ37S
CSQ4CDP1-6	C	Panel definitions	SCSQPNLA
CSQ4TC0	C	Include file	SCSQ370

*Table 36. Source for the Message Handler sample*

Member name	For language	Description	Supplied in library
CSQ4TCH0	C	Data definition	SCSQ370
CSQ4TCH1	C	Source program	SCSQ37S
CSQ4TCH2	C	Source program	SCSQ37S
CSQ4TCH3	C	Source program	SCSQ37S
CSQ4RCH1	C and COBOL	CLIST to initiate CSQ4TCH1 or CSQ4TVH1	SCSQCLST
CSQ4CHP1	C and COBOL	Panel definition	SCSQPNLA
CSQ4CHP2	C and COBOL	Panel definition	SCSQPNLA
CSQ4CHP3	C and COBOL	Panel definition	SCSQPNLA
CSQ4CHP9	C and COBOL	Panel definition	SCSQPNLA
CSQ4TVH0	COBOL	Data definition	SCSQCOBC
CSQ4TVH1	COBOL	Source program	SCSQCOBS
CSQ4TVH2	COBOL	Source program	SCSQCOBS
CSQ4TVH3	COBOL	Source program	SCSQCOBS

## Preparing the sample applications for the CICS environment

Before you run the CICS sample programs, you must log on to CICS using a LOGMODE of 32702. This is because the sample programs have been written to use a 3270 mode 2 screen.

To prepare a sample application that runs in the CICS environment, perform the following steps:

1. Create the symbolic description map and the physical screen map for the sample by assembling the BMS screen definition source (supplied in library **thlqual**.SCSQMAPS, where **thlqual** is the high-level qualifier used by your installation). When you name the maps, use the name of the BMS screen definition source (not available for Put and Get sample programs), but omit the last character of that name.
2. Perform the same steps that you would when building any CICS MQSeries for OS/390 application—these steps are listed in “Building CICS applications” on page 277. The library members that you will use are listed in Table 37 on page 404, Table 38 on page 405, Table 39 on page 405, and Table 40 on page 406.
3. Identify the map set, programs, and transaction to CICS by updating the CICS system definition (CSD) data set. The definitions you require are in the member **thlqual**.SCSQPROC(CSQ4S100). For guidance on how to do this, see the *MQSeries for OS/390 System Management Guide*.

**Note:** For the Credit Check sample application, you will get an error message at this stage if you have not already created the VSAM data set that the sample uses.

## Preparing and running samples

4. For the Credit Check and Mail Manager sample applications, ensure that the queues they use are available on your system. For the Credit Check sample, they are defined in the member **thlqual.SCSQPROC(CSQ4CVB)** for COBOL, and **thlqual.SCSQPROC(CSQ4CCB)** for C. For the Mail Manager sample, they are defined in the member **thlqual.SCSQPROC(CSQ4CVD)**. To ensure that these queues are always available, you could add these members to your CSQINP2 initialization input data set, or use the CSQUTIL program to load these queue definitions.

For the Queue Attributes sample application, you could use one or more of the queues that are supplied for the other sample applications. Alternatively, you could use your own queues. However, note that in the form that it is supplied, this sample works only with queues that have the characters CSQ4SAMP in the first eight bytes of their name.

## QLOP abend

When the CICS sample applications supplied with MQSeries for OS/390 use MQI calls, they do not test for the return codes that indicate that the queue manager is not available. If the queue manager is not available when you attempt to run one of the CICS samples, the sample abends with the CICS abend code QLOP. If this happens, you must connect your queue manager to your CICS system before you attempt to start the sample application again. For information about starting a connection, see the *MQSeries for OS/390 System Management Guide*.

## Names of the sample CICS applications

The source and JCL files that are supplied for each of the sample CICS applications are listed in the following tables:

<b>Put and Get samples</b>	Table 37
<b>Queue attributes sample</b>	Table 38 on page 405
<b>Mail Manager (CICS) sample</b>	Table 39 on page 405
<b>Credit Check (CICS) sample</b>	Table 40 on page 406

<b>Member name</b>	<b>For language</b>	<b>Description</b>	<b>Supplied in library</b>
CSQ4CCK1	C	Source program	SCSQC37S
CSQ4CCJ1	C	Source program	SCSQC37S
CSQ4CVJ1	COBOL	Source program	SCSQCOBS
CSQ4CVK1	COBOL	Source program	SCSQCOBS
CSQ4S100	independent	CICS system definition data set	SCSQPROC

*Table 38. Source for the Queue Attributes sample*

Member name	For language	Description	Supplied in library
CSQ4CVC1	COBOL	Source program	SCSQCOBS
CSQ4VMSG	COBOL	Message definition	SCSQCOBC
CSQ4VCMS	COBOL	BMS screen definition	SCSQMAPS
CSQ4CAC1	Assembler	Source program	SCSQASMS
CSQ4AMSG	Assembler	Message definition	SCSQMACS
CSQ4ACMS	Assembler	BMS screen definition	SCSQMAPS
CSQ4CCC1	C	Source program	SCSQC37S
CSQ4CMMSG	C	Message definition	SCSQC370
CSQ4CCMS	C	BMS screen definition	SCSQMAPS
CSQ4S100	independent	CICS system definition data set	SCSQPROC

*Table 39. Source and JCL for the Mail Manager (CICS) sample (COBOL only)*

Member name	Description	Supplied in library
CSQ4CVD	MQSeries for OS/390 object definitions	SCSQPROC
CSQ4CVD1	Source for Menu program	SCSQCOBS
CSQ4CVD2	Source for Get Mail program	SCSQCOBS
CSQ4CVD3	Source for Display Message program	SCSQCOBS
CSQ4CVD4	Source for Send Mail program	SCSQCOBS
CSQ4CVD5	Source for Nickname program	SCSQCOBS
CSQ4VDMS	BMS screen definition source	SCSQMAPS
CSQ4S100	CICS system definition data set	SCSQPROC
CSQ4VD0	Data definition	SCSQCOBC
CSQ4VD3	Data definition	SCSQCOBC
CSQ4VD4	Data definition	SCSQCOBC

## Preparing and running samples

<i>Table 40. Source and JCL for the Credit Check CICS sample</i>			
<b>Member name</b>	<b>For language</b>	<b>Description</b>	<b>Supplied in library</b>
CSQ4CVB	independent	MQSeries object definitions	SCSQPROC
CSQ4CCB	independent	MQSeries object definitions	SCSQPROC
CSQ4CVB1	COBOL	Source for user-interface program	SCSQCOBS
CSQ4CVB2	COBOL	Source for credit application manager	SCSQCOBS
CSQ4CVB3	COBOL	Source for checking-account program	SCSQCOBS
CSQ4CVB4	COBOL	Source for distribution program	SCSQCOBS
CSQ4CVB5	COBOL	Source for agency-query program	SCSQCOBS
CSQ4CCB1	C	Source for user-interface program	SCSQ37S
CSQ4CCB2	C	Source for credit application manager	SCSQ37S
CSQ4CCB3	C	Source for checking-account program	SCSQ37S
CSQ4CCB4	C	Source for distribution program	SCSQ37S
CSQ4CCB5	C	Source for agency-query program	SCSQ37S
CSQ4CB0	C	Include file	SCSQ370
CSQ4CBMS	C	BMS screen definition source	SCSQMAPS
CSQ4VBMS	COBOL	BMS screen definition source	SCSQMAPS
CSQ4VB0	COBOL	Data definition	SCSQCOBC
CSQ4VB1	COBOL	Data definition	SCSQCOBC
CSQ4VB2	COBOL	Data definition	SCSQCOBC
CSQ4VB3	COBOL	Data definition	SCSQCOBC
CSQ4VB4	COBOL	Data definition	SCSQCOBC
CSQ4VB5	COBOL	Data definition	SCSQCOBC
CSQ4VB6	COBOL	Data definition	SCSQCOBC
CSQ4VB7	COBOL	Data definition	SCSQCOBC
CSQ4VB8	COBOL	Data definition	SCSQCOBC
CSQ4BAQ	independent	Source for VSAM data set	SCSQPROC
CSQ4FILE	independent	JCL to build VSAM data set used by CSQ4CVB3	SCSQPROC
CSQ4S100	independent	CICS system definition data set	SCSQPROC

---

## Preparing the sample application for the IMS environment

Part of the Credit Check sample application can run in the IMS environment. To prepare this part of the application to run with the CICS sample you must first perform the steps described in “Preparing the sample applications for the CICS environment” on page 403.

Then perform the following steps:

1. Perform the same steps that you would when building any IMS MQSeries for OS/390 application—these steps are listed in “Building IMS (BMP or MPP) applications” on page 278. The library members that you will use are listed in Table 41 on page 408.
2. Identify the application program and database to IMS. Samples are provided with PSBGEN, DBDGEN, ACB definition, IMSGEN, and IMSDALOC statements to enable this.
3. Load the database CSQ4CA by tailoring and running the sample JCL provided for this purpose (CSQ4ILDB). This JCL loads the database with data from the file CSQ4BAQ. Update the IMS control region with a DD statement for the database CSQ4CA.
4. Start the checking-account program as a batch message processing (BMP) program by tailoring and running the sample JCL provided for this purpose. This JCL starts a batch-oriented BMP program. To run the program as a message-oriented BMP program, remove the comment characters from the line in the JCL that contains the IN= statement.

## Names of the sample IMS application

The source and JCL that are supplied for the Credit Check sample IMS application are listed in Table 41.

Member name	Description	Supplied in library
CSQ4CVB	MQSeries object definitions	SCSQPROC
CSQ4ICB3	Source for checking-account program	SCSQC37S
CSQ4ICBL	Source for loading the checking-account database	SCSQC37S
CSQ4CBI	Data definition	SCSQC370
CSQ4PSBL	PSBGEN JCL for database-load program	SCSQPROC
CSQ4PSB3	PSBGEN JCL for checking-account program	SCSQPROC
CSQ4DBDS	DBDGEN JCL for database CSQ4CA	SCSQPROC
CSQ4GIMS	IMSGEN macro definitions for CSQ4IVB3 and CSQ4CA	SCSQPROC
CSQ4ACBG	Application control block (ACB) definition for CSQ4IVB3	SCSQPROC
CSQ4BAQ	Source for database	SCSQPROC
CSQ4ILDB	Sample run JCL for database-load job	SCSQPROC
CSQ4ICBR	Sample run JCL for checking-account program	SCSQPROC
CSQ4DYNA	IMSDALOC macro definitions for database	SCSQPROC

## The Put samples

The Put sample programs put messages on a queue using the MQPUT call.

The source programs are supplied in C and COBOL in the batch and CICS environments (see Table 32 on page 400 and Table 37 on page 404).

## Design of the Put sample

The flow through the program logic is:

1. Connect to the queue manager using the MQCONN call. If this call fails, print the completion and reason codes and stop processing.

**Note:** If you are running the sample in a CICS environment, you do not need to issue an MQCONN call; if you do, it returns DEF\_HCONN. You can use the connection handle MQHC\_DEF\_HCONN for the MQI calls that follow.

2. Open the queue using the MQOPEN call with the MQOO\_OUTPUT option. On input to this call, the program uses the connection handle that is returned in step 1. For the object descriptor structure (MQOD), it uses the default values for all fields except the queue name field which is passed as a parameter to the program. If the MQOPEN call fails, print the completion and reason codes and stop processing.
3. Create a loop within the program issuing MQPUT calls until the required number of messages are put on the queue. If an MQPUT call fails, the loop is abandoned early, no further MQPUT calls are attempted, and the completion and reason codes are returned.
4. Close the queue using the MQCLOSE call with the object handle returned in step 2. If this call fails, print the completion and reason codes.
5. Disconnect from the queue manager using the MQDISC call with the connection handle returned in step 1. If this call fails, print the completion and reason codes.

**Note:** If you are running the sample in a CICS environment, you do not need to issue an MQDISC call.

## The Put samples for the batch environment

To run the samples, you must edit and run the sample JCL, as described in “Preparing and running sample applications for the batch environment” on page 399.

The programs take the following parameters in an EXEC PARM, separated by spaces in C and commas in COBOL:

1. The name of the queue manager (4 characters)
2. The name of the target queue (48 characters)
3. The number of messages (up to 4 digits)
4. The padding character to be written in the message (1 character)
5. The number of characters to write in the message (up to 4 digits)
6. The persistence of the message (1 character: 'P' for persistent or 'N' for nonpersistent)

If you enter any of the above parameters wrongly, you will receive appropriate error messages.

Any messages from the samples are written to the SYSPRINT data set.

### Usage notes

- To keep the samples simple, there are some minor functional differences between language versions. However, these differences are minimized if the layout of the parameters shown in the sample run JCL, CSQ4BCJR, and CSQ4BVJR, is used. None of the differences relate to the MQI.
- CSQ4BCK1 allows you to enter more than four digits for the number of messages sent and the length of the messages.
- For the two numeric fields, enter any digit between 1 and 9999. The value you enter should be a positive number. For example, to put a single message, you can enter 1 or 01 or 001 or 0001 as the value. If you enter non-numeric or negative values, you may receive an error. For example, if you enter '-1', the

## Put samples

COBOL program will send a one-byte message, but the C program will receive an error.

- For both programs, CSQ4BCK1 and CSQ4BVK1, you must enter 'P' in the persistence parameter, ++PER++, if you require the message to be persistent. If you fail to do so, the message will be nonpersistent.

## The Put samples for the CICS environment

The transactions take the following parameters separated by commas:

1. The number of messages (up to 4 digits)
2. The padding character to be written in the message (1 character)
3. The number of characters to write in the message (up to 4 digits)
4. The persistence of the message (1 character: 'P' for persistent or 'N' for nonpersistent)
5. The name of the target queue (48 characters)

If you enter any of the above parameters wrongly, you will receive appropriate error messages.

For the COBOL sample, invoke the Put sample in the CICS environment by entering:

```
MVPT,9999,*,9999,P,QUEUE.NAME
```

For the C sample, invoke the Put sample in the CICS environment by entering:

```
MCPT,9999,*,9999,P,QUEUE.NAME
```

Any messages from the samples are displayed on the screen.

### Usage notes

- To keep the samples simple, there are some minor functional differences between language versions. None of the differences relate to the MQI.
- If you enter a queue name that is longer than 48 characters, its length is truncated to the maximum of 48 characters but no error message is returned.
- Before entering the transaction, press the 'CLEAR' key.
- For the two numeric fields, enter any number between 1 and 9999. The value you enter should be a positive number. For example, to put a single message, you can enter the value 1 or 01 or 001 or 0001. If you enter non-numeric or negative values, you may receive an error. For example, if you enter '-1', the COBOL program will send a 1 byte message, and the C program will abend with an error from malloc().
- For both programs, CSQ4CCK1 and CSQ4CVK1, you must enter 'P' in the persistence parameter, if you require the message to be persistent. For non-persistent messages, enter 'N' in the persistence parameter. If you enter any other value you will receive an error message.
- The messages are put in syncpoint because default values are used for all parameters except those set during program invocation.

## The Get samples

The Get sample programs get messages from a queue using the MQGET call.

The source programs are supplied in C and COBOL in the batch and CICS environments (see Table 32 on page 400 and Table 37 on page 404).

## Design of the Get sample

The flow through the program logic is:

1. Connect to the queue manager using the MQCONN call. If this call fails, print the completion and reason codes and stop processing.

**Note:** If you are running the sample in a CICS environment, you do not need to issue an MQCONN call; if you do, it returns DEF\_HCONN. You can use the connection handle MQHC\_DEF\_HCONN for the MQI calls that follow.

2. Open the queue using the MQOPEN call with the MQOO\_INPUT\_SHARED and MQOO\_BROWSE options. On input to this call, the program uses the connection handle that is returned in step 1. For the object descriptor structure (MQOD), it uses the default values for all fields except the queue name field which is passed as a parameter to the program. If the MQOPEN call fails, print the completion and reason codes and stop processing.
3. Create a loop within the program issuing MQGET calls until the required number of messages are retrieved from the queue. If an MQGET call fails, the loop is abandoned early, no further MQGET calls are attempted, and the completion and reason codes are returned.

The following options are specified on the MQGET call:

- MQGMO\_NO\_WAIT
- MQGMO\_ACCEPT\_TRUNCATED\_MESSAGE
- MQGMO\_SYNCPOINT or MQGMO\_NO\_SYNCPOINT
- MQGMO\_BROWSE\_FIRST and MQGMO\_BROWSE\_NEXT

For a description of these options, see “MQGMO - Get-message options” in the *MQSeries Application Programming Reference* manual.

For each message, the message number is printed followed by the length of the message and the message data.

4. Close the queue using the MQCLOSE call with the object handle returned in step 2. If this call fails, print the completion and reason codes.
5. Disconnect from the queue manager using the MQDISC call with the connection handle returned in step 1. If this call fails, print the completion and reason codes.

**Note:** If you are running the sample in a CICS environment, you do not need to issue an MQDISC call.

## The Get samples for the batch environment

To run the samples, you must edit and run the sample JCL, as described in “Preparing and running sample applications for the batch environment” on page 399.

## Get samples

The programs take the following parameters in an EXEC PARM, separated by spaces in C and commas in COBOL:

1. The name of the queue manager (4 characters)
2. The name of the target queue (48 characters)
3. The number of messages to get (up to 4 digits)
4. The browse/get message option (1 character: 'B' to browse or 'D' to destructively get the messages)
5. The syncpoint control (1 character: 'S' for syncpoint or 'N' for no syncpoint)

If you enter any of the above parameters wrongly, you will receive appropriate error messages.

Output from the samples is written to the SYSPRINT data set:

```
=====
PARAMETERS PASSED :
  QMGR      - VC9
  QNAME     - A.Q
  NUMMSGs   - 000000002
  GET       - D
  SYNCPOINT - N
=====
MQCONN SUCCESSFUL
MQOPEN SUCCESSFUL
000000000 : 000000010 : *****
000000001 : 000000010 : *****
000000002 MESSAGES GOT FROM QUEUE
MQCLOSE SUCCESSFUL
MQDISC SUCCESSFUL
```

### Usage notes

- To keep the samples simple, there are some minor functional differences between language versions. However, these differences are minimized if the layout of the parameters shown in the sample run JCL, CSQ4BCJR, and CSQ4BVJR, are used. None of the differences relate to the MQI.
- CSQ4BCJ1 allows you to enter more than four digits for the number of messages retrieved.
- Messages longer than 64 KB are truncated.
- CSQ4BCJ1 can only correctly display character messages as it only displays until the first NULL (\0) character is displayed.
- For the numeric number-of-messages field, enter any digit between 1 and 9999. The value you enter should be a positive number. For example, to get a single message, you can enter 1 or 01 or 001 or 0001 as the value. If you enter non-numeric or negative values, you may receive an error. For example, if you enter '-1', the COBOL program will retrieve one message, but the C program will not retrieve any messages.
- For both programs, CSQ4BCJ1 and CSQ4BVJ1, you must enter 'B' in the get parameter, ++GET++, if you want to browse the messages.
- For both programs, CSQ4BCJ1 and CSQ4BVJ1, you must enter 'S' in the syncpoint parameter, ++SYNC++, for messages to be retrieved in syncpoint.

## The Get samples for the CICS environment

The transactions take the following parameters in an EXEC PARM, separated by commas:

1. The number of messages to get (up to 4 digits)
2. The browse/get message option (1 character: 'B' to browse or 'D' to destructively get the messages)
3. The syncpoint control (1 character: 'S' for syncpoint or 'N' for no syncpoint)
4. The name of the target queue (48 characters)

If you enter any of the above parameters wrongly, you will receive appropriate error messages.

For the COBOL sample, invoke the Get sample in the CICS environment by entering:

```
MVGT,9999,B,S,QUEUE.NAME
```

For the C sample, invoke the Get sample in the CICS environment by entering:

```
MCGT,9999,B,S,QUEUE.NAME
```

When the messages are retrieved from the queue, they are put on a CICS temporary storage queue with the same name as the CICS transaction (for example, MCGT for the C sample).

Here is example output of the Get samples:

```
***** TOP OF QUEUE *****
00000000 : 00000010 : *****
00000001 : 00000010 : *****
***** BOTTOM OF QUEUE *****
```

### Usage notes

- To keep the samples simple, there are some minor functional differences between language versions. None of the differences relate to the MQI.
- If you enter a queue name that is longer than 48 characters, its length is truncated to the maximum of 48 characters but no error message is returned.
- Before entering the transaction, press the 'CLEAR' key.
- CSQ4CCJ1 can only correctly display character messages as it only displays until the first NULL (\0) character is displayed.
- For the numeric field, enter any number between 1 and 9999. The value you enter should be a positive number. For example, to get a single message, you can enter the value 1 or 01 or 001 or 0001. If you enter a non-numeric or negative value, you may receive an error.
- Messages longer than 24526 bytes in C and 9950 bytes in COBOL are truncated. This is due to the way the CICS temporary storage queues are used.
- For both programs, CSQ4CCK1 and CSQ4CVK1, you must enter 'B' in the get parameter if you want to browse the messages, otherwise enter 'D'. This will perform destructive MQGET calls. If you enter any other value you will receive an error message.

## Browse sample

- For both programs, CSQ4CCJ1 and CSQ4CVJ1, you must enter 'S' in the syncpoint parameter for messages to be retrieved in syncpoint. If you enter 'N' in the syncpoint parameter the MQGET calls will be issued out of syncpoint. If you enter any other value you will receive an error message.

---

## The Browse sample

The Browse sample is a batch application that demonstrates how to browse messages on a queue using the MQGET call. The application steps through all the messages in a queue, printing the first 80 bytes of each one. You could use this application to look at the messages on a queue without changing them.

Source programs and sample run JCL are supplied in the COBOL, assembler, PL/I, and C languages (see Table 33 on page 401).

To start the application, you must edit and run the sample run JCL, as described in "Preparing and running sample applications for the batch environment" on page 399. You can look at messages on one of your own queues by specifying the name of the queue in the run JCL.

When you run the application (and there are some messages on the queue), the output data set looks this:

```
07/12/1998                                SAMPLE QUEUE REPORT                PAGE    1
                                           QUEUE MANAGER NAME : VC4
                                           QUEUE NAME   : CSQ4SAMP.DEAD.QUEUE

      RELATIVE
      MESSAGE  MESSAGE
      NUMBER   LENGTH ----- MESSAGE DATA -----
      1        740 HELLO. PLEASE CALL ME WHEN YOU GET BACK.
      2        429 CSQ4BQRM
      3        429 CSQ4BQRM
      4        429 CSQ4BQRM
      5         22 THIS IS A TEST MESSAGE
      6         8  CSQ4TEST
      7        36 CSQ4MSG - ANOTHER TEST MESSAGE.....!
      8         9  CSQ4STOP

                                           ***** END OF REPORT *****
```

If there are no messages on the queue, the data set contains the headings and the "End of report" message only. If an error occurs with any of the MQI calls, the completion and reason codes are added to the output data set.

## Design of the Browse sample

The Browse sample application uses a single program module—one is provided in each of the supported programming languages.

The flow through the program logic is:

1. Open a print data set and print the title line of the report. Check that names of the queue manager and queue have been passed from the run JCL. If both names have been passed, print the lines of the report that contain the names. If they have not, print an error message, close the print data set, and stop processing.

The way that the program tests the parameters it is passed from the JCL depends on the language in which the program is written—for more information, see “Language-dependent design considerations” on page 416.

2. Connect to the queue manager using the MQCONN call. If this call is not successful, print the completion and reason codes, close the print data set, and stop processing.
3. Open the queue using the MQOPEN call with the MQOO\_BROWSE option. On input to this call, the program uses the connection handle returned in step 2. For the object descriptor structure (MQOD), it uses the default values for all the fields except the queue name (which was passed in step 1 on page 414). If this call is not successful, print the completion and reason codes, close the print data set, and stop processing.
4. Browse the first message on the queue, using the MQGET call. On input to this call, the program specifies:
  - The connection and queue handles from steps 2 and 3
  - An MQMD structure with all fields set to their initial values
  - Two options:
    - MQGMO\_BROWSE\_FIRST
    - MQGMO\_ACCEPT\_TRUNCATED\_MSG
  - A buffer of size 80 bytes to hold the data copied from the message

The MQGMO\_ACCEPT\_TRUNCATED\_MSG option allows the call to complete even if the message is longer than the 80-byte buffer specified in the call. If the message is longer than the buffer, the message is truncated to fit the buffer, and the completion and reason codes are set to show this. The sample was designed so that messages are truncated to 80 characters simply to make the report easy to read. The buffer size is set by a DEFINE statement, so you can easily change it if you want to.

5. Perform the following loop until the MQGET call fails:
  - a. Print a line of the report showing:
    - The sequence number of the message (this is a count of the browse operations).
    - The true length of the message (not the truncated length). This value is returned in the *DataLength* field of the MQGET call.
    - The first 80 bytes of the message data.
  - b. Reset the *MsgId* and *CorrelId* fields of the MQMD structure to nulls
  - c. Browse the next message, using the MQGET call with these two options:
    - MQGMO\_BROWSE\_NEXT
    - MQGMO\_ACCEPT\_TRUNCATED\_MSG
6. If the MQGET call fails, test the reason code to see if the call has failed because the browse cursor has got to the end of the queue. In this case, print the “End of report” message and go to step 7; otherwise, print the completion and reason codes, close the print data set, and stop processing.
7. Close the queue using the MQCLOSE call with the object handle returned in step 3.
8. Disconnect from the queue manager using the MQDISC call with the connection handle returned in step 2.

9. Close the print data set and stop processing.

## Language-dependent design considerations

Source modules are provided for the Browse sample in four programming languages. There are two main differences between the source modules:

- When testing the parameters passed from the run JCL, the COBOL, PL/I, and assembler-language modules search for the comma character (,). If the JCL passes `PARM=(,LOCALQ1)`, the application attempts to open queue LOCALQ1 on the default queue manager. If there is no name after the comma (or no comma), the application returns an error. The C module does not search for the comma character. If the JCL passes a single parameter (for example, `PARM=('LOCALQ1')`), the C module uses this as a queue name on the default queue manager.
- To keep the assembler-language module simple, it uses the date format `yy/dd` (for example, `93/116`) when it creates the print report. The other modules use the calendar date in `mm/dd/yy` format.

---

## The Print Message sample

The Print Message sample is a simple batch application that demonstrates how to remove all the messages from a queue using the MQGET call. It also prints, for each message, the fields of the message descriptor, followed by the message data. The program prints the data both in hexadecimal and as characters (if they are printable). If a character is not printable, the program replaces it with a period character (.). You can use the program when diagnosing problems with an application that is putting messages on a queue.

You can change the application so that it browses the messages, rather than removing them from the queue. To do this, remove the comment characters from two lines in the code, as indicated in “Design of the sample” on page 418.

The application has a single source program, which is written in the C language. Sample run JCL code is also supplied (see Table 34 on page 401).

To start the application, you must edit and run the sample run JCL, as described in “Preparing and running sample applications for the batch environment” on page 399. When you run the application (and there are some messages on the queue), the output data set looks like that in Figure 43 on page 417.

```

MQCONN to VC4
MQOPEN - 'CSQ4SAMP.DEAD.QUEUE'

MQGET of message number 1
****Message descriptor****
  StrucId : 'MD ' Version : 1
  Report  : 0 MsgType : 2
  Expiry  : -1 Feedback : 0
  Encoding : 785 CodedCharSetId : 500
  Format   : '      '
  Priority : 3 Persistence : 0
  MsgId    : X'C3E2D840E5C3F44040404040404040A6FE06A95105C620'
  CorrelId : X'C3E2D840E5C3F44040404040404040A6FE062950C2F125'
  BackoutCount : 0
  ReplyToQ      : '      '
  ReplyToQMgr   : 'VC4   '
  ** Identity Context
  UserIdentifier : 'CICSUSER '
  Account.Token  :
  X'160DD5E3E2D5C5E34BC9C7D7C2F6F1FE060D3B55B60001000000000000000000'
  ApplIdentData : '      '
  ** Origin Context
  PutApplType   : '1'
  PutApplName   : 'VICAUT4 MVB5 '
  PutDate       : '19930203' PutTime : '20165982'
  ApplOriginData : '      '

```

Figure 43 (Part 1 of 2). Example of a report from the Print Message sample application

## Print message sample

```
**** Message ****
length - 429 bytes

00000000: C3E2 D8F4 C2D8 D9D4 4040 4040 4040 4040 'CSQ4BQRM      '
00000010: 4040 4040 4040 4040 4040 4040 4040 4040 '              '
00000020: 4040 4040 4040 4040 4040 4040 4040 4040 '              '
00000030: 4040 4040 4040 4040 4040 4040 4040 4040 '              '
00000040: 4040 4040 4040 4040 4040 4040 4040 4040 '              '
00000050: 4040 4040 4040 40D1 D6C8 D540 D140 4040 '          JOHN J '
00000060: 4040 4040 4040 4040 4040 40F1 F2F3 F4F5 '          12345'
00000070: F6F7 F8F9 C6C9 D9E2 E340 C7C1 D3C1 C3E3 '6789FIRST GALACT'
00000080: C9C3 40C2 C1D5 D240 4040 4040 4040 4040 'IC BANK      '
00000090: 4040 E2D6 D4C5 E3C8 C9D5 C740 C4C9 C6C6 ' SOMETHING DIFF'
000000A0: C5D9 C5D5 E340 4040 4040 4040 4040 4040 'ERENT        '
000000B0: F3F5 F0F1 F6F7 F6F2 F1F2 F1F0 F0F0 F0F0 '3501676212100000'
000000C0: D985 A297 9695 A285 4086 9996 9440 C3E2 'Response from CS'
000000D0: D8F4 E2C1 D4D7 4BC2 F74B D4C5 E2E2 C1C7 'Q4$AMP.B7.MESSAG'
000000E0: C5E2 4040 4040 4040 4040 4040 4040 4040 'ES           '
000000F0: 4040 4040 4040 4040 4040 4040 4040 4040 '              '
00000100: 4040 4040 4040 4040 4040 4040 4040 4040 '              '
00000110: 4040 4040 40D3 9681 9540 8194 96A4 95A3 '          Loan amount'
00000120: 40F1 F0F0 F0F0 F040 8696 9940 D1D6 C8D5 ' 100000 for JOHN'
00000130: 40D1 4040 4040 4040 4040 4040 4040 4040 ' J           '
00000140: 4040 4040 4040 4040 4040 4040 4040 4040 '              '
00000150: 4040 4040 4040 4040 4040 4040 4040 4040 '              '
00000160: 4040 4040 C399 8584 89A3 40A6 9699 A388 '          Credit worth'
00000170: 8995 85A2 A240 8995 8485 A740 6040 C2C1 'iness index - BA'
00000180: C440 4040 4040 4040 4040 4040 4040 4040 'D            '
00000190: 4040 4040 4040 4040 4040 4040 4040 4040 '              '
000001A0: 4040 4040 4040 4040 4040 4040 40      '              '

No more messages
MQCLOSE
MQDISC
```

Figure 43 (Part 2 of 2). Example of a report from the Print Message sample application

## Design of the sample

The Print message sample application uses a single program written in the C language.

The flow through the program logic is:

1. Check that names of the queue manager and queue have been passed from the run JCL. If they have not, print an error message and stop processing.
2. Connect to the queue manager using the MQCONN call. If this call is not successful, print the completion and reason codes and stop processing; otherwise print the name of the queue manager.
3. Open the queue using the MQOPEN call with the MQOO\_INPUT\_SHARED option.

**Note:** If you want the application to browse the messages rather than remove them from the queue, remove the comment characters from the line in the program that adds the MQOO\_BROWSE option.

On input to this call, the program uses the connection handle returned in step 2. For the object descriptor structure (MQOD), it uses the default values for all the fields except the queue name (which was passed in step 1). If this call is not successful, print the completion and reason codes and stop processing; otherwise, print the name of the queue.

4. Perform the following loop until the MQGET call fails:
  - a. Initialize the buffer to blanks so that the message data does not get corrupted by any data already in the buffer.
  - b. Set the *MsgId* and *CorrelId* fields of the MQMD structure to nulls so that the MQGET call selects the first message from the queue.
  - c. Get a message from the queue, using the MQGET call. On input to this call, the program specifies:
    - The connection and object handles from steps 2 and 3.
    - An MQMD structure with all fields set to their initial values. (Note that *MsgId* and *CorrelId* are reset to nulls for each MQGET call.)
    - The option MQGMO\_NO\_WAIT.

**Note:** If you want the application to browse the messages rather than remove them from the queue, remove the comment characters from the line in the program that adds the MQOO\_BROWSE\_NEXT option. When this option is used on a call against a queue for which no browse cursor has previously been used with the current object handle, the browse cursor is positioned logically before the first message.

    - A buffer of size 32 KB to hold the data copied from the message.
  - d. Call the printMD subroutine. This prints the name of each field in the message descriptor, followed by its contents.
  - e. Print the length of the message, followed by the message data. Each line of message data is in this format:
    - Relative position (in hexadecimal) of this part of the data
    - 16 bytes of hexadecimal data
    - The same 16 bytes of data in character format, if it is printable (nonprintable characters are replaced by periods)
5. If the MQGET call fails, test the reason code to see if the call failed because there are no more messages on the queue. In this case, print the message: "No more messages"; otherwise, print the completion and reason codes. In both cases, go to step 6 on page 420.

**Note:** The MQGET call fails if it finds a message that has more than 32 KB of data. To change the program to handle larger messages, you could do one of the following:

- Add the MQGMO\_ACCEPT\_TRUNCATED\_MSG option to the MQGET call, so that the call gets the first 32 KB of data and discards the remainder
- Make the program leave the message on the queue when it finds one with this amount of data

## Queue attributes sample

- Increase the size of the buffer
6. Close the queue using the MQCLOSE call with the object handle returned in step 3 on page 418.
  7. Disconnect from the queue manager using the MQDISC call with the connection handle returned in step 2 on page 418.

---

## The Queue Attributes sample

The Queue Attributes sample is a conversational-mode CICS application that demonstrates the use of the MQINQ and MQSET calls. It shows how to inquire about the values of the *InhibitPut* and *InhibitGet* attributes of queues, and how to change them so that programs cannot put messages on, or get messages from, a queue. You may want to **lock** a queue in this way when you are testing a program.

To prevent accidental interference with your own queues, this sample works only on a queue object that has the characters CSQ4SAMP in the first eight bytes of its name. However, the source code includes comments to show you how to remove this restriction.

Source programs are supplied in the COBOL, assembler, and C languages (see Table 38 on page 405).

The assembler-language version of the sample uses reenterable code. To do this, you will notice that the code for each MQI call in that version of the sample includes the MF keyword; for example:

```
CALL MQCONN, (NAME, HCONN, COMPCODE, REASON), MF=(E, PARMAREA), VL
```

(The VL keyword means that you can use the CICS Execution Diagnostic Facility (CEDF) supplied transaction for debugging the program.) For more information on writing reenterable programs, see “Writing reenterable programs” on page 81.

To start the application, start your CICS system and use the following CICS transactions:

- For COBOL, MVC1
- For Assembler language, MAC1
- For C, MCC1

You can change the name of any of these transactions by changing the CSD data set mentioned in step 3 on page 403.

## Design of the sample

When you start the sample, firstly it displays a screen map that has fields for:

- Name of the queue
- User request (valid actions are: inquire, allow, or inhibit)
- Current status of put operations for the queue
- Current status of get operations for the queue

The first two fields are for user input. The last two fields are filled by the application: they show the word INHIBITED or the word ALLOWED.

The application validates the values you enter in the first two fields. It checks that the queue name starts with the characters CSQ4SAMP and that you entered one of

the three valid requests in the Action field. The application converts all your input to uppercase, so you cannot use any queues with names that contain lowercase characters.

If you enter 'inquire' in the Action field, the flow through the program logic is:

1. Open the queue using the MQOPEN call with the MQOO\_INQUIRE option
2. Call MQINQ using the selectors MQIA\_INHIBIT\_GET and MQIA\_INHIBIT\_PUT
3. Close the queue using the MQCLOSE call
4. Analyze the attributes that are returned in the *IntAttrs* parameter of the MQINQ call and move the words 'INHIBITED' or 'ALLOWED', as appropriate, to the relevant screen fields

If you enter 'inhibit' in the Action field, the flow through the program logic is:

1. Open the queue using the MQOPEN call with the MQOO\_SET option
2. Call MQSET using the selectors MQIA\_INHIBIT\_GET and MQIA\_INHIBIT\_PUT, and with the values MQQA\_GET\_INHIBITED and MQQA\_PUT\_INHIBITED in the *IntAttrs* parameter
3. Close the queue using the MQCLOSE call
4. Move the word 'INHIBITED' to the relevant screen fields

If you enter 'allow' in the Action field, the application performs similar processing to that for an 'inhibit' request. The only differences are the settings of the attributes and the words displayed on the screen.

When the application opens the queue, it uses the default connection handle to the queue manager. (CICS establishes a connection to the queue manager when you start your CICS system.) The application can trap the following errors at this stage:

- The application is not connected to the queue manager
- The queue does not exist
- The user is not authorized to access the queue
- The application is not authorized to open the queue

For other MQI errors, the application displays the completion and reason codes.

---

## The Mail Manager sample

The Mail Manager sample application is a suite of programs that demonstrates the sending and receiving of messages, both within a single environment and across different environments. The application is a simple electronic mailing system that allows users to exchange messages, even if they use different queue managers.

The application demonstrates how to create queues using the MQOPEN call and by putting MQSeries for OS/390 commands on the system-command input queue.

Three versions of the application are provided:

- A CICS application written in COBOL
- A TSO application written in COBOL
- A TSO application written in C

### Preparing the sample

The Mail Manager is provided in versions that run in two environments. The preparation you must carry out before you run the application depends on the environment you want to use.

A user can access mail queues and nickname queues from both TSO and CICS so long as their sign-on user IDs are the same on each system.

Before you can send messages to another queue manager, you must set up a message channel to that queue manager. To do this, use the channel control function of MQSeries, described in “Channel control function” in the *MQSeries Intercommunication* book.

### Preparing the sample for the TSO environment

Follow these steps:

1. Prepare the sample as described in “Preparing sample applications for the TSO environment” on page 401.
2. Tailor the CLIST provided for the sample to define:
  - The location of the panels
  - The location of the message file
  - The location of the load modules
  - The name of the queue manager you want to use with the application

A separate CLIST is provided for each language version of the sample:

**For the COBOL version:** CSQ4RVD1

**For the C version:** CSQ4RCD1

3. Ensure that the queues used by the application are available on the queue manager. (The queues are defined in CSQ4CVD.)

**Note:** VS COBOL II does not support multitasking with ISPF. This means that you cannot use the Mail Manager sample application on both sides of a split screen. If you do, the results are unpredictable.

### Running the sample

To start the sample in the TSO environment, execute your tailored version of the CLIST from the TSO command processor within ISPF.

To start the sample in the CICS Transaction Server for OS/390 environment, run transaction MAIL. If you have not already signed-on to CICS, the application prompts you to enter a user ID to which it can send your mail.

When you start the application, it opens your mail queue. If this queue does not already exist, the application creates one for you. Mail queues have names of the form CSQ4SAMP.MAILMGR.*userid*, where *userid* depends on the environment:

#### In TSO

The user's TSO ID

#### In CICS

The user's CICS sign-on or the user ID entered by the user when prompted when the Mail Manager started

All parts of the queue names that the Mail Manager uses must be uppercase.

The application then presents a menu panel that has options for:

- Read incoming mail
- Send mail
- Create nickname

The menu panel also shows you how many messages are waiting on your mail queue. Each of the menu options displays a further panel:

### Read incoming mail

The Mail Manager displays a list of the messages that are on your mail queue. (Note that only the first 99 messages on the queue are displayed.) For an example of this panel, see Figure 46 on page 428. When you select a message from this list, the contents of the message are displayed (see Figure 47 on page 428).

### Send mail

A panel prompts you to enter:

- The name of the user to whom you want to send a message
- The name of the queue manager that owns their mail queue
- The text of your message

In the user name field you can enter either a user ID or a nickname that you created using the Mail Manager. You can leave the queue manager name field blank if the user's mail queue is owned by the same queue manager that you are using, and you must leave it blank if you entered a nickname in the user name field:

- If you specify only a user name, the program first assumes that the name is a nickname, and sends the message to the object defined by that name. If there is no such nickname, the program attempts to send the message to a local queue of that name.
- If you specify both a user name and a queue manager name, the program sends the message to the mail queue that is defined by those two names.

For example, if you want to send a message to user JONESM on remote queue manager QM12, you could send them a message in either of two ways:

- Use both fields to specify user JONESM at queue manager QM12.
- Define a nickname (for example, MARY) for that user and send them a message by putting MARY in the user name field and nothing in the queue manager name field.

### Create nickname

You can define an easy-to-remember name that you can use when you send a message to another user who you contact frequently. You are prompted to enter the user ID of the other user and the name of the queue manager that owns their mail queue.

Nicknames are queues that have names of the form `CSQ4SAMP.MAILMGR.userid.nickname`, where *userid* is your own user ID and *nickname* is the nickname that you want to use. With names structured in this way, users can each have their own set of nicknames.

## Mail manager sample

The type of queue that the program creates depends on how you fill in the fields of the Create Nickname panel:

- If you specify only a user name, or the queue manager name is the same as that of the queue manager to which the Mail Manager is connected, the program creates an alias queue.
- If you specify both a user name and a queue manager name (and the queue manager is not the one to which the Mail Manager is connected), the program creates a local definition of a remote queue. The program does not check the existence of the queue to which this definition resolves, or even that the remote queue manager exists.

For example, if your own user ID is SMITHK and you create a nickname called MARY for user JONESM (who uses the remote queue manager QM12), the nickname program creates a local definition of a remote queue named CSQ4SAMP.MAILMGR.SMITHK.MARY. This definition resolves to Mary's mail queue, which is CSQ4SAMP.MAILMGR.JONESM at queue manager QM12. If you are using queue manager QM12 yourself, the program instead creates an alias queue of the same name (CSQ4SAMP.MAILMGR.SMITHK.MARY).

The C version of the TSO application makes greater use of ISPF's message-handling capabilities than does the COBOL version. You may notice that different error messages are displayed by the C and COBOL versions.

## Design of the sample

The following sections describe each of the programs that comprise the Mail Manager sample application. The relationships between the programs and the panels that the application uses is shown in Figure 44 on page 425 for the TSO version, and Figure 45 on page 426 for the CICS Transaction Server for OS/390 version.




Figure 44. Programs and panels for the TSO versions of the Mail Manager. This figure shows the names for the COBOL version.




Figure 45. Programs and panels for the CICS version of the Mail Manager

### Menu program

In the TSO environment, the menu program is invoked by the CLIST. In the CICS environment, the program is invoked by transaction MAIL.

The menu program is the initial program in the suite. It displays the menu and invokes the other programs when they are selected from the menu.

The program first obtains the user's ID:

- In the CICS version of the program, if the user has signed on to CICS, the user ID is obtained by using the CICS command ASSIGN USERID. If the user has not signed on, the program displays the sign-on panel (CSQ4VD0) to prompt the user to enter a user ID. There is no security processing within this program—the user can give **any** user ID.
- In the TSO version, the user's ID is obtained from TSO in the CLIST. It is passed to the menu program as a variable in the ISPF shared pool.

After the program has obtained the user ID, it checks to ensure that the user has a mail queue (CSQ4SAMP.MAILMGR.*userid*). If a mail queue does not exist, the program creates one by putting a message on the system-command input queue. The message contains the MQSeries for OS/390 command DEFINE QLOCAL. The object definition that this command uses sets the maximum depth of the queue to 9999 messages.

The program also creates a temporary dynamic queue to handle replies from the system-command input queue. To do this, the program uses the MQOPEN call, specifying the SYSTEM.DEFAULT.MODEL.QUEUE as the template for the dynamic queue. The queue manager creates the temporary dynamic queue with a name that has the prefix CSQ4SAMP; the remainder of the name is generated by the queue manager.

The program then opens the user's mail queue and finds the number of messages on the queue by inquiring about the current depth of the queue. To do this, the program uses the MQINQ call, specifying the MQIA\_CURRENT\_Q\_DEPTH selector.

The program then performs a loop that displays the menu and processes the selection that the user makes. The loop is stopped when the user presses the PF3 key. When a valid selection is made, the appropriate program is started; otherwise an error message is displayed.

### Get-mail and display-message programs

In the TSO versions of the application, the get-mail and display-message functions are performed by the same program. In the CICS version of the application, these functions are performed by separate programs.

The Mail Awaiting panel (see Figure 46 on page 428 for an example) shows all the messages that are on the user's mail queue. To create this list, the program uses the MQGET call to browse all the messages on the queue, saving information about each one. In addition to the information displayed, the program records the *MsgId* and *CorrelId* of each message.

## Mail manager sample

```
----- MQSeries for OS/390 Sample Programs ----- ROW 16 OF 29
COMMAND ==>                                     Scroll ==> PAGE
                                                USERID - NTSFV02
                                                QMGR   - VC4

                Mail Manager System
                Mail Awaiting

                Msg      Mail      Date      Time
                No      From      Sent      Sent
                16
                16      Deleted
                17      JOHNJ      01/06/1993 12:52:02
                18      JOHNJ      01/06/1993 12:52:02
                19      JOHNJ      01/06/1993 12:52:03
                20      JOHNJ      01/06/1993 12:52:03
                21      JOHNJ      01/06/1993 12:52:03
                22      JOHNJ      01/06/1993 12:52:04
                23      JOHNJ      01/06/1993 12:52:04
                24      JOHNJ      01/06/1993 12:52:04
                25      JOHNJ      01/06/1993 12:52:05
                26      JOHNJ      01/06/1993 12:52:05
                27      JOHNJ      01/06/1993 12:52:05
                28      JOHNJ      01/06/1993 12:52:06
                29      JOHNJ      01/06/1993 12:52:06
```

Figure 46. Example of a panel showing a list of waiting messages

From the Mail Awaiting panel the user can select one message and display the contents of the message (see Figure 47 for an example). The program uses the MQGET call to remove this message from the queue, using the *MsgId* and *CorrelId* that the program noted when it browsed all the messages. This MQGET call is performed using the MQGMO\_SYNCPOINT option. The program displays the contents of the message, then declares a syncpoint: this commits the MQGET call, so the message now no longer exists.

```
----- MQSeries for OS/390 Sample Programs -----
COMMAND ==>                                     USERID - NTSFV02
                                                QMGR   - VC4

                Mail Manager System
                Received Mail

Mail sent from JOHNJ   at VC4

Sent on the 01/06/1993 at 12:52:02
----- Message -----
HELLO FROM JOHNJ
```

Figure 47. Example of a panel showing the contents of a message

An obvious extension to the function provided by the Mail Manager is to give the user the option to leave the message on the queue after viewing its contents. To

do this, you would have to back out the MQGET call that removes the message from the queue, after displaying the message.

### Send-mail program

When the user has completed the Send Mail panel, the send-mail program puts the message on the receiver's mail queue. To do this, the program uses the MQPUT1 call. The destination of the message depends on how the user has filled the fields in the Send Mail panel:

- If the user has specified only a user name, the program first assumes that the name is a nickname, and sends the message to the object defined by that name. If there is no such nickname, the program attempts to send the message to a local queue of that name.
- If the user has specified both a user name and a queue manager name, the program sends the message to the mail queue that is defined by those two names.

The program does not accept blank messages, and it removes leading blanks from each line of the message text.

If the MQPUT1 call is successful, the program displays a message that shows the user name and queue manager name to which the message was put. If the call is unsuccessful, the program checks specifically for the reason codes that indicate the queue or the queue manager do not exist; these are MQRC\_UNKNOWN\_OBJECT\_NAME and MQRC\_UNKNOWN\_OBJECT\_Q\_MGR. The program displays its own error message for each of these errors; for other errors, the program displays the completion and reason codes returned by the call.

### Nickname program

When the user defines a nickname, the program creates a queue that has the nickname as part of its name. The program does this by putting a message on the system-command input queue. The message contains the MQSeries for OS/390 command DEFINE QALIAS or DEFINE QREMOTE. The type of queue that the program creates depends on how the user has filled the fields of the Create Nickname panel:

- If the user has specified only a user name, or the queue manager name is the same as that of the queue manager to which the Mail Manager is connected, the program creates an alias queue.
- If the user has specified both a user name and a queue manager name, (and the queue manager is not the one to which the Mail Manager is connected), the program creates a local definition of a remote queue. The program does not check the existence of the queue to which this definition resolves, or even that the remote queue manager exists.

The program also creates a temporary dynamic queue to handle replies from the system-command input queue.

If the queue manager cannot create the nickname queue for a reason that the program expects (for example, the queue already exists), the program displays its own error message. If the queue manager cannot create the queue for a reason that the program does not expect, the program displays up to two of the error messages that are returned to the program by the command server.

**Note:** For each nickname, the nickname program creates only an alias queue or a local definition of a remote queue. The local queues to which these queue names resolve are created only when the user ID that is contained in the nickname is used to start the Mail Manager application.

---

### The Credit Check sample

The Credit Check sample application is a suite of programs that demonstrates how to use many of the features provided by MQSeries for OS/390. It shows how the many component programs of an application can pass messages to each other using message queuing techniques.

The sample can run as a stand-alone CICS application. However, to demonstrate how to design a message queuing application that uses the facilities provided by both the CICS and IMS environments, one module is also supplied as an IMS batch message processing program. This extension to the sample is described in “The IMS extension to the Credit Check sample” on page 442.

You can also run the sample on more than one queue manager, and send messages between each instance of the application. To do this, see “The Credit Check sample with multiple queue managers” on page 442.

The CICS programs are delivered in C and COBOL. The single IMS program is delivered only in C. The supplied data sets are shown in Table 40 on page 406 and Table 41 on page 408.

The application demonstrates a method of assessing the risk when bank customers ask for loans. The application shows how a bank could work in two ways to process loan requests:

- When dealing directly with a customer, bank staff want immediate access to account and credit-risk information.
- When dealing with written applications, bank staff can submit a series of requests for account and credit-risk information, and deal with the replies at a later time.

The financial and security details in the application have been kept simple so that the message queuing techniques are clear.

### Preparing and running the Credit Check sample

To prepare and run the Credit Check sample, perform the following steps:

1. Create the VSAM data set that holds information about some example accounts. Do this by editing and running the JCL supplied in data set CSQ4FILE.
2. Perform the steps in “Preparing the sample applications for the CICS environment” on page 403. (The additional steps you must perform if you want to use the IMS extension to the sample are described in “The IMS extension to the Credit Check sample” on page 442.)
3. Start the CKTI trigger monitor (supplied with MQSeries for OS/390) against queue CSQ4SAMP.INITIATION.QUEUE, using the CICS transaction CKQC.
4. To start the application, start your CICS system and use the transaction MVB1.

5. Select **Immediate** or **Batch** inquiry from the first panel.

The immediate and batch inquiry panels are similar—Figure 48 shows the Immediate Inquiry panel.

```

CSQ4VB2                MQSeries for OS/390 Sample Programs

                        Credit Check - Immediate Inquiry

Specify details of the request, then press Enter.
Name . . . . . _____
Social security number _____
Bank account name . . _____
Account number . . . . _____
Amount requested . . . 012345
Response from CHECKING ACCOUNT for name : _____
Account information not found
Credit worthiness index - NOT KNOWN

..
..
..
..
..
..
..
..
..
..
MESSAGE LINE
F1=Help F3=Exit F5=Make another inquiry

```

Figure 48. Immediate Inquiry panel for the Credit Check sample application

6. Enter an account number and loan amount in the appropriate fields. See “Entering information in the inquiry panels” for guidance on what information you should enter in these fields.

### Entering information in the inquiry panels

The Credit Check sample application checks that the data you enter in the ‘Amount requested’ field of the inquiry panels is in the form of integers.

If you enter one of the following account numbers, the application finds the appropriate account name, average account balance, and credit worthiness index in the VSAM data set CSQ4BAQ:

```

2222222222
3111234329
3256478962
3333333333
3501676212
3696879656
4444444444
5555555555
6666666666
7777777777

```

You can enter any, or no, information in the other fields. The application retains any information that you do enter and returns the same information in the reports that it generates.

### Design of the sample

This section describes the design of each of the programs that comprise the Credit Check sample application. For a discussion of some of the techniques that were considered during the design of the application, see “Design considerations” on page 439.

Figure 49 on page 433 shows the programs that make up the application, and also the queues that these programs serve. In this figure, the prefix CSQ4SAMP has been omitted from all the queue names to make the figure easier to understand.




Figure 49. Programs and queues for the Credit Check sample application (COBOL programs only). In the sample application, the queue names shown in this figure have the prefix 'CSQ4SAMP.'

### User-interface program (CSQ4CVB1)

When you start the conversational-mode CICS transaction MVB1, this starts the user-interface program for the application. This program puts inquiry messages on queue CSQ4SAMP.B2.INQUIRY and gets replies to those inquiries from a reply-to queue that it specifies when it makes the inquiry. From the user interface you can submit either immediate or batch inquiries:

- For immediate inquiries, the program creates a temporary dynamic queue that it uses as a reply-to queue. This means that each inquiry has its own reply-to queue.
- For batch inquiries, the user-interface program gets replies from the queue CSQ4SAMP.B2.RESPONSE. For simplicity, the program gets replies for all its inquiries from this one reply-to queue. It is easy to see that a bank might want to use a separate reply-to queue for each user of MVB1, so that they could each see replies to only those inquiries they had initiated.

Important differences between the properties of messages used in the application when in batch and immediate mode are:

- For batch working, the messages have a low priority, so they are processed after any loan requests that are entered in immediate mode. Also, the messages are persistent, so they are recovered if the application or the queue manager has to restart.
- For immediate working, the messages have a high priority, so they are processed before any loan requests that are entered in batch mode. Also, messages are not persistent so they are discarded if the application or the queue manager has to restart.

However, in all cases, the properties of loan request messages are propagated throughout the application. So, for example, all messages that result from a high-priority request will also have a high priority.

### Credit application manager (CSQ4CVB2)

The Credit Application Manager (CAM) program performs most of the processing for the Credit Check application.

The CAM is started by the CKTI trigger monitor (supplied with MQSeries for OS/390) when a trigger event occurs on either queue CSQ4SAMP.B2.INQUIRY or queue CSQ4SAMP.B2.REPLY.*n*, where *n* is an integer that identifies one of a set of reply queues. The trigger message contains data that includes the name of the queue on which the trigger event occurred.

The CAM uses queues with names of the form CSQ4SAMP.B2.WAITING.*n* to store information about inquiries it is processing. The queues are named so that they are each paired with a reply-to queue; for example, queue CSQ4SAMP.B2.WAITING.3 contains the input data for a particular inquiry, and queue CSQ4SAMP.B2.REPLY.3 contains a set of reply messages (from programs that query databases) all relating to that same inquiry. To understand the reasons behind this design, see “Separate inquiry and reply queues in the CAM” on page 439.

**Start-up logic:** If the trigger event occurs on queue CSQ4SAMP.B2.INQUIRY, the CAM opens the queue for shared access. It then tries to open each reply queue until a free one is found. If it cannot find a free reply queue, the CAM logs the fact and terminates normally.

If the trigger event occurs on queue CSQ4SAMP.B2.REPLY.n, the CAM opens the queue for exclusive access. If the return code reports that the object is already in use, the CAM terminates normally. If any other error occurs, the CAM logs the error and terminates. The CAM opens the corresponding waiting queue and the inquiry queue, then starts getting and processing messages. From the waiting queue, the CAM recovers details of partially-completed inquiries.

For the sake of simplicity in this sample, the names of the queues used are held in the program. In a business environment, the queue names would probably be held in a file accessed by the program.

**Getting a message:** The CAM first attempts to get a message from the inquiry queue using the MQGET call with the MQGMO\_SET\_SIGNAL option. If a message is available immediately, the message is processed; if no message is available, a signal is set.

The CAM then attempts to get a message from the reply queue, again using the MQGET call with the same option. If a message is available immediately, the message is processed; otherwise a signal is set.

When both signals are set, the program waits until one of the signals is posted. If a signal is posted to indicate a message is available, the message is retrieved and processed. If the signal expires or the queue manager is terminating, the program terminates.

**Processing the message retrieved:** A message retrieved by the CAM may be one of four types:

- An inquiry message
- A reply message
- A propagation message
- An unexpected or unwanted message

The CAM processes these messages as follows:

#### **Inquiry message**

Inquiry messages come from the user-interface program. It creates an inquiry message for each loan request.

For all loan requests, the CAM requests the average balance of the customer's checking account. It does this by putting a request message on alias queue CSQ4SAMP.B2.OUTPUT.ALIAS. This queue name resolves to queue CSQ4SAMP.B3.MESSAGES, which is processed by the checking-account program, CSQ4CVB3. When the CAM puts a message on this alias queue, it specifies the appropriate CSQ4SAMP.B2.REPLY.n queue for the reply-to queue. An alias queue is used here so that program CSQ4CVB3 can easily be replaced by another program that processes a base queue of a different name. To do this, you simply redefine the alias queue so that its name resolves to the new queue. Also, you could assign differing access authorities to the alias queue and to the base queue.

If a user requests a loan that is larger than 10000 units, the CAM initiates checks on other databases as well. It does this by putting a request message on queue CSQ4SAMP.B4.MESSAGES, which is processed by the distribution program, CSQ4CVB4. The process serving this queue propagates the message to queues served by programs that have access to other records such as credit card history, savings accounts, and mortgage payments. The data from these programs is returned to the reply-to queue specified in the put operation. Additionally, a propagation message is sent to the reply-to queue by this program to specify how many propagation messages have been sent.

In a business environment, the distribution program would probably reformat the data provided to match the format required by each of the other types of bank account.

Any of the queues referred to here can be on a remote system.

For each inquiry message, the CAM initiates an entry in the memory-resident Inquiry Record Table (IRT). This record contains:

- The *MsgId* of the inquiry message
- In the ReplyExp field, the number of responses expected (equal to the number of messages sent)
- In the ReplyRec field, the number of replies received (zero at this stage)
- In the PropsOut field, an indication of whether a propagation message is expected

The CAM copies the inquiry message on to the waiting queue with:

- *Priority* set to 3
- *CorrelId* set to the *MsgId* of the inquiry message
- The other message-descriptor fields set to those of the inquiry message

### Propagation message

A propagation message contains the number of queues to which the distribution program has forwarded the inquiry. The message is processed as follows:

1. Add to the ReplyExp field of the appropriate record in the IRT the number of messages sent. This information is in the message.
2. Increment by 1 the ReplyRec field of the record in the IRT.
3. Decrement by 1 the PropsOut field of the record in the IRT.
4. Copy the message on to the waiting queue. The CAM sets the *Priority* to 2 and the other fields of the message descriptor to those of the propagation message.

### Reply message

A reply message contains the response to one of the requests to the checking-account program or to one of the agency-query programs. Reply messages are processed as follows:

1. Increment by 1 the ReplyRec field of the record in the IRT.
2. Copy the message on to the waiting queue with *Priority* set to 1 and the other fields of the message descriptor set to those of the reply message.
3. If ReplyRec = ReplyExp, and PropsOut = 0, set the MsgComplete flag.

**Other messages**

The application does not expect other messages. However, the application might receive messages broadcast by the system, or reply messages with unknown *CorrelIds*.

The CAM puts these messages on queue CSQ4SAMP.DEAD.QUEUE, where they can be examined. If this put operation fails, the message is lost and the program continues. For more information on the design of this part of the program, see “How the sample handles unexpected messages” on page 440.

***Sending an answer:*** When the CAM has received all the replies it is expecting for an inquiry, it processes the replies and creates a single response message. It consolidates into one message all the data from all reply messages that have the same *CorrelId*. This response is put on the reply-to queue specified in the original loan request. The response message is put within the same unit of work that contains the retrieval of the final reply message. This is to simplify recovery by ensuring that there is never a completed message on queue CSQ4SAMP.B2.WAITING.n.

***Recovery of partially-completed inquiries:*** The CAM copies on to queue CSQ4SAMP.B2.WAITING.n all the messages that it receives. It sets the fields of the message descriptor like this:

- *Priority* is determined by the type of message:
  - For request messages, priority = 3
  - For datagrams, priority = 2
  - For reply messages, priority = 1
- *CorrelId* is set to the *MsgId* of the loan request message
- Other MQMD fields are copied from those of the received message

When an inquiry has been completed, the messages for a specific inquiry are removed from the waiting queue during answer processing. Therefore, at any time, the waiting queue contains all messages relevant to in-progress inquiries. These messages are used to recover details of in-progress inquiries if the program has to restart. The different priorities are set so that inquiry messages are recovered before propagations or reply messages.

**Checking-account program (CSQ4CVB3)**

The checking-account program is started by a trigger event on queue CSQ4SAMP.B3.MESSAGES. After it has opened the queue, this program gets a message from the queue using the MQGET call with the wait option, and with the wait interval set to 30 seconds.

The program searches VSAM data set CSQ4BAQ for the account number in the loan request message. It retrieves the corresponding account name, average balance, and credit worthiness index, or notes that the account number is not in the data set.

The program then puts a reply message (using the MQPUT1 call) on the reply-to queue named in the loan request message. For this reply message, the program:

- Copies the *CorrelId* of the loan request message
- Uses the MQPMO\_PASS\_IDENTITY\_CONTEXT option

The program continues to get messages from the queue until the wait interval expires.

### Distribution program (CSQ4CVB4)

The distribution program is started by a trigger event on queue CSQ4SAMP.B4.MESSAGES. To simulate the distribution of the loan request to other agencies that have access to records such as credit card history, savings accounts, and mortgage payments, the program puts a copy of the same message on all the queues in the namelist CSQ4SAMP.B4.NAMELIST. There are three of these queues, with names of the form CSQ4SAMP.Bn.MESSAGES, where *n* is 5, 6, or 7. In a business application, the agencies could be at separate locations, so these queues could be remote queues. If you want to modify the sample application to show this, see “The Credit Check sample with multiple queue managers” on page 442.

The distribution program performs the following steps:

1. From the namelist, gets the names of the queues the program is to use. The program does this by using the MQINQ call to inquire about the attributes of the namelist object.
2. Opens these queues and also CSQ4SAMP.B4.MESSAGES.
3. Performs the following loop until there are no more messages on queue CSQ4SAMP.B4.MESSAGES:
  - a. Get a message using the MQGET call with the wait option, and with the wait interval set to 30 seconds.
  - b. Put a message on each queue listed in the namelist, specifying the name of the appropriate CSQ4SAMP.B2.REPLY.n queue for the reply-to queue. The program copies the *CorrelId* of the loan request message to these copy messages, and it uses the MQPMO\_PASS\_IDENTITY\_CONTEXT option on the MQPUT call.
  - c. Send a datagram message to queue CSQ4SAMP.B2.REPLY.n to show how many messages it has successfully put.
  - d. Declare a syncpoint.

### Agency-query program (CSQ4CVB5/CSQ4CCB5)

The agency-query program is supplied as both a COBOL program and a C program. Both programs have the same design. This shows that programs of different types can easily coexist within an MQSeries application, and that the program modules that comprise such an application can easily be replaced.

An instance of the program is started by a trigger event on any of these queues:

- For the COBOL program (CSQ4CVB5):
  - CSQ4SAMP.B5.MESSAGES
  - CSQ4SAMP.B6.MESSAGES
  - CSQ4SAMP.B7.MESSAGES
- For the C program (CSQ4CCB5), queue CSQ4SAMP.B8.MESSAGES

**Note:** If you want to use the C program, you must alter the definition of the namelist CSQ4SAMP.B4.NAMELIST to replace the queue CSQ4SAMP.B7.MESSAGES with CSQ4SAMP.B8.MESSAGES.

To do this, you can use any one of:

- The MQSeries for OS/390 operations and control panels
- The ALTER NAMELIST command (described in “ALTER NAMELIST” in the *MQSeries Command Reference* manual)
- The CSQUTIL utility (described in the *MQSeries for OS/390 System Management Guide*)

After it has opened the appropriate queue, this program gets a message from the queue using the MQGET call with the wait option, and with the wait interval set to 30 seconds.

The program simulates the search of an agency's database by searching the VSAM data set CSQ4BAQ for the account number that was passed in the loan request message. It then builds a reply that includes the name of the queue it is serving and a credit-worthiness index. To simplify the processing, the credit-worthiness index is selected at random.

When putting the reply message, the program uses the MQPUT1 call and:

- Copies the *CorrelId* of the loan request message
- Uses the MQPMO\_PASS\_IDENTITY\_CONTEXT option

The program sends the reply message to the reply-to queue named in the loan request message. (The name of the queue manager that owns the reply-to queue is also specified in the loan request message.)

## Design considerations

This section discusses:

- Why the CAM uses separate inquiry and reply queues
- How the sample handles errors
- How the sample handles unexpected messages
- How the sample uses syncpoints
- How the sample uses message context information

### Separate inquiry and reply queues in the CAM

The application could use a single queue for both inquiries and replies, but it was designed to use separate queues for the following reasons:

- When the program is handling the maximum number of inquiries, further inquiries can be left on the queue. If a single queue were being used, these would have to be taken off the queue and stored elsewhere.
- Other instances of the CAM could be started automatically to service the same inquiry queue if message traffic was high enough to warrant it. But the program must track in-progress inquiries, and to do this it must get back all replies to inquiries it has initiated. If only one queue were used, the program would have to browse the messages to see if they were for this program or for another. This would make the operation much less efficient.

The application can support multiple CAMs and can recover in-progress inquiries effectively by using paired reply-to and waiting queues.

- The program can wait on multiple queues effectively by using signaling.

### How the sample handles errors

The user-interface program handles errors very simply by reporting them directly to the user. The other programs do not have user interfaces, so they have to handle errors in other ways. Also, in many situations (for example, if an MQGET call fails) these other programs do not know the identity of the user of the application.

The other programs put error messages on a CICS temporary storage queue called CSQ4SAMP. You can browse this queue using the CICS-supplied transaction CEBR. The programs also write error messages to the CICS CSML log.

### How the sample handles unexpected messages

When you design a message-queuing application, you must decide how to handle messages that arrive on a queue unexpectedly. The two basic choices are:

- The application must do no more work until it has processed the unexpected message. This probably means that the application must notify an operator, terminate itself, and ensure that it is not restarted automatically (it can do this by setting triggering off). This choice means that all processing for the application can be halted by a single unexpected message, and the intervention of an operator is required to restart the application.
- The application must remove the message from the queue it is serving, put the message in another location, and continue processing. The best place to put this message is on the system dead-letter queue.

If you choose the second option:

- An operator, or another program, should examine the messages that are put on the dead-letter queue to find out where the messages are coming from.
- An unexpected message is lost if it cannot be put on the dead-letter queue.
- An long unexpected message is truncated if it is longer than the limit for messages on the dead-letter queue, or longer than the buffer size in the program.

To ensure that the application smoothly handles all inquiries with minimal impact from outside activities, the Credit Check sample application uses the second option. To allow you to keep the sample separate from other applications that use the same queue manager, the Credit Check sample does not use the system dead-letter queue: instead, it uses its own dead-letter queue. This queue is named CSQ4SAMP.DEAD.QUEUE. The sample truncates any messages that are longer than the buffer area provided for the sample programs. You can use the Browse sample application to browse messages on this queue, or use the Print Message sample application to print the messages together with their message descriptors.

However, if you extend the sample to run across more than one queue manager, unexpected messages, or messages that cannot be delivered, could be put on the system dead-letter queue by the queue manager.

### How the sample uses syncpoints

The programs in the Credit Check sample application declare syncpoints to ensure that:

- Only one reply message is sent in response to each expected message
- Multiple copies of unexpected messages are never put on the sample's dead-letter queue

- The CAM can recover the state of all partially-completed inquiries by getting persistent messages from its waiting queue

To achieve this, a single unit of work is used to cover the getting of a message, the processing of that message, and any subsequent put operations.

### How the sample uses message context information

When the user-interface program (CSQ4CVB1) sends messages, it uses the MQPMO\_DEFAULT\_CONTEXT option. This means that the queue manager generates both identity and origin context information. The queue manager gets this information from the transaction that started the program (MVB1) and from the user ID that started the transaction.

When the CAM sends inquiry messages, it uses the MQPMO\_PASS\_IDENTITY\_CONTEXT option. This means that the identity context information of the message being put is copied from the identity context of the original inquiry message. With this option, origin context information is generated by the queue manager.

When the CAM sends reply messages, it uses the MQPMO\_ALTERNATE\_USER\_AUTHORITY option. This causes the queue manager to use an alternate user ID for its security check when the CAM opens a reply-to queue. The CAM uses the user ID of the submitter of the original inquiry message. This means that users are allowed to see replies to only those inquiries they have originated. The alternate user ID is obtained from the identity context information in the message descriptor of the original inquiry message.

When the query programs (CSQ4CVB3/4/5) send reply messages, they use the MQPMO\_PASS\_IDENTITY\_CONTEXT option. This means that the identity context information of the message being put is copied from the identity context of the original inquiry message. With this option, origin context information is generated by the queue manager.

**Note:** The user ID associated with the MVB3/4/5 transactions requires access to the B2.REPLY.n queues. These user IDs may not be the same as those associated with the request being processed. To get around this possible security exposure, the query programs could use the MQPMO\_ALTERNATE\_USER\_AUTHORITY option when putting their replies. This would mean that each individual user of MVB1 needs authority to open the B2.REPLY.n queues.

### Use of message and correlation identifiers in the CAM

The application has to monitor the progress of all the “live” inquiries it is processing at any one time. To do this it uses the unique message identifier of each loan request message to associate all the information it has about each inquiry.

The CAM copies the *MsgId* of the inquiry message into the *CorrelId* of all the request messages it sends for that inquiry. The other programs in the sample (CSQ4CVB3 - 5) copy the *CorrelId* of each message they receive into the *CorrelId* of their reply message.

## The Credit Check sample with multiple queue managers

You can use the Credit Check sample application to demonstrate distributed queuing by installing the sample on two queue managers. After you have installed the sample on each queue manager, you need to:

1. Set up the communication link between the two queue managers. For information on how to do this, see “Setting up communication” in the *MQSeries Intercommunication* book.
2. On one queue manager, create a local definition for each of the remote queues (on the other queue manager) that you want to use. These queues can be any of CSQ4SAMP.Bn.MESSAGES, where *n* is 3, 5, 6, or 7. (These are the queues that are served by the checking-account program and the agency-query program.) For information on how to do this, see “DEFINE QREMOTE” in the *MQSeries Command Reference* manual.
3. Change the definition of the namelist (CSQ4SAMP.B4.NAMELIST) so that it contains the names of the remote queues you choose to use. For information on how to do this, see “ALTER NAMELIST” in the *MQSeries Command Reference* manual.

## The IMS extension to the Credit Check sample

A version of the checking-account program is supplied as an IMS batch message processing (BMP) program. It is written in the C language.

The program performs the same function as the CICS version, except that to obtain the account information, the program reads an IMS database instead of a VSAM file. If you replace the CICS version of the checking-account program with the IMS version, you see no difference in the method of using the application.

To prepare and run the IMS version you must:

1. Follow the steps in “Preparing and running the Credit Check sample” on page 430.
2. Follow the steps in “Preparing the sample application for the IMS environment” on page 407.
3. Alter the definition of the alias queue CSQ4SAMP.B2.OUTPUT.ALIAS to resolve to queue CSQ4SAMP.B3.IMS.MESSAGES (instead of CSQ4SAMP.B3.MESSAGES). To do this, you can use any one of:
  - The MQSeries for OS/390 operations and control panels
  - The ALTER QALIAS command (described in “ALTER QALIAS” in the *MQSeries Command Reference* manual)

Another way of using the IMS checking-account program is to make it serve one of the queues that receives messages from the distribution program. In the delivered form of the Credit Check sample application, there are three of these queues (B5/6/7.MESSAGES), all served by the agency-query program. This program searches a VSAM data set. To compare the use of the VSAM data set and the IMS database, you could make the IMS checking-account program serve one of these queues instead. To do this, you must alter the definition of the namelist CSQ4SAMP.B4.NAMELIST to replace one of the CSQ4SAMP.Bn.MESSAGES queues with the CSQ4SAMP.B3.IMS.MESSAGES queue. You can use any one of:

- The MQSeries for OS/390 operations and control panels

- The ALTER NAMELIST command (described in “ALTER NAMELIST” in the *MQSeries Command Reference* manual)

You can then run the sample from CICS transaction MVB1 as usual. The user sees no difference in operation or response. The IMS BMP stops either after receiving a stop message or after being inactive for five minutes.

### Design of the IMS checking-account program (CSQ4ICB3)

This program runs as a BMP. You must start the program using its JCL before any MQSeries messages are sent to it.

The program searches an IMS database for the account number in the loan request messages. It retrieves the corresponding account name, average balance, and credit worthiness index.

The program sends the results of the database search to the reply-to queue named in the MQSeries message being processed. The message returned appends the account type and the results of the search to the message received so that the transaction building the response can confirm that the correct query is being processed. The message is in the form of three 79-character groups, as follows:

```
'Response from CHECKING ACCOUNT for name : JONES J B'
'      Opened 870530, 3-month average balance = 000012.57'
'      Credit worthiness index - BBB'
```

When running as a message-oriented BMP, the program drains the IMS message queue, then reads messages from the MQSeries for OS/390 queue and processes them. No information is received from the IMS message queue. The program reconnects to the queue manager after each checkpoint because the handles have been closed.

When running in a batch-oriented BMP, the program continues to be connected to the queue manager after each checkpoint because the handles are not closed.

---

## The Message Handler sample

The Message Handler sample TSO application allows you to browse, forward, and delete messages on a queue. The sample is available in C and COBOL.

### Preparing and running the sample

Follow these steps:

1. Prepare the sample as described in “Preparing sample applications for the TSO environment” on page 401.
2. Tailor the CLIST (CSQ4RCH1) provided for the sample to define:
  - The location of the panels
  - The location of the message file
  - The location of the load modules

CLIST CSQ4RCH1 may be used to run both the C and the COBOL version of the sample. The supplied version of CSQ4RCH1 runs the C version, and contains instructions on the tailoring necessary for the COBOL version.

## Message handler sample

### Notes:

1. There are no sample queue definitions provided with the sample.
2. VS COBOL II does not support multitasking with ISPF, so you should not use the Message Handler sample application on both sides of a split screen. If you do, the results are unpredictable.

## Using the sample

Having installed the sample and invoked it from the tailored CLIST CSQ4RCH1, the screen shown in Figure 50 is displayed.

```
----- MQSeries for OS/390 -- Samples -----
COMMAND ==>
User Id : JOHNJ

Enter information. Press ENTER :

Queue Manager Name : _____ :
Queue Name         : _____ :

F1=HELP   F2=SPLIT   F3=END     F4=RETURN   F5=RFIND   F6=RCHANGE
F7=UP     F8=DOWN    F9=SWAP   F10=LEFT   F11=RIGHT  F12=RETRIEVE
```

Figure 50. Initial screen for Message Handler sample

Enter the Queue Manager and Queue name to be viewed (case sensitive) and the message list screen is displayed (see Figure 51).

```
----- MQSeries for OS/390 -- Samples ----- Row 1 to 4 of 4
COMMAND ==>
Queue Manager   : VM03
Queue           : MQEI.IMS.BRIDGE.QUEUE

Message number  01 of 04

Msg  Put Date  Put Time  Format   User      Put Application
No  MM/DD/YYYY HH:MM:SS Name  Identifier Type   Name
01  10/16/1998 13:51:19 MQIMS   NTSFV02  00000002 NTSFV02A
02  10/16/1998 13:55:45 MQIMS   JOHNJ    00000011 EDIT\CLASSES\BIN\PROGTS
03  10/16/1998 13:54:01 MQIMS   NTSFV02  00000002 NTSFV02B
04  10/16/1998 13:57:22 MQIMS   johnj    00000011 EDIT\CLASSES\BIN\PROGTS
***** Bottom of data *****
```

Figure 51. Message list screen for Message Handler sample

This screen shows the first 99 messages on the queue and, for each, shows the following fields:

**Msg No** Message number  
**Put Date MM/DD/YYYY** Date the message was put on the queue (GMT)  
**Put Time HH:MM:SS** Time the message was put on the queue (GMT)  
**Format Name** MQMD.Format field  
**User Identifier** MQMD.UserIdentifier field  
**Put Application Type** MQMD.PutAppIType field  
**Put Application Name** MQMD.PutAppIName field

The total number of messages on the queue is also displayed.

From this screen a message can be chosen, by number not by cursor position, and then displayed. For an example, see Figure 52.

```

----- MQSeries for OS/390 -- Samples ----- Row 1 to 35 of 35
COMMAND ==>

Queue Manager   : VM03
Queue           : MQE1.IMS.BRIDGE.QUEUE
Forward to Q Mgr : VM03
Forward to Queue : QL.TEST.ISCRES1

Action : _ : (D)elete (F)orward

Message Content :
-----
Message Descriptor
StrucId       : MD
Version       : 000000001
Report        : 000000000
MsgType       : 000000001
Expiry        : -000000001
Feedback      : 000000000
Encoding      : 000000785
CodedCharSetId : 000000500
Format        : MQIMS
Priority       : 000000000
Persistence   : 000000001
MsgId         : C3E2D840E5D4F0F34040404040404040AF6B30F0A89B7605 X
CorrelId      : 000000000000000000000000000000000000000000000000 X
BackoutCount   : 000000000
ReplyToQ       : QL.TEST.ISCRES1
ReplyToQMgr    : VM03
UserIdentifier : NTSFV02
AccountingToken :
06F2F5F5F3F0F1000000000000000000000000000000000000000000000000 X
AppIIdentityData :
PutAppIType    : 000000002
PutAppIName    : NTSFV02A
PutDate        : 19971016
PutTime        : 13511903
AppIOriginData :

Message Buffer : 108 byte(s)
00000000 : C9C9 C840 0000 0001 0000 0054 0000 0311 I IH .....
00000010 : 0000 0000 4040 4040 4040 4040 0000 0000 ....
00000020 : 4040 4040 4040 4040 4040 4040 4040 4040
00000030 : 4040 4040 4040 4040 4040 4040 4040 4040
00000040 : 0000 0000 0000 0000 0000 0000 0000 0000 .....
00000050 : 40F1 C300 0018 0000 C9C1 D7D4 C4C9 F2F8 1C....IAPMDI28
00000060 : 40C8 C5D3 D3D6 40E6 D6D9 D3C4 HELLO WORLD
***** Bottom of data *****
    
```

Figure 52. Chosen message is displayed

## Message handler sample

Once the message has been displayed it can be deleted, left on the queue, or forwarded to another queue. The Forward to Q Mgr and Forward to Queue fields are initialized with values from the MQMD, these can be changed prior to forwarding the message.

The sample design will only allow messages with unique MsgId / CorrelId combinations to be selected and displayed, this is because the message is retrieved using the MsgId and CorrelId as the key. If the key is not unique the sample cannot retrieve the chosen message with certainty.

## Design of the sample

This section describes the design of each of the programs that comprise the Message Handler sample application.

### Object validation program

This requests a valid queue and queue manager name. If you do not specify a queue manager name, the default queue manager is used, if available. Only local queues can be used; an MQINQ is issued to check the queue type and an error is reported if the queue is not local. If the queue is not opened successfully, or the MQGET call is inhibited on the queue, error messages are returned indicating the CompCode and Reason return code.

### Message list program

This displays a list of messages on a queue with information about them such as the putdate, puttime and the message format. The maximum number of messages stored in the list is 99. If there are more messages on the queue than this, the current queue depth is also displayed. To choose a message for display, type the message number into the entry field (the default is 01). If your entry is invalid, you will receive an appropriate error message.

### Message content program

This displays message content. The content is formatted and split into two parts:

1. the message descriptor
2. the message buffer

The message descriptor shows the contents of each field on a separate line.

The message buffer is formatted depending on its contents. If the buffer holds a dead letter header (MQDLH) or a transmission queue header (MQXQH), these are formatted and displayed before the buffer itself.

Before the buffer data is formatted, a title line shows the buffer length of the message in bytes. The maximum buffer size is 32768 bytes, and any message longer than this is truncated. The full size of the buffer is displayed along with a message indicating that only the first 32768 bytes of the message are displayed.

The buffer data is formatted in two ways:

1. After the offset into the buffer is printed, the buffer data is displayed in HEX.
2. The buffer data is then displayed again as EBCDIC values. If any EBCDIC value cannot be printed, it prints a '.' instead.

You may enter 'D' for delete, or 'F' for forward into the action field. If you choose to forward the message, the *forward-to queue* and *queue manager name* must be filled in appropriately. The defaults for these fields are read from the message descriptor ReplyToQ and ReplyToQMgr fields.

If you forward a message, any header block stored in the buffer is stripped. If the message is forwarded successfully, it is removed from the original queue. If you enter invalid actions, error messages are displayed.

An example help panel is also available called CSQ4CHP9.

## Message handler sample

---

## Part 5. Appendixes

<b>Appendix A. Language compilers and assemblers</b> . . . . .	453
<b>Appendix B. MQI names in RPG</b> . . . . .	457
Names of calls . . . . .	457
Names of call parameters . . . . .	457
Data types . . . . .	458
Names of fields in structures . . . . .	458
Names of constants . . . . .	466
<b>Appendix C. C language examples</b> . . . . .	487
Connecting to a queue manager . . . . .	488
Disconnecting from a queue manager . . . . .	488
Creating a dynamic queue . . . . .	489
Opening an existing queue . . . . .	489
Closing a queue . . . . .	490
Putting a message using MQPUT . . . . .	490
Putting a message using MQPUT1 . . . . .	491
Getting a message . . . . .	492
Getting a message using the wait option . . . . .	492
Getting a message using signaling . . . . .	493
Inquiring about the attributes of an object . . . . .	494
Setting the attributes of a queue . . . . .	495
<b>Appendix D. COBOL examples</b> . . . . .	497
Connecting to a queue manager . . . . .	498
Disconnecting from a queue manager . . . . .	498
Creating a dynamic queue . . . . .	499
Opening an existing queue . . . . .	500
Closing a queue . . . . .	501
Putting a message using MQPUT . . . . .	501
Putting a message using MQPUT1 . . . . .	502
Getting a message . . . . .	503
Getting a message using the wait option . . . . .	504
Getting a message using signaling . . . . .	505
Inquiring about the attributes of an object . . . . .	506
Setting the attributes of a queue . . . . .	507
<b>Appendix E. System/390 assembler-language examples</b> . . . . .	509
Connecting to a queue manager . . . . .	510
Disconnecting from a queue manager . . . . .	510
Creating a dynamic queue . . . . .	511
Opening an existing queue . . . . .	512
Closing a queue . . . . .	512
Putting a message using MQPUT . . . . .	513
Putting a message using MQPUT1 . . . . .	513
Getting a message . . . . .	514
Getting a message using the wait option . . . . .	515
Getting a message using signaling . . . . .	516
Inquiring about and setting the attributes of a queue . . . . .	517

<b>Appendix F. PL/I examples</b>	519
Connecting to a queue manager	520
Disconnecting from a queue manager	520
Creating a dynamic queue	521
Opening an existing queue	521
Closing a queue	522
Putting a message using MQPUT	522
Putting a message using MQPUT1	523
Getting a message	524
Getting a message using the wait option	525
Getting a message using signaling	526
Inquiring about the attributes of an object	527
Setting the attributes of a queue	528
<b>Appendix G. MQSeries data definition files</b>	529
C language include files	530
Visual Basic module files	531
COBOL copy files	532
System/390 assembler-language macros	535
PL/I include files	536
<b>Appendix H. List of MQSeries products</b>	537
Level 1 products	537
Level 2 products	537
<b>Appendix I. MQSeries platforms - functional comparisons</b>	539
What is included here	539
Syncpoint	540
Level 1 product range support	541
Level 1–browse-with-lock support	542
Level 2 product range support	542
Migration recommendations	543
Triggering	544
Level 1 product range support	545
Level 2 product range support	545
Migration recommendations	546
Input	547
Shared and exclusive input	548
Browse-with-lock, and full browse	548
Signal	548
Get by MsgId and CorrelId	549
Data conversion	550
Message properties and protocols	551
Maximum message length	552
Maximum priority	552
Nonpersistent messages	552
Exception reports	553
MsgId and CorrelId options for responses	553
Extra message types	554
COA, COD, and Expiry message	554
PAN and NAN messages	554
Threading	555
Threaded applications on UNIX platforms	555

Security	556
Authorization checks	556
Message context	557
Alternate user ID checks	558
Channel exits	558
API-crossing exit	559
Object types	560
Model and dynamic queues	560
Namelists	561
Queue-manager object	561
Administration	562
Command queues	562
Handles broken	563
MQSET support	563
Programming languages	564
Header files	564
Connection	566
Default connection	566
<b>Appendix J. Notices</b>	<b>567</b>
Programming interface information	569
Trademarks	570



## Appendix A. Language compilers and assemblers

Table 42 lists the language compilers and assemblers supported.

<i>Table 42 (Page 1 of 3). Language compilers and assemblers</i>		
<b>Platform</b>	<b>Language</b>	<b>Compiler/Assembler</b>
MQSeries for AIX	C++	IBM C Set++ for AIX, V3.1 IBM C++ compiler, V3.6.4 (for AIX V4.3)
	C	IBM C for AIX, V3.1.4 IBM C Set++ for AIX, V3.1 (C bindings only) IBM C++ compiler, V3.6.4 (for AIX V4.3)
	COBOL	IBM COBOL Set for AIX, V1.1 Micro Focus COBOL Compiler for UNIX, V4.0
	PL/I	IBM PL/I Set for AIX, V1.1
MQSeries for AS/400	C++	IBM VisualAge for C++ for AS/400, V4.2.1
	C	IBM ILE C for AS/400, V4.2.1
	COBOL	IBM ILE COBOL for AS/400, V4.2.1
	RPG	IBM ILE RPG for AS/400, V4.2.1
MQSeries for AT&T GIS UNIX	C++	AT&T C++ language system for AT&T GIS UNIX
	C	AT&T GIS High Performance C, V1.0b
MQSeries for Digital OpenVMS	C++	DEC C++, V5.0 (VAX), V5.2 (AXP)
	C	DEC C, V5.0
	COBOL	DEC COBOL, V5.0 (VAX), V2.2 (AXP)
MQSeries for HP-UX	C++	ANSI C++ for HP-UX V10 and V11 HP C++, V3.1 for HP-UX V10.x IBM C++ compiler, V3.6
	C	ANSI C++ for HP-UX V10 and V11 C bundled compiler C Softbench, V5.0 HP C++, V3.1 for HP-UX V10.x HP-UX ANSI C compiler IBM C compiler, V3.6
	COBOL	COBOL Softbench, V4.0 Micro Focus COBOL compiler, V4.0 for UNIX
MQSeries for OS/2 Warp	C++	IBM C++ compiler, V3.6 IBM VisualAge for C++ for OS/2, V3.0
	C	Borland C++, V2 (C bindings only) IBM C compiler, V3.6 IBM VisualAge for C++ for OS/2, V3.0 (C bindings only)
	COBOL	IBM VisualAge for COBOL for OS/2, V1.1 Micro Focus COBOL, V4.0
	PL/I	IBM PL/I for OS/2, V1.2 IBM VisualAge for PL/I for OS/2

## Compilers and assemblers

Table 42 (Page 2 of 3). Language compilers and assemblers

Platform	Language	Compiler/Assembler
MQSeries for OS/390	Assembler	Assembler H assembler IBM High Level Assembler/MVS assembler
	C++	IBM OS/390 C/C++, V2R4
	C	C/370, Release 2.1.0 IBM OS/390 C/C++, V2R4 IBM SAA AD/Cycle® C/370
	COBOL	IBM SAA AD/Cycle COBOL/370™ VS COBOL II
	PL/I	IBM SAA AD/Cycle PL/I Compiler OS PL/I Optimizing compiler
MQSeries for SINIX and DC/OSx	C	DC/OSx: C4.0 compiler, V4.0.1 SINIX: C compiler (C-DS, MIPS), V1.1
	COBOL	Micro Focus COBOL, V3.2
MQSeries for Sun Solaris	C++	SunWorkShop compiler C++, V4.2
	C	SunWorkShop compiler C, V4.2
	COBOL	Micro Focus COBOL Compiler, V4.0 for UNIX
MQSeries for Tandem NSK	C	D30 or later using WIDE memory model (32-bit integers)
	COBOL	D30 or later
	TAL	D30 or later
MQSeries for VSE/ESA	C	IBM C for VSE/ESA, V1.1
	COBOL	IBM COBOL for VSE/ESA, V1.1
	PL/I	IBM PL/I for VSE/ESA, V1.1
MQSeries for Windows V2.0	16-bit Basic	Microsoft Visual Basic, V3.0 or V4.0
	32-bit Basic	Microsoft Visual Basic, V4.0
	16-bit C	Microsoft Visual C++, V1.5
	32-bit C	Microsoft Visual C++, V2.0
MQSeries for Windows V2.1	Basic	Microsoft Visual Basic, V4.0
	C	Microsoft Visual C++, V4.0 Borland C

Table 42 (Page 3 of 3). Language compilers and assemblers

Platform	Language	Compiler/Assembler
MQSeries for Windows NT	Basic	Visual Basic for Windows, V4.0 (16-bit) Visual Basic for Windows, V5.0 (32-bit)
	C++	IBM C++ compiler, V3.6.4 IBM VisualAge for C++ for Windows, V3.5 IBM VisualAge for C++ Professional, V4.0 Microsoft Visual C++ for Windows 95 and NT, V4.0 and V5.0
	C	IBM C compiler, V3.6.4 IBM VisualAge for C++ for Windows, V3.5 Microsoft Visual C++ for Windows 95 and NT, V4.0 and V5.0
	COBOL	IBM VisualAge COBOL Enterprise, V2.2 IBM VisualAge COBOL for Windows NT, V2.1 Micro Focus Object COBOL for Windows NT, V3.3 or V4.0
	Java	IBM VisualAge e-business for Windows, V1.0.1 IBM VisualAge for Java Enterprise, V2.0 IBM VisualAge for Java Professional, V2.0
	PL/I	IBM PL/I for Windows, V1.2 IBM VisualAge for PL/I for Windows IBM VisualAge PL/I Enterprise, V2.1
DOS clients	C	Microsoft C, V7.0 Microsoft Visual C++, V1.5
VM/ESA clients	Assembler	IBM Assembler
	C	IBM C for VM Release, 3.1
	COBOL	IBM VS COBOL II
	PL/I	IBM OS/PL/I, Release 2.3
	REXX	IBM VM/ESA REXX/VM
Windows 3.1 clients	C++	Microsoft Visual C++, V1.5
	C	Microsoft C, V7.0
Windows 95 and Windows 98 clients	C++	IBM VisualAge for C++ for Windows, V3.5 Microsoft Visual C++, V4.0
	C	Microsoft Visual C++, V4.0
	COBOL	Micro Focus COBOL Workbench, V4.0
<b>Note:</b> RPG bindings are shown for the IBM SAA AD/Cycle RPG/400 compiler.		



## Appendix B. MQI names in RPG

### Note for RPG programmers

The names of MQI calls, call parameters, data types, fields of structures, and constants (applicable to RPG) are shown in this book with long names. When writing RPG programs, use the equivalent short RPG names given in the tables in this appendix. The RPG names are used in the *MQSeries for AS/400 Application Programming Reference (RPG)* manual.

### Names of calls

Long name	RPG name
MQCLOSE	CID=MQCLOS
MQCONN	CID=MQCONN
MQDISC	CID=MQDISC
MQGET	CID=MQGET
MQINQ	CID=MQINQ
MQOPEN	CID=MQOPEN
MQPUT	CID=MQPUT
MQPUT1	CID=MQPUT1
MQSET	CID=MQSET

### Names of call parameters

Long name	RPG name
<i>Buffer</i>	<i>BUFFER</i>
<i>BufferLength</i>	<i>BUFLen</i>
<i>CharAttrs</i>	<i>CHRATR</i>
<i>CharAttrLength</i>	<i>CALEN</i>
<i>CompCode</i>	<i>CMPCOD</i>
<i>DataLength</i>	<i>DATLEN</i>
<i>GetMsgOpts</i>	<i>GMO</i>
<i>Hconn</i>	<i>HCONN</i>
<i>Hobj</i>	<i>HOBJ</i>
<i>IntAttrs</i>	<i>INTATR</i>
<i>IntAttrCount</i>	<i>IACNT</i>
<i>MsgDesc</i>	<i>MSGDSC</i>
<i>QMgrName</i>	<i>QMNAME</i>
<i>ObjDesc</i>	<i>OBJDSC</i>
<i>Options</i>	<i>OPTS</i>

## MQI names in RPG

<i>Table 44 (Page 2 of 2). Names of call parameters</i>	
<b>Long name</b>	<b>RPG name</b>
<i>PutMsgOpts</i>	<i>PMO</i>
<i>Reason</i>	<i>REASON</i>
<i>Selectors</i>	<i>SELS</i>
<i>SelectorCount</i>	<i>SELCNT</i>

## Data types

Many of the data types have the same RPG name and long name, for example MQDLH, MQGMO, MQMD, and so on. The following table shows only those data types where the RPG representation is different from the long name.

<i>Table 45. Data types</i>	
<b>Long name</b>	<b>RPG representation</b>
MQBYTE	1-byte bit string
MQBYTE <sub>n</sub>	n-byte bit string
MQCHAR	1 character
MQCHAR <sub>n</sub>	n-byte character string
MQHCONN (structure field)	9-digit binary integer
MQHCONN (call parameter)	9-digit decimal integer
MQHOBJ (structure field)	9-digit binary integer
MQHOBJ (call parameter)	9-digit decimal integer
MQLONG (structure field)	9-digit binary integer
MQLONG (call parameter)	9-digit decimal integer
PMQLONG	9-digit binary integer

## Names of fields in structures

<i>Table 46 (Page 1 of 9). Names of fields in structures</i>	
<b>Long name</b>	<b>RPG name</b>
<i>AccountingToken</i> (MQMD)	<i>MDACC</i>
<i>AccountingToken</i> (MQPMR)	<i>PRACC</i>
<i>AlternateUserId</i> (MQOD)	<i>ODAU</i>
<i>ApplId</i> (MQTMC)	<i>TCAI</i>
<i>ApplId</i> (MQTM)	<i>TMAI</i>
<i>ApplIdentityData</i> (MQMD)	<i>MDAID</i>
<i>ApplOriginData</i> (MQMD)	<i>MDAOD</i>
<i>ApplType</i> (MQTMC)	<i>TCAT</i>
<i>ApplType</i> (MQTM)	<i>TMAT</i>
<i>AppOptions</i> (MQDXP)	<i>DXAOP</i>
<i>Authenticator</i> (MQIIH)	<i>IIAUT</i>
<i>BackoutCount</i> (MQMD)	<i>MDBOC</i>

<i>Table 46 (Page 2 of 9). Names of fields in structures</i>	
<b>Long name</b>	<b>RPG name</b>
<i>BatchInterval</i> (MQCD)	<i>CDBI</i>
<i>BatchSize</i> (MQCD)	<i>CDBS</i>
<i>CapabilityFlags</i> (MQCXP)	<i>CXCAP</i>
<i>ChannelName</i> (MQCD)	<i>CDCHN</i>
<i>ChannelType</i> (MQCD)	<i>CDCHT</i>
<i>CodedCharSetId</i> (MQDH)	<i>DHCSI</i>
<i>CodedCharSetId</i> (MQDLH)	<i>DLCSI</i>
<i>CodedCharSetId</i> (MQDXP)	<i>DXCSI</i>
<i>CodedCharSetId</i> (MQIIH)	<i>IICSI</i>
<i>CodedCharSetId</i> (MQMD)	<i>MDCSI</i>
<i>CodedCharSetId</i> (MQMDE)	<i>MECSI</i>
<i>CodedCharSetId</i> (MQRMH)	<i>RMCSI</i>
<i>CodedCharSetId</i> (MQCFSL)	<i>SLCSI</i>
<i>CodedCharSetId</i> (MQCFST)	<i>STCSI</i>
<i>Command</i> (MQCFH)	<i>FHCMD</i>
<i>CommitMode</i> (MQIIH)	<i>IICMT</i>
<i>CompCode</i> (MQDXP)	<i>DXCC</i>
<i>CompCode</i> (MQCFH)	<i>FHCMP</i>
<i>CompCode</i> (MQRR)	<i>RRCC</i>
<i>ConnectionName</i> (MQCD)	<i>CDCON</i>
<i>Context</i> (MQPMO)	<i>PMCT</i>
<i>Control</i> (MQCFH)	<i>FHCTL</i>
<i>CorrelId</i> (MQMD)	<i>MDCID</i>
<i>CorrelId</i> (MQPMR)	<i>PRCID</i>
<i>Count</i> (MQCFIL)	<i>ILCNT</i>
<i>Count</i> (MQCFSL)	<i>SLCNT</i>
<i>DataConversion</i> (MQCD)	<i>CDDC</i>
<i>DataLength</i> (MQDXP)	<i>DXLEN</i>
<i>DataLogicalLength</i> (MQRMH)	<i>RMDL</i>
<i>DataLogicalOffset</i> (MQRMH)	<i>RMDO</i>
<i>DataLogicalOffset2</i> (MQRMH)	<i>RMDO2</i>
<i>Desc</i> (MQCD)	<i>CDDES</i>
<i>DestEnvLength</i> (MQRMH)	<i>RMDEL</i>
<i>DestEnvOffset</i> (MQRMH)	<i>RMDEO</i>
<i>DestNameLength</i> (MQRMH)	<i>RMDNL</i>
<i>DestNameOffset</i> (MQRMH)	<i>RMDNO</i>
<i>DestQMgrName</i> (MQDLH)	<i>DLDM</i>
<i>DestQName</i> (MQDLH)	<i>DLDQ</i>

<i>Table 46 (Page 3 of 9). Names of fields in structures</i>	
<b>Long name</b>	<b>RPG name</b>
<i>DiscInterval</i> (MQCD)	<i>CDDI</i>
<i>DynamicQName</i> (MQOD )	<i>ODDN</i>
<i>Encoding</i> (MQDH)	<i>DHENC</i>
<i>Encoding</i> (MQDLH)	<i>DLENC</i>
<i>Encoding</i> (MQDXP)	<i>DXENC</i>
<i>Encoding</i> (MQIIH)	<i>IIENC</i>
<i>Encoding</i> (MQMD)	<i>MDENC</i>
<i>Encoding</i> (MQMDE)	<i>MEENC</i>
<i>Encoding</i> (MQRMH)	<i>RMENC</i>
<i>EnvData</i> (MQTMC)	<i>TCED</i>
<i>EnvData</i> (MQTM)	<i>TMED</i>
<i>ExitData</i> (MQCXP)	<i>CXDAT</i>
<i>ExitDataLength</i> (MQCD)	<i>CDXDL</i>
<i>ExitId</i> (MQCXP)	<i>CXXID</i>
<i>ExitNameLength</i> (MQCD)	<i>CDXNL</i>
<i>ExitNumber</i> (MQCXP)	<i>CXEXN</i>
<i>ExitOptions</i> (MQDXP)	<i>DXXOP</i>
<i>ExitReason</i> (MQCXP)	<i>CXREA</i>
<i>ExitResponse</i> (MQCXP)	<i>CXRES</i>
<i>ExitResponse</i> (MQDXP)	<i>DXRES</i>
<i>ExitResponse2</i> (MQCXP)	<i>CXRE2</i>
<i>ExitUserArea</i> (MQCXP)	<i>CXUA</i>
<i>Expiry</i> (MQMD)	<i>MDEXP</i>
<i>Feedback</i> (MQCXP)	<i>CXFB</i>
<i>Feedback</i> (MQMD)	<i>MDFB</i>
<i>Feedback</i> (MQPMR)	<i>PRFB</i>
<i>Flags</i> (MQDH)	<i>DHFLG</i>
<i>Flags</i> (MQIIH)	<i>IIFLG</i>
<i>Flags</i> (MQMDE)	<i>MEFLG</i>
<i>Flags</i> (MQRMH)	<i>RMFLG</i>
<i>Format</i> (MQDH)	<i>DHFMT</i>
<i>Format</i> (MQDLH)	<i>DLFMT</i>
<i>Format</i> (MQIIH)	<i>IIFMT</i>
<i>Format</i> (MQMD)	<i>MDFMT</i>
<i>Format</i> (MQMDE)	<i>MEFMT</i>
<i>Format</i> (MQRMH)	<i>RMFMT</i>
<i>FAPLevel</i> (MQCXP)	<i>CXFAP</i>
<i>GroupId</i> (MQMD)	<i>MDGID</i>

<i>Table 46 (Page 4 of 9). Names of fields in structures</i>	
<b>Long name</b>	<b>RPG name</b>
<i>GroupId (MQMDE)</i>	<i>MEGID</i>
<i>GroupId (MQPMR)</i>	<i>PRGID</i>
<i>GroupStatus (MQGMO)</i>	<i>GMGST</i>
<i>Hconn (MQDXP)</i>	<i>DXHCN</i>
<i>HeaderLength (MQCXP)</i>	<i>CXHDL</i>
<i>HeartbeatInterval (MQCD)</i>	<i>CDHBI</i>
<i>InvalidDestCount (MQOD)</i>	<i>ODIDC</i>
<i>InvalidDestCount (MQPMO)</i>	<i>PMIDC</i>
<i>KnownDestCount (MQOD)</i>	<i>ODKDC</i>
<i>KnownDestCount (MQPMO)</i>	<i>PMKDC</i>
<i>LongRetryCount (MQCD)</i>	<i>CDLRC</i>
<i>LongRetryInterval (MQCD)</i>	<i>CDLRI</i>
<i>LTermOverride (MQIIH)</i>	<i>IILTO</i>
<i>MatchOptions (MQGMO)</i>	<i>GMMO</i>
<i>MaxSegmentLength (MQCXP)</i>	<i>CXMSL</i>
<i>ModeName (MQCD)</i>	<i>CDMOD</i>
<i>MsgDesc (MQXQH)</i>	<i>XQMD</i>
<i>MsgExit (MQCD)</i>	<i>CDMSX</i>
<i>MsgExitsDefined (MQCD)</i>	<i>CDMXD</i>
<i>MsgExitPtr (MQCD)</i>	<i>CDMXP</i>
<i>MsgFlags (MQMD)</i>	<i>MDMFL</i>
<i>MsgFlags (MQMDE)</i>	<i>MEMFL</i>
<i>MsgId (MQMD)</i>	<i>MDMID</i>
<i>MsgId (MQPMR)</i>	<i>PRMID</i>
<i>MsgRetryCount (MQCD)</i>	<i>CDMRC</i>
<i>MsgRetryCount (MQCXP)</i>	<i>CXMRC</i>
<i>MsgRetryExit (MQCD)</i>	<i>CDMRX</i>
<i>MsgRetryInterval (MQCD)</i>	<i>CDMRI</i>
<i>MsgRetryInterval (MQCXP)</i>	<i>CXMRI</i>
<i>MsgRetryReason (MQCXP)</i>	<i>CXMRR</i>
<i>MsgRetryUserData (MQCD)</i>	<i>CDMRD</i>
<i>MsgSeqNumber (MQCFH)</i>	<i>FHSEQ</i>
<i>MsgSeqNumber (MQMD)</i>	<i>MDSEQ</i>
<i>MsgSeqNumber (MQMDE)</i>	<i>MESEQ</i>
<i>MsgType (MQMD)</i>	<i>MDMT</i>
<i>MsgUserData (MQCD)</i>	<i>CDMSD</i>
<i>MsgUserDataPtr (MQCD)</i>	<i>CDMUP</i>
<i>MCAName (MQCD)</i>	<i>CDMCA</i>

<i>Table 46 (Page 5 of 9). Names of fields in structures</i>	
<b>Long name</b>	<b>RPG name</b>
<i>MCAType (MQCD)</i>	<i>CDCAT</i>
<i>MCAUserIdentifier (MQCD)</i>	<i>CDAUI</i>
<i>MFSMapName (MQIIH)</i>	<i>IIMMN</i>
<i>NonPersistentMsgSpeed (MQCD)</i>	<i>CDNPM</i>
<i>ObjectInstanceId (MQRMH)</i>	<i>RMOII</i>
<i>ObjectName (MQOD)</i>	<i>ODON</i>
<i>ObjectName (MQOR)</i>	<i>ORON</i>
<i>ObjectQMgrName (MQOD)</i>	<i>ODMN</i>
<i>ObjectQMgrName (MQOD)</i>	<i>ODMN</i>
<i>ObjectQMgrName (MQOR)</i>	<i>ORMN</i>
<i>ObjectRecOffset (MQDH)</i>	<i>DHORO</i>
<i>ObjectRecOffset (MQOD)</i>	<i>ODORO</i>
<i>ObjectType (MQOD)</i>	<i>ODOT</i>
<i>ObjectRecPtr (MQOD)</i>	<i>ODORP</i>
<i>ObjectType (MQRMH)</i>	<i>RMOT</i>
<i>Offset (MQMD)</i>	<i>MDOFF</i>
<i>Offset (MQMDE)</i>	<i>MEOFF</i>
<i>Options (MQGMO)</i>	<i>GMOPT</i>
<i>Options (MQPMO)</i>	<i>PMOPT</i>
<i>OriginalLength (MQMD)</i>	<i>MDOLN</i>
<i>OriginalLength (MQMDE)</i>	<i>MEOLN</i>
<i>Parameter (MQCFIL)</i>	<i>ILPRM</i>
<i>Parameter (MQCFIN)</i>	<i>INPRM</i>
<i>Parameter (MQCFSL)</i>	<i>SLPRM</i>
<i>Parameter (MQCFST)</i>	<i>STPRM</i>
<i>ParameterCount (MQCFH)</i>	<i>FHCNT</i>
<i>PartnerName (MQCXP)</i>	<i>CXPNM</i>
<i>Password (MQCD)</i>	<i>CDPW</i>
<i>Persistence (MQMD)</i>	<i>MDPER</i>
<i>Priority (MQMD)</i>	<i>MDPRI</i>
<i>Persistence (MQMD)</i>	<i>MDPER</i>
<i>ProcessName (MQTM)</i>	<i>TMPN</i>
<i>PutApplName (MQDLH)</i>	<i>DLPAN</i>
<i>PutApplName (MQMD)</i>	<i>MDPAN</i>
<i>PutApplType (MQDLH)</i>	<i>DLPAT</i>
<i>PutApplType (MQMD)</i>	<i>MDPAT</i>
<i>PutAuthority (MQCD)</i>	<i>CDPA</i>
<i>PutDate (MQDLH)</i>	<i>DLPD</i>

<i>Table 46 (Page 6 of 9). Names of fields in structures</i>	
<b>Long name</b>	<b>RPG name</b>
<i>PutDate (MQMD)</i>	<i>MDPD</i>
<i>PutMsgRecFields (MQDH)</i>	<i>DHPRF</i>
<i>PutMsgRecFields (MQPMO)</i>	<i>PMPRF</i>
<i>PutMsgRecOffset (MQDH)</i>	<i>DHPRO</i>
<i>PutMsgRecOffset (MQPMO)</i>	<i>PMPRO</i>
<i>PutMsgRecPtr (MQPMO)</i>	<i>PMPRP</i>
<i>PutTime (MQDLH)</i>	<i>DLPT</i>
<i>PutTime (MQMD)</i>	<i>MDPT</i>
<i>QMgrName (MQCD)</i>	<i>CDQM</i>
<i>QName (MQTMC)</i>	<i>TCQN</i>
<i>QName (MQTM)</i>	<i>TMQN</i>
<i>Reason (MQDLH)</i>	<i>DLREA</i>
<i>Reason (MQDXP)</i>	<i>DXREA</i>
<i>Reason (MQCFH)</i>	<i>FHREA</i>
<i>Reason (MQRR)</i>	<i>RRREA</i>
<i>ReceiveExit (MQCD)</i>	<i>CDRCX</i>
<i>ReceiveExitsDefined (MQCD)</i>	<i>CDRXD</i>
<i>ReceiveExitPtr (MQCD)</i>	<i>CDRXP</i>
<i>ReceiveUserData (MQCD)</i>	<i>CDRCD</i>
<i>ReceiveUserDataPtr (MQCD)</i>	<i>CDRUP</i>
<i>RecsPresent (MQDH)</i>	<i>DHCNT</i>
<i>RecsPresent (MQOD)</i>	<i>ODREC</i>
<i>RecsPresent (MQOD)</i>	<i>PMREC</i>
<i>RemotePassword (MQCD)</i>	<i>CDRPW</i>
<i>RemoteQMgrName (MQXQH)</i>	<i>XQRQM</i>
<i>RemoteQMgrName (MQXQH)</i>	<i>XQRQM</i>
<i>RemoteQName (MQXQH)</i>	<i>XQRQ</i>
<i>RemoteUserIdentifier (MQCD)</i>	<i>CDRUI</i>
<i>ReplyToFormat (MQIIH)</i>	<i>IIRFM</i>
<i>ReplyToQ (MQMD)</i>	<i>MDRQ</i>
<i>ReplyToQMgr (MQMD)</i>	<i>MDRM</i>
<i>Report (MQMD)</i>	<i>MDREP</i>
<i>Reserved (MQIIH)</i>	<i>IIRSV</i>
<i>Reserved1 (MQGMO)</i>	<i>GMRE1</i>
<i>ResolvedQMgrName (MQPMO)</i>	<i>PMRMN</i>
<i>ResolvedQName (MQGMO)</i>	<i>GMRQN</i>
<i>ResolvedQName (MQPMO)</i>	<i>PMRQN</i>
<i>ResponseRecOffset (MQOD)</i>	<i>ODRRO</i>

<i>Table 46 (Page 7 of 9). Names of fields in structures</i>	
<b>Long name</b>	<b>RPG name</b>
<i>ResponseRecOffset</i> (MQPMO)	<i>PMRRO</i>
<i>ResponseRecPtr</i> (MQOD)	<i>ODRRP</i>
<i>ResponseRecPtr</i> (MQPMO)	<i>PMRRP</i>
<i>SecurityExit</i> (MQCD)	<i>CDSCX</i>
<i>SecurityScope</i> (MQIIH)	<i>IISEC</i>
<i>SecurityUserData</i> (MQCD)	<i>CDSCD</i>
<i>Segmentation</i> (MQGMO)	<i>GMSEG</i>
<i>SegmentStatus</i> (MQGMO)	<i>GMSST</i>
<i>SendExit</i> (MQCD)	<i>CDSNX</i>
<i>SendExitsDefined</i> (MQCD)	<i>CDSXD</i>
<i>SendExitPtr</i> (MQCD)	<i>CDSXP</i>
<i>SendUserData</i> (MQCD)	<i>CDSND</i>
<i>SendUserDataPtr</i> (MQCD)	<i>CDSUP</i>
<i>SeqNumberWrap</i> (MQCD)	<i>CDSNW</i>
<i>ShortConnectionName</i> (MQCD)	<i>CDSCN</i>
<i>ShortRetryCount</i> (MQCD)	<i>CDSRC</i>
<i>ShortRetryInterval</i> (MQCD)	<i>CDSRI</i>
<i>Signal1</i> (MQGMO)	<i>GMSG1</i>
<i>Signal2</i> (MQGMO)	<i>GMSG2</i>
<i>SrcEnvLength</i> (MQRMH)	<i>RMSEL</i>
<i>SrcEnvOffset</i> (MQRMH)	<i>RMSEO</i>
<i>SrcNameLength</i> (MQRMH)	<i>RMSNL</i>
<i>SrcNameOffset</i> (MQRMH)	<i>RMSNO</i>
<i>String</i> (MQCFST)	<i>STSTR</i>
<i>Strings</i> (MQCFSL)	<i>SLSTR</i>
<i>StringLength</i> (MQCFSL)	<i>SLSTL</i>
<i>StringLength</i> (MQCFST)	<i>STSTL</i>
<i>StrucId</i> (MQCXP)	<i>CXSID</i>
<i>StrucId</i> (MQDH)	<i>DHSID</i>
<i>StrucId</i> (MQDLH)	<i>DLSID</i>
<i>StrucId</i> (MQDXP)	<i>DXSID</i>
<i>StrucId</i> (MQGMO)	<i>GMSID</i>
<i>StrucId</i> (MQIIH)	<i>IISID</i>
<i>StrucId</i> (MQMD)	<i>MDSID</i>
<i>StrucId</i> (MQMDE)	<i>MESID</i>
<i>StrucId</i> (MQOD)	<i>ODSID</i>
<i>StrucId</i> (MQPMO)	<i>PMSID</i>
<i>StrucId</i> (MQRMH)	<i>RMSID</i>

<i>Table 46 (Page 8 of 9). Names of fields in structures</i>	
<b>Long name</b>	<b>RPG name</b>
<i>StrucId (MQTMC)</i>	<i>TCSID</i>
<i>StrucId (MQTM)</i>	<i>TMSID</i>
<i>StrucId (MQXQH)</i>	<i>XQSID</i>
<i>StrucLength (MQCD)</i>	<i>CDLEN</i>
<i>StrucLength (MQDH)</i>	<i>DHLEN</i>
<i>StrucLength (MQCFH)</i>	<i>FHLEN</i>
<i>StrucLength (MQIIH)</i>	<i>IILEN</i>
<i>StrucLength (MQCFIL)</i>	<i>ILLEN</i>
<i>StrucLength (MQCFIN)</i>	<i>INLEN</i>
<i>StrucLength (MQMDE)</i>	<i>MELEN</i>
<i>StrucLength (MQRMH)</i>	<i>RMLEN</i>
<i>StrucLength (MQCFSL)</i>	<i>SILEN</i>
<i>StrucLength (MQCFST)</i>	<i>STLEN</i>
<i>Timeout (MQPMO)</i>	<i>PMTO</i>
<i>TpName (MQCD)</i>	<i>CDTP</i>
<i>TransportType (MQCD)</i>	<i>CDTRT</i>
<i>TranInstanceId (MQIIH)</i>	<i>IITID</i>
<i>TranState (MQIIH)</i>	<i>IITST</i>
<i>TriggerData (MQTMC)</i>	<i>TCTD</i>
<i>TriggerData (MQTM)</i>	<i>TMTD</i>
<i>TriggerData (MQTM)</i>	<i>TMTD</i>
<i>Type (MQCFH)</i>	<i>FHTYP</i>
<i>Type (MQCFIL)</i>	<i>ILTYP</i>
<i>Type (MQCFIN)</i>	<i>INTYP</i>
<i>Type (MQCFSL)</i>	<i>SLTYP</i>
<i>Type (MQCFST)</i>	<i>STTYP</i>
<i>UnknownDestCount (MQOD)</i>	<i>ODUDC</i>
<i>UnknownDestCount (MQPMO)</i>	<i>PMUDC</i>
<i>UserData (MQTMC)</i>	<i>TCUD</i>
<i>UserData (MQTM)</i>	<i>TMUD</i>
<i>UserIdentifier (MQCD)</i>	<i>CDUID</i>
<i>UserIdentifier (MQMD)</i>	<i>MDUID</i>
<i>Value (MQCFIN)</i>	<i>INVAL</i>
<i>Values (MQCFIL)</i>	<i>ILVAL</i>
<i>Version (MQCD)</i>	<i>CDVER</i>
<i>Version (MQCXP)</i>	<i>CXVER</i>
<i>Version (MQDH)</i>	<i>DHVER</i>
<i>Version (MQDLH)</i>	<i>DLVER</i>

## MQI names in RPG

<i>Table 46 (Page 9 of 9). Names of fields in structures</i>	
<b>Long name</b>	<b>RPG name</b>
<i>Version (MQDXP)</i>	<i>DXVER</i>
<i>Version (MQCFH)</i>	<i>FHVER</i>
<i>Version (MQGMO)</i>	<i>GMVER</i>
<i>Version (MQIIH)</i>	<i>IIVER</i>
<i>Version (MQMD)</i>	<i>MDVER</i>
<i>Version (MQMDE)</i>	<i>MEVER</i>
<i>Version (MQOD)</i>	<i>ODVER</i>
<i>Version (MQPMO)</i>	<i>PMVER</i>
<i>Version (MQRMH)</i>	<i>RMVER</i>
<i>Version (MQTMC)</i>	<i>TCVER</i>
<i>Version (MQTM)</i>	<i>TMVER</i>
<i>Version (MQXQH)</i>	<i>XQVER</i>
<i>WaitInterval (MQGMO)</i>	<i>GMWI</i>
<i>XmitQName (MQCD)</i>	<i>CDXQ</i>

## Names of constants

<i>Table 47 (Page 1 of 21). Names of constants</i>	
<b>Long name</b>	<b>RPG name</b>
MQ_ABEND_CODE_LENGTH	LNABNC
MQ_ACCOUNTING_TOKEN_LENGTH	LNACCT
MQ_APPL_IDENTITY_DATA_LENGTH	LNAIDD
MQ_APPL_NAME_LENGTH	LNAPPN
MQ_APPL_ORIGIN_DATA_LENGTH	LNAORD
MQ_ATTENTION_ID_LENGTH	LNATID
MQ_AUTHENTICATOR_LENGTH	LNAUTH
MQ_BRIDGE_NAME_LENGTH	LNBRGN
MQ_CANCEL_CODE_LENGTH	LNCNCL
MQ_CHANNEL_DATE_LENGTH	LNCDAT
MQ_CHANNEL_DESC_LENGTH	LNCHD
MQ_CHANNEL_NAME_LENGTH	LNCHN
MQ_CHANNEL_TIME_LENGTH	LNCTIM
MQ_CONN_NAME_LENGTH	LNCONN
MQ_CORREL_ID_LENGTH	LNCID
MQ_CREATION_DATE_LENGTH	LNCRTD
MQ_CREATION_TIME_LENGTH	LNCRTT
MQ_EXIT_DATA_LENGTH	LNEXDA
MQ_EXIT_NAME_LENGTH	LNEXN
MQ_EXIT_USER_AREA_LENGTH	LNEXUA

<i>Table 47 (Page 2 of 21). Names of constants</i>	
<b>Long name</b>	<b>RPG name</b>
MQ_FACILITY_LENGTH	LNFAC
MQ_FACILITY_LIKE_LENGTH	LNFACL
MQ_FORMAT_LENGTH	LNFMFT
MQ_FUNCTION_LENGTH	LNFUNC
MQ_GROUP_ID_LENGTH	LNGID
MQ_LTERM_OVERRIDE_LENGTH	LNLTOV
MQ_LUWID_LENGTH	LNLUWI
MQ_MCA_JOB_NAME_LENGTH	LNMC AJ
MQ_MCA_NAME_LENGTH	LNMCAN
MQ_MFS_MAP_NAME_LENGTH	LNMF MN
MQ_MODE_NAME_LENGTH	LNMODN
MQ_MSG_HEADER_LENGTH	LNMH D
MQ_MSG_ID_LENGTH	LNMI D
MQ_NAMELIST_DESC_LENGTH	LNNL D
MQ_NAMELIST_NAME_LENGTH	LNNL N
MQ_OBJECT_INSTANCE_ID_LENGTH	LNOI D
MQ_PASSWORD_LENGTH	LNPWR D
MQ_PROCESS_APPL_ID_LENGTH	LNPRO A
MQ_PROCESS_DESC_LENGTH	LNPRO D
MQ_PROCESS_ENV_DATA_LENGTH	LNPRO E
MQ_PROCESS_NAME_LENGTH	LNPRON
MQ_PROCESS_USER_DATA_LENGTH	LNPRO U
MQ_PUT_APPL_NAME_LENGTH	LNPAN
MQ_PUT_DATE_LENGTH	LNPDA T
MQ_PUT_TIME_LENGTH	LNPTI M
MQ_Q_DESC_LENGTH	LNQD
MQ_Q_MGR_DESC_LENGTH	LNQMD
MQ_Q_MGR_NAME_LENGTH	LNQM N
MQ_Q_NAME_LENGTH	LNQN
MQ_REMOTE_SYS_ID_LENGTH	LNRSI D
MQ_SHORT_CONN_NAME_LENGTH	LNSCO N
MQ_START_CODE_LENGTH	LNSTC O
MQ_STORAGE_CLASS_LENGTH	LNSTG C
MQ_TOTAL_EXIT_DATA_LENGTH	LNTEX D
MQ_TOTAL_EXIT_NAME_LENGTH	LNTEX N
MQ_TP_NAME_LENGTH	LNTPN
MQ_TRAN_INSTANCE_ID_LENGTH	LNTI D
MQ_TRANSACTION_ID_LENGTH	LNTRI D

<i>Table 47 (Page 3 of 21). Names of constants</i>	
<b>Long name</b>	<b>RPG name</b>
MQ_TRIGGER_DATA_LENGTH	LNTRGD
MQ_USER_ID_LENGTH	LNUID
MQACT_NONE	ACNONE
MQAT_AIX	ATAIX
MQAT_CICS	ATCICS
MQAT_DEFAULT	ATDEF
MQAT_DOS	ATDOS
MQAT_IMS	ATIMS
MQAT_IMS_BRIDGE	ATIMSB
MQAT_MVS	ATMVS
MQAT_NO_CONTEXT	ATNCON
MQAT_OS2	ATOS2
MQAT_OS400	AT400
MQAT_QMGR	ATQM
MQAT_UNIX	ATUNIX
MQAT_UNKNOWN	ATUNK
MQAT_USER_FIRST	ATUFST
MQAT_USER_LAST	ATULST
MQAT_WINDOWS	ATWIN
MQAT_WINDOWS_NT	ATWINT
MQAT_XCF	ATXCF
MQCA_APPL_ID	CAAPPI
MQCA_BACKOUT_REQ_Q_NAME	CABRQN
MQCA_BASE_Q_NAME	CABASQ
MQCA_CHANNEL_AUTO_DEF_EXIT	CACADX
MQCA_COMMAND_INPUT_Q_NAME	CACMDQ
MQCA_CREATION_DATE	CACRTD
MQCA_CREATION_TIME	CACRTT
MQCA_DEAD_LETTER_Q_NAME	CADLQ
MQCA_DEF_XMIT_Q_NAME	CADXQN
MQCA_ENV_DATA	CAENVD
MQCA_FIRST	CAFRST
MQCA_INITIATION_Q_NAME	CAINIQ
MQCA_LAST	CALAST
MQCA_LAST_USED	CALSTU
MQCA_NAMELIST_DESC	CALSTD
MQCA_NAMELIST_NAME	CALSTN
MQCA_NAMES	CANAMS

<i>Table 47 (Page 4 of 21). Names of constants</i>	
<b>Long name</b>	<b>RPG name</b>
MQCA_PROCESS_DESC	CAPROD
MQCA_PROCESS_NAME	CAPRON
MQCA_Q_DESC	CAQD
MQCA_Q_MGR_DESC	CAQMD
MQCA_Q_MGR_NAME	CAQMN
MQCA_Q_NAME	CAQN
MQCA_REMOTE_Q_MGR_NAME	CARQMN
MQCA_REMOTE_Q_NAME	CARQN
MQCA_STORAGE_CLASS	CASTGC
MQCA_TRIGGER_DATA	CATRGD
MQCA_USER_DATA	CAUSRD
MQCA_XMIT_Q_NAME	CAXQN
MQCC_FAILED	CCFAIL
MQCC_OK	CCOK
MQCC_WARNING	CCWARN
MQCCSI_DEFAULT	CSDEF
MQCCSI_EMBEDDED	CSEMBD
MQCCSI_Q_MGR	CSQM
MQCD_CURRENT_VERSION	CDVERC
MQCD_LENGTH_4	CDLEN4
MQCD_VERSION_1	CDVER1
MQCD_VERSION_2	CDVER2
MQCD_VERSION_3	CDVER3
MQCD_VERSION_4	CDVER4
MQCDC_NO_SENDER_CONVERSION	DCNSND
MQCDC_SENDER_CONVERSION	DCSND
MQCF_DIST_LISTS	CFDIST
MQCF_NONE	CFNONE
MQCFC_LAST	CFCLST
MQCFC_NOT_LAST	CFCNOT
MQCFH_CURRENT_VERSION	FHVERC
MQCFH_STRUC_LENGTH	FHLENV
MQCFH_VERSION_1	FHVER1
MQCFIL_STRUC_LENGTH_FIXED	ILLENV
MQCFIN_STRUC_LENGTH	INLENV
MQCFSL_STRUC_LENGTH_FIXED	SLENV
MQCFST_STRUC_LENGTH_FIXED	STLENV
MQCFT_COMMAND	CFTCMD

<i>Table 47 (Page 5 of 21). Names of constants</i>	
<b>Long name</b>	<b>RPG name</b>
MQCFT_EVENT	CFTEVT
MQCFT_INTEGER	CFTINT
MQCFT_INTEGER_LIST	CFTINL
MQCFT_RESPONSE	CFTRSP
MQCFT_STRING	CFTSTR
MQCFT_STRING_LIST	CFTSTL
MQCHAD_DISABLED	CHADDI
MQCHAD_ENABLED	CHADEN
MQCHT_ALL	CTALL
MQCHT_CLNTCONN	CTCLCN
MQCHT_RECEIVER	CTRCVR
MQCHT_REQUESTER	CTREQR
MQCHT_SENDER	CTSEND
MQCHT_SERVER	CTSERV
MQCHT_SVRCONN	CTSVCN
MQCI_NEW_SESSION	CINEWS
MQCI_NONE	CINONE
MQCMD_CHANGE_CHANNEL	CMCHCH
MQCMD_CHANGE_PROCESS	CMCHPR
MQCMD_CHANGE_Q	CMCHQ
MQCMD_CHANGE_Q_MGR	CMCHQM
MQCMD_CHANNEL_EVENT	CMCHEV
MQCMD_CLEAR_Q	CMCLQ
MQCMD_COPY_CHANNEL	CMCPCH
MQCMD_COPY_PROCESS	CMCPPR
MQCMD_COPY_Q	CMCPQ
MQCMD_CREATE_CHANNEL	CMCRCH
MQCMD_CREATE_PROCESS	CMCRPR
MQCMD_CREATE_Q	CMCRQ
MQCMD_DELETE_CHANNEL	CMDLCH
MQCMD_DELETE_PROCESS	CMDLPR
MQCMD_DELETE_Q	CMDLQ
MQCMD_ESCAPE	CMESC
MQCMD_INQUIRE_CHANNEL	CMINCH
MQCMD_INQUIRE_CHANNEL_NAMES	CMINCN
MQCMD_INQUIRE_CHANNEL_STATUS	CMINCS
MQCMD_INQUIRE_PROCESS	CMINPR
MQCMD_INQUIRE_PROCESS_NAMES	CMINPN

<i>Table 47 (Page 6 of 21). Names of constants</i>	
<b>Long name</b>	<b>RPG name</b>
MQCMD_INQUIRE_Q	CMINQ
MQCMD_INQUIRE_Q_MGR	CMINQM
MQCMD_INQUIRE_Q_NAMES	CMINQN
MQCMD_PERFM_EVENT	CMPFEV
MQCMD_PING_CHANNEL	CMPNCH
MQCMD_PING_Q_MGR	CMPNQM
MQCMD_Q_MGR_EVENT	CMQMEV
MQCMD_RESET_CHANNEL	CMRSCH
MQCMD_RESET_Q_STATS	CMRSQS
MQCMD_RESOLVE_CHANNEL	CMRVCH
MQCMD_START_CHANNEL	CMSTCH
MQCMD_START_CHANNEL_INIT	CMSTCI
MQCMD_START_CHANNEL_LISTENER	CMSTCL
MQCMD_STOP_CHANNEL	CMSPCH
MQCMDL_LEVEL_1	CMLVL1
MQCMDL_LEVEL_101	CML101
MQCMDL_LEVEL_110	CML101
MQCMDL_LEVEL_114	CML114
MQCMDL_LEVEL_120	CML120
MQCMDL_LEVEL_200	CML200
MQCMDL_LEVEL_201	CML201
MQCMDL_LEVEL_221	CML221
MQCMDL_LEVEL_230	CML230
MQCMDL_LEVEL_320	CML320
MQCMDL_LEVEL_500	CML500
MQCMDL_LEVEL_510	CML510
MQCO_DELETE	CODEL
MQCO_DELETE_PURGE	COPURG
MQCO_NONE	CONONE
MQCXP_CURRENT_VERSION	CXVERC
MQCXP_STRUC_ID	CXSIDV
MQCXP_VERSION_1	CXVER1
MQCXP_VERSION_2	CXVER2
MQCXP_VERSION_3	CXVER3
MQDCC_DEFAULT_CONVERSION	DCCDEF
MQDCC_NONE	DCCNON
MQDCC_SOURCE_ENC_FACTOR	DCCSFA
MQDCC_SOURCE_ENC_MASK	DCCSMA

<i>Table 47 (Page 7 of 21). Names of constants</i>	
<b>Long name</b>	<b>RPG name</b>
MQDCC_SOURCE_ENC_NATIVE	DCCSNA
MQDCC_SOURCE_ENC_NORMAL	DCCSNO
MQDCC_SOURCE_ENC_REVERSED	DCCSRE
MQDCC_SOURCE_ENC_UNDEFINED	DCCSUN
MQDCC_TARGET_ENC_FACTOR	DCCTFA
MQDCC_TARGET_ENC_MASK	DCCTMA
MQDCC_TARGET_ENC_NATIVE	DCCTNA
MQDCC_TARGET_ENC_NORMAL	DCCTNO
MQDCC_TARGET_ENC_REVERSED	DCCTRE
MQDCC_TARGET_ENC_UNDEFINED	DCCTUN
MQDH_CURRENT_VERSION	DHVERC
MQDH_STRUC_ID	DHSIDV
MQDH_VERSION_1	DHVER1
MQDHF_NEW_MSG_IDS	DHFNEW
MQDHF_NONE	DHFNON
MQDL_NOT_SUPPORTED	DLNSUP
MQDL_SUPPORTED	DLSUPP
MQDLH_CURRENT_VERSION	DLVERC
MQDLH_STRUC_ID	DLSIDV
MQDLH_VERSION_1	DLVER1
MQDXP_CURRENT_VERSION	DXVERC
MQDXP_STRUC_ID	DXSIDV
MQDXP_VERSION_1	DXVER1
MQEI_UNLIMITED	EIULIM
MQENC_DECIMAL_MASK	ENDMSK
MQENC_DECIMAL_NORMAL	ENDNOR
MQENC_DECIMAL_REVERSED	ENDREV
MQENC_DECIMAL_UNDEFINED	ENDUND
MQENC_FLOAT_IEEE_NORMAL	ENFNOR
MQENC_FLOAT_IEEE_REVERSED	ENFREV
MQENC_FLOAT_MASK	ENFMSK
MQENC_FLOAT_S390	ENF390
MQENC_FLOAT_UNDEFINED	ENFUND
MQENC_INTEGER_MASK	ENIMSK
MQENC_INTEGER_NORMAL	ENINOR
MQENC_INTEGER_REVERSED	ENIREV
MQENC_INTEGER_UNDEFINED	ENIUND
MQENC_NATIVE	ENNAT

<i>Table 47 (Page 8 of 21). Names of constants</i>	
<b>Long name</b>	<b>RPG name</b>
MQENC_RESERVED_MASK	ENRMSK
MQEVR_DISABLED	EVRDIS
MQEVR_ENABLED	EVRENA
MQFB_	FB
MQFB_APPL_CANNOT_BE_STARTED	FBABEG
MQFB_APPL_FIRST	FBAFST
MQFB_APPL_LAST	FBALST
MQFB_APPL_TYPE_ERROR	FBATYP
MQFB_BUFFER_OVERFLOW	FBBUFO
MQFB_COA	FBCOA
MQFB_COD	FBCOD
MQFB_DATA_LENGTH_NEGATIVE	FBDLN
MQFB_DATA_LENGTH_TOO_BIG	FBDLTB
MQFB_DATA_LENGTH_ZERO	FBDLZ
MQFB_EXPIRATION	FBEXP
MQFB_IIH_ERROR	FBIIH
MQFB_IMS_ERROR	FBIERR
MQFB_IMS_FIRST	FBIFST
MQFB_IMS_LAST	FBILST
MQFB_LENGTH_OFF_BY_ONE	FBLOB1
MQFB_NAN	FBNAN
MQFB_NONE	FBNONE
MQFB_NOT_AUTHORIZED_FOR_IMS	FBNAFI
MQFB_PAN	FBPAN
MQFB_QUIT	FBQUIT
MQFB_STOPPED_BY_MSG_EXIT	FBSBMX
MQFB_SYSTEM_FIRST	FBSFST
MQFB_SYSTEM_LAST	FBSLST
MQFB_TM_ERROR	FBTM
MQFB_XMIT_Q_MSG_ERROR	FBXQME
MQFMT_ADMIN	FMADMN
MQFMT_COMMAND_1	FMCMD1
MQFMT_COMMAND_2	FMCMD2
MQFMT_DEAD_LETTER_HEADER	FMDLH
MQFMT_DIST_HEADER	FMDH
MQFMT_EVENT	FMEVNT
MQFMT_IMS	FMIMS
MQFMT_IMS_VAR_STRING	FMIMVS

*Table 47 (Page 9 of 21). Names of constants*

<b>Long name</b>	<b>RPG name</b>
MQFMT_MD_EXTENSION	FMMDE
MQFMT_NONE	FMNONE
MQFMT_PCF	FMPCF
MQFMT_REF_MSG_HEADER	FMRMH
MQFMT_STRING	FMSTR
MQFMT_TRIGGER	FMTM
MQFMT_XMIT_Q_HEADER	FMXQH
MQGI_NONE	GINONE
MQGMO_ACCEPT_TRUNCATED_MSG	GMATM
MQGMO_ALL_MSGS_AVAILABLE	GMAMSA
MQGMO_ALL_SEGMENTS_AVAILABLE	GMASGA
MQGMO_BROWSE_FIRST	GMBRWF
MQGMO_BROWSE_MSG_UNDER_CURSOR	GMBRWC
MQGMO_BROWSE_NEXT	GMBRWN
MQGMO_COMPLETE_MSG	GMCMPM
MQGMO_CONVERT	GMCONV
MQGMO_CURRENT_VERSION	GMVERC
MQGMO_FAIL_IF QUIESCING	GMFIQ
MQGMO_LOCK	GMLK
MQGMO_LOGICAL_ORDER	GMLOGO
MQGMO_MSG_UNDER_CURSOR	GMMUC
MQGMO_NO_SYNCPOINT	GMNSYP
MQGMO_NO_WAIT	GMNWT
MQGMO_NONE	GMNONE
MQGMO_STRUC_ID	GMSIDV
MQGMO_SYNCPOINT	GMSYP
MQGMO_SYNCPOINT_IF_PERSISTENT	GMPSYP
MQGMO_UNLOCK	GMUNLK
MQGMO_VERSION_1	GMVER1
MQGMO_VERSION_2	GMVER2
MQGMO_WAIT	GMWT
MQGS_LAST_MSG_IN_GROUP	GSLMIG
MQGS_MSG_IN_GROUP	GSMIG
MQGS_NOT_IN_GROUP	GSNIG
MQHC_DEF_HCONN	HCDEFH
MQHC_UNUSABLE_HCONN	HCUNUH
MQHO_UNUSABLE_HOBJ	HOUNUH
MQIA_APPL_TYPE	IAAPPT

<i>Table 47 (Page 10 of 21). Names of constants</i>	
<b>Long name</b>	<b>RPG name</b>
MQIA_AUTHORITY_EVENT	IAAUTE
MQIA_BACKOUT_THRESHOLD	IABTHR
MQIA_CHANNEL_AUTO_DEF	IACAD
MQIA_CHANNEL_AUTO_DEF_EVENT	IACADE
MQIA_CODED_CHAR_SET_ID	IACCSI
MQIA_COMMAND_LEVEL	IACMDL
MQIA_CURRENT_Q_DEPTH	IACDEP
MQIA_DEF_INPUT_OPEN_OPTION	IADINP
MQIA_DEF_PERSISTENCE	IADPER
MQIA_DEF_PRIORITY	IADPRI
MQIA_DEFINITION_TYPE	IADEFT
MQIA_DIST_LISTS	IADIST
MQIA_FIRST	IAFRST
MQIA_HARDEN_GET_BACKOUT	IAHGB
MQIA_HIGH_Q_DEPTH	IAHQD
MQIA_INDEX_TYPE	IAINDT
MQIA_INHIBIT_EVENT	IAINHE
MQIA_INHIBIT_GET	IAIGET
MQIA_INHIBIT_PUT	IAIPUT
MQIA_LAST	IALAST
MQIA_LAST_USED	IALSTU
MQIA_LOCAL_EVENT	IALCLE
MQIA_MAX_HANDLES	IAMHND
MQIA_MAX_MSG_LENGTH	IAMLEN
MQIA_MAX_PRIORITY	IAMPRI
MQIA_MAX_Q_DEPTH	IAMDEP
MQIA_MAX_UNCOMMITTED_MSGS	IAMUNC
MQIA_MSG_DELIVERY_SEQUENCE	IAMDS
MQIA_MSG_DEQ_COUNT	IAMDC
MQIA_MSG_ENQ_COUNT	IAMEC
MQIA_NAME_COUNT	IANAMC
MQIA_OPEN_INPUT_COUNT	IAOIC
MQIA_OPEN_OUTPUT_COUNT	IAOOC
MQIA_PERFORMANCE_EVENT	IAPFME
MQIA_PLATFORM	IAPLAT
MQIA_Q_DEPTH_HIGH_EVENT	IAQDHE
MQIA_Q_DEPTH_HIGH_LIMIT	IAQDHL
MQIA_Q_DEPTH_LOW_EVENT	IAQDLE

<i>Table 47 (Page 11 of 21). Names of constants</i>	
<b>Long name</b>	<b>RPG name</b>
MQIA_Q_DEPTH_LOW_LIMIT	IAQDLL
MQIA_Q_DEPTH_MAX_EVENT	IAQDME
MQIA_Q_SERVICE_INTERVAL	IAQSI
MQIA_Q_SERVICE_INTERVAL_EVENT	IAQSIE
MQIA_Q_TYPE	IAQTYP
MQIA_REMOTE_EVENT	IARMTE
MQIA_RETENTION_INTERVAL	IARINT
MQIA_SCOPE	IASCOP
MQIA_SHAREABILITY	IASHAR
MQIA_START_STOP_EVENT	IASSE
MQIA_SYNCPOINT	IASYNC
MQIA_TIME_SINCE_RESET	IATSR
MQIA_TRIGGER_CONTROL	IATRGC
MQIA_TRIGGER_DEPTH	IATRGD
MQIA_TRIGGER_INTERVAL	IATRGI
MQIA_TRIGGER_MSG_PRIORITY	IATRGP
MQIA_TRIGGER_TYPE	IATRGT
MQIA_USAGE	IAUSAG
MQIAUT_NONE	IAUNON
MQIAV_NOT_APPLICABLE	IAVNA
MQIAV_UNDEFINED	IAVUND
MQICM_COMMIT_THEN_SEND	ICMCTS
MQICM_SEND_THEN_COMMIT	ICMSTC
MQIIH_CURRENT_VERSION	IIVERC
MQIIH_LENGTH_1	IILEN1
MQIIH_NONE	IINONE
MQIIH_STRUC_ID	IISIDV
MQIIH_VERSION_1	IIVER1
MQISS_CHECK	ISSCHK
MQISS_FULL	ISSFUL
MQIT_CORREL_ID	ITCORI
MQIT_MSG_ID	ITMSGI
MQIT_NONE	ITNONE
MQITII_NONE	ITINON
MQITS_IN_CONVERSATION	ITSIC
MQITS_NOT_IN_CONVERSATION	ITSNIC
MQMCAT_PROCESS	MCPROC
MQMCAT_THREAD	MCTHRD

<i>Table 47 (Page 12 of 21). Names of constants</i>	
<b>Long name</b>	<b>RPG name</b>
MQMD_CURRENT_VERSION	MDVERC
MQMD_STRUC_ID	MDSIDV
MQMD_VERSION_1	MDVER1
MQMD_VERSION_2	MDVER2
MQMDE_CURRENT_VERSION	MEVERC
MQMDE_LENGTH_2	MELEN2
MQMDE_STRUC_ID	MESIDV
MQMDE_VERSION_2	MEVER2
MQMDEF_NONE	MEFNON
MQMDS_FIFO	MSFIFO
MQMDS_PRIORITY	MSPRIO
MQMF_ACCEPT_UNSUP_IF_XMIT_MASK	MFAUXM
MQMF_ACCEPT_UNSUP_MASK	MFAUM
MQMF_LAST_MSG_IN_GROUP	MFLMIG
MQMF_LAST_SEGMENT	MFLSEG
MQMF_MSG_IN_GROUP	MFMIG
MQMF_NONE	MFNONE
MQMF_REJECT_UNSUP_MASK	MFRUM
MQMF_SEGMENT	MFSEG
MQMF_SEGMENTATION_ALLOWED	MFSEGA
MQMF_SEGMENTATION_INHIBITED	MFSEGI
MQMI_NONE	MINONE
MQMO_MATCH_CORREL_ID	MOCORI
MQMO_MATCH_GROUP_ID	MOGRPI
MQMO_MATCH_MSG_ID	MOMSGI
MQMO_MATCH_MSG_SEQ_NUMBER	MOSEQN
MQMO_MATCH_OFFSET	MOOFFS
MQMO_NONE	MONONE
MQMT_APPL_FIRST	MTAFST
MQMT_APPL_LAST	MTALST
MQMT_DATAGRAM	MTDGRM
MQMT_REPLY	MTRPLY
MQMT_REPORT	MTRPRT
MQMT_REQUEST	MTRQST
MQMT_SYSTEM_FIRST	MTSFST
MQMT_SYSTEM_LAST	MTSLST
MQNPMS_FAST	NPFAST
MQNPMS_NORMAL	NPNORM

<i>Table 47 (Page 13 of 21). Names of constants</i>	
<b>Long name</b>	<b>RPG name</b>
MQOD_CURRENT_LENGTH	ODLENC
MQOD_CURRENT_VERSION	ODVERC
MQOD_STRUC_ID	ODSIDV
MQOD_VERSION_1	ODVER1
MQOD_VERSION_2	ODVER2
MQOII_NONE	OIINON
MQOL_UNDEFINED	OLUNDF
MQOO_ALTERNATE_USER_AUTHORITY	OOALTU
MQOO_BROWSE	OBRW
MQOO_FAIL_IF QUIESCING	OOFIQ
MQOO_INPUT_AS_Q_DEF	OINPQ
MQOO_INPUT_EXCLUSIVE	OINPX
MQOO_INPUT_SHARED	OINPS
MQOO_INQUIRE	OINQ
MQOO_OUTPUT	OOUT
MQOO_PASS_ALL_CONTEXT	OOPASA
MQOO_PASS_IDENTITY_CONTEXT	OOPASI
MQOO_SAVE_ALL_CONTEXT	OOSAVA
MQOO_SET	OSET
MQOO_SET_ALL_CONTEXT	OSETA
MQOO_SET_IDENTITY_CONTEXT	OSETI
MQOT_PROCESS	OTPRO
MQOT_Q	OTQ
MQOT_Q_MGR	OTQM
MQPA_CONTEXT	PACTXT
MQPA_DEFAULT	PADEF
MQPER_NOT_PERSISTENT	PENPER
MQPER_PERSISTENCE_AS_Q_DEF	PEQDEF
MQPER_PERSISTENT	PEPER
MQPL_AIX	PLAIX
MQPL_MVS	PLMVS
MQPL_OS2	PLOS2
MQPL_OS400	PL400
MQPL_UNIX	PLUNIX
MQPL_WINDOWS	PLWIN
MQPL_WINDOWS_NT	PLWINT
MQPMO_ALTERNATE_USER_AUTHORITY	PMALTU
MQPMO_CURRENT_LENGTH	PMLENC

<i>Table 47 (Page 14 of 21). Names of constants</i>	
<b>Long name</b>	<b>RPG name</b>
MQPMO_CURRENT_VERSION	PMVERC
MQPMO_DEFAULT_CONTEXT	PMDEFC
MQPMO_FAIL_IF QUIESCING	PMFIQ
MQPMO_LOGICAL_ORDER	PMLOGO
MQPMO_NEW_CORREL_ID	PMNCID
MQPMO_NEW_MSG_ID	PMNMID
MQPMO_NO_CONTEXT	PMNOC
MQPMO_NO_SYNCPOINT	PMNSYP
MQPMO_NONE	PMNONE
MQPMO_PASS_ALL_CONTEXT	PMPASA
MQPMO_PASS_IDENTITY_CONTEXT	PMPASI
MQPMO_SET_ALL_CONTEXT	PMSETA
MQPMO_SET_IDENTITY_CONTEXT	PMSETI
MQPMO_STRUC_ID	PMSIDV
MQPMO_SYNCPOINT	PMSYP
MQPMO_VERSION_1	PMVER1
MQPMO_VERSION_2	PMVER2
MQPMRF_ACCOUNTING_TOKEN	PFACC
MQPMRF_CORREL_ID	PFCID
MQPMRF_FEEDBACK	PFFB
MQPMRF_GROUP_ID	PFGID
MQPMRF_MSG_ID	PFMID
MQPMRF_NONE	PFNONE
MQPRI_PRIORITY_AS_Q_DEF	PRQDEF
MQQA_BACKOUT_HARDENED	QABH
MQQA_BACKOUT_NOT_HARDENED	QABNH
MQQA_GET_ALLOWED	QAGETA
MQQA_GET_INHIBITED	QAGETI
MQQA_NOT_SHAREABLE	QANSHR
MQQA_PUT_ALLOWED	QAPUTA
MQQA_PUT_INHIBITED	QAPUTI
MQQA_SHAREABLE	QASHR
MQQDT_PERMANENT_DYNAMIC	QDPERM
MQQDT_PREDEFINED	QDPRE
MQQDT_TEMPORARY_DYNAMIC	QDTEMP
MQQSIE_HIGH	QSIEHI
MQQSIE_NONE	QSIENO
MQQSIE_OK	QSIEOK

<i>Table 47 (Page 15 of 21). Names of constants</i>	
<b>Long name</b>	<b>RPG name</b>
MQQT_ALIAS	QTALS
MQQT_LOCAL	QTLOC
MQQT_MODEL	QTMOD
MQQT_REMOTE	QTREM
MQRC_ALIAS_BASE_Q_TYPE_ERROR	RC2001
MQRC_ALREADY_CONNECTED	RC2002
MQRC_BRIDGE_STARTED	RC2125
MQRC_BRIDGE_STOPPED	RC2126
MQRC_BUFFER_ERROR	RC2004
MQRC_BUFFER_LENGTH_ERROR	RC2005
MQRC_CALL_IN_PROGRESS	RC2219
MQRC_CFH_ERROR	RC2235
MQRC_CFIL_ERROR	RC2236
MQRC_CFIN_ERROR	RC2237
MQRC_CFSL_ERROR	RC2238
MQRC_CFST_ERROR	RC2239
MQRC_CHANNEL_ACTIVATED	RC2295
MQRC_CHANNEL_AUTO_DEF_ERROR	RC2234
MQRC_CHANNEL_AUTO_DEF_OK	RC2233
MQRC_CHANNEL_CONV_ERROR	RC2284
MQRC_CHANNEL_NOT_ACTIVATED	RC2296
MQRC_CHANNEL_STARTED	RC2282
MQRC_CHANNEL_STOPPED	RC2283
MQRC_CHAR_ATTR_LENGTH_ERROR	RC2006
MQRC_CHAR_ATTRS_ERROR	RC2007
MQRC_CHAR_ATTRS_TOO_SHORT	RC2008
MQRC_CICS_BRIDGE_RESTRICTION	RC2187
MQRC_CONNECTION_BROKEN	RC2009
MQRC_CONTEXT_HANDLE_ERROR	RC2097
MQRC_CONTEXT_NOT_AVAILABLE	RC2098
MQRC_CONVERTED_MSG_TOO_BIG	RC2120
MQRC_DATA_LENGTH_ERROR	RC2010
MQRC_DBCS_ERROR	RC2150
MQRC_DEF_XMIT_Q_TYPE_ERROR	RC2198
MQRC_DEF_XMIT_Q_USAGE_ERROR	RC2199
MQRC_DEST_ENV_ERROR	RC2263
MQRC_DEST_NAME_ERROR	RC2264
MQRC_DH_ERROR	RC2135

<i>Table 47 (Page 16 of 21). Names of constants</i>	
<b>Long name</b>	<b>RPG name</b>
MQRC_DLH_ERROR	RC2141
MQRC_DYNAMIC_Q_NAME_ERROR	RC2011
MQRC_EXPIRY_ERROR	RC2013
MQRC_FEEDBACK_ERROR	RC2014
MQRC_FORMAT_ERROR	RC2110
MQRC_GET_INHIBITED	RC2016
MQRC_GMO_ERROR	RC2186
MQRC_GROUP_ID_ERROR	RC2258
MQRC_HANDLE_NOT_AVAILABLE	RC2017
MQRC_HCONN_ERROR	RC2018
MQRC_HEADER_ERROR	RC2142
MQRC_HOBJ_ERROR	RC2019
MQRC_IIH_ERROR	RC2148
MQRC_INCOMPLETE_GROUP	RC2241
MQRC_INCOMPLETE_MSG	RC2242
MQRC_INCONSISTENT_BROWSE	RC2259
MQRC_INCONSISTENT_CCSIDS	RC2243
MQRC_INCONSISTENT_ENCODINGS	RC2244
MQRC_INCONSISTENT_PERSISTENCE	RC2185
MQRC_INCONSISTENT_UOW	RC2245
MQRC_INHIBIT_VALUE_ERROR	RC2020
MQRC_INT_ATTR_COUNT_ERROR	RC2021
MQRC_INT_ATTR_COUNT_TOO_SMALL	RC2022
MQRC_INT_ATTRS_ARRAY_ERROR	RC2023
MQRC_INVALID_MSG_UNDER_CURSOR	RC2246
MQRC_MATCH_OPTIONS_ERROR	RC2247
MQRC_MD_ERROR	RC2026
MQRC_MDE_ERROR	RC2248
MQRC_MISSING_REPLY_TO_Q	RC2027
MQRC_MSG_FLAGS_ERROR	RC2249
MQRC_MSG_SEQ_NUMBER_ERROR	RC2250
MQRC_MSG_TOO_BIG_FOR_CHANNEL	RC2218
MQRC_MSG_TOO_BIG_FOR_Q	RC2030
MQRC_MSG_TOO_BIG_FOR_Q_MGR	RC2031
MQRC_MSG_TYPE_ERROR	RC2029
MQRC_MULTIPLE_REASONS	RC2136
MQRC_NAME_NOT_VALID_FOR_TYPE	RC2194
MQRC_NO_EXTERNAL_PARTICIPANTS	RC2121

<i>Table 47 (Page 17 of 21). Names of constants</i>	
<b>Long name</b>	<b>RPG name</b>
MQRC_NO_MSG_AVAILABLE	RC2033
MQRC_NO_MSG_LOCKED	RC2209
MQRC_NO_MSG_UNDER_CURSOR	RC2034
MQRC_NONE	RCNONE
MQRC_NOT_AUTHORIZED	RC2035
MQRC_NOT_CONVERTED	RC2119
MQRC_NOT_OPEN_FOR_BROWSE	RC2036
MQRC_NOT_OPEN_FOR_INPUT	RC2037
MQRC_NOT_OPEN_FOR_INQUIRE	RC2038
MQRC_NOT_OPEN_FOR_OUTPUT	RC2039
MQRC_NOT_OPEN_FOR_PASS_ALL	RC2093
MQRC_NOT_OPEN_FOR_PASS_IDENT	RC2094
MQRC_NOT_OPEN_FOR_SET	RC2040
MQRC_NOT_OPEN_FOR_SET_ALL	RC2095
MQRC_NOT_OPEN_FOR_SET_IDENT	RC2096
MQRC_OBJECT_ALREADY_EXISTS	RC2100
MQRC_OBJECT_CHANGED	RC2041
MQRC_OBJECT_DAMAGED	RC2101
MQRC_OBJECT_IN_USE	RC2042
MQRC_OBJECT_NAME_ERROR	RC2152
MQRC_OBJECT_Q_MGR_NAME_ERROR	RC2153
MQRC_OBJECT_RECORDS_ERROR	RC2155
MQRC_OBJECT_TYPE_ERROR	RC2043
MQRC_OD_ERROR	RC2044
MQRC_OFFSET_ERROR	RC2251
MQRC_OPEN_FAILED	RC2137
MQRC_OPTION_NOT_VALID_FOR_TYPE	RC2045
MQRC_OPTIONS_ERROR	RC2046
MQRC_ORIGINAL_LENGTH_ERROR	RC2252
MQRC_OUTCOME_MIXED	RC2123
MQRC_OUTCOME_PENDING	RC2124
MQRC_PARTICIPANT_NOT_AVAILABLE	RC2122
MQRC_PCF_ERROR	RC2149
MQRC_PERSISTENCE_ERROR	RC2047
MQRC_PERSISTENT_NOT_ALLOWED	RC2048
MQRC_PMO_ERROR	RC2173
MQRC_PMO_RECORD_FLAGS_ERROR	RC2158
MQRC_PRIORITY_ERROR	RC2050

<i>Table 47 (Page 18 of 21). Names of constants</i>	
<b>Long name</b>	<b>RPG name</b>
MQRC_PRIORITY_EXCEEDS_MAXIMUM	RC2049
MQRC_PUT_INHIBITED	RC2051
MQRC_PUT_MSG_RECORDS_ERROR	RC2159
MQRC_Q_DELETED	RC2052
MQRC_Q_DEPTH_HIGH	RC2224
MQRC_Q_DEPTH_LOW	RC2225
MQRC_Q_FULL	RC2053
MQRC_Q_MGR_ACTIVE	RC2222
MQRC_Q_MGR_NAME_ERROR	RC2058
MQRC_Q_MGR_NOT_ACTIVE	RC2223
MQRC_Q_MGR_NOT_AVAILABLE	RC2059
MQRC_Q_MGR QUIESCING	RC2161
MQRC_Q_MGR_STOPPING	RC2162
MQRC_Q_NOT_EMPTY	RC2055
MQRC_Q_SERVICE_INTERVAL_HIGH	RC2226
MQRC_Q_SERVICE_INTERVAL_OK	RC2227
MQRC_Q_SPACE_NOT_AVAILABLE	RC2056
MQRC_Q_TYPE_ERROR	RC2057
MQRC_RECS_PRESENT_ERROR	RC2154
MQRC_REMOTE_Q_NAME_ERROR	RC2184
MQRC_REPORT_OPTIONS_ERROR	RC2061
MQRC_RESOURCE_PROBLEM	RC2102
MQRC_RESPONSE_RECORDS_ERROR	RC2156
MQRC_RMH_ERROR	RC2220
MQRC_SECURITY_ERROR	RC2063
MQRC_SEGMENT_LENGTH_ZERO	RC2253
MQRC_SELECTOR_COUNT_ERROR	RC2065
MQRC_SELECTOR_ERROR	RC2067
MQRC_SELECTOR_LIMIT_EXCEEDED	RC2066
MQRC_SELECTOR_NOT_FOR_TYPE	RC2068
MQRC_SOURCE_BUFFER_ERROR	RC2145
MQRC_SOURCE_CCSID_ERROR	RC2111
MQRC_SOURCE_DECIMAL_ENC_ERROR	RC2113
MQRC_SOURCE_FLOAT_ENC_ERROR	RC2114
MQRC_SOURCE_INTEGER_ENC_ERROR	RC2112
MQRC_SOURCE_LENGTH_ERROR	RC2143
MQRC_SRC_ENV_ERROR	RC2261
MQRC_SRC_NAME_ERROR	RC2262

<i>Table 47 (Page 19 of 21). Names of constants</i>	
<b>Long name</b>	<b>RPG name</b>
MQRC_STORAGE_NOT_AVAILABLE	RC2071
MQRC_SYNCPOINT_LIMIT_REACHED	RC2024
MQRC_SYNCPOINT_NOT_AVAILABLE	RC2072
MQRC_TARGET_BUFFER_ERROR	RC2146
MQRC_TARGET_CCSDID_ERROR	RC2115
MQRC_TARGET_DECIMAL_ENC_ERROR	RC2117
MQRC_TARGET_FLOAT_ENC_ERROR	RC2118
MQRC_TARGET_INTEGER_ENC_ERROR	RC2116
MQRC_TARGET_LENGTH_ERROR	RC2144
MQRC_TM_ERROR	RC2265
MQRC_TMC_ERROR	RC2191
MQRC_TRIGGER_CONTROL_ERROR	RC2075
MQRC_TRIGGER_DEPTH_ERROR	RC2076
MQRC_TRIGGER_MSG_PRIORITY_ERR	RC2077
MQRC_TRIGGER_TYPE_ERROR	RC2078
MQRC_TRUNCATED_MSG_ACCEPTED	RC2079
MQRC_TRUNCATED_MSG_FAILED	RC2080
MQRC_UNEXPECTED_ERROR	RC2195
MQRC_UNKNOWN_ALIAS_BASE_Q	RC2082
MQRC_UNKNOWN_DEF_XMIT_Q	RC2197
MQRC_UNKNOWN_OBJECT_NAME	RC2085
MQRC_UNKNOWN_OBJECT_Q_MGR	RC2086
MQRC_UNKNOWN_REMOTE_Q_MGR	RC2087
MQRC_UNKNOWN_REPORT_OPTION	RC2104
MQRC_UNKNOWN_XMIT_Q	RC2196
MQRC_UOW_IN_PROGRESS	RC2128
MQRC_UOW_NOT_AVAILABLE	RC2255
MQRC_WAIT_INTERVAL_ERROR	RC2090
MQRC_WRONG_GMO_VERSION	RC2256
MQRC_WRONG_MD_VERSION	RC2257
MQRC_XMIT_Q_TYPE_ERROR	RC2091
MQRC_XMIT_Q_USAGE_ERROR	RC2092
MQRC_XQH_ERROR	RC2260
MQRMH_CURRENT_VERSION	RMVERC
MQRMH_STRUC_ID	RMSIDV
MQRMH_VERSION_1	RMVER1
MQRMHF_LAST	RMLAST
MQRMHF_NOT_LAST	RMNLST

<i>Table 47 (Page 20 of 21). Names of constants</i>	
<b>Long name</b>	<b>RPG name</b>
MQRO_ACCEPT_UNSUP_IF_XMIT_MASK	ROAUXM
MQRO_ACCEPT_UNSUP_MASK	ROAUM
MQRO_COA	ROCOA
MQRO_COA_WITH_DATA	ROCOAD
MQRO_COA_WITH_FULL_DATA	ROCOAF
MQRO_COD	ROCOD
MQRO_COD_WITH_DATA	ROCODD
MQRO_COD_WITH_FULL_DATA	ROCODF
MQRO_COPY_MSG_ID_TO_CORREL_ID	ROCMTC
MQRO_DEAD_LETTER_Q	RODLQ
MQRO_DISCARD_MSG	RODISC
MQRO_EXCEPTION	ROEXC
MQRO_EXCEPTION_WITH_DATA	ROEXCD
MQRO_EXCEPTION_WITH_FULL_DATA	ROEXCF
MQRO_EXPIRATION	ROEXP
MQRO_EXPIRATION_WITH_DATA	ROEXPD
MQRO_EXPIRATION_WITH_FULL_DATA	ROEXPF
MQRO_NAN	RONAN
MQRO_NEW_MSG_ID	RONMI
MQRO_NONE	RONONE
MQRO_PAN	ROPAN
MQRO_PASS_CORREL_ID	ROPCI
MQRO_PASS_MSG_ID	ROPMI
MQRO_REJECT_UNSUP_MASK	RORUM
MQSEG_ALLOWED	SEGALW
MQSEG_INHIBITED	SEGIHB
MQSP_AVAILABLE	SPAVL
MQSP_NOT_AVAILABLE	SPNAVL
MQSS_LAST_SEGMENT	SSLSEG
MQSS_NOT_A_SEGMENT	SSNSEG
MQSS_SEGMENT	SSSEG
MQTC_OFF	TCOFF
MQTC_ON	TCON
MQTM_CURRENT_VERSION	TMVERC
MQTM_STRUC_ID	TMSIDV
MQTM_VERSION_1	TMVER1
MQTMC_STRUC_ID	TCSIDV
MQTMC_VERSION_1	TCVER1

<i>Table 47 (Page 21 of 21). Names of constants</i>	
<b>Long name</b>	<b>RPG name</b>
MQTT_DEPTH	TTDPTH
MQTT_EVERY	TTEVRY
MQTT_FIRST	TTFRST
MQTT_NONE	TTNONE
MQUS_NORMAL	USNORM
MQUS_TRANSMISSION	USTRAN
MQWI_UNLIMITED	WIULIM
MQXCC_CLOSE_CHANNEL	XCCLSC
MQXCC_OK	XCOK
MQXCC_SEND_AND_REQUEST_SEC_MSG	XCREQS
MQXCC_SEND_SEC_MSG	XCSNDS
MQXCC_SUPPRESS_EXIT	XCSUPE
MQXCC_SUPPRESS_FUNCTION	XCSUPF
MQXDR_CONVERSION_FAILED	XRFAIL
MQXDR_OK	XROK
MQXPT_LU62	XTLU62
MQXPT_NETBIOS	XTNET
MQXPT_SPX	XTSPX
MQXPT_TCP	XTTCP
MQXQH_CURRENT_VERSION	XQVERC
MQXQH_STRUC_ID	XQSIDV
MQXQH_VERSION_1	XQVER1
MQXR2_CONTINUE_CHAIN	X2CONC
MQXR2_DEFAULT_CONTINUATION	X2DEFC
MQXR2_PUT_WITH_DEF_ACTION	X2PDA
MQXR2_PUT_WITH_DEF_USERID	X2PDU
MQXR2_PUT_WITH_MSG_USERID	X2PMU
MQXR2_SUPPRESS_CHAIN	X2SUPC
MQXR2_USE_AGENT_BUFFER	X2UAB
MQXR2_USE_EXIT_BUFFER	X2UXB
MQXT_CHANNEL_MSG_EXIT	XTCMSG
MQXT_CHANNEL_MSG_RETRY_EXIT	XTCMR
MQXT_CHANNEL_RCV_EXIT	XTCRCV
MQXT_CHANNEL_SEC_EXIT	XTCSEC
MQXT_CHANNEL_SEND_EXIT	XTCSND
MQXUA_NONE	XUNONE

---

## Appendix C. C language examples

The extracts in this appendix are mostly taken from the MQSeries for OS/390 sample applications. They are applicable to all platforms, and any exception to this is noted.

The examples in this appendix demonstrate the following techniques:

Connecting to a queue manager	Figure 53 on page 488
Disconnecting from a queue manager	Figure 54 on page 488
Creating a dynamic queue	Figure 55 on page 489
Opening an existing queue	Figure 56 on page 489
Closing a queue	Figure 57 on page 490
Putting a message	Figure 58 on page 490
Putting a message with the MQPUT1 call	Figure 59 on page 491
Getting a message	Figure 60 on page 492
Getting a message using the wait option	Figure 61 on page 492
Getting a message using signaling	Figure 62 on page 493
Inquiring about the attributes of an object	Figure 63 on page 494
Setting the attributes of a queue	Figure 64 on page 495

## Connecting to a queue manager

Figure 53 demonstrates how to use the MQCONN call to connect a program to a queue manager in OS/390 batch. This extract is taken from the Browse sample application (program CSQ4BCA1) supplied with MQSeries for OS/390. For the names and locations of the sample applications on other platforms, see Chapter 31, “Sample programs (all platforms except OS/390)” on page 327.

```
#include <cmqc.h>
:
static char Parm1[MQ_Q_MGR_NAME_LENGTH] ;
:
int main(int argc, char *argv[] )
{
/*          */
/*      Variables for MQ calls          */
/*          */
MQHCONN Hconn;      /* Connection handle */
MQLONG  CompCode;   /* Completion code */
MQLONG  Reason;     /* Qualifying reason */
:
/* Copy the queue manager name, passed in the */
/* parm field, to Parm1                       */
strncpy(Parm1,argv[1],MQ_Q_MGR_NAME_LENGTH);
:
/*          */
/* Connect to the specified queue manager.    */
/* Test the output of the connect call. If the */
/* call fails, print an error message showing the */
/* completion code and reason code, then leave the */
/* program.                                    */
/*          */
MQCONN(Parm1,
        &Hconn,
        &CompCode,
        &Reason);

if ((CompCode != MQCC_OK) | (Reason != MQRC_NONE))
{
printf(pBuff, MESSAGE_4_E,
        ERROR_IN_MQCONN, CompCode, Reason);
PrintLine(pBuff);
RetCode = CSQ4_ERROR;
goto AbnormalExit2;
}
:
}
```

Figure 53. Using the MQCONN call (C language)

## Disconnecting from a queue manager

Figure 54 demonstrates how to use the MQDISC call to disconnect a program from a queue manager in OS/390 batch. This extract is taken from the Browse sample application (program CSQ4BCA1) supplied with MQSeries for OS/390. For the names and locations of the sample applications on other platforms, see Chapter 31, “Sample programs (all platforms except OS/390)” on page 327.

```
:
/*          */
/* Disconnect from the queue manager. Test the */
/* output of the disconnect call. If the call */
/* fails, print an error message showing the */
/* completion code and reason code.          */
/*          */
MQDISC(&Hconn,
        &CompCode,
        &Reason);

if ((CompCode != MQCC_OK) || (Reason != MQRC_NONE))
{
printf(pBuff, MESSAGE_4_E,
        ERROR_IN_MQDISC, CompCode, Reason);
PrintLine(pBuff);
RetCode = CSQ4_ERROR;
}
:
}
```

Figure 54. Using the MQDISC call (C language). The variables used in this code extract are those that were set in Figure 53.

## Creating a dynamic queue

Figure 55 demonstrates how to use the MQOPEN call to create a dynamic queue. This extract is taken from the Mail Manager sample application (program CSQ4TCD1) supplied with MQSeries for OS/390. For the names and locations of the sample applications on other platforms, see Chapter 31, "Sample programs (all platforms except OS/390)" on page 327.

```

:
MQLONG HCONN = 0; /* Connection handle */
MQHOBJ HOBJ; /* MailQ Object handle */
MQHOBJ HobjTempQ; /* TempQ Object Handle */
MQLONG CompCode; /* Completion code */
MQLONG Reason; /* Qualifying reason */
MQOD ObjDesc = {MQOD_DEFAULT};
MQLONG OpenOptions; /* Options control MQOPEN */
:
/*-----*/
/* Initialize the Object Descriptor (MQOD) */
/* control block. (The remaining fields */
/* are already initialized.) */
/*-----*/
strncpy( ObjDesc.ObjectName,
        SYSTEM_REPLY_MODEL,
        MQ_Q_NAME_LENGTH );

strncpy( ObjDesc.DynamicQName,
        SYSTEM_REPLY_INITIAL,
        MQ_Q_NAME_LENGTH );

OpenOptions = MQOO_INPUT_AS_Q_DEF;
/*-----*/
/* Open the model queue and, therefore, */
/* create and open a temporary dynamic */
/* queue */
/*-----*/
MQOPEN( HCONN,
        &ObjDesc,
        OpenOptions,
        &HobjTempQ,
        &CompCode,
        &Reason );

if ( CompCode == MQCC_OK ) {
:
}
else {
/*-----*/
/* Build an error message to report the */
/* failure of the opening of the model */
/* queue */
/*-----*/
MQMErrorHandling( "OPEN TEMPQ", CompCode,
                 Reason );
        ErrorFound = TRUE;
}
return ErrorFound;
}
:

```

Figure 55. Using the MQOPEN call to create a dynamic queue (C language)

## Opening an existing queue

Figure 56 demonstrates how to use the MQOPEN call to open a queue that has already been defined. This extract is taken from the Browse sample application (program CSQ4BCA1) supplied with MQSeries for OS/390. For the names and locations of the sample applications on other platforms, see Chapter 31, "Sample programs (all platforms except OS/390)" on page 327.

```

#include <cmqc.h>
:
static char Parm1[MQ_Q_MGR_NAME_LENGTH];
:
int main(int argc, char *argv[] )
{
/*
/* Variables for MQ calls */
/*
MQHCONN Hconn ; /* Connection handle */
MQLONG CompCode; /* Completion code */
MQLONG Reason; /* Qualifying reason */
MQOD ObjDesc = { MQOD_DEFAULT };
MQLONG OpenOptions; /* Options that control */
MQHOBJ Hobj; /* Object handle */
:
/* Copy the queue name, passed in the parm field, */
/* to Parm2 strncpy(Parm2,argv[2], */
/* MQ_Q_NAME_LENGTH); */
:
/*
/* Initialize the object descriptor (MQOD) control */
/* block. (The initialization default sets StrucId, */
/* Version, ObjectType, ObjectQMgrName, */
/* DynamicQName, and AlternateUserid fields) */
/*
strncpy(ObjDesc.ObjectName,Parm2,MQ_Q_NAME_LENGTH);
:
/* Initialize the other fields required for the open */
/* call (Hobj is set by the MQCONN call). */
/*
OpenOptions = MQOO_BROWSE;
:
/*
/* Open the queue. */
/* Test the output of the open call. If the call */
/* fails, print an error message showing the */
/* completion code and reason code, then bypass */
/* processing, disconnect and leave the program. */
/*
MQOPEN(Hconn,
        &ObjDesc,
        OpenOptions,
        &Hobj,
        &CompCode,
        &Reason);

```

Figure 56 (Part 1 of 2). Using the MQOPEN call to open an existing queue (C language)

## C language examples

```
if ((CompCode != MQCC_OK) || (Reason != MQRC_NONE))
{
    sprintf(pBuff, MESSAGE_4_E,
        ERROR_IN_MQOPEN, CompCode, Reason);
    PrintLine(pBuff);
    RetCode = CSQ4_ERROR;
    goto AbnormalExit1;    /* disconnect processing */
}
:
} /* end of main */
```

Figure 56 (Part 2 of 2). Using the MQOPEN call to open an existing queue (C language)

## Closing a queue

Figure 57 demonstrates how to use the MQCLOSE call to close a queue. This extract is taken from the Browse sample application (program CSQ4BCA1) supplied with MQSeries for OS/390. For the names and locations of the sample applications on other platforms, see Chapter 31, “Sample programs (all platforms except OS/390)” on page 327.

```
:
/*                               */
/* Close the queue.              */
/* Test the output of the close call. If the call */
/* fails, print an error message showing the      */
/* completion code and reason code.             */
/*                               */
MQCLOSE(Hconn,
        &Hobj,
        MQCO_NONE,
        &CompCode,
        &Reason);

if ((CompCode != MQCC_OK) || (Reason != MQRC_NONE))
{
    sprintf(pBuff, MESSAGE_4_E,
        ERROR_IN_MQCLOSE, CompCode, Reason);
    PrintLine(pBuff);
    RetCode = CSQ4_ERROR;
}
:
```

Figure 57. Using the MQCLOSE call (C language)

## Putting a message using MQPUT

Figure 58 demonstrates how to use the MQPUT call to put a message on a queue. This extract is not taken from the sample applications supplied with MQSeries. For the names and locations of the sample applications, see Chapter 31, “Sample programs (all platforms except OS/390)” on page 327 and Chapter 32, “Sample programs for MQSeries for OS/390” on page 395.

```
:
qput()
{
    MQMD    MsgDesc;
    MQPMO   PutMsgOpts;

    MQLONG  CompCode;
    MQLONG  Reason;
    MQHCONN Hconn;
    MQHOBJ  Hobj;

    char message_buffer[] = "MY MESSAGE";

    /*-----*/
    /* Set up PMO structure.          */
    /*-----*/
    memset(&PutMsgOpts, '\0', sizeof(PutMsgOpts));
    memcpy(PutMsgOpts.StrucId, MQPMO_STRUC_ID,
        sizeof(PutMsgOpts.StrucId));
    PutMsgOpts.Version = MQPMO_VERSION_1;
    PutMsgOpts.Options = MQPMO_SYNCPOINT;

    /*-----*/
    /* Set up MD structure.          */
    /*-----*/
    memset(&MsgDesc, '\0', sizeof(MsgDesc));
    memcpy(MsgDesc.StrucId, MQMD_STRUC_ID,
        sizeof(MsgDesc.StrucId));
    MsgDesc.Version      = MQMD_VERSION_1;
    MsgDesc.Expiry       = MQEI_UNLIMITED;
    MsgDesc.Report       = MQRO_NONE;
    MsgDesc.MsgType      = MQMT_DATAGRAM;
    MsgDesc.Priority     = 1;
    MsgDesc.Persistence = MQPER_PERSISTENT;
    memset(MsgDesc.ReplyToQ,
        '\0',
        sizeof(MsgDesc.ReplyToQ));

    /*-----*/
    /* Put the message.              */
    /*-----*/
    MQPUT(Hconn, Hobj, &MsgDesc, &PutMsgOpts,
        sizeof(message_buffer), message_buffer,
        &CompCode, &Reason);
}
```

Figure 58 (Part 1 of 2). Using the MQPUT call (C language)

```

/*-----*/
/* Check completion and reason codes. */
/*-----*/
switch (CompCode)
{
    case MQCC_OK:
        break;
    case MQCC_FAILED:
        switch (Reason)
        {
            case MQRC_Q_FULL:
            case MQRC_MSG_TOO_BIG_FOR_Q:
                break;
            default:
                break; /* Perform error processing */
        }
        break;
    default:
        break; /* Perform error processing */
}
}

```

Figure 58 (Part 2 of 2). Using the MQPUT call (C language)

## Putting a message using MQPUT1

Figure 59 demonstrates how to use the MQPUT1 call to open a queue, put a single message on the queue, then close the queue. This extract is taken from the Credit Check sample application (program CSQ4CCB5) supplied with MQSeries for OS/390. For the names and locations of the sample applications on other platforms, see Chapter 31, "Sample programs (all platforms except OS/390)" on page 327.

```

:
MQLONG Hconn; /* Connection handle */
MQHOBJ Hobj_CheckQ; /* Object handle */
MQLONG CompCode; /* Completion code */
MQLONG Reason; /* Qualifying reason */
MQOD ObjDesc = {MQOD_DEFAULT}; /* Object descriptor */
MQMD MsgDesc = {MQMD_DEFAULT}; /* Message descriptor */
MQLONG OpenOptions; /* Control the MQOPEN call */

MQGMO GetMsgOpts = {MQGMO_DEFAULT}; /* Get Message Options */
MQLONG MsgBufLen; /* Length of message buffer */
CSQ4BCAQ MsgBuffer; /* Message structure */
MQLONG DataLen; /* Length of message */

MQPMO PutMsgOpts = {MQPMO_DEFAULT}; /* Put Message Options */
CSQ4BQRM PutBuffer; /* Message structure */
MQLONG PutBufLen = sizeof(PutBuffer); /* Length of message buffer */

:

```

Figure 59 (Part 1 of 2). Using the MQPUT1 call (C language)

```

void Process_Query(void)
{
    /*
     * Build the reply message
     */
    :
    /*
     * Set the object descriptor, message descriptor and
     * put message options to the values required to
     * create the reply message.
     */
    :

    strncpy(ObjDesc.ObjectName, MsgDesc.ReplyToQ,
            MQ_Q_NAME_LENGTH);
    strncpy(ObjDesc.ObjectQMGrName, MsgDesc.ReplyToQMGr,
            MQ_Q_MGR_NAME_LENGTH);

    MsgDesc.MsgType = MQMT_REPLY;
    MsgDesc.Report = MQRO_NONE;
    memset(MsgDesc.ReplyToQ, ' ', MQ_Q_NAME_LENGTH);
    memset(MsgDesc.ReplyToQMGr, ' ', MQ_Q_MGR_NAME_LENGTH);

    memcpy(MsgDesc.MsgId, MQMI_NONE, sizeof(MsgDesc.MsgId));

    PutMsgOpts.Options = MQPMO_SYNCPOINT +
                        MQPMO_PASS_IDENTITY_CONTEXT;
    PutMsgOpts.Context = Hobj_CheckQ;

    PutBufLen = sizeof(PutBuffer);

    MQPUT1(Hconn,
           &ObjDesc,
           &MsgDesc,
           &PutMsgOpts,
           PutBufLen,
           &PutBuffer,
           &CompCode,
           &Reason);

    if (CompCode != MQCC_OK)
    {
        strncpy(TS_Operation, "MQPUT1",
                sizeof(TS_Operation));
        strncpy(TS_ObjName, ObjDesc.ObjectName,
                MQ_Q_NAME_LENGTH);
        Record_Call_Error();
        Forward_Msg_To_DLQ();
    }

    return;
}
:

```

Figure 59 (Part 2 of 2). Using the MQPUT1 call (C language)



```

:
void main(void)
{
:
/*
/* Initialize options and open the queue for input
/*
:
/*
/* Get and process messages
/*
/*
GetMsgOpts.Options = MQGMO_WAIT +
                    MQGMO_ACCEPT_TRUNCATED_MSG +
                    MQGMO_SYNCPOINT;
GetMsgOpts.WaitInterval = WAIT_INTERVAL;
MsgBuffLen = sizeof(MsgBuffer);

memcpy(MsgDesc.MsgId, MQMI_NONE,
        sizeof(MsgDesc.MsgId));
memcpy(MsgDesc.CorrelId, MQCI_NONE,
        sizeof(MsgDesc.CorrelId));
/*
/* Make the first MQGET call outside the loop
/*
/*
MQGET(Hconn,
      Hobj_CheckQ,
      &MsgDesc,
      &GetMsgOpts,
      MsgBuffLen,
      &MsgBuffer,
      &DataLen,
      &CompCode,
      &Reason);
:
/*
/* Test the output of the MQGET call. If the call
/* failed, send an error message showing the
/* completion code and reason code, unless the
/* reason code is NO_MSG_AVAILABLE.
/*
/*
if (Reason != MQRC_NO_MSG_AVAILABLE)
{
    strncpy(TS_Operation, "MQGET", sizeof(TS_Operation));
    strncpy(TS_ObjName, ObjDesc.ObjectName,
            MQ_Q_NAME_LENGTH);
    Record_Call_Error();
}
:

```

Figure 61 (Part 2 of 2). Using the MQGET call with the wait option (C language)

## Getting a message using signaling

Signaling is available only with MQSeries for OS/390 and MQSeries for Windows V2.1.

Figure 62 demonstrates how to use the MQGET call to set a signal so that you are notified when a suitable message arrives on a queue. This extract is not taken from the sample applications supplied with MQSeries.

```

:
get_set_signal()
{
    MQMD    MsgDesc;
    MQGMO   GetMsgOpts;

    MQLONG  CompCode;
    MQLONG  Reason;
    MQHCONN Hconn;
    MQHOBJ  Hobj;
    MQLONG  BufferLength;
    MQLONG  DataLength;

    char message_buffer[100];
    long int q_ecb, work_ecb;
    short int signal_sw, endloop;
    long int mask = 255;

    /*-----*/
    /* Set up GMO structure.
    /*-----*/
    memset(&GetMsgOpts, '\0', sizeof(GetMsgOpts));
    memcpy(GetMsgOpts.StrucId, MQGMO_STRUC_ID,
           sizeof(GetMsgOpts.StrucId));
    GetMsgOpts.Version = MQGMO_VERSION_1;
    GetMsgOpts.WaitInterval = 1000;
    GetMsgOpts.Options = MQGMO_SET_SIGNAL +
                        MQGMO_BROWSE_FIRST;

    q_ecb = 0;
    GetMsgOpts.Signal1 = &q_ecb;

    /*-----*/
    /* Set up MD structure.
    /*-----*/
    memset(&MsgDesc, '\0', sizeof(MsgDesc));
    memcpy(MsgDesc.StrucId, MQMD_STRUC_ID,
           sizeof(MsgDesc.StrucId));
    MsgDesc.Version = MQMD_VERSION_1;
    MsgDesc.Report = MQRO_NONE;
    memcpy(MsgDesc.MsgId, MQMI_NONE,
           sizeof(MsgDesc.MsgId));
    memcpy(MsgDesc.CorrelId, MQCI_NONE,
           sizeof(MsgDesc.CorrelId));
}

```

Figure 62 (Part 1 of 3). Using the MQGET call with signaling (C language)

## C language examples

```

/*-----*/
/* Issue the MQGET call. */
/*-----*/
BufferLength = sizeof(message_buffer);
signal_sw = 0;

MQGET(Hconn, Hobj, &MsgDesc, &GetMsgOpts,
      BufferLength, message_buffer, &DataLength,
      &CompCode, &Reason);
/*-----*/
/* Check completion and reason codes. */
/*-----*/
switch (CompCode)
{
  case (MQCC_OK):          /* Message retrieved */
    break;
  case (MQCC_WARNING):
    switch (Reason)
    {
      case (MQRC_SIGNAL_REQUEST_ACCEPTED):
        signal_sw = 1;
        break;
      default:
        break; /* Perform error processing */
    }
    break;
  case (MQCC_FAILED):
    switch (Reason)
    {
      case (MQRC_Q_MGR_NOT_AVAILABLE):
      case (MQRC_CONNECTION_BROKEN):
      case (MQRC_Q_MGR_STOPPING):
        break;
      default:
        break; /* Perform error processing. */
    }
    break;
  default:
    break; /* Perform error processing. */
}

/*-----*/
/* If the SET_SIGNAL was accepted, set up a loop to
/* check whether a message has arrived at one second
/* intervals. The loop ends if a message arrives or
/* the wait interval specified in the MQGMO
/* structure has expired.
/*
/* If a message arrives on the queue, another MQGET
/* must be issued to retrieve the message. If other
/* MQM calls have been made in the intervening
/* period, this may necessitate reinitializing the
/* MQMD and MQGMO structures.
/* In this code, no intervening calls
/* have been made, so the only change required to
/* the structures is to specify MQGMO_NO_WAIT,
/* since we now know the message is there.
/*
/* This code uses the EXEC CICS DELAY command to
/* suspend the program for a second. A batch program
/* may achieve the same effect by calling an
/* assembler language subroutine which issues an
/* OS/390 STIMER macro.
/*-----*/

```

Figure 62 (Part 2 of 3). Using the MQGET call with signaling (C language)

```

if (signal_sw == 1)
{
  endloop = 0;
  do
  {
    EXEC CICS DELAY FOR HOURS(0) MINUTES(0) SECONDS(1);
    work_ecb = q_ecb & mask;
    switch (work_ecb)
    {
      case (MQEC_MSG_ARRIVED):
        endloop = 1;
        mqgmo_options = MQGMO_NO_WAIT;
        MQGET(Hconn, Hobj, &MsgDesc, &GetMsgOpts,
              BufferLength, message_buffer,
              &DataLength, &CompCode, &Reason);
        if (CompCode != MQCC_OK)
          ; /* Perform error processing. */
        break;
      case (MQEC_WAIT_INTERVAL_EXPIRED):
      case (MQEC_WAIT_CANCELED):
        endloop = 1;
        break;
      default:
        break;
    }
  } while (endloop == 0);
}

return;
}

```

Figure 62 (Part 3 of 3). Using the MQGET call with signaling (C language)

## Inquiring about the attributes of an object

Figure 63 demonstrates how to use the MQINQ call to inquire about the attributes of a queue. This extract is taken from the Queue Attributes sample application (program CSQ4CCC1) supplied with MQSeries for OS/390. For the names and locations of the sample applications on other platforms, see Chapter 31, "Sample programs (all platforms except OS/390)" on page 327.

```

#include <cmqc.h> /* MQ API header file */
:
#define NUMBEROFSELECTORS 2

const MQHCONN Hconn = MQHC_DEF_HCONN;
:
static void InquireGetAndPut(char *Message,
                             PMQHOBJ pHobj,
                             char *Object)

```

Figure 63 (Part 1 of 2). Using the MQINQ call (C language)

```

{
/*      Declare local variables      */
/*      */
MQLONG SelectorCount = NUMBEROFSELECTORS;
/*      */
MQLONG IntAttrCount  = NUMBEROFSELECTORS;
/*      */
MQLONG CharAttrLength = 0;
/*      */
MQCHAR *CharAttrs ;
/*      */
MQLONG SelectorsTable[NUMBEROFSELECTORS];
/*      */
MQLONG IntAttrsTable[NUMBEROFSELECTORS];
/*      */
MQLONG CompCode;
/*      */
MQLONG Reason;
/*      */

/*      */
/*      Open the queue.  If successful, do the inquire */
/*      call.      */
/*      */
/*      */
/*      Initialize the variables for the inquire */
/*      call:      */
/*      - Set SelectorsTable to the attributes whose */
/*      status is      */
/*      required      */
/*      - All other variables are already set      */
/*      */
SelectorsTable[0] = MQIA_INHIBIT_GET;
SelectorsTable[1] = MQIA_INHIBIT_PUT;
/*      */
/*      Issue the inquire call      */
/*      Test the output of the inquire call.  If the */
/*      call failed, display an error message      */
/*      showing the completion code and reason code, */
/*      otherwise display the status of the      */
/*      INHIBIT-GET and INHIBIT-PUT attributes      */
/*      */
MQINQ(Hconn,
      *pHobj,
      SelectorCount,
      SelectorsTable,
      IntAttrCount,
      IntAttrsTable,
      CharAttrLength,
      CharAttrs,
      &CompCode,
      &Reason);

if (CompCode != MQCC_OK)
{
    sprintf(Message, MESSAGE_4_E,
            ERROR_IN_MQINQ, CompCode, Reason);
    SetMsg(Message);
}
else
{
    /* Process the changes */
}
/* end if CompCode */

```

Figure 63 (Part 2 of 2). Using the MQINQ call (C language)

## Setting the attributes of a queue

Figure 64 demonstrates how to use the MQSET call to change the attributes of a queue. This extract is taken from the Queue Attributes sample application (program CSQ4CCC1) supplied with MQSeries for OS/390. For the names and locations of the sample applications on other platforms, see Chapter 31, "Sample programs (all platforms except OS/390)" on page 327.

```

#include <cmqc.h>      /* MQ API header file      */
:
#define NUMBEROFSELECTORS 2

const MQHCONN Hconn = MQHC_DEF_HCONN;

static void InhibitGetAndPut(char *Message,
                             PMQHOBJ pHobj,
                             char *Object)
{
/*      Declare local variables      */
/*      */
MQLONG SelectorCount = NUMBEROFSELECTORS;
/*      */
MQLONG IntAttrCount  = NUMBEROFSELECTORS;
/*      */
MQLONG CharAttrLength = 0;
/*      */
MQCHAR *CharAttrs ;
/*      */
MQLONG SelectorsTable[NUMBEROFSELECTORS];
/*      */
MQLONG IntAttrsTable[NUMBEROFSELECTORS];
/*      */
MQLONG CompCode;
/*      */
MQLONG Reason;
/*      */
:
/*      */
/*      Open the queue.  If successful, do the */
/*      inquire call.      */
/*      */
:
/*      Initialize the variables for the set call: */
/*      - Set SelectorsTable to the attributes to be */
/*      set      */
/*      - Set IntAttrsTable to the required status */
/*      - All other variables are already set      */
/*      */
SelectorsTable[0] = MQIA_INHIBIT_GET;
SelectorsTable[1] = MQIA_INHIBIT_PUT;
IntAttrsTable[0] = MQQA_GET_INHIBITED;
IntAttrsTable[1] = MQQA_PUT_INHIBITED;
:
}

```

Figure 64 (Part 1 of 2). Using the MQSET call (C language)

## C language examples

```
/* */
/* Issue the set call. */
/* Test the output of the set call. If the */
/* call fails, display an error message */
/* showing the completion code and reason */
/* code; otherwise move INHIBITED to the */
/* relevant screen map fields */
/* */
MQSET(Hconn,
      *pHobj,
      SelectorCount,
      SelectorsTable,
      IntAttrCount,
      IntAttrsTable,
      CharAttrLength,
      CharAttrs,
      &CompCode,
      &Reason);

if (CompCode != MQCC_OK)
{
    sprintf(Message, MESSAGE_4_E,
            ERROR_IN_MQSET, CompCode, Reason);
    SetMsg(Message);
}
else
{
    /* Process the changes */
} /* end if CompCode */
```

Figure 64 (Part 2 of 2). Using the MQSET call (C language)

---

## Appendix D. COBOL examples

The examples in this appendix are taken from the MQSeries for OS/390 sample applications. They are applicable to all platforms, and any exception to this is noted.

The examples in this appendix demonstrate the following techniques:

Connecting to a queue manager	Figure 65 on page 498
Disconnecting from a queue manager	Figure 66 on page 498
Creating a dynamic queue	Figure 67 on page 499
Opening an existing queue	Figure 68 on page 500
Closing a queue	Figure 69 on page 501
Putting a message	Figure 70 on page 501
Putting a message with the MQPUT1 call	Figure 71 on page 502
Getting a message	Figure 72 on page 503
Getting a message using the wait option	Figure 73 on page 504
Getting a message using signaling	Figure 74 on page 505
Inquiring about the attributes of an object	Figure 75 on page 506
Setting the attributes of a queue	Figure 76 on page 507

## Connecting to a queue manager

Figure 65 demonstrates how to use the MQCONN call to connect a program to a queue manager in OS/390 batch. This extract is taken from the Browse sample application (program CSQ4BVA1) supplied with MQSeries for OS/390. For the names and locations of the sample applications on other platforms, see Chapter 31, “Sample programs (all platforms except OS/390)” on page 327.

```

* -----*
WORKING-STORAGE SECTION.
* -----*
*   W02 - Data fields derived from the PARM field
01  W02-MQM          PIC X(48) VALUE SPACES.
*   W03 - MQM API fields
01  W03-HCONN       PIC S9(9) BINARY.
01  W03-COMPCODE    PIC S9(9) BINARY.
01  W03-REASON      PIC S9(9) BINARY.
*
*   MQV contains constants (for filling in the control
*   blocks)
*   and return codes (for testing the result of a call)
*
01  W05-MQM-CONSTANTS.
    COPY CMQV SUPPRESS.
    :
*   Separate into the relevant fields any data passed
*   in the PARM statement
*
    UNSTRING PARM-STRING DELIMITED BY ALL ','
              INTO W02-MQM
                  W02-OBJECT.
    :
*   Connect to the specified queue manager.
*
    CALL 'MQCONN' USING W02-MQM
                       W03-HCONN
                       W03-COMPCODE
                       W03-REASON.
*
*   Test the output of the connect call. If the call
*   fails, print an error message showing the
*   completion code and reason code.
*
    IF (W03-COMPCODE NOT = MQCC-OK) THEN
    :
    END-IF.
    :

```

Figure 65. Using the MQCONN call (COBOL)

## Disconnecting from a queue manager

Figure 66 demonstrates how to use the MQDISC call to disconnect a program from a queue manager in OS/390 batch. This extract is taken from the Browse sample application (program CSQ4BVA1) supplied with MQSeries for OS/390. For the names and locations of the sample applications on other platforms, see Chapter 31, “Sample programs (all platforms except OS/390)” on page 327.

```

    :
*
*   Disconnect from the queue manager
*
    CALL 'MQDISC' USING W03-HCONN
                       W03-COMPCODE
                       W03-REASON.
*
*   Test the output of the disconnect call. If the
*   call fails, print an error message showing the
*   completion code and reason code.
*
    IF (W03-COMPCODE NOT = MQCC-OK) THEN
    :
    END-IF.
    :

```

Figure 66. Using the MQDISC call (COBOL). The variables used in this code extract are those that were set in Figure 65.

## Creating a dynamic queue

Figure 67 demonstrates how to use the MQOPEN call to create a dynamic queue. This extract is taken from the Credit Check sample application (program CSQ4CVB1) supplied with MQSeries for OS/390. For the names and locations of the sample applications on other platforms, see Chapter 31, "Sample programs (all platforms except OS/390)" on page 327.

```

:
* -----*
WORKING-STORAGE SECTION.
* -----*
*
*   W02 - Queues processed in this program
*
01  W02-MODEL-QNAME      PIC X(48) VALUE
   'CSQ4SAMP.B1.MODEL      '.
01  W02-NAME-PREFIX     PIC X(48) VALUE
   'CSQ4SAMP.B1.*         '.
01  W02-TEMPORARY-Q     PIC X(48).
*
*   W03 - MQM API fields
*
01  W03-HCONN          PIC S9(9) BINARY VALUE ZERO.
01  W03-OPTIONS       PIC S9(9) BINARY.
01  W03-HOBJ          PIC S9(9) BINARY.
01  W03-COMPCODE      PIC S9(9) BINARY.
01  W03-REASON        PIC S9(9) BINARY.
*
*   API control blocks
*
01  MQM-OBJECT-DESCRIPTOR.
   COPY CMQODV.
*
*   CMQV contains constants (for setting or testing
*   field values) and return codes (for testing the
*   result of a call)
*
01  MQM-CONSTANTS.
   COPY CMQV SUPPRESS.
* -----*
PROCEDURE DIVISION.
* -----*
:
* -----*
OPEN-TEMP-RESPONSE-QUEUE SECTION.
* -----*

```

Figure 67 (Part 1 of 2). Using the MQOPEN call to create a dynamic queue (COBOL)

```

*
*   This section creates a temporary dynamic queue
*   using a model queue
*
* -----*
*
*   Change three fields in the Object Descriptor (MQOD)
*   control block. (MQODV initializes the other fields)
*
   MOVE MQOT-Q          TO MQOD-OBJECTTYPE.
   MOVE W02-MODEL-QNAME TO MQOD-OBJECTNAME.
   MOVE W02-NAME-PREFIX TO MQOD-DYNAMICQNAME.
*
   COMPUTE W03-OPTIONS = MQ00-INPUT-EXCLUSIVE.
*
   CALL 'MQOPEN' USING W03-HCONN
                      MQOD
                      W03-OPTIONS
                      W03-HOBJ-MODEL
                      W03-COMPCODE
                      W03-REASON.
*
   IF W03-COMPCODE NOT = MQCC-OK
      MOVE 'MQOPEN'      TO M01-MSG4-OPERATION
      MOVE W03-COMPCODE TO M01-MSG4-COMPCODE
      MOVE W03-REASON   TO M01-MSG4-REASON
      MOVE M01-MESSAGE-4 TO M00-MESSAGE
   ELSE
      MOVE MQOD-OBJECTNAME TO W02-TEMPORARY-Q
   END-IF.
*
   OPEN-TEMP-RESPONSE-QUEUE-EXIT.
*
*   Return to performing section.
*
   EXIT.
   EJECT
*

```

Figure 67 (Part 2 of 2). Using the MQOPEN call to create a dynamic queue (COBOL)

## Opening an existing queue

Figure 68 demonstrates how to use the MQOPEN call to open an existing queue. This extract is taken from the Browse sample application (program CSQ4BVA1) supplied with MQSeries for OS/390. For the names and locations of the sample applications on other platforms, see Chapter 31, "Sample programs (all platforms except OS/390)" on page 327.

```

:
* -----*
WORKING-STORAGE SECTION.
* -----*
*
*   W01 - Fields derived from the command area input
*
01  W01-OBJECT          PIC X(48).
*
*   W02 - MQM API fields
*
01  W02-HCONN          PIC S9(9) BINARY VALUE ZERO.
01  W02-OPTIONS        PIC S9(9) BINARY.
01  W02-HOBJ           PIC S9(9) BINARY.
01  W02-COMPCODE       PIC S9(9) BINARY.
01  W02-REASON         PIC S9(9) BINARY.
*
*   CMQODV defines the object descriptor (MQOD)
*
01  MQM-OBJECT-DESCRIPTOR.
    COPY CMQODV.
*
*   CMQV contains constants (for setting or testing
*   field values) and return codes (for testing the
*   result of a call)
*
01  MQM-CONSTANTS.
    COPY CMQV SUPPRESS.
* -----*
E-OPEN-QUEUE SECTION.
* -----*
*
*   This section opens the queue
*
*   Initialize the Object Descriptor (MQOD) control
*   block
*   (The copy file initializes the remaining fields.)
*
    MOVE MQOT-Q          TO MQOD-OBJECTTYPE.
    MOVE W01-OBJECT      TO MQOD-OBJECTNAME.
*
*   Initialize W02-OPTIONS to open the queue for both
*   inquiring about and setting attributes
*
    COMPUTE W02-OPTIONS = MQ00-INQUIRE + MQ00-SET.

```

Figure 68 (Part 1 of 2). Using the MQOPEN call to open an existing queue (COBOL)

```

*
*   Open the queue
*
    CALL 'MQOPEN' USING W02-HCONN
                        MQOD
                        W02-OPTIONS
                        W02-HOBJ
                        W02-COMPCODE
                        W02-REASON.
*
*   Test the output from the open
*
*   If the completion code is not OK, display a
*   separate error message for each of the following
*   errors:
*
*   Q-MGR-NOT-AVAILABLE - MQM is not available
*   CONNECTION-BROKEN   - MQM is no longer connected to CICS
*   UNKNOWN-OBJECT-NAME - The queue does not exist
*   NOT-AUTHORIZED      - The user is not authorized to open
*                       the queue
*
*   For any other error, display an error message
*   showing the completion and reason codes
*
    IF W02-COMPCODE NOT = MQCC-OK
        EVALUATE TRUE
*
        WHEN W02-REASON = MQRC-Q-MGR-NOT-AVAILABLE
            MOVE M01-MESSAGE-6 TO M00-MESSAGE
*
        WHEN W02-REASON = MQRC-CONNECTION-BROKEN
            MOVE M01-MESSAGE-6 TO M00-MESSAGE
*
        WHEN W02-REASON = MQRC-UNKNOWN-OBJECT-NAME
            MOVE M01-MESSAGE-2 TO M00-MESSAGE
*
        WHEN W02-REASON = MQRC-NOT-AUTHORIZED
            MOVE M01-MESSAGE-3 TO M00-MESSAGE
*
        WHEN OTHER
            MOVE 'MQOPEN'          TO M01-MSG4-OPERATION
            MOVE W02-COMPCODE      TO M01-MSG4-COMPCODE
            MOVE W02-REASON        TO M01-MSG4-REASON
            MOVE M01-MESSAGE-4    TO M00-MESSAGE
        END-EVALUATE
    END-IF.
E-EXIT.
*
*   Return to performing section
*
    EXIT.
EJECT

```

Figure 68 (Part 2 of 2). Using the MQOPEN call to open an existing queue (COBOL)

## Closing a queue

Figure 69 demonstrates how to use the MQCLOSE call. This extract is taken from the Browse sample application (program CSQ4BVA1) supplied with MQSeries for OS/390. For the names and locations of the sample applications on other platforms, see Chapter 31, “Sample programs (all platforms except OS/390)” on page 327.

```

:
*
*   Close the queue
*
*   MOVE MQCO-NONE TO W03-OPTIONS.
*
*   CALL 'MQCLOSE' USING W03-HCONN
*                       W03-HOBJ
*                       W03-OPTIONS
*                       W03-COMPCODE
*                       W03-REASON.
*
*   Test the output of the MQCLOSE call. If the call
*   fails, print an error message showing the
*   completion code and reason code.
*
*   IF (W03-COMPCODE NOT = MQCC-OK) THEN
*       MOVE 'CLOSE'      TO W04-MSG4-TYPE
*       MOVE W03-COMPCODE TO W04-MSG4-COMPCODE
*       MOVE W03-REASON   TO W04-MSG4-REASON
*       MOVE W04-MESSAGE-4 TO W00-PRINT-DATA
*       PERFORM PRINT-LINE
*       MOVE W06-CSQ4-ERROR TO W00-RETURN-CODE
*   END-IF.
*

```

*Figure 69. Using the MQCLOSE call (COBOL). The variables used in this code extract are those that were set in Figure 65 on page 498.*

## Putting a message using MQPUT

Figure 70 demonstrates how to use the MQPUT call using context. This extract is taken from the Credit Check sample application (program CSQ4CVB1) supplied with MQSeries for OS/390. For the names and locations of the sample applications on other platforms, see Chapter 31, “Sample programs (all platforms except OS/390)” on page 327.

```

:
* -----*
*   WORKING-STORAGE SECTION.
* -----*
*
*   W02 - Queues processed in this program
*
*   01 W02-TEMPORARY-Q          PIC X(48).
*
*   W03 - MQM API fields
*
*   01 W03-HCONN                PIC S9(9) BINARY VALUE ZERO.
*   01 W03-HOBJ-INQUIRY        PIC S9(9) BINARY.
*   01 W03-OPTIONS             PIC S9(9) BINARY.
*   01 W03-BUFFLEN             PIC S9(9) BINARY.
*   01 W03-COMPCODE           PIC S9(9) BINARY.
*   01 W03-REASON              PIC S9(9) BINARY.
*
*   01 W03-PUT-BUFFER.
*
*   05 W03-CSQ4BIIM.
*   COPY CSQ4VB1.
*
*   API control blocks
*
*   01 MQM-MESSAGE-DESCRIPTOR.
*   COPY CMQMDV.
*   01 MQM-PUT-MESSAGE-OPTIONS.
*   COPY CMQPMOV.
*
*   MQV contains constants (for filling in the
*   control blocks) and return codes (for testing
*   the result of a call).
*
*   01 MQM-CONSTANTS.
*   COPY CMQV SUPPRESS.
* -----*
*   PROCEDURE DIVISION.
* -----*
:
*   Open queue and build message.
:

```

*Figure 70 (Part 1 of 2). Using the MQPUT call (COBOL)*

## COBOL examples

```

*
* Set the message descriptor and put-message options to
* the values required to create the message.
* Set the length of the message.
*
MOVE MQMT-REQUEST      TO MQMD-MSGTYPE.
MOVE MQCI-NONE         TO MQMD-CORRELID.
MOVE MQMI-NONE         TO MQMD-MSGID.
MOVE W02-TEMPORARY-Q   TO MQMD-REPLYTOQ.
MOVE SPACES            TO MQMD-REPLYTOQMGR.
MOVE 5                 TO MQMD-PRIORITY.
MOVE MQPER-NOT-PERSISTENT TO MQMD-PERSISTENCE.
COMPUTE MQPMO-OPTIONS  = MQPMO-NO-SYNCPOINT +
                        MQPMO-DEFAULT-CONTEXT.
MOVE LENGTH OF CSQ4BIIM-MSG TO W03-BUFFLEN.
*
CALL 'MQPUT' USING W03-HCONN
                  W03-HOBJ-INQUIRY
                  MQMD
                  MQPMO
                  W03-BUFFLEN
                  W03-PUT-BUFFER
                  W03-COMPCODE
                  W03-REASON.
IF W03-COMPCODE NOT = MQCC-OK
:
END-IF.

```

Figure 70 (Part 2 of 2). Using the MQPUT call (COBOL)

## Putting a message using MQPUT1

Figure 71 demonstrates how to use the MQPUT1 call. This extract is taken from the Credit Check sample application (program CSQ4CVB5) supplied with MQSeries for OS/390. For the names and locations of the sample applications on other platforms, see Chapter 31, "Sample programs (all platforms except OS/390)" on page 327.

```

:
* -----*
WORKING-STORAGE SECTION.
* -----*
*
* W03 - MQM API fields
*
01 W03-HCONN          PIC S9(9) BINARY VALUE ZERO.
01 W03-OPTIONS       PIC S9(9) BINARY.
01 W03-COMPCODE      PIC S9(9) BINARY.
01 W03-REASON        PIC S9(9) BINARY.
01 W03-BUFFLEN       PIC S9(9) BINARY.
*
01 W03-PUT-BUFFER.
05 W03-CSQ4BQRM.
COPY CSQ4VB4.

```

Figure 71 (Part 1 of 2). Using the MQPUT1 call (COBOL)

```

*
* API control blocks
*
01 MQM-OBJECT-DESCRIPTOR.
COPY CMQODV.
01 MQM-MESSAGE-DESCRIPTOR.
COPY CMQMDV.
01 MQM-PUT-MESSAGE-OPTIONS.
COPY CMQPMOV.
*
* CMQV contains constants (for filling in the
* control blocks) and return codes (for testing
* the result of a call).
*
01 MQM-MQV.
COPY CMQV SUPPRESS.
* -----*
PROCEDURE DIVISION.
* -----*
:
* Get the request message.
:
* -----*
PROCESS-QUERY SECTION.
* -----*
:
* Build the reply message.
:
*
* Set the object descriptor, message descriptor and
* put-message options to the values required to create
* the message.
* Set the length of the message.
*
MOVE MQMD-REPLYTOQ     TO MQOD-OBJECTNAME.
MOVE MQMD-REPLYTOQMGR TO MQOD-OBJECTQMGRNAME.
MOVE MQMT-REPLY        TO MQMD-MSGTYPE.
MOVE SPACES            TO MQMD-REPLYTOQ.
MOVE SPACES            TO MQMD-REPLYTOQMGR.
MOVE LOW-VALUES        TO MQMD-MSGID.
COMPUTE MQPMO-OPTIONS = MQPMO-SYNCPOINT +
                        MQPMO-PASS-IDENTITY-CONTEXT.
MOVE W03-HOBJ-CHECKQ   TO MQPMO-CONTEXT.
MOVE LENGTH OF CSQ4BQRM-MSG TO W03-BUFFLEN.
*
CALL 'MQPUT1' USING W03-HCONN
                  MQOD
                  MQMD
                  MQPMO
                  W03-BUFFLEN
                  W03-PUT-BUFFER
                  W03-COMPCODE
                  W03-REASON.
IF W03-COMPCODE NOT = MQCC-OK
MOVE 'MQPUT1'          TO M02-OPERATION
MOVE MQOD-OBJECTNAME  TO M02-OBJECTNAME
PERFORM RECORD-CALL-ERROR
PERFORM FORWARD-MSG-TO-DLQ
END-IF.
*

```

Figure 71 (Part 2 of 2). Using the MQPUT1 call (COBOL)

## Getting a message

Figure 72 demonstrates how to use the MQGET call to remove a message from a queue. This extract is taken from the Credit Check sample application (program CSQ4CVB1) supplied with MQSeries for OS/390. For the names and locations of the sample applications on other platforms, see Chapter 31, "Sample programs (all platforms except OS/390)" on page 327.

```

:
* -----*
WORKING-STORAGE SECTION.
* -----*
*
*   W03 - MQM API fields
*
01 W03-HCONN          PIC S9(9) BINARY VALUE ZERO.
01 W03-HOBJ-RESPONSE PIC S9(9) BINARY.
01 W03-OPTIONS       PIC S9(9) BINARY.
01 W03-BUFFLEN       PIC S9(9) BINARY.
01 W03-DATALEN       PIC S9(9) BINARY.
01 W03-COMPCODE      PIC S9(9) BINARY.
01 W03-REASON        PIC S9(9) BINARY.
*
01 W03-GET-BUFFER.
   05 W03-CSQ4BAM.
   COPY CSQ4VB2.
*
*   API control blocks
*
01 MQM-MESSAGE-DESCRIPTOR.
   COPY CMQMDV.
01 MQM-GET-MESSAGE-OPTIONS.
   COPY CMQGMV.
*
*   MQV contains constants (for filling in the
*   control blocks) and return codes (for testing
*   the result of a call).
*
01 MQM-CONSTANTS.
   COPY CMQV SUPPRESS.
* -----*
A-MAIN SECTION.
* -----*
:
*   Open response queue.
:
* -----*
PROCESS-RESPONSE-SCREEN SECTION.
* -----*
*
*   This section gets a message from the response queue.
*
*   When a correct response is received, it is
*   transferred to the map for display; otherwise
*   an error message is built.
*
* -----*

```

Figure 72 (Part 1 of 2). Using the MQGET call (COBOL)

```

*
*   Set get-message options
*
   COMPUTE MQGMO-OPTIONS = MQGMO-SYNCPOINT +
                           MQGMO-ACCEPT-TRUNCATED-MSG +
                           MQGMO-NO-WAIT.
*
*   Set msgid and correlid in MQMD to nulls so that any
*   message will qualify.
*   Set length to available buffer length.
*
   MOVE MQMI-NONE TO MQMD-MSGID.
   MOVE MQCI-NONE TO MQMD-CORRELID.
   MOVE LENGTH OF W03-GET-BUFFER TO W03-BUFFLEN.
*
   CALL 'MQGET' USING W03-HCONN
                           W03-HOBJ-RESPONSE
                           MQMD
                           MQGMO
                           W03-BUFFLEN
                           W03-GET-BUFFER
                           W03-DATALEN
                           W03-COMPCODE
                           W03-REASON.
*
   EVALUATE TRUE
     WHEN W03-COMPCODE NOT = MQCC-FAILED
       :
       *   Process the message
       :
       WHEN (W03-COMPCODE = MQCC-FAILED AND
             W03-REASON = MQRC-NO-MSG-AVAILABLE)
         MOVE M01-MESSAGE-9 TO M00-MESSAGE
         PERFORM CLEAR-RESPONSE-SCREEN
*
       WHEN OTHER
         MOVE 'MQGET ' TO M01-MSG4-OPERATION
         MOVE W03-COMPCODE TO M01-MSG4-COMPCODE
         MOVE W03-REASON TO M01-MSG4-REASON
         MOVE M01-MESSAGE-4 TO M00-MESSAGE
         PERFORM CLEAR-RESPONSE-SCREEN
   END-EVALUATE.

```

Figure 72 (Part 2 of 2). Using the MQGET call (COBOL)

## Getting a message using the wait option

Figure 73 demonstrates how to use the MQGET call with the wait option and accepting truncated messages. This extract is taken from the Credit Check sample application (program CSQ4CVB5) supplied with MQSeries for OS/390. For the names and locations of the sample applications on other platforms, see Chapter 31, "Sample programs (all platforms except OS/390)" on page 327.

```

:
* -----*
WORKING-STORAGE SECTION.
* -----*
*
* W00 - General work fields
*
01 W00-WAIT-INTERVAL PIC S9(09) BINARY VALUE 30000.
*
* W03 - MQM API fields
*
01 W03-HCONN PIC S9(9) BINARY VALUE ZERO.
01 W03-OPTIONS PIC S9(9) BINARY.
01 W03-HOBJ-CHECKQ PIC S9(9) BINARY.
01 W03-COMPCODE PIC S9(9) BINARY.
01 W03-REASON PIC S9(9) BINARY.
01 W03-DATALEN PIC S9(9) BINARY.
01 W03-BUFFLEN PIC S9(9) BINARY.
*
01 W03-MSG-BUFFER.
05 W03-CSQ4BCAQ.
COPY CSQ4VB3.
*
* API control blocks
*
01 MQM-MESSAGE-DESCRIPTOR.
COPY CMQMDV.
01 MQM-GET-MESSAGE-OPTIONS.
COPY CMQGMV.
*
* CMQV contains constants (for filling in the
* control blocks) and return codes (for testing
* the result of a call).
*
01 MQM-MQV.
COPY CMQV SUPPRESS.
* -----*
PROCEDURE DIVISION.
* -----*
:
* Open input queue.
:

```

Figure 73 (Part 1 of 2). Using the MQGET call with the wait option (COBOL)

```

*
* Get and process messages.
*
COMPUTE MQGMO-OPTIONS = MQGMO-WAIT +
MQGMO-ACCEPT-TRUNCATED-MSG +
MQGMO-SYNCPOINT.
MOVE LENGTH OF W03-MSG-BUFFER TO W03-BUFFLEN.
MOVE W00-WAIT-INTERVAL TO MQGMO-WAITINTERVAL.
MOVE MQMI-NONE TO MQMD-MSGID.
MOVE MQCI-NONE TO MQMD-CORRELID.
*
* Make the first MQGET call outside the loop.
*
CALL 'MQGET' USING W03-HCONN
W03-HOBJ-CHECKQ
MQMD
MQGMO
W03-BUFFLEN
W03-MSG-BUFFER
W03-DATALEN
W03-COMPCODE
W03-REASON.
*
* Test the output of the MQGET call using the
* PERFORM loop that follows.
*
* Perform whilst no failure occurs
* - process this message
* - reset the call parameters
* - get another message
* End-perform
*
:
* Test the output of the MQGET call. If the call
* fails, send an error message showing the
* completion code and reason code, unless the
* completion code is NO-MSG-AVAILABLE.
*
IF (W03-COMPCODE NOT = MQCC-FAILED) OR
(W03-REASON NOT = MQRC-NO-MSG-AVAILABLE)
MOVE 'MQGET ' TO M02-OPERATION
MOVE MQOD-OBJECTNAME TO M02-OBJECTNAME
PERFORM RECORD-CALL-ERROR
END-IF.
:

```

Figure 73 (Part 2 of 2). Using the MQGET call with the wait option (COBOL)

## Getting a message using signaling

Signaling is available only with MQSeries for OS/390.

Figure 74 demonstrates how to use the MQGET call with signaling. This extract is taken from the Credit Check sample application (program CSQ4CVB2) supplied with MQSeries for OS/390.

```

:
* -----*
WORKING-STORAGE SECTION.
* -----*
*
*   W00 - General work fields
:
01 W00-WAIT-INTERVAL    PIC S9(09) BINARY VALUE 30000.
*
*   W03 - MQM API fields
*
01 W03-HCONN           PIC S9(9) BINARY VALUE ZERO.
01 W03-HOBJ-REPLYQ     PIC S9(9) BINARY.
01 W03-COMPCODE        PIC S9(9) BINARY.
01 W03-REASON          PIC S9(9) BINARY.
01 W03-DATALEN         PIC S9(9) BINARY.
01 W03-BUFFLEN         PIC S9(9) BINARY.
:
01 W03-GET-BUFFER.
   05 W03-CSQ4BQRM.
   COPY CSQ4VB4.
*
   05 W03-CSQ4BIIM REDEFINES W03-CSQ4BQRM.
   COPY CSQ4VB1.
*
   05 W03-CSQ4BPGM REDEFINES W03-CSQ4BIIM.
   COPY CSQ4VB5.
:
*   API control blocks
*
01 MQM-MESSAGE-DESCRIPTOR.
   COPY CMQMDV.
01 MQM-GET-MESSAGE-OPTIONS.
   COPY CMQGMV.
:
*   MQV contains constants (for filling in the
*   control blocks) and return codes (for testing
*   the result of a call).
*
01 MQM-MQV.
   COPY CMQV SUPPRESS.
* -----*
LINKAGE SECTION.
* -----*
01 L01-ECB-ADDR-LIST.
   05 L01-ECB-ADDR1    POINTER.
   05 L01-ECB-ADDR2    POINTER.

```

Figure 74 (Part 1 of 3). Using the MQGET call with signaling (COBOL)

```

*
01 L02-ECBS.
   05 L02-INQUIRY-ECB1    PIC S9(09) BINARY.
   05 L02-REPLY-ECB2     PIC S9(09) BINARY.
01 REDEFINES L02-ECBS.
   05                      PIC X(02).
   05 L02-INQUIRY-ECB1-CC PIC S9(04) BINARY.
   05                      PIC X(02).
   05 L02-REPLY-ECB2-CC  PIC S9(04) BINARY.
*
* -----*
PROCEDURE DIVISION.
* -----*
:
* Initialize variables, open queues, set signal on
* inquiry queue.
:
* -----*
PROCESS-SIGNAL-ACCEPTED SECTION.
* -----*
* This section gets a message with signal. If a
* message is received, process it. If the signal
* is set or is already set, the program goes into
* an operating system wait.
* Otherwise an error is reported and call error set.
* -----*
PERFORM REPLYQ-GETSIGNAL.
*
EVALUATE TRUE
   WHEN (W03-COMPCODE = MQCC-OK AND
         W03-REASON = MQRC-NONE)
      PERFORM PROCESS-REPLYQ-MESSAGE
*
   WHEN (W03-COMPCODE = MQCC-WARNING AND
         W03-REASON = MQRC-SIGNAL-REQUEST-ACCEPTED)
      OR
         (W03-COMPCODE = MQCC-FAILED AND
          W03-REASON = MQRC-SIGNAL-OUTSTANDING)
      PERFORM EXTERNAL-WAIT
*
   WHEN OTHER
      MOVE 'MQGET SIGNAL' TO M02-OPERATION
      MOVE MQOD-OBJECTNAME TO M02-OBJECTNAME
      PERFORM RECORD-CALL-ERROR
      MOVE W06-CALL-ERROR TO W06-CALL-STATUS
END-EVALUATE.
*
PROCESS-SIGNAL-ACCEPTED-EXIT.
* Return to performing section
EXIT.
EJECT
*
* -----*
EXTERNAL-WAIT SECTION.
* -----*
* This section performs an external CICS wait on two
* ECBs until at least one is posted. It then calls
* the sections to handle the posted ECB.
* -----*

```

Figure 74 (Part 2 of 3). Using the MQGET call with signaling (COBOL)

## COBOL examples

```

EXEC CICS WAIT EXTERNAL
      ECBLIST(W04-ECB-ADDR-LIST-PTR)
      NUMEVENTS(2)
END-EXEC.

*
* At least one ECB must have been posted to get to this
* point. Test which ECB has been posted and perform
* the appropriate section.
*
      IF L02-INQUIRY-ECB1 NOT = 0
          PERFORM TEST-INQUIRYQ-ECB
      ELSE
          PERFORM TEST-REPLYQ-ECB
      END-IF.

*
EXTERNAL-WAIT-EXIT.
*
* Return to performing section.
*
      EXIT.
      EJECT
      :
* -----*
REPLYQ-GETSIGNAL SECTION.
* -----*
* This section performs an MQGET call (in syncpoint with *
* signal) on the reply queue. The signal field in the *
* MQGMO is set to the address of the ECB. *
* Response handling is done by the performing section. *
* -----*
*
      COMPUTE MQGMO-OPTIONS          = MQGMO-SYNCPOINT +
          MQGMO-SET-SIGNAL.
      MOVE W00-WAIT-INTERVAL        TO MQGMO-WAITINTERVAL.
      MOVE LENGTH OF W03-GET-BUFFER TO W03-BUFFLEN.

*
      MOVE ZEROS                    TO L02-REPLY-ECB2.
      SET MQGMO-SIGNAL1 TO ADDRESS OF L02-REPLY-ECB2.

*
* Set msgid and correlid to nulls so that any message
* will qualify.
*
      MOVE MQMI-NONE TO MQMD-MSGID.
      MOVE MQCI-NONE TO MQMD-CORRELID.

*
      CALL 'MQGET' USING W03-HCONN
          W03-HOBJ-REPLYQ
          MQMD
          MQGMO
          W03-BUFFLEN
          W03-GET-BUFFER
          W03-DATALEN
          W03-COMPCODE
          W03-REASON.

*
REPLYQ-GETSIGNAL-EXIT.
*
* Return to performing section.
*
      EXIT.
      EJECT
      :

```

Figure 74 (Part 3 of 3). Using the MQGET call with signaling (COBOL)

## Inquiring about the attributes of an object

Figure 75 demonstrates how to use the MQINQ call to inquire about the attributes of a queue. This extract is taken from the Queue Attributes sample application (program CSQ4CVC1) supplied with MQSeries for OS/390. For the names and locations of the sample applications on other platforms, see Chapter 31, "Sample programs (all platforms except OS/390)" on page 327.

```

      :
* -----*
WORKING-STORAGE SECTION.
* -----*
*
* W02 - MQM API fields
*
01 W02-SELECTORCOUNT    PIC S9(9) BINARY VALUE 2.
01 W02-INTATTRCOUNT    PIC S9(9) BINARY VALUE 2.
01 W02-CHARATTRLENGTH   PIC S9(9) BINARY VALUE ZERO.
01 W02-CHARATTRS        PIC X    VALUE LOW-VALUES.
01 W02-HCONN             PIC S9(9) BINARY VALUE ZERO.
01 W02-HOBJ              PIC S9(9) BINARY.
01 W02-COMPCODE          PIC S9(9) BINARY.
01 W02-REASON            PIC S9(9) BINARY.
01 W02-SELECTORS-TABLE.
   05 W02-SELECTORS      PIC S9(9) BINARY OCCURS 2 TIMES
01 W02-INTATTRS-TABLE.
   05 W02-INTATTRS      PIC S9(9) BINARY OCCURS 2 TIMES

*
* CMQODV defines the object descriptor (MQOD).
*
01 MQM-OBJECT-DESCRIPTOR.
   COPY CMQODV.

*
* CMQV contains constants (for setting or testing field
* values) and return codes (for testing the result of a
* call).
*
01 MQM-CONSTANTS.
   COPY CMQV SUPPRESS.
* -----*
PROCEDURE DIVISION.
* -----*
*
* Get the queue name and open the queue.
*
      :
*
* Initialize the variables for the inquiry call:
* - Set W02-SELECTORS-TABLE to the attributes whose
* status is required
* - All other variables are already set
*
      MOVE MQIA-INHIBIT-GET TO W02-SELECTORS(1).
      MOVE MQIA-INHIBIT-PUT TO W02-SELECTORS(2).

```

Figure 75 (Part 1 of 2). Using the MQINQ call (COBOL)

```

*
*   Inquire about the attributes.
*
*   CALL 'MQINQ' USING W02-HCONN,
*                       W02-HOBJ,
*                       W02-SELECTORCOUNT,
*                       W02-SELECTORS-TABLE,
*                       W02-INTATTRCOUNT,
*                       W02-INTATTRS-TABLE,
*                       W02-CHARATTRLENGTH,
*                       W02-CHARATTRS,
*                       W02-COMPCODE,
*                       W02-REASON.
*
* Test the output from the inquiry:
*
* - If the completion code is not OK, display an error
*   message showing the completion and reason codes
*
* - Otherwise, move the correct attribute status into
*   the relevant screen map fields
*
*   IF W02-COMPCODE NOT = MQCC-OK
*       MOVE 'MQINQ'      TO M01-MSG4-OPERATION
*       MOVE W02-COMPCODE TO M01-MSG4-COMPCODE
*       MOVE W02-REASON   TO M01-MSG4-REASON
*       MOVE M01-MESSAGE-4 TO M00-MESSAGE
*
*   ELSE
*       Process the changes.
*   :
*       END-IF.
*   :

```

Figure 75 (Part 2 of 2). Using the MQINQ call (COBOL)

## Setting the attributes of a queue

Figure 76 demonstrates how to use the MQSET call to change the attributes of a queue. This extract is taken from the Queue Attributes sample application (program CSQ4CVC1) supplied with MQSeries for OS/390. For the names and locations of the sample applications on other platforms, see Chapter 31, "Sample programs (all platforms except OS/390)" on page 327.

```

:
* -----*
* WORKING-STORAGE SECTION.
* -----*
*
*   W02 - MQM API fields
*
*   01 W02-SELECTORCOUNT   PIC S9(9) BINARY VALUE 2.
*   01 W02-INTATTRCOUNT   PIC S9(9) BINARY VALUE 2.
*   01 W02-CHARATTRLENGTH  PIC S9(9) BINARY VALUE ZERO.
*   01 W02-CHARATTRS       PIC X      VALUE LOW-VALUES.
*   01 W02-HCONN           PIC S9(9) BINARY VALUE ZERO.
*   01 W02-HOBJ            PIC S9(9) BINARY.
*   01 W02-COMPCODE        PIC S9(9) BINARY.
*   01 W02-REASON          PIC S9(9) BINARY.
*   01 W02-SELECTORS-TABLE.
*       05 W02-SELECTORS   PIC S9(9) BINARY OCCURS 2 TIMES.
*   01 W02-INTATTRS-TABLE.
*       05 W02-INTATTRS   PIC S9(9) BINARY OCCURS 2 TIMES.
*
*   CMQODV defines the object descriptor (MQOD).
*
*   01 MQM-OBJECT-DESCRIPTOR.
*       COPY CMQODV.
*
*   CMQV contains constants (for setting or testing
*   field values) and return codes (for testing the
*   result of a call).
*
*   01 MQM-CONSTANTS.
*       COPY CMQV SUPPRESS.
* -----*
* PROCEDURE DIVISION.
* -----*

```

Figure 76 (Part 1 of 2). Using the MQSET call (COBOL)

## COBOL examples

```
*
*   Get the queue name and open the queue.
*
*   :
*
*   * Initialize the variables required for the set call:
*   * - Set W02-SELECTORS-TABLE to the attributes to be set
*   * - Set W02-INTATTRS-TABLE to the required status
*   * - All other variables are already set
*
*   MOVE MQIA-INHIBIT-GET TO W02-SELECTORS(1).
*   MOVE MQIA-INHIBIT-PUT TO W02-SELECTORS(2).
*   MOVE MQQA-GET-INHIBITED TO W02-INTATTRS(1).
*   MOVE MQQA-PUT-INHIBITED TO W02-INTATTRS(2).
*
*   Set the attributes.
*
*   CALL 'MQSET' USING W02-HCONN,
*                   W02-HOBJ,
*                   W02-SELECTORCOUNT,
*                   W02-SELECTORS-TABLE,
*                   W02-INTATTRCOUNT,
*                   W02-INTATTRS-TABLE,
*                   W02-CHARATTRLENGTH,
*                   W02-CHARATTRS,
*                   W02-COMPCODE,
*                   W02-REASON.
*
* Test the output from the call:
*
* - If the completion code is not OK, display an error
*   message showing the completion and reason codes
*
* - Otherwise, move 'INHIBITED' into the relevant
*   screen map fields
*
*   IF W02-COMPCODE NOT = MQCC-OK
*       MOVE 'MQSET' TO M01-MSG4-OPERATION
*       MOVE W02-COMPCODE TO M01-MSG4-COMPCODE
*       MOVE W02-REASON TO M01-MSG4-REASON
*       MOVE M01-MESSAGE-4 TO M00-MESSAGE
*   ELSE
*
*       Process the changes.
*
*   :
*   END-IF.
```

Figure 76 (Part 2 of 2). Using the MQSET call (COBOL)

---

## Appendix E. System/390 assembler-language examples

The extracts in this appendix are mostly taken from the MQSeries for OS/390 sample applications.

The examples in this appendix demonstrate the following techniques:

Connecting to a queue manager	Figure 77 on page 510
Disconnecting from a queue manager	Figure 78 on page 510
Creating a dynamic queue	Figure 79 on page 511
Opening an existing queue	Figure 80 on page 512
Closing a queue	Figure 81 on page 512
Putting a message	Figure 82 on page 513
Putting a message with the MQPUT1 call	Figure 83 on page 513
Getting a message	Figure 84 on page 514
Getting a message using the wait option	Figure 85 on page 515
Getting a message using signaling	Figure 86 on page 516
Inquiring about and setting the attributes of a queue	Figure 87 on page 517













## Assembler-language examples

```

*
WORKSTG DSECT
*
COMPCODE DS F
REASON DS F
BUFFLEN DS F
DATALEN DS F
OPTIONS DS F
HCONN DS F
HOBJ DS F
*
BUFFER DS CL80
BUFFER_LEN EQU *-BUFFER
*
WMD CMQMDA DSECT=NO,LIST=NO
WGMO CMQGMOA DSECT=NO,LIST=NO
*
CALLLST CALL ,(0,0,0,0,0,0,0,0,0,0),VL,MF=L
*
:
END

```

Figure 85 (Part 3 of 3). Using the MQGET call with the wait option (Assembler language)

## Getting a message using signaling

Figure 86 demonstrates how to use the MQGET call to set a signal so that you are notified when a suitable message arrives on a queue. This extract is not taken from the sample applications supplied with MQSeries.

```

:
*
* CONNECT TO QUEUE MANAGER
*
CONN DS 0H
:
*
* OPEN A QUEUE FOR GET
*
OPEN DS 0H
:
*
* R4,R5,R6,R7 = WORK REGISTER.
*
GET DS 0H
LA R4,MQMD SET UP ADDRESSES AND
LA R5,MQMD_LENGTH LENGTH FOR USE BY MVCL
LA R6,WMD INSTRUCTION, AS MQMD IS
LA R7,WMD_LENGTH OVER 256 BYES LONG.
MVCL R6,R4 INITIALIZE WORKING VERSION
* OF MESSAGE DESCRIPTOR

```

Figure 86 (Part 1 of 3). Using the MQGET call with signaling (Assembler language)

```

*
MVC WGMO_AREA,MQGMO_AREA INITIALIZE WORKING MQGMO
LA R5,MQGMO_SET_SIGNAL
ST R5,WGMO_OPTIONS
MVC WGMO_WAITINTERVAL,FIVE_MINUTES WAIT UP TO FIVE
MINUTES BEFORE
FAILING THE CALL
*
*
XC SIG_ECB,SIG_ECB CLEAR THE ECB
LA R5,SIG_ECB GET THE ADDRESS OF THE ECB
ST R5,WGMO_SIGNAL1 AND PUT IT IN THE WORKING
MQGMO
*
*
LA R5,BUFFER_LEN RETRIEVE THE BUFFER LENGTH
ST R5,BUFFLEN AND SAVE IT FOR MQM USE
*
*
ISSUE MQI GET REQUEST USING REENTRANT FORM OF CALL MACRO
*
HCONN WAS SET BY PREVIOUS MQCONN REQUEST
HOBJ WAS SET BY PREVIOUS MQOPEN REQUEST
*
CALL MQGET, X
(HCONN, X
HOBJ, X
WMD, X
WGMO, X
BUFFLEN, X
BUFFER, X
DATALEN, X
COMPCODE, X
REASON), X
VL,MF=(E,CALLLST)
*
LA R5,MQCC_OK DID THE MQGET REQUEST
C R5,COMPCODE WORK OK?
BE GETOK YES, SO GO AND PROCESS.
LA R5,MQCC_WARNING NO, SO CHECK FOR A WARNING.
C R5,COMPCODE IS THIS A WARNING?
BE CHECK_W YES, SO CHECK THE REASON.
B BADCALL NO, SO GO TO ERROR ROUTINE
*

```

Figure 86 (Part 2 of 3). Using the MQGET call with signaling (Assembler language)

```

CHECK_W DS 0H
LA R5,MQRC SIGNAL_REQUEST_ACCEPTED
C R5,REASON SIGNAL_REQUEST_SIGNAL_SET?
BNE BADCALL NO, SOME ERROR OCCURRED
B DOWORK YES, SO DO SOMETHING
      ELSE
*
*
CHECKSIG DS 0H
CLC SIG_ECB+1(3),=AL3(MQEC_MSG_ARRIVED)
      IS A MESSAGE AVAILABLE?
BE GET YES, SO GO AND GET IT
*
CLC SIG_ECB+1(3),=AL3(MQEC_WAIT_INTERVAL_EXPIRED)
      HAVE WE WAITED LONG ENOUGH?
BE NOMSG YES, SO SAY NO MSG AVAILABLE
B BADCALL IF IT'S ANYTHING ELSE
      GO TO ERROR ROUTINE.
*
*
DOWORK DS 0H
      :
      TM SIG_ECB,X'40' HAS THE SIGNAL ECB BEEN POSTED?
      BO CHECKSIG YES, SO GO AND CHECK WHY
      B DOWORK NO, SO GO AND DO MORE WORK
*
NOMSG DS 0H
      :
GETOK DS 0H
      :
BADCALL DS 0H
      :
*
*
CONSTANTS
*
      CMQMDA DSECT=NO,LIST=YES
      CMQMOA DSECT=NO,LIST=YES
      CMQA
*
FIVE_MINUTES DC F'300000' GET SIGNAL INTERVAL
*
      WORKING STORAGE DSECT
*
WORKSTG DSECT
*
COMPCODE DS F
REASON DS F
BUFFLEN DS F
DATALEN DS F
OPTIONS DS F
HCONN DS F
HOBJ DS F
SIG_ECB DS F
*
BUFFER DS CL80
BUFFER_LEN EQU *-BUFFER
*
WMD CMQMDA DSECT=NO,LIST=NO
WGMO CMQMOA DSECT=NO,LIST=NO
*
CALLLST CALL ,(0,0,0,0,0,0,0,0,0,0,0,0,0,0,0,0),VL,MF=L
*
      :
      END

```

Figure 86 (Part 3 of 3). Using the MQGET call with signaling (Assembler language)

## Inquiring about and setting the attributes of a queue

Figure 87 demonstrates how to use the MQINQ call to inquire about the attributes of a queue and to use the MQSET call to change the attributes of a queue. This extract is taken from the Queue Attributes sample application (program CSQ4CAC1) supplied with MQSeries for OS/390.

```

      :
DFHEISTG DSECT
      :
OBJDESC CMQODA LIST=YES Working object descriptor
*
SELECTORCOUNT DS F Number of selectors
INTATTRCOUNT DS F Number of integer attributes
CHARATTRLENGTH DS F char attributes length
CHARATTRS DS C Area for char attributes
*
OPTIONS DS F Command options
HCONN DS F Handle of connection
HOBJ DS F Handle of object
COMPCODE DS F Completion code
REASON DS F Reason code
SELECTOR DS 2F Array of selectors
INTATTRS DS 2F Array of integer attributes
      :
OBJECT DS CL(MQ_Q_NAME_LENGTH) Name of queue
      :
CALLLST CALL ,(0,0,0,0,0,0,0,0,0,0,0,0,0,0,0,0),VL,MF=L
*****
* PROGRAM EXECUTION STARTS HERE *
      :
CSQ4CAC1 DFHEIENT CODEREG=(R3),DATAREG=(R13)
      :
* Initialize the variables for the set call
*
SR R0,R0 Clear register zero
ST R0,CHARATTRLENGTH Set char length to zero
LA R0,2 Load to set
ST R0,SELECTORCOUNT selectors add
ST R0,INTATTRCOUNT integer attributes
*
LA R0,MQIA_INHIBIT_GET Load q attribute selector
ST R0,SELECTOR+0 Place in field
LA R0,MQIA_INHIBIT_PUT Load q attribute selector
ST R0,SELECTOR+4 Place in field
*
UPDTEST DS 0H
CLC ACTION,CINHIB Are we inhibiting?
BE UPDINHBT Yes branch to section
*
CLC ACTION,CALLOW Are we allowing?
BE UPDALLOW Yes branch to section
*
MVC M00_MSG,M01_MSG1 Invalid request
BR R6 Return to caller
*

```

Figure 87 (Part 1 of 2). Using the MQINQ and MQSET calls (Assembler language)

## Assembler-language examples

```

UPDINHBT DS  0H
           MVC  UPDTYPE,CINHIBIT      Indicate action type
           LA   R0,MQQA_GET_INHIBITED Load attribute value
           ST   R0,INTATTRS+0        Place in field
           LA   R0,MQQA_PUT_INHIBITED Load attribute value
           ST   R0,INTATTRS+4        Place in field
           B    UPDCALL              Go and do call

*
UPDALLOW DS  0H
           MVC  UPDTYPE,CALLOWED      Indicate action type
           LA   R0,MQQA_GET_ALLOWED    Load attribute value
           ST   R0,INTATTRS+0        Place in field
           LA   R0,MQQA_PUT_ALLOWED    Load attribute value
           ST   R0,INTATTRS+4        Place in field
           B    UPDCALL              Go and do call

*
UPDCALL   DS  0H
           CALL MQSET,                C
           (HCONN,                   C
            HOBJ,                     C
            SELECTORCOUNT,          C
            SELECTOR,                C
            INTATTRCOUNT,          C
            INTATTRS,               C
            CHARATTRLENGTH,          C
            CHARATTRS,              C
            COMPCODE,                C
            REASON),                 C
           VL,MF=(E,CALLLIST)

*
           LA   R0,MQCC_OK           Load expected compcode
           C    R0,COMPCODE           Was set successful?
           :
* SECTION NAME : INQUIRE             *
* FUNCTION     : Inquires on the objects attributes *
* CALLED BY    : PROCESS              *
* CALLS        : OPEN, CLOSE, CODES   *
* RETURN       : To Register 6        *
INQUIRE DS  0H
           :
* Initialize the variables for the inquire call
*
           SR   R0,R0                Clear register zero
           ST   R0,CHARATTRLENGTH     Set char length to zero
           LA   R0,2                  Load to set
           ST   R0,SELECTORCOUNT     selectors add
           ST   R0,INTATTRCOUNT     integer attributes

*
           LA   R0,MQIA_INHIBIT_GET   Load attribute value
           ST   R0,SELECTOR+0         Place in field
           LA   R0,MQIA_INHIBIT_PUT   Load attribute value
           ST   R0,SELECTOR+4         Place in field
           CALL MQINQ,                C
           (HCONN,                   C
            HOBJ,                     C
            SELECTORCOUNT,          C
            SELECTOR,                C
            INTATTRCOUNT,          C
            INTATTRS,               C
            CHARATTRLENGTH,          C
            CHARATTRS,              C
            COMPCODE,                C
            REASON),                 C
           VL,MF=(E,CALLLIST)
           LA   R0,MQCC_OK           Load expected compcode
           C    R0,COMPCODE           Was inquire successful?
           :

```

Figure 87 (Part 2 of 2). Using the MQINQ and MQSET calls (Assembler language)

---

## Appendix F. PL/I examples

The use of PL/I is supported by MQSeries for AIX, OS/2 Warp, OS/390, VSE/ESA, and Windows NT only.

The examples demonstrate the following techniques:

Connecting to a queue manager	Figure 88 on page 520
Disconnecting from a queue manager	Figure 89 on page 520
Creating a dynamic queue	Figure 90 on page 521
Opening an existing queue	Figure 91 on page 521
Closing a queue	Figure 92 on page 522
Putting a message	Figure 93 on page 522
Putting a message with the MQPUT1 call	Figure 94 on page 523
Getting a message	Figure 95 on page 524
Getting a message using the wait option	Figure 96 on page 525
Getting a message using signaling	Figure 97 on page 526
Inquiring about the attributes of an object	Figure 98 on page 527
Setting the attributes of a queue	Figure 99 on page 528

## Connecting to a queue manager

Figure 88 demonstrates how to use the MQCONN call to connect a program to a queue manager in OS/390 batch. This extract is not taken from the sample applications supplied with MQSeries.

```

%INCLUDE SYSLIB(CMQP);
%INCLUDE SYSLIB(CMQEPP);
:
/*****
/* STRUCTURE BASED ON PARAMETER INPUT AREA (PARAM) */
*****/
DCL 1 INPUT_PARAM      BASED(ADDR(PARAM)),
      2 PARAM_LENGTH   FIXED BIN(15),
      2 PARAM_QMNAME   CHAR(48);
:
/*****
/* WORKING STORAGE DECLARATIONS */
*****/
DCL MQMNAME           CHAR(48);
DCL COMPCODE          BINARY FIXED (31);
DCL REASON            BINARY FIXED (31);
DCL HCONN             BINARY FIXED (31);
:
/*****
/* COPY QUEUE MANAGER NAME PARAMETER */
/* TO LOCAL STORAGE */
*****/
MQMNAME = ' ';
MQMNAME = SUBSTR(PARAM_QMNAME,1,PARAM_LENGTH);
:
/*****
/* CONNECT FROM THE QUEUE MANAGER */
*****/
CALL MQCONN (MQMNAME, /* MQM SYSTEM NAME */
            HCONN,    /* CONNECTION HANDLE */
            COMPCODE, /* COMPLETION CODE */
            REASON); /* REASON CODE */
:
/*****
/* TEST THE COMPLETION CODE OF THE CONNECT CALL. */
/* IF THE CALL HAS FAILED ISSUE AN ERROR MESSAGE */
/* SHOWING THE COMPLETION CODE AND THE REASON CODE. */
*****/
IF COMPCODE ^= MQCC_OK
    THEN DO;
:
    CALL ERROR_ROUTINE;
END;

```

Figure 88. Using the MQCONN call (PL/I)

## Disconnecting from a queue manager

Figure 89 demonstrates how to use the MQDISC call to disconnect a program from a queue manager in OS/390 batch. This extract is not taken from the sample applications supplied with MQSeries.

```

%INCLUDE SYSLIB(CMQP);
%INCLUDE SYSLIB(CMQEPP);
:
/*****
/* WORKING STORAGE DECLARATIONS */
*****/
DCL COMPCODE          BINARY FIXED (31);
DCL REASON            BINARY FIXED (31);
DCL HCONN             BINARY FIXED (31);
:
/*****
/* DISCONNECT FROM THE QUEUE MANAGER */
*****/
CALL MQDISC (HCONN, /* CONNECTION HANDLE */
            COMPCODE, /* COMPLETION CODE */
            REASON); /* REASON CODE */
:
/*****
/* TEST THE COMPLETION CODE OF THE DISCONNECT CALL. */
/* IF THE CALL HAS FAILED ISSUE AN ERROR MESSAGE */
/* SHOWING THE COMPLETION CODE AND THE REASON CODE. */
*****/
IF COMPCODE ^= MQCC_OK
    THEN DO;
:
    CALL ERROR_ROUTINE;
END;

```

Figure 89. Using the MQDISC call (PL/I)

## Creating a dynamic queue

Figure 90 demonstrates how to use the MQOPEN call to create a dynamic queue. This extract is not taken from the sample applications supplied with MQSeries.

```

%INCLUDE SYSLIB(CMQP);
%INCLUDE SYSLIB(CMQEPP);
:
/*****/
/* WORKING STORAGE DECLARATIONS */
/*****/
DCL COMPCODE          BINARY FIXED (31);
DCL REASON            BINARY FIXED (31);
DCL HCONN            BINARY FIXED (31);
DCL HOBJ             BINARY FIXED (31);
DCL OPTIONS          BINARY FIXED (31);
:
DCL MODEL_QUEUE_NAME CHAR(48) INIT('PL1.REPLY.MODEL');
DCL DYNAMIC_NAME_PREFIX CHAR(48) INIT('PL1.TEMPQ.*');
DCL DYNAMIC_QUEUE_NAME CHAR(48) INIT(' ');
:
/*****/
/* LOCAL COPY OF OBJECT DESCRIPTOR */
/*****/
DCL 1 LMQOD LIKE MQOD;
:
/*****/
/* SET UP OBJECT DESCRIPTOR FOR OPEN OF REPLY QUEUE */
/*****/
LMQOD.OBJECTTYPE =MQOT_Q;
LMQOD.OBJECTNAME = MODEL_QUEUE_NAME;
LMQOD.DYNAMICQNAME = DYNAMIC_NAME_PREFIX;
OPTIONS = MQOO_INPUT_EXCLUSIVE;

CALL MQOPEN (HCONN,
             LMQOD,
             OPTIONS,
             HOBJ,
             COMPCODE,
             REASON);

/*****/
/* TEST THE COMPLETION CODE OF THE OPEN CALL. */
/* IF THE CALL HAS FAILED ISSUE AN ERROR MESSAGE */
/* SHOWING THE COMPLETION CODE AND THE REASON CODE. */
/* IF THE CALL HAS SUCCEEDED THEN EXTRACT THE NAME OF */
/* THE NEWLY CREATED DYNAMIC QUEUE FROM THE OBJECT */
/* DESCRIPTOR. */
/*****/
IF COMPCODE ^= MQCC_OK
THEN DO;

:
CALL ERROR_ROUTINE;
END;
ELSE
DYNAMIC_QUEUE_NAME = LMQOD_OBJECTNAME;

```

Figure 90. Using the MQOPEN call to create a dynamic queue (PL/I)

## Opening an existing queue

Figure 91 demonstrates how to use the MQOPEN call to open an existing queue. This extract is not taken from the sample applications supplied with MQSeries.

```

%INCLUDE SYSLIB(CMQP);
%INCLUDE SYSLIB(CMQEPP);
:
/*****/
/* WORKING STORAGE DECLARATIONS */
/*****/
DCL COMPCODE          BINARY FIXED (31);
DCL REASON            BINARY FIXED (31);
DCL HCONN            BINARY FIXED (31);
DCL HOBJ             BINARY FIXED (31);
DCL OPTIONS          BINARY FIXED (31);
:
DCL QUEUE_NAME        CHAR(48) INIT('PL1.LOCAL.QUEUE');
:
/*****/
/* LOCAL COPY OF OBJECT DESCRIPTOR */
/*****/
DCL 1 LMQOD LIKE MQOD;
:
/*****/
/* SET UP OBJECT DESCRIPTOR FOR OPEN OF REPLY QUEUE */
/*****/
LMQOD.OBJECTTYPE = MQOT_Q;
LMQOD.OBJECTNAME = QUEUE_NAME;
OPTIONS = MQOO_INPUT_EXCLUSIVE;

CALL MQOPEN (HCONN,
             LMQOD,
             OPTIONS,
             HOBJ,
             COMPCODE,
             REASON);

/*****/
/* TEST THE COMPLETION CODE OF THE OPEN CALL. */
/* IF THE CALL HAS FAILED ISSUE AN ERROR MESSAGE */
/* SHOWING THE COMPLETION CODE AND THE REASON CODE. */
/*****/
IF COMPCODE ^= MQCC_OK
THEN DO;

:
CALL ERROR_ROUTINE;
END;

```

Figure 91. Using the MQOPEN call to open an existing queue (PL/I)

## Closing a queue

Figure 92 demonstrates how to use the MQCLOSE call. This extract is not taken from the sample applications supplied with MQSeries.

```

%INCLUDE SYSLIB(CMQP);
%INCLUDE SYSLIB(CMQEPP);
:
/*****
/* WORKING STORAGE DECLARATIONS */
/*****
DCL COMPCODE          BINARY FIXED (31);
DCL REASON            BINARY FIXED (31);
DCL HCONN            BINARY FIXED (31);
DCL HOBJ             BINARY FIXED (31);
DCL OPTIONS          BINARY FIXED (31);
:
/*****
/* SET CLOSE OPTIONS */
/*****
OPTIONS=MQCO_NONE;

/*****
/* CLOSE QUEUE */
/*****
CALL MQCLOSE (HCONN, /* CONNECTION HANDLE */
              HOBJ, /* OBJECT HANDLE */
              OPTIONS, /* CLOSE OPTIONS */
              COMPCODE, /* COMPLETION CODE */
              REASON); /* REASON CODE */

/*****
/* TEST THE COMPLETION CODE OF THE CLOSE CALL. */
/* IF THE CALL HAS FAILED ISSUE AN ERROR MESSAGE */
/* SHOWING THE COMPLETION CODE AND THE REASON CODE. */
/*****
IF COMPCODE ^= MQCC_OK
THEN DO;

:
CALL ERROR_ROUTINE;
END;

```

Figure 92. Using the MQCLOSE call (PL/I)

## Putting a message using MQPUT

Figure 93 demonstrates how to use the MQPUT call using context. This extract is not taken from the sample applications supplied with MQSeries.

```

%INCLUDE SYSLIB(CMQP);
%INCLUDE SYSLIB(CMQEPP);
:
/*****
/* WORKING STORAGE DECLARATIONS */
/*****
DCL COMPCODE          BINARY FIXED (31);
DCL REASON            BINARY FIXED (31);
DCL HCONN            BINARY FIXED (31);
DCL HOBJ             BINARY FIXED (31);
DCL OPTIONS          BINARY FIXED (31);
DCL BUFFLEN          BINARY FIXED (31);
DCL BUFFER            CHAR(80);
:
DCL PL1_TEST_MESSAGE CHAR(80)
INIT('***** THIS IS A TEST MESSAGE *****');
:
/*****
/* LOCAL COPY OF MESSAGE DESCRIPTOR */
/* AND PUT MESSAGE OPTIONS */
/*****
DCL 1 LMQMD LIKE MQMD;
DCL 1 LMQPMO LIKE MQPMO;
:
/*****
/* SET UP MESSAGE DESCRIPTOR */
/*****
LMQMD.MSGTYPE = MQMT_DATAGRAM;
LMQMD.PRIORITY = 1;
LMQMD.PERSISTENCE = MQPER_PERSISTENT;
LMQMD.REPLYTOQ = ' ';
LMQMD.REPLYTOQMGR = ' ';
LMQMD.MSGID = MQMI_NONE;
LMQMD.CORRELID = MQCI_NONE;

/*****
/* SET UP PUT MESSAGE OPTIONS */
/*****
LMQPMO.OPTIONS = MQPMO_NO_SYNCPOINT;

/*****
/* SET UP LENGTH OF MESSAGE BUFFER AND THE MESSAGE */
/*****
BUFFLEN = LENGTH(BUFFER);
BUFFER = PL1_TEST_MESSAGE;

/*****
/*
/* HCONN WAS SET BY PREVIOUS MQCONN REQUEST.
/* HOBJ WAS SET BY PREVIOUS MQOPEN REQUEST.
/*
/*****
CALL MQPUT (HCONN,
           HOBJ,
           LMQMD,
           LMQPMO,
           BUFFLEN,
           BUFFER,
           COMPCODE,
           REASON);

```

Figure 93 (Part 1 of 2). Using the MQPUT call (PL/I)

```

/*****
/* TEST THE COMPLETION CODE OF THE PUT CALL.          */
/* IF THE CALL HAS FAILED ISSUE AN ERROR MESSAGE     */
/* SHOWING THE COMPLETION CODE AND THE REASON CODE.  */
/*****
    IF COMPCODE ^= MQCC_OK
        THEN DO;

:
        CALL ERROR_ROUTINE;
    END;

```

Figure 93 (Part 2 of 2). Using the MQPUT call (PL/I)

## Putting a message using MQPUT1

Figure 94 demonstrates how to use the MQPUT1 call. This extract is not taken from the sample applications supplied with MQSeries.

```

%INCLUDE SYSLIB(CMQEPP);
%INCLUDE SYSLIB(CMQP);
:
/*****
/* WORKING STORAGE DECLARATIONS                      */
/*****
DCL COMPCODE          BINARY FIXED (31);
DCL REASON            BINARY FIXED (31);
DCL HCONN             BINARY FIXED (31);
DCL OPTIONS           BINARY FIXED (31);
DCL BUFFLEN           BINARY FIXED (31);
DCL BUFFER            CHAR(80);
:
DCL REPLY_TO_QUEUE    CHAR(48) INIT('PL1.REPLY.QUEUE');
DCL QUEUE_NAME        CHAR(48) INIT('PL1.LOCAL.QUEUE');
DCL PL1_TEST_MESSAGE  CHAR(80)
    INIT('***** THIS IS ANOTHER TEST MESSAGE *****');
:
/*****
/* LOCAL COPY OF OBJECT DESCRIPTOR, MESSAGE DESCRIPTOR */
/* AND PUT MESSAGE OPTIONS                             */
/*****
DCL 1 LMQOD LIKE MQOD;
DCL 1 LMQMD LIKE MQMD;
DCL 1 LMQPMO LIKE MQPMO;
:
/*****
/* SET UP OBJECT DESCRIPTOR AS REQUIRED.                */
/*****
LMQOD.OBJECTTYPE = MQOT_Q;
LMQOD.OBJECTNAME = QUEUE_NAME;

/*****
/* SET UP MESSAGE DESCRIPTOR AS REQUIRED.              */
/*****
LMQMD.MSGTYPE = MQMT_REQUEST;
LMQMD.PRIORITY = 5;
LMQMD.PERSISTENCE = MQPER_PERSISTENT;
LMQMD.REPLYTOQ = REPLY_TO_QUEUE;
LMQMD.REPLYTOQMGR = ' ';
LMQMD.MSGID = MQMI_NONE;
LMQMD.CORRELID = MQCI_NONE;

```

Figure 94 (Part 1 of 2). Using the MQPUT1 call (PL/I)

## PL/I examples

```

/*****
/* SET UP PUT MESSAGE OPTIONS AS REQUIRED */
/*****
    LMQPMO.OPTIONS = MQPMO_NO_SYNCPOINT;

/*****
/* SET UP LENGTH OF MESSAGE BUFFER AND THE MESSAGE */
/*****
    BUFFLEN = LENGTH(BUFFER);
    BUFFER = PL1_TEST_MESSAGE;

    CALL MQPUT1 (HCONN,
                LMQOD,
                LMQMD,
                LMQPMO,
                BUFFLEN,
                BUFFER,
                COMPCODE,
                REASON);

/*****
/* TEST THE COMPLETION CODE OF THE PUT1 CALL. */
/* IF THE CALL HAS FAILED ISSUE AN ERROR MESSAGE SHOWING */
/* THE COMPLETION CODE AND THE REASON CODE. */
/*****
    IF COMPCODE ^= MQCC_OK
        THEN DO;

        :
            CALL ERROR_ROUTINE;
        END;

```

Figure 94 (Part 2 of 2). Using the MQPUT1 call (PL/I)

## Getting a message

Figure 95 demonstrates how to use the MQGET call to remove a message from a queue. This extract is not taken from the sample applications supplied with MQSeries.

```

%INCLUDE SYSLIB(CMQP);
%INCLUDE SYSLIB(CMQEPP);
:
/*****
/* WORKING STORAGE DECLARATIONS */
/*****
    DCL COMPCODE          BINARY FIXED (31);
    DCL REASON           BINARY FIXED (31);
    DCL HCONN            BINARY FIXED (31);
    DCL HOBJ             BINARY FIXED (31);
    DCL BUFFLEN          BINARY FIXED (31);
    DCL DATALEN         BINARY FIXED (31);
    DCL BUFFER           CHAR(80);

:

```

Figure 95 (Part 1 of 2). Using the MQGET call (PL/I)

```

/*****
/* LOCAL COPY OF MESSAGE DESCRIPTOR AND */
/* GET MESSAGE OPTIONS */
/*****
    DCL 1 LMQMD LIKE MQMD;
    DCL 1 LMQGMO LIKE MQGMO;

:

/*****
/* SET UP MESSAGE DESCRIPTOR AS REQUIRED. */
/* MSGID AND CORRELID IN MQMD SET TO NULLS SO FIRST */
/* AVAILABLE MESSAGE WILL BE RETRIEVED. */
/*****
    LMQMD.MSGID = MQMI_NONE;
    LMQMD.CORRELID = MQCI_NONE;

/*****
/* SET UP GET MESSAGE OPTIONS AS REQUIRED. */
/*****
    LMQGMO.OPTIONS = MQGMO_NO_SYNCPOINT;

/*****
/* SET UP LENGTH OF MESSAGE BUFFER. */
/*****
    BUFFLEN = LENGTH(BUFFER);

/*****
/* HCONN WAS SET BY PREVIOUS MQCONN REQUEST. */
/* HOBJ WAS SET BY PREVIOUS MQOPEN REQUEST. */
/*****

    CALL MQGET (HCONN,
                HOBJ,
                LMQMD,
                LMQGMO,
                BUFFERLEN,
                BUFFER,
                DATALEN,
                COMPCODE,
                REASON);

/*****
/* TEST THE COMPLETION CODE OF THE GET CALL. */
/* IF THE CALL HAS FAILED ISSUE AN ERROR MESSAGE */
/* SHOWING THE COMPLETION CODE AND THE REASON CODE. */
/*****
    IF COMPCODE ^= MQCC_OK
        THEN DO;

        :
            CALL ERROR_ROUTINE;
        END;

```

Figure 95 (Part 2 of 2). Using the MQGET call (PL/I)

## Getting a message using the wait option

Figure 96 demonstrates how to use the MQGET call with the wait option and accepting truncated messages. This extract is not taken from the sample applications supplied with MQSeries.

```

%INCLUDE SYSLIB(CMQP);
%INCLUDE SYSLIB(CMQEPP);
:
/*****
/* WORKING STORAGE DECLARATIONS */
/*****
DCL COMPCODE          BINARY FIXED (31);
DCL REASON            BINARY FIXED (31);
DCL HCONN             BINARY FIXED (31);
DCL HOBJ              BINARY FIXED (31);
DCL BUFFLEN          BINARY FIXED (31);
DCL DATALEN         BINARY FIXED (31);
DCL BUFFER           CHAR(80);

:
/*****
/* LOCAL COPY OF MESSAGE DESCRIPTOR AND GET MESSAGE */
/* OPTIONS */
/*****
DCL 1 LMQMD LIKE MQMD;
DCL 1 LMQGMO LIKE MQGMO;

:
/*****
/* SET UP MESSAGE DESCRIPTOR AS REQUIRED. */
/* MSGID AND CORRELID IN MQMD SET TO NULLS SO FIRST */
/* AVAILABLE MESSAGE WILL BE RETRIEVED. */
/*****
LMQMD.MSGID = MQMI_NONE;
LMQMD.CORRELID = MQCI_NONE;

/*****
/* SET UP GET MESSAGE OPTIONS AS REQUIRED. */
/* WAIT INTERVAL SET TO ONE MINUTE. */
/*****
LMQGMO.OPTIONS = MQGMO_WAIT +
                MQGMO_ACCEPT_TRUNCATED_MSG +
                MQGMO_NO_SYNCPOINT;
LMQGMO.WAITINTERVAL=60000;

/*****
/* SET UP LENGTH OF MESSAGE BUFFER. */
/*****
BUFFLEN = LENGTH(BUFFER);

```

Figure 96 (Part 1 of 2). Using the MQGET call with the wait option (PL/I)

```

/*****
/*
/* HCONN WAS SET BY PREVIOUS MQCONN REQUEST. */
/* HOBJ WAS SET BY PREVIOUS MQOPEN REQUEST. */
/*
/*****

CALL MQGET (HCONN,
            HOBJ,
            LMQMD,
            LMQGMO,
            BUFFERLEN,
            BUFFER,
            DATALEN,
            COMPCODE,
            REASON);

/*****
/* TEST THE COMPLETION CODE OF THE GET CALL. */
/* TAKE APPROPRIATE ACTION BASED ON COMPLETION CODE AND */
/* REASON CODE. */
/*****
SELECT(COMPCODE);
    WHEN (MQCC_OK) DO; /* GET WAS SUCCESSFUL */

:

END;
WHEN (MQCC_WARNING) DO;
    IF REASON = MQRC_TRUNCATED_MSG_ACCEPTED
    THEN DO; /* GET WAS SUCCESSFUL */

:

END;
ELSE DO;

:

CALL ERROR_ROUTINE;
END;
WHEN (MQCC_FAILED) DO;

:

CALL ERROR_ROUTINE;
END;
END;
OTHERWISE;
END;

```

Figure 96 (Part 2 of 2). Using the MQGET call with the wait option (PL/I)

## Getting a message using signaling

Signaling is available only with MQSeries for OS/390.

Figure 97 demonstrates how to use the MQGET call with signaling. This extract is not taken from the sample applications supplied with MQSeries.

```

%INCLUDE SYSLIB(CMQP);
%INCLUDE SYSLIB(CMQEPP);
:
/*****
/* WORKING STORAGE DECLARATIONS */
/*****
DCL COMPCODE          BINARY FIXED (31);
DCL REASON            BINARY FIXED (31);
DCL HCONN             BINARY FIXED (31);
DCL HOBJ              BINARY FIXED (31);
DCL DATALEN         BINARY FIXED (31);
DCL BUFFLEN           BINARY FIXED (31);
DCL BUFFER            CHAR(80);

:
DCL ECB_FIXED          FIXED BIN(31);
DCL 1 ECB_OVERLAY BASED(ADDR(ECB_FIXED)),
    3 ECB_WAIT        BIT,
    3 ECB_POSTED      BIT,
    3 ECB_FLAG3_8     BIT(6),
    3 ECB_CODE        PIC'999';

:
/*****
/* LOCAL COPY OF MESSAGE DESCRIPTOR AND GET MESSAGE */
/* OPTIONS */
/*****
DCL 1 LMQMD LIKE MQMD;
DCL 1 LMQGMO LIKE MQGMO;

:
/*****
/* CLEAR ECB FIELD. */
/*****
ECB_FIXED = 0;

:
/*****
/* SET UP MESSAGE DESCRIPTOR AS REQUIRED. */
/* MSGID AND CORRELLID IN MQMD SET TO NULLS SO FIRST */
/* AVAILABLE MESSAGE WILL BE RETRIEVED. */
/*****
LMQMD.MSGID = MQMI_NONE;
LMQMD.CORRELLID = MQCI_NONE;
/*****
/* SET UP GET MESSAGE OPTIONS AS REQUIRED. */
/* WAIT INTERVAL SET TO ONE MINUTE. */
/*****
LMQGMO.OPTIONS = MQGMO_SET_SIGNAL +
                MQGMO_NO_SYNCPOINT;
LMQGMO.WAITINTERVAL=60000;
LMQGMO.SIGNAL1 = ADDR(ECB_FIXED);

```

Figure 97 (Part 1 of 3). Using the MQGET call with signaling (PL/I)

```

/*****
/* SET UP LENGTH OF MESSAGE BUFFER. */
/* CALL MESSGE RETRIEVAL ROUTINE. */
/*****
BUFFLEN = LENGTH(BUFFER);
CALL GET_MSG;

/*****
/* TEST THE COMPLETION CODE OF THE GET CALL. */
/* TAKE APPROPRIATE ACTION BASED ON COMPLETION CODE AND */
/* REASON CODE. */
/*****
SELECT;
    WHEN ((COMPCODE = MQCC_OK) &
          (REASON = MQCC_NONE)) DO

:
    CALL MSG_ROUTINE;

:
    END;
    WHEN ((COMPCODE = MQCC_WARNING) &
          (REASON = MQRC_SIGNAL_REQUEST_ACCEPTED)) DO;

:
    CALL DO_WORK;

:
    END;
    WHEN ((COMPCODE = MQCC_FAILED) &
          (REASON = MQRC_SIGNAL_OUTSTANDING)) DO;

:
    CALL DO_WORK;

:
    END;
    OTHERWISE DO; /* FAILURE CASE */
/*****
/* ISSUE AN ERROR MESSAGE SHOWING THE COMPLETION CODE */
/* AND THE REASON CODE. */
/*****
:
    CALL ERROR_ROUTINE;

:
    END;
END;

:

```

Figure 97 (Part 2 of 3). Using the MQGET call with signaling (PL/I)

```

DO_WORK: PROC;
:
  IF ECB_POSTED
    THEN DO;
      SELECT(ECB_CODE);
      WHEN(MQEC_MSG_ARRIVED) DO;
:
      CALL GET_MSG;
:
      END;
      WHEN(MQEC_WAIT_INTERVAL_EXPIRED) DO;
:
      CALL NO_MSG;
:
      END;
      OTHERWISE DO;      /* FAILURE CASE */
/*****
/* ISSUE AN ERROR MESSAGE SHOWING THE COMPLETION CODE */
/* AND THE REASON CODE. */
*****/
:
      CALL ERROR_ROUTINE;
:
      END;
      END;
      END;
:
END DO_WORK;

GET_MSG: PROC;
/*****
/*
/* HCONN WAS SET BY PREVIOUS MQCONN REQUEST. */
/* HOBJ WAS SET BY PREVIOUS MQOPEN REQUEST. */
/* MD AND GMO SET UP AS REQUIRED. */
/*
*****/
      CALL MQGET (HCONN,
                  HOBJ,
                  LMQMD,
                  LMQGMO,
                  BUFFLEN,
                  BUFFER,
                  DATALEN,
                  COMPCODE,
                  REASON);

      END GET_MSG;

NO_MSG: PROC;
:
      END NO_MSG;

```

Figure 97 (Part 3 of 3). Using the MQGET call with signaling (PL/I)

## Inquiring about the attributes of an object

Figure 98 demonstrates how to use the MQINQ call to inquire about the attributes of a queue.

This extract is not taken from the sample applications supplied with MQSeries.

```

      %INCLUDE SYSLIB(CMQP);
      %INCLUDE SYSLIB(CMQEPP);
      :
/*****
/* WORKING STORAGE DECLARATIONS */
*****/
      DCL COMPCODE          BINARY FIXED (31);
      DCL REASON            BINARY FIXED (31);
      DCL HCONN             BINARY FIXED (31);
      DCL HOBJ              BINARY FIXED (31);
      DCL OPTIONS           BINARY FIXED (31);
      DCL SELECTORCOUNT   BINARY FIXED (31);
      DCL INTATTRCOUNT   BINARY FIXED (31);
      DCL 1 SELECTOR_TABLE,
          3 SELECTORS(5)      BINARY FIXED (31);
      DCL 1 INTATTR_TABLE,
          3 INTATTRS(5)      BINARY FIXED (31);
      DCL CHARATTRLENGTH   BINARY FIXED (31);
      DCL CHARATTRS        CHAR(100);
:
/*****
/* SET VARIABLES FOR INQUIRE CALL */
/* INQUIRE ON THE CURRENT QUEUE DEPTH */
*****/
      SELECTORS(01) = MQIA_CURRENT_Q_DEPTH;

      SELECTORCOUNT = 1;
      INTATTRCOUNT = 1;

      CHARATTRLENGTH = 0;
/*****
/*
/* HCONN WAS SET BY PREVIOUS MQCONN REQUEST. */
/* HOBJ WAS SET BY PREVIOUS MQOPEN REQUEST. */
/*
*****/
      CALL MQINQ (HCONN,
                  HOBJ,
                  SELECTORCOUNT,
                  SELECTORS,
                  INTATTRCOUNT,
                  INTATTRS,
                  CHARATTRLENGTH,
                  CHARATTRS,
                  COMPCODE,
                  REASON);

```

Figure 98 (Part 1 of 2). Using the MQINQ call (PL/I)

## PL/I examples

```
/******  
/* TEST THE COMPLETION CODE OF THE INQUIRE CALL. */  
/* IF THE CALL HAS FAILED ISSUE AN ERROR MESSAGE SHOWING */  
/* THE COMPLETION CODE AND THE REASON CODE. */  
/******  
    IF COMPCODE ^= MQCC_OK  
        THEN DO;  
  
    :  
        CALL ERROR_ROUTINE;  
    END;
```

Figure 98 (Part 2 of 2). Using the MQINQ call (PL/I)

## Setting the attributes of a queue

Figure 99 demonstrates how to use the MQSET call to change the attributes of a queue. This extract is not taken from the sample applications supplied with MQSeries.

```
    %INCLUDE SYSLIB(CMQP);  
    %INCLUDE SYSLIB(CMQEPP);  
    :  
/******  
/* WORKING STORAGE DECLARATIONS */  
/******  
    DCL COMPCODE          BINARY FIXED (31);  
    DCL REASON            BINARY FIXED (31);  
    DCL HCONN             BINARY FIXED (31);  
    DCL HOBJ              BINARY FIXED (31);  
    DCL OPTIONS           BINARY FIXED (31);  
    DCL SELECTORCOUNT    BINARY FIXED (31);  
    DCL INTATTRCOUNT    BINARY FIXED (31);  
    DCL 1 SELECTOR_TABLE,  
        3 SELECTORS(5)      BINARY FIXED (31);  
    DCL 1 INTATTR_TABLE,  
        3 INTATTRS(5)      BINARY FIXED (31);  
    DCL CHARATTRLENGTH    BINARY FIXED (31);  
    DCL CHARATTRS         CHAR(100);  
  
    :  
  
/******  
/* SET VARIABLES FOR SET CALL */  
/* SET GET AND PUT INHIBITED */  
/******  
  
    SELECTORS(01) = MQIA_INHIBIT_GET;  
    SELECTORS(02) = MQIA_INHIBIT_PUT;  
  
    INTATTRS(01) = MQQA_GET_INHIBITED;  
    INTATTRS(02) = MQQA_PUT_INHIBITED;  
  
    SELECTORCOUNT = 2;  
    INTATTRCOUNT = 2;  
  
    CHARATTRLENGTH = 0;
```

Figure 99 (Part 1 of 2). Using the MQSET call (PL/I)

```
/******  
/* */  
/* HCONN WAS SET BY PREVIOUS MQCONN REQUEST. */  
/* HOBJ WAS SET BY PREVIOUS MQOPEN REQUEST. */  
/* */  
/******  
    CALL MQSET (HCONN,  
                HOBJ,  
                SELECTORCOUNT,  
                SELECTORS,  
                INTATTRCOUNT,  
                INTATTRS,  
                CHARATTRLENGTH,  
                CHARATTRS,  
                COMPCODE,  
                REASON);
```

```
/******  
/* TEST THE COMPLETION CODE OF THE SET CALL. */  
/* IF THE CALL HAS FAILED ISSUE AN ERROR MESSAGE SHOWING */  
/* THE COMPLETION CODE AND THE REASON CODE. */  
/******  
    IF COMPCODE ^= MQCC_OK  
        THEN DO;  
  
    :  
        CALL ERROR_ROUTINE;  
    END;
```

Figure 99 (Part 2 of 2). Using the MQSET call (PL/I)

## Appendix G. MQSeries data definition files

MQSeries provides data definition files to assist you with the writing of your applications. Data definition files are also known as:

Language	Data definitions
C	Include files or header files
Visual Basic	Module files
COBOL	Copy files
Assembler	Macros
PL/I	Include files
TAL	Header files

See Appendix A, “Language compilers and assemblers” on page 453 for the compilers that are supported and suitable for use with these data definition files.

The data definition files to assist with the writing of channel exits are described in the “Data definition files” in the *MQSeries Intercommunication* book.

The data definition files to assist with the writing of installable services exits are described in Appendix C, “Header, COPY, and INCLUDE files” in the *MQSeries Programmable System Management* book.

For data definition files supported on C++, see the *MQSeries Using C++* book.

For data definition files supported on RPG, see the *MQSeries for AS/400 Application Programming Reference (RPG)* book.

The names of the data definition files have the prefix CMQ, and a suffix that is determined by the programming language:

Suffix	Language
<b>a</b>	Assembler language
<b>b</b>	Visual Basic
<b>c</b>	C
<b>l</b>	COBOL (without initialized values)
<b>p</b>	PL/I
<b>v</b>	COBOL (with default values set)

### Installation library

The name **thlqual** is the high-level qualifier of the installation library on OS/390.

## C language include files

The MQSeries C include files are listed in Table 48. They are installed in the following directories or libraries:

Platform	Installation directory or library
AIX	/usr/mqm/inc/
Digital OpenVMS	/mqm/inc/
Other UNIX platforms	/opt/mqm/inc/
OS/2	\mqm\tools\c\include
Windows NT	\Program Files\MQSeries\Tools\C\Include
Windows V2.0	\MQWINCLUDE
Windows V2.1	\Program Files\MQSeries for Windows\Lib
OS/390	thlqual.SCSQC370
Tandem NSK	\$volume.zmqslib
VSE/ESA	PRD2.MQSERIES

### Notes:

1. For UNIX platforms (not including Digital OpenVMS), the include files are symbolically linked into /usr/include.
2. For AS/400, include files are supplied as members of H in library QMQM.

For more information on the structure of directories, see Appendix B, "Directory structure (UNIX systems)" (for MQSeries for AIX, HP-UX, and Sun Solaris), Appendix C, "Directory structure (OS/2)," and Appendix D, "Directory structure (Windows NT)," in the *MQSeries System Administration* book; for other platforms, see the appropriate *System Management Guide*.

Table 48. C include files for MQSeries

File name	Contents
<cmqc.h>	Call prototypes, data types, structures, return codes, and constants
<cmqfc.h> (1, 2)	Definitions for programmable commands
<cmqxc.h>(2)	Definitions for channel exits and data-conversion exits
<cmqzc.h>(2, 3, 4)	Definitions for installable services exits
<p><b>Notes:</b> The files are protected against multiple declaration, so you can include them many times.</p> <ol style="list-style-type: none"> <li>1. MQSeries for Windows does not provide this include file.</li> <li>2. MQSeries for VSE/ESA does not provide this include file.</li> <li>3. MQSeries for OS/390 and MQSeries for Windows do not provide this include file.</li> <li>4. Not provided on MQSeries for AS/400.</li> <li>5. On Tandem NSK filenames cannot contain a period (.) so the header filenames are &lt;cmqch&gt; and so on.</li> </ol>	

## Visual Basic module files

MQSeries for Windows Version 2.0 provides two Visual Basic module files. They are listed in Table 49 and installed in \MQW\INCLUDE.

<i>Table 49. Visual Basic module files for MQSeries for Windows V2.0</i>	
<b>File name</b>	<b>Contents</b>
CMQB3.BAS	Call declarations, data types, and named constants for the 16-bit MQI.(1)
CMQB4.BAS	Call declarations, data types, and named constants for both the 16-bit and 32-bit MQI.(2)
<b>Notes:</b>	
1. Use this with Microsoft Visual Basic Version 3.	
2. Use this with Microsoft Visual Basic Version 4.	

MQSeries for Windows Version 2.1 provides two Visual Basic module files. They are listed in Table 50 and installed in \Program Files\MQSeries for Windows\Lib.

<i>Table 50. Visual Basic module files for MQSeries for Windows V2.1</i>	
<b>File name</b>	<b>Contents</b>
CMQB.BAS	Call declarations, data types, and named constants for the main MQI.
CMQB4.BAS	Call declarations, data types, and named constants for the channel exits.
<b>Note:</b> In a default installation, the form files (.BAS) are supplied in the \Program Files\MQSeries for Windows\Include subdirectory.	

MQSeries for Windows NT V5.1 provides four Visual Basic module files. They are listed in Table 51 and installed in \Program Files\MQSeries\Tools\Samples\VB\Include.

<i>Table 51. Visual Basic module files for MQSeries for Windows NT V5.1</i>	
<b>File name</b>	<b>Contents</b>
CMQB.BAS	Call declarations, data types, and named constants for the main MQI.
CMQBB.BAS	Call declarations, data types, and named constants for MQAI support.
CMQCFB.BAS	Call declarations, data types, and named constants for PCF support.
CMQXB.BAS	Call declarations, data types, and named constants for the channel exits.

## COBOL copy files

For COBOL, MQSeries provides separate copy files containing the named constants, and two copy files for each of the structures. There are two copy files for each structure because each is provided both with and without initial values:

- In the WORKING-STORAGE SECTION of a COBOL program, use the files that initialize the structure fields to default values. These structures are defined in the copy files that have names suffixed with the letter “V” (values).
- In the LINKAGE SECTION of a COBOL program, use the structures without initial values. These structures are defined in copy files that have names suffixed with the letter “L” (linkage).

The MQSeries COBOL copy files are listed in Table 52 on page 533. They are installed in the following directories:

Platform	Installation directory or library
AIX	/usr/mqm/inc/
Digital OpenVMS	/mqm/inc/
Other UNIX platforms	/opt/mqm/inc/
OS/2	\mqm\tools\cobol\copybook (for Micro Focus COBOL) \mqm\tools\cobol\copybook\VAcobol (for IBM VisualAge COBOL)
Windows NT	\Program Files\MQSeries\Tools\Cobol\Copybook (for Micro Focus COBOL) \Program Files\MQSeries\Tools\Cobol\Copybook\VAcobol (for IBM VisualAge COBOL)
OS/390	thlqual.SCSQCOBC
Tandem NSK	\$volume.zmqslib
VSE/ESA	PRD2.MQSERIES

**Notes:** For AS/400, they are supplied in the library QMQM:

For OPM, they are supplied as members of the file QLBLSRC.

For ILE, they are supplied as members of the file QCBLLESRC.

For Tandem NSK, all the sections are contained in one ENSCRIBE file CMPCOBOL.

<i>Table 52. COBOL copy files</i>		
<b>File name (with initial values)</b>	<b>File name (without initial values)</b>	<b>Contents</b>
CMQBOV (not AS/400)	CMQBOL (not AS/400)	Begin options structure (MQBO)
CMQCFV (OS/390 only)	not applicable	Additional named constants for events and PCF commands
CMQCIHV	CMQCIHL	CICS information header structure
CMQCNOV	CMQCNO	Connect options structure (MQCNO)
CMQDHV	CMQDHL	Distribution header structure (MQDH)
CMQDLHV	CMQDLHL	Dead-letter (undelivered-message) header structure (MQDLH)
CMQDXPV	CMQDXPL	Data-conversion exit parameter structure (MQDXP)
CMQGMOV	CMQGMOL	Get-message options structure (MQGMO)
CMQIIHV	CMQIIHL	IMS header structure (MQIIH)
CMQMDEV	CMQMDEL	Message descriptor extension structure (MQMDE)
CMQMDV	CMQMDL	Message descriptor structure (MQMD)
CMQODV	CMQODL	Object descriptor structure (MQOD)
CMQORV	CMQORL	Object record structure (MQOR)
CMQPMOV	CMQPMOL	Put-message options structure (MQPMO)
CMQRRV	CMQRRL	Response record structure (MQRR)
CMQTMCV	CMQTMCL	Trigger-message structure (character format)
CMQTM2V	CMQTM2L	Trigger-message structure (character format) (MQTMC)
CMQTMV	CMQTML	Trigger-message structure (MQTM)
CMQV	not applicable	Named constants for the MQI
CMQWIHV	CMQWIHL	Work-information header structure
CMQXQHV	CMQXQHL	Transmission-queue header structure (MQXQH)
CMQXV	not applicable	Named constants for exits

Include in your program only those files you need. Do this with one or more COPY statements after a level-01 declaration. This means you can include multiple versions of the structures in a program if necessary. However, note that CMQV is a large file.

## COBOL copy files

Here is an example of COBOL code for including the CMQMDV copy file:

```
01 MQM-MESSAGE-DESCRIPTOR.  
    COPY CMQMDV.
```

Each structure declaration begins with a level-10 item; this means you can declare several instances of the structure by coding the level-01 declaration followed by a COPY statement to copy in the remainder of the structure declaration. To refer to the appropriate instance, use the IN keyword.

Here is an example of COBOL code for including two instances of CMQMDV:

```
* Declare two instances of MQMD  
01 MY-CMQMD.  
    COPY CMQMDV.  
01 MY-OTHER-CMQMD.  
    COPY CMQMDV.  
  
*  
* Set MSGTYPE field in MY-OTHER-CMQMD  
    MOVE MQMT-REQUEST TO MQMD-MSGTYPE IN MY-OTHER-CMQMD.
```

The structures should be aligned on 4-byte boundaries. If you use the COPY statement to include a structure following an item that is not the level-01 item, try to ensure that the structure is a multiple of 4-bytes from the start of the level-01 item. If you do not do this, you may get a reduction in the performance of your application.

The structures are described in Chapter 2, "Data type descriptions - structures" in the *MQSeries Application Programming Reference* manual. The descriptions of the field in the structures show the names of fields without a prefix. In COBOL programs you must prefix the field names with the name of the structure followed by a hyphen, as shown in the COBOL declarations. The fields in the structure copy files are prefixed this way.

The field names in the declarations in the structure copy files are in uppercase. You can use mixed case or lowercase instead. For example, the field *StrucId* of the MQGMO structure is shown as MQGMO-STRUCID in the COBOL declaration and in the copy file.

The V-suffix structures are declared with initial values for all of the fields, so you need to set only those fields where the value required is different from the initial value.

## System/390 assembler-language macros

MQSeries for OS/390 provides two assembler-language macros containing the named constants, and one macro to generate each structure. They are listed in Table 53 and installed in **thlqual.SCSQMACS**.

Table 53. System/390 assembler-language macros

Macro	Contents
CMQA	Values of the return codes for the API calls Constants for filling in the option fields Constants for each object attribute, used by the MQINQ and MQSET calls
CMQCFA	Additional named constants for events and PCF commands
CMQCIHA	CICS information-header structure
CMQDLHA	Definition of the MQDLH structure
CMQDXPA	Definition of the MQDXP structure
CMQGMOA	Definition of the MQGMO structure
CMQIIHA	Definition of the MQIIH structure
CMQMDA	Definition of the MQMD structure
CMQODA	Definition of the MQOD structure
CMQPMOA	Definition of the MQPMO structure
CMQTMA	Definition of the MQTM structure
CMQTMC2A	Definition of the MQTMC2 structure
CMQWIHA	Work-information header structure
CMQXA	Constants for exits
CMQXPA	Definition of the MQXP structure
CMQXQHA	Definition of the MQXQH structure

These macros are called using code like this:

```
MY_MQMD CMQMDA EXPIRY=0,MSGTYPE=MQMT_DATAGRAM
```

## PL/I include files

MQSeries for OS/390, AIX, OS/2 Warp, and Windows NT provide include files that contain all the definitions you need when you write MQSeries applications in PL/I. They are listed in Table 54. They are installed in the following directories:

Platform	Installation directory or library
AIX	/usr/mqm/inc/
OS/2	\mqm\tools\pli\include
Windows NT	\Program Files\MQSeries\Tools\PLI\Include
OS/390	thlqual.SCSQPLIC
VSE/ESA	PRD2.MQSERIES

Table 54. PL/I include files

Include file	Contents
CMQCFP(1)	Definitions for programmable commands
CMQEPP	Entry point definitions for the API calls.
CMQP	Definitions of all the constants and return codes, data types and structures, and constants to initialize the structures.
CMQXP(1)	Definitions for channel exits and data-conversion exits on OS/390. Named constants related to PCF on AIX, OS/2 Warp, and Windows NT.
<b>Note:</b>	
1. MQSeries for VSE/ESA does not provide this include file.	

Include these files in your program if you are going to link the MQSeries stub to your program (see “Preparing your program to run” on page 275). Include only CMQP if you intend to link the MQSeries calls dynamically (see “Dynamically calling the MQSeries stub” on page 279). Dynamic linking can be performed for batch and IMS programs only.

## Appendix H. List of MQSeries products

At the time of publication of this document, MQSeries products were available for the hardware and software platforms listed below.

Some of the products in the list have been renamed. For those products, the name by which the product used to be known is given, as well as the current product name.

These products fall into two broad categories, Level 1 and Level 2, in respect of the function they support. These are referred to in Appendix I, "MQSeries platforms - functional comparisons" on page 539.

### Level 1 products

<i>Table 55. MQSeries products, Level 1</i>	
Product name	Previous name
MQSeries for UnixWare V1.4.1	ezBRIDGE Transact on UnixWare for MQSeries Release 3.0

### Level 2 products

<i>Table 56. MQSeries products, Level 2</i>		
Product name	Server	Client
MQSeries for AIX V5.1	Yes	Yes
MQSeries for AS/400 V4R2M1	Yes	No
MQSeries for AT&T GIS UNIX V2.2	Yes	Yes
MQSeries for Digital OpenVMS V2.2	Yes	Yes
MQSeries for HP-UX V5.1	Yes	Yes
MQSeries for OS/2 Warp V5.1	Yes	Yes
MQSeries for OS/390 V2.1 (formerly MQSeries for MVS/ESA)	Yes	No
MQSeries for SINIX and DC/OSx V2.2	Yes	Yes
MQSeries for Sun Solaris V5.1	Yes	Yes
MQSeries for Tandem NonStop Kernel V2.2	Yes	No
MQSeries for VSE/ESA V2.1	Yes	No
MQSeries for Windows V2.0	No	No
MQSeries for Windows V2.1	No	No
MQSeries for Windows NT V5.1	Yes	Yes



---

## Appendix I. MQSeries platforms - functional comparisons

This describes the functional differences between MQSeries queue manager products, concentrating on the functionality relating to the Message Queue Interface (MQI).

You may need this information for the following:

- Program migration when the queue-manager is upgraded

Programs written to work with one MQSeries queue manager will migrate unchanged, with only a relink, when the queue manager is upgraded to one which offers more function, operating on the same platform. You may, alternatively, want to plan for additional functionality.

- Program migration from one platform to another

You may need to write programs in such a way that they are readily ported to a different platform on which there is another MQSeries queue manager.

- Personnel migration

You may need to become familiar with the functionality of more than one MQSeries queue manager.

- Message movement

Most of the functional differences are not relevant to the progress of messages from one platform (or queue manager) to another. However a few are relevant, for example differences in the maximum message size that is supported. See "Message properties and protocols" on page 551 for differences which are relevant in this area.

---

### What is included here

Enough information about the functions is given here to allow you to understand the differences between the products. For detailed information, see the *MQSeries Application Programming Reference* manual.

The categories used here are:

- Syncpoint (see page 540)
- Triggering (see page 544)
- Input (see page 547)
- Message properties (see page 551)
- Threading (see page 555)
- Security (see page 556)
- Object types (see page 560)
- Administration (see page 562)
- Programming languages (see page 564)
- Connection (see page 566)

Within each category, a summary table of differences is given, and a brief explanation of the features involved. Differences between support by the various products are discussed, and recommendations made for ways in which migration can be made easier.

## Syncpoint

Table 57. Syncpoint support - function summary

Product	Syncpoint available	Coordination with other RMs	Coordination of other RMs	No syncpoint options (1)	Syncpoint options (2)	Default	Browse with lock	Backout count	Mark skip backout
A	Yes	No	No	Accepted (checked)	Accepted (checked)	No syncpoint	Yes	Yes	No
C	Yes	CICS, IMS, or RRS resources	No	Accepted (checked)	Accepted (checked)	Syncpoint	No	Yes	Yes
D	Yes	CICS or other resources	Yes	Accepted (checked)	Accepted (checked)	No syncpoint	Yes	Yes	No
E	Yes	CICS and OS/400 resources	No	Accepted (checked)	Accepted (checked)	No syncpoint	Yes	Yes	No
G	Yes	TMF resources	No	Rejected	Accepted	Syncpoint	No	No	No
H	No	No	No	Accepted	Rejected	No syncpoint	Yes	No	No
I	Yes	CICS resources	No	Rejected	Accepted	Syncpoint	Yes	No	No
J	Yes	No	No	Accepted	Accepted	No syncpoint	No	Yes	No
K	Yes	No	No	Accepted	Accepted	No syncpoint	No	Yes	No
L	Yes	CICS or other resources	Yes	Accepted (checked)	Accepted (checked)	No syncpoint	Yes	Yes	No
M	Yes	CICS or other resources	No	Accepted (checked)	Accepted (checked)	No syncpoint	Yes	Yes	No
N	Yes	CICS or other resources	Yes	Accepted (checked)	Accepted (checked)	No syncpoint	Yes	Yes	No

**Note:**

1. MQGMO\_NO\_SYNCPOINT for MQGET, and MQPMO\_NO\_SYNCPOINT for MQPUT and MQPUT1
2. MQGMO\_SYNCPOINT for MQGET, and MQPMO\_SYNCPOINT for MQPUT and MQPUT1
3. Not required since shared input is not supported

**Product key:**

- A MQSeries for Digital OpenVMS V2.2
- C MQSeries for OS/390 V2.1
- D MQSeries for OS/2 Warp V5.1
- E MQSeries for AS/400 V4R2M1
- G MQSeries for Tandem NonStop Kernel V2.2
- H MQSeries for UnixWare V1.4.1
- I MQSeries for VSE/ESA V2.1
- J MQSeries for Windows V2.0
- K MQSeries for Windows V2.1
- L MQSeries for Windows NT V5.1
- M MQSeries V2 for UNIX systems.  
This includes MQSeries for AT&T GIS UNIX V2.2 and MQSeries for SINIX and DC/OSx V2.2.
- N MQSeries V5 for UNIX systems.  
This includes MQSeries for AIX V5.1, MQSeries for HP-UX V5.1, and MQSeries for Sun Solaris V5.1.

Syncpoint coordination for MQSeries allows coordination of the effect of a number of get or put, or both, actions issued from the same application within a single unit of work, so that either all of these actions take place automatically, or none of them does. Usually other actions, such as file or database updates, can also be coordinated within the same unit of work.

A resource manager that participates in syncpoint is a component which owns a particular resource, such as a file system. The resource manager controls updates to that resource so that updates made from a particular unit of work are not visible from outside that unit of work until a syncpoint is reached. At that time, depending upon whether the syncpoint action is to commit or backout, all of the updates made from within the unit of work are either made permanent, and visible to other units of work, or backed out, so that other units of work never see them. If the updates are made, they are made automatically. This will happen even if the application or the system fails at any point. In order to carry out this action, the resource manager must log changes, and lock uncommitted changes to prevent other units of work from seeing them.

If the updates from more than one resource manager are to be coordinated, then the services of a syncpoint coordinator are required. If the updates from all of the resource managers are to take place automatically, then two-phase commit is needed; otherwise, or if only one resource manager is involved, single-phase commit is all that is needed. On MQSeries Version 5 products, MQSeries can act as a syncpoint coordinator coordinating other resource managers.

Note the variation between platforms in the calls to declare the syncpoint, and indicate the application's decision to commit or backout. Also, in some cases, there is a variation between platforms in calls to declare the start of a new unit of work. For MQSeries for OS/390 batch, MQSeries for OS/2 Warp V5.0, MQSeries Version 2 for UNIX systems, and MQSeries for Windows NT applications, these calls are provided through the MQI, otherwise they are provided by the environment. MQSeries for OS/2 Warp V5.0, MQSeries Version 2 for UNIX systems and MQSeries for Windows NT support both internally-coordinated units of work (using the MQI) and externally-coordinated units of work.

In some cases these calls need not be issued at all by the application. For example, if an application terminates abnormally before committing its unit of work, the unit of work will be backed out automatically. Similarly, if a CICS transaction terminates normally, it is as if it had committed the unit of work.

### **Level 1 product range support**

The products in this range never act as a resource manager. An underlying file or database system is always used to hold the message queues. The resource manager is the owner of the appropriate file or database system. This means that the underlying system controls whether or not the MQI gets and puts participate in a syncpoint operation. In some cases the underlying system is never coordinated, so in these cases MQI gets and puts are never coordinated.

In other cases, whether the underlying system is coordinated depends upon how the user has set it up. The setup can specify that actions on some queues are always coordinated, while those on others are never coordinated.

A product in this subset will not be informed of this, and therefore does not have any record of whether the MQI request will be coordinated. If it is coordinated,

## Comparison - syncpoint

however, it will be fully coordinated with any other updates to the underlying system, since only a single resource manager is involved. Additionally, if this resource manager acts as a participant with other resource managers, under the control of a syncpoint coordinator, MQI requests will also be coordinated with updates to the resources owned by these other resource managers. Where an MQI call might or might not be coordinated depending upon the setup, the queue manager accepts both syncpoint and no-syncpoint options, without being able to validate that the option will be honored.

### Level 1—browse-with-lock support

Where there is no syncpoint support, an application can be written in order to avoid the possibility of losing incoming messages if the system or application crashes:

```
Do forever
  MQGET with MQGMO_BROWSE_FIRST
  Process message, and make updates as necessary
  MQGET with MQGMO_MSG_UNDER_CURSOR
End
```

If there is a failure before the updates are complete, the message is still available on the input queue after restart. The second MQGET deletes the message from the queue.

However, if more than one application can process the queue, this technique is not adequate, since several applications might browse the message at the top of the queue and begin making updates on its behalf.

To overcome this, a browse-with-lock feature is supported on platforms that don't have any syncpoint capability but do support shared input. This enables an application to browse the first message on the queue, locking it at the same time so that it is not available to other applications. The application is written in a similar way, except that the MQGMO\_LOCK option is added for the initial browse:

```
Do forever
  MQGET with MQGMO_BROWSE_FIRST and MQGMO_LOCK
  Process message, and make updates as necessary
  MQGET with MQGMO_MSG_UNDER_CURSOR
End
```

### Level 2 product range support

In Level 2 products, management of the message queues is not delegated to an underlying file system. These products always act as a resource manager, and include full coordination with the other resource managers, except for:

- OS/390 batch applications, and
- MQSeries Version 2 for UNIX systems, MQSeries for OS/2 V2.0.1, and MQSeries for Windows NT V2.0 if there is no external coordinator available,

where syncpoint facilities only apply to MQI requests.

The full MQI support enables applications to specify, on a particular get or put request, whether or not this request is to be coordinated within a unit of work. If they do not specify this, a default is taken.

The full MQI also provides a *BackoutCount*, which informs the getter of a message how many times this message has been retrieved and subsequently backed out.

The count may be inaccurate, unless the *HardenGetBackout* local queue attribute for the queue specifies that it should be hardened. This does carry a resulting performance penalty. This count can be used as an indication that a message might be causing the application to terminate abnormally and that the application should not attempt to process it again. Of course, the message might have been backed out for reasons unconnected with the message itself - for example, a system crash.

On the MQSeries for OS/390 queue manager only, the option `MQGMO_MARK_SKIP_BACKOUT` can be issued with an `MQGET` call. This is an advanced option, which can be used if the application might make some updates as a result of an input message, but might then discover that these updates should be backed out without reinstating the input message on the queue (since it would only give the same result when it was processed the next time).

## Migration recommendations

1. If your application is not sensitive to whether the gets and puts are within syncpoint scope, do not specify the syncpoint or `no_syncpoint` options with `MQGET`, `MQPUT`, and `MQPUT1`.
2. If your application is designed to run without syncpoint, always specify the `no_syncpoint` options (`MQGMO_NO_SYNCPOINT` and `MQPMO_NO_SYNCPOINT`) with `MQGET`, `MQPUT`, and `MQPUT1`. With queue managers that accept these options but do not validate them, ensure that the underlying file or database system is set up so that operations on the relevant objects do not participate in syncpoint.

If you want to port this application to a platform that always has syncpoint, the application will have to be modified.

3. If your application is designed to run with syncpoint, always specify the syncpoint options (`MQGMO_SYNCPOINT` and `MQPMO_SYNCPOINT`) with `MQGET`, `MQPUT`, and `MQPUT1`. With queue managers that accept these options but do not validate them, ensure that the underlying file or database system is set up so that operations on the relevant objects do participate in syncpoint.

If you want to port this application to a platform that does not support syncpoint, the application will have to be modified. Use the browse technique outlined above, with lock support if multiple applications can service the queue.

If you have already written the application in this way, and now wish to port it to a platform that does support syncpoint, it will have to be changed to use the syncpoint support rather than the browse-with-lock technique. However, MQSeries Version 2 for UNIX systems and MQSeries for OS/2 Warp V5.0 do support the lock option to allow you to move your application without making the changes. If you are writing a new application on either of these platforms you are recommended to use syncpoint support.

4. Try to avoid `MQGMO_MARK_SKIP_BACKOUT` if portability is important. If the database is designed so that the application can establish, before making any updates, that the transaction can be processed successfully, this option will not be necessary.
5. Avoid using the *BackoutCount* if portability beyond the Level 2 queue managers is important.

## Triggering

<i>Table 58. Triggering support - function summary</i>				
Product	Triggering	Depth, priority triggering	Type of applications started	Passed to started application (1)
A	Yes	Yes	VMS system applications	MQTM structure
C	Yes	Yes	CICS or IMS (2)	MQTM structure for CICS; MQTMC2 structure for IMS
D	Yes	Yes	OS/2 applications (including CICS)	MQTMC2 structure
E	Yes	Yes	OS/400 applications (including CICS)	MQTMC2 structure
G	Yes	Yes	Tandem NSK applications	MQTMC2 structure
H	No	No	-	-
I	Yes	No	CICS only	MQTM structure
J	No	No	-	-
K	No	No	-	-
L	Yes	Yes	Windows NT applications (including CICS)	MQTMC2 structure
M	Yes	Yes	UNIX systems applications (including CICS)	MQTMC2 structure
N	Yes	Yes	UNIX systems applications (including CICS)	MQTMC2 structure

**Note:**

1. MQTMC is a version of the trigger message (MQTM) structure, in which the two binary fields in the structure are replaced with character fields of the same length. MQTMC2 is a version of the trigger message structure, in which the two binary fields in the structure are replaced with character fields of the same length and to which the queue manager name has been added.
2. There is currently no automatic support supplied for starting OS/390 batch applications. However, this could be added by a user.

**Product key:**

- A MQSeries for Digital OpenVMS V2.2
- C MQSeries for OS/390 V2.1
- D MQSeries for OS/2 Warp V5.1
- E MQSeries for AS/400 V4R2M1
- G MQSeries for Tandem NonStop Kernel V2.2
- H MQSeries for UnixWare V1.4.1
- I MQSeries for VSE/ESA V2.1
- J MQSeries for Windows V2.0
- K MQSeries for Windows V2.1
- L MQSeries for Windows NT V5.1
- M MQSeries V2 for UNIX systems.  
This includes MQSeries for AT&T GIS UNIX V2.2 and MQSeries for SINIX and DC/OSx V2.2.
- N MQSeries V5 for UNIX systems.  
This includes MQSeries for AIX V5.1, MQSeries for HP-UX V5.1, and MQSeries for Sun Solaris V5.1.

If triggering is supported, a trigger message is written to the initiation queue when the trigger conditions for the queue are satisfied. Various conditions can be

specified as described in “Conditions for a trigger event” on page 204. Briefly, the conditions include the following:

- When any message arrives on the queue (*every* triggering)
- When the queue goes from being empty to having messages on it (*first* triggering)
- When a specified number of messages have arrived on the queue (*depth* triggering)

With any of these conditions, a minimum priority can also be specified. Only messages with this or a higher priority are included when evaluating whether the trigger conditions have been met (*priority* triggering).

There are also a number of unusual conditions which cover cases in which a restart or other failure has occurred.

When the application is started, it is passed a structure which contains the name of the queue which caused the trigger event, and from which the application is now expected to retrieve messages. Other data in this structure includes information which the administrator can add to the process definition, which can be used to control the operation of the application.

The MQTM, MQTMC, and MQTMC2 structures are very similar; the difference between them is that some binary fields in the MQTM structure are replaced by character equivalents (of the same length) in the MQTMC and MQTMC2 structure. (MQTMC2 also contains the name of the queue manager.) If these fields are not referenced, portability is increased. However, one of the fields is the structure version, and it is safer to always check that, at the cost of a possible small change to the application in an area which would probably need change anyway.

## Level 1 product range support

No Level 1 product supports triggering.

## Level 2 product range support

Under MQSeries for VSE/ESA there is no actual initiation queue; the application is started directly by the queue manager. User information in the trigger message is not supported.

On MQSeries for VSE/ESA two forms of triggering are supported. The triggered application can be initiated by an:

- EXEC CICS START, where the started application must issue a CICS RETRIEVE call in order to get the trigger message. (This form is compatible with triggering for OS/390.)
- EXEC CICS LINK, where the trigger message is passed in COMMAREA.

Depth and priority triggering are not supported by MQSeries for VSE/ESA.

The other Level 2 products provide full support. There is a real initiation queue, and the trigger monitor which reads trigger messages from this queue and starts applications, could be replaced by a customer-written version.

## Comparison - triggering

The trigger monitor on MQSeries Version 2 for UNIX systems, MQSeries for OS/2 Warp V5.0, and MQSeries for Windows NT V5.0 can run either on a server or a client, with the exception of clients in DOS and Windows 3.1 environments.

## Migration recommendations

1. At present, triggering is not available on several platforms. Alternative techniques must be used, for example on some platforms a long-running application which does a get with signal may be used. This may migrate better between the platforms of interest. See "Input" on page 547.
2. If migration between CICS for VSE/ESA and CICS Transaction Server for OS/390 or CICS for MVS/ESA is important, use the form of triggering on VSE/ESA which is compatible with the OS/390 form.

## Input

Table 59. Input features - function summary

Product	Shared input	Exclusive input	Input default to queue definition	Browse with lock	Full browse (1)	Signal	Selective get by MsgId / CorrelId (2)	Data conversion
<b>A</b>	Yes	Yes	Yes	Yes	Yes	No	Yes	Yes
<b>C</b>	Yes	Yes	Yes	No	Yes	Yes	Yes	Yes
<b>D</b>	Yes	Yes	Yes	Yes	Yes	No	Yes	Yes
<b>E</b>	Yes	Yes	Yes	Yes	Yes	No	Yes	Yes
<b>G</b>	Yes	Yes	Yes	Yes	Yes	Yes	No	Yes
<b>H</b>	Yes	Yes	No	Yes	No (3)	No	No	No
<b>I</b>	Yes	Yes	No	Yes	Yes	No	Yes	No
<b>J</b>	Yes	Yes	Yes	No	Yes	No	Yes	No
<b>K</b>	Yes	Yes	Yes	No	Yes	Yes	Yes	No
<b>L</b>	Yes	Yes	Yes	Yes	Yes	No	Yes	Yes
<b>M</b>	Yes	Yes	Yes	Yes	Yes	No	Yes	Yes
<b>N</b>	Yes	Yes	Yes	Yes	Yes	No	Yes	Yes

**Note:**

- Other than Browse-with-lock
- All products support generating a *MsgId* if zero is specified at put time, conveying both *MsgId* and *CorrelId* with the message, and delivering them to the getter. Not all products support selective get, however, which is the ability of the getter to specify the *MsgId* or *CorrelId* or both that the retrieved message must have.
- Only the first message on a queue can be browsed.

**Product key:**

**A** MQSeries for Digital OpenVMS V2.2  
**C** MQSeries for OS/390 V2.1  
**D** MQSeries for OS/2 Warp V5.1  
**E** MQSeries for AS/400 V4R2M1  
**G** MQSeries for Tandem NonStop Kernel V2.2  
**H** MQSeries for UnixWare V1.4.1  
**I** MQSeries for VSE/ESA V2.1  
**J** MQSeries for Windows V2.0  
**K** MQSeries for Windows V2.1  
**L** MQSeries for Windows NT V5.1  
**M** MQSeries V2 for UNIX systems.  
This includes MQSeries for AT&T GIS UNIX V2.2 and MQSeries for SINIX and DC/OSx V2.2.  
**N** MQSeries V5 for UNIX systems.  
This includes MQSeries for AIX V5.1, MQSeries for HP-UX V5.1, and MQSeries for Sun Solaris V5.1.

### Shared and exclusive input

These options (MQOO\_INPUT\_EXCLUSIVE and MQOO\_INPUT\_SHARED) control whether more than one application is allowed to have the queue open for input at the same time.

If the application is not sensitive to this, MQOO\_INPUT\_AS\_Q\_DEF can be specified, and exclusivity is determined by the queue definition. This feature is available only with queue managers within Level 2 products.

Another feature available only with queue managers within the Level 2 products, is a queue attribute for *Shareability*. If this is set to MQQA\_NOT\_SHAREABLE, only one application is allowed to have the queue open for input at any time (the MQOO\_INPUT\_SHARED open option for this queue is effectively treated as if it were MQOO\_INPUT\_EXCLUSIVE).

MQOO\_INPUT\_EXCLUSIVE is supported on all platforms and is the safest to choose from a portability point of view. However, if an application is not sensitive to exclusivity, and portability to Digital Vax platform is not an issue, MQOO\_INPUT\_SHARED, is a better choice.

Note that on MQSeries for VSE/ESA, a single MQOPEN cannot request both input and output functions. If input and output for the same queue are required, two MQOPEN calls must be issued, one for each. Other queue managers do not have this restriction, so bear it in mind if your application might need to migrate to MQSeries for VSE/ESA in the future.

### Browse-with-lock, and full browse

For more information about browse-with-lock support see “Syncpoint” on page 540. With the products in Level 1, only the first message on the queue can be browsed. Browse-with-lock is supported only by queue managers for which no syncpoint support is available, and where shared input is possible, with the exception of MQSeries for AS/400, MQSeries Version 2 for UNIX systems, and MQSeries for OS/2 Warp where it is supported to enable you to migrate from Version 1 to Version 2.

Full browse support allows an application to inspect each of the messages on the queue in turn, without retrieving them destructively. A browse cursor marks the position on the queue that the browse scan has reached. Full browse is supported by the queue managers of Level 2 products, and by some queue managers in the Level 1 product range. Others in the Level 1 product range offer a limited form of browse, in which only the first message on the queue can be browsed.

Browse can be used to select a message to get destructively. It can also be used in order to monitor or display the messages on the queue.

### Signal

Get using an operating-system signal (option MQGMO\_SET\_SIGNAL) is used to allow the application to continue with other work, without blocking, while waiting for a suitable message to arrive. The signal is an operating-system dependent object (for example, in OS/390 it is an ECB). If the operating system supports waiting on multiple signals, as OS/390 does, then the application can effectively wait for a message arriving on one of several queues.

This feature is only available on platforms where there is a suitable facility provided in the operating environment. If applications that use this feature are ported between platforms, some change will be needed even if signal support is available on both platforms, because the signal itself is specific to the operating environment. If signal is not available, the application logic will have to change; MQGMO\_WAIT can be used to provide a blocking wait (MQGMO\_WAIT is available with all queue managers).

## Get by MsgId and CorrelId

This allows an application to specify a non-zero *MsgId* or *CorrelId* or both when issuing an MQGET (either a browse or a destructive get). If this is done, only messages which have a matching *MsgId* or *CorrelId*, or both, are eligible to be satisfied by the get. Setting either value to zero means that no matching is required for that identifier.

This can be used for retrieving a group of messages, all of which have the same identifier, usually the *CorrelId*, even though they are not all together at the top of the queue. Getting for a specific *MsgId*, and possibly also for a specific *CorrelId* as well, can be used to retrieve a specific message. Note however that there is no guarantee that *MsgIds* are unique within a queue. If a message that is to be retrieved has been found by issuing browse requests, it is much safer to retrieve the message using the MQGMO\_MSG\_UNDER\_CURSOR option than by quoting its *MsgId*.

This facility is provided only by the products in Level 2 queue managers. Level 1 queue managers check that *MsgId* and *CorrelId* have been set to zero for an MQGET, so applications migrating from Level 1 to Level 2 queue managers will need no change in this area. Migrating the other way will require the application to search for the required message itself by browsing, where this is supported. If browse is not supported, more radical changes may be needed.

However, as previously mentioned, all MQSeries products support the putting of a message with a non-zero *MsgId* and *CorrelId*. Therefore, in a client-server type of environment, the client might MQPUT or MQPUT1 *MsgId* and/or *CorrelId* to a server system, such as MQSeries for OS/390, or MQSeries for AS/400, where MQGET by *MsgId* / *CorrelId* is supported. The recomposition of several related messages could then be done at the server or host with the results message then sent back to the client.

Alternatively, each group of messages could request replies to unique reply-to queue names; therefore facilitating *recomposition* on the same or another system, even if the specific MQGET by *CorrelId* function is not available on that system.

### Data conversion

See Chapter 11, “Writing data-conversion exits” on page 161 for a list of conditions under which a data-conversion exit is invoked.

User-written exits can be provided to perform data conversion. A utility is supplied with these products which accepts a C structure, and produces source code from which a data-conversion exit suitable for use by the queue manager can be generated.

Some queue managers do not support data conversion (see Table 59 on page 547). However, when sending messages from a queue manager that does support data conversion to one that doesn't, a channel attribute can be set at the sending queue manager to request that text is converted *before* each message is transmitted.

## Message properties and protocols

Table 60. Message properties - function summary

Product	Default maximum message length	Maximum priority	Nonpersistent messages	Exception reports	Msgld, Correlld response options	Extra message types	COA, COD, Expiry	PAN, NAN	Protocols
<b>A</b>	4 MB	9	Yes	Yes	Yes	Yes	Yes	No	LU 6.2 TCP/IP DECnet
<b>C</b>	4 MB (1)	9	Yes	Yes	Yes	Yes	Yes	Yes	LU 6.2 TCP/IP
<b>D</b>	100 MB	9	Yes	Yes	Yes	Yes	Yes	Yes	LU 6.2 TCP/IP NetBIOS SPX
<b>E</b>	4 MB	9	Yes	Yes	Yes	Yes	Yes	Yes	LU 6.2 TCP/IP
<b>G</b>	4 MB	0	No	No	No	No	No	No	LU 6.2 TCP/IP
<b>H</b>	64000	0	No	No	No	No	No	No	LU 6.2 TCP/IP
<b>I</b>	4 MB	0	Yes	No	No	No	No	No	LU 6.2 TCP/IP
<b>J</b>	4 MB	9	Yes	Yes	Yes	Yes	Yes	No	TCP/IP
<b>K</b>	4 MB	9	Yes	Yes	Yes	Yes	Yes	No	TCP/IP
<b>L</b>	100 MB	9	Yes	Yes	Yes	Yes	Yes	Yes	LU 6.2 TCP/IP NetBIOS SPX
<b>M</b>	4 MB	9	Yes	Yes	Yes	Yes	Yes	No	LU 6.2 TCP/IP
<b>N</b>	100 MB	9	Yes	Yes	Yes	Yes	Yes	Yes	LU 6.2 TCP/IP

**Note:**

- The CICS message mover on the OS/390 Queue Manager has a maximum segment size of 32 KB. Because Level 1 queue managers do not support segmentation, the maximum transmission size is 32 KB to a CICS mover.

**Product key:**

- A** MQSeries for Digital OpenVMS V2.2
- C** MQSeries for OS/390 V2.1
- D** MQSeries for OS/2 Warp V5.1
- E** MQSeries for AS/400 V4R2M1
- G** MQSeries for Tandem NonStop Kernel V2.2
- H** MQSeries for UnixWare V1.4.1
- I** MQSeries for VSE/ESA V2.1
- J** MQSeries for Windows V2.0
- K** MQSeries for Windows V2.1
- L** MQSeries for Windows NT V5.1
- M** MQSeries V2 for UNIX systems.  
This includes MQSeries for AT&T GIS UNIX V2.2 and MQSeries for SINIX and DC/OSx V2.2.
- N** MQSeries V5 for UNIX systems.  
This includes MQSeries for AIX V5.1, MQSeries for HP-UX V5.1, and MQSeries for Sun Solaris V5.1.

Message context is another message property. See "Security" on page 556.

### Maximum message length

The lowest maximum size of message (excluding headers) supported is 10 000 bytes. You should limit your message text size to this if you want to enable your message to go to any platform.

For Level 2 products, the maximum size is given by the queue manager attribute *MaxMsgLength*, minus MQ\_MSG\_HEADER\_LENGTH. This currently gives 4 MB - 4000 bytes by default. This formula can be used with these queue managers for messages that are not going to travel to, or through, a product in Level 1. If there is any possibility of this, messages should be restricted appropriately.

If longer messages have to be split up for this (or any other) reason, a sequence number or relative starting address should be carried in the message data, so that the receiving application can reconstruct the original text correctly. In some cases it cannot be guaranteed that messages will be delivered in the same order as that in which they were put. An example of this is where multiple hops may be necessary to reach the final destination.

See also “Handling large messages” on page 140.

### Maximum priority

The queue managers of Level 2 products recognize 10 message priority levels, in the range 0 through 9. A message’s priority controls the position at which it is enqueued when it arrives at a queue, and hence the order in which it will be delivered to an application issuing MQGET.

The queue managers of Level 2 products also support a local queue attribute *MsgDeliverySequence*, that allows this to be overridden. If this attribute is set to FIFO only, all messages are enqueued at the same priority. However, the priority value carried with the message still records its intended priority.

Level 1 queue managers treat all messages as having equal priority, so effectively the maximum message priority for them is zero. However, to allow messages of higher priority to pass through, they do not reject an MQPUT of a message where the priority is greater than zero. In this case they issue a warning. So, although the priority does not affect the speed at which the message passes through the system, it can still be honored when the message reaches its destination at a Level 2 queue manager.

However, application program writers must ensure that the priority value is in the range 0 through 9 when a put is issued. Values greater than 9 are rejected by the MQSeries for OS/390 queue manager.

### Nonpersistent messages

The queue managers of Level 2 products support both persistent and nonpersistent messages. Persistent messages are ones which are guaranteed not to be lost if the system crashes. Messages on them are written to DASD, either as part of the queue backup storage, or as part of the log, so that they can be recovered if necessary. Nonpersistent messages, however, are guaranteed **not** to be recovered after a restart of the queue manager which owns the queue; even if they do happen to be found on DASD, they are discarded.

Persistent messages are vital if the message represents a business action that has to be performed. In order for messages not to be lost, as guaranteed by MQSeries products, they must be marked as persistent. All MQSeries queue managers support persistent messages.

Nonpersistent messages are supported only by Level 2 queue managers. They offer important performance advantages because the message does not have to be written to DASD at all if the capacity of the main-storage buffers permits, and it is processed sufficiently quickly. Nonpersistent messages can be used for queries, where the query will simply be repeated if necessary, and for non-critical notifications (for example, an update to an airport flight information screen).

The queue managers of Level 2 products also provide a third option, which allows the persistence property of the message to be defaulted to the queue, rather than specified by the putting application. In general a given queue can contain a mixture of persistent and nonpersistent messages.

Although the Level 1 queue managers reject an attempt by an application to put a nonpersistent message, they do not prevent a nonpersistent message from passing through (or arriving at) a queue manager.

If a program that runs with a queue manager of an Level 2 product specifies nonpersistent when putting a message, the program will need to be changed to run with a queue manager of a Level 1 product.

### Exception reports

With Level 2 queue managers, exception reports can be requested when a message is put. In this case, if there is a problem with the message, for example, it cannot be delivered because the destination queue is full, an exception report is generated and sent to the reply-to queue. The report carries a code indicating the nature of the problem.

In addition to requesting exception reports, applications can ask that the first 100 bytes of the original message or all of the original message be included with the report. This is convenient if state information is held at the front of the message data; it helps the originator to identify the message which had a problem.

An exception report is not generated if the putting application can be notified of the problem synchronously, by a reason code at the time of the put.

Level 1 queue managers and transmission programs do not generate exception reports, nor do they allow reports to be requested. They do, however, allow an application to generate a report message. Events that would cause an exception report to be generated are notified instead, for example with a console message, at the queue manager where the problem occurs. There is, however, no direct notification to the application.

### MsgId and CorrelId options for responses

With Level 2 queue managers, it is possible to request how the *MsgId* and *CorrelId* of the report should be constructed. It is beneficial if applications honor these requests, to facilitate requests from applications which use different schemes to manage business unit-of-work correlation.

## Comparison - message properties

However, these options are not supported for applications connected to Level 1 queue managers. Applications have to choose, based on the correlation scheme in use, how to generate the *MsgId* and *CorrelId* of their replies.

## Extra message types

With Level 2 queue managers the *MsgType* field in the message descriptor allows a wide range of values to be accepted. These values are not accepted by queue managers of Level 1 products, and should only be used with messages that do not pass through, or to, applications connected to Level 1 queue managers.

## COA, COD, and Expiry message

MQSeries for AS/400, MQSeries for OS/2 Warp, MQSeries for OS/390, MQSeries Version 2 for UNIX systems, and MQSeries for Windows NT allow a program putting a message to request:

- That a confirm-of-arrival report (COA) is generated when the message has been put on its final destination queue. (This is supported also on MQSeries for VSE/ESA).
- That a confirm-of-delivery report (COD) is generated when the message has been retrieved from its final destination queue. (This is supported also on MQSeries for VSE/ESA).
- That the message is discarded if it has not been retrieved within a specified time, and optionally a report is generated if this happens.

These functions are not supported on other MQSeries queue managers.

Level 1 queue managers (and earlier versions of MQSeries for OS/390) do not allow a message requesting any of these options to pass through them.

## PAN and NAN messages

MQSeries for AIX, MQSeries for AS/400, MQSeries for HP-UX, MQSeries for OS/2 Warp, MQSeries for OS/390, MQSeries for Sun Solaris, and MQSeries for Windows NT allow a program putting a message to request:

- That a positive action notification (PAN) is generated when the request has been successfully serviced
- That a negative action notification (NAN) is generated when the request has not been successfully serviced

These functions are not supported on other MQSeries queue managers.

## Threading

Table 61. Threading - function summary

Product	Multithreaded applications
MQSeries for Digital OpenVMS V2.2	No
MQSeries for OS/390 V2.1	No
MQSeries for OS/2 Warp V5.1	No
MQSeries for AS/400 V4R2M1	No
MQSeries for Tandem NonStop Kernel V2.2	No
MQSeries for UnixWare V1.4.1	No
MQSeries for VSE/ESA V2.1	No
MQSeries for Windows V2.0	No
MQSeries for Windows V2.1	Yes
MQSeries for Windows NT V5.1	Yes
MQSeries for AT&T GIS UNIX V2.2	(1)
MQSeries for SINIX and DC/OSx V2.2	
MQSeries for AIX V5.1	Yes
MQSeries for HP-UX V5.1	
MQSeries for Sun Solaris V5.1	
<b>Note:</b>	
1. MQSeries for SINIX supports multithreaded applications whereas MQSeries for DC/OSx does not.	

## Threaded applications on UNIX platforms

On UNIX, an application can connect to a single queue manager only; it **cannot** connect different threads to different queue managers.

A multithreaded MQSeries application must ensure that MQDISC is executed in each thread. This can be done using a thread exit handler. Do not use detached threads.

Those platforms that support multithreaded applications have some limitations:

### AIX, Sun Solaris, and HP-UX

In addition to the considerations for "UNIX signal handling on MQSeries Version 5 products" on page 85, a multithreaded MQSeries application must not establish signal handlers for SIGSEGV and SIGBUS while any thread has an open connection to MQSeries. These signal handlers should be set up process wide before MQSeries is called. MQSeries' handlers will then attempt to invoke the application's handlers when possible and appropriate.

### SINIX

In addition to the considerations for "UNIX signal handling on MQSeries Version 5 products" on page 85, a multithreaded MQSeries application must not use SIGALRM, SIGSEGV, or SIGBUS.

## Security

Table 62. Security - function summary

Product	Authorization checks	Message context	Alternate user ID checks	Transmission program exits	API crossing exit
A	Yes	Yes	Yes	Yes	No
C	Yes	Yes	Yes	Yes	Yes (2)
D	Yes	Yes	Yes	Yes	No
E	Yes	Yes	Yes	Yes	No
G	Yes	No (1)	No	No	No
H	Yes	No (1)	No	No	No
I	Yes	No (1)	No	No	No
J	No	No	No	No	No
K	No	No	No	No	No
L	Yes	Yes	Yes	Yes	No
M	Yes	Yes	Yes	Yes	No
N	Yes	Yes	Yes	Yes	No

**Note:**

1. Context information is accepted and passed on, but not validated.
2. CICS applications only

**Product key:**

- A** MQSeries for Digital OpenVMS V2.2
- C** MQSeries for OS/390 V2.1
- D** MQSeries for OS/2 Warp V5.1
- E** MQSeries for AS/400 V4R2M1
- G** MQSeries for Tandem NonStop Kernel V2.2
- H** MQSeries for UnixWare V1.4.1
- I** MQSeries for VSE/ESA V2.1
- J** MQSeries for Windows V2.0
- K** MQSeries for Windows V2.1
- L** MQSeries for Windows NT V5.1
- M** MQSeries V2 for UNIX systems.  
This includes MQSeries for AT&T GIS UNIX V2.2 and MQSeries for SINIX and DC/OSx V2.2.
- N** MQSeries V5 for UNIX systems.  
This includes MQSeries for AIX V5.1, MQSeries for HP-UX V5.1, and MQSeries for Sun Solaris V5.1.

## Authorization checks

Authorization checks are carried out for each resource, for example a queue, that is accessed. The user identifier under which the application is running is used to validate access to the resource.

Level 1 queue managers provide no direct support for this. However, queues are always implemented as files or database objects, and so when a read or write to the underlying object takes place as a result of a request from a Level 1 product, authority to perform this operation can be validated by the underlying system.

Level 2 queue managers provide more direct support, in that they request security validation for each function and object for which the application attempts an open. However, Level 2 queue managers do not themselves maintain the security tables which specify the operations each user is authorized for, although they may keep temporary caches of this information. In OS/390 these tables are maintained by an external security manager such as, RACF, and in OS/400 by the native OS/400 support. MQSeries Version 2 on UNIX systems and MQSeries for Windows NT provide an Object Authority Manager (OAM) that controls access to queue manager resources by user and group IDs. MQSeries for OS/2 Warp provides an interface that allows users to provide controlled access to queue manager resources by user and group IDs.

At this level, there is no impact on the MQI statements in a program, and so there is no direct effect on program migration. However, users may need to review the security capabilities on each platform to determine how they will map.

## Message context

Level 2 queue managers support various fields that are transmitted with each message, collectively referred to as the context information for the message. This information includes the user identifier and accounting token of the user who originated the message, and the name of the program that generated it. There are also fields which can be set by suitably-authorized applications or exits (see “Channel exits” on page 558) to contain information such as whether the other context information has been validated at this queue manager.

Progressively higher levels of authority are required to alter these fields. At the lowest level of authority, an application is unable to set any information in them; the queue manager sets them all to default values.

Within the Level 2 products the *UserIdentifier* context field holds a user identifier that can be used by an application for validating authority to open resources.

Level 1 queue managers do not support context fields directly. That is, they do not set information in them on behalf of an application, nor do they check that an application is suitably authorized to set them. Whatever information an application sets in these fields when putting a message is carried with the message, and made available to the recipient of the message. A message passing through one of these queue managers will therefore retain any context information that it contains.

Applications connected to Level 1 queue managers can set user identifier and other context information, and can carry out their own checks when receiving messages, bearing in mind that with these queue managers no system security functions have been used to authorize the setting of this information. Note, however, that if applications do set the context information themselves, they will not migrate unchanged to Level 2 queue managers unless they are given an unusually high level of authority.

If messages are received at a Level 2 product queue manager from a Level 1 product queue manager, the context fields can be set, changed or verified in the transmission program’s Message Exit (see “Channel exits” on page 558).

### Alternate user ID checks

When a resource of a Level 2 product, such as a queue, is opened, the authorization check that is carried out by default uses the user identifier under which the application is running. Level 2 queue managers support an option which allows the user identifier which is used to be specified explicitly by the application. An application, for example a server, can use this feature to specify the user identifier taken from the context field of a message that it has retrieved, and for which it is currently doing work.

This feature is not supported by Level 1 queue managers.

### Channel exits

Channels (also called Message Channel Agents), of Level 2 products support exits that can be used for:

- Security exit
- Message exit
- Send exit
- Receive exit
- Message retry exit (supported by MQSeries for AIX, MQSeries for AS/400, MQSeries for Digital OpenVMS, MQSeries for OS/2 Warp, MQSeries for Tandem NSK, and MQSeries for Windows NT)

Each end of the channel, if it is connected to a Level 2 queue manager can have each of the four types of exit. For some purposes, for example encryption, it is necessary that there is a corresponding exit at the other end of the channel.

Security exits are given control when the channel is initiated. They can initiate an exchange of security messages, of a format that is defined by the exits themselves. Only when each exit, if present, is satisfied can transmissions proceed along the channel.

Message exits receive control:

- At the sending end, after a message has been retrieved from the transmission queue, and before it is segmented if necessary, and transmitted, and
- At the receiving end, just before a message is put to its destination queue.

In particular, these exits can manipulate the context information. For example they can:

- Validate user identifiers
- Translate user identifiers, if the messages are entering a new authority domain
- Set the user context fields, to show other programs the degree to which the message is trusted.

Send and receive exits can be used for journaling and message encryption.

Message retry exits can be used to reduce the number of messages on a dead-letter queue. After a message has failed to be put on a queue, the exit will make additional attempts to put the message on the target queue. The message is only added to the dead-letter queue if this fails.

Transmission program exits are not available with Level 1 products.

### **API-crossing exit**

The MQSeries for OS/390 queue manager supports an exit, for CICS Transaction Server for OS/390 applications only, which is executed both before and after every API call. The exit can cause the call to be rejected, and can set, or change, any of the parameters being returned to the application. It can therefore be used to implement additional security checks.

Application programs do not have to be changed to cause this exit to be invoked, so in general there are no issues of program migration involved with it, although if it is used for security purposes migration of this function may be difficult.

This exit could also be used to perform processing essential to the working of the application, for example, data conversion (see “Data conversion” on page 550). If this is done, difficulty will again occur if the application has to be migrated.

## Object types

Table 63. Object types - function summary

Product	Model and dynamic queues	Cluster queues	Namelists	Queue manager object	Distribution lists
A	Yes	No	No	Yes	No
C	Yes	Yes	Yes	Yes	No
D	Yes	Yes	Yes	Yes	Yes
E	Yes	No	No	Yes	Yes
G	Yes	No	No	Yes	No
H	No	No	No	No	No
I	No	No	No	No	No
J	Yes	No	No	Yes	No
K	Yes	No	No	Yes	No
L	Yes	Yes	Yes	Yes	Yes
M	Yes	No	No	Yes	No
N	Yes	Yes	Yes	Yes	Yes

**Product key:**

- A** MQSeries for Digital OpenVMS V2.2
- C** MQSeries for OS/390 V2.1
- D** MQSeries for OS/2 Warp V5.1
- E** MQSeries for AS/400 V4R2M1
- G** MQSeries for Tandem NonStop Kernel V2.2
- H** MQSeries for UnixWare V1.4.1
- I** MQSeries for VSE/ESA V2.1
- J** MQSeries for Windows V2.0
- K** MQSeries for Windows V2.1
- L** MQSeries for Windows NT V5.1
- M** MQSeries V2 for UNIX systems.  
This includes MQSeries for AT&T GIS UNIX V2.2 and MQSeries for SINIX and DC/OSx V2.2.
- N** MQSeries V5 for UNIX systems.  
This includes MQSeries for AIX V5.1, MQSeries for HP-UX V5.1, and MQSeries for Sun Solaris V5.1.

## Model and dynamic queues

The MQSeries for AS/400, MQSeries for OS/2 Warp, MQSeries for OS/390, MQSeries for Tandem NSK, MQSeries for UNIX systems, and MQSeries for Windows NT queue managers support a type of queue called a model queue. Opening a model queue causes a dynamic queue to be created.

One of the main uses of this is for a requester to create a reply queue dynamically, avoiding the need for it to be predefined. This is convenient if there needs to be several instances of such requesters. Using dynamic queues means that there need be no fixed limit on the total number of them.

However, this feature is currently available only with some queue managers, and so applications making use of it will need to be changed if they are to be migrated to other queue managers.

## Namelists

MQSeries for OS/390 and V5.1 of MQSeries for AIX, HP-UX, OS/2 Warp, Sun Solaris, and Windows NT support a type of object called a namelist. Although this is intended to hold a list of queue names, it can in fact hold a list of any names (subject to a maximum of 48 characters per name), since there is no check that the objects named do in fact exist.

Namelists can be used by monitoring applications to inquire a list of the queues to be monitored. The benefit is that the list of queues in the namelist is maintained by the systems administrator, independently of the application.

However, namelists are supported by only these platforms, so applications making use of them will not migrate to other platforms.

## Queue-manager object

With Level 2 queue managers, a queue-manager object can be opened. This allows the application to inquire the values of various queue-manager attributes, including the maximum message length (*MaxMsgLength*) supported by the queue manager. This feature is not available with Level 1 queue managers, and applications making use of it will not migrate to them unchanged.

## Administration

There are substantial differences in the way administration is carried out for the various queue managers, in particular between the Level 1 queue managers, as a whole, and each of the Level 2 queue managers. All Level 2 products provide single point of control for their object administration. In addition, the administration of MQSeries for AS/400, MQSeries for OS/2 Warp, MQSeries for UNIX systems, and MQSeries for Windows NT can be done remotely, from any one of MQSeries for AS/400, MQSeries for OS/2 Warp, MQSeries for UNIX systems, or MQSeries for Windows NT.

With Level 1 products, each queue manager must be administered individually. The only factors that are discussed here are those which affect program migration. For other details see the appropriate publication for the queue manager.

Table 64. Administration - function summary

Product	Command queue	Handles broken	MQSET supported
A	Yes	Yes	Yes
C	Yes	Yes	Yes
D	Yes	Yes	Yes
E	Yes	Yes	Yes
G	Yes	Yes	Yes
H	No	No	No
I	No	No	Yes
J	No	Yes	Yes
K	Yes	Yes	Yes
L	Yes	Yes	Yes
M	Yes	Yes	Yes
N	Yes	Yes	Yes

**Product key:**

- A MQSeries for Digital OpenVMS V2.2
- C MQSeries for OS/390 V2.1
- D MQSeries for OS/2 Warp V5.1
- E MQSeries for AS/400 V4R2M1
- G MQSeries for Tandem NonStop Kernel V2.2
- H MQSeries for UnixWare V1.4.1
- I MQSeries for VSE/ESA V2.1
- J MQSeries for Windows V2.0
- K MQSeries for Windows V2.1
- L MQSeries for Windows NT V5.1
- M MQSeries V2 for UNIX systems.  
This includes MQSeries for AT&T GIS UNIX V2.2 and MQSeries for SINIX and DC/OSx V2.2.
- N MQSeries V5 for UNIX systems.  
This includes MQSeries for AIX V5.1, MQSeries for HP-UX V5.1, and MQSeries for Sun Solaris V5.1.

## Command queues

Level 2 queue managers support a command input queue to which command messages can be sent. If the user identifier in the message's context is authorized for the command, the command is executed and a reply message sent giving the results of the command.

However, the format of these commands is different between the MQSeries for OS/390 queue manager, and that for the other Level 2 queue managers. For OS/390, the command messages contain character information, in the same format as is supported at the command line. The other Level 2 queue managers support messages containing Programmable Command Formats, which include binary information. Replies to these messages are in a similar format, which is easier for programs, as opposed to humans, to parse.

The queue managers of the Level 1 products do not provide command queues. Administration is only carried out using the supplied utility.

### Handles broken

When changes are made to the configuration information, for example a new queue is defined or the attributes of a queue are changed, the immediacy with which this takes effect varies.

With Level 2 queue managers, changes generally take immediate effect. Any change to an attribute which affects the name resolution of a queue (for example, a change to the name of the queue to which an alias queue resolves), causes any handle for that queue to be marked as *broken* by the queue manager. Any subsequent call (other than MQCLOSE) using such a handle fails, with an MQRC\_OBJECT\_CHANGED reason code. The application has to close the handle, and reopen the queue, whereupon the change will take effect. Changes to other attributes generally take immediate effect for any new messages arriving on the queue.

With Level 1 queue managers, handles are not broken when changes to the configuration occur. The application does not normally see the change until it closes and reopens the queue; the MQRC\_OBJECT\_CHANGED reason code is never issued. Changes to the Inhibit-get and Inhibit-put attributes do take immediate effect, because these attributes are checked at get or put time, not at open time.

Some Level 1 queue managers, however, do not permit changes to the configuration which would affect currently-open handles.

It is likely that only long-running applications need to be sensitive to changes in the configuration tables. If portability is a strong consideration for long-running applications, it may be better to close and reopen queues periodically, rather than check for MQRC\_OBJECT\_CHANGED.

### MQSET support

Level 2 queue managers support the MQSET call to set a limited number of queue attributes. This call is not supported by Level 1 queue managers.

## Programming languages

Support here means that the queue manager has been tested with the language, and that header files or copybooks as appropriate are supplied, together with relevant documentation. It is possible that other languages can be used, providing the calling interface is (or can be made to be) the same as that generated by one of the supported languages.

Table 65. Programming languages supported - function summary

Product	C	C++	Visual Basic	COBOL	RPG	Assembler	PL/I
A	Yes	No	No	Yes	No	No	No
C	Yes	Yes	No	Yes	No	Yes	Yes
D	Yes	Yes	No	Yes	No	No	Yes
E	Yes	Yes	No	Yes	Yes	No	No
G	Yes	No	No	No	No	Yes (TAL)	No
H	Yes	No	No	No	No	No	No
I	Yes	No	No	Yes	No	No	Yes
J	Yes	No	Yes	No	No	No	No
K	Yes	No	Yes	No	No	No	No
L	Yes	Yes	Yes	Yes	No	No	Yes
M	Yes	No	No	(1)	No	No	No
N	Yes	Yes	No	Yes	No	No	(2)

**Note:**

1. Not supported on MQSeries for AT&T GIS UNIX
2. Supported on MQSeries for AIX only

**Product key:**

- A MQSeries for Digital OpenVMS V2.2
- C MQSeries for OS/390 V2.1
- D MQSeries for OS/2 Warp V5.1
- E MQSeries for AS/400 V4R2M1
- G MQSeries for Tandem NonStop Kernel V2.2
- H MQSeries for UnixWare V1.4.1
- I MQSeries for VSE/ESA V2.1
- J MQSeries for Windows V2.0
- K MQSeries for Windows V2.1
- L MQSeries for Windows NT V5.1
- M MQSeries V2 for UNIX systems.  
This includes MQSeries for AT&T GIS UNIX V2.2 and MQSeries for SINIX and DC/OSx V2.2.
- N MQSeries V5 for UNIX systems.  
This includes MQSeries for AIX V5.1, MQSeries for HP-UX V5.1, and MQSeries for Sun Solaris V5.1.

## Header files

The header files and copybooks supplied with queue managers include, for example, constants for options, that are supported by that queue manager. However, some constants (reason codes for example), that are usually part of a test rather than being set within a program, are also included if they cannot be generated on a particular platform. This makes it easier to port applications which do need to test for reason codes.

Constant values are not reused for different purposes across queue managers. For example, MQRC\_OBJECT\_CHANGED has the value 2041. There is no risk that

the value 2041 will be used for a different reason code on a queue manager that never generates MQRC\_OBJECT\_CHANGED.

## Connection

Table 66. Default connection to a queue manager - function summary

Product	Default connection to a queue manager
MQSeries for Digital OpenVMS V2.2	No
MQSeries for OS/390 V2.1	Yes (1)
MQSeries for OS/2 Warp V5.1	No
MQSeries for AS/400 V4R2M1	Yes
MQSeries for Tandem NonStop Kernel V2.2	No
MQSeries for UnixWare V1.4.1	No
MQSeries for VSE/ESA V2.1	Yes (1)
MQSeries for Windows V2.0	No
MQSeries for Windows V2.1	No
MQSeries for Windows NT V5.1	No
MQSeries for AT&T GIS UNIX V2.2 MQSeries for SINIX and DC/OSx V2.2	No
MQSeries for AIX V5.1 MQSeries for HP-UX V5.1 MQSeries for Sun Solaris V5.1	No
<b>Note:</b>	
1. CICS applications only	

## Default connection

With MQSeries for AS/400 and with MQSeries for VSE/ESA there is a default connection to a queue manager. It is not essential for applications to issue the MQCONN and MQDISC verbs. However, it is recommended that even on these platforms applications do always issue these verbs, in order to enhance their portability.

---

## Appendix J. Notices

This information was developed for products and services offered in the United States. IBM may not offer the products, services, or features discussed in this information in other countries. Consult your local IBM representative for information on the products and services currently available in your area. Any reference to an IBM product, program, or service is not intended to state or imply that only that IBM product, program, or service may be used. Any functionally equivalent product, program, or service that does not infringe any IBM intellectual property right may be used instead. However, it is the user's responsibility to evaluate and verify the operation of any non-IBM product, program, or service.

IBM may have patents or pending patent applications covering subject matter described in this information. The furnishing of this information does not give you any license to these patents. You can send license inquiries, in writing, to:

| IBM Director of Licensing  
| IBM Corporation  
| North Castle Drive  
| Armonk, NY 10504-1785  
| U.S.A.

For license inquiries regarding double-byte (DBCS) information, contact the IBM Intellectual Property Department in your country or send inquiries, in writing, to:

IBM World Trade Asia Corporation  
Licensing  
2-31 Roppongi 3-chome, Minato-ku  
Tokyo 106, Japan

**The following paragraph does not apply to the United Kingdom or any other country where such provisions are inconsistent with local law:**

INTERNATIONAL BUSINESS MACHINES CORPORATION PROVIDES THIS PUBLICATION "AS IS" WITHOUT WARRANTY OF ANY KIND, EITHER EXPRESS OR IMPLIED, INCLUDING, BUT NOT LIMITED TO, THE IMPLIED WARRANTIES OF NON-INFRINGEMENT, MERCHANTABILITY, OR FITNESS FOR A PARTICULAR PURPOSE. Some states do not allow disclaimer of express or implied warranties in certain transactions, therefore this statement may not apply to you.

This information could include technical inaccuracies or typographical errors. Changes are periodically made to the information herein; these changes will be incorporated in new editions of the information. IBM may make improvements and/or changes in the product(s) and/or the program(s) described in this information at any time without notice.

Any references in this information to non-IBM documentation or non-IBM Web sites are provided for convenience only and do not in any manner serve as an endorsement of those documents or Web sites. The materials for those documents or Web sites are not part of the materials for this IBM product and use of those documents or Web sites is at your own risk.

## Notices

Licensees of this program who wish to have information about it for the purpose of enabling: (i) the exchange of information between independently created programs and other programs (including this one) and (ii) the mutual use of the information which has been exchanged, should contact:

IBM United Kingdom Laboratories,  
Mail Point 151,  
Hursley Park,  
Winchester,  
Hampshire,  
England  
SO21 2JN.

Such information may be available, subject to appropriate terms and conditions, including in some cases, payment of a fee.

The licensed program described in this information and all licensed material available for it are provided by IBM under terms of the IBM Customer Agreement, IBM International Programming License Agreement, or any equivalent agreement between us.

This information contains sample application programs in source language, which illustrate programming techniques on various operating platforms. You may copy, modify, and distribute these sample programs in any form without payment to IBM, for the purposes of developing, using, marketing or distributing application programs conforming to the application programming interface for the operating platform for which the sample programs are written. These examples have not been thoroughly tested under all conditions. IBM, therefore, cannot guarantee or imply reliability, serviceability, or function of these programs. You may copy, modify, and distribute these sample programs in any form without payment to IBM for the purposes of developing, using, marketing, or distributing application programs conforming to IBM's application programming interfaces.

---

## Programming interface information

This book documents General-use Programming Interface and Associated Guidance Information and Product-sensitive Programming Interface and Associated Guidance Information provided by MQSeries for AIX V5.1, MQSeries for AS/400 V4R2M1, MQSeries for AT&T GIS UNIX V2.2, MQSeries for Digital OpenVMS V2.2, MQSeries for HP-UX V5.1, MQSeries for OS/2 Warp V5.1, MQSeries for OS/390 V2.1, MQSeries for SINIX and DC/OSx V2.2, MQSeries for Sun Solaris V5.1, MQSeries for Tandem NonStop Kernel V2.2, MQSeries for VSE/ESA V2.1, MQSeries for Windows V2.0, MQSeries for Windows V2.1, and MQSeries for Windows NT V5.1.

General-use programming interfaces allow the customer to write programs that obtain the services of these products.

General-use Programming Interface and Associated Guidance Information is identified where it occurs, either by an introductory statement to a chapter or section or by the following marking:

General-use programming interface

General-use Programming Interface and Associated Guidance Information...

End of General-use programming interface

Product-sensitive programming interfaces allow the customer installation to perform tasks such as diagnosing, modifying, monitoring, repairing, tailoring, or tuning of these products. Use of such interfaces creates dependencies on the detailed design or implementation of the IBM software product. Product-sensitive programming interfaces should be used only for these specialized purposes. Because of their dependencies on detailed design and implementation, it is to be expected that programs written to such interfaces may need to be changed in order to run with new product releases or versions, or as a result of service.

Product-sensitive Programming Interface and Associated Guidance Information is identified where it occurs, either by an introductory statement to a chapter or section or by the following marking:

Product-sensitive programming interface

Product-sensitive Programming Interface and Associated Guidance Information...

End of Product-sensitive programming interface

---

## Trademarks

The following terms are trademarks of International Business Machines Corporation in the United States, or other countries, or both:

400	AD/Cycle	AIX
AS/400	BookManager	C/370
C/400	CICS	CICS/ESA
COBOL/370	COBOL/400	Common User Access
DB2	eNetwork	IBM
IBMLink	IMS	IMS/ESA
Language Environment	MQ	MQSeries
MVS/ESA	OS/2	OS/390
OS/400	OpenEdition	RACF
RPG/400	SupportPac	System/390
VM/ESA	VSE/ESA	VisualAge

Lotus, Lotus Notes, LotusScript, and Notes are trademarks of Lotus Development Corporation in the United States, or other countries, or both.

ActiveX, BackOffice, Microsoft, Visual Basic, Visual C++, Windows, Windows NT, and the Windows logo are trademarks of Microsoft Corporation in the United States and/or other countries.

Java and all Java-based trademarks and logos are trademarks or registered trademarks of Sun Microsystems, Inc. in the United States and/or other countries.

UNIX is a registered trademark in the United States and/or other countries licensed exclusively through X/Open Company Limited.

Other company, product, and service names may be trademarks or service marks of others.

---

## Part 6. Glossary and Index



## Glossary of terms and abbreviations

This glossary defines MQSeries terms and abbreviations used in this book. If you do not find the term you are looking for, see the Index or the *IBM Dictionary of Computing*, New York: McGraw-Hill, 1994.

This glossary includes terms and definitions from the *American National Dictionary for Information Systems*, ANSI X3.172-1990, copyright 1990 by the American National Standards Institute (ANSI). Copies may be purchased from the American National Standards Institute, 11 West 42 Street, New York, New York 10036. Definitions are identified by the symbol (A) after the definition.

### A

**abend reason code.** A 4-byte hexadecimal code that uniquely identifies a problem with MQSeries for OS/390. A complete list of MQSeries for OS/390 abend reason codes and their explanations is contained in the *MQSeries for OS/390 Messages and Codes* manual.

**active log.** See *recovery log*.

**adapter.** An interface between MQSeries for OS/390 and TSO, IMS, CICS, or batch address spaces. An adapter is an attachment facility that enables applications to access MQSeries services.

**address space.** The area of virtual storage available for a particular job.

**address space identifier (ASID).** A unique, system-assigned identifier for an address space.

**administrator commands.** MQSeries commands used to manage MQSeries objects, such as queues, processes, and namelists.

**affinity.** An association between objects that have some relationship or dependency upon each other.

**alert.** A message sent to a management services focal point in a network to identify a problem or an impending problem.

**alert monitor.** In MQSeries for OS/390, a component of the CICS adapter that handles unscheduled events occurring as a result of connection requests to MQSeries for OS/390.

**alias queue object.** An MQSeries object, the name of which is an alias for a base queue defined to the local queue manager. When an application or a queue

manager uses an alias queue, the alias name is resolved and the requested operation is performed on the associated base queue.

**allied address space.** See *ally*.

**ally.** An OS/390 address space that is connected to MQSeries for OS/390.

**alternate user security.** A security feature in which the authority of one user ID can be used by another user ID; for example, to open an MQSeries object.

**APAR.** Authorized program analysis report.

**application-defined format.** In message queuing, application data in a message, which has a meaning defined by the user application. Contrast with *built-in format*.

**application environment.** The software facilities that are accessible by an application program. On the OS/390 platform, CICS and IMS are examples of application environments.

**application log.** In Windows NT, a log that records significant application events.

**application queue.** A queue used by an application.

**archive log.** See *recovery log*.

**ASID.** Address space identifier.

**asynchronous messaging.** A method of communication between programs in which programs place messages on message queues. With asynchronous messaging, the sending program proceeds with its own processing without waiting for a reply to its message. Contrast with *synchronous messaging*.

**attribute.** One of a set of properties that defines the characteristics of an MQSeries object.

**authorization checks.** Security checks that are performed when a user tries to issue administration commands against an object, for example to open a queue or connect to a queue manager.

**authorization file.** In MQSeries on UNIX systems, a file that provides security definitions for an object, a class of objects, or all classes of objects.

**authorization service.** In MQSeries on UNIX systems, MQSeries for OS/2 Warp, and MQSeries for Windows NT, a service that provides authority checking of

commands and MQI calls for the user identifier associated with the command or call.

**authorized program analysis report (APAR).** A report of a problem caused by a suspected defect in a current, unaltered release of a program.

## B

**backout.** An operation that reverses all the changes made during the current unit of recovery or unit of work. After the operation is complete, a new unit of recovery or unit of work begins. Contrast with *commit*.

**basic mapping support (BMS).** An interface between CICS and application programs that formats input and output display data and routes multiple-page output messages without regard for control characters used by various terminals.

**BMS.** Basic mapping support.

**bootstrap data set (BSDS).** A VSAM data set that contains:

- An inventory of all active and archived log data sets known to MQSeries for OS/390
- A wrap-around inventory of all recent MQSeries for OS/390 activity

The BSDS is required if the MQSeries for OS/390 subsystem has to be restarted.

**browse.** In message queuing, to use the MQGET call to copy a message without removing it from the queue. See also *get*.

**browse cursor.** In message queuing, an indicator used when browsing a queue to identify the message that is next in sequence.

**BSDS.** Bootstrap data set.

**buffer pool.** An area of main storage used for MQSeries for OS/390 queues, messages, and object definitions. See also *page set*.

**built-in format.** In message queuing, application data in a message, which has a meaning defined by the queue manager. Synonymous with *in-built format*. Contrast with *application-defined format*.

## C

**call back.** In MQSeries, a requester message channel initiates a transfer from a sender channel by first calling the sender, then closing down and awaiting a call back.

**CCF.** Channel control function.

**CCSID.** Coded character set identifier.

**CDF.** Channel definition file.

**channel.** See *message channel*.

**channel control function (CCF).** In MQSeries, a program to move messages from a transmission queue to a communication link, and from a communication link to a local queue, together with an operator panel interface to allow the setup and control of channels.

**channel definition file (CDF).** In MQSeries, a file containing communication channel definitions that associate transmission queues with communication links.

**channel event.** An event indicating that a channel instance has become available or unavailable. Channel events are generated on the queue managers at both ends of the channel.

**checkpoint.** (1) A time when significant information is written on the log. Contrast with *syncpoint*. (2) In MQSeries on UNIX systems, the point in time when a data record described in the log is the same as the data record in the queue. Checkpoints are generated automatically and are used during the system restart process.

**CI.** Control interval.

**CICS transaction.** In CICS, a unit of application processing, usually comprising one or more units of work.

**circular logging.** In MQSeries on UNIX systems, MQSeries for OS/2 Warp, and MQSeries for Windows NT, the process of keeping all restart data in a ring of log files. Logging fills the first file in the ring and then moves on to the next, until all the files are full. At this point, logging goes back to the first file in the ring and starts again, if the space has been freed or is no longer needed. Circular logging is used during restart recovery, using the log to roll back transactions that were in progress when the system stopped. Contrast with *linear logging*.

**CL.** Control Language.

**client.** A run-time component that provides access to queuing services on a server for local user applications. The queues used by the applications reside on the server. See also *MQSeries client*.

**client application.** An application, running on a workstation and linked to a client, that gives the application access to queuing services on a server.

**client connection channel type.** The type of MQI channel definition associated with an MQSeries client. See also *server connection channel type*.

**cluster.** A network of queue managers that are logically associated in some way.

**coded character set identifier (CCSID).** The name of a coded set of characters and their code point assignments.

**command.** In MQSeries, an administration instruction that can be carried out by the queue manager.

**command prefix (CPF).** In MQSeries for OS/390, a character string that identifies the queue manager to which MQSeries for OS/390 commands are directed, and from which MQSeries for OS/390 operator messages are received.

**command processor.** The MQSeries component that processes commands.

**command server.** The MQSeries component that reads commands from the system-command input queue, verifies them, and passes valid commands to the command processor.

**commit.** An operation that applies all the changes made during the current unit of recovery or unit of work. After the operation is complete, a new unit of recovery or unit of work begins. Contrast with *backout*.

**completion code.** A return code indicating how an MQI call has ended.

**configuration file.** In MQSeries on UNIX systems, MQSeries for OS/2 Warp, and MQSeries for Windows NT, a file that contains configuration information related to, for example, logs, communications, or installable services. Synonymous with *.ini file*. See also *stanza*.

**connect.** To provide a queue manager connection handle, which an application uses on subsequent MQI calls. The connection is made either by the MQCONN call, or automatically by the MQOPEN call.

**connection handle.** The identifier or token by which a program accesses the queue manager to which it is connected.

**context.** Information about the origin of a message.

**context security.** In MQSeries, a method of allowing security to be handled such that messages are obliged to carry details of their origins in the message descriptor.

**control command.** In MQSeries on UNIX systems, MQSeries for OS/2 Warp, and MQSeries for Windows NT, a command that can be entered interactively from

the operating system command line. Such a command requires only that the MQSeries product be installed; it does not require a special utility or program to run it.

**control interval (CI).** A fixed-length area of direct access storage in which VSAM stores records and creates distributed free spaces. The control interval is the unit of information that VSAM transmits to or from direct access storage.

**Control Language (CL).** In MQSeries for AS/400, a language that can be used to issue commands, either at the command line or by writing a CL program.

**controlled shutdown.** See *quiesced shutdown*.

**CPF.** Command prefix.

**Cross Systems Coupling Facility (XCF).** Provides the OS/390 coupling services that allow authorized programs in a multisystem environment to communicate with programs on the same or different OS/390 systems.

## D

**DAE.** Dump analysis and elimination.

**data conversion interface (DCI).** The MQSeries interface to which customer- or vendor-written programs that convert application data between different machine encodings and CCSIDs must conform. A part of the MQSeries Framework.

**datagram.** The simplest message that MQSeries supports. This type of message does not require a reply.

**DCE.** Distributed Computing Environment.

**DCI.** Data conversion interface.

**data-conversion service.** A service that converts application data to the character set and encoding that are required by applications on other platforms.

**dead-letter queue (DLQ).** A queue to which a queue manager or application sends messages that it cannot deliver to their correct destination.

**dead-letter queue handler.** An MQSeries-supplied utility that monitors a dead-letter queue (DLQ) and processes messages on the queue in accordance with a user-written rules table.

**default object.** A definition of an object (for example, a queue) with all attributes defined. If a user defines an object but does not specify all possible attributes for that object, the queue manager uses default attributes in place of any that were not specified.

**deferred connection.** A pending event that is activated when a CICS subsystem tries to connect to MQSeries for OS/390 before MQSeries for OS/390 has been started.

**distributed application.** In message queuing, a set of application programs that can each be connected to a different queue manager, but that collectively constitute a single application.

**Distributed Computing Environment (DCE).**

Middleware that provides some basic services, making the development of distributed applications easier. DCE is defined by the Open Software Foundation (OSF).

**distributed queue management (DQM).** In message queuing, the setup and control of message channels to queue managers on other systems.

**distribution list.** A list of queues to which a message can be put using a single MQPUT or MQPUT1 statement.

**DLQ.** Dead-letter queue.

**DQM.** Distributed queue management.

**dual logging.** A method of recording MQSeries for OS/390 activity, where each change is recorded on two data sets, so that if a restart is necessary and one data set is unreadable, the other can be used. Contrast with *single logging*.

**dual mode.** See *dual logging*.

**dump analysis and elimination (DAE).** An OS/390 service that enables an installation to suppress SVC dumps and ABEND SYSUDUMP dumps that are not needed because they duplicate previously written dumps.

**dynamic queue.** A local queue created when a program opens a model queue object. See also *permanent dynamic queue* and *temporary dynamic queue*.

## E

**environment.** See *application environment*.

**ESM.** External security manager.

**ESTAE.** Extended specify task abnormal exit.

**event.** See *channel event*, *instrumentation event*, *performance event*, and *queue manager event*.

**event data.** In an event message, the part of the message data that contains information about the event

(such as the queue manager name, and the application that gave rise to the event). See also *event header*.

**event header.** In an event message, the part of the message data that identifies the event type of the reason code for the event.

**event log.** See *application log*.

**event message.** Contains information (such as the category of event, the name of the application that caused the event, and queue manager statistics) relating to the origin of an instrumentation event in a network of MQSeries systems.

**event queue.** The queue onto which the queue manager puts an event message after it detects an event. Each category of event (queue manager, performance, or channel event) has its own event queue.

**Event Viewer.** A tool provided by Windows NT to examine and manage log files.

**extended specify task abnormal exit (ESTAE).** An OS/390 macro that provides recovery capability and gives control to the specified exit routine for processing, diagnosing an abend, or specifying a retry address.

**external security manager (ESM).** A security product that is invoked by the OS/390 System Authorization Facility. RACF is an example of an ESM.

## F

**FIFO.** First-in-first-out.

**first-in-first-out (FIFO).** A queuing technique in which the next item to be retrieved is the item that has been in the queue for the longest time. (A)

**forced shutdown.** A type of shutdown of the CICS adapter where the adapter immediately disconnects from MQSeries for OS/390, regardless of the state of any currently active tasks. Contrast with *quiesced shutdown*.

**format.** In message queuing, a term used to identify the nature of application data in a message. See also *built-in format* and *application-defined format*.

**Framework.** In MQSeries, a collection of programming interfaces that allow customers or vendors to write programs that extend or replace certain functions provided in MQSeries products. The interfaces are:

- MQSeries data conversion interface (DCI)
- MQSeries message channel interface (MCI)
- MQSeries name service interface (NSI)
- MQSeries security enabling interface (SEI)

- MQSeries trigger monitor interface (TMI)

**FRR.** Functional recovery routine.

**functional recovery routine (FRR).** An OS/390 recovery/termination manager facility that enables a recovery routine to gain control in the event of a program interrupt.

## G

**GCPC.** Generalized command preprocessor.

**generalized command preprocessor (GCPC).** An MQSeries for OS/390 component that processes MQSeries commands and runs them.

**Generalized Trace Facility (GTF).** An OS/390 service program that records significant system events, such as supervisor calls and start I/O operations, for the purpose of problem determination.

**get.** In message queuing, to use the MQGET call to remove a message from a queue. See also *browse*.

**global trace.** An MQSeries for OS/390 trace option where the trace data comes from the entire MQSeries for OS/390 subsystem.

**GTF.** Generalized Trace Facility.

## H

**handle.** See *connection handle* and *object handle*.

## I

**immediate shutdown.** In MQSeries, a shutdown of a queue manager that does not wait for applications to disconnect. Current MQI calls are allowed to complete, but new MQI calls fail after an immediate shutdown has been requested. Contrast with *quiesced shutdown* and *preemptive shutdown*.

**in-built format.** See *built-in format*.

**in-doubt unit of recovery.** In MQSeries, the status of a unit of recovery for which a syncpoint has been requested but not yet confirmed.

**.ini file.** See *configuration file*.

**initialization input data sets.** Data sets used by MQSeries for OS/390 when it starts up.

**initiation queue.** A local queue on which the queue manager puts trigger messages.

**input/output parameter.** A parameter of an MQI call in which you supply information when you make the call, and in which the queue manager changes the information when the call completes or fails.

**input parameter.** A parameter of an MQI call in which you supply information when you make the call.

**installable services.** In MQSeries on UNIX systems, MQSeries for OS/2 Warp, and MQSeries for Windows NT, additional functionality provided as independent components. The installation of each component is optional: in-house or third-party components can be used instead. See also *authorization service*, *name service*, and *user identifier service*.

**instrumentation event.** A facility that can be used to monitor the operation of queue managers in a network of MQSeries systems. MQSeries provides instrumentation events for monitoring queue manager resource definitions, performance conditions, and channel conditions. Instrumentation events can be used by a user-written reporting mechanism in an administration application that displays the events to a system operator. They also allow applications acting as agents for other administration networks to monitor reports and create the appropriate alerts.

**Interactive Problem Control System (IPCS).** A component of OS/390 that permits online problem management, interactive problem diagnosis, online debugging for disk-resident abend dumps, problem tracking, and problem reporting.

**Interactive System Productivity Facility (ISPF).** An IBM licensed program that serves as a full-screen editor and dialog manager. It is used for writing application programs, and provides a means of generating standard screen panels and interactive dialogues between the application programmer and terminal user.

**IPCS.** Interactive Problem Control System.

**ISPF.** Interactive System Productivity Facility.

## L

**linear logging.** In MQSeries on UNIX systems, MQSeries for OS/2 Warp, and MQSeries for Windows NT, the process of keeping restart data in a sequence of files. New files are added to the sequence as necessary. The space in which the data is written is not reused until the queue manager is restarted. Contrast with *circular logging*.

**listener.** In MQSeries distributed queuing, a program that monitors for incoming network connections.

**local definition.** An MQSeries object belonging to a local queue manager.

## local definition of a remote queue • message queue interface (MQI)

**local definition of a remote queue.** An MQSeries object belonging to a local queue manager. This object defines the attributes of a queue that is owned by another queue manager. In addition, it is used for queue-manager aliasing and reply-to-queue aliasing.

**locale.** On UNIX systems, a subset of a user's environment that defines conventions for a specific culture (such as time, numeric, or monetary formatting and character classification, collation, or conversion). The queue manager CCSID is derived from the locale of the user ID that created the queue manager.

**local queue.** A queue that belongs to the local queue manager. A local queue can contain a list of messages waiting to be processed. Contrast with *remote queue*.

**local queue manager.** The queue manager to which a program is connected and that provides message queuing services to the program. Queue managers to which a program is not connected are called *remote queue managers*, even if they are running on the same system as the program.

**log.** In MQSeries, a file recording the work done by queue managers while they receive, transmit, and deliver messages, to enable them to recover in the event of failure.

**log control file.** In MQSeries on UNIX systems, MQSeries for OS/2 Warp, and MQSeries for Windows NT, the file containing information needed to monitor the use of log files (for example, their size and location, and the name of the next available file).

**log file.** In MQSeries on UNIX systems, MQSeries for OS/2 Warp, and MQSeries for Windows NT, a file in which all significant changes to the data controlled by a queue manager are recorded. If the primary log files become full, MQSeries allocates secondary log files.

**logical unit of work (LUW).** See *unit of work*.

## M

**machine check interrupt.** An interruption that occurs as a result of an equipment malfunction or error. A machine check interrupt can be either hardware recoverable, software recoverable, or nonrecoverable.

**MCA.** Message channel agent.

**MCI.** Message channel interface.

**media image.** In MQSeries on UNIX systems, MQSeries for OS/2 Warp, and MQSeries for Windows NT, the sequence of log records that contain an image of an object. The object can be recreated from this image.

**message.** (1) In message queuing applications, a communication sent between programs. See also *persistent message* and *nonpersistent message*. (2) In system programming, information intended for the terminal operator or system administrator.

**message channel.** In distributed message queuing, a mechanism for moving messages from one queue manager to another. A message channel comprises two message channel agents (a sender at one end and a receiver at the other end) and a communication link. Contrast with *MQI channel*.

**message channel agent (MCA).** A program that transmits prepared messages from a transmission queue to a communication link, or from a communication link to a destination queue. See also *message queue interface*.

**message channel interface (MCI).** The MQSeries interface to which customer- or vendor-written programs that transmit messages between an MQSeries queue manager and another messaging system must conform. A part of the MQSeries Framework.

**message descriptor.** Control information describing the message format and presentation that is carried as part of an MQSeries message. The format of the message descriptor is defined by the MQMD structure.

**message format service (MFS).** In IMS, an editing facility that allows application programs to deal with simple logical messages, instead of device-dependent data, thus simplifying the application development process. See *message input descriptor* and *message output descriptor*.

**message group.** A group of logical messages. Logical grouping of messages allows applications to group messages that are similar and to ensure the sequence of the messages.

**message input descriptor (MID).** In IMS, the MFS control block that describes the format of the data presented to the application program. Contrast with *message output descriptor*.

**message output descriptor (MOD).** In IMS, the MFS control block that describes the format of the output data produced by the application program. Contrast with *message input descriptor*.

**message priority.** In MQSeries, an attribute of a message that can affect the order in which messages on a queue are retrieved, and whether a trigger event is generated.

**message queue.** Synonym for *queue*.

**message queue interface (MQI).** The programming interface provided by the MQSeries queue managers.

This programming interface allows application programs to access message queuing services.

**message queuing.** A programming technique in which each program within an application communicates with the other programs by putting messages on queues.

**message segment.** One of a number of segments of a message that is too large either for the application or for the queue manager to handle.

**message sequence numbering.** A programming technique in which messages are given unique numbers during transmission over a communication link. This enables the receiving process to check whether all messages are received, to place them in a queue in the original order, and to discard duplicate messages.

**messaging.** See *synchronous messaging* and *asynchronous messaging*.

**MFS.** Message format service.

**model queue object.** A set of queue attributes that act as a template when a program creates a dynamic queue.

**MQAI.** MQSeries Administration Interface.

**MQI.** Message queue interface.

**MQI channel.** Connects an MQSeries client to a queue manager on a server system, and transfers only MQI calls and responses in a bidirectional manner. Contrast with *message channel*.

**MQSC.** MQSeries commands.

**MQSeries.** A family of IBM licensed programs that provides message queuing services.

**MQSeries Administration Interface (MQAI).** A programming interface to MQSeries.

**MQSeries client.** Part of an MQSeries product that can be installed on a system without installing the full queue manager. The MQSeries client accepts MQI calls from applications and communicates with a queue manager on a server system.

**MQSeries commands (MQSC).** Human readable commands, uniform across all platforms, that are used to manipulate MQSeries objects. Contrast with *programmable command format (PCF)*.

## N

**namelist.** An MQSeries object that contains a list of names, for example, queue names.

**name service.** In MQSeries on UNIX systems, MQSeries for OS/2 Warp, and MQSeries for Windows NT, the facility that determines which queue manager owns a specified queue.

**name service interface (NSI).** The MQSeries interface to which customer- or vendor-written programs that resolve queue-name ownership must conform. A part of the MQSeries Framework.

**name transformation.** In MQSeries on UNIX systems, MQSeries for OS/2 Warp, and MQSeries for Windows NT, an internal process that changes a queue manager name so that it is unique and valid for the system being used. Externally, the queue manager name remains unchanged.

**New Technology File System (NTFS).** A Windows NT recoverable file system that provides security for files.

**nonpersistent message.** A message that does not survive a restart of the queue manager. Contrast with *persistent message*.

**NSI.** Name service interface.

**NTFS.** New Technology File System.

**null character.** The character that is represented by X'00'.

## O

**OAM.** Object authority manager.

**object.** In MQSeries, an object is a queue manager, a queue, a process definition, a channel, a namelist, or a storage class (OS/390 only).

**object authority manager (OAM).** In MQSeries on UNIX systems and MQSeries for Windows NT, the default authorization service for command and object management. The OAM can be replaced by, or run in combination with, a customer-supplied security service.

**object descriptor.** A data structure that identifies a particular MQSeries object. Included in the descriptor are the name of the object and the object type.

**object handle.** The identifier or token by which a program accesses the MQSeries object with which it is working.

## off-loading • queue

**off-loading.** In MQSeries for OS/390, an automatic process whereby a queue manager's active log is transferred to its archive log.

**Open Transaction Manager Access (OTMA).** A transaction-based, connectionless client/server protocol. It functions as an interface for host-based communications servers accessing IMS TM applications through the OS/390 Cross Systems Coupling Facility (XCF). OTMA is implemented in an OS/390 sysplex environment. Therefore, the domain of OTMA is restricted to the domain of XCF.

**OTMA.** Open Transaction Manager Access.

**output log-buffer.** In MQSeries for OS/390, a buffer that holds recovery log records before they are written to the archive log.

**output parameter.** A parameter of an MQI call in which the queue manager returns information when the call completes or fails.

## P

**page set.** A VSAM data set used when MQSeries for OS/390 moves data (for example, queues and messages) from buffers in main storage to permanent backing storage (DASD).

**PCF.** Programmable command format.

**PCF command.** See *programmable command format*.

**pending event.** An unscheduled event that occurs as a result of a connect request from a CICS adapter.

**percolation.** In error recovery, the passing along a preestablished path of control from a recovery routine to a higher-level recovery routine.

**performance event.** A category of event indicating that a limit condition has occurred.

**performance trace.** An MQSeries trace option where the trace data is to be used for performance analysis and tuning.

**permanent dynamic queue.** A dynamic queue that is deleted when it is closed only if deletion is explicitly requested. Permanent dynamic queues are recovered if the queue manager fails, so they can contain persistent messages. Contrast with *temporary dynamic queue*.

**persistent message.** A message that survives a restart of the queue manager. Contrast with *nonpersistent message*.

**ping.** In distributed queuing, a diagnostic aid that uses the exchange of a test message to confirm that a message channel or a TCP/IP connection is functioning.

**platform.** In MQSeries, the operating system under which a queue manager is running.

**point of recovery.** In MQSeries for OS/390, the term used to describe a set of backup copies of MQSeries for OS/390 page sets and the corresponding log data sets required to recover these page sets. These backup copies provide a potential restart point in the event of page set loss (for example, page set I/O error).

**preemptive shutdown.** In MQSeries, a shutdown of a queue manager that does not wait for connected applications to disconnect, nor for current MQI calls to complete. Contrast with *immediate shutdown* and *quiesced shutdown*.

**principal.** In MQSeries on UNIX systems, MQSeries for OS/2 Warp, and MQSeries for Windows NT, a term used for a user identifier. Used by the object authority manager for checking authorizations to system resources.

**process definition object.** An MQSeries object that contains the definition of an MQSeries application. For example, a queue manager uses the definition when it works with trigger messages.

**programmable command format (PCF).** A type of MQSeries message used by:

- User administration applications, to put PCF commands onto the system command input queue of a specified queue manager
- User administration applications, to get the results of a PCF command from a specified queue manager
- A queue manager, as a notification that an event has occurred

Contrast with *MQSC*.

**program temporary fix (PTF).** A solution or by-pass of a problem diagnosed by IBM field engineering as the result of a defect in a current, unaltered release of a program.

**PTF.** Program temporary fix.

## Q

**queue.** An MQSeries object. Message queuing applications can put messages on, and get messages from, a queue. A queue is owned and maintained by a queue manager. Local queues can contain a list of messages waiting to be processed. Queues of other

types cannot contain messages—they point to other queues, or can be used as models for dynamic queues.

**queue manager.** (1) A system program that provides queuing services to applications. It provides an application programming interface so that programs can access messages on the queues that the queue manager owns. See also *local queue manager* and *remote queue manager*. (2) An MQSeries object that defines the attributes of a particular queue manager.

**queue manager event.** An event that indicates:

- An error condition has occurred in relation to the resources used by a queue manager. For example, a queue is unavailable.
- A significant change has occurred in the queue manager. For example, a queue manager has stopped or started.

**queuing.** See *message queuing*.

**quiesced shutdown.** (1) In MQSeries, a shutdown of a queue manager that allows all connected applications to disconnect. Contrast with *immediate shutdown* and *preemptive shutdown*. (2) A type of shutdown of the CICS adapter where the adapter disconnects from MQSeries, but only after all the currently active tasks have been completed. Contrast with *forced shutdown*.

**quiescing.** In MQSeries, the state of a queue manager prior to it being stopped. In this state, programs are allowed to finish processing, but no new programs are allowed to start.

## R

**RBA.** Relative byte address.

**reason code.** A return code that describes the reason for the failure or partial success of an MQI call.

**receiver channel.** In message queuing, a channel that responds to a sender channel, takes messages from a communication link, and puts them on a local queue.

**recovery log.** In MQSeries for OS/390, data sets containing information needed to recover messages, queues, and the MQSeries subsystem. MQSeries for OS/390 writes each record to a data set called the *active log*. When the active log is full, its contents are off-loaded to a DASD or tape data set called the *archive log*. Synonymous with *log*.

**recovery termination manager (RTM).** A program that handles all normal and abnormal termination of tasks by passing control to a recovery routine associated with the terminating function.

**reference message.** A message that refers to a piece of data that is to be transmitted. The reference

message is handled by message exit programs, which attach and detach the data from the message so allowing the data to be transmitted without having to be stored on any queues.

**Registry.** In Windows NT, a secure database that provides a single source for system and application configuration data.

**Registry Editor.** In Windows NT, the program item that allows the user to edit the Registry.

**Registry Hive.** In Windows NT, the structure of the data stored in the Registry.

**relative byte address (RBA).** The displacement in bytes of a stored record or control interval from the beginning of the storage space allocated to the data set to which it belongs.

**remote queue.** A queue belonging to a remote queue manager. Programs can put messages on remote queues, but they cannot get messages from remote queues. Contrast with *local queue*.

**remote queue manager.** To a program, a queue manager that is not the one to which the program is connected.

**remote queue object.** See *local definition of a remote queue*.

**remote queuing.** In message queuing, the provision of services to enable applications to put messages on queues belonging to other queue managers.

**reply message.** A type of message used for replies to request messages. Contrast with *request message* and *report message*.

**reply-to queue.** The name of a queue to which the program that issued an MQPUT call wants a reply message or report message sent.

**report message.** A type of message that gives information about another message. A report message can indicate that a message has been delivered, has arrived at its destination, has expired, or could not be processed for some reason. Contrast with *reply message* and *request message*.

**requester channel.** In message queuing, a channel that may be started remotely by a sender channel. The requester channel accepts messages from the sender channel over a communication link and puts the messages on the local queue designated in the message. See also *server channel*.

**request message.** A type of message used to request a reply from another program. Contrast with *reply message* and *report message*.

## RESLEVEL • single logging

**RESLEVEL.** In MQSeries for OS/390, an option that controls the number of CICS user IDs checked for API-resource security in MQSeries for OS/390.

**resolution path.** The set of queues that are opened when an application specifies an alias or a remote queue on input to an MQOPEN call.

**resource.** Any facility of the computing system or operating system required by a job or task. In MQSeries for OS/390, examples of resources are buffer pools, page sets, log data sets, queues, and messages.

**resource manager.** An application, program, or transaction that manages and controls access to shared resources such as memory buffers and data sets. MQSeries, CICS, and IMS are resource managers.

| **Resource Recovery Services (RRS).** An OS/390 facility that provides 2-phase syncpoint support across participating resource managers.

**responder.** In distributed queuing, a program that replies to network connection requests from another system.

**resynch.** In MQSeries, an option to direct a channel to start up and resolve any in-doubt status messages, but without restarting message transfer.

**return codes.** The collective name for completion codes and reason codes.

**rollback.** Synonym for *back out*.

| **RRS.** Resource Recovery Services.

**RTM.** Recovery termination manager.

**rules table.** A control file containing one or more rules that the dead-letter queue handler applies to messages on the DLQ.

## S

**SAF.** System Authorization Facility.

**SDWA.** System diagnostic work area.

**security enabling interface (SEI).** The MQSeries interface to which customer- or vendor-written programs that check authorization, supply a user identifier, or perform authentication must conform. A part of the MQSeries Framework.

**SEI.** Security enabling interface.

**sender channel.** In message queuing, a channel that initiates transfers, removes messages from a

transmission queue, and moves them over a communication link to a receiver or requester channel.

**sequential delivery.** In MQSeries, a method of transmitting messages with a sequence number so that the receiving channel can reestablish the message sequence when storing the messages. This is required where messages must be delivered only once, and in the correct order.

**sequential number wrap value.** In MQSeries, a method of ensuring that both ends of a communication link reset their current message sequence numbers at the same time. Transmitting messages with a sequence number ensures that the receiving channel can reestablish the message sequence when storing the messages.

**server.** (1) In MQSeries, a queue manager that provides queue services to client applications running on a remote workstation. (2) The program that responds to requests for information in the particular two-program, information-flow model of client/server. See also *client*.

**server channel.** In message queuing, a channel that responds to a requester channel, removes messages from a transmission queue, and moves them over a communication link to the requester channel.

**server connection channel type.** The type of MQI channel definition associated with the server that runs a queue manager. See also *client connection channel type*.

**service interval.** A time interval, against which the elapsed time between a put or a get and a subsequent get is compared by the queue manager in deciding whether the conditions for a service interval event have been met. The service interval for a queue is specified by a queue attribute.

**service interval event.** An event related to the service interval.

**session ID.** In MQSeries for OS/390, the CICS-unique identifier that defines the communication link to be used by a message channel agent when moving messages from a transmission queue to a link.

**shutdown.** See *immediate shutdown*, *preemptive shutdown*, and *quiesced shutdown*.

**signaling.** In MQSeries for OS/390 and MQSeries for Windows 2.1, a feature that allows the operating system to notify a program when an expected message arrives on a queue.

**single logging.** A method of recording MQSeries for OS/390 activity where each change is recorded on one data set only. Contrast with *dual logging*.

**single-phase backout.** A method in which an action in progress must not be allowed to finish, and all changes that are part of that action must be undone.

**single-phase commit.** A method in which a program can commit updates to a queue without coordinating those updates with updates the program has made to resources controlled by another resource manager. Contrast with *two-phase commit*.

**SIT.** System initialization table.

**stanza.** A group of lines in a configuration file that assigns a value to a parameter modifying the behavior of a queue manager, client, or channel. In MQSeries on UNIX systems, MQSeries for OS/2 Warp, and MQSeries for Windows NT, a configuration (.ini) file may contain a number of stanzas.

**storage class.** In MQSeries for OS/390, a storage class defines the page set that is to hold the messages for a particular queue. The storage class is specified when the queue is defined.

**store and forward.** The temporary storing of packets, messages, or frames in a data network before they are retransmitted toward their destination.

**subsystem.** In OS/390, a group of modules that provides function that is dependent on OS/390. For example, MQSeries for OS/390 is an OS/390 subsystem.

**supervisor call (SVC).** An OS/390 instruction that interrupts a running program and passes control to the supervisor so that it can perform the specific service indicated by the instruction.

**SVC.** Supervisor call.

**switch profile.** In MQSeries for OS/390, a RACF profile used when MQSeries starts up or when a refresh security command is issued. Each switch profile that MQSeries detects turns off checking for the specified resource.

**symptom string.** Diagnostic information displayed in a structured format designed for searching the IBM software support database.

**synchronous messaging.** A method of communication between programs in which programs place messages on message queues. With synchronous messaging, the sending program waits for a reply to its message before resuming its own processing. Contrast with *asynchronous messaging*.

**syncpoint.** An intermediate or end point during processing of a transaction at which the transaction's protected resources are consistent. At a syncpoint,

changes to the resources can safely be committed, or they can be backed out to the previous syncpoint.

**System Authorization Facility (SAF).** An OS/390 facility through which MQSeries for OS/390 communicates with an external security manager such as RACF.

**system.command.input queue.** A local queue on which application programs can put MQSeries commands. The commands are retrieved from the queue by the command server, which validates them and passes them to the command processor to be run.

**system control commands.** Commands used to manipulate platform-specific entities such as buffer pools, storage classes, and page sets.

**system diagnostic work area (SDWA).** Data recorded in a SYS1.LOGREC entry, which describes a program or hardware error.

**system initialization table (SIT).** A table containing parameters used by CICS on start up.

**SYS1.LOGREC.** A service aid containing information about program and hardware errors.

## T

**target library high-level qualifier (thlqual).** High-level qualifier for OS/390 target data set names.

**task control block (TCB).** An OS/390 control block used to communicate information about tasks within an address space that are connected to an OS/390 subsystem such as MQSeries for OS/390 or CICS.

**task switching.** The overlapping of I/O operations and processing between several tasks. In MQSeries for OS/390, the task switcher optimizes performance by allowing some MQI calls to be executed under subtasks rather than under the main CICS TCB.

**TCB.** Task control block.

**TCP/IP.** Transmission Control Protocol/Internet Protocol.

**temporary dynamic queue.** A dynamic queue that is deleted when it is closed. Temporary dynamic queues are not recovered if the queue manager fails, so they can contain nonpersistent messages only. Contrast with *permanent dynamic queue*.

**termination notification.** A pending event that is activated when a CICS subsystem successfully connects to MQSeries for OS/390.

**thlqual.** Target library high-level qualifier.

**thread.** In MQSeries, the lowest level of parallel execution available on an operating system platform.

**time-independent messaging.** See *asynchronous messaging*.

**TMI.** Trigger monitor interface.

**trace.** In MQSeries, a facility for recording MQSeries activity. The destinations for trace entries can include GTF and the system management facility (SMF). See also *global trace* and *performance trace*.

**tranid.** See *transaction identifier*.

**transaction.** See *unit of work* and *CICS transaction*.

**transaction identifier.** In CICS, a name that is specified when the transaction is defined, and that is used to invoke the transaction.

**transaction manager.** A software unit that coordinates the activities of resource managers by managing global transactions and coordinating the decision to commit them or roll them back. V5.1 of MQSeries for AIX, HP-UX, OS/2 Warp, Sun Solaris, and Windows NT is a transaction manager.

**Transmission Control Protocol/Internet Protocol (TCP/IP).** A suite of communication protocols that support peer-to-peer connectivity functions for both local and wide area networks.

**transmission program.** See *message channel agent*.

**transmission queue.** A local queue on which prepared messages destined for a remote queue manager are temporarily stored.

**trigger event.** An event (such as a message arriving on a queue) that causes a queue manager to create a trigger message on an initiation queue.

**triggering.** In MQSeries, a facility allowing a queue manager to start an application automatically when predetermined conditions on a queue are satisfied.

**trigger message.** A message containing information about the program that a trigger monitor is to start.

**trigger monitor.** A continuously-running application serving one or more initiation queues. When a trigger message arrives on an initiation queue, the trigger monitor retrieves the message. It uses the information in the trigger message to start a process that serves the queue on which a trigger event occurred.

**trigger monitor interface (TMI).** The MQSeries interface to which customer- or vendor-written trigger monitor programs must conform. A part of the MQSeries Framework.

**two-phase commit.** A protocol for the coordination of changes to recoverable resources when more than one resource manager is used by a single transaction. Contrast with *single-phase commit*.

## U

**UIS.** User identifier service.

**undelivered-message queue.** See *dead-letter queue*.

**undo/redo record.** A log record used in recovery. The redo part of the record describes a change to be made to an MQSeries object. The undo part describes how to back out the change if the work is not committed.

**unit of recovery.** A recoverable sequence of operations within a single resource manager. Contrast with *unit of work*.

**unit of work.** A recoverable sequence of operations performed by an application between two points of consistency. A unit of work begins when a transaction starts or after a user-requested syncpoint. It ends either at a user-requested syncpoint or at the end of a transaction. Contrast with *unit of recovery*.

**user identifier service (UIS).** In MQSeries for OS/2 Warp, the facility that allows MQI applications to associate a user ID, other than the default user ID, with MQSeries messages.

**utility.** In MQSeries, a supplied set of programs that provide the system operator or system administrator with facilities in addition to those provided by the MQSeries commands. Some utilities invoke more than one function.

## X

**X/Open XA.** The X/Open Distributed Transaction Processing XA interface. A proposed standard for distributed transaction communication. The standard specifies a bidirectional interface between resource managers that provide access to shared resources within transactions, and between a transaction service that monitors and resolves transactions.

**XCF.** Cross Systems Coupling Facility.

# Index

## A

- abend
  - AEY9 223
  - QLOP 223
- accounting using message context 37
- AccountingToken field 37
- activation group
  - AS/400 266
- adapter
  - batch 221
  - CICS 222
  - IMS 224
  - trace points 222
- administration, platform comparison 562
- AEY9 abend 223
- alias queue
  - examples of when to use 44
  - overview 41
  - resolving queue name 101
- alias queue manager definition 99
- alternate PCB, IMS bridge 242
- alternate user authority 104
- AlternateUserId field 104
- AMQ0ECHA sample program 369
- amq0gbr0 sample program 327, 346
- amq0get0 sample program 327, 349
- AMQ0GET4 sample program 349
- amq0put0 sample program 327, 342
- amq0req0 sample program 327, 359
- AMQ0REQ4 sample program 359
- AMQ0SETA sample program 367
- amqiech2 sample program 330, 369
- amqiechx sample program 327, 369
- amqiinq2 sample program 330, 366
- amqiinqx sample program 327, 366
- amqiset2 sample program 330, 367
- amqisetx sample program 327, 367
- amqltmc0 trigger monitor 214
- amqmech2 sample program 330, 369
- amqmechx sample program 327, 369
- amqminq2 sample program 330, 366
- amqminqx sample program 327, 366
- amqmset2 sample program 330, 367
- amqmsetx sample program 327, 367
- amqrgrma sample program 351
- amqsbcg sample program 347
- amqsbcg0 sample program 327, 347
- amqsbcgc sample program 347
- amqscic0 sample transaction 327, 379
- amqscic21 sample transaction 327
- amqsdlq sample program 327
- amqsech sample program 369
- amqsecha sample program 327, 369
- amqsechc sample program 369
- AMQSERV4 sample program 212, 371, 372
- amqsgbr sample program 346
- amqsgbr0 sample program 327, 346
- AMQSGBR4 sample program 346
- amqsgbrc sample program 346
- amqsget0 sample program 327, 349
- AMQSGET4 sample program 349
- amqsgetc sample program 327, 349
- amqsgetw sample program 327, 349
- amqsinqa sample program 366
- amqsinqc sample program 366
- amqsprma sample program 351
- amqsptl0 sample program 345
- amqsput0 sample program 327, 342
- AMQSPUT4 sample program 342
- amqsputc sample program 327, 342
- amqsputw sample program 327, 342, 343
- amqsreq sample program 359
- amqsreq0 sample program 327, 359
- AMQSREQ4 sample program 359
- amqsreqc sample program 359
- amqsset sample program 367
- amqsseta sample program 367
- amqssetc sample program 367
- amqstrg sample program 371
- amqstrg0 sample program 327, 371
- AMQSTRG4 sample program 212, 371
- amqstrgc sample program 371
- amqstxgx sample program 327, 379
- amqstxpx sample program 327, 379
- amqstxsx sample program 327, 379
- amqsvfc0 sample program 330, 370
- AMQSVFC4 sample program 333, 370
- amqsvfcx sample program 370
- amqsxa4x sample transaction 327
- amqsxab0.sqb sample 373
- amqsxab0.sqc sample 373
- amqsxaex sample transaction 327, 390
- amqsxaf0.sqb sample 373
- amqsxaf0.sqc sample 373
- amqsxag0.c sample 373
- amqsxag0.cbl sample 373
- amqsxas0.sqb sample 373
- amqsxas0.sqc sample 373
- amqsxrma sample program 351
- amqzsc (XA switch load module) 195
- amqzsc21 (XA switch load module) 195

## Index

- amqzsca (XA switch load module) 195
  - API (Application Programming Interface)
    - calls 66
    - dealing with failure of a call 53
  - API-crossing exit for OS/390 225
  - application data 23
  - application design
    - for more than one platform 21
    - overview 13
  - application queue 197
  - applications, writing 243
  - ApplIdentityData field 37
  - ApplOriginData field 38
  - assembler language
    - assemblers supported 453
    - examples
      - MQCLOSE 512
      - MQCONN 510
      - MQDISC 510
      - MQGET 514
      - MQGET with signaling 516
      - MQGET with wait option 515
      - MQINQ 517
      - MQOPEN for dynamic queue 511
      - MQOPEN for existing queue 512
      - MQPUT 513
      - MQPUT1 513
      - MQSET 517
    - macros 535
    - preparing your program to run 275
    - support for 79
    - using constants and structures 535
    - using the MQI 79
  - attributes
    - DefInputOpenOption 102
    - DefPriority 32
    - HardenGetBackout 36, 55
    - IndexType 139
    - inquiring about 179
    - MaxMsgLength 111, 128
    - MaxPriority 32
    - MsgDeliverySequence 35, 128
    - queue manager 39
    - queues 43
    - selectors 179
    - setting 179
    - Shareability 102
    - TriggerControl 208
    - TriggerDepth 209
    - TriggerInterval 210
    - TriggerMsgPriority 208
    - TriggerType 208
  - audit trail using message context 37
  - authority checking
    - alternate user authority on MQOPEN 104
    - by MQCLOSE 95
    - authority checking (*continued*)
      - by MQDISC 95
      - by MQOPEN 97
  - automatically starting an application
    - an example 361
    - how triggering works 197
    - introduction 17
- ## B
- backing out changes 35, 183
  - backout, skipping 150
  - BackoutCount field 35, 55
  - base queue 44
  - Basic
    - compilers supported 453
  - batch for MQSeries for OS/390
    - adapter 221
    - building an application 275
    - calling the stub dynamically 279
    - restrictions 84
    - support for 219
  - benefits of message queuing 10
  - bibliography xviii
  - binding
    - FASTPATH 92
    - STANDARD 92
  - BookManager xxii
  - browse cursor 102, 154
  - browsing (sample for MQSeries for OS/390) 414
  - browsing messages 154
  - browsing messages in logical order 156
  - Buffer parameter 111
  - BufferLength parameter 127
  - building your application
    - batch with MQSeries for OS/390 275
    - CICS and MQSeries for OS/390 277
    - IMS 278
    - on AIX 259
    - on AS/400 265
    - on Digital OpenVMS 269
    - on HP-UX 271
    - on NCR UNIX SVR4 MP-RAS, R3.0 267
    - on OS/2 Warp 289
    - on OS/390 275
    - on SINIX or DC/OSx 293
    - on Sun Solaris 297
    - on Tandem NSK 301
    - on VSE/ESA 305
    - on Windows 307
    - on Windows NT 309
  - built-in formats 31

**C**

## C language

compilers supported 453

## examples

MQCLOSE 490

MQCONN 488

MQDISC 488

MQGET 492

MQGET with signaling 493

MQGET with wait option 492

MQINQ 494

MQOPEN for dynamic queue 489

MQOPEN for existing queue 489

MQPUT 490

MQPUT1 491

MQSET 495

include files 530

support for 76

## C language include files

&lt;cmqc.h&gt; 530

&lt;cmqfc.h&gt; 530

&lt;cmqxc.h&gt; 530

&lt;cmqzc.h&gt; 530

header files 530

include files 530

## C++

support for 75

## C++ language

compilers supported 453

## C++ sample programs 327

## call interface 66

calling dynamically with MQSeries for OS/390 279

CAM (credit application manager) 434

CCSID (Coded Character Set Identifier)

same as queue manager 30

CEDF (CICS Execution Diagnostic Facility) 82, 223

CETR (CICS Trace Control transaction) 284

## channel

data-conversion exit 161

channel queue 42

## CICS

adapter 222

calling the stub dynamically with MQSeries for OS/390 279

COBOL applications 262, 311, 312

debugging programs 284

Execution Diagnostic Facility 82

MQSeries for OS/390 support 219

preparing C programs 263, 300

sample transaction for MQSeries for AIX 263, 273

sample transaction for MQSeries for SINIX and DC/OSx 295

sample transaction for MQSeries for Sun

Solaris 300

storage protection facility 228

CICS (*continued*)

trace 284

Trace Control transaction 284

with MQSeries for AIX 262

with MQSeries for HP-UX 273

with MQSeries for OS/2 Warp 290

with MQSeries for OS/390 277

with MQSeries for SINIX and DC/OSx 295

with MQSeries for Sun Solaris 299

with MQSeries for Windows NT 310

## CICS adapter

abends 223

QLOP abend 223

trace points 222

using CEDF 223

## CICS bridge

3270 considerations 234

error handling 233

examples 234

handling units of work 233

message structure 231

messages returned 232

writing applications 230

CICS Execution Diagnostic Facility (CEDF) 223

CICS for OS/2 user exit 15 193

CICS sample transaction 379

CKQC transaction 89, 284

CKTI transaction 212, 217

client (MQSeries)

LU 6.2 link library 272

MQSeries clients and servers 10

triggering support 197

what it is 6

CLISTs for Mail Manager sample application (MQSeries for OS/390) 422

## cluster

what it is 6

## cluster queue

MQOPEN option 102

overview 42

## clusters (message affinities)

MQSeries techniques 17

## COBOL

CICS applications 262, 311, 312

compilers supported 453

copy files 532

## examples

MQCLOSE 501

MQCONN 498

MQDISC 498

MQGET 503

MQGET with signaling 505

MQGET with wait option 504

MQINQ 506

MQOPEN for dynamic queue 499

MQOPEN for existing queue 500

MQPUT 501

## Index

- COBOL (*continued*)
  - examples (*continued*)
    - MQPUT1 502
    - MQSET 507
  - LITLINK directive 291, 294, 312
  - on AIX 260
  - on AS/400 265
  - on HP-UX 272
  - on OS/2 291
  - on SINIX or DC/OSx 294
  - on Sun Solaris 298
  - on Windows NT 311
  - support for 78
  - using named constants 79
- Coded Character Set Identifier (CCSID)
  - same as queue manager 30
- coded character sets 32
- CodedCharSetId (CCSID) 30
  - message data 30
- commit
  - single-phase 183
  - two-phase 184
- commitment control considerations 188
- committing changes 183
- communication
  - connectionless 7
  - time-independent 8
- comparisons, functional 539
- comparisons, MQSeries platforms 539
- compilers supported 453
- compiling
  - for MQSeries for AIX 259
  - for MQSeries for AS/400 265
  - for MQSeries for AT&T GIS UNIX 267
  - for MQSeries for Digital OpenVMS 269
  - for MQSeries for HP-UX 271
  - for MQSeries for OS/2 Warp 289
  - for MQSeries for OS/390 275
  - for MQSeries for SINIX and DC/OSx 293
  - for MQSeries for Sun Solaris 297
  - for MQSeries for Windows 307
  - for MQSeries for Windows NT 309
- completion code 74
- confirmation of arrival (COA) report 25
- confirmation of delivery (COD) report 25
- connecting to a queue manager 90, 92
- connection 566
- connection handle
  - returned from MQCONN 91
  - returned from MQCONNX 92
  - using with MQGET 124
  - what it is 74
- connectionless communication 7
- constants in COBOL 79
- context
  - default 113
- context (*continued*)
  - identity 37
  - message 37
  - MQOPEN options 103
  - MQPUT options 113
  - origin 38
- context (Credit Check sample application) 441
- Context field 109
- control information 23
- convert characters call 164
- convert message data
  - MQGET 125, 152
- copy files
  - how to use them 532
- copying messages 154
- correlation identifier 35
- CorrelId field 35, 137
- creating conversion-exit code 164
- credit application manager (CAM) 434
- credit check sample (MQSeries for OS/390) 430
- CRTMQCVX 164
- CSQ4BAA1 sample 414
- CSQ4BCA1 sample 414
- CSQ4BVA1 sample 414
- CSQ4CAC1 sample 420
- CSQ4CCB5 sample 438
- CSQ4CCC1 sample 420
- CSQ4CCG1 sample 416
- CSQ4CVB1 sample 434
- CSQ4CVB2 sample 434
- CSQ4CVB3 sample 437
- CSQ4CVB4 sample 438
- CSQ4CVB5 sample 438
- CSQ4CVC1 sample 420
- CSQ4CVD1 sample 426
- CSQ4CVD2 sample 427
- CSQ4CVD3 sample 427
- CSQ4CVD4 sample 429
- CSQ4CVD5 sample 429
- CSQ4ICB3 sample 443
- CSQ4RCD1 sample 422
- CSQ4RVD1 sample 422
- CSQ4TCD1 sample 426
- CSQ4TCD2 sample 427
- CSQ4TCD4 sample 429
- CSQ4TCD5 sample 429
- CSQ4TVD1 sample 426
- CSQ4TVD2 sample 427
- CSQ4TVD4 sample 429
- CSQ4TVD5 sample 429
- CSQCAPX sample 225
- CSQQTRMN transaction 212, 217
- cursor, browse 102, 154
- CVTMQMMDTA 164

**D**

- data
  - application 23
  - message 23, 111
- data conversion
  - amqsvfc0 sample program 370
  - AMQSVFC4 sample program 370
  - amqsvfcx sample program 370
  - application 31
  - comparison by platform 550
  - convert characters call 164
  - convert MQSeries Data Type command 164
  - create MQSeries conversion-exit command 164
  - IMS bridge 242
  - interface 161
  - message 152
  - MQGET 125, 152
  - MQXCNCV call 68
  - OS/390 considerations 162
  - UNIX environment 174
- data conversion interface (DCI) 161
- data definition files 69
  - copy files 529
  - header files 529
  - include files 529
  - macros 529
- data in a message 23, 111
- data types
  - elementary 68
  - structures 68
- data-conversion exit 161, 163
  - amqsvfc0 sample program 370
  - AMQSVFC4 sample program 370
  - amqsvfcx sample program 370
  - convert characters call 164
  - convert MQSeries Data Type command 164
  - create MQSeries conversion-exit command 164
  - IMS bridge 242
  - invoking 161
  - MQXCNCV call 68
  - skeleton 164
  - UNIX environment 174
  - writing 168
    - AS/400 167
    - Digital OpenVMS 172
    - OS/2 168
    - OS/390 170
    - Tandem NSK systems 171
    - UNIX systems 172
    - Windows NT 177
- datagram 24
- DataLength parameter 127
- DCE environment for MQSeries for HP-UX
  - DCE threaded, libraries to use 271
- DCE sample exits 327
- dead-letter (undelivered-message) queue 440
  - handler 58
  - overview 48
  - sample to deal with messages on it 391
  - use within MQSeries for OS/390 sample 440
  - using 57
- dead-letter queue handler
  - brief description 58
  - sample 391
- DeadLetterQName field 204
- debugging programs 284
- default context 113
- defining alias for queue manager 99
- DefInputOpenOption attribute 102
- DefPriority attribute 32
- design considerations
  - performance hints and tips 18
- disconnecting from a queue manager 94
- distribution lists 116
  - identifying 117
  - opening 116
  - putting messages to 119
  - using the MQPMR structure 120
- DOS clients
  - compilers supported 453
- DOS, no triggering support 197
- dynamic linking of MQI calls for MQSeries for OS/390 279
- dynamic queue
  - closing temporary queue 105
  - creating 104
  - overview 45
  - permanent queue properties 46
  - temporary queue properties 45
  - when to use 46
- dynamic XA resource management structure 192
- DynamicQName field 104

**E**

- EBCDIC newline character conversion 153
- ECB (event control block) 148
- Encina sample transaction 390
- Encoding field 30
- ENDMQM
  - AS/400 266
- environments for MQSeries for OS/390 219
- errors
  - dead-letter (undelivered-message) queue 57
  - dealing with failure of a call 53
  - incorrect message data 55
  - report message 55
  - system interruptions 54
  - undelivered-message queue 57

## Index

- event control block 148
  - event queue 42
  - event-driven processing 9
  - examples
    - assembler language
      - MQCLOSE 512
      - MQCONN 510
      - MQDISC 510
      - MQGET 514
      - MQGET with signaling 516
      - MQGET with wait option 515
      - MQINQ 517
      - MQOPEN for dynamic queue 511
      - MQOPEN for existing queue 512
      - MQPUT 513
      - MQPUT1 513
      - MQSET 517
  - C
    - MQCLOSE 490
    - MQCONN 488
    - MQDISC 488
    - MQGET 492
    - MQGET with signaling 493
    - MQGET with wait option 492
    - MQINQ 494
    - MQOPEN for dynamic queue 489
    - MQOPEN for existing queue 489
    - MQPUT 490
    - MQPUT1 491
    - MQSET 495
  - COBOL
    - MQCLOSE 501
    - MQCONN 498
    - MQDISC 498
    - MQGET 503
    - MQGET with signaling 505
    - MQGET with wait option 504
    - MQINQ 506
    - MQOPEN for dynamic queue 499
    - MQOPEN for existing queue 500
    - MQPUT 501
    - MQPUT1 502
    - MQSET 507
  - PL/I
    - MQCLOSE 522
    - MQCONN 520
    - MQDISC 520
    - MQGET 524
    - MQGET with signaling 526
    - MQGET with wait option 525
    - MQINQ 527
    - MQOPEN for dynamic queue 521
    - MQOPEN for existing queue 521
    - MQPUT 522
    - MQPUT1 523
    - MQSET 528
  - exception report 25
  - exclusive access to a queue 102
  - Execution Diagnostic Facility 82
  - execution key of CICS programs 228
  - exit programs 225
    - data conversion 163
  - expiry report 25
  - external syncpoint
    - coordination 191
    - interfaces 192
    - restrictions 193
    - X/Open XA interface 192
- ## F
- FASTPATH binding 92
  - feedback codes, IMS bridge 242
  - Feedback field 27
  - fields
    - AlternateUserId 104
    - ApplIdentityData 37
    - ApplOriginData 38
    - BackoutCount 35, 55
    - Context 109
    - CorrelId 35, 137
    - DeadLetterQName 204
    - DynamicQName 104
    - Encoding 30
    - Feedback 27
    - Format 30
    - GroupId
      - match options 137
      - MQMO 137
    - InitiationQName 202
    - MsgId 137
    - Persistence 34
    - Priority 32
    - PutAppName 38
    - PutAppType 38
    - PutDate 38
    - PutMsgRecFields 110
    - PutMsgRecOffset 110
    - PutMsgRecPtr 110
    - PutTime 38
    - RecsPresent 110
    - ReplyToQ 36
    - ReplyToQMgr 36
    - Report 25
    - ResolvedQMgrName 109
    - ResolvedQName 109
    - ResponseRecOffset 111
    - ResponseRecPtr 111
    - StrucId 109
    - UserIdentifier 37
    - Version 109, 110
    - WaitInterval 126, 146

fonts in this book xvii

format

control information 30

message data 30

Format field 30

formats

built-in 31

user-defined 31

functional comparisons 539

administration 562

connection 566

data conversion 550

input 547

message properties 551

object types 560

programming languages 564

protocols 551

security 556

syncpoint 540

threading 555

triggering 544

## G

get (sample for MQSeries for OS/390) 411

get-message options structure 125

getting

a particular message 137

message from triggered queue 211

message when the length is unknown 155

messages 123

options 123

glossary 573

group

identifier 35

GroupStatus field

MQGMO structure 127

## H

handle

scope of connection 91

scope of connection handle 98

scope of object handle 98

using 74

using object handle 97

HardenGetBackout attribute 36, 55

heap size

for OS/2 MQI client 290

MQSeries for Windows NT 310

HTML (Hypertext Markup Language) xxiii

Hypertext Markup Language (HTML) xxiii

## I

identity context 37

IMS

adapter 224

building an MQSeries for OS/390 application 278

calling the stub dynamically with MQSeries for OS/390 279

closing objects 97

enquiry application (IMS) 249

mapping MQSeries messages to transactions 241

support for 219

using MQI calls 246

using syncpoints 245

writing a server application 246

writing an enquiry application 249

writing MQSeries applications 245

IMS bridge

alternate PCB 242

data conversion 242

feedback codes 242

IMS commands 239

LLZZ data segment 242

mapping MQSeries messages to transactions 241

message segmentation 242

NAK 239

reply messages 242

sense codes 242

undelivered messages 239

writing applications 239

IMS commands, IMS bridge 240

include files

PL/I for MQSeries for OS/390 536

increasing MaxMsgLength 140

initiation queue 47

example to create one 202

what it is 199

InitiationQName field 202

input, platform comparison 547

inquiring about attributes

MQSeries for AS/400 sample program 366

MQSeries for OS/2 Warp sample program 366

MQSeries for OS/390 sample 420

MQSeries for UNIX sample program 366

MQSeries for Windows NT sample program 366

using MQINQ 179

interfaces to external syncpoint managers 192

internal syncpoint coordination 190

invoking data-conversion exit 161

## J

JCL (Job Control Language)

batch 275

CICS and MQSeries for OS/390 277

IMS 278

## Index

### L

- languages 75
- languages supported 453
- large messages
  - reference messages 140
  - segmented messages 140
- LDAP (lightweight directory access protocol) 315
- libraries to use
  - with MQSeries for AIX 259
  - with MQSeries for AT&T GIS UNIX 268
  - with MQSeries for Digital OpenVMS 269
  - with MQSeries for HP-UX 271
  - with MQSeries for OS/2 Warp 289
  - with MQSeries for SINIX and DC/OSx 296
  - with MQSeries for Sun Solaris 298
  - with MQSeries for Windows 307
  - with MQSeries for Windows NT 309
- library files 69
- libsna.a 272
- libsna stubs.a 272
- lightweight directory access protocol (LDAP) 315
- linking 293
  - for MQSeries for AIX 259
  - for MQSeries for AS/400 265
  - for MQSeries for AT&T GIS UNIX 267
  - for MQSeries for Digital OpenVMS 269
  - for MQSeries for HP-UX 271
  - for MQSeries for OS/2 Warp 289
  - for MQSeries for OS/390 275
  - for MQSeries for SINIX and DC/OSx 293
  - for MQSeries for Sun Solaris 297
  - for MQSeries for Windows 307
  - for MQSeries for Windows NT 309
- linking in the MQI client environment
  - when using LU 6.2 272
- LLZZ data segment, IMS bridge 242
- local queue 41
- looking at a message 154

### M

- macros, assembler language 535
- mail manager sample application (MQSeries for OS/390) 421
- MatchOptions field
  - MQGMO structure 127
- maximum message length
  - increasing 140
- MaxMsgLength attribute 111, 128
- MaxPriority attribute 32
- MCA (message channel agent), definition of 4
- message
  - backed out 35
  - browsing 154
  - browsing and removing 156

- message (*continued*)
  - browsing in logical order 156
  - browsing when message length unknown 155
  - channel agent definition 4
  - confirm arrival 25, 554
  - confirm delivery 25, 554
  - context
    - MQOPEN options 103
    - MQPUT options 113
    - types 37
  - copying 154
  - creating 23
  - data 23, 111
  - data conversion
    - considerations 31
    - MQGET 152
  - data format 29
  - datagram 24
  - definition 4
  - descriptor
    - MQMD structure 23
    - when using MQGET 124
    - when using MQPUT 108
  - design 15
  - exception 25
  - expiry 25, 554
  - getting 123
  - getting a particular 137
  - groups 33
  - identifier 35
  - large 140
  - logical ordering 129
  - looking at 154
  - maximum size 111
  - negative action notification 26, 554
  - notification of arrival 147
  - order of retrieval from a queue 128
  - originator information 38
  - persistence 34
  - persistence and triggers 215
  - physical ordering 129
  - positive action notification 26, 554
  - priority 32, 128
  - priority and triggers 215
  - problem delivering 57
  - putting 107
  - putting one 114
  - reference 144
  - removing after browsing 156
  - reply 25
  - reply, IMS bridge 242
  - report 25, 55
  - request 24
  - retry sending 57
  - return to sender 57
  - sample to deal with those on dead-letter queue 391

- message (*continued*)
  - segmentation 141
  - segmented 33
  - selecting from a queue 35
  - signaling 147
  - size 111
  - structure 23
  - trigger 198, 215
  - trigger after queue manager restart 215
  - trigger format 216
  - type for status information 25
  - type when no reply required 24
  - types 24
  - undeliverable, IMS bridge 241
  - undelivered 57
  - undelivered, sample to handle 391
  - use of types 24
  - waiting for 146
- message affinities (clusters)
  - MQSeries techniques 17
- message channel agent (MCA), definition of 4
- message context (Credit Check sample application) 441
- message data conversion, MQGET 125, 152
- message handler sample (MQSeries for OS/390) 443
- message properties, platform comparison 551
- Message Queue Interface 18
  - calls 66
  - data definition files 69
  - dealing with failure of a call 53
  - elementary data types 68
  - library files 69
  - structures 68
  - stub programs 69
  - using System/390 assembler 79
- message queue, definition of 4
- message queuing 3
  - benefits of 10
  - features 7
- message segmentation, IMS bridge 242
- messages
  - mapping to IMS transaction types 241
- model queue 45, 104
- MQ\_MSG\_HEADER\_LENGTH 112
- MQ\*\_DEFAULT values
  - with MQSeries for AIX 77
- MQCA\_\* values 179
- MQCLOSE
  - authority checking 95
  - call parameters 106
  - closing a queue 105
- MQCMIT 186
- MQCONN
  - call parameters 90
  - scope of 91
- MQCONNX 92
- MQDH 112
- MQDISC
  - authority checking 95
  - when to use 94
- MQDLH 57, 111
- MQGET
  - backing out changes 183
  - buffer size 127
  - call parameters 123
  - committing changes 183
  - data conversion 152
  - increase speed of 139
  - message data conversion 125
  - message options 125
  - order of message retrieval 128
  - to get a specific message 137
  - triggered queues 211
  - unknown message length 155
  - using MQGMO 125
  - using MQMD 124
  - when it fails 159
  - when to use 123
- MQGMO 125
- MQGMO\_ACCEPT\_TRUNCATED\_MSG 127
- MQGMO\_BROWSE\_\* 301
- MQGMO\_BROWSE\_FIRST 154
- MQGMO\_BROWSE\_MSG\_UNDER\_CURSOR 155
- MQGMO\_BROWSE\_NEXT 154
- MQGMO\_CONVERT 152
- MQGMO\_MARK\_SKIP\_BACKOUT 55
  - explanation 150
- MQGMO\_MSG\_UNDER\_CURSOR 156
- MQGMO\_WAIT 146
- MQI (Message Queue Interface)
  - calls 66
  - client library files 69
  - data definition files 69
  - dealing with failure of a call 53
  - elementary data types 68
  - IMS applications 246
  - library files 69
  - overview 18
  - structures 68
  - stub programs 69
  - using System/390 assembler 79
- MQI client
  - LU 6.2 link library 272
- MQIA\_\* values 180
- MQIIH 239
- MQINQ
  - call parameters 180
  - use of selectors 179
  - when it fails 181
- MQMD
  - overview 23

## Index

- MQMD (*continued*)
  - when using MQGET 124
  - when using MQPUT 108
- MQMT\_\* values 24
- MQOD 99
- MQOO\_\* values 101
- MQOPEN
  - browse cursor 154
  - call parameters 98
  - MQOO\_\* values 101
  - object handle 97
  - using MQOD 99
  - using options parameter 101
- MQPMO 108
- MQPUT
  - backing out changes 183
  - call parameters 107
  - committing changes 183
  - context information 113
  - if it fails 121
  - quiescing queue manager 109
  - syncpointing 109
  - using MQPMO 108
- MQPUT1
  - call parameters 114
  - if it fails 121
  - performance 107
- MQRC\_SECOND\_MARK\_NOT\_ALLOWED 150
- MQRMIXASwitch 192
- MQRMIXASwitchDynamic 192
- MQSeries applications
  - planning 13
  - testing 21
- MQSeries client
  - connection to queue manager 91
  - using triggering 198
  - what it is 6
- MQSeries data conversion interface 161
- MQSeries for AIX
  - amqisetx 367
  - amqmsetx 367
  - amqsseta 367
  - amqzsc 195
  - amqzsc21 195
  - amqzsca 195
  - build TUXEDO server environment 379
  - building your application 259
  - CICS support 262
  - compilers supported 453
  - key features 12
  - sample programs 327
  - scope of MQCONN 91
  - set sample 367
  - syncpoints 189
  - triggering using samples 361
  - TUXEDO samples 379
- MQSeries for AIX (*continued*)
  - ubbstxcx.cfg example 384
  - XA switch load module 195
- MQSeries for AS/400
  - AMQZSTUB 265
  - building your application 265
  - commitment control considerations 188
  - compilers supported 453
  - compiling 265
  - CRTCBPLPGM 265
  - CRTCMOD 265
  - disconnecting from queue manager 94
  - key features 12
  - linking 265
  - sample program
    - using triggering 363
  - syncpoint considerations with CICS for AS/400 189
  - syncpoints 188
- MQSeries for AT&T GIS UNIX
  - amqisetx 367
  - amqmsetx 367
  - amqsseta 367
  - building your application 267
  - C compiler 267
  - compilers supported 453
  - flags when compiling 267
  - key features 12
  - link libraries 268
  - sample programs 327
  - set sample 367
  - syncpoints 189
  - triggering using samples 361
  - TUXEDO samples 379
  - ubbstxcx.cfg example 384
- MQSeries for Digital OpenVMS
  - building your application 269
  - C compiler 269
  - compilers supported 453
  - flags when compiling 269
  - link libraries 269
  - sample programs 327
- MQSeries for HP-UX
  - amqisetx 367
  - amqmsetx 367
  - amqsseta 367
  - amqzsc 195
  - build TUXEDO server environment 382
  - building your application 271
  - CICS support 273
  - compilers supported 453
  - sample programs 327
  - scope of MQCONN 91
  - set sample 367
  - syncpoints 189
  - triggering using samples 361
  - TUXEDO samples 379

- MQSeries for HP-UX (*continued*)
  - ubbstxcx.cfg example 384
  - XA switch load module 195
- MQSeries for OS/2 Warp
  - building your application 289
  - CICS support 290
  - compilers supported 453
  - key features 12
  - sample programs 327
  - scope of MQCONN 91
  - syncpoints 189
  - Transaction Server support 290, 292
  - triggering using samples 361
  - TZ environment variable 38
- MQSeries for OS/390
  - building your application 275
  - CMQA 535
  - CMQDLHA 535
  - CMQDXPA 535
  - CMQEPP 536
  - CMQGMOA 535
  - CMQIIHA 535
  - CMQMDA 535
  - CMQODA 535
  - CMQP 536
  - CMQPMOA 535
  - CMQTMA 535
  - CMQTMCA 535
  - CMQXA 535
  - CMQXPA 535
  - CMQXQHA 535
  - compilers and assemblers supported 453
  - CSQBSTUB 276
  - CSQCSTUB 277
  - CSQQSTUB 278
  - key features 10
  - requesting no backout of MQGET 150
  - using signaling 147
- MQSeries for SINIX and DC/OSx
  - build TUXEDO server environment 383, 384
  - building your application 293
  - CICS support 295
  - compilers supported 453
  - flags when compiling 293
  - link libraries 296
  - sample programs 327
- MQSeries for Sun Solaris
  - build TUXEDO server environment 380, 384
  - building your application 297
  - C compiler 297
  - CICS support 299
  - compilers supported 453
  - link libraries 298
  - sample programs 327
- MQSeries for Tandem NonStop Kernel
  - compilers supported 453
- MQSeries for Tandem NSK
  - building your application 301
  - notification of message arrival 147
  - sample programs 327
  - syncpoint considerations 194
  - using signaling 147
- MQSeries for VSE/ESA
  - building your application 305
  - compilers supported 453
  - sample programs 327
- MQSeries for Windows
  - building your application 307
  - sample programs 327
  - using signaling 147
- MQSeries for Windows NT
  - build TUXEDO server environment 385
  - building your application 309
  - CICS support 310
  - compilers supported 453
  - key features 12
  - sample programs 327
  - scope of MQCONN 91
  - syncpoints 189
  - Transaction Server support 310
  - triggering using samples 361
  - TUXEDO sample makefile 387
  - TUXEDO samples 379
  - ubbstxcn.cfg example 386
- MQSeries for Windows V2.0
  - compilers supported 453
- MQSeries for Windows V2.1
  - compilers supported 453
- MQSeries object
  - closing 105
  - creating 14
  - introduction 14
  - namelist 48
  - naming 49
  - opening 97
  - process definition
    - attributes 49
    - create 202
  - queue 40
  - queue manager 39
  - rules for naming 49
  - storage class 49
  - what it is 39
- MQSeries on UNIX systems
  - key features 12
  - platforms included xvii
  - sample programs 327
  - syncpoints 189
  - triggering using samples 361
  - TUXEDO 379
  - ubbstxcx.cfg example 384

## Index

MQSeries publications xviii  
MQSeries Workflow 249  
MQSET  
    attribute list 182  
    call parameters 182  
    use of selectors 179  
MQTM 216  
MQTM (trigger message) 214  
MQTMC (trigger message, character) 214  
MQTMC2 (trigger message, character) 214  
MQXCNVC data-conversion call 68  
MQXQH 111  
MsgDeliverySequence attribute 35, 128  
Msgld field 137  
MsgToken field  
    MQGMO structure 127

## N

NAK, IMS bridge 241  
name resolution 50, 99  
namelist  
    attributes 48  
    opening 97  
    rules for naming 49  
    sample application 438  
naming of MQSeries objects 49  
negative action notification (NAN) report 26  
notification of message arrival 147

## O

object  
    closing 105  
    creating 14  
    descriptor 99  
    handle 74  
    introduction 14  
    namelist 48  
    naming 49  
    opening 97  
    process definition 202  
        attributes 49  
    queue 40  
    queue manager 39  
    rules for naming 49  
    storage class 49  
    using handle 97  
    what it is 39  
object types, platform comparison 560  
object-oriented programming (OOP) 251  
OOP (object-oriented programming) 251  
opening an MQSeries object 97  
opening distribution lists  
    identifying distribution lists 117  
    identifying Object Records 117

opening distribution lists (*continued*)  
    the MQOD structure 117  
    the MQOR structure 117  
Options field  
    MQGMO structure 125  
    MQPMO structure 109  
Options parameter (MQOPEN call) 101  
order of message retrieval 128  
origin context 38  
OS/390  
    batch restrictions 84  
    OpenEdition 224  
    support for 219  
    WLM (workload manager) 249  
    workload manager (WLM) 249  
OTMA sense codes 242

## P

parameters  
    Buffer 111  
    BufferLength 127  
    DataLength 127  
    Options 101  
PDF (Portable Document Format) xxiii  
performance  
    design hints and tips 18  
    MQGET and buffer size 128  
    MQGET for a particular message 139  
    MQPUT1 107  
    persistent messages 34  
permanent dynamic queue, properties 46  
Persistence field 34  
PL/I  
    CMQEPP 536  
    CMQP 536  
    compilers supported 453  
    examples  
        MQCLOSE 522  
        MQCONN 520  
        MQDISC 520  
        MQGET 524  
        MQGET with signaling 526  
        MQGET with wait option 525  
        MQINQ 527  
        MQOPEN for dynamic queue 521  
        MQOPEN for existing queue 521  
        MQPUT 522  
        MQPUT1 523  
        MQSET 528  
    include files 536  
    on AIX 261  
    on OS/2 292  
    on Windows NT 313  
    support for 83

- planning an MQSeries application 13
  - platform support
    - functional comparison 539
    - list of 19
  - platforms, comparisons
    - administration 562
    - connection 566
    - data conversion 550
    - input 547
    - message properties 551
    - object types 560
    - programming languages 564
    - prptocols 551
    - security 556
    - syncpoint 540
    - threading 555
    - triggering 544
  - Portable Document Format (PDF) xxiii
  - positive action notification (PAN) report 26
  - PostScript format xxiii
  - print message (sample for MQSeries for OS/390) 416
  - Priority field 32
  - priority in messages 32
  - problem delivering a message, overview 35
  - problem determination
    - abend codes issued by the CICS adapter 223
    - trace points in CICS adapter 222
    - using CEDF with the CICS adapter 223
  - problem determination, use of report message 55
  - process definition object
    - attributes 49
    - example to create one 202
    - opening 97
    - rules for naming 49
    - triggering prerequisite 202
    - what it is 198
  - ProcessName 203, 214
  - product names
    - new, new and old 537
  - programming languages 75, 564
  - protocols, platform comparison 551
  - publications
    - MQSeries xviii
    - related xxiv
  - put (sample for MQSeries for OS/390) 408
  - put-message options 108
  - PutAppName field 38
  - PutApplType field 38
  - PutDate field 38
  - PutMsgRecFields field 110
  - PutMsgRecOffset field 110
  - PutMsgRecPtr field 110
  - PutTime field 38
  - putting
    - messages 107
    - one message 114
  - putting messages to a distribution list
    - the MQPMR structure 120
- ## Q
- QLOP abend on MQSeries for OS/390 404
  - QLOP abend, CICS adapter 223
  - QMQM library 530
  - queue
    - alias 41, 44
    - application 198
    - attributes 43
    - authority check on MQOPEN 97
    - base 44
    - channel 42
    - closing 97, 105
    - cluster 42
    - creating 41
    - dead-letter 48, 57
    - dead-letter on MQSeries for OS/390 440
    - definition 4
    - dynamic
      - permanent 46
      - temporary 45
    - dynamic, creation of 104
    - event 42
    - exclusive access 102
    - handle 97
    - initiation 47, 199
    - introduction to 40
    - local definition 41
    - model 45, 104
    - name resolution 50
    - name resolution when remote 105
    - object handle 97
    - opening 97
    - order of messages 35
    - remote
      - definition 41
      - putting messages 112
      - using 43
      - using local definition 99
      - using MQOPEN 105
    - reply-to 36
    - resolving name 99
    - rules for naming 49
    - selecting messages 35
    - shared access 102
    - system admin command 48
    - system command 42
    - system command input 48
    - system default 42, 48
    - transmission 42, 47
    - triggered 210
    - undelivered message 57
    - undelivered-message 48

## Index

- queue attributes for MQSeries for OS/390
  - sample application 420
- queue manager
  - alias definition 99
  - attributes 39
  - authority checking 95
  - connecting using MQCONN 90
  - connecting using MQCONNX 92
  - definition 5
  - disconnecting 94
  - location of default 90
  - number per system 5
  - reply-to 36
  - restart and trigger messages 215
  - scope of MQCONN 91
  - workload management 40
- queuing
  - definition 3
  - features 7
- quiescing connection
  - MQGET 125
- quiescing queue manager
  - how applications should react 54
  - MQCONN 91
  - MQOPEN 104
  - MQPUT 109
- R**
- reason codes 74
- recoverable resource manager services (RRS)
  - batch adapter 221
  - what it is 187
- recovery 9, 220
- RecsPresent field 110
- reenterable assembler-language programs 81
- reference messages 144
- related publications xxiv
- remote queue
  - definition 41
  - using 43
  - using local definition of 99
  - using MQOPEN 105
- reply message 25
- reply messages, IMS bridge 242
- reply-to queue 36
- reply-to queue manager 36
- ReplyToQ field 36
- ReplyToQMgr field 36
- report
  - confirmation of arrival (COA) 25
  - confirmation of delivery (COD) 25
  - exception 25
  - expiry 25
  - negative action notification (NAN) 26
  - positive action notification (PAN) 26
- Report field 25
- report message
  - creating 56
  - options 26
  - type of 25
- reports
  - application-generated 28
  - MQSeries-generated 27
  - retrieval of 28
  - segmented messages 27
- request message 24
- resolution of queue names 50, 99
- ResolvedQMgrName field 109
- ResolvedQName field
  - MQGMO structure 127
  - MQPMO structure 109
- resource manager, XA compliant
  - name 192
- ResponseRecOffset field 111
- ResponseRecPtr field 111
- restrictions in OS/390 batch 84
- retry sending message 57
- return codes 74
- ReturnedLength field
  - MQGMO structure 127
- RPG language
  - compilers supported 453
  - on AS/400 266
  - support for 82
- RPG sample programs 327
- RRS (recoverable resource manager services)
  - batch adapter 221
  - what it is 187
- runmqmtrmc** trigger monitor 214
- runmqmtrm** trigger monitor
  - error detection 218
  - how to run 213
- running a program automatically
  - an example 361
  - how triggering works 197
- S**
- sample applications
  - API-crossing exit for OS/390 225
- sample applications for MQSeries for OS/390
  - browse 414
  - credit check 430
  - features of MQI demonstrated 395
  - get 411
  - logging on to CICS 403
  - mail manager 421
  - message handler 443
  - preparing in batch 399
  - preparing in CICS Transaction Server for OS/390 403

## sample applications for MQSeries for OS/390

*(continued)*

- preparing in IMS 407
- preparing in TSO 401
- print message 416
- put 408
- queue attributes 420

## sample programs

- building C versions 339
- building COBOL versions 339
- building TAL versions 340
- C++ 327
- DCE exits 327
- preparing and running
  - AS/400 336
  - Digital OpenVMS systems 337
  - OS/2 and Windows NT 338
  - Tandem NSK 338
  - UNIX systems 336
  - Windows 340
- RPG 327

## sample programs for MQSeries for AS/400

- AMQ0ECHA 369
- AMQ0GET4 349
- AMQ0REQ4 359
- AMQ0SETA 367
- AMQSECHA 369
- AMQSERV4 371, 372
- AMQSGBR4 346
- AMQSGET4 349
- AMQSPUT4 342
- AMQSREQ4 359
- AMQSSETA 367
- AMQSTRG4 371
- AMQSVFC4 370
- put 342
- trigger monitor 371
- trigger server 372
- using remote queues 373
- using triggering 363

## sample programs for MQSeries for OS/2 Warp,

Windows NT, and UNIX systems

- amq0gbr0 346
- amq0get0 349
- amq0put0 342
- amq0req0 359
- amqiech2 369
- amqiechx 369
- amqiinq2 366
- amqiinqx 366
- amqiset2 367
- amqisetx 367
- amqmech2 369
- amqmechx 369
- amqminq2 366
- amqminqx 366

## sample programs for MQSeries for OS/2 Warp,

Windows NT, and UNIX systems *(continued)*

- amqmset2 367
- amqmsetx 367
- amqrgrm 351
- amqrgrma 351
- amqsbcg 347
- amqsbcg0 347
- amqsbcgc 347
- amqscic0 379
- amqsdliq 391
- amqsech 369
- amqsecha 369
- amqsechc 369
- amqsgbr 346
- amqsgbr0 346
- amqsgbrc 346
- amqsget0 349
- amqsgetc 349
- amqsgetw 349
- amqsinq 366
- amqsinqa 366
- amqsinqc 366
- amqsprm 351
- amqsprma 351
- amqsptl0 345
- amqsput0 342
- amqsputc 342
- amqsputw 342
- amqsreq 359
- amqsreq0 359
- amqsreqc 359
- amqsset 367
- amqsseta 367
- amqssetc 367
- amqstrg 371
- amqstrg0 371
- amqstrgc 371
- amqstxgx 390
- amqstxpx 389
- amqstxsx.c 379
- amqsvfc0 370
- amqsvfcx 370
- amqsxab0.sqb 373
- amqsxab0.sqc 373
- amqsxaf0.sqb 373
- amqsxaf0.sqc 373
- amqsxag0.c 373
- amqsxag0.cbl 373
- amqsxas0.sqb 373
- amqsxas0.sqc 373
- amqsxrm 351
- amqsxrma 351
- browse 346
- browser 347
- CICS transaction 379

## Index

- sample programs for MQSeries for OS/2 Warp, Windows NT, and UNIX systems (*continued*)
    - data conversion 370
    - dead-letter queue handler 391
    - distribution list 345
    - echo 369
    - get 349
    - inquire 366
    - put 342
    - reference messages 351
    - request 359
    - set sample 367
    - trigger monitor 371
    - TUXEDO 379
    - TUXEDO get 390
    - TUXEDO put 389
    - using remote queues 373
    - using triggering 361
    - XA transaction manager 373
  - scope, handles 91, 98
  - security 9, 556
  - Segmentation field
    - MQGMO structure 127
  - segmented messages 33
    - reports 27
  - segmented messages, IMS bridge 242
  - SegmentStatus field
    - MQGMO structure 127
  - selection of messages from queues 35
  - selector for attributes 179
  - send message, retry on failure 57
  - sense codes, IMS 242
  - server application (IMS) 246
  - server environment
    - TUXEDO 379
  - setting attributes 179
  - setting attributes on MQSeries for OS/390 420
  - Shareability attribute 102
  - shared access to a queue 102
  - Signal handling on UNIX 85
  - Signal1 field 126, 148
  - Signal2 field
    - MQGMO structure 127
  - signaling 16, 147
  - single-phase commit 183
  - size of messages 111
  - skeleton data-conversion exit 164
  - skipping backout 150
  - softcopy books xxii
  - stack size
    - for OS/2 MQI client 290
    - MQSeries for Windows NT 310
  - starting applications automatically
    - an example 361
    - how triggering works 197
    - introduction 17
  - static XA resource management structure 192
  - store-and-forward 8
  - Strucld field
    - MQGMO structure 125
    - MQPMO structure 109
  - structures 68
    - in COBOL copy files 532
  - stub program for MQSeries for OS/390
    - batch 276
    - CICS 277
    - CSQBSTUB 276
      - calling dynamically 279
    - CSQCSTUB 277
      - calling dynamically 279
    - CSQQSTUB 278
    - IMS 278
  - stub programs 69
  - syncpoint
    - calls by platform 67
    - considerations 184
    - external coordination 191
    - external manager interfaces 192
    - IMS applications 245
    - in CICS for AS/400 applications 189
    - in Tandem NSK applications 194
    - in the Credit Check sample application 440
    - internal coordination 190
    - MQBACK 187
    - MQCMIT 186
    - overview 9
    - single-phase commit 183
    - support comparison by platform 540
    - two-phase commit 184
    - with MQSeries for AIX 189
    - with MQSeries for AS/400 188
    - with MQSeries for HP-UX 189
    - with MQSeries for OS/2 Warp 189
    - with MQSeries for OS/390 220
    - with MQSeries for Windows NT 189
    - with MQSeries on UNIX systems 189
    - X/Open XA interface 192
  - system command queue 42
  - system command queues 48
  - system default queue 42, 48
  - system interruptions 54
- ## T
- TAL
    - compilers supported 453
    - support for 84
  - techniques with MQSeries 16
  - temporary dynamic queue
    - closing 105
    - properties 45

- terminology used in this book xvii, 573
- testing MQSeries applications 21
- threading 555
- threads, maximum no. 91
- time-independent communication 8
- TMI (trigger monitor interface) 214
- trace entries for CICS adapter 284
- trace points in CICS adapter 222
- Transaction Server
  - with MQSeries for OS/2 Warp 290, 292
  - with MQSeries for Windows NT 310
- translation of data 153
- transmission queue 42, 47
- trigger
  - event 198
    - conditions for 204
    - controlling 208
  - feedback code 217
  - following queue manager restart 215
  - message
    - definition 198
    - MQTM format 216
    - object attribute changes 216
    - persistence and priority 215
    - properties 215
    - without application messages 205
  - monitor
    - what it is 199
    - writing your own 214
  - monitor, provided
    - amqltmc0 212
    - AMQSERV4 212
    - AMQSTRG0 212
    - AMQSTRG4 212
    - AMQSTRG4 sample program 371
    - CKTI 212
    - CSQQTRMN 212
    - runmqtmc 212
    - runmqtrm 212
  - process definition 198
  - server
    - AMQSERV4 sample program 372
  - type of 209
- trigger monitor
  - provided, by platform 212
  - what it is 199
- trigger monitor interface (TMI) 214
- TriggerControl attribute 208
- TriggerDepth attribute 209
- triggered applications 301
- triggering
  - application design 210
  - application queue 197
  - comparison by platform 544
  - example of type DEPTH 209
  - example of type EVERY 209
- triggering (*continued*)
  - example of type FIRST 209, 210
  - getting messages 211
  - how it works 200
  - how it works with the samples 361
  - IMS bridge 245
  - introduction 17, 197
  - no DOS support 197
  - points to note 200
  - prerequisites 202
  - process definition attributes 49
  - sample program
    - for MQSeries for AS/400 363
  - sample trigger monitor for MQSeries for OS/2 Warp 371
  - sample trigger monitor for MQSeries for Windows NT 371
  - sample trigger monitor for MQSeries on UNIX systems 371
  - sequence of events 200
  - setting conditions 208
  - what it is 197
  - when it does not work 217
  - with the request sample on MQSeries for OS/2 Warp 361
  - with the request sample on MQSeries for Windows NT 361
  - with the request sample on MQSeries on UNIX systems 361
  - with units of work 210
  - without application messages 205
- triggering for MQSeries for OS/390
  - sample application 434
- TriggerInterval attribute 210
- TriggerMsgPriority attribute 208
- TriggerType attribute 208
- trusted applications 92
- TUXEDO sample makefile for MQSeries for Windows NT 387
- TUXEDO sample programs
  - amqstxgx 379
  - amqstxpx 379
  - amqstxsx 379
  - building server environment 379
- TUXEDO ubbstxcn.cfg example for MQSeries for Windows NT 386
- TUXEDO ubbstxcx.cfg example for MQSeries on UNIX systems 384
- two-phase commit 184
- type styles in this book xvii
- TZ environment variable
  - MQSeries for OS/2 Warp only 38

## Index

### U

- ubbstxcn.cfg example for MQSeries for Windows NT 386
- ubbstxcx.cfg example for MQSeries on UNIX systems 384
- undelivered messages, IMS bridge 241
- undelivered-message queue, using 57
- unit of work
  - message persistence 34
  - syncpoint 183
  - triggering 210
- UNIX signal handling 85
- UNIX-based platforms 537
- use of message types 24
- user exits 225
- user-defined formats 31
- UserIdentifier field 37

### V

- valid syntax
  - creating conversion-exit code 166
  - input data set 166
- Version field 110
  - MQGMO structure 125
  - MQPMO structure 109
- Visual Basic
  - on Windows 307
  - on Windows NT 313
- Visual Basic language
  - module files 531
- Visual Basic module files
  - CMQB.BAS 531
  - CMQB3.BAS 531
  - CMQB4.BAS 531
  - CMQBB.BAS 531
  - CMQCFB.BAS 531
  - CMQXB.BAS 531
  - module files 531

### W

- waiting for messages 16, 146
- WaitInterval field 126, 146
- Windows 3.1 clients
  - compilers supported 453
- Windows 95 and Windows 98 clients
  - compilers supported 453
- Windows Help xxiii
- WLM (workload manager) 249
- Workflow 249
- workload management
  - queue manager 40
- workload manager (WLM) 249

- writing applications 243
- writing exit programs
  - data conversion
    - Digital OpenVMS 172
    - MQSeries for AS/400 167
    - MQSeries for OS/2 Warp 168
    - MQSeries for OS/390 170
    - Tandem NSK systems 171
    - UNIX systems 172
    - Windows NT 177

### X

- X/Open XA interface support 192
- XA resource manager
  - name 192
  - structure 192
  - XA switch location 192
- XA transaction manager samples 373

---

## **Sending your comments to IBM**

**MQSeries®**

### **Application Programming Guide**

**SC33-0807-09**

If you especially like or dislike anything about this book, please use one of the methods listed below to send your comments to IBM.

Feel free to comment on what you regard as specific errors or omissions, and on the accuracy, organization, subject matter, or completeness of this book. Please limit your comments to the information in this book and the way in which the information is presented.

To request additional publications, or to ask questions or make comments about the functions of IBM products or systems, you should talk to your IBM representative or to your IBM authorized remarketer.

When you send comments to IBM, you grant IBM a nonexclusive right to use or distribute your comments in any way it believes appropriate, without incurring any obligation to you.

You can send your comments to IBM in any of the following ways:

- By mail, use the Readers' Comment Form
- By fax:
  - From outside the U.K., after your international access code use 44 1962 870229
  - From within the U.K., use 01962 870229
- Electronically, use the appropriate network ID:
  - IBM Mail Exchange: GBIBM2Q9 at IBMMAIL
  - IBMLink: HURSLEY(IDRCF)
  - Internet: idrcf@hursley.ibm.com

Whichever you use, ensure that you include:

- The publication number and title
- The page number or topic to which your comment applies
- Your name and address/telephone number/fax number/network ID.



# Readers' Comments

MQSeries®

## Application Programming Guide

### SC33-0807-09

Use this form to tell us what you think about this manual. If you have found errors in it, or if you want to express your opinion about it (such as organization, subject matter, appearance) or make suggestions for improvement, this is the form to use.

To request additional publications, or to ask questions or make comments about the functions of IBM products or systems, you should talk to your IBM representative or to your IBM authorized remarketer. This form is provided for comments about the information in this manual and the way it is presented.

When you send comments to IBM, you grant IBM a nonexclusive right to use or distribute your comments in any way it believes appropriate without incurring any obligation to you.

Be sure to print your name and address below if you would like a reply.

---

Name

---

Address

---

Company or Organization

---

Telephone

---

Email

**You can send your comments POST FREE on this form from any one of these countries:**

Australia	Finland	Iceland	Netherlands	Singapore	United States
Belgium	France	Israel	New Zealand	Spain	of America
Bermuda	Germany	Italy	Norway	Sweden	
Cyprus	Greece	Luxembourg	Portugal	Switzerland	
Denmark	Hong Kong	Monaco	Republic of Ireland	United Arab Emirates	


If your country is not listed here, your local IBM representative will be pleased to forward your comments to us. Or you can pay the postage and send the form direct to IBM (this includes mailing in the U.K.).

1 Cut along this line

2 Fold along this line

**By air mail**  
*Par avion*

IBRS/CCR NUMBER: PHQ - D/1348/SO



**REPONSE PAYEE  
GRANDE-BRETAGNE**

IBM United Kingdom Laboratories  
Information Development Department (MP095)  
Hursley Park,  
WINCHESTER, Hants  
SO21 2ZZ United Kingdom

3 Fold along this line

*From:* Name \_\_\_\_\_  
 Company or Organization \_\_\_\_\_  
 Address \_\_\_\_\_  
 \_\_\_\_\_  
 EMAIL \_\_\_\_\_  
 Telephone \_\_\_\_\_

1 Cut along this line

4 Fasten here with adhesive tape



Printed in the United States of America  
on recycled paper containing 10%  
recovered post-consumer fiber.

SC33-0807-09

