VisualAge Generator EGL Plug-in for VSE



# **Reference Manual**

Version 1.0

VisualAge Generator EGL Plug-in for VSE



# **Reference Manual**

Version 1.0

#### - Note!

Before using this information and the product it supports, be sure to read the general information under "Notices" on page 41.

#### Second Edition (December 2006)

This edition applies to IBM VisualAge Generator EGL Plug-in for VSE Version 1, Release 0, Program Number 5724-L93 and to any subsequent releases until otherwise indicated in new editions. Make sure you are using the correct edition for the level of the product.

Order publications through your IBM representative or the IBM branch office serving your locality. Publications are not stocked at the address below.

A form for reader's comments is provided at the back of this publication. If the form has been removed, address your comments to:

IBM Corporation Readers Comments DTX/E269 555 Bailey Avenue San Jose, CA 95141-1003 U.S.A.

When you send information to IBM, you grant IBM a nonexclusive right to use or distribute the information in any way it believes appropriate without incurring any obligation to you.

© Copyright International Business Machines Corporation 2005, 2006. All rights reserved. US Government Users Restricted Rights – Use, duplication or disclosure restricted by GSA ADP Schedule Contract with IBM Corp.

## Contents

	Figures	. v
	Tables	vii
	<b>Chapter 1. Overview</b> Supported and unsupported functions within EGL New functionality delivered with EGL/VSE 1.0 Fix Pack 1	
I	Chapter 2. Prerequisites and installation         Prerequisites         Plug-in prerequisites.         Server prerequisites         Installation         Installation of RAD or RWD and the plug-in on the developer platform         Installation of the Server and associated PTFs         Installation of the migration function for         VisualAge Generator Developer         Installation of Fix Pack 1	. 3 . 3 . 4 . 4 . 5 . 6
	<b>Chapter 3. Migration to EGL</b> Generation options and symbolic parameters	
	Dynamic arrays	19 19 19 19 20 20 20 20 20

VisualAge	G	ene	rat	or	fea	tur	es	that	ar	e r	not	sup	эрс	orte	d	
by EGL.												•	•			21

Chapter 5. Generation of	of a	ap	pli	ca	tio	ns	5	23
Build descriptor options								. 23
Resource Association options								
Outputs from generation								. 25

## Chapter 6. Preparation of generated

parts			27
Transferring parts to the VSE host system .			. 27
File transfer options			. 27
Outputs of the file transfer			. 28
Character code conversion			. 28
FTP commands issued during preparation			. 29
Running precompilers, compilers and linkers			. 29
Changes to the templates			. 29
Outputs from the execution of the preparat	ior	ı	
JCL			. 30

## Chapter 7. Execution of generated

applications	•	•		•	•	•	•	•	•	•	ı	•	31
Additional runtim	ne	mes	ssag	ges									. 31

Chapter 8. Recommend	lati	ior	ıs			33
Connections to DB2 on VSE .						. 33
Allocating Printer Files						. 33

Appendix. Samples 3	5
Sample 1: Basic build descriptor options	35
Sample 2: The associated Resource Association File	35
Sample 3: The resultant XML file	36
Sample 4: An FTP trace	37
Sample 5: SQL database connections	39
Notices 4	1
Trademarks	
Bibliography 4	3
Index	5

## Figures

1.	The basic build descriptor options			. 35
2.	The Resource Association File .			. 36

4.	Sample FTP trace										38
5.	Parameters used to	co	nne	ct t	0 8	D	B2	dat	ab	ase	
	on a VSE host										39

## Tables

## **Chapter 1. Overview**

The Rational<sup>®</sup> Development Products with the Enterprise Generation Language (EGL) component are the successor products for VisualAge<sup>®</sup> Generator. For the VSE platform, the VisualAge Generator EGL plug-in for VSE (which from now on will be called the "plug-in") is the successor product for VisualAge Generator.

The purpose of the plug-in is to generate COBOL applications that can be executed with VisualAge Generator Server for VSE (the "Server"). Currently the plug-in executes with Rational Application Developer (RAD) and Rational Web Developer (RWD). At a later stage, the plug-in may be shipped as a feature of other Rational or WebSphere<sup>®</sup> products.

Because the plug-in is based on the z/OS<sup>®</sup> EGL COBOL Generator, the two products share many similarities, and references to z/OS in EGL manuals will often apply for the VSE platform. This Reference Manual provides VSE-specific information to supplement or replace the information provided about z/OS in EGL manuals. More information is available from:

- The Rational Developer products online help system
- The EGL Reference Guide SC31-6837
- The VisualAge Generator to EGL Migration Guide SH23-0263
- The VisualAge Generator Generation Guide SH23-0263
- The VisualAge Generator Server Guide for MVS, VSE and VM SH23-0256
- The TCPIP for VSE Installation Guide from Connectivity Systems
- The web site and news group for VisualAge Generator. The web site is at http://www.ibm.com/software/awdtools/visgen/
- The web site for the VisualAge Generator Plug-in for VSE. The web site is at http://www.ibm.com/software/awdtools/visgen/vse/
- The web site and news group for the Rational Developer product that you are using.
- The web site and news group for Enterprise Generation Languages. The web site is at http://www.ibm.com/developerworks/rational/products/egl/

### Supported and unsupported functions within EGL

EGL represents a major change and enhancement from the VisualAge Generator generation language. Due to restrictions on the VSE platform, or restrictions within the Server, not all of the functionality within EGL is currently supported by the plug-in.

The new EGL functions that are not supported by the plug-in are:

- Library functions
- Enhanced date and time functionality (VisualAge Generator date and time functions such as EZEDTE and EZETIM are still supported.)
- · Formatting of numbers provided by the strLib.formatNumber EGL function
- Numeric items greater than 18 digits or numeric items with decimal places greater than 18 digits. In Fix Pack 1, the VSE-specific symbolic parameter COBOLV2 is included, and is set to YES. This restricts numerical items to a maximum of 18 digits.

1

Т

T

• DLI/VSE support

data items.

I

|

I	Primitive 'character-type' UNICODE
	The new EGL functions that are supported by the plug-in are: • Dynamic arrays
	• Comparisons using the EGL like and matches statements
	Some VisualAge Generator functionality is not currently supported by EGL-generated COBOL, although there are plans to provide support in later versions of EGL:
	Web transactions
	DL/I support
I	Support for this functionality is now provided in Fix Pack 1.
	For more information about supported and unsupported functions, refer to Chapter 4, "Enhancements to the VSE Server Runtime to support EGL," on page 19.
New function	nality delivered with EGL/VSE 1.0 Fix Pack 1
I	The following functionality has been added:
I	Web transactions

• The new symbolic parameter COBOLV2. This controls the generation of numeric

2 VisualAge Generator EGL Plug-in for VSE V1R0: Reference Manual

## **Chapter 2. Prerequisites and installation**

## **Prerequisites**

1

## **Plug-in prerequisites**

Here are the minimum software requirements for the plug-in:

• RAD v 6.0.0.1 with iFix001, iFix002, and iFix003

or

• RWD v 6.0.0.1 with iFix001, iFix002, and iFix003

The following restrictions and recommendations apply:

- Both RAD and RWD have hardware and software prerequisites. Refer to the web sites for more information.
  - RAD: http://www.ibm.com/software/awdtools/developer/application/ index.html
  - RWD: http://www.ibm.com/software/awdtools/developer/web/index.html
- The VSE plug-in replaces an existing EGL COBOL generator plug-in if one has been installed.
- The VSE plug-in is not supported when installed with any other EGL COBOL generator plug-in.
- If you need to run both the VSE plug-in and another EGL COBOL generator plug-in (such as the z/OS COBOL generator), then set up two separate development environments running on separate hardware, one for VSE the other for the other platform.

#### Fix Pack 1 pre-requisites

One of the following:

- RAD v 6.0.1.1 with iFix003 or iFix003a (plus base framework temporary plugin src.jar)
- RAD v 6.0.1.1 with iFix004
- RWD v 6.0.1.1 with iFix003 or iFix003a (plus base framework temporary plugin src.jar)
- RWD v 6.0.1.1 with iFix004

## Server prerequisites

To execute programs generated from EGL, a version of the Server software must be installed on the VSE host platform. The following version of the Server software is supported:

• VisualAge Generator Server for VSE Version 1.2 (Program Number 5648-B02)

The Server software is dependent on other software products that are installed on the VSE host system. All of these products should be at a currently supported level.

The products that are mandatory are:

**VSE System** 

## including z/VSE Version 3.1. A currently supported version of CICS<sup>®</sup> up to and including CICS CICS Transaction Server 1.1.1 (Program Number 5648-054). TCP/IP A currently supported version of Connectivity Systems TCP/IP for VSE up to and including TCP/IP for VSE 1.5 (Program Number 5686-A04). **COBOL** compiler A currently supported version of COBOL for VSE/ESA<sup>™</sup> up to and including COBOL for VSE/ESA Version 1.1 (Program Number 5686-068). LE A currently supported version of Language Environment<sup>®</sup> up to and including LE/VSE Version 144 (Program Number 5686-CF7-32). If LE/VSE version 144 is used, then apply PTF UK02403. Optional products are: **MOSeries** A currently supported version of MQSeries<sup>®</sup> for VSE up to and including MQSeries for VSE Version 2.1.2 (Program Number 5686-A06). A currently supported version of DB2<sup>®</sup> Server for VSE and VM up to and DB2 including DB2 Server for VSE and VM Version 7.4 (Program Number 5697-F42). To find out if your version is currently supported, check the relevant web site, or contact IBM support. **Optional products for Fix Pack 1 Server prerequisites CICS** Transaction Gateway Minimum version 5.1 required to support Web Transactions. Websphere Application Server Required to support Web Transactions. DL/1 for VSE 1.1\* with PTFs UK14921 or UK14924 installed. DL/1

## Installation

T

T

I

Before you can generate and execute applications for VSE from EGL, there are four distinct installations:

A currently supported version of the VSE operating system up to and

- Installation of RAD or RWD and the plug-in on the developer platform.
- Installation of PTFs for the Server on the VSE host platform.
- Installation of the migration function for VisualAge Generator Developer (if you will be migrating VisualAge Generator applications to EGL).
- Installation of Fix Pack 1

# Installation of RAD or RWD and the plug-in on the developer platform

For information about installing RAD or RWD please refer to the documentation for these products.

Before you install the VisualAge Generator EGL Plug-in for VSE, make sure that your machine has one of these products currently installed:

Either

IBM Rational Application Developer 6.0.0.1 with iFix001, iFix002, and iFix003 or

IBM Rational Web Developer 6.0.0.1 with iFix001, iFix002, and iFix003

The Enterprise Generation Language (EGL) feature should be installed on RAD or RWD. This feature is offered during the install of RAD or RWD under the **Additional Features** list. If you do not install the EGL feature, you will not be able to use the plug-in. If EGL is not installed, you should be able to execute the RAD/RWD installation procedure again to install it. Only select the installation of the EGL feature.

If RAD or RWD is installed at the v6.0 level, please use the Rational Product Updater to bring the product up to the 6.0.0.1 iFix003 level before you start to install VisualAge Generator EGL Plug-in for VSE. As iFixes are not necessarily cummulative, you should also install iFix001 and iFix002. See the appropriate RAD or RWD documentation for information on using the Rational Product Updater.

Once RAD or RWD is at the required level, here is the installation process:

- Ensure that RAD or RWD is closed down.
- Ensure there is enough disk space. For a successful installation, there must be at least 100 MB of disk space available on the installation disk drive.
- Review the readme file on the CD.
- Run the setup.exe file that is in the root directory of the CD that contains the VisualAge Generator EGL Plug-in for VSE. This initiates the installation of the plug-in.
- Follow the prompts to perform the install. No user input is required since the VisualAge Generator EGL Plug-in for VSE installs into the same location as either RAD or RWD. Note that the installation of the plug-in can take up to twenty minutes, depending on the workstation configuration.

To uninstall the plug-in, go to Add/Remove Programs in the Windows Control Panel. Select IBM VisualAge Generator EGL Plug-in for VSE V1.0 and then click on the Change/Remove button. Follow the prompts in the Uninstaller to complete the removal of the plug-in from your system.

#### Installation of the Server and associated PTFs

To execute EGL-generated applications, you must install the Server on the VSE host platform, and then customize to site-specific requirements. In addition, there are updates to the Server product to support applications generated using the plug-in. These updates are delivered as PTFs. Install them using normal VSE maintenance procedures.

If you are performing a new installation of the Server, review the *Program Directory for VisualAge Generator Server for VSE* and the *VisualAge Generator Server Guide for MVS, VSE and VM* carefully before you install.

The following PTFs should be installed:

- UQ28232
- UQ36262
- UQ36930
- UQ37330
- UQ37988

I

T

1

1

I

- UQ40396
- UQ40851
- UQ40861
- UQ41992
- UQ52350
- UQ58427
- UQ61004
- UQ67369
- UQ76719
- UQ84692
- UQ85016
- UQ85060
- UK04007

The plug-in website (http://www.ibm.com/software/awdtools/visgen/) contains information about the latest PTFs that are available for VisualAge Generator Server for VSE. Check the web site regularly to ensure that you are aware of recent changes or new information about the product.

If your site has already installed the latest version of the Server, it should be sufficient to install all PTFs required by Server.

## Installation of the migration function for VisualAge Generator Developer

If your site is migrating from VisualAge Generator Developer, refer to the *VisualAge Generator to EGL Migration Guide* to determine what additional software you need for migration purposes. The *VisualAge Generator to EGL Migration Guide* contains instructions about the installation of the Stage 1 tool that runs on VisualAge Generator Developer.

## **Installation of Fix Pack 1**

#### RAD or RWD

Before installing this fix pack ensure that your machine has one of these products currently installed:

- IBM Rational Application Developer v 6.0.1.1 with iFix003 or iFix003a (plus base framework temporary plug-in src.jar)
- IBM Rational Application Developer v 6.0.1.1 with iFix004
- IBM Rational Web Developer v 6.0.1.1 with iFix003 or iFix003a (plus base framework temporary plug-in src.jar)
- IBM Rational Web Developer v 6.0.1.1 with iFix004

This fixpack includes JCL templates which can optionally be copied to the relevant installation folder (...VSEtemplates).

#### Server updates

The following PTFs should be installed:

• UK15199 (runtime APAR PK19349)

Ι	Install instruc	tions		
	1. Make sure	Ũ	tor for VSE complete the fo g on your computer. sk1.	ollowing steps:
I	🛱 disk1			
	File Edit View Favorites Too	ls Help		All I
	🕝 Back 🔹 🕥 – 🏂 🔎	Search 🕞 Folders	· []]-	
	Address 🛅 disk1			Go
	Folder Tasks (2) Extract all Mys Duration: 2 min. Last Response: 2 min	Name A Setup media.inf setup.exe	Type File Folder Setup Information Application JAR File	
	Other Places       Image: Constraint of the second se			
1	4 objects	<	m	• .:!

3. Run setup.exe and wait until the first installer wizard page appears.

I

I

I

|

	Welcome to the InstallShield Wizard for IBM VisualAge Generator EGL Plug-in for VSE V1.0
	The InstallShield Wizard will install IBM VisualAge Generator EGL Plug-in for VSE V1.0 on your computer.
	To continue, choose Next.
	IBM VisualAge Generator EGL Plug-in for VSE V1.0
IB)	

4. Click on Next and read the information.

Installer	
	Please read the information below. IBM VisualAge Generator EGL Plug-in for VSE V1.0 is a separately licensed product. Please ensure that a license has been purchased prior to installing this product. Click "Next" to continue or "Cancel" to quit.
InstallShield	Sack Next > Cancel

I

Ι

| | 5. If you would like to continue, click on Next.

I

| |

|

	Please read the following license agreement carefully.
	International Program License Agreement
	Part 1 - General Terms
	BY DOWNLOADING, INSTALLING, COPYING, ACCESSING, OR USING THE PROGRAM YOU AGREE TO THE TERMS OF THIS AGREEMENT. IF YOU ARE ACCEPTING THESE TERMS ON BEHALF OF ANOTHER PERSON OR A COMPANY OR OTHER LEGAL ENTITY, YOU REPRESENT AND WARRANT THAT YOU HAVE FULL AUTHORITY TO BIND THAT PERSON, COMPANY, OR LEGAL ENTITY TO THESE TERMS. IF YOU DO NOT AGREE TO THESE TERMS,
	- DO NOT DOWNLOAD, INSTALL, COPY, ACCESS, OR USE THE PROGRAM; AND
	O I accept the terms in the license agreement
IEI	I do not accept the terms in the license agreement

6. Choose the appropriate radio button.

● Installer	
MARKEN II	Software License Agreement
	Please read the following license agreement carefully.
	International Program License Agreement
	Part 1 - General Terms
	BY DOWNLOADING, INSTALLING, COPYING, ACCESSING, OR USING THE PROGRAM YOU AGREE TO THE TERMS OF THIS AGREEMENT. IF YOU ARE ACCEPTING THESE TERMS ON BEHALF OF ANOTHER PERSON OR A COMPANY OR OTHER LEGAL ENTITY, YOU REPRESENT AND WARRANT THAT YOU HAVE FULL AUTHORITY TO BIND THAT PERSON, COMPANY, OR LEGAL ENTITY TO THESE TERMS. IF YOU DO NOT AGREE TO THESE TERMS,
	- DO NOT DOWNLOAD, INSTALL, COPY, ACCESS, OR USE THE PROGRAM; AND
	O I accept the terms in the license agreement
	I do not accept the terms in the license agreement
la ata UCh la lui	
InstallShield	
	< Back Next > Cancel

I

Ι Ι

Ι

7. Assuming you have agreed with the license agreement, click on Next.

I

| |

Ι

P Installer	
MANNA H -	Please read the summary information below.
	IBM VisualAge Generator EGL Plug-in for VSE V1.0 will be installed in the following location:
	C:\Program Files\IBM\Rational\SDP\6.0
	with the following features:
	IBM VisualAge Generator EGL Plug-in for VSE V1.0
	for a total size:
	8.8 MB
P 00000	
24	
and the second se	
IBM	
InstallShield	
	< <u> </u>

8. Click on Next and wait until the copy process and activation finish.

Initializing Eclipse	
< Back	Next >

I

Ι

Ι

| | | **9**. Usually the activation process takes around 20 minutes. So be patient until the Rational logo page disappears and the following wizard page appears. Then click on Finish to close the installer wizard.

Installer	
TANK IN	Please read the summary information below.
	The InstallShield Wizard has successfully installed IBM VisualAge Generator EGL Plug-in for VSE V1.0. Choose Finish to exit the wizard.
IBM.	< <u>B</u> ack Next >

## Chapter 3. Migration to EGL

I

Migration from VisualAge Generator Developer to EGL is described fully in the *VisualAge Generator to EGL Migration Guide*. It is beyond the scope of this Reference Manual to deal with all issues concerning migration.

The information in this chapter highlights VSE-specific migration issues.

In general, migration for VSE is the same as that for z/OS migration. The main points of departure exist where there are VSE-specific functions that have no equivalent function or requirement in z/OS.

## Generation options and symbolic parameters

Table 1 on page 16 contains a list of VisualAge Generator parameters that are specific to VSE, and the equivalent parameter in EGL. The VisualAge Generator parameter is migrated to the EGL parameter during the migration process and stored in a build descriptor. For a description of the parameters and how they are used, refer to the *VisualAge Generator Generation Guide*.

Table 1. Parameter migration to EGL

VisualAge Generator generation option or		Minute Ltr. FOI	
symbolic parameter	Usage in VisualAge Generator	Migrated to EGL As	Usage in EGL
/BLKSIZE	Defined in the Resource Association File	blockSize	Defined in the Resource Association File
/LABEL /NOLABEL	Defined in the Resource Association file	standardLabel	Defined in the Resource Association file
/SYSNUM	Defined in the Resource Association File	systemNumber	Defined in the Resource Association File
/JOBCARD	Defined in the Generation Options	JOBCARD	Defined as a symbolic parameter in the generation option file
/JOBNAME	Defined in the Generation Options	JOBNAME	Defined as a symbolic parameter in the generation option file
/VSELIB	Defined in the Generation Options	vseLibrary	Defined in the build descriptor options file
PROCLIB	Defined as a symbolic parameter	PROCLIB	Defined as a symbolic parameter in the symbolic parameter file
PWRCLASS	Defined as a symbolic parameter	PWRCLASS	Defined as a symbolic parameter in the symbolic parameter file
SQLDBNAM	Defined as a symbolic parameter	SQLDBNAM	Defined as a symbolic parameter in the symbolic parameter file
SQLPKGNM	Defined as a symbolic parameter	SQLPKGNM	Defined as a symbolic parameter in the symbolic parameter file
SQLPROPT	Defined as a symbolic parameter	SQLPROPT	Defined as a symbolic parameter in the symbolic parameter file
SQLSTMDE	Defined as a symbolic parameter	SQLSTMDE	Defined as a symbolic parameter in the symbolic parameter file
SQLSTOPT	Defined as a symbolic parameter	SQLSTOPT	Defined as a symbolic parameter in the symbolic parameter file
SQLUSRPW	Defined as a symbolic parameter	SQLUSRPW	Defined as a symbolic parameter in the symbolic parameter file
VUSERLIB	Defined as a symbolic parameter	VUSERLIB	Defined as a symbolic parameter in the symbolic parameter file

Note that the /JOBCARD and /JOBNAME generation options have been converted to symbolic parameters in EGL. The JOBCARD and JOBNAME symbolic parameters are used as follows:

#### **JOBNAME**

Specifies the value used for the job name in the job statement built for the runtime JCL. This name must be a valid VSE job name. This job name is used to replace the EZEJOB parameter in the job template.

#### JOBCARD

Specifies the name of the file containing the job statement you want to use for generated preparation or runtime JCL. The value for the JOBCARD symbolic parameter should be the name of a file located in the directory specified by the templateDir build descriptor option, or in the default VSE Templates directory. The default filename is fda2vjob.tpl.

### Templates for preparation and execution of generated applications

Templates are used in the generation process as skeletons for JCL generation. The generated JCL is transferred to the host VSE system where it is used to prepare parts for run time, and to run the prepared parts.

The templates for EGL have been copied from the VisualAge Generator templates, and updates have been made. The updates keep the JCL in line with newer versions of the VSE operating system and COBOL compiler. Refer to Chapter 6, "Preparation of generated parts," on page 27 for details about these changes.

The templates are provided with the plug-in at installation. They are stored within the plug-in directory structure in a default directory called VSETemplates. It is possible to customize the templates in this default directory, however, our recommendation is to copy them to another directory structure and then customize them. Set the templateDir build descriptor option to point the generation process at the customized templates in the new directory. By customizing the templates in a new directory, any maintenance that is shipped will not overwrite your customized templates.

Table 2 lists the VisualAge Generator template and the EGL equivalent.

VisualAge Generator		
Template	EGL Template	Template Description and Use
efk2vcal.tpl	fda2vcal.tpl	Comment generation in the runtime JCL
efk2veba.tpl	fda2veba.tpl	Generation of DLBL statements in runtime JCL
efk2vebd.tpl	fda2vebd.tpl	Generation of runtime JCL with DB2 access
efk2vebe.tpl	fda2vebe.tpl	Generation of runtime JCL
efk2veza.tpl	fda2veza.tpl	Comment generation in the runtime JCL
efk2vezd.tpl	fda2vezd.tpl	Comment and DLBL generation
efk2vjob.tpl	fda2vjob.tpl	Generation of the job statement for the preparation JCL
efk2vlba.tpl	fda2vlba.tpl	Batch DB2 link edit template used for preparation
efk2vlbc.tpl	fda2vlbc.tpl	Batch link edit template used for preparation
efk2vlca.tpl	fda2vlca.tpl	CICS link edit template used for preparation
efk2vlcc.tpl	fda2vlcc.tpl	CICS and DB2 link edit template used for preparation
efk2vmfm.tpl	fda2vmfm.tpl	Mapgroup link edit template used for preparation

Table 2. VisualAge Generator template and EGL equivalent

#### **Migration to EGL**

VisualAge Generator		
Template	EGL Template	Template Description and Use
efk2vpba.tpl	fda2vpba.tpl	Batch preparation template
efk2vpbd.tpl	fda2vpbd.tpl	Batch preparation template including DB2 access
efk2vpca.tpl	fda2vpca.tpl	CICS preparation template
efk2vpcb.tpl	fda2vpcb.tpl	CICS preparation template including DB2 access
efk2vpej.tpl	fda2vpej.tpl	End of job template
efk2vsei.tpl	fda2vsei.tpl	Runtime sequential input file allocation template
efk2vseo.tpl	fda2vseo.tpl	Runtime sequential output file allocation template
efk2vtcl.tpl	fda2vtcl.tpl	Preparation template for print services programs
efk2vvsi.tpl	fda2vvsi.tpl	Runtime VSAM input file allocation template
efk2vvso.tpl	fda2vvso.tpl	Runtime VSAM output file allocation template

Table 2. VisualAge Generator template and EGL equivalent (continued)

There is more information about templates and how they are used at generation time in Chapter 11 of the *VisualAge Generator Generation Guide*.

# Chapter 4. Enhancements to the VSE Server Runtime to support EGL

The *VisualAge Generator to EGL Migration Guide* has a detailed description of the language functionality that has been migrated from VisualAge Generator to EGL. This functionality continues to be supported by the Server runtime. In addition, the Server runtime has been enhanced to support dynamic arrays, the like operator, and the matches operator which are new functions available with EGL. Any enhancements to the Server are delivered as PTFs, which you should install according to the standard installation procedures. Refer to Chapter 2, "Prerequisites and installation," on page 3 for more details about installation of PTFs.

## EGL features supported by the server

## **Dynamic arrays**

With EGL, an array of records or data items can be declared without specifying the number of elements. The number of elements in the array varies at runtime as elements are inserted or deleted from the array. This ability to use dynamic arrays is supported by the Server runtime code if the relevant PTFs are installed.

For more information on the use of dynamic arrays, refer to the *EGL Reference Guide* and the EGL on-line help.

### like and matches operators

With EGL, the like and matches operators can be used in logical expressions for comparison of strings. These operators are supported by the Server runtime code, providing that the relevant PTFs are installed.

For more information on the use of the like and matches operators, refer to the *EGL Reference Guide* and the EGL online help.

## EGL Features introduced by Fix Pack 1 and runtime APAR PK19349

I	DL/1 support
I	EGL allows you to develop programs which interface with VSE DL/1 databases.
	For more information on this topic refer to the EGL Reference Guide topics dealing with $DL/1$ and IMS runtime support.
I	VSE restrictions:
I	<ul> <li>Only supports the following record parts:</li> </ul>
I	DLISegment
I	PSBRecord
I	<ul> <li>Only supports the following predefined record part:</li> </ul>
I	DB_PCBRecord
I	• Before using DL/1 command codes check the appropriate DL/1 for VSE
I	documentation to make sure that the command codes are valid. For example,
	command code $'*C'$ (concatenated key) is not valid under VSE.

|

1

T

T

## Web transactions

EGL provides support for Web-based applications. For more information on this topic refer to the *EGL Reference Guide* topics dealing with Web support.

## EGL features that are not supported by the Server or Plug-in

Not all features that are available in EGL are supported by COBOL generation; for more information about these unsupported features, refer to the *EGL Reference Guide*. In addition to these unsupported features, the features described below are not supported by the Server or Plug-in. At some stage in the future, support for these features may be included.

## Date and time support

Enhanced date and time features that are available in EGL are not supported by the Server runtime. Date and time functions that have been migrated from VisualAge Generator to EGL will continue to be supported.

Table 3 shows the EZE words and the equivalent EGL statement that are supported by VisualAge Generator, and are supported in the new EGL form.

EZE word in VisualAge Generator 4.5	EGL definition
EZEDAY	VGVar.currentShortJulianDate
EZEDAYL	VGVar.currentJulianDate
EZEDAYLC	VGVar.currentFormattedJulianDate
EZEDTE	VGVar.currentShortGregorianDate
EZEDTEL	VGVar.currentGregorianDate
EZEDTELC	VGVar.currentFormattedGregorianDate
EZETIM	VGVar.currentFormattedTime

Table 3. EZE words and equivalent EGL statements

## Library functions

A library part contains a set of functions, variables and constants that can be used by programs or other libraries. Library functions are not supported by the Server runtime.

## Formatting of numbers

The strLib.formatNumber EGL statement is not supported by the Server runtime.

## Numeric items and numeric items with decimal places

EGL allows the definition of numeric items with more than 18 digits, or numeric items with decimal places of more than 18 digits. The COBOL compiler on VSE does not support this, therefore the 18-digit limit set by VisualAge Generator Developer applies to the plug-in. In Fix Pack 1, the VSE-specific symbolic parameter COBOLV2 is included, and is set to YES. This restricts numerical items to a maximum of 18 digits.

## VisualAge Generator features that are not supported by EGL

The following features of VisualAge Generator are not yet supported by EGL:

- Web transactions
- DL/I data access

I

|

They may be supported at some stage in the future.

These two features (web transactions and DL/1 data access) are now supported by extensions included with Fix Pack 1. For more information on the use of these features refer to the appropriate sections in the EGL Reference Guide.

## Chapter 5. Generation of applications

Various parameters and options govern the generation of COBOL applications and the generation of JCL for preparation and execution. These parameters are described in the *EGL Reference Guide* and the on-line help.

This chapter describes VSE-specific options as a supplement to other documentation.

The build descriptor options, symbolic parameters and other parameters are entered in a "dialog based" editor. The editor may retain white space characters such as spaces. At generation time, white space may be removed for certain parameters. It is recommended that white space characters be used only where they are appropriate.

## **Build descriptor options**

1

The **build descriptor options** that are VSE specific, or have special meaning for VSE are listed below. Refer to the *VisualAge Generator Generation Guide* for full descriptions of these parameters.

#### system

The two valid values for VSE generation are VSEBATCH and VSECICS.

#### vseLibrary

This is equivalent to the /VSELIB generation option in VisualAge Generator and is used to specify the library where objects are created during generation.

VSE-specific **symbolic parameters** that can be defined as part of the build descriptor are:

#### COBOLV2

Always set to YES. Restricts the size of COBOL numeric data items to 18 digits.

#### **JOBCARD**

The file that is to be used as a jobcard template. This file should exist in the template directory specified by the templateDir build parameter, or in the default VSETemplates directory

#### **JOBNAME**

The job name used for compiles and linkedits. The first seven characters of this symbolic parameter are used to generate the jobname of the preparation JCL.

#### PROCLIB

Used to change the VSE PROCLIB (16 bytes)

#### PWRCLASS

User-defined POWER class

#### **SQLDBNAM**

Used to change the default database name

#### **SQLPKGNM**

Used to change the default package name

#### SQLPROPT

Precompiler options part name

#### SQLSTMDE

DB2 startup mode

#### SQLSTOPT

Startup options file

#### SQLUSRPW

Userid and password for database connection

#### TRANSLATETABLE

Used to change the FTP Translate Table on the VSE host system. Refer to Chapter 6, "Preparation of generated parts," on page 27 for a detailed description.

#### **VUSERLIB**

Additional library used for link-editing

The JOBCARD and JOBNAME symbolic parameters were part of the generation options parameters in VisualAge Generator, and have been migrated to symbolic parameters in EGL. The other symbolic parameters, with the exception of TRANSLATETABLE, are available in both VisualAge Generator and EGL, and their usage is the same across both products. Refer to the *VisualAge Generator Generation Guide* for a full description of these symbolic parameters.

In the chapters that follow, the use of these symbolic parameters is described in more detail. Sample build descriptors are provided in "Samples," on page 35.

There are other build descriptor options that are common to z/OS and VSE. In particular, we recommend that you read about the CICS-related options in the *VisualAge Generator Generation Guide*.

#### **Resource Association options**

These parameters in the Resource Association Editor should be used for VSE generation:

#### system

The two valid values for VSE generation are VSEBATCH and VSECICS.

For VSE generation, three properties have been added to the Resource Association Editor:

#### blockSize

Equivalent to the /BLKSIZE property in VisualAge Generator.

#### standardLabel

Equivalent to the /LABEL property in VisualAge Generator; this only applies to VSEBATCH. If standardLabel=YES is set, then for PRINTER files, the generator generates a LABEL RECORDS ARE STANDARD clause. For serial files, a LABEL RECORDS statement is not generated. The default is standardLabel=Yes.

If standardLabel=NO is set, for PRINTER files, the generator will generate a LABEL RECORDS ARE OMITTED clause. For SERIAL files, LABEL RECORDS ARE OMITTED will also be generated.

Printer data is written to a logical file called PRINTER. The PRINTER file in EGL-generated programs is equivalent to the EZEPRINT file generated with the VisualAge Generator Developer. Refer to "Allocating Printer Files" on page 33 for further information.

#### systemNumber

Equivalent to the /SYSNUM property in VisualAge Generator.

Refer to the *VisualAge Generator Generation Guide* and APAR PQ25672 for more information about the use of these properties.

## **Outputs from generation**

For VSEBATCH, depending on the build descriptor options set, a successful generation may produce the following generated parts:

- COBOL programs with a suffix of .cbl
- Preparation JCL with a suffix of .jcp
- Execution JCL with a suffix of .jcx

For VSECICS, depending on the build descriptor options and the application, a successful generation may produce the following generated parts:

- COBOL programs with a suffix of .cbl
- Map format modules with a suffix of .fmt
- Preparation JCL with a suffix of .jcp
- Execution JCL with a suffix of .jcx
- CICS PCT entries with a suffix of .pct
- · CICS PPT entries with a suffix of .ppt

These generated parts are placed in the directory specified by the genDirectory build descriptor option.

## Chapter 6. Preparation of generated parts

The preparation process has two steps:

- 1. Transferring parts to the VSE host, including code conversion if needed.
- 2. Running precompilers, compilers, and linkers.

### Transferring parts to the VSE host system

If the prep option is not set, then no file transfer occurs.

If the prep option is set in the build descriptor file, the plug-in will transfer the generated files to a VSE host using the file transfer protocol (FTP). A prerequisite product, therefore, is TCPIP for VSE from Connectivity Systems. The FTP server available with this product should be configured and active on the host VSE system. The FTP server should be configured to allow:

- Submission of jobs to the internal reader.
- Write access to all libraries that are used for generation output.

Note that SNA file transfer that is supported in VisualAge Generator is not supported by the plug-in.

### File transfer options

These build descriptor options control the file transfer:

#### debugTrace

Controls the amount of tracing produced by the FTP process. For each element transferred to the host, a file is created with trace information, and placed in the directory specified by the genDirectory build descriptor option. The filename for the trace has this format:

element.suffix.FTPresults

For example, if a program is called PROG1, then the trace information is written to a file named PROG1.cbl.FTPResults.

If you experience problems with FTP during the preparation phase, then IBM Support may ask you to set the debugTrace option and provide a copy of the resultant trace file.

#### destHost

The TCP/IP host address or hostname of the VSE host server.

#### destPort

The port on which the FTP server is listening for FTP requests. The default is 21.

#### destPassword

The password associated with the destUserID used to connect to the FTP server.

#### destUserId

The userid that is used to connect to the FTP server.

#### serverCodeSet

Character code conversion control for maps. For more information, see "Character code conversion."

#### vseLibrary

The VSE library and sublibrary on the host server that is used to store the output of the FTP process and the preparation process.

In addition, the following symbolic parameter is used for character code conversion:

#### TRANSLATETABLE

Changes the FTP Translation Table on the VSE host system.

#### Outputs of the file transfer

For VSEBATCH, a successful FTP process transfers parts to the library and sublibrary specified in the vseLibrary option. These parts have a VSE "type" as listed:

- COBOL programs: type of "C"
- Preparation JCL: type of "Z"
- Execution JCL: type of "X"

For VSECICS, a successful FTP process transfers the following parts to the library and sublibrary specified in the vseLibrary option:

- COBOL programs: type of "C"
- Map format modules: type of "OBJ"
- Preparation JCL: type of "Z"
- Execution JCL: type of "X"
- CICS PCT entries: type of "PCT"
- CICS PPT entries: type of "PPT"

The preparation JCL is also FTPed to the VSE/POWER<sup>™</sup> reader queue on the host system.

A log of the FTP process is created in the genDirectory. For details about the control of the log, refer to the debugTrace build descriptor option described above. Three types of FTP log message are produced:

- Information messages with a suffix of "i".
- Error messages with a suffix of "e".
- Trace messages with a suffix of "t".

### Character code conversion

Character code conversion is performed at two different times:

- 1. At generation time, for text fields defined in a form group part.
- 2. At preparation time, for text fields in generated COBOL source.

#### Character code conversion at generation

The serverCodeSet build descriptor option is used for converting the text in maps from the code page on the development platform, to a code page on the host VSE system. The value specified by the serverCodeSet build descriptor option should be the name of a valid code page translation table as defined on the workstation. Once the map format module is generated, it is transferred to the VSE host using a binary FTP transfer.

#### Character code conversion at preparation

The TRANSLATETABLE symbolic parameter is used for converting characters in generated parts such as COBOL programs, tables and JCL, from the code page on the development platform to a code page on the host VSE system.

The value specified by the TRANSLATETABLE symbolic parameter should be the name of a valid code page translation table as defined to the FTP server on the host.

If no value is entered for the TRANSLATETABLE symbolic parameter, then the default code page translation table as defined to the FTP server is used.

If a value is entered for the TRANSLATETABLE build descriptor option, then for text parts, this value is sent to the FTP server as part of a SITE TRANSLATE command.

For information on code page translation, and the FTP server, refer to Chapter 11, "ASCII to EBCDIC translation" in the *TCPIP for VSE Installation Guide*.

### FTP commands issued during preparation

These FTP commands are issued during the preparation process, and should be enabled on the FTP server:

CWD PASV PORT PWD QUIT SITE clrf off/on SITE crlf on SITE lrecl 80 SITE reclf on SITE reclf on SITE TRANSLATE STOR TYPE I USER

In addition, JCL is transferred to the VSE/POWER reader queue using FTP. Transfer to the VSE/POWER reader queue should also be enabled on the FTP server.

### Running precompilers, compilers and linkers

The templates used by VisualAge Generator for JCL generation have been used as a basis for the plug-in. For EGL, the templates have been renamed and placed in the VSETemplates directory. Minor changes to the templates bring the JCL up to date with new versions of the compiler and operating system.

Chapter 2, "Prerequisites and installation," on page 3 contains a table with the name of the VisualAge Generator template and the name of the equivalent template in the plug-in.

### Changes to the templates

For the plug-in, the following changes have been made to the templates:

- In template fda2vjob, a "J" has been added to the jobname to differentiate it from other jobs that are part of the preparation stream.
- Construction of the jobname for all jobs has been changed. To create the jobname, up to seven characters of the JOBNAME symbolic parameter are used

with a character appended according to the stage of preparation. If no JOBNAME symbolic parameter is specified, then the first seven characters of the program name are used.

• EZETPROC is set to eight characters in length where:

#### position 1-4

First four characters of the destUserID build descriptor option

If destUserID is not set, then the first four characters of the program name are used.

If less than four characters are available, then  $^{\prime\prime}Z^{\prime\prime}$  is used as the padding character

#### position 5-8

MMSS (min,min,sec,sec) obtained from the system-generated time.

For example, if destUserID is set to USERID and the program is generated at 8:45:29, SYMPARM EZETPROC is set to USER4529.

- The RES COBOL compiler option has been removed from these templates:
  - fda2vpba.tpl
    fda2vpbd.tpl
    fda2vpca.tpl
    fda2vpcb.tpl
    fda2vtcl.tpl
- In fda2vpca.tpl and fda2vpcb.tpl, for the CICS translator step, the SP parameter has been added as an option to XOPTs.

### Outputs from the execution of the preparation JCL

As there has been no significant change to the preparation JCL, the outputs from the execution of the preparation JCL are similar to that of VisualAge Generator. Refer to the *VisualAge Generator Server Guide for MVS, VSE and VM* for more information.

## Chapter 7. Execution of generated applications

As there has been no significant change to the generation of the execution JCL, or COBOL programs, the process for running generated applications has not changed. Refer to the *VisualAge Generator Server Guide for MVS, VSE and VM* for more information.

### Additional runtime messages

New runtime messages have been added for the support of dynamic arrays. An explanation of the new messages follows:

#### ELA00269E Array index value \$01D07 out of range for Array \$02C18 with size of \$03D07

**Explanation:** An attempt has been made to access an element in an array, at a position in the array which is outside the array's range.

The run unit ends.

**User response:** Change the program to only use indexes within the size of the array.

ELA00270E An attempt was made to exceed the maximum size of array \$01C18

**Explanation:** An attempt has been made to add an element to an array, but the array is too small to hold the additional element.

The run unit ends.

User response: Increase the size of the array.

## **Chapter 8. Recommendations**

### Connections to DB2 on VSE

With EGL, it is possible to connect to DB2 to debug programs and to retrieve SQL record definitions. To connect to a DB2 system running on a VSE host, a type 2 JDBC connection should be used.

It is beyond the scope of this document to provide detailed descriptions of the configuration required to support JDBC calls to DB2 VSE. However, in broad terms, the following software will need to be configured:

- **DB2 Connect**<sup>™</sup> should be installed on the developer platform. We recommend use of the JDBC driver available with DB2 Connect. Within DB2 Connect a database definition should be made for the databases that reside on the VSE host.
- In **RAD/RWD** the *Preferences* > *EGL* > *SQL Database Connections* should be configured to use a type 2 JDBC driver. See "Sample 5: SQL database connections" on page 39 for an example configuration.
- **DB2 VSE Server** should be configured to allow TCP/IP and JDBC communication. Refer to the DB2 manuals for further information.

### **Allocating Printer Files**

For printer files, the plug-in generates a default filename of PRINTER. This is in contrast to VisualAge Generator Developer which generates a filename of EZEPRINT. To control the characteristics of the printer file, we recommend that a resource association element be created for filename PRINTER.

For CICS applications, you can associate the PRINTER file with either a transient data queue (type TRANSIENT) or a VSE/POWER file (type SPOOL) using a PRINTER resource association. We recommend that:

- Either a default transient data queue named PRIN be defined to the CICS system, or
- A resource association entry for PRINTER be defined with a systemname of EZEP (as a transient data queue called EZEP is defined when the Server is installed)

Resource Association files migrated from VisualAge Generator Developer to EGL should have any EZEPRINT resource association definitions migrated to PRINTER resource association definitions.

## **Appendix. Samples**

These samples are provided as a reference only, and should be customized according to site requirements.

## Sample 1: Basic build descriptor options

Figure 1 shows the basic build descriptor options.

📳 VSEBatchOptions		G	eneral Options	<enter a="" description="" here=""> 💌 🔩</enter>
uild option filter	Batch Target System (Basic) 💌		Symbolic parameters:	
Show only specified	options		Name	Value
			JOBCARD	yourjobcard.tpl
Option	Value (F1 for Help)		JOBNAME	YOURJOB
destHost	yourHost		PROCLIB	YOUR.PROCLIB
destPassword	yourPwd		PWRCLASS	A
destPort	21		SQLDBNAM	SQLDS
destUserID	yourUID		SQLPKGNM	SQLAPPL
genDataTables	YES		SQLPROPT	ELASQLPR
genDirectory	D:\Genout\vsebatch		SQLSTMDE	MULTIUSER
genFormGroup	YES		SQLSTOPT	SYSMODE=S,LOGMODE=N
projectID	(no value set)		SQLUSRPW	SQLUID/SQLPWD
resourceAssociations	VSEBatchRAF		TRANSLATETABLE	
system	VSEBATCH		VUSERLIB	YOUR.USERLIB
vseLibrary	YOUR.EZELIB			
			1 1	
			Add Remove	

Figure 1. The basic build descriptor options

## Sample 2: The associated Resource Association File

Figure 2 on page 36 shows the Resource Association File associated with the build descriptor options in Sample 1.

#### Sample 3: The resultant XML file

ssociation elements:			Properties of selected (	Properties of selected system entries:		
File Name	System	File Type	Property	Value (F1 for Help)		
OUTFILE			system	vsebatch		
	vsebatch	seq	fileType	seq		
			blockSize	REC, 100		
			standardLabel	YES		
			systemName	YOURUID.OUTFILE		
			systemNumber	010		
			-			
			-			
			-			
			-			
			-			
			-			
			-			
			-			
			-			
			_			
			-			

Figure 2. The Resource Association File

## Sample 3: The resultant XML file

Figure 3 on page 37 shows the XML file that holds the build descriptor options of Sample 1 and resource association file of Sample 2.

```
<?xml version="1.0" encoding="UTF-8"?>
<!DOCTYPE EGL PUBLIC "-//IBM Corporation, Inc.//DTD EGL Build Parts 6.0//EN" "">
<EGL>
  <BuildDescriptor name="VSEBatchOptions" destHost="yourHost" destPassword="yourPwd" destPort="21"
destUserID="yourUID" genDataTables="YES" genDirectory="D:\Genout\vsebatch" genFormGroup="YES"
system="VSEBATCH" vseLibrary="YOUR.EZELIB" resourceAssociations="VSEBatchRAF">
    <symbolicParameter name="JOBCARD">
      <symbolicValue><![CDATA[yourjobcard.tpl]]></symbolicValue></symbolicParameter>
    <symbolicParameter name="JOBNAME">
     <symbolicValue><![CDATA[YOURJOB]]></symbolicValue></symbolicParameter>
    <symbolicParameter name="PROCLIB">
     <symbolicValue><![CDATA[YOUR.PROCLIB]]></symbolicValue></symbolicParameter>
    <symbolicParameter name="PWRCLASS">
      <symbolicValue><![CDATA[A]]></symbolicValue></symbolicParameter>
    <symbolicParameter name="SQLDBNAM">
      <symbolicValue><![CDATA[SQLDS]]></symbolicValue></symbolicParameter>
    <symbolicParameter name="SQLPKGNM">
      <symbolicValue><![CDATA[SQLAPPL]]></symbolicValue></symbolicParameter>
    <symbolicParameter name="SQLPROPT">
      <symbolicValue><![CDATA[ELASQLPR]]></symbolicValue></symbolicParameter>
    <symbolicParameter name="SQLSTMDE">
      <symbolicValue><![CDATA[MULTIUSER]]></symbolicValue></symbolicParameter>
    <symbolicParameter name="SQLSTOPT">
      <symbolicValue><![CDATA[SYSMODE=S,LOGMODE=N]]></symbolicValue></symbolicParameter>
    <symbolicParameter name="SQLUSRPW">
      <symbolicValue><![CDATA[SQLUID/SQLPWD]]></symbolicValue></symbolicParameter>
    <symbolicParameter name="TRANSLATETABLE">
      <symbolicValue><![CDATA[]]></symbolicValue></symbolicParameter>
    <symbolicParameter name="VUSERLIB">
     <symbolicValue><![CDATA[YOUR.USERLIB]]></symbolicValue></symbolicParameter>
  </BuildDescriptor>
  <ResourceAssociations name="VSEBatchRAF">
    <association fileName="OUTFILE">
      <vsebatch>
        <seq systemNumber="010" systemName="YOURUID.OUTFILE" standardLabel="YES" blockSize="REC,100"/>
      </vsebatch>
    </association>
  </ResourceAssociations>
</EGL>
Figure 3. Sample XML file
```

### Sample 4: An FTP trace

Figure 4 on page 38 shows an FTP trace produced when the debugTrace build descriptor option (see page 27) is specified.

#### Sample 4: An FTP trace

20050322 05:04:10 ELA.FTP.0000.i (c) Copyright, IBM Corp. 2005 20050322 05:04:10 ELA.FTP.2001.t Attempt connection to yourHost on port 21 20050322 05:04:10 ELA.FTP.2010.t FTP server response: 220-TCP/IP for VSE FTP Daemon Version 01.05 C 10/12/03 22.50 20050322 05:04:10 ELA.FTP.2010.t FTP server response: Copyright (c) 1995,2003 Connectivity Systems Incorporated 20050322 05:04:10 ELA.FTP.2010.t FTP server response: 220 FTPD ready for new user. 20050322 05:04:10 ELA.FTP.2007.t FTP Reply code of 220 . 20050322 05:04:10 ELA.FTP.0001.i Connection to yourHost opened on port 21 20050322 05:04:10 ELA.FTP.2003.t Attempt login with userid youruid . 20050322 05:04:10 ELA.FTP.2006.t Issue FTP command 'USER youruid' . 20050322 05:04:10 ELA.FTP.2010.t FTP server response: 331 User name okay, need password. 20050322 05:04:10 ELA.FTP.2007.t FTP Reply code of 331 20050322 05:04:10 ELA.FTP.2006.t Issue FTP command 'PASS \*\*\*\*\*\*\*' 20050322 05:04:10 ELA.FTP.2010.t FTP server response: 230 User logged in, proceed. 20050322 05:04:10 ELA.FTP.2007.t FTP Reply code of 230 . 20050322 05:04:10 ELA.FTP.0003.i Login to Host for user youruid successful. 20050322 05:04:10 ELA.FTP.2006.t Issue FTP command 'SITE lrec' 80' 20050322 05:04:10 ELA.FTP.2010.t FTP server response: 200 Command okay. 20050322 05:04:10 ELA.FTP.2007.t FTP Reply code of 200 20050322 05:04:10 ELA.FTP.2006.t Issue FTP command 'SITE crlf on' . 20050322 05:04:10 ELA.FTP.2010.t FTP server response: 200 Command okay. 20050322 05:04:10 ELA.FTP.2007.t FTP Reply code of 200 20050322 05:04:10 ELA.FTP.2006.t Issue FTP command 'SITE reclf on' 20050322 05:04:10 ELA.FTP.2010.t FTP server response: 200 Command okay. 20050322 05:04:10 ELA.FTP.2007.t FTP Reply code of 200 20050322 05:04:10 ELA.FTP.2004.t Attempt 'cd' to YOUR.EZELIB 20050322 05:04:10 ELA.FTP.0004.i Change Directory command to library YOUR.EZELIB successful. 20050322 05:04:10 ELA.FTP.2005.t Attempt 'put' command for file TESTDLBL.cbl 20050322 05:04:10 ELA.FTP.2006.t Issue FTP command 'PORT nnn,nnn,nnn,nnn,nn' 20050322 05:04:10 ELA.FTP.2010.t FTP server response: 200 Command okay. 20050322 05:04:10 ELA.FTP.2007.t FTP Reply code of 200 20050322 05:04:10 ELA.FTP.2006.t Issue FTP command 'STOR TESTDLBL.c' . 20050322 05:04:11 ELA.FTP.2010.t FTP server response: 150-About to open data connection 20050322 05:04:11 ELA.FTP.2010.t FTP server response: File: YOUR.EZELIB.TESTDLBL.C 20050322 05:04:11 ELA.FTP.2010.t FTP server response: Type: ASCII Recfm: FB Lrecl: 80 80 Blksize: 20050322 05:04:11 ELA.FTP.2010.t FTP server response: CC=ON UNIX=OFF RECLF=ON TRCC=OFF CRLF=ON 20050322 05:04:11 ELA.FTP.2010.t FTP server response: Translate with US\_ENG\_03 20050322 05:04:11 ELA.FTP.2010.t FTP server response: MODE=Stream STRU=File 20050322 05:04:12 ELA.FTP.2010.t FTP server response: 150 File status okay; about to open data connection 20050322 05:04:12 ELA.FTP.2007.t FTP Reply code of 150 20050322 05:04:13 ELA.FTP.2010.t FTP server response: 226-Bytes received: 102,949 20050322 05:04:14 ELA.FTP.2010.t FTP server response: Records received: 1,356 20050322 05:04:14 ELA.FTP.2010.t FTP server response: Transfer Seconds: 1.68 ( 100K/Sec) 20050322 05:04:14 ELA.FTP.2010.t FTP server response: File I/O Seconds: .09 ( OK/Sec) 20050322 05:04:14 ELA.FTP.2010.t FTP server response: 226 Closing data connection. 20050322 05:04:14 ELA.FTP.2007.t FTP Reply code of 226 20050322 05:04:14 ELA.FTP.0005.i Put command for file TESTDLBL.cbl successful. 20050322 05:04:14 ELA.FTP.2002.t Attempt to close connection to Host. 20050322 05:04:14 ELA.FTP.2006.t Issue FTP command 'QUIT' 20050322 05:04:14 ELA.FTP.2010.t FTP server response: 221 FTPD closing control connection. 20050322 05:04:14 ELA.FTP.2007.t FTP Reply code of 221 . 20050322 05:04:14 ELA.FTP.0002.i Connection to Host closed.

Figure 4. Sample FTP trace

## Sample 5: SQL database connections

Figure 5 shows an example of parameters used to connect to a DB2 database on a VSE host.

Preferences				- 🗆 🛛		
	_					
Crystal Enterprise     Crystal Reports Designer	^	SQL Database Connections				
Crystal Reports Designer     Crystal Reports Viewers						
		Connection URL:	jdbc:db2:YOURDB			
EGL		Database:	YOURDB			
Debug		<u>U</u> ser ID:	youruid			
Default Build Descriptor     Editor		Password:	*******			
EGL Form Editor			,			
SQL Database Connect		Database <u>v</u> endor type:	DB2 Universal Database for z/OS and OS/390 V7	•		
SQL Retrieve		JDBC driver:	Other DB2/390 Driver	-		
i Help		<u></u>				
Install/Update     Internet		JDBC driver d <u>a</u> ss:	COM.ibm.db2.jdbc.app.DB2Driver			
J2EE	=	Class location:	D:\DB2\DB2 Connect v 8.2 Enterprise Edition\java\db2java.zip Brow	vse		
+ Java		Class jocation:		/sc		
. Modeling		Connection JNDI name:				
Process		Secondary Authentication ID:				
🕀 Run/Debug						
+ Server						
Template Editor						
Validation     Web and XML						
Web Diagram						
	-					
	•		Restore Defaults Ap	oply		
Import Export			ОК	Cancel		

Figure 5. Parameters used to connect to a DB2 database on a VSE host

Sample 5: SQL database connections

## Notices

This information was developed for products and services offered in the U.S.A.

IBM may not offer the products, services, or features discussed in this document in other countries. Consult your local IBM representative for information on the products and services currently available in your area. Any reference to an IBM product, program, or service is not intended to state or imply that only that IBM product, program, or service may be used. Any functionally equivalent product, program, or service that does not infringe any IBM intellectual property right may be used instead. However, it is the user's responsibility to evaluate and verify the operation of any non-IBM product, program, or service.

IBM may have patents or pending patent applications covering subject matter described in this document. The furnishing of this document does not give you any license to these patents. You can send license inquiries, in writing, to:

IBM Director of Licensing IBM Corporation North Castle Drive Armonk, NY 10504-1785 U.S.A.

Licensees of this program who wish to have information about it for the purpose of enabling: (i) the exchange of information between independently created programs and other programs (including this one) and (ii) the mutual use of the information which has been exchanged, should contact:

IBM Corporation Mail Station P300 2455 South Road Poughkeepsie New York 12601-5400 U.S.A.

Such information may be available, subject to appropriate terms and conditions, including in some cases, payment of a fee.

The licensed program described in this document and all licensed material available for it are provided by IBM under terms of the IBM Customer Agreement, IBM International Program License Agreement or any equivalent agreement between us.

For license inquiries regarding double-byte (DBCS) information, contact the IBM Intellectual Property Department in your country or send inquiries, in writing, to:

IBM World Trade Asia Corporation Licensing 2-31 Roppongi 3-chome, Minato-ku Tokyo 106-0032, Japan

The following paragraph does not apply to the United Kingdom or any other country where such provisions are inconsistent with local law: INTERNATIONAL BUSINESS MACHINES CORPORATION PROVIDES THIS PUBLICATION "AS IS" WITHOUT WARRANTY OF ANY KIND, EITHER EXPRESS OR IMPLIED, INCLUDING, BUT NOT LIMITED TO, THE IMPLIED WARRANTIES OF NON-INFRINGEMENT, MERCHANTABILITY OR FITNESS FOR A PARTICULAR

#### Notices

PURPOSE. Some states do not allow disclaimer of express or implied warranties in certain transactions, therefore, this statement may not apply to you.

This information could include technical inaccuracies or typographical errors. Changes are periodically made to the information herein; these changes will be incorporated in new editions of the publication. IBM may make improvements and/or changes in the product(s) and/or the program(s) described in this publication at any time without notice.

Any references in this information to non-IBM Web sites are provided for convenience only and do not in any manner serve as an endorsement of those Web sites. The materials at those Web sites are not part of the materials for this IBM product and use of those Web sites is at your own risk.

If you are viewing this information softcopy, the photographs and color illustrations may not appear.

### Trademarks

The following are trademarks of International Business Machines Corporation in the United States, or other countries, or both.

CICS DB2 DB2 Connect IBM Language Environment MQSeries MVS POWER Rational VisualAge VSE/ESA WebSphere z/OS

UNIX is a registered trademark of The Open Group in the United States and other countries.

Windows is a trademark of Microsoft Corporation in the United States, other countries, or both.

Other company, product, and service names may be trademarks or service marks of others.

## **Bibliography**

EGL Reference Guide, SC31-6837

*Program Directory for VisualAge Generator Server for VSE*, GI10-0813

*TCPIP for VSE Installation Guide*, published by Connectivity Systems

*VisualAge Generator EGL Plug-in for VSE Reference Manual*, SC18-9531

*VisualAge Generator Generation Guide,* SH23-0263

VisualAge Generator to EGL Migration Guide, SH23-0263

*VisualAge Generator Server Guide for MVS, VSE and VM*, SH23-0256

## Index

## Special characters

/BLKSIZE generation option 16
/JOBCARD generation option 16
/JOBNAME generation option 16
/LABEL generation option 16
/NOLABEL generation option 16
/SYSNUM generation option 16
/VSELIB generation option 16
equivalent to vseLibrary build descriptor option 23

## A

applications generation 23 ASCII 29

## B

blockSize build descriptor option 16 blockSize resource association property 24 build descriptor options 23 basic sample 35 blockSize 16 controlling generated parts file transfer 27 debugTrace 27 destHost 27 destPassword 27 destPort 27 destUserId 27 prep 27 samples 35 serverCodeSet 28 standardLabel 16 system 23 systemNumber 16 vseLibrary 16, 23, 28 build descriptors 15

## С

character code conversion 28 at generation 28 at preparation 29 CICS mandatory product 4 PRINTER file association 33 COBOL compiler mandatory product 4 COBOLV2 symbolic parameter 23 comparisons supported 2 compilers 29

### D

date not supported 20 support when migrated 20 date function not supported 1 DB2 connecting to 33 optional product 4 debugTrace build descriptor option 27 destHost build descriptor option 27 destPassword build descriptor option 27 destPort build descriptor option 27 destUserId build descriptor option 27 DL/I data access not supported 21 DL/I support not supported 2 dynamic arrays supported 2, 19

## Ε

EBCDIC 29 EGL enhancements to support 19 migration to 15 statements equivalent to EZE words 20 supported functions 1 unsupported functions 1 EGL feature installing 5 enhancements to support EGL 19 Enterprise Generation Language See EGL Enterprise Generation Language feature See EGL feature execution outputs 30 EZE words equivalent EGL statements 20 EZEDAY EZE word EGL equivalent 20 **EZEDTE** function supported 1 EZEPRINT default VisualAge Generator Developer print filename 33 EZETIM function supported 1 EZETPROC symbolic parameter 30

### F

file transfer options 27 file transfer outputs 28 formatting numbers not supported 1, 20 FTP commands issued during preparation 29 FTP process controlling tracing 27 log produced 28 FTP server configuration 27 FTP trace sample 37 functions supported within EGL 1 unsupported within EGL 1

## G

generated applications executing 17 preparing 17 generated parts from successful generation 25 location 25 preparing 27 transferring to VSE host system 27 VSE type after transfer 28 VSECICS type after transfer 28 generation outputs 25 generation of applications 23 generation options 15 /BLKSIZE 16 /JOBCARD 16 /JOBNAME 16 /LABEL 16 /NOLABEL 16 /SYSNUM 16 /VSELIB 16

iFix 5

## J

JCL 17 output from preparation 30 JOBCARD symbolic parameter 23 usage 17 JOBNAME symbolic parameter 23, 30 usage 17

### L

LE mandatory product 4 library functions not supported 20 license inquiry 41 like comparison supported 2 like operator 19 linkers 29 log produced by FTP process 28 log messages *See* messages

## Μ

mandatory products 3 match comparison supported 2 matches operator 19 messages error 28 information 28 runtime 31 trace 28 migration function installation 6 MQSeries optional product 4

## 0

operators like 19 matches 19 optional products 4 outputs from execution of preparation JCL 30 from file transfer 28 from generation 25

## Ρ

parts See generated parts plug-in installation 4 more information 1 prerequisites 3 purpose 1 uninstalling 5 website 6 precompilers 29 prep build descriptor option 27 preparation character conversion 29 FTP commands issued during 29 prerequisites plug-in 3 server 3 primitive UNICODE supported 2 PRINTER default plug-in print filename 25, 33 printer files allocating 33 PROCLIB symbolic parameter 16, 23 PTFs to be installed 5 publications VisualAge Generator 43 PWRCLASS symbolic parameter 16, 23

### R

RAD fix001 5 fix002 5 fix003 5 installation 4 minimum software requirement 3 updating 5 Rational Application Developer See RAD Rational Product Updater using to update RAD or RWD 5 Rational Web Developer See RWD Resource Association file sample 35 resource association options 24 resource association parameters system 24 resource association properties blockSize 24 standardLabel 24 systemNumber 25 RWD fix001 5 fix002 5 fix003 5 installation 4 minimum software requirement 3 updating 5

S

samples 35 server enhancements 19 installation 5 installing 5 prerequisites 3 version supported 3 server software 3 serverCodeSet build descriptor option 28 SITE FTP command 29 SITE TRANSLATE FTP command 29 SNA file transfer not supported by plug-in 27 SQL database connections sample 39 SQLDBNAM symbolic parameter 16, 23 SQLPKGNM symbolic parameter 16, 23 SQLPROPT symbolic parameter 16, 24 SQLSTMDE symbolic parameter 16, 24 SQLSTOPT symbolic parameter 16, 24 SQLUSRPW symbolic parameter 16, 24 standardLabel build descriptor option 16 standardLabel resource association property 24 strLib.formatNumber EGL statement not supported 20 symbolic parameters 15 COBOLV2 23 EZETPROC 30 JOBCARD 23 **JOBNAME** 23, 30

symbolic parameters (continued) PROCLIB 16, 23 PWRCLASS 16, 23 SQLDBNAM 16, 23 SQLPKGNM 16, 23 SQLPROPT 16, 24 SQLSTMDE 16, 24 SQLSTOPT 16, 24 SQLUSRPW 16, 24 TRANSLATETABLE 24, 28, 29 VUSERLIB 16 system build descriptor option 23 system resource association parameter 24 systemNumber build descriptor option 16 systemNumber resource association property 25

## T

TCP/IP mandatory product 4 TCPIP for VSE prerequisite product 27 templates changes to 29 default location 17 EGL equivalent 17 purpose 17 time not supported 20 support when migrated 20 time function not supported 1 trace sample 37 TRANSLATE keyword 29 TRANSLATETABLE symbolic parameter 24, 28, 29

## V

VisualAge Generator EGL plug-in for VSE See plug-in VisualAge Generator Server for VSE See server VSE mandatory product 4 VSEBATCH output of successful FTP process 28 value of resource association parameter 24 value of system build descriptor option 23 VSECICS output of successful FTP process 28 value of resource association parameter 24 value of system build descriptor option 23 vseLibrary build descriptor option 16, 23, 28 VSETemplates directory for template storage 17

VUSERLIB symbolic parameter 16

## W

web transactions 21 Neb transactions not supported 2

## Χ

XML file sample 36

## **Readers' Comments — We'd Like to Hear from You**

VisualAge Generator EGL Plug-in for VSE Reference Manual Version 1.0

#### Publication No. SC18-9531-01

We appreciate your comments about this publication. Please comment on specific errors or omissions, accuracy, organization, subject matter, or completeness of this book. The comments you send should pertain to only the information in this manual or product and the way in which the information is presented.

For technical questions and information about products and prices, please contact your IBM branch office, your IBM business partner, or your authorized remarketer.

When you send comments to IBM, you grant IBM a nonexclusive right to use or distribute your comments in any way it believes appropriate without incurring any obligation to you. IBM or any other organizations will only use the personal information that you supply to contact you about the issues that you state on this form.

Comments:

Thank you for your support.

Submit your comments using one of these channels:

• Send your comments to the address on the reverse side of this form.

If you would like a response from IBM, please fill in the following information:

Name

Address

Company or Organization

Phone No.

E-mail address



Cut or Fold Along Line

Fold and Tape

Please do not staple



NO POSTAGE NECESSARY IF MAILED IN THE UNITED STATES

Fold and Tape

# **BUSINESS REPLY MAIL**

FIRST-CLASS MAIL PERMIT NO. 40 ARMONK, NEW YORK

POSTAGE WILL BE PAID BY ADDRESSEE

IBM Corporation Reader Comments DTX/E269 555 Bailey Avenue San Jose, CA 95141-9989 U.S.A.

Fold and Tape

Please do not staple

Fold and Tape

## IBW ®

Program Number: 5724-L93

Printed in USA

SC18-9531-01

