


MQSeries® Everyplace



Programming reference

Version 1

MQSeries® Everyplace



Programming reference

Version 1

Take Note!

Before using this information and the product it supports, be sure to read the general information under "Appendix. Notices" on page 355

Licence warning

MQSeries Everyplace Version 1 is a toolkit that enables users to write MQSeries Everyplace applications and to create an environment in which to run them.

The licence conditions under which the toolkit is purchased determine the environment in which it can be used:

If MQSeries Everyplace is purchased for use as a device (client) it may not be used to create an MQSeries Everyplace channel manager, or an MQSeries Everyplace channel listener., or an MQSeries Everyplace bridge

The presence of an MQSeries Everyplace channel manager, or an MQSeries Everyplace channel listener, or an MQSeries Everyplace bridge defines a gateway (server) environment, which requires a gateway licence.

First Edition (June 2000)

This edition applies to MQSeries Everyplace Version 1 and to all subsequent releases and modifications until otherwise indicated in new editions.

This document is continually being updated with new and improved information. For the latest edition, please see the MQSeries family library Web page at <http://www.ibm.com/software/ts/mqseries/library/>.

© Copyright International Business Machines Corporation 2000. All rights reserved.

US Government Users Restricted Rights – Use, duplication or disclosure restricted by GSA ADP Schedule Contract with IBM Corp.

Contents

About this book	ix
Who should read this book	ix
Prerequisite knowledge	ix
Terms used in this book	ix
Chapter 1. MQSeries Everyplace classes and interfaces	1
com.ibm.mqe	1
com.ibm.mqe.administration	2
com.ibm.mqe.attributes	2
com.ibm.mqe.registry	3
com.ibm.mqe.server	3
com.ibm.mqe.mqemqmessage	3
com.ibm.mqe.mqbridge	4
Chapter 2. Classes in com.ibm.mqe	5
MQe	7
Constants	7
Publically accessible variables	10
Method summary	11
MQe abbreviate	11
MQe alias	12
MQe asciiToByte	13
MQe byteToAscii	13
MQe byteToHex	13
MQe byteToInt	14
MQe byteToLong	14
MQe byteToShort	15
MQe byteToUnicode	15
MQe debug	15
MQe getEventLogHandler	16
MQe getTraceHandler	16
MQe hexToAscii	17
MQe hexToByte	17
MQe intToByte	18
MQe log	18
MQe mapFileDescriptor	19
MQe setEventLogHandler	19
MQe setTraceHandler	20
MQe sliceByteArray	20
MQe trace	21
MQe type	22
MQe unicodeToByte	22
MQe unicodeToUTF	23
MQe uniqueValue	23
MQe utfToUnicode	23
MQeAdapter	25
Method summary	25
MQeAdapter activate	25
MQeAdapter checkOption	26
MQeAdapter close	26
MQeAdapter control	27
MQeAdapter equals	27
MQeAdapter erase	27
MQeAdapter open	28
MQeAdminMsg	33
Constants and variables	33
Constructor summary	34
Method summary	34
MQeAdminMsg	35
MQeAdminMsg characteristics	35
MQeAdminMsg create	36
MQeAdminMsg delete	36
MQeAdminMsg duplicate	37
MQeAdminMsg getAction	38
MQeAdminMsg getErrorFields	38
MQeAdminMsg getFieldInError	39
MQeAdminMsg getInputFields	39
MQeAdminMsg getMaxAttempts	40
MQeAdminMsg getName	40
MQeAdminMsg getOutputFields	41
MQeAdminMsg getRC	41
MQeAdminMsg getReason	42
MQeAdminMsg getTargetQMGr	42
MQeAdminMsg inquire	43
MQeAdminMsg inquireAll	43
MQeAdminMsg setAction	44
MQeAdminMsg setName	44
MQeAdminMsg setTargetQMGr	45
MQeAdminMsg update	45
MQeAttribute	47
Constructor summary	47
Method summary	47
MQeAttribute	47
MQeAttribute activate	48
MQeAttribute authenticatedID	49
MQeAttribute change	49
MQeAttribute close	49
MQeAttribute decodeData	50
MQeAttribute encodeData	50
MQeAttribute equals	51
MQeAttribute getAuthenticator	51
MQeAttribute getCompressor	51
MQeAttribute getCryptor	52
MQeChannelListener	53
Constructor summary	53
Method summary	53
MQeChannelListener	53
MQeChannelListener activate	54
MQeChannelListener setTimer	55
MQeChannelListener stop	55
MQeChannelManager	57

Constructor summary	57
Method summary	57
MQeChannelManager	57
MQeChannelManager getGlobalHashtable	58
MQeChannelManager mapDestination	58
MQeChannelManager numberOfChannels	59
MQeChannelManager process	59
MQeChannelManager timeOut	60
MQeChannelManager totalNumberOfChannels	61
MQeEnumeration	62
Method summary	62
MQeEnumeration getLockId	62
MQeEnumeration getNextMessage	62
MQeEnumeration getQueueManagerName	64
MQeEnumeration getQueueName	64
MQeException	66
Constructor summary	66
Method summary	66
MQeException	66
MQeException code	67
MQeFields.	68
Constructor summary	68
Method summary	68
MQeFields.	70
MQeFields contains	71
MQeFields copy	71
MQeFields dataType	72
MQeFields delete	73
MQeFields dump	73
MQeFields dumpToString	75
MQeFields dumpedType	76
MQeFields equals	77
MQeFields fields	77
MQeFields getArrayLength	78
MQeFields getArrayOfByte	78
MQeFields getArrayOfDouble	79
MQeFields getArrayOfFloat	79
MQeFields getArrayOfInt	80
MQeFields getArrayOfLong	80
MQeFields getArrayOfShort	81
MQeFields getAscii	81
MQeFields getAsciiArray	82
MQeFields getAttribute	83
MQeFields getBoolean	83
MQeFields getByte	83
MQeFields getByteArray	84
MQeFields getDouble	84
MQeFields getDoubleArray	85
MQeFields getFields	86
MQeFields getFieldsArray	86
MQeFields getFloat	87
MQeFields getFloatArray	87
MQeFields getInt	88
MQeFields getIntArray	88
MQeFields getLong	89
MQeFields getLongArray	89
MQeFields getShort	90
MQeFields getShortArray	90
MQeFields getUnicode	91
MQeFields getUnicodeArray	91
MQeFields hide	92
MQeFields putArrayLength	92
MQeFields putArrayOfByte	93
MQeFields putArrayOfDouble	93
MQeFields putArrayOfFloat	94
MQeFields putArrayOfInt	94
MQeFields putArrayOfLong	95
MQeFields putArrayOfShort	95
MQeFields putAscii	96
MQeFields putAsciiArray	96
MQeFields putBoolean	97
MQeFields putByte	97
MQeFields putByteArray	98
MQeFields putDouble	98
MQeFields putDoubleArray	99
MQeFields putFields	99
MQeFields putFieldsArray	100
MQeFields putFloat	100
MQeFields putFloatArray	101
MQeFields putInt	101
MQeFields putIntArray	102
MQeFields putLong	102
MQeFields putLongArray	103
MQeFields putShort	103
MQeFields putShortArray	104
MQeFields putUnicode	104
MQeFields putUnicodeArray	105
MQeFields rename	105
MQeFields restore	106
MQeFields restoreFromFile	106
MQeFields restoreFromString	107
MQeFields setAttribute	108
MQeFields updateValue	109
MQeKey	110
Constructor summary	110
Method summary	110
MQeKey	110
MQeKey setLocalKey	110
MQeMessageEvent	112
Method summary	112
MQeMessageEvent getMsgFields	112
MQeMessageEvent getQueueManagerName	113
MQeMessageEvent getQueueName	113
MQeMsgObject class	115
Constants and variables	115
Constructor summary	116
Method summary	116
MQeMsgObject	116
MQeMsgObject getMsgUIDFields	117
MQeMsgObject getOriginQMGr	118
MQeMsgObject getTimeStamp	118
MQeMsgObject putOriginQMGr	119
MQeMsgObject resetMsgUIDFields	119
MQeMsgObject unwrapMessageObject	119
MQeQueue	121
Method summary	121
MQeQueue getCreationDate	122
MQeQueue getDefaultPriority	123
MQeQueue getDescription	123
MQeQueue getExpiryInterval	124
MQeQueue getMaxMessageSize	124
MQeQueue getMaxQueueSize	125

MQeQueue getNumberOfMessages	125
MQeQueue getQueueAttribute	126
MQeQueue getQueueManagerName	127
MQeQueue getQueueName	127
MQeQueue getQueueStore	128
MQeQueueManager	130
Constructor summary	130
Method summary	130
MQeQueueManager	131
MQeQueueManager activate	133
MQeQueueManager addMessageListener	134
MQeQueueManager browseMessages	135
MQeQueueManager browseMessagesAndLock	137
MQeQueueManager checkActive	139
MQeQueueManager close	139
MQeQueueManager confirmGetMessage	140
MQeQueueManager confirmPutMessage	141
MQeQueueManager deleteMessage	142
MQeQueueManager getMessage	143
MQeQueueManager getName	145
MQeQueueManager getReference	146
MQeQueueManager putMessage	146
MQeQueueManager removeMessageListener	148
MQeQueueManager triggerTransmission	149
MQeQueueManager undo	150
MQeQueueManager unlockMessage	151
MQeQueueManager waitForMessage	152
MQeQueueManagerConfigure	155
Constructor summary	155
Method summary	155
MQeQueueManagerConfigure	155
MQeQueueManagerConfigure activate	156
MQeQueueManagerConfigure close	157
MQeQueueManagerConfigure	
defineDefaultAdminQueue	158
MQeQueueManagerConfigure	
defineDefaultAdminReplyQueue	158
MQeQueueManagerConfigure	
defineDefaultDeadLetterQueue	159
MQeQueueManagerConfigure	
defineDefaultSystemQueue	160
MQeQueueManagerConfigure	
defineQueueManager	160
MQeQueueManagerConfigure	
deleteAdminQueueDefinition	161
MQeQueueManagerConfigure	
deleteAdminReplyQueueDefinition	161
MQeQueueManagerConfigure	
deleteDeadLetterQueueDefinition	162
MQeQueueManagerConfigure	
deleteQueueManagerDefinition	163
MQeQueueManagerConfigure	
deleteStandardQMDefinitions	163
MQeQueueManagerConfigure	
deleteSystemQueueDefinition	164
MQeQueueManagerConfigure	
queueManagerExists	165
MQeQueueManagerConfigure	
setChannelTimeout	165
MQeQueueManagerConfigure	
setChnlAttributeName	166
MQeQueueManagerConfigure setDescription	167
MQeQueueManagerRule	168
Method summary	168
MQeQueueManagerRule activateQueues	168
MQeQueueManagerRule addQueue	169
MQeQueueManagerRule deleteMessage	170
MQeQueueManagerRule getMessage	171
MQeQueueManagerRule getRetryCount	172
MQeQueueManagerRule peerConnection	172
MQeQueueManagerRule putMessage	173
MQeQueueManagerRule queueManagerActivate	174
MQeQueueManagerRule queueManagerClose	175
MQeQueueManagerRule removeQueue	176
MQeQueueManagerRule transmit	177
MQeQueueManagerRule triggerTransmission	178
MQeQueueManagerRule undo	179
MQeQueueRule	181
Method summary	182
MQeQueueRule addListener	182
MQeQueueRule attributeChange	183
MQeQueueRule browseMessage	184
MQeQueueRule deleteMessage	185
MQeQueueRule duplicateMessage	185
MQeQueueRule getMessage	186
MQeQueueRule getPendingMessage	187
MQeQueueRule indexEntry	188
MQeQueueRule messageExpired	189
MQeQueueRule putMessage	190
MQeQueueRule queueActivate	190
MQeQueueRule queueClose	191
MQeQueueRule removeListener	192
MQeQueueRule resetMessageLock	193
MQeQueueRule undo	194
MQeQueueRule useCountChanged	195
MQEventLogInterface	196
Method summary	196
MQEventLogInterface activate	196
MQEventLogInterface close	196
MQEventLogInterface logOutput	196
MQMessageListenerInterface	197
Method summary	197
MQMessageListener messageArrived	197
MQRunListInterface	198
Method summary	198
MQRunListInterface activate	198
MQSecurityInterface	201
Method summary	201
MQSecurityInterface alias	201
MQSecurityInterface channelCommand	201
MQSecurityInterface newAdapter	202
MQSecurityInterface mapFileDescriptor	202
MQTraceInterface	203
Method summary	203
MQTraceInterface activate	203
MQTraceInterface traceMessage	203
MQTraceInterface addMessage	204
MQTraceInterface addMessageBundle	204
Standard trace messages	205
MQTraceInterface close	207
MQTraceInterface getMessage	207

Chapter 3. Classes in com.ibm.mqe.administration	209
MQeAdminQueueAdminMsg	210
Constants and variables	210
MQeConnectionAdminMsg	211
Constants and variables	211
Method summary	212
MQeConnectionAdminMsg create	213
MQeConnectionAdminMsg update	213
MQeHomeServerQueueAdminMsg	215
Constants and variables	215
MQeQueueAdminMsg	216
Constants and variables	216
Constructor summary	218
Method summary	219
MQeQueueAdminMsg	219
MQeQueueAdminMsg addAlias	219
MQeQueueAdminMsg removeAlias	220
MQeQueueAdminMsg setName	220
MQeQueueManagerAdminMsg	222
Constants and variables	222
MQeRemoteQueueAdminMsg	224
Constants and variables	224
MQeStoreAndForwardQueueAdminMsg	225
Constants and variables	225
Method summary	225
MQeStoreAndForwardQueueAdminMsg addQueueManager	225
MQeStoreAndForwardQueueAdminMsg removeQueueManager	226
Chapter 4. Classes in com.ibm.mqe.attributes	227
MQe3DESCryptor	228
MQe3DESCryptor	228
MQeDESCryptor	229
MQeDESCryptor	229
MQeGenDH	230
Method summary	230
MQeGenDH main	230
MQeGenDH genParams	231
MQeLocalSecure	232
Constructor summary	232
Method summary	232
MQeLocalSecure	232
MQeLocalSecure open	232
MQeLocalSecure read	233
MQeLocalSecure write	233
MQeLZWCompressor	235
MQeLZWCompressor	235
MQeMARSCryptor	236
MQeMARSCryptor	236
MQeMAttribute	237
Constructor summary	237
Method summary	237
MQeMAttribute	237
MQeMAttribute decodeData	238
MQeMAttribute encodeData	239
MQeMTrustAttribute	240
Constructor summary	240
Method summary	240
MQeMTrustAttribute decodeData	242
MQeMTrustAttribute encodeData	243
MQeMTrustAttribute setHomeServer	243
MQeMTrustAttribute setPrivateRegistry	244
MQeMTrustAttribute setPublicRegistry	244
MQeRC4Cryptor	245
MQeRC4Cryptor	245
MQeRC6Cryptor	246
MQeRC6Cryptor	246
MQeRleCompressor	247
MQeRleCompressor	247
MQeWTLSCertAuthenticator	248
MQeWTLSCertAuthenticator	248
MQeXORCryptor	249
Constructor summary	249
Method summary	249
MQeXORCryptor	249
MQeXORCryptor setDecryptKey	250
MQeXORCryptor setEncryptKey	250
Chapter 5. Classes in com.ibm.mqe.registry	251
MQePrivateRegistry	252
Constructor summary	252
Method summary	252
MQePrivateRegistry	252
MQePrivateRegistry activate	252
MQePrivateRegistry deleteCertificate	254
MQePrivateRegistry getCertificate	254
MQePrivateRegistry getRegistryName	255
MQePrivateRegistry resetPIN	255
MQePrivateRegistry setTargetRegistryName	255
MQePrivateRegistryConfigure	257
Constructor summary	257
Method summary	257
MQePrivateRegistryConfigure	257
MQePrivateRegistryConfigure activate	258
MQePrivateRegistryConfigure close	260
MQePrivateRegistryConfigure credentialsExist	260
MQePrivateRegistryConfigure getCredentials	261
MQePrivateRegistryConfigure isPrivate	263
MQePublicRegistry	264
Constructor summary	264
Method summary	264
MQePublicRegistry	264
MQePublicRegistry activate	264
MQePublicRegistry deleteCertificate	265
MQePublicRegistry getCertificate	266
MQePublicRegistry putCertificate	266
MQePublicRegistry requestCertificate	266
MQePublicRegistry shareCertificate	267
Chapter 6. Classes in com.ibm.mqe.server	269
MQeMiniCertIssuanceInterface	270
Method summary	270
MQeMiniCertIssuanceInterface	270
addAuthenticatableEntity	270

MQeMiniCertIssuanceInterface	271
addEntityRegisteredAddress	271
MQeMiniCertIssuanceInterface	271
authoriseMiniCertRequest	271
MQeMiniCertIssuanceInterface	271
deleteAuthenticatableEntity	271
MQeMiniCertIssuanceInterface	272
deleteEntityRegisteredAddress	272
MQeMiniCertIssuanceInterface	272
readAuthenticatableEntity	272
MQeMiniCertIssuanceInterface	272
readEntity	272
RegisteredAddress	272
MQeMiniCertIssuanceInterface	273
SetRegistry	273
MQeMiniCertIssuanceInterface	273
updateAuthenticatableEntity	273
MQeMiniCertIssuanceInterface	273
updateEntityRegisteredAddress	273

Chapter 7. Classes in **com.ibm.mqe.mqemqmmessage** **275**

MQeMQMsgObject class	276
Constructor summary	276
Method summary	276
MQeMQMsgObject	278
MQeMQMsgObject dumpAllToString	278
MQeMQMsgObject dumpToString	279
MQeMQMsgObject equals	279
MQeMQMsgObject getAccountingToken	279
MQeMQMsgObject getApplicationIdData	280
MQeMQMsgObject getApplicationOriginData	281
MQeMQMsgObject getBackoutCount	281
MQeMQMsgObject getCharacterSet	282
MQeMQMsgObject getData	282
MQeMQMsgObject getCorrelationId	283
MQeMQMsgObject getEncoding	283
MQeMQMsgObject getExpiry	284
MQeMQMsgObject getFeedback	284
MQeMQMsgObject getFormat	285
MQeMQMsgObject getGroupId	285
MQeMQMsgObject getMessageFlags	286
MQeMQMsgObject getMessageId	286
MQeMQMsgObject	287
getCharacterSet	287
getMessageSequenceNumber	287
MQeMQMsgObject getMessageType	287
MQeMQMsgObject getOffset	288
MQeMQMsgObject getOriginalLength	289
MQeMQMsgObject getPersistence	289
MQeMQMsgObject getPriority	290
MQeMQMsgObject getPutApplicationName	290
MQeMQMsgObject getPutApplicationType	291
MQeMQMsgObject getPutDateTime	291
MQeMQMsgObject	292
getReplyToQueueManagerName	292
MQeMQMsgObject getReplyToQueueName	292
MQeMQMsgObject getReport	293
MQeMQMsgObject getUserId	293
MQeMQMsgObject setAccountingToken	294
MQeMQMsgObject setApplicationIdData	294
MQeMQMsgObject setApplicationOriginData	295
MQeMQMsgObject setBackoutCount	296
MQeMQMsgObject setCharacterSet	296

MQeMQMsgObject setCorrelationId	297
MQeMQMsgObject setData	297
MQeMQMsgObject setEncoding	298
MQeMQMsgObject setExpiry	298
MQeMQMsgObject setFeedback	299
MQeMQMsgObject setFormat	299
MQeMQMsgObject setGroupId	300
MQeMQMsgObject setMessageFlags	300
MQeMQMsgObject setMessageId	301
MQeMQMsgObject setMessageSequenceNumber	301
MQeMQMsgObject setMessageType	302
MQeMQMsgObject setOffset	303
MQeMQMsgObject setOriginalLength	303
MQeMQMsgObject setPersistence	304
MQeMQMsgObject setPriority	304
MQeMQMsgObject setPutApplicationName	305
MQeMQMsgObject setPutApplicationType	305
MQeMQMsgObject setPutDateTime	306
MQeMQMsgObject	306
setReplyToQueueManagerName	306
MQeMQMsgObject setReplyToQueueName	307
MQeMQMsgObject setReport	307
MQeMQMsgObject setUserId	308

Chapter 8. Classes in **com.ibm.mqe.mqbridge** **309**

MQeCharacteristicLabels	310
Constants and variables	310
MQeCharacteristicLabels	313
MQeClientConnectionAdminMsg	314
Constants and variables	314
Constructor summary	314
Method summary	314
MQeClientConnectionAdminMsg	314
MQeClientConnectionAdminMsg characteristics	315
MQeClientConnectionAdminMsg	315
getClientConnectionName	316
MQeClientConnectionAdminMsg getName	316
MQeClientConnectionAdminMsg	317
putClientConnectionName	317
MQeClientConnectionAdminMsg setName	317
MQeListenerAdminMsg	319
Constructor summary	319
Method summary	319
MQeListenerAdminMsg	319
MQeListenerAdminMsg characteristics	320
MQeListenerAdminMsg getListenerName	321
MQeListenerAdminMsg getName	321
MQeListenerAdminMsg putListenerName	322
MQeListenerAdminMsg setName	322
MQeMQBridgeAdminMsg	324
Constants and variables	324
Constructor summary	324
Method summary	324
MQeMQBridgeAdminMsg	324
MQeMQBridgeAdminMsg characteristics	325
MQeMQBridgeAdminMsg create	326
MQeMQBridgeAdminMsg getBridgeName	326
MQeMQBridgeAdminMsg getName	327
MQeMQBridgeAdminMsg delete	327
MQeMQBridgeAdminMsg putBridgeName	328

MQeMQBridgeAdminMsg setName	328
MQeMQBridgeQueue	330
Method summary	330
MQeMQBridgeQueue getMQQMgr	330
MQeMQBridgeQueue getQueueAttribute	331
MQeMQBridgeQueue getQueueManagerName	331
MQeMQBridgeQueue getQueueName	331
MQeMQBridgeQueue getRemoteQName	332
MQeMQBridgeQueueAdminMsg	333
Constants and variables	333
Constructor summary	337
Method summary	337
MQeMQBridgeQueueAdminMsg	337
MQeMQBridgeQueueAdminMsg characteristics	338
MQeMQBridges	339
Constructor summary	339
Method summary	339
MQeMQBridges	339
MQeMQBridges activate	340
MQeMQBridges close	340
MQeMQBridgesAdminMsg	342
Constants and variables	342
Constructor summary	342
Method summary	342
MQeMQBridgesAdminMsg	342
MQeMQBridgesAdminMsg characteristics	343
MQeMQBridgesAdminMsg getName	343
MQeMQBridgesAdminMsg start	344
MQeMQBridgesAdminMsg stop	345
MQeMQMgrProxyAdminMsg	347
Constructor summary	347
Method summary	347
MQeMQMgrProxyAdminMsg	347
MQeMQMgrProxyAdminMsg characteristics	348
MQeMQMgrProxyAdminMsg	
getMQQMgrProxyName	349
MQeMQMgrProxyAdminMsg getName	349
MQeMQMgrProxyAdminMsg	
putMQQMgrProxyName	349
MQeMQMgrProxyAdminMsg setName	350
MQeRunState	351
Constants and variables	351
MQeTransformerInterface	352
Method summary	352
MQeTransformerInterface activate	352
MQeTransformerInterface transform	352
Appendix. Notices	355
Trademarks	356
Bibliography	357

About this book

This book is a programming reference for the MQSeries Everyplace product and contains details of the parameters and calling sequences of the various methods within the MQSeries Everyplace class libraries. This book is intended to be used in conjunction with the MQSeries Everyplace Programming Guide and existing books or manuals on the programming languages that are used to write MQSeries Everyplace programs.

This document is continually being updated with new and improved information. For the latest edition, please see the MQSeries family library Web page at <http://www.ibm.com/software/ts/mqseries/library/>.

Who should read this book

This book is intended for programmers wanting to write MQSeries Everyplace programs for use in a pervasive computing environment.

Prerequisite knowledge

It is assumed that the reader has a working knowledge of the basic programming techniques for the language in which the MQSeries Everyplace programs are to be written

An initial understanding of the concepts of secure messaging is an advantage. If you do not have this understanding, you may find it useful to read the following MQSeries books:

- *MQSeries An Introduction to Messaging and Queuing*
- *MQSeries for Windows NT® V5R1 Quick Beginnings*

These books are available in softcopy form from Book section of the online MQSeries library. This can be reached from the MQSeries Web site, URL address <http://www.ibm.com/software/ts/MQSeries/library/>

Terms used in this book

The following terms are used throughout this book:

MQSeries

refers to the following three MQSeries Messaging product groups:

- Distributed messaging
- Host messaging
- Workstation messaging

MQSeries Everyplace

refers to the fourth MQSeries Messaging product group, pervasive messaging.

Device

A computer of any size that is running MQSeries Everyplace programs but *does not have a channel manager object installed*.

Note: For licensing purposes *device* is synonymous with *MQSeries Everyplace client*.

Gateway

A computer of any size that is running MQSeries Everyplace programs and has a *channel manager* object installed.

Note: For licensing purposes *gateway* is synonymous with *MQSeries Everyplace server*.

Chapter 1. MQSeries Everyplace classes and interfaces

The following chapters contain detailed information about the classes and interfaces supplied with MQSeries Everyplace. The classes are arranged in alphabetical order within the package in which they are delivered.

MQSeries Everyplace contains the following packages:

Note: Classes marked ** are available only in the high security version of MQSeries Everyplace Version 1.0.

com.ibm.mqe

Table 1. Classes in package com.ibm.mqe

Class name	Purpose
MQe	Used to derive other MQSeries Everyplace classes
MQeAdapter	This is the definition for the methods that all MQe adapters must provide. Any new adapters must inherit from MQeAdapter
MQeAdminMsg	Provides a base for administration messages
MQeAttribute	Contains the mechanisms to perform authentication, encryption and compression
MQeChannelListener	Used to create a listener for incoming MQSeries Everyplace logical channels
MQeChannelManager	Creates a manager for the MQSeries Everyplace logical channels
MQeEnumeration	Holds a collection of MQSeries Everyplace message objects
MQeException	Creates an MQeException object
MQeFields	Holds data items and provides mechanisms to dump and restore the data
MQeKey	Creates an MQeKey object that can be attached to and used by an attribute object
MQeMessageEvent	Creates an MQeMessageEvent object that is passed to an application when an MQeMessage event occurs
MQeMsgObject	Holds the data, or contains the necessary logic to obtain the data, to send from one MQSeries Everyplace system to another
MQeQueue	Creates an MQSeries Everyplace queue object
MQeQueueManager	Creates an MQSeries Everyplace queue manager object
MQeQueueManagerConfigure	Used to create and delete queue managers and the default queues.
MQeQueueManagerRules	Contains methods that are invoked when the queue manager performs certain operations

MQSeries Everyplace classes

Table 1. Classes in package com.ibm.mqe (continued)

Class name	Purpose
MQeQueueRule	Contains methods that are invoked when certain events occur on queues.

Table 2. Interfaces in package com.ibm.mqe

Interface name	Purpose
MQeEventLogInterface	All MQSeries Everyplace log handlers must implement this interface
MQeMessageListenerInterface	This interface must be implemented by all objects that wish to receive MQeMessage events
MQeRunListInterface	An interface that allows a list of MQSeries Everyplace applications to be passed to a queue manager when it is activated
MQeSecurityInterface	An optional interface that allows a Java® security manager to authorize or reject a call
MQeTraceInterface	All MQSeries Everyplace trace handlers must implement this interface

com.ibm.mqe.administration

Table 3. Classes in package com.ibm.mqe.administration

Class name	Purpose
MQeAdminQueueAdminMsg	Used to manage queues of type MQeAdminQueue
MQeConnectionAdminMsg	Class used to manage connections of type MQeConnectionDefinition
MQeHomeServerQueueAdminMsg	Used to manage queues of type MQeHomeServerQueue
MQeQueueAdminMsg	Used to manage MQSeries Everyplace local queues of type MQeQueue
MQeQueueManagerAdminMsg	Used to manage queue managers of type MQeQueueManager
MQeRemoteQueueAdminMsg	Used to manage remote queues of type MQeRemoteQueue
MQeStoreAndForwardQueueAdminMsg	Used to manage queues of type MQeStoreAndForwardQueue

com.ibm.mqe.attributes

Table 4. Classes in package com.ibm.mqe.attributes

Class name	Purpose
**MQe3DESCryptor	Provides mechanisms for 3DES encryption
MQeDESCryptor	Provides mechanisms for DES encryption
MQeGenDH	Creates an MQeDHk.java file from which solution unique MQeDHk class objects can be created

MQSeries Everyplace classes

Table 4. Classes in package com.ibm.mqe.attributes (continued)

Class name	Purpose
MQeLocalSecure	Provides a simple local security service
MQeLZWCompressor	Provides mechanisms for LZW compression
**MQeMARSCryptor	Provides mechanisms for MARS encryption
MQeMAttribute	Provide simple message-level protection
**MQeMTrustAttribute	Provides more advanced message-level protection
**MQeRC4Cryptor	Provides mechanisms for RC4 encryption
**MQeRC6Cryptor	Provides mechanisms for RC6 encryption
MQeRleCompressor	Provides mechanisms for Run Length encoded compression
**MQeWTLSCertAuthenticator	Provides mechanisms for mini-certificate authentication
MQeXORCryptor	Provides mechanisms for XOR encryption

com.ibm.mqe.registry

Table 5. Classes in package com.ibm.mqe.registry

Class name	Purpose
MQePrivateRegistry	Creates a private registry object that provides controlled access to a set of private and public objects
MQePrivateRegistryConfigure	Used to configure a private registry
MQePublicRegistry	Creates a public registry object that provides controlled access to a set of public objects

com.ibm.mqe.server

Table 6. Interfaces in package com.ibm.mqe.server

Interface name	Purpose
**MQeMiniCertIssuanceInterface	Used to define the way in which instances of MQeMiniCertificateServerGUI manages new Mini-Certificate issuance

com.ibm.mqe.mqemqmmessage

Table 7. Interfaces in package com.ibm.mqe.mqemqmmessage

Interface name	Purpose
MQeMQMsgObject	Used to represent an MQSeries style message object within MQSeries Everyplace

MQSeries Everyplace classes

com.ibm.mqe.mqbridge

Table 8. Classes in package com.ibm.mqe.mqbridge

Class name	Purpose
MQeCharacteristicLabels	Groups together all the <i>labels</i> used in any MQeFields object used in the bridge code
MQeClientConnectionAdminMsg	Used to encapsulate an administration command that acts on the MQeClientConnection object.
MQeListenerAdminMsg	Used to encapsulate an administration command that acts on the MQeListener object.
MQeMQBridgeAdminMsg	Used to encapsulate an administration command that acts on the MQeBridge object.
MQeMQBridgeQueue	This queue is used as the interface to the MQS bridge
MQeMQBridgeQueueAdminMsg	Used to administer an MQBridge queue
MQeMQBridges	Loads and maintains all bridge objects associated with a given MQe server"
MQeMQBridgesAdminMsg	Used to encapsulate an administration command that acts on the MQeBridges object.
MQeMQQMProxyAdminMsg	Used to encapsulate an administration command that acts on the MQeQMProxy object.
MQeRunState	Holds the <i>run state</i> of an administered object

Table 9. Interfaces in package com.ibm.mqe.mqbridge

Interface name	Purpose
MQeTransformerInterface	All classes that can transform MQMessages to MQeMsgObjects (and vice versa) must conform to this interface

Chapter 2. Classes in com.ibm.mqe

This section contains detailed information about the following MQSeries Everyplace classes and interfaces

Table 10. Classes in package com.ibm.mqe

Class name	Purpose
MQe	Used to derive other MQSeries Everyplace classes
MQeAdapter	This is the definition for the methods that all MQe adapters must provide. Any new adapters must inherit from MQeAdapter
MQeAdminMsg	Provides a base for administration messages
MQeAttribute	Contains the mechanisms to perform authentication, encryption and compression
MQeChannelListener	Used to create a listener for incoming MQSeries Everyplace logical channels
MQeChannelManager	Creates a manager for the MQSeries Everyplace logical channels
MQeEnumeration	Holds a collection of MQSeries Everyplace message objects
MQeException	Creates an MQeException object
MQeFields	Holds data items and provides mechanisms to dump and restore the data
MQeKey	Creates an MQeKey object that can be attached to and used by an attribute object
MQeMessageEvent	Creates an MQeMessageEvent object that is passed to an application when an MQeMessage event occurs
MQeMsgObject	Holds the data, or contains the necessary logic to obtain the data, to send from one MQSeries Everyplace system to another
MQeQueue	Creates an MQSeries Everyplace queue object
MQeQueueManager	Creates an MQSeries Everyplace queue manager object
MQeQueueManagerConfigure	Used to create and delete queue managers and the default queues.
MQeQueueManagerRule	Contains methods that are invoked when the queue manager performs certain operations
MQeQueueRule	Contains methods that are invoked when certain events occur on queues.

Table 11. Interfaces in package com.ibm.mqe

Interface name	Purpose
MQeEventLogInterface	All MQSeries Everyplace log handlers must implement this interface
MQeMessageListenerInterface	This interface must be implemented by all objects that wish to receive MQeMessage events

Classes in com.ibm.mqe

Table 11. Interfaces in package com.ibm.mqe (continued)

Interface name	Purpose
MQeRunListInterface	An interface that allows a list of MQSeries Everyplace applications to be passed to a queue manager when it is activated
MQeSecurityInterface	An optional interface that allows a Java security manager to authorize or reject a call
MQeTraceInterface	All MQSeries Everyplace trace handlers must implement this interface

MQe

This class is used to derive other MQSeries Everyplace classes. It contains various useful constant definitions and utility methods to assist with the programming of MQSeries Everyplace . Under normal circumstances applications classes should inherit from this class, for example 'class xxxx extends MQe'.

Package com.ibm.mqe

This class is a descendant of **Object** and implements **Serializable**

Constants

This class provides the following constants:

MQe MsgObject field names

```
public final static String Msg_CorrelID
public final static String Msg_MsgID
public final static String Msg_OriginQMgr
public final static String Msg_Priority
public final static String Msg_Time
public final static String Msg_ReplyToQ
public final static String Msg_ReplyToQMgr
public final static String Msg_Style
public final static String Msg_LockID
public final static String Msg_Resend
public final static String Msg_ExpireTime
public final static String Msg_WrapMsg
```

Message style modifiers

```
public final static int Msg_Style Datagram
public final static int Msg_Style Request
public final static int Msg_Style Reply
```

Standard queue names

```
public final static String Admin_Queue_Name
public final static String Admin_Reply_Queue_Name
public final static String Deadletter_Queue_Name
public final static String System_Default_Queue_Name
```

Options for use with MQeAdapter objects

```
public final static String MQe_Adapter_APPEND
public final static String MQe_Adapter_BINARY
public final static String MQe_Adapter_CONTENT
public final static String MQe_Adapter_FINAL
public final static String MQe_Adapter_FLUSH
public final static String MQe_Adapter_HEADER
public final static String MQe_Adapter_HEADERSP
public final static String MQe_Adapter_LENGTH
public final static String MQe_Adapter_LISTEN
public final static String MQe_Adapter_PERSIST
public final static String MQe_Adapter_READ
public final static String MQe_Adapter_RESET
public final static String MQe_Adapter_SYNC
public final static String MQe_Adapter_UNICODE
public final static String MQe_Adapter_UPDATE
public final static String MQe_Adapter_WRITE
```

Control Options for use with MQeAdapter objects

```
public final static String MQe_Adapter_ACCEPT
public final static String MQe_Adapter_FILENAME
public final static String MQe_Adapter_FILTER
public final static String MQe_Adapter_GETPERSIST
```

MQe

```
public final static String MQe_Adapter_LIST
public final static String MQe_Adapter_PULSE
public final static String MQe_Adapter_QOSINPUTS
public final static String MQe_Adapter_SECTION
public final static String MQe_Adapter_SETSOCKET
```

Status Options for use with MQeAdapter objects

```
public final static String MQe_Adapter_BYTECOUNTS
public final static String MQe_Adapter_LOCALHOST
public final static String MQe_Adapter_LINKPARM
public final static String MQe_Adapter_NETWORK
```

Quality of service field names

```
public final static String QoS_BytesRead
public final static String QoS_BytesWritten
public final static String QoS_Cost
public final static String QoS_DialRetry
public final static String QoS_DialRetryWait
public final static String QoS_Duration
public final static String QoS_ErrorRate
public final static String QoS_Errors
public final static String QoS_Jitter
public final static String QoS_Latency
public final static String QoS_Pulse
public final static String QoS_Rate
public final static String QoS_Retry
public final static String QoS_Size
public final static String QoS_TimeOut
```

Log interface log types

```
public final static byte MQe_Log_SUCCESS
public final static byte MQe_Log_ERROR
public final static byte MQe_Log_WARNING
public final static byte MQe_Log_INFORMATION
```

Exception index numbers

```
public final static int Except_UnCoded
public final static int Except_Debug
public final static int Except_NotSupported
public final static int Except_Syntax
public final static int Except_Type
public final static int Except_Command
public final static int Except_NotFound
public final static int Except_Data
public final static int Except_BadRequest
public final static int Except_Stopped
public final static int Except_Closed
public final static int Except_Duplicate
public final static int Except_NotAllowed
public final static int Except_Rule
public final static int Except_TimeOut
public final static int Except_InvalidHandle
public final static int Except_AllocationFail
public final static int Except_Chnl_Attributes
public final static int Except_Chnl_Destination
public final static int Except_Chnl_Limit
public final static int Except_Chnl_ID
public final static int Except_Chnl_Overrun
public final static int Except_Trnsport_QMgr
public final static int Except_Trnsport_Request
public final static int Except_QMgr_NotActive
public final static int Except_QMgr_InvalidQMgrName
public final static int Except_QMgr_Activated
```

```

public final static int Except_QMgr_AlreadyExists
public final static int Except_QMgr_InvalidQName
public final static int Except_QMgr_QExists
public final static int Except_QMgr_UnknownQMgr
public final static int Except_QMgr_QNotEmpty
public final static int Except_QMgr_QDoesNotExist
public final static int Except_QMgr_QInUse
public final static int Except_QMgr_WrongQType
public final static int Except_QMgr_InvalidChannel
public final static int Except_QMgr_SecureMsgDecodeFailed
public final static int Except_QMgr_NotConfigured
public final static int Except_QMgr_Busy
public final static int Except_Q_NoMsgAvailable
public final static int Except_Q_NoMatchingMsg
public final static int Except_Q_InvalidPriority
public final static int Except_Q_Full
public final static int Except_Q_MsgTooLarge
public final static int Except_Q_NotActive
public final static int Except_Q_Active
public final static int Except_Q_InvalidName
public final static int Except_Q_TargetRegistryRequired
public final static int Except_Uncontactable_DontTransmit
public final static int Except_RasDialFailed
public final static int Except_RasGetProjectionInfoFailed
public final static int Except_RasHangUpFailed
public final static int Except_Connect_AdapterNotActive
public final static int Except_Connect_InvalidDefinition
public final static int Except_Con_AlreadyExists
public final static int Except_Con_AliasAlreadyExists
public final static int Except_Con_AdapterRequired
public final static int Except_Con_InvalidName
public final static int Except_Client_Con_Not_Available
public final static int Except_Reg_NullName
public final static int Except_Reg_AlreadyExists
public final static int Except_Reg_DoesNotExist
public final static int Except_Reg_OpenFailed
public final static int Except_Reg_InvalidSession
public final static int Except_Reg_NotDefined
public final static int Except_Reg_AddFailed
public final static int Except_Reg_DeleteFailed
public final static int Except_Reg_ReadFailed
public final static int Except_Reg_UpdateFailed
public final static int Except_Reg_ListFailed
public final static int Except_Reg_SearchFailed
public final static int Except_Reg_RenameFailed
public final static int Except_Reg_ResetPINFailed
public final static int Except_Reg_CRTKeyDecFailed
public final static int Except_Reg_CRTKeySignFailed
public final static int Except_Reg_DeleteRegistryFailed
public final static int Except_Reg_AlreadyOpen
public final static int Except_Reg_NotSecure
public final static int Except_PrivateReg_BadPIN
public final static int Except_PrivateReg_ActivateFailed
public final static int Except_PrivateReg_NotOpen
public final static int Except_MiniCertReg_BadPIN
public final static int Except_MiniCertReg_ActivateFailed
public final static int Except_MiniCertReg_NotOpen
public final static int Except_PublicReg_ActivateFailed
public final static int Except_PublicReg_InvalidRequest
public final static int Except_Admin_NotAdminMsg
public final static int Except_Admin_ActionNotSupported
public final static int Except_Admin_InvalidField

```

MQe

```
public final static int Except_Authenticate
public final static int Except_S_Cipher
public final static int Except_S_InvalidSignature
public final static int Except_S_CertificateExpired
public final static int Except_S_InvalidAttribute
public final static int Except_S_MiniCertNotAvailable
public final static int Except_S_RegistryNotAvailable
public final static int Except_S_BadIntegrity
public final static int Except_S_NoPresetKeyAvailable
public final static int Except_S_MissingSection
```

Log record types

```
public final static byte MQe_Log_Success
public final static byte MQe_Log_Error
public final static byte MQe_Log.Warning
public final static byte MQe_Log.Information
public final static byte MQe_Log_Audit_Success
public final static byte MQe_Log_Audit_Failure
```

Events

```
public final static int Event_Activate
public final static int Event_Close
public final static int Event_Logon
public final static int Event_Logoff
public final static int Event_QueueManager
public final static int Event_Queue
public final static int Event_Attribute
public final static int Event_Authenticate
public final static int Event_MiniCert_Validate
public final static int Event_UserBase
```

Publically accessible variables

debugCall:

When set to **true** causes a stack trace and the contents of the MQeFields object to be written to System.err.println.

```
public static boolean debugCall = false;
```

debugExcept:

When set to **true** a stack trace is printed on System.err.println when certain Exceptions occur within the MQSeries Everyplace system (these exceptions should be handled by a try ... catch ... and would not normally be seen).

```
public static boolean debugExcept = false;
```

debugMQeExcept:

When set to **true**, causes a stack trace to be printed on System.err.println whenever an MQeException is raised.

```
public static boolean debugMQeExcept = false;
```

loader:

This is an object reference to a class loader that enables class files to be dynamically loaded from either the local system or from a remote system.

```
public static MQeLoader loader
```

MQeObjectCount:

This is an integer that contains the current number of instantiated objects that are descendants of the MQe class.

```
public static int MQeObjectCount
```

Method summary

Static methods

Method	Purpose
abbreviate	Returns either the full name or an abbreviated name for the supplied class name.
alias	Adds an alias name for a class name.
asciiToByte	Converts an ASCII string into a byte array
byteToAscii	Converts a byte array into an ASCII string
byteToHex	Converts a byte array to ASCII hex
byteToInt	Converts 4 bytes into an int value
byteToLong	Converts 8 bytes into a long value
byteToShort	Converts 2 bytes into a short value
byteToUnicode	Converts a byte array to a Unicode String
debug	Prints the current call stack to <code>System.out.println</code> . This is used for debugging purposes.
getEventLogHandler	Returns a reference to the currently active log handler or <code>null</code> .
getTraceHandler	Returns a reference to the currently active trace handler or <code>null</code> .
hexToByte	Converts ASCII hex to a byte array
intToByte	Converts an int value into 4 bytes
log	Loads data with the log handler.
mapFileDescriptor	Maps a String to a file descriptor.
setEventLogHandler	Sets the class that will handle log requests.
SetTraceHandler	Sets the class that will process trace messages.
sliceByteArray	Copies a slice out of a byte array
unicodeToByte	Converts a Unicode String to a byte array
unicodeToUTF	Converts a Unicode String to a UTF encoded byte array.
uniqueValue	Generates a unique long value for the current environment.
utfToUnicode	Converts UTF encoded byte array to a Unicode String

Non-Static methods

Method	Purpose
trace	Writes a trace message to either <code>System.out.println</code> or <code>System.err.println</code>
type	Returns a string representation of the class name

MQe abbreviate

Syntax

```
public static String abbreviate(String className, int index )
```

Description

This method resolves an abbreviated class name, or abbreviates a class name.

MQe

An abbreviated class name is of the form "nn:aaaaaa" where nn is an number and aaaaa is a string appended to the abbreviation to create a fully qualified class name.

For example, 5:RleCompressor would resolve to com.ibm.mqe.attributes.MQeRleCompressor.

Parameters

ClassName A String containing the class name or an abbreviated class name

index An integer. Current supported values are:

0 turn an abbreviated name into a fully qualified class name

1 turn a fully qualified name into an abbreviation

Return values

A String that is either a fully qualified class name or an abbreviated name

Exceptions

none

Example

```
class MyApplication
{
...
...
String abbrev = MQe.abbreviate( "com.ibm.MQe.Adapters.MQeTcpipHttpAdapater", 1 );
...
}
```

MQe alias

Syntax

```
public static void alias( String from, String to )
```

Description

This method assigns or removes an alias name for a class. The **from** parameter is the alias and the **to** parameter is the full class name. To remove an alias set the **to** parameter to *null*.

Parameters

from A String containing the alias name

to A String containing the full class name for this alias, or *null* to remove the alias

Return values

none

Exceptions

none

Example

```
class MyApplication
{
...
...
MQe.alias( "Network", "com.ibm.MQe.Adapters.MQeTcpipHttpAdapater" );
...
}
```

MQe asciiToByte

Syntax

```
public static byte[] asciiToByte( String data )
```

Description

This method converts a String into a byte array preserving only the low byte of each character.

Parameters

data	A String containing the ASCII data
-------------	------------------------------------

Return values

A byte array containing the ASCII data
--

Exceptions

none

Example

```
class MyApplication
{
    ...
    ...
    byte data[] = MQe.asciiToByte( "This is some test data" );
    ...
}
```

MQe byteToAscii

Syntax

```
public static String byteToAscii( byte data[] )
```

Description

This method converts a byte array into an ASCII string by copying the byte into the low byte of each character in the String.

Parameters

data	A byte array containing the data to be converted
-------------	--

Return values

A String containing the converted data
--

Exceptions

none

Example

```
class MyApplication
{
    ...
    ...
    String data = MQe.byteToAscii( new byte[] { 64, 65, 66, 67, 68 } );
    ...
}
```

MQe byteToHex

Syntax

```
public static String byteToHex( byte data )
```

```
public static String byteToHex( byte data[], int offset, int count )
```

MQe

Description

This method converts a byte array to a String containing the character Hex representation of the data.

Parameters

data	A byte array containing the data to be converted
offset	The starting element index of within the data array
count	The number of elements to be converted

Return values

The HEX String.

Exceptions

none

Example

```
...
String hexData = byteToHex( ByteArray );
...
```

MQe byteToInt

Syntax

```
public static int byteToInt( byte data[], int offset )
```

Description

This method converts a byte array to an integer value

Parameters

data	A byte array containing the data to be converted
offset	The starting element index of within the data array

Return values

The HEX String.

Exceptions

none

Example

```
...
int value = byteToInt( ByteArray );
...
```

MQe byteToLong

Syntax

```
public static long byteToLong( byte data[], int offset )
```

Description

This method converts a byte array to an integer value

Parameters

data	A byte array containing the data to be converted
offset	The starting element index of within the data array

Return values

The long integer value

Exceptions

none

Example

```
...
long value = byteToLong( byteArray, 0 );
...
```

MQe byteToShort**Syntax**

```
public static int byteToShort( byte data[], int offset )
```

Description

This method converts a byte array to a short integer value

Parameters

data	A byte array containing the data to be converted
offset	The starting element index of within the data array

Return values

The shortinteger value

Exceptions

none

Example

```
...
short value = byteToShort( byteArray, 0 );
...
```

MQe byteToUnicode**Syntax**

```
public static String byteToUnicode( byte data[] )
```

Description

This method converts a byte array to a Unicode string

Parameters

data	A byte array containing the data to be converted
-------------	--

Return values

The Unicode string

Exceptions

none

Example

```
...
String data = byteToUnicode( byteArray );
...
```

MQe debug**Syntax**

```
public static void debug( String data )
```

Description

Causes a stack trace to be written to `System.err.println` followed by the String data. Processing continues normally.

MQe

Parameters

data A String containing data to identify this stack print

Return values

none

Exceptions

none

Example

```
class MySampleClass extends MQe
{
    MySampleClass ( )
    {
        ...
        MQe.debug( "" );
        ...
    }
    ...
}
```

MQe getEventLogHandler

Syntax

```
Public static MQeEventLogInterface getEventLogHandler( )
```

Description

Returns the current event log handler object

Parameters

none

Return values

The log handler object or *null*

Exceptions

none

Example

```
class MySampleClass extends MQe
{
    MySampleClass ( )
    {
        ...
        MQeEventLogInterface Logger= MQe.getEventLogHandler( );
        ...
    }
    ...
}
```

MQe getTraceHandler

Syntax

```
Public static MQeTraceInterface getTraceHandler( )
```

Description

Returns the current trace handler object

Parameters

none

Return values

The trace handler object or *null*

Exceptions

none

Example

```

class MySampleClass extends MQe
{
    MySampleClass ( )
    {
        ...
        MQeTraceInterface Logger= MQe.getTraceHandler( );
        ...
    }
    ...
}
```

MQe hexToAscii**Syntax**

```
public static String hexToAscii( String data ) throws Exception
```

Description

This method converts a String containing the character Hex representation of the data to a byte array.

Parameters

data A String containing the data to be converted

Return values

A String array containing the converted data.

Exceptions

none

Example

```

...
String data = hexToAscii( "30313233343536373839" );
...
```

MQe hexToByte**Syntax**

```
public static byte[] hexToByte( String data ) throws Exception
```

Description

This method converts a String containing the character Hex representation of the data to a byte array..

Parameters

data A String containing the data to be converted

Return values

A Byte array containing the converted data.

Exceptions

none

Example

```

...
byte data[] = hexToByte( "30313233343536373839" );
...
```

MQe intToByte

Syntax

```
public static byte[] intToByte( int data )
```

Description

Convert an integer value to 4 bytes of a byte array

Parameters

data	An integer containing the data to be converted
-------------	--

Return values

A byte array containing the converted data

Exceptions

none

Example

```
...
byte data[] = intToByte( "30313233343536373839" );
...
```

MQe log

Syntax

```
public static void log( byte logType, int logNumber, Object logData)
```

Description

Sends a message to the event log routine

Parameters

logType	a byte containing the type of the log message. For example:
----------------	---

- MQe.MQE_Log_Success
- MQe.MQE_Log_Error
- MQe.MQE_Log_Warning
- MQe.MQE_Log_Information
- MQe.MQE_Log_Audit_Success
- MQe.MQE_Log_Audit_Failure

logNumber	an integer identifying the message
------------------	------------------------------------

logData	a String containing the message data to be logged
----------------	---

Return values

none

Exceptions

none

Example

```
...
try
{
    setLogHandler( new MyLogHandler( ... );
    log( MQe.MQE_LogSuccess, 123, "TEST opened" );
    ...
}
catch ( Exception e )
```

```

{
    log( MQe.MQE_LogError, 123, "TEST failed" );
}
...

```

MQe mapFileDescriptor

Syntax

```
public static void mapFileDescriptor( String filedDesc,
                                     Object newDesc[] )
```

Description

Assigns an alias or nickname to a file descriptor, parameters and options.
This method is normally used internally.

Parameters

fileDesc A String containing a file descriptor

newDesc An object array containing the new filedescriptor and any parameter and option data

Return values

none

Exceptions

none

Example

```

...
MQe.MapFileDescriptor( "QMgrName", new String[] {
    "TcpipHttp:127.0.0.1:8080",
    "?Channel",
    "" } );
...
...

```

MQe setEventLogHandler

Syntax

```
public static MQeEventLogInterface setEventLogHandler(
    MQeLogInterface logObj )
```

Description

Returns the current event log handler object and sets the new handler so that MQe will use it. The log handler object gets control on all Log requests

Parameters

logObj A log handler object that conforms to the **MQeEventLogInterface**

Return values

The previous log handler object or *null*

Exceptions

none

Example

```

class MySampleClass extends MQe
{
    MySampleClass ( )
    {
        super( );
    }
}
```

MQe

```
        setEventLogHandler( new Examples.Log.LogToDiskFile( "ThisFile.log" ) );
        ...
    }
    ...
}
```

MQe setTraceHandler

Syntax

```
public static MQeTraceInterface setTraceHandler( MQeTraceInterface traceObj )
```

Description

Returns the current trace handler object and sets the new handler so that MQe will use it. The trace handle object gets control on all MQe.Trace method calls.

Parameters

traceObj A trace handler object that conforms to the **MQeTraceInterface**

Return values

The previous trace handler object or *null*

Exceptions

none

Example

```
class MySampleClass extends MQe
{
    MySampleClass ( )
    {
        super( );
        setTraceHandler( new MQeTraceWindow( "Window Title", null ) );
        ...
    }
    ...
}
```

MQe sliceByteArray

Syntax

```
public static byte[] sliceByteArray( byte data[],
int offset,
int length )
```

Description

This method returns an array of bytes that consists of the data starting at data[Offset] and has length number of elements.

Note: This is a copy of a portion of the **data** array

Parameters

data Source byte array

offset Starting element within Data to be copied

length Number of bytes to be copied

Return values

A byte array containing a copy of the elements from data.

Exceptions

none

Example

```

class MySampleClass extends MQe
{
    MySampleClass ( )
    {
        ...
        byte data[] = { (byte) 1, (byte) 2, (byte) 3, (byte) 4, (byte) 5, };
        byte temp[] = sliceByteArray( data, 1, 3 );
        ...
    }
    ...
}
```

MQe trace**Syntax**

```

public void trace( String msg )
public void trace(int msgNumber, long insert)
public void trace( int msgNumber, Object insert )
```

Description

Sends a message to the trace routine

Parameters

msg A String containing a prefix character and the message.
The prefix byte consists of:

- " " user message
- "I" Information message
- "W" Warning message
- "E" Error message
- "S" Security message
- "D" Debug message
- "_" user message
- "i" Information message
- "w" Warning message
- "e" Error message
- "s" Security message
- "d" Debug message

msgNumber An integer containing the number of the message to be displayed. The message must have previously been added using the **MQeTrace.addMessage** method. The message number must be in the range $0 \leq msgNumber \leq 32767$.

insert Either an integer value or an Object of type String or String[] that is inserted into the point in message template where there is an insert identifier (see the Trace example for details).

Return values

none

Exceptions

MQe

IOException I/O error occurred

Example

```
...
{
...
trace( "I:Information message" );
trace( 5, "Error message text" );
...
...
}
```

MQe type

Syntax

```
public String type( )
```

Description .

Returns the String name of the object.

Note: This may or may not return an abbreviated class name, see the **abbreviate** method.

Parameters

none

Return values

A String containing the name of the object

Exceptions

none

Example

```
...
MQe.MQeMsgObject object = new MQeMsgObject( );
String objectName = object.type();
...
```

MQe unicodeToByte

Syntax

```
public static byte[] unicodeToByte( String data )
```

Description

This method converts a Unicode String to a byte array

Parameters

data A byte array containing the data to be converted

Return values

A Byte array containing the converted data.

Exceptions

none

Example

```
...
byte data[] = unicodeToByte( "This is a Data string" );
...
```

MQe unicodeToUTF

Syntax

```
public static byte[] unicodeToUTF( String data )
```

Description

This method converts a Unicode String to a byte array

Parameters

data A byte array containing the data to be converted

Return values

A byte array containing the converted data.

Exceptions

none

Example

```
...
byte data[] = unicodeToUTF( "This is a Data string" );
...
```

MQe uniqueValue

Syntax

```
public long uniqueValue( )
```

Description .

Returns a long value using the **System.currentTimeMillis()** call, guaranteeing that the value will not have been returned by any previous call to uniqueValue.

Parameters

none

Return values

A long integer value that is a unique number for the current environment.

Exceptions

none

Example

```
...
long number = MQe.uniqueValue( );
...
```

MQe utfToUnicode

Syntax

```
public static String utfToUnicode( byte data[] )
```

Description

This method converts a byte array containing UTF encoded Unicode to a Unicode String.

Parameters

data A byte array containing the data to be converted

Return values

The Unicode String

MQe

Exceptions

none

Example

```
...
String data = MQe.utfToUnicode( byteArray );
...
```

MQeAdapter

This is the definition for the methods that all MQSeries Everyplace adapters must provide. Any new adapters must inherit from MQeAdapter

Package com.ibm.mqe

Method summary

Method	Purpose
activate	Activates the loaded adapter
close	Used to finish with the adapter
control	Performs some adapter specific control function.
checkOption	Used within the file adapters to check for options.
equals	Performs an equality check with the adapter instance.
erase	Erases a file via the adapter.
open	Opens an adapter.
qualityOfService	Returns the qualityOfService object (an MQeFields object).
read	Reads data from the adapter.
readEOF	Reads a complete file, or until an EOF Exception occurs from the adapter.
readln	Reads data up to a new line character from an adapter.
readObject	Reads data from the adapter and return an object.
status	Requests adapter status information.
write	Writes data via an adapter.
writeln	Writes data followed by a new line character to an adapter.
WriteObject	Writes data from an object to an adapter.

MQeAdapter activate

Syntax

```
public void activate( String fileId,
                      Object parameter,
                      Object option,
                      int value1,
                      int value2 ) throws Exception
```

Description

This constructor is used to activate an adapter.

Note: This entry point is meant to be used by the MQSeries Everyplace object library not by application programs.

Parameters

fileId	Identifier of the file
parameter	Any parameters for the adapter, or <i>null</i>
options	Any options for the adapter, or <i>null</i>
value1	An integer value, or -1 to indicate not set
value2	An integer value, or -1 to indicate not set

MQeAdapter

Return values

none

Exceptions

IOException Device not operational or I/O error occurred

MQeAdapter checkOption

Syntax

1.
protected boolean checkOption(String what) throws Exception
2.
protected boolean checkOption(Object options,
String what) throws Exception

Description

This protected method is used when writing new MQSeries Everyplace adapters. The method checks for a matching option and if found will return **true**. There are two forms of the method:

1. Checks the options that were specified on the activate method
2. Checks the options that are supplied in the **options** parameter

Note: This entry point is meant to be used by descendants of MQeAdapter not by application programs.

Parameters

option Options for this operation

what A String containing the option to be checked

Return values

A boolean return code:

true The option was found

false The option was not found

Exceptions

IOException Error closing the file

MQeAdapter close

Syntax

```
public void close( Object options ) throws Exception
```

Description

To unbind from a file.

The MQeAdapter base class throws a "not supported" exception. New adapters should override this method if appropriate.

Note: This entry point is meant to be used by the MQSeries Everyplace object library not by application programs.

Parameters

options Any options for the adapter, or *null*

Return values

none

Exceptions

IOException Device not operational or I/O error occurred

MQeAdapter control**Syntax**

```
public Object control(Object options,
                      Object ctrlObj ) throws Exception
```

Description

The MQeAdapter base class throws a "not supported" exception. New adapters should override this method if appropriate.

Note: This entry point is meant to be used by the MQSeries Everyplace object library not by application programs.

Parameters

options Any options for the adapter, or *null*

ctrlObj An object used by the adapter for the control function (specific to each adapter type)

Return values

An object dependent on the adapter type or *null*.

Exceptions

IOException Device not operational or I/O error occurred

MQeAdapter equals**Syntax**

```
public boolean equals( Object item )
```

Description

This method is used to perform an equality check with this adapter.

The MQeAdapter base class compares the fileId with the supplied **item** if **item** is a string otherwise the base object equals method is called.

Note: This entry point is meant to be used by the MQSeries Everyplace object library not by application programs.

Parameters

item An Object to be compared against

Return values

A Boolean, either true or false

Exceptions

IOException Device not operational or I/O error occurred

MQeAdapter erase**Syntax**

```
public void erase( Object options ) throws Exception
```

Description

This method is used to delete an existing file.

MQeAdapter

The MQeAdapter base class throws a "not supported" exception. New adapters should override this method if appropriate.

Note: This entry point is meant to be used by the MQSeries Everyplace object library not by application programs.

Parameters

options Any options for the adapter, or *null*

Return values

none

Exceptions

IOException Device not operational or I/O error occurred

MQeAdapter open

Syntax

```
public void open( Object options ) throws Exception
```

Description

This method is used to bind to a file via the adapter.

The MQeAdapter base class throws a "not supported" exception. New adapters should override this method if appropriate.

Note: This entry point is meant to be used by the MQSeries Everyplace object library not by application programs.

Parameters

options Any options for the adapter, or *null*

Return values

none

Exceptions

IOException Device not operational or I/O error occurred

MQeAdapter qualityOfService

Syntax

```
public void qualityOfService( Object options ) throws Exception
```

Description

This method is used to get the quality of service object associated with this instance of the adapter.

Note: This entry point is meant to be used by the MQSeries Everyplace object library not by application programs.

Parameters

options Any options for the adapter, or *null*

Return values

A Quality of service object

Exceptions

none

MQeAdapter read

Syntax

```
public byte[] read( Object options,
                    int value0 ) throws Exception
```

Description

This method is used to read a record from the specified file.

The MQeAdapter base class throws a "not supported" exception. New adapters should override this method if appropriate.

Note: This entry point is meant to be used by the MQSeries Everyplace object library not by application programs.

Parameters

options	Any options for the adapter, or <i>null</i>
value0	The record number to be written or -1

Return values

A QualityOfService byte array containing the data bytes read from the file object

Exceptions

IOException	Device not operational or I/O error occurred
EOFException	Past end of file for this file

MQeAdapter readEOF

Syntax

```
public byte[] readEOF( Object options ) throws Exception
```

Description

This method is used to read the file until EOF condition is reached.

The MQeAdapter base class throws a "not supported" exception. New adapters should override this method if appropriate.

Note: This entry point is meant to be used by the MQSeries Everyplace object library not by application programs.

Parameters

options	Any options for the adapter, or <i>null</i>
----------------	---

Return values

A byte array containing the file data bytes.

Exceptions

IOException	Device not operational or I/O error occurred
--------------------	--

MQeAdapter readIn

Syntax

```
public String readIn( Object options ) throws Exception
```

Description

This method is used to read a record from the specified file.

MQeAdapter

The MQeAdapter base class throws a "not supported" exception. New adapters should override this method if appropriate.

Note: This entry point is meant to be used by the MQSeries Everyplace object library not by application programs.

Parameters

options Any options for the adapter, or *null*

Return values

A String containing the data bytes read from the file.

Exceptions

IOException Device not operational or I/O error occurred

EOFException Past end of file for this file

MQeAdapter readObject

Syntax

```
public Object readObject( Object options ) throws Exception
```

Description

This method is used to read an Object from the specified file.

The MQeAdapter base class throws a "not supported" exception. New adapters should override this method if appropriate.

Note: This entry point is meant to be used by the MQSeries Everyplace object library not by application programs.

Parameters

options Any options for the adapter, or *null*

Return values

An Object containing the data read from the file.

Exceptions

IOException Device not operational or I/O error occurred

EOFException Past end of file for this file

MQeAdapter status

Syntax

```
public Object status( Object options ) throws Exception
```

Description

This method is used to return adapter status information as a String.

The MQeAdapter base class throws a "not supported" exception. New adapters should override this method if appropriate.

Note: This entry point is meant to be used by the MQSeries Everyplace object library not by application programs.

Parameters

options Any options for the adapter, or *null*. All adapters must support as a minimum the following options:

MQe_File_NETWORK

Returns null or the network type (TCPIP for example)

MQe_File_BYTECOUNTS

Returns the number of bytes read and/or written via the adapter

Return values

A String containing the data bytes read from the file.

Exceptions

IOException Device not operational or I/O error occurred

EOFException Past end of file for this file

MQeAdapter write**Syntax**

```
public void write( Object options,
                  int value0,
                  byte data[] ) throws Exception
```

Description

This method is used to write data to the specified file.

The MQeAdapter base class throws a "not supported" exception. New adapters should override this method if appropriate.

Note: This entry point is meant to be used by the MQSeries Everyplace object library not by application programs.

Parameters

options Any options for the adapter, or *null*

value0 The record number to be written or -1

data Byte array containing the data to be written

Return values

none

Exceptions

IOException Device not operational or I/O error occurred

EOFException Past end of file for this file

MQeAdapter writeln**Syntax**

```
public void Writeln( Object options,
                     String data ) throws Exception
```

Description

This method is used to write data to the specified file.

The MQeAdapter base class throws a "not supported" exception. New adapters should override this method if appropriate.

Note: This entry point is meant to be used by the MQSeries Everyplace object library not by application programs.

Parameters

MQeAdapter

options	Any options for the adapter, or <i>null</i>
data	String containing the data to be written.
Return values	
none	
Exceptions	
IOException	Device not operational or I/O error occurred
EOFException	Past end of file for this file

MQeAdapter writeObject

Syntax

```
public void writeObject( Object options,  
                        Object data ) throws Exception
```

Description

This method is used to write an Object to the specified file.

The MQeAdapter base class throws a "not supported" exception. New adapters should override this method if appropriate.

Note: This entry point is meant to be used by the MQSeries Everyplace object library not by application programs.

Parameters

options	Any options for the adapter, or <i>null</i>
data	An Object containing the data to be written.

Return values

none

Exceptions

IOException Device not operational or I/O error occurred

EOFException Past end of file for this file

MQeAdminMsg

This class is used to create a basic MQeAdminMsg. The class extends MQeMsgObject and provides a base for administration messages. Descendants of this class are created to administer different types of resource.

Package com.ibm.mqe

This class is a descendant of **MQeMsgObject**

Constants and variables

MQeAdminMsg provides the following constants and variables in addition to those provided and inherited by MQeMsgObject:

Additional fields in the message

Action:

The administration action to perform (int)
`public final static String Admin_Action;`

Errors:

Errors resulting from action (MQeFields)
`public final static String Admin_Errors;`

MaxAttempts:

Maximum number of times request should be tried (int)
`public final static String Admin_MaxAttempts;`

Parms:

Input/Output parameters for/from the action (MQeFields). Contains the characteristics of a managed resource that the action requires or has returned as a result of the action.
`public final static String Admin_Parms;`

RC:

Result of action code (byte)
`public final static String Admin_RC;`

Reason:

Reason for failure (unicode)
`public final static String Admin_Reason;`

TargetQMgr:

The name of the target queue manager where the action is to be performed(ascii)
`public final static String Admin_TargetQMgr`

Basic types of administration actions

Create:

Create the resource
`public final static int Admin_Create;`

Delete:

Delete the resource
`public final static int Admin_Delete;`

Inquire:

Return requested characteristics of resource
`public final static int Admin_Inquire;`

InquireAll:

Return all characteristics of resource

MQeAdminMsg

```
public final static int Admin_InquireAll;
```

Update:

Update characteristics of resource

```
public final static int Admin_Update;
```

Field name of the resource to be managed (ascii)

Name: Managed resource name. This is a characteristic of the managed resource, hence the field must reside within the **Admin_Parms** field.

```
public final static String Admin_Name;
```

Java class of the managed resource (ascii)

Class: Managed resource class. This is a characteristic of the managed resource, hence the field must reside within the **Admin_Parms** field.

```
public final static String Admin_Class;
```

Return codes

Fail: Action failed - see **Reason**

```
public final static int RC_Fail;
```

Mixed:

Action was partially successful - see **Reason**

```
public final static int RC_Mixed;
```

Success:

Action was successful

```
public final static int RC_Success;
```

Constructor summary

Constructor	Purpose
MQeAdminMsg	Creates and initializes a default MQeAdminMsg

Method summary

Method	Purpose
characteristics	Returns an MQeFields object containing the characteristics of the resource
create	Sets up an administration message to run the Admin_Create action
delete	Sets up an administration message to run the Admin_Delete action
duplicate	Creates a new message of the type specified by the replyType parameter
getAction	Returns the administration action that is to be or has been performed
getErrorFields	Returns a reference to the error fields object
getFieldInError	Given a field name return any error that occurred when processing the field.
getInputFields	Returns a reference to the input fields object

Method	Purpose
getName	Gets the name of the managed resource
getOutputFields	Returns a reference to the output fields object
getRC	Returns the return code resulting from the action
getReason	Returns the reason for failure if an error occurred
getTargetQMgr	Returns the queue manager where the request is to be processed
inquire	Sets up the administration message to perform the Action_Inquire action
inquireAll	Sets up the administration message to perform the Action_InquireAll action
setAction	Sets the administration action to perform
setName	Sets the name of the resource that the action is to be performed on
setTargetQMgr	Sets the queue manager where the request is to be processed
update	Sets the administration message up to perform the Action_Update action

MQeAdminMsg

Syntax

```
public MQeAdminMsg() throws Exception
```

Description

The constructor creates and initializes a default MQeAdminMsg

Parameters

none

Return Values

none

Exceptions

java.lang.Exception	Various
----------------------------	---------

Example

```
class MyApplication
{
    MQeAdminMsg aMsg = new MQeAdminMsg();
}
```

MQeAdminMsg characteristics

Syntax

```
public MQeFields characteristics() throws Exception
```

Description

Returns an MQeFields object containing the characteristics of the resource. The complete set of field names and types for the resource can be determined from the resulting MQeFields object. (It does not contain the value of each characteristic)

Parameters

none

MQeAdminMsg

Return values

Valid characteristics of the resource

Exceptions

java.lang.Exception Various

Example

```
class MyApplication
{
    MQeFields chars = msg.characteristics();
    Enumeration fields = chars.fields()
    while ( fields.hasMoreElements() )
    {
        System.out.println( "Contains field: "+
            (String)fields.nextElement() );
    }
}
```

MQeAdminMsg create

Syntax

```
public void create( MQeFields parms ) throws Exception
```

Description

Sets up an administration message to run the Admin_Create action. Attempts to create a new managed resource with characteristics as specified in the **parms** parameter.

Parameters

parms	An MQeFields object containing name value pairs for any characteristics that require a setting different to the managed resources default setting. The name of the resource can be included in parms but can also be set with the setName method.
--------------	---

Return values

none

Exceptions

java.lang.Exception Various

Example

```
class MyApplication
{
    ...
    // Create ExampleQ
    MQeFields parms = new MQeFields();
    msg.setName( "ExampleQM", "ExampleQ" );
    parms.putUnicode( MQeQueueAdminMsg.Queue_Description,
        "a new description ..." );

    // Set the action required and its parameters
    // into the message
    msg.create( parms );
}
```

MQeAdminMsg delete

Syntax

```
public void delete( MQeFields parms ) throws Exception
```

Description

Sets up an administration message to run the Admin_Delete action.
Attempts to delete a managed resource.

Parameters

parms An MQeFields object which must contain the name of the managed resource to delete if it has not been set with the **setName** method.

Return values

none

Exceptions

java.lang.Exception Various

Example

```
class MyApplication
{
    ...
    // Delete ExampleQ
    MQeFields parms = new MQeFields();
    msg.setName( "ExampleQM", "ExampleQ" );
    msg.delete( parms );
}
```

MQeAdminMsg duplicate**Syntax**

```
public MQeFields duplicate( String replyType ) throws Exception
```

Description

Create a new message of the type specified by the **replyType** parameter. If *null*, a message that is the same type as this message is returned. All fields are duplicated with the exception of fields that constitute the unique message ID.

Note: The **MQeFields.copy** method is employed so only a shallow copy of the message is made.

Parameters

replyType The type of message to be returned or *null* if the same as this message

Return values

Duplicate message

Exceptions

ClassNotFoundException

Example

```
class MyApplication
{
    // Create a message as the same type as this one
    MQeQueueAdminMsg reply =
        (MQeQueueAdminMsg).requestMsg.duplicate( null );
}
```

MQeAdminMsg

MQeAdminMsg getAction

Syntax

```
public int getAction( )
```

Description

Returns the administration action that is to be, or has been performed

Parameters

none

Return values

Field Admin_Action from the MQeAdminMsg or Action_Unknown if not set

Exceptions

none

Example

```
class MyApplication
{
    ...
    int action = requestMsg.getAction();
    switch ( action )
    {
        case Create :
            performCreate();
            break;
        case Delete :
            performDelete();
            ...
    }
}
```

MQeAdminMsg getErrorFields

Syntax

```
public MQeFields getErrorFields()
```

Description

Returns a reference to the error fields object.

Error fields contain any errors related to subproblems that occurred when processing the action. For instance, if a request was made to update 2 characteristics and 1 request succeeds and the other fails, ErrorFields contain the details of the one that failed. The name of the field in error matches that in the Admin_Parms field.

Use the **getRC** method to check the overall result of the action.

Parameters

none

Return values

An empty MQeFields object or the Admin_Errors field from the MQeAdminMsg

Exceptions

none

Example

```
class MyApplication
{
    if ( replyMsg.getRC() != 0 )
```

```
{  
    MQeFields errs = replyMsg.getErrorFields();  
    Enumeration fields = errs.fields()  
    while ( fields.hasMoreElements() )  
    {  
        String errF = (String)fields.nextElement()  
        System.out.println( "Field: "+  
                            errF+  
                            "failed with error "+  
                            fields.getAscii( Msg_RC ) );  
    }  
}
```

MQeAdminMsg getFieldInError

Syntax

```
public String[] getFieldInError( String fieldName )
```

Description

This method is used to obtain information on individual errors after a getRC return of RC_Fail or RC_Mixed. Given a field name return any error that occurred when processing the field. If the field that was processed was an array then a corresponding string array is returned that contains the same number of elements. If the field that was processed was not an array then the returned array will only contain one element. If the field was not in error then *null* is returned.

Parameters

fieldname Name of field to test for error

Return values

A string array containing any error that occurred when processing the named field

Exceptions

none

Example

```
class MyApplication  
{  
    if ( replyMsg.getRC() != 0 )  
    {  
        String fieldName = MQeQueueAdminMsg.Queue_Priority  
        String[] errs = replyMsg.getFieldInError( fieldName );  
        if ( errs != null )  
            System.out.println( "Error setting priority"+ errs[0] )  
    }  
}
```

MQeAdminMsg getInputFields

Syntax

```
public MQeFields getInputFields()
```

Description

Returns a reference to the input fields object. The input fields object contains the input parameters required by an action.

Parameters

none

MQeAdminMsg

Return values

Reference to an MQeFields object that contains input parameters required for an action

Exceptions

none

Example

```
class MyApplication
{
    MQeFields parms = requestMsg.getInputFields()
}
```

MQeAdminMsg getMaxAttempts

Syntax

```
public int getMaxAttempts( )
```

Description

Get the maximum number of times the request should be retried in the event that the request is held up due to the resource being unavailable at the time the request is processed.

Parameters

none

Return values

Field Admin_MaxAttempts from the MQeAdminMsg is returned or a default of 1 if not set

Exceptions

none

Example

```
class MyApplication
{
    ...
    int tries = requestMsg.getMaxAttempts();
    ...
}
```

MQeAdminMsg getName

Syntax

```
public String getName( )
```

Description

Get the name of the managed resource or *null* if not set

Parameters

none

Return values

Field Admin_Name from the MQeAdminMsg or *null* if not set

Exceptions

none

Example

```
class MyApplication
{
    ...
    String name = requestMsg.getName();
    ...
}
```

MQeAdminMsg getOutputFields

Syntax

```
public MQeFields getOutputFields()
```

Description

Returns a reference to the output fields object. OutputFields contains both the input parameters of a request together with the results of the request.

Parameters

none

Return values

Results of an action

Exceptions

none

Example

```
class MyApplication
{
    MQeFields parms = replyMsg.getOutputFields()
    if (parms.contains( MQeQueueAdminMsg.desc ) )
    {
        System.out.println("Queue description: "+
            parms.getUnicode(MqeQueueAdminMsg.Desc));
    }
}
```

MQeAdminMsg getRC

Syntax

```
public int getRC( ) throws Exception
```

Description

Returns the code resulting from the action

Parameters

none

Return value

Return code.

Possible values are:

```
public final static int RC_Success;
public final static int RC_Fail;
public final static int RC_Mixed;
```

Exceptions

java.lang.Exception	Various
----------------------------	---------

Example

```
class MyApplication
{
    ...
    int rc = ReplyMsg.getRC();
```

MQeAdminMsg

```
if (rc != ReplyMsg.RC_success)
    String error = replyMsg.getReason();

}
....
```

MQeAdminMsg getReason

Syntax

```
public String getReason( )
```

Description

Returns the reason for failure if an error occurred

Parameters

none

Return values

String, typically the exception that caused the failure. If the exception is of type MQeException the string will include the MQeException code at the start of the string as "Code=nnn;"

Exceptions

none

Example

```
class MyApplication
{
    ...
    int rc = replyMsg.getRC();

    if (rc != replyMsg.RC_success)
        String error = replyMsg.getReason();

    ...
}
```

MQeAdminMsg getTargetQMgr

Syntax

```
public String getTargetQMgr( ) throws MQeException
```

Description

Returns the queue manager where the request is to be processed.

Parameters

none

Return values

Queue manager where the request is to be processed.

Exceptions

MQeException

Except_Type, "wrong field type"

Except_NotFound, Item + " not found".

Example

```
class MyApplication
{
    try
    {
        String targetQMgr = requestMsg.getTargetQMgr();
    }
    catch ( MQeException e)
```

```
{  
    System.out.println("Target queue manager not set")  
}
```

MQeAdminMsg inquire

Syntax

```
public void inquire( MQeFields parms ) throws Exception
```

Description

Sets up the administration message to perform the Action_Inquire action

Parameters

parms The names of the characteristics of the managed resource that are to be inquired on. The managed resource name can also be included in the parameters if not set via the **setName()** method.

Return values

none

Exceptions

NullPointerException

Example

```
class MyApplication  
{  
    ...  
    // Request the value of description and max queue depth  
    MQeFields parms = new MQeFields();  
    parms.putUnicode( MQeQueueAdminMsg.Queue_Description, null );  
    parms.putInt( MQeQueueAdminMsg.Queue_MaxQDepth, 0 );  
  
    // set the name of the queue to inquire on  
    msg.setName( "ExampleQM", "ExampleQ" );  
  
    // Set the action required and its parameters  
    // into the message  
    msg.inquire( parms );  
}
```

MQeAdminMsg inquireAll

Syntax

```
public void inquireAll( MQeFields parms ) throws Exception
```

Description

Sets up the administration message to perform the Action_InquireAll action. The InquireAll action returns all characteristics of the managed resource.

Parameters

parms needs to contain the name of the resource to be inquired on or *null* if the name has been set via the **setName()** method.

Return values

none

Exceptions

NullPointerException

MQeAdminMsg

Example

```
class MyApplication
{
    ...
    // set the name of the queue to inquire on
    msg.setName( "ExampleQM", "ExampleQ" );

    // Set the action required and its parameters
    // into the message
    msg.inquireAll( new MQeFields() );

}
```

MQeAdminMsg setAction

Syntax

```
public void setAction(int action )
```

Description

Sets the administration action to be performed. Sets the Admin_Action field in the MQeAdminMsg

Parameters

action	Possible values are: public final static int Action_Create; public final static int Action_Delete; public final static int Action_Inquire; public final static int Action_InquireAll; public final static int Action_Update; // additional actions can implemented in subclass
---------------	--

Return values

none

Exceptions

java.lang.Exception Various

Example

```
class MyApplication
{
    ...
    MQeAdminMsg requestMsg = new MQeAdminMsg()
    requestMsg.setAction(MQeAdminMsg.Action_Inquire);
    ...
}
```

MQeAdminMsg setName

Syntax

```
public void setName( String resourceName ) throws Exception
```

Description

Sets the name of the resource that the action is to be performed on.

Parameters

resourceName Name of the resource

Return values

none

Exceptions

java.lang.Exception Various

Example

```
class MyApplication
{
    ...
    // Delete a queue
    MQeFields parms = new MQeFields();

    // Set the action required and its parameters
    // into the message
    MQeQueueManagerAdminMsg msg = new MQeQueueManagerAdminMsg();
    msg.inquireAll( parms );
    msg.setName( "ExampleQM" );
    ...
}
```

MQeAdminMsg setTargetQMgr**Syntax**

```
public String setTargetQMgr( String targetQMgr ) throws Exception
```

Description

Sets the queue manager where the request is to be processed.

Parameters

targetQMgr Name of the queue manager that will process the request

Return values

none

Exceptions

none

Example

```
class MyApplication
{
    MQeQueueAdminMsg requestMsg = new MQeQueueAdminMsg();
    requestMsg.setTargetQMgr("ExampleQM");
    requestMsg.setName("ExampleQM", "ExampleQ" );
    requestMsg.create( new MQeFields() );
}
```

MQeAdminMsg update**Syntax**

```
public void update( MQeFields parms ) throws Exception
```

Description

Sets up the administration message to perform the Action_Update action, which attempts to update a managed resources characteristics based on those in **parms**.

Parameters

parms The characteristics that are to be updated. If the name of the resource to be managed has not been set then it can be included in parameters.

Return values

none

Exceptions

NullPointerException.

MQeAdminMsg

Example

```
class MyApplication
{
    /**
     * Setname of resource to be managed
     msg.setName( "ExampleQM", "ExampleQ" );

    // Change the value of description
    MQeFields parms = new MQeFields();
    parms.putUnicode( MQeQueueAdminMsg.Queue_Desc, "Change description ... " );

    // Set the action required and its parameters
    // into the message
    msg.update( parms );

}
```

MQeAttribute

This class is used to create an attribute object. This object contains the mechanisms to perform authentication, encryption and compression. Attribute objects can be associated with channels, queues, messages, and MQeFields objects.

Package com.ibm.mqe

This class is a descendant of **MQe**

Constructor summary

Constructor	Purpose
MQeAttribute	Constructs an MQeAttribute object

Method summary

Method	Purpose
authenticatedID	Returns a String that is the authenticated identifier
activate	Activates an MQeAttribute object
change	Used to change the characteristics of this attribute object
close	Release any resources used by this object
decodeData	Decrypt and/or decompress the supplied data
encodeData	Compress and/or encrypt the supplied data
equals	Compares the settings for one attribute object with this one
getAuthenticator	Gets the object reference to the authenticator
getCompressor	Gets the object reference to the compressor
getCryptor	Gets the object reference to the cryptor.

MQeAttribute

Syntax

1.

```
public MQeAttribute( )
```
2.

```
public MQeAttribute( MQeAuthenticator authenticator,
                     MQeCryptor cryptor,
                     MQeCompressor compressor
                   ) throws Exception
```

Description

Constructs an MQeAttribute object. There are two forms of constructor:

1. Creates an object that requires the attributes to be set with the activate method call
2. Creates a object and automatically calls the activate method

Parameters

- authenticator** An object reference to an MQeAuthenticator object
- cryptor** An object reference to an MQeCryptor object
- compressor** An object reference to an MQeCompressor object

MQeAttribute

Return values

none

Exceptions

MQeException

Various activation errors

IOException

Various IO errors depending on protocol type

Example

```
class MySampleClass
{
    ...
    MQeAttribute attribute = new MQeAttribute( null,
                                              new MQeXorCryport( ),
                                              new MQeRleCompressor( ) );
    ...
    MQeChannel channel = new MQeChannel( attribute,
                                         "HTTP://test.server.ibm.com:8080" );
    ...
}
```

MQeAttribute activate

Syntax

```
public void activate( MQeRule rule,
                      MQeAuthenticator authenticator,
                      MQeCryptor cryptor,
                      MQeCompressor compressor) throws Exception
```

Description

Activates an MQeAttribute object.

Parameters

rule	An object reference to an MQeRule object to be used by this attribute.
authenticator	An object reference to an MQeAuthenticator object
cryptor	An object reference to an MQeCryptor object
compressor	An object reference to an MQeCompressor object

Return values

none

Exceptions

MQeException

Various activation errors

IOException

Various IO errors depending on protocol type

Example

```
class MySampleClass
{
    ...
    MQeAttribute attribute = new MQeAttribute( null,
                                              new MQeXorCryport( ),
                                              new MQeRleCompressor( ) );
    ...
    MQeChannel channel = new MQeChannel( attribute,
                                         "HTTP://test.server.ibm.com:8080" );
    ...
}
```

MQeAttribute authenticatedID

Syntax

```
public String authenticatedID( )
```

Description

This method returns a String that is the authenticated id, or *null* if it is not authenticated. This is typically used on the server side of a channel if there is data or a process that is allowed to be run only by certain users.

Parameters

none

Return values

A String that is the authenticated identifier or *null*

Exceptions

none

MQeAttribute change

Syntax

```
public synchronized void change( MQeChannel channel,
                                MQeRule rule,
                                MQeAttribute attribute) throws Exception
```

Description

This method is called to change the characteristics of an attribute object. That is, to change the rule, authenticator, cryptor or compressor used by the attribute object. If the Channel parameter is not *null*, the remote end of the channel has to agree to the change of characteristics otherwise an exception is thrown.

Parameters

channel An object reference to a channel used for any communications

rule A rules object used to verify that the change is allowed.

Note: The previous rules object has to allow the new rules object.

attribute An object reference to an MQeAttribute

Return values

none

Exceptions

MQeException	Except_Rule, "Disallowed by rule"
---------------------	-----------------------------------

Depends on the authenticator, cryptor and/or the compressor used by the attribute

MQeAttribute close

Syntax

```
public void close( ) throws Exception
```

Description

Closes and releases resources used by the authenticator.

MQeAttribute

Parameters

none

Return values

none

Exceptions

MQeException

Invalid or not allowed

MQeAttribute decodeData

Syntax

```
public byte[] decodeData( MQeChannel channel,  
                         byte data[],  
                         int offset,  
                         int count ) throws Exception
```

Description

This method is called to decode (decrypt and/or decompress) the bytes referenced by **data**, **offset** and for length **count**.

Note: This method is intended for internal use and is not normally called by applications.

Parameters

channel	An object reference to the channel used to receive the encoded data or <i>null</i>
data	An object reference to a byte array containing the data to be decoded
offset	An integer index specifying the start byte in the data array
count	An integer count of the number of bytes to decode

Return values

none

Exceptions

Depends on the authenticator, cryptor and/or the compressor used by the attribute

MQeAttribute encodeData

Syntax

```
public byte[] encodeData( MQeChannel channel,  
                         byte data[],  
                         int offset,  
                         int count ) throws Exception
```

Description

Is called to encode (encrypt and/or compress) the bytes referenced by **data**, **offset** and, for length, **count**.

Note: This method is intended for internal use and is not normally called by applications.

Parameters

channel	An object reference to the channel used to transmit the encoded data or <i>null</i>
----------------	---

MQeAttribute

data	An object reference to a byte array containing the data to be encoded
offset	An integer index specifying the start byte in the data array
count	An integer count of the number of bytes to encode
Return values	
none	
Exceptions	
	Depends on the authenticator, cryptor and/or the compressor used by the attribute

MQeAttribute equals

Syntax

```
public boolean equals( Object thisItem )
```

Description

This method is called to compare **thisItem** with this attribute object for equality.

Parameters

thisItem An object reference, normally to an MQeAttribute object

Return values

A boolean value:

true implies they compare equal

false implies they are not equal

Exceptions

Depends on the authenticator, cryptor and/or the compressor used by the attribute

MQeAttribute getAuthenticator

Syntax

```
public MQeAuthenticator getAuthenticator( )
```

Description

Is called to return the object reference to the authenticator used by this attribute, or *null* if there is no authenticator.

Parameters

none

Return values

An MQeAuthenticator object reference or *null*.

Exceptions

none

MQeAttribute getCompressor

Syntax

```
public MQeCompressor getCompressor( )
```

Description

Is called to return the object reference to the compressor used by this attribute, or *null* if there is no compressor.

MQeAttribute

Parameters

none

Return values

An MQeCompressor object reference or *null*.

Exceptions

none

MQeAttribute getCryptor

Syntax

```
public MQeCryptor getCryptor( )
```

Description

Is called to return the object reference to the cryptor used by this attribute, or *null* if there is no cryptor.

Parameters

none

Return values

An MQeCryptor object reference or *null*

Exceptions

none

MQeChannelListener

Licence warning

The use of this class is subject to the following conditions:

- *If MQSeries Everyplace is purchased for use as a device (client) it may not be used to create a channel listener.*
- *The presence of a channel listener defines a gateway environment which requires a gateway (server) licence.*

This class is used to create a listener for incoming MQSeries Everyplace logical channels.

Package com.ibm.mqe

This class is a descendant of **MQe**

Constructor summary

Constructor	Purpose
MQeChannelListener	used to create a listener for incoming MQSeries Everyplace logical channels

Method summary

Method	Purpose
activate	Activates the channel listener if it was not activated by the class constructor.
setTimer	Called to set up a time-out interval for any channels accepted by this channel listener.
stop	Called to stop the channel listener accepting any new inbound requests.

MQeChannelListener

Syntax

1.
public MQeChannelListener()
2.
public MQeChannelListener (Object listener,
 String fileType,
 Object processor)

Description

Constructs an MQeChannelListener object. This is the class that handles incoming MQeChannel requests if not running under the control of a Server (e.g. WebSphere). There are two forms of the constructor:

1. With no parameters. The class is instantiated but not activated. In order to activate the class the **activate** method must be called.
2. With parameters that define:
 - The Listening adapter , for example **QNetwork::80Q**

Note: for the TCPIP adapters the **Qadapter::port_noQ** means listen

MQeChannelListener

- The file type to be used when an incoming request is accepted, for example `QNetwork:Q`
- A class instance that processes the channel requests. Normally this is an instance of **MQeChannelManager**

Parameters

listener	An object defining either an MQeAdapter object or a file descriptor string used to listen for incoming requests
fileType	A String defining the file descriptor to be used in creating a new instance of an MQeAdapter object used to read and write data for the new channel
processor	An instance of an object to be used to manage the channels, normally an instance of MQeChannelManager

Return values

none

Exceptions

none.

Example

```
class MySampleClass
{
    ...
    MQeChannelListener c1 = new MQeChannelManager( QNetwork:::8080Q,
                                                QNetwork:Q,
                                                new MQeChannelManager( ) );
    ...
}
```

MQeChannelListener activate

Syntax

```
public void activate( Object listener,
                      String fileType,
                      Object processor )
```

Description

Activates an **MQeChannelListener** object. This is normally used only if the class was instantiated using a constructor with no parameters. The parameters define:

- The Listening adapter, for example `QNetwork::80Q`

Note: For the TCPIP adapters the `Qadapter::port_noQ` means listen

- The file type to be used when an incoming request is accepted, for example `QNetwork:Q`
- A class instance that processes the channel requests. Normally this is an instance of **MQeChannelManager**

Parameters

listener	An object defining either an MQeAdapter object or a file descriptor string used to listen for incoming requests
fileType	A String defining the file descriptor to be used in creating a new instance of an MQeAdapter object used to read and write data for the new channel

MQeChannelListener

processor A instance of an object to be used to manage the channels, normally an instance of **MQeChannelManager**

Return values

none

Exceptions

none

Example

```
class MySampleClass
{
...
MQeChannelListener cl = new MQeChannelManager( );
cl.activate( QNetwork::8080Q, QNetwork::Q, new MQeChannelManager( ) );
...
}
```

MQeChannelListener setTimer

Syntax

```
public void setTimer( int interval ) throws Exception
```

Description

This method is used to set a channel time-out interval for any channels accepted by this channel listener.

Parameters

interval	An integer value in seconds of the desired time out interval
-----------------	--

Return values

none

Exceptions

MQeException	Invalid channel or not allowed
IOException	Error performing I/O operations

Example

```
class MySampleClass extends MQe
{
MQeChannelListener cl = new MQeChannelManager( "Network::8080",
"Network:",
new MQeChannelManager( ) );
...
cl.setTimer( 300 );
...
}
```

MQeChannelListener stop

Syntax

```
public void stop( )
```

Description

Used to stop the channel listener accepting any new channel requests

Parameters

none

MQeChannelListener

Return values

none

Exceptions

none.

Example

```
class MySampleClass
{
    MQeChannelListener cl = new MQeChannelManager( "Network::8080",
                                                 "Network:",
                                                 new MQeChannelManager( ) );

    ...
    cl.stop( );
    ...
}
```

MQeChannelManager

Licence warning

The use of this class is subject to the following conditions:

- *If MQSeries Everyplace is purchased for use as a device (client) it may not be used to create a channel manager.*
- *The presence of a channel manager defines a gateway environment which requires a gateway (server) licence.*

This class is used to create a manager for the MQSeries Everyplace logical channels.

Package

`com.ibm.mqe`

This class is a descendant of **MQe**.

Constructor summary

Constructor	Purpose
<code>MQeChannelManager</code>	Constructs a MQeChannelManager object.

Method summary

Method	Purpose
<code>getGlobalHashtable</code>	Called to get a reference to the Hashtable used to hold any shared objects.
<code>mapDestination</code>	Called to set up a reroute for one destination to another.
<code>numberOfChannels</code>	Called to get the number of currently active logical channels.
<code>process</code>	Called to process data (bytes) received, destined for an MQSeries Everyplace logical channel.
<code>timeOut</code>	Called to force any logical channels to be timed out if they have been idle for more than a specified interval.
<code>totalNumberOfChannels</code>	Called to get the total number of channels that have been used since the channel manager was activated.

MQeChannelManager

Syntax

```
public MQeChannel( )
```

Description

Constructs a MQeChannelManager object.

Parameters

none

Return values

none

Exceptions

none

MQeChannelManager

Examples

```
class MySampleClass
{
    ...
    MQeChannelManager cm = new MQeChannelManager( );
    ...
}
```

MQeChannelManager getGlobalHashtable

Syntax

```
public Hashtable getGlobalHashTable( )
```

Description

Returns the Global hashtable belonging to this instance of the channel manager. This table can be used to hold information that persists across channels

Parameters

none

Return Values

none

Exceptions

none

Example

```
class MySampleClass
{
    try
    {
        MQeChannelManager cm = new MQeChannelManager( );
        Hashtable table = cm.getGlobalHashtable( );
        ...
    }
    catch ( Exception e )
    {
        ...
    }
    ...
}
```

MQeChannelManager mapDestination

Syntax

```
public void mapDestination(String destination,
                           String newDestination)
```

Description

This method is used to set up a route from **destination** to **newDestination**.

Parameters

destination A string defining the destination to be remapped

newDestination

A string defining the new destination

Return values

none

Exceptions

none

Example

```

class MySampleClass
{
try
{
    MQeChannelManager cm = new MQeChannelManager( );
    cm.mapDestination( "One", "Two" );
    ...
}
catch ( Exception e )
{
}
...
}

```

MQeChannelManager numberOfChannels**Syntax**

```
public int numberOfChannels( int newLimit )
```

Description

This method returns the number of currently active channels.

Parameters

newLimit	The new maximum number of concurrent channels allowed by this channel manager, a value of 0 implies no limit
-----------------	--

Return Values

An integer value that is the number of current channels.

Exceptions

none

Example

```

...
MQeChannelManager cm = new MQeChannelManager( );
int count = cm.numberOfChannels( 0 );
...
...
```

MQeChannelManager process**Syntax**

1.
public void process(MqeAdapter adapter) throws Exception

2.
public void process(MqeAdapter adapter,
byte data[]) throws Exception

Description

There are two forms of the process method :

1. An MQeAdapter object as the only parameter. This is used to read the data to be passed on to the logical channel.
2. An MQeAdapter (or *null*) and an array of bytes. The array contains the data to be processed by the logical channel.

Parameters

adapter	An MQeAdapter object to be used for any I/O operations
----------------	---

MQeChannelManager

data A byte array containing the data to be processed

Return values

none

Exceptions

MQeException Invalid channel or not allowed

data A byte array containing the data to be processed

Example

```
class MySampleClass extends MQe
{
    try
    {
        MQeChannelManager cm = new MQeChannelManager( );
        ...
        cm.process( null, data );
        ...
    }
    catch ( Exception e )
    {
    }
    ...
}
```

MQeChannelManager timeOut

Syntax

1.

```
public void timeOut( long age )
```

2.

```
public void timeOut( MQeChannel channel, long age )
```

Description

This method is used to check all channels or one specific channel to see if they have been idle for more than **age** milliseconds. Any channels that have exceeded this time are closed

Parameters

age An interval in milliseconds. If the channel has been idle for more than this interval it is considered to have timed out, and is closed

channel A specific MQeChannel to be checked to see if it has timed out

Return Values

none

Exceptions

none

Example

```
...
cm.timeOut( 30 * 60 * 1000 );
...
```

MQeChannelManager totalNumberOfChannels

Syntax

```
public long totalNumberOfChannels( )
```

Description .

This method returns the total number of channels that have been used since the channel manager was activated.

Parameters

none

Return Values

A long integer value that is the total number of channels.

Exceptions

none

Example

```
MQeChannelManager cm = new MQeChannelManager( );  
long count = cm.totalNumberOfChannels( );  
...  
...
```

MQeEnumeration

MQeEnumeration

This class is used to hold a collection of MQSeries Everyplace message objects. It allows the messages to be enumerated in an identical manner to the standard Java Enumeration class.

Package com.ibm.mqe

Extends **java.util.Enumeration**.

Method summary

Method	Purpose
<code>getLockId</code>	Returns the lock id associated with this group of messages, if one exists.
<code>getNextMessage</code>	Returns the next message in the enumeration.
<code>getQueueManagerName</code>	Returns the name of the queue manager that owns the queue from which the messages contained in the enumeration were browsed.
<code>getQueueName</code>	Returns the name of the queue from which the messages contained in the enumeration were browsed.

MQeEnumeration getLockId

Syntax

```
public long getLockId()
```

Description

If a there is a lock id associated with the group of messages contained in this enumeration, it is returned by this method. The lock id is only set if this enumeration is the result of a **browseMessagesAndLock** operation. Otherwise this method returns a dummy value of "-1".

Parameters

none

Return Values

A long value containing the lock id of the group of messages contained within this enumeration.

Exceptions

none

Example

```
class MyMQeApplication
{
    ...
    /* Lock all msgs on this queue */
    MQeEnumeration msgEnum = QMgr.browseMessagesAndLock( null, "MyQueue",
                                                       null, null, 0, false );
    long lockId = msgEnum.getLockId(); /* get the Lock Id */
    ...
}
```

MQeEnumeration getNextMessage

Syntax

```
public MQeMsgObject getNextMessage( MQeAttribute attribute,  
                                long confirmId ) throws Exception
```

Description

This method returns the next message in the enumeration. However, the behaviour of this method is dependent upon the justUID parameter of the browse request that created this enumeration. The justUID parameter determines whether the enumeration contains just the unique ID fields of the messages matched by the browse, or all of the fields contained in each message.

If the browse request's justUID parameter is set to true, this method returns the next message in the enumeration (in this case it works identically to the `nextElement()` method).

If the browse request's justUID parameter is set to false, this method returns the message by issuing a get message command against the target queue. This causes the message to be removed from the target queue.

Use the `nextElement()` method (inherited from **java.util.Enumeration**) to return a message without removing it from the target queue.

Parameters

attribute	An MQeAttribute object used to provide message-level security. The attribute must match the attribute attached to the message returned by this method. Failure to do this may result in message loss.
confirmId	A long value denoting whether or not to use assured message delivery. A nonzero value does not remove the message from the target queue, this occurs on a subsequent confirm flow. A value of zero removes the message from the target queue immediately.

Return Values

An **MQeMsgObject** containing the next element in the enumeration

Exceptions

Except_NotSupported

Example

```
class MyMQeApplication  
{  
    ...  
    MQeEnumeration msgEnum = null;  
    msgEnum = qmgr/browseMessages( "RemoteQMgr", "RemoteQueue", null, null,  
                                    false );  
    while( msgEnum.hasMoreElements() )  
    {  
        /* get message */  
        MQeMsgObject msg = msgEnum.getNextMessage( null, MQe.uniqueValue() );  
        /* confirm get */  
        qmgr/confirmGetMessage( msgEnum.getQueueManagerName(),  
                               msgEnum.getQueueName(),  
                               msg.getMsgUIDFields() );  
    }  
    ...  
}
```

MQEnumeration

MQEnumeration getQueueManagerName

Syntax

```
public String getQueueManagerName()
```

Description

This method returns the name of the queue manager that owns the queue from which the messages contained in the enumeration were browsed.

Parameters

none

Return Values

A String containing the name of the queue manager that owns the queue from which these messages were browsed.

Exceptions

none

Example

```
class MyMQeApplication
{
    ...
    MQEnumeration msgEnum = null;
    msgEnum = qmgr/browseMessages( "RemoteQMgr", "RemoteQueue", null, null,
                                    false );
    while( msgEnum.hasMoreElements() )
    {
        /* get message */
        MQeMsgObject msg = msgEnum.getNextMessage( null, MQe.uniqueValue() );
        /* confirm get */
        qmgr.confirmGetMessage( msgEnum.getQueueManagerName(),
                               msgEnum.getQueueName(), msg.getMsgUIDFields() );
        ...
    }
}
```

Related functions

[getQueueName](#)

MQEnumeration getQueueName

Syntax

```
public String getQueueName()
```

Description

This method returns the name of the queue from which the messages contained in the enumeration were browsed

Parameters

none

Return Values

A String containing the name of the queue from which these messages were browsed.

Exceptions

none

Example

```
class MyMQeApplication
{
    ...
    MQEnumeration msgEnum = null;
    msgEnum = qmgr/browseMessages( "RemoteQMgr", "RemoteQueue", null, null,
                                    false );
```

MQeEnumeration

```
while( msgEnum.hasMoreElements() )  
{  
    /* get message */  
    MQeMsgObject msg = msgEnum.getNextMessage( null, MQe.uniqueValue() );  
    /* confirm get */  
    qmgr.confirmGetMessage( msgEnum.getQueueManagerName(),  
                           msgEnum.getQueueName(), msg.getMsgUIDFields() );  
    ...  
}
```

Related functions

[getQueueManagerName](#)

MQeException

MQeException

This class is used to create an MQeException object.

Package com.ibm.mqe

This class is a descendant of **MQe**

Constructor summary

Constructor	Purpose
MQeException	Constructs an MQeException object.

Method summary

Method	Purpose
code	Returns the integer value of the exception

MQeException

Syntax

1.
public MQeException()
2.
public MQeException(int codeValue)
3.
public MQeException(String errorMsg)
4.
public MQeException(int codeValue, String errorMsg)

Description

Constructs an MQeException object. There are five forms of constructor:

1. Creates an object that has a **codeValue** of 0 and does not have an error message
2. Creates an object that has the specified **codeValue** and does not have an error message
3. Creates an object that has a **codeValue** of 0 and has an error message
4.
 - a. Creates an object that has the specified **codeValue** and has an error message
 - b. Creates an object that has the specified **codeValue**, has an error message and has imbedded (hidden) data

The value of the **codeValue** parameter should be one of the constants defined in the **MQe** class, for example, MQe.Except_NotFound.

Parameters

codeValue An integer value, normally one of the MQe.Except_... constants

errorMsg A String associated with the exception, and possibly displayed when the exception occurs

Return values

none

Exceptions

none

Example

```
class MySampleClass
{
...
    if ( data == null )
        throw new MQeException( MQe.Except_Data, "Data missing" );
...
}
```

MQeException code

Syntax

```
public int code( )
```

Description

This method extracts the code value of the MQeException, that is the value that was set when the exception was created.

Parameters

none

Return values

An integer

Exceptions

none

Example

```
class MySampleClass
{
...
try
{
...
}
catch ( Exception e )
{
    if ( e instanceof MQeException )
        switch (((MQeException) e).code( ))
        {
            case MQe.Except_Data:
                System.err.println( "Data format error" );
                break;
            case MQe.Except_NotFound:
                System.err.println( "Data not specified" );
                break;
        }
    else
        System.err.println( "Error:" + e.toString( ) );
}
...
```

MQeFields

MQeFields

This class is used to create a basic MQeFields object. This object is used to hold various data items and provide mechanisms to dump and restore these field items to or from a byte array.

Fields items are assigned a character name at the time they are added to the Fields object. This name must:

- Be at least 1 character long
- Conform to the ASCII character set, that is characters with values $20 < \text{value} < 128$
- Must not include any of the characters {}[]#();,:"=

Note: These rules are not enforced but the results are unpredictable if they are not followed.

Package com.ibm.mqe

This class is a descendant of **MQe**

Constructor summary

Constructor	Purpose
MQeFields	Creates and initializes theMQeFields object

Method summary

Method	Purpose
contains	Verifies that the field exists within the object
copy	Copies a field or set of fields from one MQeFields object to another
dataType	Determines the data type of a field in the object
delete	Removes a field from the object
dump	Dumps the contents of the message object to a byte array
dumpedType	Returns the object type of the dumped Fields object
dumpToString	Produces a human readable representation of the contents of the Fields object
equals	Performs an equality test with another Fields object
fields	Returns an enumeration of all the fields in the object
getArrayLength	Extracts the length value of a dynamic array of field's
getArrayOfByte	Extracts a fixed size array of bytes
getArrayOfDouble	Extracts a fixed size array of double size floating point numbers
getArrayOfFloat	Extracts a fixed size array of float size floating point numbers
getArrayOfInt	Extracts a fixed size array of int size integers
getArrayOfLong	Extracts a fixed size array of long size integers
getArrayOfShort	Extracts a fixed size array of short size integers
getAscii	Extracts an Ascii string
getAsciiArray	Extracts an Ascii array of strings

Method	Purpose
<code>getAttribute</code>	Extracts the current attribute object reference
<code>getBoolean</code>	Extracts a boolean value or <code>null</code>
<code>getByte</code>	Extracts a byte value
<code>getByteArray</code>	Extracts a dynamic size array of byte values
<code>getDouble</code>	Extracts a double floating point value
<code>getDoubleArray</code>	Extracts a dynamic size array of double floating point values
<code>getFields</code>	Extracts an imbedded Fields object
<code>getFieldsArray</code>	Extracts a dynamic size array of Fields objects
<code>getFloat</code>	Extracts a float value
<code>getInt</code>	Extracts an integer
<code>getIntArray</code>	Extracts a dynamic size integer array
<code>getLong</code>	Extracts a long integer
<code>getLongArray</code>	Extracts a dynamic size long integer array
<code>getShort</code>	Extracts a short integer
<code>getShortArray</code>	Extracts a short integer array
<code>getUnicode</code>	Extracts a Unicode string
<code>getUnicodeArray</code>	Extracts a dynamic size array of Unicode strings
<code>hide</code>	Prevents a field from being used within the equals check
<code>putArrayLength</code>	Sets the length value of a dynamic array of field's
<code>putArrayOfByte</code>	Sets a fixed size array of bytes
<code>putArrayOfDouble</code>	Sets a fixed size array of double size floating point numbers
<code>putArrayOfFloat</code>	Sets a fixed size array of float size floating point numbers
<code>putArrayOfInt</code>	Sets a fixed size array of int size integers
<code>putArrayOfLong</code>	Sets a fixed size array of long size integers
<code>putArrayOfShort</code>	Sets a fixed size array of short size integers
<code>putAscii</code>	Sets a string containing ASCII characters
<code>putAsciiArray</code>	Sets a dynamic size array of strings containing ASCII characters
<code>putBoolean</code>	Sets a boolean value
<code>putByte</code>	Sets in the message data from a byte
<code>putByteArray</code>	Sets a dynamic size array of byte values
<code>putDouble</code>	Sets a double floating point value
<code>putDoubleArray</code>	Sets a dynamic size double floating-point array
<code>putFields</code>	Sets an imbedded Fields object
<code>putFieldsArray</code>	Sets an array of Fields objects
<code>putFloat</code>	Sets a float value
<code>putFloatArray</code>	Sets a dynamic size float array
<code>.putInt</code>	Sets an integer
<code>.putIntArray</code>	Sets a dynamic size integer array
<code>putLong</code>	Sets a long integer
<code>putLongArray</code>	Sets a dynamic size long integer array
<code>putShort</code>	Sets a short integer

MQeFields

Method	Purpose
putShortArray	Sets a dynamic size short integer array
putUnicode	Sets a string containing Unicode characters
putUnicodeArray	Sets a dynamic size array of strings containing Unicode characters
rename	Renames an item held within the fields object
restore	Restores the contents of a Fields object from a byte array produced by the dump method
restoreFromFile	Restores the contents of a fields object from a file in either binary or formatted ASCII
restoreFromString	Restores the contents of a Fields object from an ascii string (typically produced by a dumpToString method call)
setAttribute	Assigns an attribute object to this MQeFields
updateValue	Updates (increments or decrements) an integer type value within a Fields object

MQeFields

Syntax

1.
public MQeFields()
2.
public MQeFields(byte data[])

Description

The constructor creates and initializes the MQeFields object. There are two forms of the constructor:

1. With no parameters. This constructs an empty Fields object.
2. With a byte array. This restores a Fields object from the supplied byte array.

Note: The objects must be of the same type

Parameters

data A byte array containing a dumped Fields object

Return values

none

Exceptions

MQeException	Except_data, "data:xxxx" Except_Type, "Type: aaaa - bbbb"
---------------------	--

Example

```
class MyApplication
{
    ...
    MQeFields fields = new MQeFields( );
    ...
}
```

MQeFields contains

Syntax

```
public boolean contains( String item )
```

Description

This method verifies that a field exists within the MQeFields object

Parameters

item	The name of the item to be checked
-------------	------------------------------------

Return values

true	the field was found
-------------	---------------------

false	the field was not found
--------------	-------------------------

Exceptions

none

Example

```
class MyApplication
{
    ...
    MQeFields msg = new MQeFields( );
    msg.putAscii("Data", "This is some data" );
    ...
    if ( msg.contains( "Data" ) )
        ...
    ...
}
```

MQeFields copy

Syntax

- 1.
- 2.

```
public void copy( MQeFields from,
                  boolean replace )
public void copy( MQeFields from,
                  boolean replace,
                  String item )
```

Description

This method will copy a reference to a field (or all field's) from one Fields object to another. There are two forms:

1. Copies all fields
2. Copies an individual field

The boolean value **replace**, if set to **false**, throws an exception if the field already exists within the target Fields object, if set to **true**, it replaces the value that already exists.

Parameters

from	The MQeFields object to be used as the source of the data
replace	A boolean controlling if a field is to be replaced or not
item	The name of a single field to be copied

Return values

none

MQeFields

Exceptions

MQeException Except_Duplicate, "Duplicate: aaaa"

Example

```
class MyApplication
{
    ...
    ...
    MQeFields fields1 = new MQeFields( );
    fields1.putAscii("data", "This is some data" );
    ...
    MQeFields fields2 = new MQeFields( );
    fields2.copy(fields1, true, "data" )
    ...
}
```

MQeFields dataType

Syntax

```
public char dataType( String item )
```

Description

This method will return the data type of a field within the MQeFields object.

Parameters

item The name of the item to be checked

Return values

A character value representing the data type of the field. The predefined data types in MQeFields are:

public final static char	TypeUntyped
public final static char	TypeAscii
public final static char	TypeUnicode
public final static char	TypeBoolean
public final static char	TypeByte
public final static char	TypeShort
public final static char	TypeInt
public final static char	TypeLong
public final static char	TypeFloat
public final static char	TypeDouble
public final static char	TypeArrayElements
public final static char	TypeFields

Exceptions

MQeException Various

Example

```
class MyApplication
{
    ...
    ...
    MQeFieldsmgs = new MQeFields( );
    msg.putAscii("Data", "This is some data" );
    ...
    if ( msg.dataType( "Data" ) ==TypeInt
    ...
}
```

MQeFields delete

Syntax

```
public void delete( String item )
```

Description

This method deletes an existing field from the MQeFields object.

Parameters

item	The name of the item to be removed
-------------	------------------------------------

Return values

Exceptions

none

Example

```
class MyApplication
{
...
MQeFields msg = new MQeFields( );
msg.putAscii("Data", "This is some data" );
...
msg.delete( "Data" );
...
}
```

MQeFields dump

Syntax

1.

```
public byte[] dump( ) throws Exception
```

2.

```
public byte[] dump( boolean allowXor ) throws Exception
```

Description

This method dumps out to a byte array, the contents of this MQeFields object so that it can be restored using the restore method. There are two forms of this method:

1. With no parameter
2. With **allowXor**. If this is set to **false**, the MQeFields object is dumped to a byte array. With **allowXor** set to **true**, each field is XOR'd with a previous version (held internally) in an attempt to increase the number of bytes that have a value of 0x00 to try to improve the compression ratio.

If intelligent fields objects are to be created, that is fields that have program logic in them, then it is in the dump and restore methods that this logic should be activated. For example when just before the fields object is dumped, a data base query could be issued to get latest data, or just after a restore data could be automatically stored in a data base.

Parameters

allowXor	A boolean expression. true implies XOR the Fields, false implies do not XOR the Fields
-----------------	--

Return values

none

MQeFields

Exceptions

MQException Various

Example

```
class MyApplication
{
...
MQeFields msg = new MQeFields( );
msg.putAscii( "Data", "This is some data" );
...
byte dumpData[] = msg.dump( );
...
}
```

MQeFields dump data format

Data sent between MQSeries Everyplace environments is encoded using the following layout:

{Length Identifier Fence {Data}} {Length Identifier Fence {Data}} { ... }

Where:

Length

A variable number of bytes between 1 and 4. The length is encoded in the following manner:

The first byte has the first two bits reserved and they are used as the length of the length field:

00 = 1 byte used for length (6 bits = 0-63)

01 = 2 bytes used for length (14 bits = 0-16,383)

10 = 3 bytes used for length (22 bits = 0-4,194,303)

11 = 4 bytes used for length (30 bits = 0-1,073,741,823)

Identifier

A variable length string of bytes (each byte value must be less than 0x80) typically this would be an ASCII string. The end of the identifier is determined when a byte with 0xC0 bits set, is encountered. The identifier is subject to the following restrictions:

- Must be at least 1 character long
 - Conform the ASCII character set ($20 < \text{value} < 128$)
 - Must not include any of the characters {}, () ; , ' = "

Fence

A special byte delimiting the boundary between the identifier and the optional data item. This byte is used to contain the data type of the data item as shown in the following example:

```
/* Field mask values */
public final static char TypeFenceMask = 0x00C0;
public final static char TypeHidden = 0x0020;
public final static char TypeModifier = 0x0010;
/* Field data types */
public final static char TypeUntyped = 0x0000 | TypeFenceMask;
public final static char TypeAscii = 0x0001 | TypeFenceMask;
public final static char TypeUnicode = 0x0002 | TypeFenceMask;
public final static char TypeBoolean = 0x0003 | TypeFenceMask;
public final static char TypeByte = 0x0004 | TypeFenceMask;
public final static char TypeShort = 0x0005 | TypeFenceMask;
public final static char TypeInt = 0x0006 | TypeFenceMask;
public final static char TypeLong = 0x0007 | TypeFenceMask;
public final static char TypeFloat = 0x0008 | TypeFenceMask;
```

```

public final static char TypeDouble      = 0x0009 | TypeFenceMask;
public final static char TypeArrayElements = 0x000A | TypeFenceMask;
public final static char TypeFields       = 0x000B | TypeFenceMask;

```

The order of the items within the data stream is not significant.

```

08 5349 C7 1122334455 102 44 D3 103 5349 D6 14603 534443 C4
6E01534FE32054E16....

```

Savings in number of bytes transmitted

Using this data structure savings in the byte stream are achieved by:

- Reserving two bits in the first length byte allowing variable length lengths.
Variable length Length code (1 to 4 bytes) i.e. only the required length bytes are sent.
- Leading 0x00s and 0xFF's of integer values are not placed in the output stream.
If a value is "0" or "-1" no data bytes are sent.
- All the data items are typed and can be type checked at the receiving end.
- Null items are still transmitted (with data type), hence the presence of the item can be checked at the receiving end.
- Using the Fence byte for 3 distinct functions
 1. Delimiting the Identifier
 2. Defining the data type
 3. Defining that the data is:
 - *null* (no Data bytes)
 - positive or negative (possibly no Data bytes sent, 0 or -1)
 - boolean true or false (no Data bytes sent)

Note: Further savings can be achieved by compressing the data. The compressors can usually be helped by performing an XOR with a previous byte stream producing repeated bytes of 0x00, but because of the variable nature of these fields and the order of the fields may change a simple XOR will not produce the desired effect. However an "intelligent" XOR that worked on a field by field basis produces repeated 0x00 bytes thus assisting the compressor

MQeFields dumpToString

Syntax

```
public String dumpToString( String template )
```

Description

This method dumps the Fields object in human readable form and returns the data as a String.

Parameters

template	A String template used when formatting the output. The template should have 3 insert sequences '#n'. That is: <ul style="list-style-type: none"> • "#0" for the data type, • "#1" for the Field name • "#2" for the field value.
-----------------	---

Example:

```
"Sample template -Name=#1, Type=#0, Value=#2"
```

MQeFields

Return values

A String containing a representation of the Fields object

Exceptions

Various conversion Exceptions

Examples

```
class MyApplication
{
    ...
    MQeFields fields = new MQeFields();
    fields.putBoolean( "tb", true );
    ...
    fields.putLong( "ml", -1 );
    System.out.println( fields.dumpToString( "Test1.obj (#0)\t#1\t=#2\r\n" ) );
    ...
}
```

Example output from the dumpToString call:

```
Test1.obj  (long)    la  =[2] { 0000000000000001, FFFFFFFFFFFFE }
Test1.obj  (boolean) tb  =true Test1.obj  (byte) ba =[5] { 01, FE, FD, 04, 05 }
Test1.obj  (long)    pl  =101
Test1.obj  (ascii)   A   =Ascii string
Test1.obj  (ascii)   nA  =null
Test1.obj  (unicode) U   =Unicode string
Test1.obj  (byte)    mb  =[1] { FE }
Test1.obj  (int)     i   =1
Test1.obj  (byte)    pb  =[1] { 02 }
Test1.obj  (boolean) fb  =false
Test1.obj  (short)   ms  =-1
Test1.obj  (short)   sa  =[5] { 0001, FFFE, FFFD, 0004, 0005 }
Test1.obj  (short)   ps  =0
Test1.obj  (int)     ia  =[3] { 00000001, FFFFFFFE, FFFFFFFD }
Test1.obj  (long)    ml  =-1
```

MQeFields dumpedType

Syntax

```
public static String dumpedType( byte data[] ) throws Exception
```

Description

This method will return an enumeration object that contains all the field names within the object.

Parameters

data	A byte array containing a dump of a fields object
-------------	---

Return values

A String containing the class name of the object that was dumped

Exceptions

MQeException	Except_Data,, "Data:aaa"
---------------------	--------------------------

Example

```
class MyApplication
{
    ...
    MQeFields fields = new MQeFields();
    fields.putAscii( "Data", "This is some data" );
    byte dumpdata[] = fields.dump(fields.dump( ));
```

```
...
String ObjType = fields.dumpedType(objType = MQeFields.dumpedType( dumpdata );
...
}
```

MQeFields equals

Syntax

```
public boolean equals( MQeFields match ) throws Exception
```

Description

The default method requires an MQeFields (or descendent) as a parameter, each field in the parameter object is checked for equality with a matching field in the MQeFields.

Override this method to provide a different type of equality check.

Parameters

match	An MQeFields object containing the items to be used for the comparison.
--------------	---

Return values

true if the there is a match otherwise **false**

Exceptions

MQeException	Except_Type,"wrong field type"
MQeException	Except_NotFound, item + " not found"

Example

```
class MyApplication
{
...
MQeFields fields = new MQeFields( );
fields.putAscii( "Data1", "This is some data" );
fields.putAscii( "Data2", "This is more data" );
...
MQeFields test = new MQeFields( );
test.putAscii( "Data1", "This is some data" );
...
if ( fields.equals( test ) )
...
else
...
}
```

MQeFields fields

Syntax

```
public Enumeration fields( )
```

Description

This method returns an enumeration object that contains all the field names within the object.

Parameters

none

Return values

An enumeration object containing the field names

Exceptions

MQeFields

MQeException	Except_Type, "wrong field type"
MQeException	Except_NotFound, item + " not found"

Example

```
class MyApplication
{
...
MQeFields fields = new MQeFields( );
fields.putAscii( "data", "This is some data" );
...
Enumeration names = fields.fields( );
...
}
```

MQeFields getArrayLength

Syntax

```
public int getArrayLength( String item ) throws Exception
```

Description

This extracts the dynamic array length of the specified item. An exception is thrown if there is no data or it is of the wrong data type.

Parameters

item The name of the item to be retrieved

Return values

An array of strings containing the ASCII data from the message

Exceptions

MQeException	Except_Type, "wrong field type"
	Except_NotFound, item + " not found"

Example

```
class MyApplication
{
...
MQeFields fields = new MQeFields( dumpData );
...
int numElements = fields.getArrayLength( "Data" );
...
}
```

MQeFields getArrayOfByte

Syntax

```
public byte[] getArrayOfByte( String item ) throws Exception
```

Description

This extracts an array of bytes data from the Fields object. An exception is thrown if there is no data or it is of the wrong data type.

Parameters

item The name of the item to be retrieved

Return values

A byte array containing the data from the message

Exceptions

MQeException	Except_Type, "wrong field type"
---------------------	---------------------------------

Except_NotFound, item + " not found"

Example

```
class MyApplication
{
...
MQeFields fields = new MQeFields( );
fields.restore( dumpData );
...
byte data[] = fields.getArrayOfByte( "Data" );
...
}
```

MQeFields getArrayOfDouble**Syntax**

```
public double[] getArrayOfDouble( String item ) throws Exception
```

Description

This extracts an array of double floating point numbers from the Fields object. An exception is thrown if there is no data or it is of the wrong data type.

Parameters

item	The name of the item to be retrieved
------	--------------------------------------

Return values

An array of double values

Exceptions

MQeException	Except_Type, "wrong field type" Except_NotFound, item + " not found"
---------------------	---

Example

```
class MyApplication
{
...
MQeFields fields = new MQeFields( );
fields.restore( dumpData );
...
double data[] = fields.getArrayOfDouble( "Data" );
...
}
```

MQeFields getArrayOfFloat**Syntax**

```
public float[] getArrayOfFloat( String item ) throws Exception
```

Description

This extracts an array of floating point numbers from the Fields object. An exception is thrown if there is no data or it is of the wrong data type.

Parameters

item	The name of the item to be retrieved
------	--------------------------------------

Return values

An array of float values

Exceptions

MQeException	Except_Type, "wrong field type"
---------------------	---------------------------------

MQeFields

Except_NotFound, item + " not found"

Example

```
class MyApplication
{
...
MQeFields fields = new MQeFields( );
fields.restore( dumpData );
...
float data[] = fields.getArrayOfFloat( "Data" );
...
}
```

MQeFields getArrayOfInt

Syntax

```
public int[] getArrayOfInt( String item ) throws Exception
```

Description

This extracts an array of int length integer numbers from the Fields object.
An exception is thrown if there is no data or it is of the wrong data type.

Parameters

item The name of the item to be retrieved.

Return values

An array of int values

Exceptions

MQeException Except_Type, "wrong field type"
Except_NotFound, item + " not found"

Example

```
class MyApplication
{
...
MQeFields fields = new MQeFields( );
fields.restore( dumpData );
...
int data[] = fields.getArrayOfInt( "Data" );
...
}
```

MQeFields getArrayOfLong

Syntax

```
public long[] getArrayOfLong( String item ) throws Exception
```

Description

This extracts an array of long length integer numbers from the Fields object. An exception is thrown if there is no data or it is of the wrong data type.

Parameters

item The name of the item to be retrieved

Return values

An array of long values

Exceptions

MQeException	Except_Type, "wrong field type" Except_NotFound, item + " not found"
---------------------	---

Example

```
class MyApplication
{
...
MQeFields fields = new MQeFields( );
fields.restore( dumpData );
...
long data[] = fields.getArrayOfLong( "Data" );
...
}
```

MQeFields getArrayOfShort**Syntax**

```
public short[] getArrayOfShort( String item ) throws Exception
```

Description

This extracts an array of short length integer numbers from the Fields object. An exception is thrown if there is no data or it is of the wrong data type.

Parameters

item	The name of the item to be retrieved
-------------	--------------------------------------

Return values

An array of short values

Exceptions

MQeException	Except_Type, "wrong field type" Except_NotFound, item + " not found"
---------------------	---

Example

```
class MyApplication
{
...
MQeFields fields = new MQeFields( );
fields.restore( dumpData );
...
short data[] = fields.getArrayOfShort( "Data" );
...
}
```

MQeFields getAscii**Syntax**

```
public String getAscii( String item ) throws Exception
```

Description

This extracts the ASCII data from the Fields object and returns it as a string. An exception is thrown if there is no data or it is of the wrong data type.

Note: The **item** parameter is a java Unicode string, which must only contain character codes that appear in the invariant part of the Ascii code pages (characters with values 20 < value < 128, not including {}[]#();";=). If you attempt to pass variant character codes, these codes are subject to translations between machines when different

MQeFields

codepages are used to manipulate the data, possibly resulting in unpredictable results. If you wish to pass variant character codes in an MQSeries Everyplace message, we recommend you use the `putArrayOfByte()` method and handle your own codepage translations between machines , or `putUnicode()` method where no codepage translations is required.

Parameters

item The name of the item to be retrieved

Return values

A string containing the ASCII data from the message

Exceptions

MQeException	Except_Type, "wrong field type" Except_NotFound, item + " not found"
---------------------	---

Example

```
class MyApplication
{
...
MQeFields fields = new MQeFields();
fields.restore( dumpData );
...
String data = fields.getAscii( "Data" );
...
}
```

MQeFields getAsciiArray

Syntax

```
public String[] getAsciiArray( String item ) throws Exception
```

Description

This extracts the ASCII data (see note in “MQeFields getAscii” on page 81) from the Fields object and returns it as an array of strings. An exception is thrown if there is no data or it is of the wrong data type.

Parameters

item The name of the item to be retrieved

Return values

An array of strings containing the ASCII data from the message

Exceptions

MQeException	Except_Type, "wrong field type" Except_NotFound, item + " not found"
---------------------	---

Example

```
class MyApplication
{
...
MQeFields fields = new MQeFields( );
fields.restore( dumpData );
...
String data[] = fields.getAsciiArray( "Data" );
...
}
```

MQeFields getAttribute

Syntax

```
public MQeAttribute getAttribute( )
```

Description

This method returns an MQeAttribute object reference associated with this Fields object, or *null* if there is no attribute.

Parameters

none

Return values

An MQeAttribute object reference

Exceptions

none

Example

```
class MyApplication
{
    ...
    MQeAttribute thisAttribute = fields.getAttribute( );
    ...
}
```

MQeFields getBoolean

Syntax

```
public boolean getBooean( String item ) throws Exception
```

Description

This extracts a boolean value from the Fields object. An exception is thrown if there is no data or it is of the wrong data type.

Parameters

item	The name of the item to be retrieved
------	--------------------------------------

Return values

A boolean set to either **true** or **false**

Exceptions

MQeException	Except_Type, "wrong field type" Except_NotFound, item + " not found"
---------------------	---

Example

```
class MyApplication
{
    ...
    MQeFields fields = new MQeFields( );
    fields.restore( dumpData );
    ...
    boolean data = fields.getBoolean( "Data" );
    ...
}
```

MQeFields getByte

Syntax

```
public byte getByte( String item ) throws Exception
```

MQeFields

Description

This extracts a byte of data from the Fields object. An exception is thrown if there is no data or it is of the wrong data type.

Parameters

item The name of the item to be retrieved

Return values

A byte containing the data from the field

Exceptions

MQeException Except_Type, "wrong field type"
Except_NotFound, item + " not found"

Example

```
class MyApplication
{
    ...
    MQeFields fields = new MQeFields( );
    fields.restore( dumpData );
    ...
    byte data = fields.getByte( "Data" );
    ...
}
```

MQeFields getByteArray

Syntax

```
public byte[] getByteArray( String item ) throws Exception
```

Description

This extracts the byte data from the Fields object and returns it as a byte array. An exception is thrown if there is no data or it is of the wrong data type.

Parameters

item The name of the item to be retrieved

Return values

A byte array containing the data from the field

Exceptions

MQeException Except_Type, "wrong field type"
Except_NotFound, item + " not found"

Example

```
class MyApplication
{
    ...
    MQeFields fields = new MQeFields( );
    fields.restore( dumpData );
    ...
    byte data[] = fields.getByteArray( "Data" );
    ...
}
```

MQeFields getDouble

Syntax

```
public double getDouble( String item ) throws Exception
```

Description

This extracts a double length floating point value from the Fields object.
An exception is thrown if there is no data or it is of the wrong data type.

Parameters

item The name of the item to be retrieved

Return values

A double containing the value from the field

Exceptions

MQeException	Except_Type, "wrong field type" Except_NotFound, item + " not found"
---------------------	---

Example

```
class MyApplication
{
...
MQeFields fields = new MQeFields( );
fields.restore( dumpData );
...
double data = fields.getDouble( "Data" );
...
}
```

MQeFields getDoubleArray

Syntax

```
public byte[] getDoubleArray( String item ) throws Exception
```

Description

This extracts a dynamic array of double length floating point values from the Fields object and returns it as an array of doubles. The length of the array is determined by the ArrayLength value for this item. An exception is thrown if there is no data or it is of the wrong data type.

Parameters

item The name of the item to be retrieved

Return values

A byte array containing the data from the field

Exceptions

MQeException	Except_Type, "wrong field type" Except_NotFound, item + " not found"
---------------------	---

Example

```
class MyApplication
{
...
MQeFields fields = new MQeFields( );
fields.restore( dumpData );
...
double data[] = fields.getDoubleArray( "Data" );
...
}
```

MQeFields

MQeFields getFields

Syntax

```
public MQeFields getFields( String item ) throws Exception
```

Description

This extracts a Fields object item from the Fields object. An exception is thrown if there is no data or it is of the wrong data type.

Parameters

item The name of the item to be retrieved

Return values

A double containing the value from the field

Exceptions

MQeException	Except_Type, "wrong field type"
	Except_NotFound, item + " not found"

Example

```
class MyApplication
{
    ...
    MQeFields fields = new MQeFields( );
    fields.restore( dumpData );
    ...
    MQeFields data = fields.getFields( "Data" );
    ...
}
```

MQeFields getFieldsArray

Syntax

```
public MQeFields[] getFieldsArray( String item ) throws Exception
```

Description

This extracts a dynamic array of MQeFields objects from the Fields object and returns it as an array. The length of the array is determined by the ArrayLength value for this item. An exception is thrown if there is no data or it is of the wrong data type.

Parameters

item The name of the item to be retrieved

Return values

An array containing the MQeFields objects

Exceptions

MQeException	Except_Type, "wrong field type"
	Except_NotFound, item + " not found"

Example

```
class MyApplication
{
    ...
    MQeFields fields = new MQeFields( );
    fields.restore( dumpData );
```

```
...
MQeFields data[] = fields.getFieldsArray( "Data" );
...
}
```

MQeFields getFloat

Syntax

```
public float getFloat( String item ) throws Exception
```

Description

This extracts a float value item from the Fields object. An exception is thrown if there is no data or it is of the wrong data type.

Parameters

item The name of the item to be retrieved

Return values

A float containing the value from the field

Exceptions

MQeException	Except_Type, "wrong field type" Except_NotFound, item + " not found"
---------------------	---

Example

```
class MyApplication
{
...
MQeFields fields = new MQeFields( );
fields.restore( dumpData );
...
float data = fields.getFloat( "Data" );
...
}
```

MQeFields getFloatArray

Syntax

```
public float[] getFloatArray( String item ) throws Exception
```

Description

This extracts a dynamic array of float values from the Fields object and returns it as an array. The length of the array is determined by the ArrayLength value for this item. An exception is thrown if there is no data or it is of the wrong data type.

Parameters

item The name of the item to be retrieved

Return values

An array containing the float values

Exceptions

MQeException	Except_Type, "wrong field type" Except_NotFound, item + " not found"
---------------------	---

Example

```
class MyApplication
{
...
}
```

MQeFields

```
MQeFields fields = new MQeFields( );
fields.restore( dumpData );
...
float data[] = fields.getFloatArray( "Data" );
...
```

MQeFields getInt

Syntax

```
public int getInt( String item ) throws Exception
```

Description

This extracts an int length integer value item from the Fields object. An exception is thrown if there is no data or it is of the wrong data type.

Parameters

item The name of the item to be retrieved

Return values

An int containing the value from the field

Exceptions

MQeException	Except_Type, "wrong field type" Except_NotFound, item + " not found"
---------------------	---

Example

```
class MyApplication
{
...
MQeFields fields = new MQeFields( );
fields.restore( dumpData );
...
int data = fields.getInt( "Data" );
...
}
```

MQeFields getIntArray

Syntax

```
public int[] getIntArray( String item ) throws Exception
```

Description

This extracts a dynamic array of int length integer values from the Fields object and returns it as an array. The length of the array is determined by the ArrayLength value for this item. An exception is thrown if there is no data or it is of the wrong data type.

Parameters

item The name of the item to be retrieved

Return values

An array containing the int values

Exceptions

MQeException	Except_Type, "wrong field type" Except_NotFound, item + " not found"
---------------------	---

Example

```

class MyApplication
{
...
MQeFields fields = new MQeFields( );
fields.restore( dumpdDta );
...
int data[] = fields.getIntArray( "Data" );
...
}

```

MQeFields getLong

Syntax

```
public long getLong( String item ) throws Exception
```

Description

This extracts an long length integer value item from the Fields object. An exception is thrown if there is no data or it is of the wrong data type.

Parameters

item	The name of the item to be retrieved
-------------	--------------------------------------

Return values

A long containing the value from the field

Exceptions

MQeException	Except_Type, "wrong field type" Except_NotFound, item + " not found"
---------------------	---

Example

```

class MyApplication
{
...
MQeFields fields = new MQeFields( );
fields.restore( dumpData );
...
long data = fields.getLong( "Data" );
...
}

```

MQeFields getLongArray

Syntax

```
public long[] getLongArray( String item ) throws Exception
```

Description

This extracts a dynamic array of long length integer values from the Fields object and returns it as an array. The length of the array is determined by the ArrayLength value for this item. An exception is thrown if there is no data or it is of the wrong data type.

Parameters

item	The name of the item to be retrieved
-------------	--------------------------------------

Return values

An array containing the long values

Exceptions

MQeException	Except_Type, "wrong field type" Except_NotFound, item + " not found"
---------------------	---

MQeFields

Example

```
class MyApplication
{
...
MQeFields fields = new MQeFields( );
fields.restore( dumpData );
...
long data[] = fields.getLongArray( "Data" );
...
}
```

MQeFields getShort

Syntax

```
public short getShort( String item ) throws Exception
```

Description

This extracts a short length integer value item from the Fields object. An exception is thrown if there is no data or it is of the wrong data type.

Parameters

item The name of the item to be retrieved

Return values

A short integer containing the value from the field

Exceptions

MQeException	Except_Type, "wrong field type"
	Except_NotFound, item + " not found"

Example

```
class MyApplication
{
...
MQeFields fields = new MQeFields( );
fields.restore( dumpData );
...
short data = fields.getShort( "Data" );
...
}
```

MQeFields getShortArray

Syntax

```
public short[] getShortArray( String item ) throws Exception
```

Description

This extracts a dynamic array of short length integer values from the Fields object and returns it as an array. The length of the array is determined by the ArrayLength value for this item. An exception is thrown if there is no data or it is of the wrong data type.

Parameters

item The name of the item to be retrieved

Return values

An array containing the short values

Exceptions

MQeException	Except_Type, "wrong field type"
---------------------	---------------------------------

Except_NotFound, item + " not found"

Example

```
class MyApplication
{
...
MQeFields fields = new MQeFields( );
fields.restore( dumpData );
...
short data[] = fields.getShortArray( "Data" );
...
}
```

MQeFields getUnicode**Syntax**

```
public String getUnicode( String item ) throws Exception
```

Description

This extracts the Unicode data from the message object and returns it as a string. An exception is thrown if there is no data or it is of the wrong data type.

Parameters

item	The name of the item to be retrieved
-------------	--------------------------------------

Return values

A string containing the Unicode data from the message

Exceptions

MQeException	Except_Type, "wrong field type" Except_NotFound, item + " not found"
---------------------	---

Example

```
class MyApplication
{
...
MQeFields fields = new MQeFields( );
fields.restore( dumpData );
...
String data = fields.getUnicode( "Data" );
...
}
```

MQeFields getUnicodeArray**Syntax**

```
public String[] getUnicodeArray( String item ) throws Exception
```

Description

This extracts the Unicode data from the message object and returns it as an array of strings. An exception is thrown if there is no data or it is of the wrong data type.

Parameters

item	The name of the item to be retrieved
-------------	--------------------------------------

Return values

An array of strings containing the Unicode data from the message
--

Exceptions

MQeFields

MQeException

Except_Type, "wrong field type"
Except_NotFound, item + " not found"

Example

```
class MyApplication
{
...
MQeFields fields = new MQeFields( );
fields.restore( dumpData );
...
String data[] = fields.getUnicodeArray( "Data" );
...
}
```

MQeFields hide

Syntax

```
public void hide( String item, boolean state ) throws Exception
```

Description

This sets an item within the Fields object to be included (**true**) or not included (**false**), when an equals test is performed against the Fields object

Parameters

item	The name of the item to be hidden/included.
state	hide (true) or include (false)

Return values

none

Exceptions

MQeException

Except_NotFound, item + " not found"

Example

```
class MyApplication
{
...
MQeFields fields = new MQeFields( dumpData );
...
fields.hide( "Data" );
if ( OldFields.equals( fields ) )
...
...
}
```

MQeFields putArrayLength

Syntax

```
public void putArrayLength( String item, int length ) throws Exception
```

Description

This sets the dynamic array length of the specified item.

Parameters

item	The name of the item to be set
length	The length of the array in number of elements

Return values

none

Exceptions

none

Example

```
class MyApplication
{
    ...
    MQeFields fields = new MQeFields( dumpData );
    ...
    fields.putArrayLength( "Data", 5 );
    ...
}
```

MQeFields putArrayOfByte**Syntax**

```
public void putArrayOfByte( String item, byte data ) throws Exception
```

Description

This method sets the data in the message object for the supplied byte array.

Parameters

item The name of the item to be set

data A byte array containing the data to be set into the message object

Return values

none

Exceptions

MQeException	Various
---------------------	---------

Example

```
class MyApplication
{
    ...
    MQeFields fields = new MQeFields( );
    ...
    fields.putArrayOfByte( "Data", new byte[] { 1, 2, 3, 4 } );
    ...
}
```

MQeFields putArrayOfDouble**Syntax**

```
public void putArrayOfDouble( String item, double data[] )
    throws Exception
```

Description

This sets an array of double floating point numbers into the Fields object.

Parameters

item The name of the item to be set

data The array of double values to be copied into the Fields object

Return values

none

Exceptions

none

MQeFields

Example

```
class MyApplication
{
    ...
    MQeFields fields = new MQeFields( );
    fields.restore( dumpData );
    ...
    double data[] = fields.putArrayOfDouble( "Data" );
    ...
}
```

MQeFields putArrayOfFloat

Syntax

```
public void putArrayOfFloat( String item, float data[] )
                            throws Exception
```

Description

This sets an array of floating point numbers into the Fields object.

Parameters

item	The name of the item to be set
data	The array of float values to be copied into the Fields object

Return values

none

Exceptions

none

Example

```
class MyApplication
{
    ...
    MQeFields fields = new MQeFields( );
    fields.restore( dumpData );
    ...
    float data[] = fields.putArrayOfFloat( "Data" );
    ...
}
```

MQeFields putArrayOfInt

Syntax

```
public void putArrayOfInt( String item, int data[] ) throws Exception
```

Description

This sets an array of int length integer numbers into the Fields object.

Parameters

item	The name of the item to be set
data	The array of int values to be copied into the Fields object

Return values

none

Exceptions

none

Example

```
class MyApplication
{
...
MQeFields fields = new MQeFields();
fields.restore( dumpData );
...
fields.putArrayOfInt( "Data",new int[] { 1, 2, 3, 4 } );
...
}
```

MQeFields putArrayOfLong

Syntax

```
public void putArrayOfLong( String item, long data[] ) throws Exception
```

Description

This sets an array of long length integer numbers into the Fields object.

Parameters

item	The name of the item to be set
data	The array of long values to be copied into the Fields object

Return values

none

Exceptions

none

Example

```
class MyApplication
{
...
MQeFields fields = new MQeFields();
fields.restore( dumpData );
...
fields.putArrayOfLong( "Data",new long[] { 1, 2, 3, 4 } );
...
}
```

MQeFields putArrayOfShort

Syntax

```
public void putArrayOfShort( String item, short data[] )
    throws Exception
```

Description

This sets an array of short length integer numbers into the Fields object.

Parameters

item	The name of the item to be retrieved
data	The array of long values to be copied into the Fields object

Return values

none

Exceptions

none

Example

```
class MyApplication
{
...
}
```

MQeFields

```
MQeFields fields = new MQeFields( );
fields.restore( dumpData );
...
fields.putArrayOfShort( "Data", new short[] { 1, 2, 3, 4 } );
...
```

MQeFields putAscii

Syntax

```
public void putAscii( String item, String data ) throws Exception
```

Description

This method sets ASCII data (see note in “MQeFields getAscii” on page 81) into the Fields object and sets the data type.

Parameters

item The name of the item to be set

data A string containing the data to be set into the Fields object

Return values

none

Exceptions

none

Example

```
class MyApplication
{
...
MQeFields fields = new MQeFields( );
...
fields.putAscii( "Data", "This is some data" );
...
}
```

MQeFields putAsciiArray

Syntax

```
public void putAsciiArray( String item, String data[] ) throws Exception
```

Description

This method sets ASCII data (see note in “MQeFields getAscii” on page 81) from an array of strings into the Fields object and sets the data type.

Parameters

item The name of the item to be set

data A string array containing the data to be set into the Fields object

Return values

none

Exceptions

MQeException Various

Example

```
class MyApplication
{
...
MQeFields fields = new MQeFields( );
```

```
...
String data[] = { "This is some data", "This is more data" };
fields.putAsciiArray( "Data", data[] );
...
}
```

MQeFields putBoolean

Syntax

```
public void putBoolean( String item, boolean data ) throws Exception
```

Description

This sets a boolean value into the Fields object.

Parameters

item	The name of the item to be set
data	The boolean value to be set

Return values

none

Exceptions

none

Example

```
class MyApplication
{
...
MQeFields fields = new MQeFields( );
fields.restore( dumpData );
...
fields.putBoolean( "Data", false );
...
}
```

MQeFields putByte

Syntax

```
public void putByte( String item, byte data ) throws Exception
```

Description

This method sets the data in the Fields object for the supplied byte.

Parameters

item	The name of the item to be set
data	A byte containing the data to be set into the message object

Return values

none

Exceptions

none

Example

```
class MyApplication
{
...
MQeFields fields = new MQeFields( );
...
fields.putByte( "Data", 123 );
...
}
```

MQeFields

MQeFields putByteArray

Syntax

```
public void putByteArray( String item, byte data[][] ) throws Exception
```

Description

This method sets the data in the Fields object for the supplied array of byte arrays.

Parameters

item	The name of the item to be set
data	An array of byte arrays containing the data to be set into the Fields object

Return values

none

Exceptions

none

Example

```
class MyApplication
{
    ...
    MQeFields fields = new MQeFields();
    ...
    byte data[][] = new byte[2][];
    data[1][] = { 1, 2, 3, 4 };
    data[2][] = { 5, 6, 7, 8 };
    fields.putByteArray( "Data", data );
    ...
}
```

MQeFields putDouble

Syntax

```
public void putDouble( String item, double data ) throws Exception
```

Description

This method sets the data in the Fields object for the supplied double value.

Parameters

item	The name of the item to be set
data	A double value to be set into the Fields object

Return values

none

Exceptions

none

Example

```
class MyApplication
{
    ...
    MQeFields fields = new MQeFields();
    ...
    fields.putDouble( "Data", 123.456 );
    ...
}
```

MQeFields putDoubleArray

Syntax

```
public void putDoubleArray( String item, byte data[][] )
                           throws Exception
```

Description

This method sets an array of double length floating point values into the Fields.

Parameters

item The name of the item to be set

data An array of double values to be set into the Fields object

Return values

none

Exceptions

none

Example

```
class MyApplication
{
...
MQeFields fields = new MQeFields( );
...
double data[] = new byte[2];
data[1] = 1.234;
data[2] = 5.678;
fields.putDoubleArray( "Data", data );
...
}
```

MQeFields putFields

Syntax

```
public void putFields( String item, MQeFields data ) throws Exception
```

Description

This method sets the data Fields object as an item within this Fields object.

Parameters

item The name of the item to be set

data An MQeFields object to be set into this Fields object

Return values

none

Exceptions

none

Example

```
class MyApplication
{
...
MQeFields fields = new MQeFields( );
...
MQeFields subFields = new MQeFields( );
...
fields.putFields( "Data", subFields );
...
}
```

MQeFields

MQeFields putFieldsArray

Syntax

```
public void putFieldsArray( String item, MQeFields data[] )  
    throws Exception
```

Description

This method sets an array of MQeFields objects into this Fields.

Parameters

item	The name of the item to be set
data	An array of MQeFields objects to be set into this Fields object

Return values

none

Exceptions

none

Example

```
class MyApplication  
{  
    ...  
    MQeFields fields = new MQeFields( );  
    ...  
    MQeFields subFields = new MQeFields[2];  
    MQeFields subFields[0] = new MQeFields( );  
    MQeFields subFields[1] = new MQeFields( );  
    ...  
    fields.putFieldsArray( "Data", subFields );  
    ...  
}
```

MQeFields putFloat

Syntax

```
public void putFloat( String item, float data ) throws Exception
```

Description

This method sets the data in the Fields object for the supplied float value.

Parameters

item	The name of the item to be set
data	A float value to be set into the Fields object

Return values

none

Exceptions

none

Example

```
class MyApplication  
{  
    ...  
    MQeFields fields = new MQeFields( );  
    ...  
    fields.putFloat( "Data", 123.456 );  
    ...  
}
```

MQeFields putFloatArray

Syntax

```
public void putFloatArray( String item, float data[] ) throws Exception
```

Description

This method sets an array of floating point values into the Fields object.

Parameters

item	The name of the item to be set
data	An array of floating point values to be set into the Fields object

Return values

none

Exceptions

none

Example

```
class MyApplication
{
...
MQeFields fields = new MQeFields();
...
float data[] = new byte[2];
data[1] = 1.234;   data[2] = 5.678;
fields.putFloatArray( "Data", data );
...
}
```

MQeFields putInt

Syntax

```
public void putInt( String item, int data ) throws Exception
```

Description

This method sets the an int length integer into the Fields object.

Parameters

item	The name of the item to be set
data	An int value to be set into the Fields object

Return values

none

Exceptions

none

Example

```
class MyApplication
{
...
MQeFields fields = new MQeFields();
...
fields.putInt( "Data", 123456 );
...
}
```

MQeFields

MQeFields putIntArray

Syntax

```
public void putIntArray( String item, int data[] ) throws Exception
```

Description

This method sets an array of int length integer values into the Fields object.

Parameters

item	The name of the item to be set
data	An array of int values to be set into the Fields object

Return values

none

Exceptions

none

Example

```
class MyApplication
{
...
MQeFields fields = new MQeFields( );
...
int data[] = new byte[2];
data[1] = 1234; data[2] = 5678;
fields.putIntArray( "Data", data );
...
}
```

MQeFields putLong

Syntax

```
public void putLong( String item, long data ) throws Exception
```

Description

This method sets the a long length integer into the Fields object.

Parameters

item	The name of the item to be set
data	A long value to be set into the Fields object

Return values

Exceptions

none

Example

```
class MyApplication
{
...
MQeFields fields = new MQeFields( );
...
fields.putLong( "Data", 123456 );
...
}
```

MQeFields putLongArray

Syntax

```
public void putLongArray( String item, long data[] ) throws Exception
```

Description

This method sets an array of long length integer values into the Fields object.

Parameters

item	The name of the item to be set
data	An array of long values to be set into the Fields object

Return values

none

Exceptions

none

Example

```
class MyApplication
{
...
MQeFields fields = new MQeFields();
...
long data[] = new byte[2];
data[1] = 1234; data[2] = 5678;
fields.putLongArray( "Data", data );
...
}
```

MQeFields putShort

Syntax

```
public void putShort( String item, short data ) throws Exception
```

Description

This method sets the a short length integer into the Fields object.

Parameters

item	The name of the item to be set
data	A short value to be set into the Fields object

Return values

none

Exceptions

none

Example

```
class MyApplication
{
...
MQeFields fields = new MQeFields();
...
fields.putShort( "Data", 123 );
...
}
```

MQeFields

MQeFields putShortArray

Syntax

```
public void putShortArray( String item, short data[] ) throws Exception
```

Description

This method sets an array of short length integer values into the Fields object.

Parameters

item	The name of the item to be set
data	An array of short values to be set into the Fields object

Return values

none

Exceptions

none

Example

```
class MyApplication
{
    ...
    MQeFields fields = new MQeFields( );
    ...
    short data[] = new byte[2];
    data[1] = 1234;
    data[2] = 5678;
    fields.putShortArray( "Data", data );
    ...
}
```

MQeFields putUnicode

Syntax

```
public void putUnicode( String item, String data ) throws Exception
```

Description

This method sets Unicode data into the message object and sets the data type.

Parameters

item	The name of the item to be set
data	A string containing the data to be set into the message object

Return values

none

Exceptions

none

Example

```
class MyApplication
{
    ...
    MQeFields msg = new MQeFields( );
    ...
    msg.putUnicode( "Data", "Merry xmas to all our readers" );
    ...
}
```

MQeFields putUnicodeArray

Syntax

```
public void putUnicodeArray( String item, String data[] )
                            throws Exception
```

Description

This method sets Unicode data into the message object for the string array and sets the data type.

Parameters

item	The name of the item to be set
data	An array of strings containing the data to be set into the message object

Return values

none

Exceptions

none

Example

```
class MyApplication
{
...
MQeFields msg = new MQeFields( );
...
String data[] = new String[2];
data[1] = "Merry xmas to all our readers";
data[2] = "and a happy new year";
msg.putUnicode( "Data", data );
...
}
```

MQeFields rename

Syntax

```
public void rename( String itemName, String newName ) throws Exception
```

Description

This method renames an existing item within the fields object to the specified new name. If an item already exists in the fields object with the **newName** it is replaced by the renamed item..

Parameters

itemName	A String containing the name of the item to be renamed.
newName	A String containing the new name of the item

Return values

none

Exceptions

MQeException	Except_NotFound, Item + " not found"
---------------------	--------------------------------------

Example

```
class MyApplication
{
...
dumpDatafields.rename( "ThisItem", "ThatItem" );
...
}
```

MQeFields

MQeFields restore

Syntax

```
public void restore( byte data[] ) throws Exception
```

Description

This method restores a message object from a byte array that was created using the dump method.

Parameters

data A byte array containing a dumped MQeFields

Return values

none

Exceptions

MQeException	Except_Type, "wrong field type" Except_NotFound, item + " not found" Except_data, "data:xxxx" Except_Type, "Type: aaaa - bbbb"
---------------------	---

Example

```
class MyApplication
{
...
MQeFields fields = new MQeFields( );
...
fields.restore( dumpData );
...
}
```

MQeFields restoreFromFile

Syntax

1.

```
public MQeFields restoreFromFile( String fileName,
                                 MQeAttribute attribute ) throws Exception
```

2.

```
public MQeFields restoreFromFile( String fileName,
                                 String endRecord,
                                 String sectionMatch,
                                 String template ) throws Exception
```

Description

These methods create a new MQeFields object from the contents of a disk file. There are two forms:

1. A binary file containing a byte array from a dumped MQeFields object
2. An ASCII file containing sections delimited by records delimited by endRecord strings and nested fields object from a sectionMatch and endRecord delimited string

Parameters

fileName A String containing the name of the file to be read

attribute An MQeAttribute object used to decode (decrypt and/or decompress) the binary data

endRecord	A String containing the characters that delimit an end of record. E.g. '\r\n'
sectionMatch	A String containing a pattern template for: <ul style="list-style-type: none"> • The section name, for example '[#0]' • The characters that delimit an end of record, for example '\r\n' The sectionMatch template should have only one insert sequence '#0'
template	A String template used to parse the input. The Template should have up to 3 insert sequences '#n': <ul style="list-style-type: none"> #0" for the data type #1" for the Field name #2" for the field value as shown in the following example: Name=#1, Type=#0, Value=#2
Return values	An MQeFields object containing the restored values

Exceptions

Various conversion exceptions

Example

```
class MyApplication
{
  ...
  MQeFields fields = MQeFields.restoreFromFile(File.separator + "directory" +
                                                File.separator + "thisfile.xyz",
                                                "\r\n",
                                                "[#0]",
                                                "#1=#2" );
  ...
}
```

The preceding example processes an ASCII file with the following structure

```
[Section1]
item1=1235678
item2=abcdef
[Section2]
item1=qwertyiop
```

It constructs a fields object containing two imbedded fields objects with item names of **Section1** and **Section2**, each of these imbedded fields has the relevant items from that section.

MQeFields restoreFromString**Syntax**

1.


```
public void restoreFromString( String template,
                                String data ) throws Exception
```
2.


```
public void restoreFromString( String endRecord,
                                String template,
                                String data ) throws Exception
```

MQeFields

3.

```
public static MQeFields restoreFromString( String endRecord,
                                         String sectionMatch,
                                         String template,
                                         String data ) throws Exception
```

Description

These methods restore:

1. An individual item from string
2. A group of items from an EndRecord delimited string
3. A nested Fields within Fields object from a SectionMatch and EndRecord delimited string

Parameters

template

A String template used to parse the input.

The Template should have up to 3 insert sequences "#n":

"#0" for the data type
"#1" for the Field name
"#2" for the field value

as shown in the following example:

Name=#1, Type=#0, Value=#2

Return values

An MQeFields object containing the restored values

Exceptions

Various conversion exceptions

Example

```
class MyApplication
{
...
MQeFields fields = new MQeFields();
fields.putBoolean( "tb", true );
...
fields.putLong( "ml", -1 );
String data = fields.dumpToString( "Name=#1, Type=#0 Value=#2\r\n" );
...
MQeFields newFields = new MQeFields();
newFields.restoreFromString( "Name=#1, Type=#0 Value=#2\r\n", data );
...
}
```

MQeFields setAttribute

Syntax

```
public void setAttribute( MQeAttribute attribute ) throws Exception
```

Description

This method assigns an attribute to be used to encode or decode the contents of the Fields object when ever it is dumped or restored.

Parameters

attribute An MQeAttribute object reference

Return values

none

Exceptions

none

Example

```
class MyApplication
{
...
MQeFields fields = new MQeFields( );
...
MQeAttribute attr = new MQeAttribute( null, new MQeXorCryptor( ), null );
fields.setAttribute( attr );
...
}
```

MQeFields updateValue

Syntax

```
public long updateValue( String item, long update ) throws Exception
```

Description

This method increments or decrements an integer value held within this Fields object.

Parameters

item The name of the item to be set

update A value to be added to the current value of the specified item

Return values

The updated value

Exceptions

MQeException Various

Example

```
class MyApplication
{
...
MQeFields fields = new MQeFields( );
...
fields.putInt( "Data", 123 );
...
long l = fields.updateValue("Data", -3 );
...
}
```

MQeKey

MQeKey

This class is used to create an MQeKey object. MQeKey objects can be attached to and used by an attribute object. Attributes are associated with channel and MQeFields objects.

Package com.ibm.mqe

This class is a descendant of MQe

Constructor summary

Constructor	Purpose
MQeKey	Constructs an MQeKey object

Method summary

Method	Purpose
setLocalKey	Sets local encrypt and decrypt keys to a value derived from the CipherKey seed provided

MQeKey

Syntax

```
public MQeKey( )
```

Description

Constructs an MQeKey object

Parameters

none

Return values

none

Exceptions

none

Related functions

- MQeAttribute
- MQeMAttribute

MQeKey setLocalKey

Syntax

```
Public void setLocalKey ( String localCipherKey ) throws MQeException
```

Description

Protects data and writes it to the given target filename

Parameters

localCipherKey

Seed from which the Key encrypt and decrypt keys are derived

Return Values

none

Exceptions**MQeException**Except_NotAllowed, "invalid
localCipherKey"**Example**

```

class MySampleClass extends MQe
{
    try
    {
        /* protecting MQeFields data */
        MQeDESCryptor des = new MQeDESCryptor( );
        MQeAttribute desA = new MQeAttribute( null, des, null );
        MQeKey localkey = new MQeKey();
        localkey.setLocalKey( "It_is_a_secret" );
        desA.setKey( localkey );
        MQeFields localf = new MQeFields( );
        localf.setAttribute( desA );
        Trace ( "i: test data = " + "0123456789abcdef...." );
        localf.putArrayOfByte(
            "TestData", asciiToByte("0123456789abcdef....") );
        byte[] temp = localf.dump( );
        Trace ( "i: test data protected using MQeKey = " +
            byteToHex( temp ) );
        /* unprotecting MQeFields data */
        MQeDESCryptor des2 = new MQeDESCryptor( );
        MQeAttribute desA2 = new MQeAttribute( null, des2, null );
        MQeKey localkey2 = new MQeKey();
        localkey2.setLocalKey( "It_is_a_secret" );
        desA2.setKey( localkey );
        MQeFields localf2 = new MQeFields( );
        localf2.setAttribute( desA2 );
        localf2.restore ( temp );
        Trace ( "i: unprotected test data = " +
            byteToAscii(localf2.getArrayOfByte( "TestData" ) );
    }
    catch ( Exception e )
    {
    }
}

```

Related functions

- **MQeLocalSecure**

MQeMessageEvent

MQeMessageEvent

This object is passed to an application when an MQSeries Everyplace Message event occurs.

Package com.ibm.mqe

extends java.util.EventObject

Method summary

Method	Purpose
getMsgFields	Returns an MQeFields object containing selected fields from the message that caused the event to be generated.
getQueueManagerName	Returns a String containing the name of the queue manager that owns the queue that generated this event
getQueueName	Returns a String containing the name of the queue that generated this event

MQeMessageEvent getMsgFields

Syntax

```
public MQeFields getMsgFields()
```

Description

This method returns an MQeFields object containing selected fields from the message that caused the event to be generated. The unique id of the message (consisting of a timestamp plus the origin queue manager name) is always returned together with the MQSeries Message Id, MQSeries Correlation Id, and message priority values if they are present in the message.

Parameters

none.

Return values

An MQeFields object containing selected fields from the message that caused the event to be generated.

Exceptions

none.

Example

```
class MyMQeApplication
{
    ...
    /* called when a msg event occurs */
    public void messageArrived( MQeMessageEvent e )
    {
        String eventQueueName = e.getQueueName(); /* get origin Q name */
        if ( eventQueueName.equals( "SYSTEM.DEFAULT.LOCAL.QUEUE" ) )
        {
            ...
            /* get msg info */
            MQeFields filter = e.getMsgFields();
            System.out.println( "Message received from QueueMgr: " +
                e.getQueueManagerName() );
            qmgr.getMessage( null, "SYSTEM.DEFAULT.LOCAL.QUEUE", filter, null, 0 );
            ...
        }
    }
}
```

```
    } ...
}
}
```

MQeMessageEvent getQueueManagerName

Syntax

```
public String getQueueManagerName()
```

Description

This method returns a String containing the name of the queue manager that owns the queue that generated this event.

Parameters

none

Return values

A String containing the name of the queue manager that owns the queue that generated this event.

Exceptions

none

Example

```
class MyMQeApplication
{
    ...
    /* called when a msg event occurs */
    public void messageArrived( MQeMessageEvent e )
    {
        String eventQMgr = e.getQueueManagerName(); /* get origin QMgr */
        String eventQueueName = e.getQueueName(); /* get origin Q name */

        if ( eventQMgr.equals( localQMgr.getName() ) )
        { /* local QMgr */
            ...
            ...
        }
        ...
    }
    ...
}
```

Related functions

[getQueueName](#)

MQeMessageEvent getQueueName

Syntax

```
public String getQueueName()
```

Description

This method returns a String containing the name of the queue that generated this event.

Parameters

none

Return values

A String containing the name of the queue that generated this event.

Exceptions

none

Example

MQeMessageEvent

```
class MyMQeApplication
{
    ...
    /* called when a msg event occurs */
    public void messageArrived( MQeMessageEvent e )
    {
        String eventQueueName = e.getQueueName(); /* get origin Q name */
        if ( eventQueueName.equals( "SYSTEM.DEFAULT.LOCAL.QUEUE" ) )
        {
            ...
        }
        ...
        if ( eventQueueName.equals( "MyQueue" ) )
        {
            ...
        }
        ...
    }
}
```

Related functions

[**getQueueManagerName**](#)

MQeMsgObject class

This section describes the Java class used to create a basic MQeMsgObject, this object is used to hold data, or to contain the necessary logic to obtain the data to send from one MQSeries Everyplace system to another. Normally a descendant of this class would be used to hold additional characteristics, data or code.

Package com.ibm.MQe

This class is a descendant of **MQeFields**

Constants and variables

The following field name constants from the MQSeries Everyplace base class are used by MQeMsgObject.

The following two constants combine to make up the unique message identifier. They are set by the MQSeries Everyplace system and the application should not attempt to modify these values. **Msg_OriginQMgr** is an ASCII item and **Msg_Time** is a long integer value.

```
public final static String Msg_OriginQMgr
public final static String Msg_Time
```

The following field name constants are provided for use by message destined for or received from MQS systems and are not required for messages wholly within an MQSeries Everyplace environment.

They should be treated as byte arrays, and if they are to sent to MQS then they should be 24 bytes in length.

```
public final static String Msg_CorrelID
public final static String Msg_MsgID
```

The following field name constant is provided for use by message destined for or received from MQS systems and is not required for messages wholly within an MQSeries Everyplace environment. It is used to set the message style.

```
public final static String Msg_Style
```

This constant is an int integer and may have the following values:

```
public final static int Msg_Style_Datagram
public final static int Msg_Style_Request
public final static int Msg_Style_Reply
```

The following field name constants are provided for use by a message destined for, or received from, an MQS system and are not required for messages wholly within an MQSeries Everyplace environment. They can be used to have equal meaning by an application retrieving messages from a queue in an MQSeries Everyplace environment.

Both these field items are ASCII.

```
public final static String Msg_ReplyToQ
public final static String Msg_ReplyToQMgr
```

The following field name constant must be a byte value between the 0 and 9 and it sets the message priority. If it is not set when added to a queue then the queues default priority value takes effect.

```
public final static String Msg_Priority
```

MQeMsgObject

The following field name constant can be used to expire a message. MQe can discard the message if it has expired.

This constant can have one of two meanings.

1. If it is a long integer, the expire time is considered as the absolute time and date after which the message can be discarded.
2. If the item is an int integer, the expire time is relative to the creation time of the message object.

```
public final static String Msg_ExpireTime
```

The following field name is a Boolean value that the application can set or can be set by the system to indicate that the message is or has been resent.

This resend flag is set and/or reset by the MQSeries Everyplace system in order to control guaranteed message delivery on its internal flows.

```
public final static String Msg_Resend
```

The following field name constant is a long integer value, normally the value returned by a browseMessages request when browsing with lock. It is not required for messages wholly within an MQSeries Everyplace environment.

```
public final static String Msg_LockID
```

Constructor summary

Constructor	Purpose
MQeMsgObject	Creates and initializes the MQeMsgObject object

Method summary

Method	Purpose
getMsgUIDFields	Extracts the unique identifier for the message
getOriginQMgr	Extracts the name of the origination queue manager (if present)
getTimeStamp	Extracts the time the message object was created
putOriginQMgr	Sets the messages originating queue manager name Note: Once set this cannot be changed.
resetMsgUIDFields	Resets the message objects Unique id
unwrapMessageObject	Unwraps a wrapped message object

MQeMsgObject

Syntax

1.

```
public MQeMsgObject( )
```
2.

```
public MQeMsgObject ( byte data[] )
```
3.

```
public MQeMsgObject ( MQeMsgObject msg )
```

Description

The constructor creates and initializes the MQeMsgObject object. There are three forms of the constructor:

1. With no parameters. This constructs an empty message object.
2. With a byte array. This restores a fields object from the supplied byte array .

Note: The objects must be of the same type

3. With a MQeMsgObject. This wraps the supplied message into a new message object. This is normally used to wrapper messages that have attributes attached that force the data to be held encoded.

Parameters

data A byte array containing a dumped fields object.

Return values

none

Exceptions

MQeException	Except_Type, "wrong field type" Except_NotFound, item + " not found" Except_data, "data:xxxx" Except_Type, "Type: aaaa - bbbb"
---------------------	---

Example

```
class MyApplication
{
...
MQeFields fields = new MQeFields( );
...
}
```

MQeMsgObject getMsgUIDFields**Syntax**

```
public MQeFields getMsgUIDFields ( )
```

Description

This method returns an **MQeFields** object containing the following field items:

msg_Time	The time the message was created
msg-OriginQMgr	The name of the originating queue manager

The returned fields object can be used as a match parameter in an equality test or in a browse or get message call.

Parameters

none

Return values

An **MQeFields** object containing the fields used to make the unique message identifier.

Exceptions

MQeMsgObject

MQeException

Except_NotAllowed,'Queue Manager not set'

Example

```
class MyApplication
{
...
...
MQeFields uid = Msg.getMsgIDFields( );
...
}
```

MQeMsgObject getOriginQMgr

Syntax

```
public String getOriginQMgr( )
```

Description

Returns a String containing the name of the originating queue manager or *null* if not set.

Parameters

none

Return values

A String or *null*

Exceptions

none

Example

```
class MyApplication
{
...
...
String uid = Msg.getOriginQMgr();
...
}
```

MQeMsgObject getTimeStamp

Syntax

```
public long getTimeStamp( )
```

Description

Returns a long integer value containing the time in milliseconds when the object was created.

Parameters

none

Return values

A long value in milliseconds

Exceptions

none

Example

```
class MyApplication
{
...
}
```

```
...
long uid = Msg.getTimeStamp ( );
...
```

MQeMsgObject putOriginQMgr

Syntax

```
public void putOriginQMgr( )
```

Description

Sets the name of the originating queue manager. Once this name has been set, it cannot be reset.

Note: Normally this method would only be called internally by the queue manager when PutMessage call is issued.

Parameters

none

Return values

none

Exceptions

none

MQeMsgObject resetMsgUIDFields

Syntax

```
public void resetMsgUIDFields ( )
```

Description

This method resets the message objects unique id such that a new **Msg_Time** value is generated and the **Msg-OriginQMgr** is set to *null*. This in effect creates a new message object but retains any field items that were set.

Parameters

none

Return values

none

Exceptions

none

Example

```
{
...
...
msg.resetMsgUIDFields ( );
...
}
```

MQeMsgObject unwrapMessageObject

Syntax

```
public MQeMsgObject unwrapMessageObject( MQeAttribute attribute )
```

Description

This method unwraps an imbedded MQeMsgObject, decode using the supplied attribute (if appropriate), and returns the new message object.

MQeMsgObject

Parameters

attribute An **MQeAttribute** object reference or *null*, used to decode the imbedded message object

Return values

none

Exceptions

none

Example

```
class MyApplication
{
    ...
    ...
    msg.resetMsgUIDFields( );
    ...
}
```

MQeQueue

MQeQueue is the base queue class, all other types of queue are descendants of this object.

queues are objects that hold messages, the messages are held in a message store owned by the queue. Typically, this message store would be a persistent storage device, such as a hard disk. However, other types of store can be used, such as a database. MQSeries Everyplace relies on the fact that the queues have persistent store to be able to offer it's assured message delivery, and so the use of any non-persistent storage, would invalidate MQe's assured message delivery.

The queue uses a *queue store adapter* to handle its communications with the storage device. Adapters are interfaces between MQSeries Everyplace and hardware devices, such as disks or networks, or to software, such as databases. Adapters are designed to be pluggable components, allowing the queue store to be easily changed.

The messages held on the queue can be protected by an authenticator and cryptor. The messages can also be compressed by using a compressor. Together, the authenticator, cryptor, and compressor are known as the attributes of the queue, and they are defined by specifying an appropriate MQeAttribute object to be associated with the queue.

The behaviour of the queue is governed by a set of rules. These rules take the form of a Java class and can be extended by an MQSeries Everyplace solution. The base set of queue rules is defined in the class, **MQeQueueRule**. During the operation of the queue, the rules are called when certain events occur, for example, when a message is put, a message expires, or a duplicate message arrives. The rules then determine how the queue handles these events.

A queue expiry interval can be defined. If a message has remained on the queue for a length of time greater than the queue's expiry interval, then the message is marked as expired. The queue's rules then determine what happens to the message, but typically the message would be either deleted, or placed on a 'dead letter queue'. The queue's expiry interval is different to a message's expiry interval.

The maximum number of messages and the maximum allowable size of an individual message can also be defined.

All queues are owned by a queue manager. The queues owned by a queue manager are known as that queue manager's *local queues*. A queue manager can also access queues belonging to another queue manager. These queues are known as *remote queues*. When a queue manager accesses a remote queue, it stores the information it has learnt about the characteristics of that queue. The information is stored in a remote queue definition. The remote queue definition is represented by the class, **MQeRemoteQueue**.

Package

`com.ibm.mqe`

Method summary

Method	Purpose
<code>getCreationDate</code>	This method returns a long value representing the date and time at which the queue was created.

MQeQueue

Method	Purpose
<code>getDefaultValue</code>	This method returns an integer value that is the queue's default priority.
<code>getDescription</code>	This method returns a String object containing the description string for the queue.
<code>getExpiryInterval</code>	This method returns a long value that is the message expiry interval (in milliseconds) for the queue.
<code>getMaxMessageSize</code>	This method returns an integer value that is the maximum size of message (in bytes) which the queue can hold.
<code>getMaxQueueSize</code>	This method returns an integer value that is the maximum number of messages that can be held on this queue.
<code>getNumberOfMessages</code>	This method returns an integer value that is the current number of messages held on this queue.
<code>getQueueAttribute</code>	This method returns a MQeAttribute object, which defines the authenticator, cryptor, and compressor used by this queue.
<code>getQueueName</code>	This method returns a String object containing the name of the queue.
<code>getQueueStore</code>	This method returns a String object containing the pathname of the queue's persistent store.

MQeQueue getCreationDate

Syntax

```
public long getCreationDate()
```

Description

This method returns the date and time that this queue was created.

Parameters

none

Return values

A long value representing the time that this queue was created

Exceptions

none

Example

```
class ExampleQueueManagerRules extends MQeQueueManagerRule
{
    ...
    public void addQueue( MQeQueue queue ) throws MQeException
    {
        /* only allow the addition of queues created after 1st June 2000 */
        Calendar calendar = Calendar.getInstance();
        calendar.set( 2000, 05, 01 );
        Date date = calendar.getTime();
        /* get current time */
        Date qDate = new Date( queue.getCreationDate() );
        /* compare the two dates */
        if ( date.after( qDate ) )
            throw new MQeException( Except_Rule, "addQueue disallowed" );
    }
    ...
}
```

MQeQueue getDefaultPriority

Syntax

```
public int getDefaultPriority()
```

Description

This method returns the Queue's default priority value. This is the priority value which will be used for any message placed on the Queue that has not previously been assigned a priority value.

Parameters

none

Return Values

An integer value which is the default priority for this queue.

Exceptions

MQeException	none
---------------------	------

Example

```
class ExampleQueueManagerRules extends MQeQueueManagerRule
{
    ...
    public boolean transmit( MQeQueue queue )
    {
        /* allow transmission if queue's priority is greater than 5 */
        if ( queue.getDefaultPriority() > 5 )
            return (true);
        else
            return (false);
    }
    ...
}
```

MQeQueue getDescription

Syntax

```
public String getDescription()
```

Description

This method returns the description string for this queue.

Parameters

none

Return values

A String object containing the description string for this queue.

Exceptions

none

Example

```
import examples.eventlog.*;

class ExampleQueueManagerRules extends MQeQueueManagerRule
{
    public final static int Event_QueueManager_AddQueue = 201;
    LogToDiskFile logFile = null;
    ...
    public void addQueue( MQeQueue queue )
    {
        /* log the addition of a new queue */
        log( MQe_Log_Information, Event_QueueManager_AddQueue,
            "Queue " + queue.getQueueManagerName() + "+" + queue.getQueueName() +
```

MQeQueue

```
        ":" + queue.getDescription() );
}

public void queueManagerActivate() throws Exception
{
    /* create a new log file */
    logFile = new LogToDiskFile( "\\\log.txt");
}

public void queueManagerClose()
{
    /* close log file */
    logFile.close();
}
...
}
```

MQeQueue getExpiryInterval

Syntax

```
public long getExpiryInterval()
```

Description

This method returns the message expiry interval for this queue. Any message that has been on the queue for a length of time greater than the expiry interval will be marked as expired. The queue's rules then determine what happens to the message.

Parameters

none

Return Values

A long value that is the message expiry interval (in milliseconds) for this queue. A value of zero means that the queue has no message expiry interval set.

Exceptions

none

Example

```
class ExampleQueueManagerRules extends MQeQueueManagerRule
{
    ...
    public boolean transmit( MQeQueue queue )
    {
        /* transmit if queue has a low message expiry time (less than 1 day) */
        /* (zero means no expiry) */
        if ( queue.getExpiryInterval() < (60 * 60 * 24 * 1000) &&
            queue.getExpiryInterval() > 0 )
            return (true);
        else
            return (false);
    }
    ...
}
```

MQeQueue getMaxMessageSize

Syntax

```
public int getMaxMessageSize()
```

Description

This method returns the maximum size of a message (in bytes) that can be held on this queue.

Parameters

none

Return Values

An integer value that is the maximum size of a message (in bytes) that can be held on this queue.

Exceptions

none

Example

```
{
    ...
    public void addQueue( MQeQueue queue ) throws MQeException
    {
        /* only allow addition of queue if it supports messages of at least 2MB */
        if ( queue.getMaxMessageSize() < 2048000 )
            throw new MQeException( Except_Rule, "Message size too small" );
    }
    ...
}
```

MQeQueue getMaxQueueSize**Syntax**

```
public int getMaxQueueSize()
```

Description .

This method returns the maximum number of messages that can be held on this queue.

Parameters

none

Return Values

An integer value that is the maximum number of messages that can be held on this queue.

Exceptions

none

Example

```
class ExampleQueueManagerRules extends MQeQueueManagerRule
{
    ...
    public void addQueue( MQeQueue queue ) throws MQeException
    {
        /* only allow addition of queue if it supports more than 100 messages */
        if ( queue.getMaxQueueSize() < 100 )
            throw new MQeException( Except_Rule, "Max Queue depth too small" );
    }
    ...
}
```

MQeQueue getNumberOfMessages**Syntax**

```
public int getNumberOfMessages()
```

Description

This method returns the current number of messages held on this queue.

Parameters

none

MQeQueue

Return Values

An integer value that is the current number of messages held on this queue.

Exceptions

none

Example

```
class ExampleQueueManagerRules extends MQeQueueManagerRule
{
    ...
    public boolean transmit( MQeQueue queue )
    {
        /* only allow queue to transmit if it contains more than 10 messages */
        if ( queue.getNumberofMessages() >= 10 )
            return (true);
        else
            return (false);
    }
    ...
}
```

MQeQueue getQueueAttribute

Syntax

```
public MQeAttribute getQueueAttribute()
```

Description

This method returns this queue's attribute object. The attribute object defines the authenticator, cryptor and compressor used by this queue. These attributes are used upon any messages stored on the queue.

Parameters

none

Return Values

A MQeAttribute object that defines the authenticator, cryptor, and compressor used by the queue.

Exceptions

none

Example

```
class ExampleQueueManagerRules extends MQeQueueManagerRule
{
    ...
    public void addQueue( MQeQueue queue ) throws Exception
    {
        /* only allow addition of queues with a defined DES Cryptor */
        MQeAttribute qAttribute = queue.getQueueAttribute();
        if ( qAttribute == null )
            throw new MQeException( Except_Rule, "No queue attribute defined" );

        MQeCryptor cryptor = qAttribute.getCryptor();
        if ( cryptor == null )
            throw new MQeException( Except_Rule, "No cryptor defined" );

        if ( !(cryptor.securityLevel().equals( "DES" )) )
            throw new MQeException( Except_Rule, "DES Cryptor not defined" );
    }
    ...
}
```

MQeQueue getQueueManagerName

Syntax

```
public String getQueueManagerName()
```

Description

This method returns the name of the Queue Manager to which this Queue belongs.

Parameters

none

Return Values

A String object containing the name of the Queue Manager to which this Queue belongs.

Exceptions

none

Examples

```
import examples.eventlog.*;

class ExampleQueueManagerRules extends MQeQueueManagerRule
{
    public final static int Event_QueueManager_AddQueue = 201;
    LogToDiskFile logFile = null;
    ...
    public void addQueue( MQeQueue queue )
    {
        /* log the addition of a new queue */
        log( MQe_Log_Information, Event_QueueManager_AddQueue,
            "Queue " + queue.getQueueManagerName() + "+" + queue.getQueueName() +
            ": " + queue.getDescription() );
    }

    public void queueManagerActivate() throws Exception
    {
        /* create a new log file */
        logFile = new LogToDiskFile( "\\\log.txt" );
    }

    public void queueManagerClose()
    {
        /* close log file */
        logFile.close();
    }
    ...
}
```

Related Functions

[getQueueName](#)

MQeQueue getQueueName

Syntax

```
public String getQueueName()
```

Description

This method returns the name of this queue.

Parameters

none

Return values

A String object that is the name of this queue.

MQeQueue

Exceptions

none

Examples

```
import examples.eventlog.*;

class ExampleQueueManagerRules extends MQeQueueManagerRule
{
    public final static int Event_QueueManager_AddQueue = 201;
    LogToDiskFile logFile = null;
    ...
    public void addQueue( MQeQueue queue )
    {
        /* log the addition of a new queue */
        log( MQe_Log_Information, Event_QueueManager_AddQueue,
            "Queue " + queue.getQueueManagerName() + "+" + queue.getQueueName() +
            ":" + queue.getDescription() );
    }

    public void queueManagerActivate() throws Exception
    {
        /* create a new log file */
        logFile = new LogToDiskFile( "\\\log.txt" );
    }

    public void queueManagerClose()
    {
        /* close log file */
        logFile.close();
    }
    ...
}
```

Related functions

[getQueueManagerName](#)

MQeQueue getQueueStore

Syntax

```
public String getQueueStore()
```

Description

This method returns the pathname to the queue's persistent store.

Parameters

none

Return values

A String object that is the pathname to the queue's persistent store.

Exceptions

none

Example

```
import examples.eventlog.*;

class ExampleQueueManagerRules extends MQeQueueManagerRule
{
    public final static int Event_QueueManager_AddQueue = 201;
    LogToDiskFile logFile = null;
    ...
    public void addQueue( MQeQueue queue )
    {
        /* log the addition of a new queue */
        log( MQe_Log_Information, Event_QueueManager_AddQueue,
            "Queue " + queue.getQueueManagerName() + "+" + queue.getQueueName() +
            ":" + queue.getDescription() );
    }

    public void queueManagerActivate() throws Exception
    {
        /* create a new log file */
        logFile = new LogToDiskFile( "\\\log.txt" );
    }

    public void queueManagerClose()
    {
        /* close log file */
        logFile.close();
    }
    ...
}
```

```
": " + queue.getDescription() + ": Persistent store: " +
queue.getQueueStore() );
}

public void queueManagerActivate() throws Exception
{
    /* create a new log file */
    logFile = new LogToDiskFile( "\\\log.txt");
}

public void queueManagerClose()
{
    /* close log file */
    logFile.close();
}
...
}
```

MQeQueueManager

This class is used to construct an MQSeries Everyplace queue manager object.

The MQSeries Everyplace queue manager is the focal point of the MQSeries Everyplace system. It provides:

- A central point of access to the MQSeries Everyplace and MQS network for MQSeries Everyplace applications
- Once-only assured delivery of messages
- Full recovery from failure conditions
- Extendable rules-based behavior

Package

com.ibm.mqe

Constructor summary

Constructor	Purpose
MQeQueueManager	Constructs a MQeQueueManager object.

Method summary

Method	Purpose
activate	Activates a queue manager that has already been instantiated.
addMessageListener	Registers an object as a listener for MQSeries Everyplace message events.
browseMessages	Returns an MQeEnumeration containing the messages on the specified queue that match the specified filter.
browseMessagesAndLock	Works identically to browseMessages but with the addition that all messages returned are left locked on the queue.
checkActive	Returns a boolean value denoting whether or not the queue manager is active.
close	Closes down the queue manager.
confirmGetMessage	Confirms a previous getMessage operation.
confirmPutMessage	Confirms a previous putMessage operation.
deleteMessage	Removes a message from the specified queue.
getMessage	Returns a message from the specified queue.
getName	Returns the unique queue manager name.
getReference	Returns an object reference to the specified queue manager.
putMessage	Places a message onto the specified queue.
removeMessageListener	Cancels an objects subscription to MQSeries Everyplace message events.
triggerTransmission	Allows an application to initiate the transmission of any pending messages.
undo	This method is intended to be used in the event of an error whilst executing a putMessage(), getMessage() or browseMessagesAndLock() command.

MQeQueueManager

Method	Purpose
<code>unlockMessage</code>	Unlocks a message that has previously been locked by a <code>browseMessagesAndLock</code> operation.
<code>waitForMessage</code>	Performs an identical function to <code>getMessage</code> , with the exception that if no message is available, the queue manager waits for a specified period for a message to become available.

MQeQueueManager

Syntax

1.

```
public MQeQueueManager()
```
2.

```
public MQeQueueManager( MQeFields startupParameters ) throws Exception
```

Description

Constructs an **MQeQueueManager** object.

There are two versions of the constructor:

1. Creates a default queue manager that must be initialized by calling the `activate` method.
2. Creates and starts a new queue manager using the parameters supplied in the specified `MQeFields` object. Subsequently the queue manager is activated via an internal call to the `activate` method.

Note: Before starting a queue manager, all required MQSeries Everyplace aliases must have been added. Refer to the MQSeries Everyplace Programmers Guide for details of how to do this.

Parameters

startupParameters

An `MQeFields` object containing the startup parameters for the queue manager.

The startup parameters must contain two sections, **MQeQueueManager.QueueManager**, which sets up the queue manager and **MQeQueueManager.Registry**, which sets up the registry.

MQeQueueManager.QueueManager

This section contains the following:

MQeQueueManager.Name

An ascii string containing the queue manager's unique name. This name must:

- Be at least 1 character long
- Conform to the ASCII character set, i.e. characters with values 20 < value < 128
- Must not include any of the characters {}[]#();,'=
- The first character of the queue manager name should be alphanumeric

MQeQueueManager

However, to maintain compatibility with MQSeries, it is recommended that queue manager names are limited to a maximum length of 48 characters. The characters can be any of the following:

- Uppercase A-Z
- Lowercase a-z · Numerics 0-9
- Period (.)
- Underscore (_)
- Forward slash (/)
- Percent sign (%)

MQeQueueManager.Registry

Contains the following:

MQeRegistry.LocalRegType

An ascii string containing the type of registry to use. Currently the only recognized types are MQeRegistry.FileRegistry and MQeRegistry.PrivateRegistry.

Note: Once a registry has been created, it is recommended that the registry type is not changed. Changing the registry type may cause secure queues to function incorrectly

MQeRegistry.DirName

An ascii string containing a pathname to the queue manager's registry.

Two further sections, **MQeQueueManager.AppRunList**, and **MQeQueueManager.CloseAppRunList** are optional. These sections specify a list of MQSeries Everyplace applications that are invoked once the queue manager is active, and when it receives a close request. (See "MQeRunListInterface" on page 198

Return values

none

Exceptions

MQeException	Except_QMgr_Activated Except_QMgr_AlreadyExists Except_QMgr_InvalidQMgrName Except_QMgr_NotConfigured
---------------------	--

Examples

```
class MyMQeApplication
{
    ...
    /* Create QueueManager startup parameters */
    MQeFields qmgrParams = new MQeFields();
    qmgrParams.putAscii( MQeQueueManager.Name, "TestQMgr" );
```

```
/* Create Registry startup parameters */
MQeFields regParams = new MQeFields();
regParams.putAscii(MQeRegistry.LocalRegType, MQeRegistry.FileRegistry );
regParams.putAscii( MQeRegistry.DirName, "c:\\TestQMgr\\Registry" );

/* Create a list of MQSeries Everyplace applications to run at start-up time
MQeFields appList = new MQeFields();
appList.putAscii( "MQeApp1", "Examples.mqe.MQEtest" );

/* Combine the three sets of parameters into a single Fields object      */
MQeFields params = new MQeFields();
params.putFields( MQeQueueManager.QueueManager, qmgrParams );
params.putFields( MQeQueueManager.Registry, regParams );
params.putFields( MQeQueueManager.AppRunList, appList );

/* Instantiate null Queue Manager */
MQeQueueManager qmgr = new MQeQueueManager( );
qmgr.activate( params ); /* Activate QMgr using parameters */
...
}
```

MQeQueueManager activate

Syntax

1.
public void activate(MQeFields startupParameters) throws Exception
2.
public void activate(String name) throws Exception

Description

Note: Before starting a queue manager, all required MQSeries Everyplace aliases must have already been added. Refer to the MQSeries Everyplace Programmers Guide for details of how to do this.

There are two versions of the method:

1. This is the recommended version of the method. It takes as input an **MQeFields** object containing startup parameters for the queue manager. The queue manager then initializes all its subcomponents correctly, and reads any information stored in its registry.
2. This version is provided solely to allow the standard queue manager activation procedure to be overridden by a class extending from MQeQueueManager. This method performs no activation procedure other than to set the queue manager name.

Note: Any class extending MQeQueueManager must call MQeQueueManager.activate() to ensure that the queue manager name is set correctly.

Parameters

startupParameters

An **MQeFields** object containing startup parameters for the queue manager.

See the MQeQueueManager startupParameters for details of these parameters.

name

An ascii string containing the name of the queue manager

MQeQueueManager

Return values

none

Exceptions

MQeException	Except_QMgr_Activated Except_QMgr_AlreadyExists Except_QMgr_InvalidQMngrName Except_QMgr_NotConfigured Except_NotFound
--------------	--

Example

```
class MyMQeApplication
{
    /*
     * Create QueueManager startup parameters */
    MQeFields QMgrParams = new MQeFields();
    QMgrParams.PutAscii( MQeQueueManager.Name, "TestQMngr" );
    QMgrParams.PutAscii( MQeQueueManager.QueueStore, "MsgLog:c:\\\TestQMngr" );

    /* Create Registry startup parameters */
    MQeFields RegParams = new MQeFields();
    RegParams.PutAscii( MQeQueueManager.RegType, MQeQueueManager.FileRegistry );
    RegParams.PutAscii( MQeQueueManager.Path, "MsgLog:c:\\\TestQMngr\\\Registry" );

    /* Combine the two sets of parameters into a single Fields object */
    MQeFields Params = new MQeFields();
    Params.PutFields( MQeQueueManager.QueueManager, QMgrParams );
    Params.PutFields( MQeQueueManager.Registry, RegParams );

    /* Instantiate 'null' Queue Manager */
    MQeQueueManager QMgr = new MQeQueueManager( );
    QMgr.Activate( Params ); /* Activate QMgr using parameters */
}

```

Related functions

- [close](#)

MQeQueueManager addMessageListener

Syntax

```
public void addMessageListener( MQeMessageListenerInterface listener,
                                String queueName,
                                MQeFields filter ) throws Exception;
```

Description

This method registers an object as a listener to any MQeMessage events generated by the queue specified in the `queueName` parameter. It is only possible to add listeners to local queues.

Note: The listening object must implement the `MQeMessageListenerInterface`. Events are processed by the event handler methods specified in this interface.

A message filter consisting of message fields (for example MessageId or Priority) may be specified so that the listening object only receives events concerning messages that include the same fields as those specified. If no fields are specified, events are triggered for all messages on the queue.

Parameters

listener	A reference to the subscribing object
queueName	A String containing the name of the queue from which the listener wishes to receive events
params	<i>null</i> , or an MQeFields object containing message fields. A value of <i>null</i> means that the listener wishes to receive events for all messages on the queue. Specifying an MQeFields object containing message fields means that the listener is only interested in events concerning messages whose fields match those contained in the filter.

Return Values

none

Exceptions

MQeException	Except_QMgr_NotActive Except_QMgr_QdoesNotExist
---------------------	--

Example

```
class MyMQeApplication implements MQeMessageListenerInterface
{
    ...
    MQeFields filter = new MQeFields(); /* search parameters */
    filter.putByte( MQe.Msg_Priority,(byte)3); /* only interested in */
                                                /* msgs of priority 3 */

    ...
    /* add listener */
    MyQM.addMessageListener( this, "MyQueue", filter );
    ...
    /* Message arrived event handler */
    public void messageArrived( MQeMessageEvent msgEvent )
    {
        ...
        /* is it the Queue we are interested in?? */
        if ( msgEvent.getQueueName().equals("MyQueue") )
        {
            ...
        }
        ...
    }
}
```

Related Functions

- [removeMessageListener](#)

MQeQueueManager browseMessages**Syntax**

```
public MQeEnumeration browseMessages( String qmgrName,
                                      String queueName,
                                      MQeFields filter,
                                      MQeAttribute attribute,
                                      boolean justUID ) throws Exception;
```

Description

This method returns an enumeration of the messages available on a specified queue. The messages are not deleted from the queue. The queue can belong to a local or remote queue manager.

MQeQueueManager

A filter can be specified, consisting of message fields (for example MessageId or Priority). This causes only messages that have matching fields to be returned

Returning an enumeration of messages in their entirety can be expensive in terms of system resources, so if the **justUID** parameter is set to **true**, just the unique ids of the messages that match the filter are returned.

The messages returned in the enumeration are still visible to other MQSeries Everyplace applications. Therefore, when performing subsequent operations on the messages contained in the enumeration, the application should be aware that it is possible for another application to have processed these messages in the time since the enumeration was returned. To lock the messages contained in the enumeration, therefore preventing other applications from processing them, use the **browseMessagesAndLock** method.

Parameters

qmgrname

A string containing the name of the queue manager that holds the queue to be browsed. If a value of *null* is used it is assumed that the local queue manager is to be used.

queueName

A string containing the name of the queue to browse

filter

null, or an **MQeFields** object containing the parameters with which to perform the browse.

attribute

An **MQeAttribute** object used to provide message-level security.

justUID

A boolean value denoting whether to return the all the fields in the messages, or just the unique id values.

Return values

An **MQeEnumeration** containing zero or more **MQeMsgObject** message objects.

Exceptions

MQeException

Except_QMgr_NotActive

Except_QMgr_InvalidQMGrName

Except_QMgr_QDoesNotExist

Various other exceptions

Example

```
class MyMQeApplication
{
    ...
    MQeEnumeration msgs = null;
    byte[] msgId = MQe.asciiToByte(240999);
    byte[] correID = MQe.asciiToByte("240999/2");

    try
    {
        /* setup parameters object for matching */
        MQeFields filter = new MQeFields(); /* match against msgs */
        filter.putArrayOfByte( MQe.Msg_MsgID, msgId ); /* with this Msg Id */
    }
}
```

MQeQueueManager

```
filter.putArrayOfByte( MQe.Msg_CorrelID, /* & this Correl Id */
                      correlId );

/* look at available messages */
msgs = qmgr/browseMessages( null, "MyQueue", filter, null, false );

...
/* get this one and remove from queue */
MQeMsgObject msgObj = qmgr/getMessage( null, "MyQueue",
                                         (MQeFields)msgs.nextElement(),
                                         null, 0 );

}
catch ( MQeException e )
{
    ...
}
...
}
```

Related Functions

- [browseMessagesAndLock](#)

MQeQueueManager browseMessagesAndLock

Syntax

```
public MQeEnumeration browseMessagesAndLock( String qmgrName,
                                             String queueName,
                                             MQeFields filter,
                                             MQeAttribute attribute,
                                             long confirmId,
                                             boolean justUID ) throws Exception;
```

Description

This method returns an enumeration of the messages available on a specified queue. The messages are not deleted from the queue. The queue may belong a local or remote queue manager.

A filter can be specified, which consists of message fields (MessageId and Priority for example), so that only messages that have matching fields are returned.

Any messages that are returned by this operation are also locked on the queue. This means that these messages still exist on the queue, but they will not be visible to any subsequent operations, until they are unlocked.

A lock id is returned as part of the browse enumeration. The lock ID allows operations to be performed on locked messages so long as it is specified as part of the message filter that is passed into that operation.

Lock ids are unique, so every browse and lock operation generates a different id. The lock id applies to all the messages that are returned by the browse operation.

The operations that can be performed on a locked message are:

- [getMessage\(\)](#)
- [deleteMessage\(\)](#)
- [unlockMessage\(\)](#)
- [waitForMessage\(\)](#)

Returning an enumeration of messages in their entirety can be expensive in terms of system resources, so if the **justUID** parameter is set to true just the unique ids of the messages that match the filter are returned.

MQeQueueManager

Specifying an **MQeAttribute** object allows browsing of messages that have message-level security defined with a matching attribute. Browsing queues containing messages with differing levels of message-level security may cause undefined results.

The **confirmID** is used in the event of an error whilst executing this command. The error could occur before the lock id is returned to the application and yet leave the messages in a locked state on the target queue. Passing the same confirm id used on this method to the undo method restores the messages to their previous state. It is recommended that a unique value be used for each browse and lock operation. A unique value can be generated using the **MQe.uniqueValue()** method.

Parameters

qmgrName	A string containing the name of the queue manager that holds the queue to be browsed. If a value of <i>null</i> is used it is assumed that the local queue manager is to be used.
queueName	A string containing the name of the queue to browse.
filter	<i>null</i> , or an MQeFields object containing the message fields with which to perform the browse.
attribute	An MQeAttribute object used to provide message-level security.
confirmId	A long value that is used in the event of a queue manager failure. The application should store the value used, and use it to reset the messages should a failure occur.
justUID	A boolean value denoting whether to return the entire message, or just its unique id.

Return Values

An **MQeEnumeration** containing zero or more **MQeMsgObject** message objects. The enumeration also contains the lock id, which can be accessed using the **getLockID()** method.

Exceptions

MQeException	Except_QMgr_NotActive Except_QMgr_InvalidQMngrName Except_QMgr_QDoesNotExist
---------------------	--

Various other exceptions

Example

```
class MyMQeApplication extends MQe
{
    ...
    MQeEnumeration msgs = null;
    byte[] msgId = asciiToByte("240999");
    byte[] correlId = asciiToByte("240999/2");

    try
    {
        /* setup parameters object for matching */
        MQeFields filter = new MQeFields(); /* match against msgs */
        filter.putArrayOfByte( MQe.Msg_MsgId, msgId ); /* with this Msg Id */
        filter.putArrayOfByte( MQe.Msg_CorrelId, /* & this Correl Id */
            correlId );
    }
}
```

MQeQueueManager

```
/* look at available messages */
msgs = qmgr/browseMessagesAndLock( null, "MyQueue", filter, null, 0,
                                    false );
long lockId = msgs.getLockId(); /* get Lock Id */

filter.putLong( MQe.Msg_LockID, lockId ); /* Add lock Id */

/* get the first locked message from queue */
MQeMsgObject msgObj = qmgr/getMessage( null, "MyQueue", filter, null, 0 );
}
catch ( MQeException e )
{
    ...
}
...
}
```

Related Functions

- [getMessage](#)
- [waitForMessage](#)
- [browseMessagesAndLock](#)
- [unlockMessage](#)
- [deleteMessage](#)
- [undo](#)

MQeQueueManager checkActive

Syntax

```
public boolean checkActive()
```

Description

This method allows an application to determine whether or not the queue manager is active.

Parameters

none

Return Values

A boolean value denoting whether or not the queue manager is active

Exceptions

none

Example

```
class MyMQeApplication
{
    ...
    qmgr = new MQeQueueManager( startupParams );
    if ( qmgr.checkActive() ) /* verify that QMgr is active */
    {
        ...
    }
    else
        throw new Exception( "Queue Manager not active" );
}
```

MQeQueueManager close

Syntax

```
public void close() throws MQeException
```

MQeQueueManager

Description .

This method closes down the queue manager. It should be called by MQe applications when they have finished using the queue manager.

Parameters

none

Return Values

none

Exceptions

MQeException

Except_QMgr_NotActive

Example

```
class MyMQeApplication
{
    ...
    try
    {
        qmgr.putMessage( null, "MyQueue", msgObj, null, 0 );
    }
    catch ( MQeException e )
    {
        ...
        ...
        qmgr.close(); /* close QMgr */
    }
}
```

Related Functions

- activate

MQeQueueManager confirmGetMessage

Syntax

```
public void confirmGetMessage( String qmgrName,
                               String queueName,
                               MQeFields filter ) throws Exception
```

Description

This method confirms the successful receipt of a message that was retrieved from a queue by a previous getMessage operation. The message remains locked on the target queue until the confirm flow is received.

Parameters

queueName A string containing the name of the queue on which the message is held.

qmgrName A string containing the name of the queue manager that holds the queue. If a value of *null* is used it is assumed that the local queue manager is to be used.

filter An **MQeFields** object containing a message filter. The filter must contain the message's unique id for the operation to be successful.

Return Values

none

Exceptions

MQeException

Except_NotFound

MQeQueueManager

Note: This exception is thrown when attempting to confirm a message that has already been confirmed. If an application has reissued a confirm get message request then this exception can be treated as a successful return code.

Various other exceptions

Example

```
class MyMQeApplication
{
    ...
    /* generate a unique confirmId for this operation */
    long confirmId = MQe.uniqueValue();
    /* get next available msg - msg still locked on target queue */
    MQeMsgObject msg = qmgr.getMessage( "RemoteQMgr", "RemoteQueue", null,
                                         null, confirmId );
    /* confirm the successful Get */
    qmgr.confirmGetMessage( "RemoteQMgr", "RemoteQueue",
                           msg.getMsgUIDFields() );
    ...
}
```

Related Functions

- [getMessage](#)

MQeQueueManager confirmPutMessage

Syntax

```
public void confirmPutMessage( String qmgrName,
                               String queueName,
                               MQeFields filter ) throws Exception
```

Description

This method performs the confirmation of a previously successful putMessage operation.

Parameters

queueName	A string containing the name of the queue on which the message is held.
qmgrName	A string containing the name of the queue manager that holds the queue. If a value of <i>null</i> is used it is assumed that the local queue manager is to be used.
filter	An MQeFields object containing a message filter. The filter must contain the message's unique id for the operation to be successful.

Return Values

none

Exceptions

MQeException

Except_NotFound

Note: This exception is thrown when attempting to confirm a message that has already been confirmed. If an application has reissued a confirm get message request then

MQeQueueManager

this exception can be treated as a successful return code.
Various other exceptions

Example

```
class MyMQeApplication
{
    ...
    /* generate a unique confirmId for this operation */
    long confirmId = MQe.uniqueValue();
    qmgr.putMessage( "RemoteQMGr", "RemoteQueue", msg, null,
                     confirmId );
    /* confirm the put */
    qmgr.confirmPutMessage( "RemoteQMGr", "RemoteQueue",
                           msg.getMsgUIDFields() );
    ...
}
```

Related Functions

- [putMessage](#)

MQeQueueManager deleteMessage

Syntax

```
public void deleteMessage( String qmgrName,
                           String queueName,
                           MQeFields filter ) throws MQeException
```

Description

This method deletes a message from a queue. It does not return the message to the application that called it.

Only one message can be deleted per operation and the unique id(timestamp and origin queue manager name) of the message must always be supplied.

The queue may belong to a local or remote MQSeries Everyplace queue manager.

Messages that have been locked by a previous operation (browse for example) can be deleted by included a valid lock id in the message filter.

If the message is not available, an exception is thrown.

Parameters

queueName	A String containing the name of the queue on which the message is held.
qmgrName	A String containing the name of the queue manager that holds the queue. If a value of <i>null</i> is used it is assumed that the queue manager is local.
filter	An MQeFields object containing a message filter. The filter must contain the unique id of the message for the operation to be successful.

Return Values

none

Exceptions

MQeException

Except_QMgr_InvalidQName

Except_QMgr_NotActive

MQeQueueManager

Except_QMgr_QDoesNotExist
Except_QMgr_WrongType
Except_NotFound
Except_NotAllowed

Various other exceptions

Examples

```
class MyMQeApplication
{
    ...
    MQeEnumeration msgEnum;
    ...
    MQeFields filter = new MQeFields();
    filter.putArrayOfByte( MQe.Msg_MsgID, new byte[] { 1,2,3,4 } );
    /* return all messages with a Message Id of 1234 */
    msgEnum = qmgr/browseMessages( null, "MyQueue", filter, null, false );
    /* delete all message with a Message Id of 1234 */
    while( msgEnum.hasMoreElements() )
        qmgr.deleteMessage( null, "MyQueue",
                            (MQeMsgObject)msgEnum.nextElement() );
    ...
}
```

Related Functions

- [waitForMessage](#)
- [browseMessages](#)
- [browseMessagesAndLock](#)
- [putMessage](#)
- [getMessage](#)

MQeQueueManager getMessage

Syntax

```
public MQeMsgObject getMessage( String qmgrName,
                                String queueName,
                                MQeFields filter,
                                MQeAttribute attribute,
                                long confirmId ) throws MQeException;
```

Description

This method returns an available message from the specified queue and the message is removed from the queue. The queue can belong to a local or a remote MQSeries Everyplace queue manager.

If no message filter is specified, the first available message on the queue is returned. If a message filter is specified, the first available message that matches the filter is returned.

Messages that have been locked by a previous browse operation can be retrieved by including, in the message filter, the lock id that was used to lock the message.

If no message is available, an exception is thrown.

The use of assured message delivery is dependent upon the value of the **confirmId** parameter. Passing a nonzero value returns the message as normal, but the message is locked and is not removed from the target queue until a subsequent confirm is received. A confirm can be issued

MQeQueueManager

using the **confirmGetMessage()** method. Passing a value of zero returns the message and removes it from the target queue, however, the message delivery is not assured.

The **confirmId** parameter is also used in the event of an error when executing this command. A failure could occur before the message is returned to the application and yet leave the message in a locked state on the target queue. Passing the same confirm id used for the get operation to the undo method restores the message to its previous state. It is recommended that a unique value be used for each get operation. A unique value can be generated using the **MQe.uniqueValue()** method.

Parameters

queueName	A string containing the name of the queue from which to obtain a message.
qmgrName	A string containing the name of the queue manager that holds the queue. If a value of <i>null</i> is used it is assumed that the queue manager is local.
filter	<i>null</i> , or an MQeFields object containing a message filter.
attribute	An MQeAttribute object used to provide message-level security. The attribute supplied must match any attribute attached to the message returned by this method. Failure to do this may result in message loss.
confirmId	A long value denoting whether or not to use guaranteed message delivery. A nonzero value does not remove the message from the target queue, this occurs on a subsequent confirm flow. A value of zero will remove the message from the target queue.

Return values

An **MQeMsgObject** containing the message obtained from the specified queue

Exceptions

MQeException	Except_QMgr_NotActive Except_QMgr_InvalidQName Except_QMgr_QDoesNotExist Except_QMgr_WrongQType Except_Q_NoMatchingMsg Except_NotFound
---------------------	---

Various other exceptions

Examples

Example 1-Simple get, no message filter

```
class MyMQeApplication
{
    ...
    try
    {
        /* get 1st available message on the queue */
        MQeMsgObject myMsgObject = qmgr.getMessage( null, "MyQueue", null, null,
                                                    0 );
    }
}
```

```

        catch ( MQeException e )
        {
            ...
        }
        ...
    }
}

```

Example 2–Browse and get

```

class MyMQeApplication
{
    ...
    /* Lock all msgs on this queue */
    MQeEnumeration msgEnum = qmgr/browseMessagesAndLock( null, "MyQueue",
                                                       null, null, 0, false );
    long lockId = msgEnum.getLockId(); /* get the Lock Id */
    MQeFields filter = new MQeFields(); /* create a msg filter */
    filter.putLong( MQe.Msg_LockID, lockId ); /* add lock Id */
    /* get the 1st locked message on the queue */
    MQeMsgObject msgObj = qmgr/getMessage( null, "MyQueue", filter, null, 0 );
    ...
}

```

Example 3–get with assured message delivery

```

class MyMQeApplication
{
    ...
    /* generate a unique confirmId for this operation */
    long confirmId = MQe.uniqueValue();
    /* get next available msg - msg remains locked on the target queue */
    MQeMsgObject msg = qmgr/getMessage( "RemoteQMgr", "RemoteQueue", null,
                                         null, confirmId );
    /* confirm the successful Get */
    qmgr/confirmGetMessage( "RemoteQMgr", "RemoteQueue",
                           msg.getMsgUIDFields() );
    ...
}

```

Related functions

- [waitForMessage](#)
- [browseMessages](#)
- [browseMessagesAndLock](#)
- [putMessage](#)
- [deleteMessage](#)
- [confirmGetMessage](#)
- [undo](#)

MQeQueueManager getName

Syntax

```
public String getName();
```

Description

This method returns the name of this queue manager.

Note: It is strongly recommended that all queue manager names are unique within an MQSeries Everyplace network.

Parameters

none

MQeQueueManager

Return values

A string containing the name of the queue manager.

Exceptions

none

Example

```
class MyMQeApplication
{
    ...
    String qmgrName = qmgr.getName();
    ...
}
```

MQeQueueManager getReference

Syntax

```
public static MQeQueueManager getReference( String qmgrName ) throws MQeException
```

Description

This method is used to obtain an object reference to an instantiated queue manager.

Parameters

qmgrName A String containing the name of an queue manager.

Return values

An MQeQueueManager object.

Exceptions

MQeException

Except_QMgr_InvalidQMgrName

Example

```
class MyMQeApplication
{
    ...
    MQeQueueManager qmgr = null;
    ...
    /* Obtain a reference to "MyQMgr" Queue Manager */
    qmgr = MQeQueueManager.getReference( "MyQMgr" );
    /* Put a message */
    qmgr.putMessage( null, "DestQ", Msg, null, 0 );
    ...
}
```

MQeQueueManager putMessage

Syntax

```
public void putMessage( String qmgrName,
                        String queueName,
                        MQeMsgObject msg,
                        MQeAttribute attribute,
                        long confirmId ) throws Exception;
```

Description

This method places the specified message onto the specified queue. This queue may belong to a local or a remote queue manager.

Puts to remote queues can occur immediately, or at some later time depending upon how the remote queue is defined on the local queue manager.

If a remote queue is defined as synchronous, the transmission of the message over the network occurs immediately.

If a remote queue is defined as asynchronous, the message is stored within the local queue manager. The message remains there until the queue manager rules decide that it is time to transmit any pending messages or the queue manager is triggered through the **triggerTransmission()** method.

If the local queue manager does not hold a definition of the remote queue then it attempts to contact the queue synchronously.

The assured delivery of the message is dependent on the value of the **confirmId** parameter. Passing a nonzero value transmits the message as normal, but the message is locked on the target queue until a subsequent confirm is received. Passing a value of zero transmits the message without the need for a subsequent confirm, however the delivery of the message is not assured.

The **confirmID** is also used in the event of an error during the execution of this command. Passing the same confirm id used for the put operation to the undo method removes the unconfirmed message from the target queue. It is recommended that a unique value be used for each put operation. A unique value can be generated using the **MQe.uniqueValue()** method.

A message can be protected using message-level security (see *MQSeries Everyplace Programming Guide* for information on MQSeries Everyplace security). The security is defined by providing an **MQeAttribute** object, or one of its descendants. The attribute can be attached to the message prior to any put message request, or the attribute parameter can be used to specify the message-level security to be used.

If the attribute parameter is not *null*, the value overrides any attribute attached to the message prior to the put message request. If the attribute parameter is *null*, it has no effect on the sending of the message.

Parameters

queueName A string containing the name of the queue on which the message should be placed.

qmgrName A string containing the name of the remote queue manager to which the specified queue belongs. If a value of *null* is used it is assumed that the queue manager is local.

msg An **MQeMsgObject** containing the message.

attribute An **MQeAttribute** object or a descendant, or *null*.

If *null*, then this parameter has no effect on the sending of the message.

The attribute specified here over-rides any attribute that has been previously associated with the message, and **MQeFields** data in the message using previous calls to the **MQeFields.setAttribute()** or **MQeMsgObject.setAttribute()** methods.

You may pass an **MQeMAttribute** or **MQeMTrustAttribute** to perform message-level security operations.

confirmId A long value denoting whether or not to use assured

MQeQueueManager

message delivery. A nonzero value locks the message on the target queue, it is not made visible until a subsequent confirm flow. A value of zero transmits the message without the need for a subsequent confirm.

Return values

none.

Exceptions

MQeException

Except_QMgr_InvalidQName
Except_QMgr_NotActive
Except_QMgr_QDoesNotExist
Except_Duplicate

Various other exceptions

Example

Example 1–simple put

```
class MyMQeApplication
{
    ...
    try
    {
        qmgr.putMessage( null, "MyQueue", msgObj, /* simple put */
                         null, 0 );
    }
    catch ( MQeException e )
    {
        ...
    }
    ...
}
```

Example 2–put with assured message delivery

```
class MyMQeApplication
{
    ...
    /* generate a unique confirmId for this operation */
    long confirmId = MQe.uniqueValue();
    qmgr.putMessage( "RemoteQMGR", "RemoteQueue", msg, null, confirmId );
    /* confirm the put */
    qmgr.confirmPutMessage( "RemoteQMGR", "RemoteQueue",
                           msg.getMsgUIDFields() );
    ...
}
```

Related functions

- [getMessage](#)
- [waitForMessage](#)
- [confirmPutMessage](#)
- [undo](#)

MQeQueueManager removeMessageListener

Syntax

```
public void removeMessageListener( MQeMessageListenerInterface listener,
                                    String queueName,
                                    MQeFields filter ) throws MQeException
```

Description

This method removes an objects subscription to MQSeries Everyplace message events generated by the queue specified in **queueName**. It is only possible to have listeners on local queues.

Note: The listening object must implement the **MQeMessageListenerInterface**.

If an optional message filter is specified, the object's subscription is only removed for events concerning messages that include the same fields as those specified in the filter. If the filter is *null*, the object's subscription for events concerning all messages is removed.

Parameters

listener A reference to the subscribing object.

queueName A String containing the name of the queue from which the listener wishes to receive events.

filter *null* or a **MQeFields** object containing a message filter.

Return values

none

Exceptions

MQeException Except_QMgr_NotActive

Except_QMgr_InvalidQName

Except_QMgr_QDoesNotExist

Example

```
class MyMQeApplication implements MQeMessageListenerInterface
{
    ...
    /* remove the 'all messages' listener for this queue */
    qmgr.removeMessageListener( this, "MY.QUEUE", null );
    ...
}
```

Related Functions

[addMessageListener](#)

MQeQueueManager triggerTransmission

Syntax

```
public void triggerTransmission() throws Exception
```

Description

This method causes an attempt to transmit any pending messages.

Pending messages are messages awaiting transmission to remote queue managers. Typically, the transmission of pending messages would be handled by the queue manager rules, but this method allows transmission of pending messages at a time convenient to the application.

In addition, this method triggers any home server queues that are defined. These queues attempt to collect messages from their home servers.

This method overrides the operation of the **MQeQueueManagerRule.triggerTransmission()** rule, however, it does call the **MQeQueueManagerRule.transmi()** rule.

MQeQueueManager

Parameters

none

Return values

none

Exceptions

MQeException

Except_BadRequest

Except_QMgr_NotActive

Except_QMgr_QDoesNotExist

Various other exceptions

Examples

```
class MyMQeApplication
{
    ...
    try
    {
        if ( timeToTransmit() ) /* application decides it's time to */
            qmgr.triggerTransmission(); /* transmit */
    }
    catch ( MQeException e )
    {
        if ( e.Code() != Except_QMgr_Busy )
            throw e;
    }
    ...
}
```

MQeQueueManager undo

Syntax

```
public void undo( String qmgrName,
                  String queueName,
                  long confirmId ) throws Exception
```

Description

This method is intended to be used in the event of an error during a **put**, **get**, or **browseAndLock** command. It is possible that the error could leave messages in an unconfirmed or locked state on the target queue. This method resets the message to the state (either locked or unlocked) that it was in prior to the failed operation, or in the case of an unconfirmed put operation, the message is deleted.

To reset the message, it is necessary to supply the **confirmId** that was used in the failed operation. It is recommended that confirm ids are unique for each message. A unique value can be generated using the **MQe.uniqueValue()** method.

Parameters

qmgrName A string containing the name of the queue manager that holds the queue. If a value of *null* is used, it is assumed that the local queue manager is the queue manager to be used.

queueName A string containing the name of the queue that holds the locked message

confirmId A long value that is the same as the confirm id used on the failed operation.

Return values

none.

Exceptions**MQeException**

Except_QMgr_NotActive
 Except_QMgr_InvalidQName
 Except_QMgr_QDoesNotExist
 Except_Q_NoMatchingMsg
 Except_NotAllowed

Various other exceptions

Examples

```
class MyMQeApplication
{
    ...
    /* generate a unique confirmId for this operation */
    long confirmId = MQe.uniqueValue();
    try
    {
        qmgr.putMessage( "RemoteQMGR", "RemoteQueue", msg, null, confirmId );
        qmgr.confirmPutMessage( "RemoteQMGR", "RemoteQueue",
                               msg.getMsgUIDFields() );
    }
    catch ( Exception e )
    {
        /* Give the remote Queue Manager time to recover from error */
        Thread.sleep( 30000 );
        /* Remote Queue Manager failure - undo the put message */
        qmgr.undo("RemoteQMGR", "RemoteQueue", confirmId );
    }
    ...
}
```

Related functions

- [browseMessagesAndLock](#)
- [getMessage](#)
- [putMessage](#)

MQeQueueManager unlockMessage**Syntax**

```
public void unlockMessage( String qmgrName,
                           String queueName,
                           MQeFields filter ) throws Exception
```

Description

This method unlocks a message that has been previously locked. This makes it visible once again to all applications. Only one message can be unlocked at a time and both the unique id (timestamp and origin queue manager name), and lock id of the message must be supplied.

The queue may belong to a local or remote queue manager.

If the message is not available, an exception is thrown.

This method would typically be used in conjunction with the [browseMessagesAndLock\(\)](#) method.

Parameters

MQeQueueManager

qmgrName A string containing the name of the queue manager that holds the queue. If a value of *'null'* is used, it is assumed that the local queue manager is to be used.

queueName A string containing the name of the queue that holds the locked message.

filter An **MQeFields** object containing a message filter. This must contain both the message unique id and lock id for the operation to be successful.

Return values

none

Exceptions

MQeException

Except_QMgr_NotActive

Except_QMgr_InvalidQName

Except_QMgr_QDoesNotExist

Except_Q_NoMatchingMsg

Except_NotAllowed

Various other exceptions

Example

```
class MyMQeApplication
{
    ...
    MQeEnumeration msgEnum;
    ...
    /* lock all msgs on queue */
    msgEnum = qmgr/browseMessagesAndLock( null, "MyQueue", null, null, 0,
                                         false );
    long lockID = msgEnum.getLockID(); /* get lockID */
    while( msgEnum.hasMoreElements() )
    {
        MQeFields msgFields = (MQeFields)msgEnum.nextElement();
        String msgID = byteToAscii( msgFields.getArrayOfByte( MQe.Msg_MsgID ) );
        /* Unlock all messages with an ID of 1234 */
        if ( msgID.equals("1234") )
        {
            msgFields.putLong( MQe.Msg_LockID, lockID );
            qmgr.unlockMessage( null, "MyQueue", msgFields );
        }
    }
    ...
}
```

Related Functions

- **browseMessageAndLock**

MQeQueueManager waitForMessage

Syntax

```
public MQeMsgObject waitForMessage( String qmgrName,
                                    String queueName,
                                    MQeFields filter,
                                    MQeAttribute attribute,
                                    long confirmId,
                                    int milliseconds ) throws MQeException;
```

Description

This method works in an identical manner to **getMessage**. However, if no message is available, the method waits for the period of time specified by **milliseconds**. If no message is available at the end of this period, an Exception is thrown.

Parameters

qmgrName	A string containing the name of the queue manager that holds the queue. If a value of <i>null</i> is used, it is assumed that the local queue manager is to be used.
queueName	a string containing the name of the MQSeries Everyplace queue from which to obtain a message.
filter	<i>null</i> , or an MQeFields object containing a message filter.
attribute	An MQeAttribute object used to provide message-level security.
confirmId	A long value denoting whether or not to use assured message delivery. A nonzero value does not remove the message from the target queue, this occurs on a subsequent confirm flow. A value of zero removes the message from the target queue.
milliseconds	The period of time (specified in milliseconds) for which to wait for a message to become available.

Return values

An **MQeMsgObject** containing the message obtained from the specified queue.

Exceptions

MQeException	Except_QMgr_NotActive Except_QMgr_InvalidQName Except_QMgr_QDoesNotExist Except_Q_NoMatchingMsg Except_Q_NoMsgAvailable
---------------------	---

Various other exceptions

Examples

```
class MyMQeApplication extends MQe
{
    ...
    String MsgId = "260399";
    String CorrelId = "260399/2";
    ...
    /* set up a parameters object to match with */
    /* only interested in msgs*/
    MQeFields filter = new MQeFields();
    /* with this message Id*/
    filter.putArrayOfByte( MQe.Msg_MsgID, asciiToByte( MsgId ) );
    /* & this correlation Id */
    filter.putArrayOfByte ( MQe.Msg_CorrelID, asciiToByte( CorrelId ) );
    ...
    /* wait 10 seconds for a msg to arrive */

    ...
```

MQeQueueManager

```
MQeMsgObject msgObj = qmgr.waitForMessage( null, "MyQueue", filter,
    null, 0, 10000 );
}
...
```

Related functions

- [getMessage](#)

MQeQueueManagerConfigure

This class is used to configure a queue manager. It is used to create and delete queue managers and their default queues.

Package com.ibm.mqe

Constructor summary

Constructor	Purpose
MQeQueueManagerConfigure	Instantiates the QueueManagerConfigure object

Method summary

Method	Purpose
activate	Activates the configuration object
close	Closes the configuration object
defineDefaultAdminQueue	Defines a standard default <i>administration queue</i> in the registry
defineDefaultAdminReplyQueue	Defines a standard default <i>administration reply queue</i> in the registry
defineDefaultDeadLetterQueue	Defines a standard default <i>dead letter queue</i> in the registry
defineDefaultSystemQueue	Defines a standard default local queue in the registry.
defineQueueManager	Defines a standard queue manager in the registry.
deleteAdminQueueDefinition	Deletes the <i>administration queue</i> from the registry.
deleteAdminReplyQueueDefinition	Deletes the <i>administration reply queue</i> from the registry.
deleteDeadLetterQueueDefinition	Deletes the <i>dead letter queue</i> from the registry.
deleteQueueManagerDefinition	Deletes the queue manager from the registry.
deleteStandardQMDefinitions	Deletes the queue manager and the standard queues from the registry.
deleteSystemQueueDefinition	Deletes the standard default local queue from the registry.
queueManagerExists	Checks whether the queue manager exists in the registry.
setChannelTimeout	Sets the Channel time-out value for the queue manager.
setChnlAttributeRuleName	Sets the name of the Channel Attribute Rule for the queue manager.
setDescription	Sets the description of the queue manager.

MQeQueueManagerConfigure

Syntax

- 1.

```
public MQeQueueManagerConfigure()
```

- 2.

MQeQueueManagerConfigure

```
public MQeQueueManagerConfigure( MqeFields startupParameters ) throws Exception  
3.  
public MQeQueueManagerConfigure( MqeFields startupParameters,  
                                String qStore ) throws Exception
```

Description

The constructors instantiate the queue manager configuration object. There are three forms of the constructor:

1. This form is designed for dynamic loading and must be followed by a call to **activate()**
2. This form can be used to only for the deletion of a queue manager.
3. This form can be used for the creation or deletion of a queue manager

Parameters

startupParameters

An **MQEFields** object containing the initialization parameters for the queue manager. These are described in **MQeQueueManager startupParameters**.

qStore

The location where the standard default queues are stored. This must be specified if a queue manager is being created. If a queue manager is being deleted this parameter can be *null*.

Return Values

none

Exceptions

Exception - thrown if there is a problem initializing the queue manager configure object

Example

```
MQeQueueManagerConfigure qmConfig1;  
qmConfig1 = new MQeQueueManagerConfigure();  
  
try  
{  
    MQeQueueManagerConfigure qmConfig2;  
    MQeFields parms = new MQeFields();  
    // initialize the parameters  
    ...  
    qmConfig2 = new MQeQueueManagerConfigure( parms );  
}  
catch (Exception e)  
{ ... }  
  
try  
{  
    MQeQueueManagerConfigure qmConfig3;  
    MQeFields parms = new MQeFields();  
    // initialize the parameters  
    ...  
    qmConfig3 = new MQeQueueManagerConfigure( parms, "qmName" + File.separator +  
                                         "Queues" + File.separator );  
}  
catch (Exception e)  
{ ... }
```

MQeQueueManagerConfigure activate

Syntax

```
public void activate( MqeFields startupParameters, String qStore ) throws Exception
```

MQeQueueManagerConfigure

Description

This method initializes the object ready to configure a queue manager.

Parameters

startupParameters

An **MQeFields** object containing the initialization parameters for the queue manager. These are described in **MQeQueueManager startupParameters**.

qStore

The location where the standard default queues are stored. This must be specified if a queue manager is being created. If a queue manager is being deleted, this parameter can be *null*.

Return Values

none

Exceptions

Exception - is thrown if there is a problem initializing the object.

Example

```
try
{
    MQeQueueManagerConfigure qmConfig;
    MQeFields parms = new MQeFields();
    // initialize the parameters
    ...
    qmConfig = new MQeQueueManagerConfigure( );
    qmConfig.activate( parms, "qmName" + File.separator +
                      "Queues" + File.separator );
}
catch (Exception e)
{ ... }
```

MQeQueueManagerConfigure close

Syntax

```
public void close()
```

Description

This method closes the configuration object. An attempt to use the object after it has been closed will result in an exception. The configuration object must be closed before the queue manager itself can be activated.

Parameters

none

Return Values

none

Exceptions

none

Example

```
try
{
    MQeQueueManagerConfigure qmConfig;
    MQeFields parms = new MQeFields();
    // initialize the parameters
    ...
    qmConfig = new MQeQueueManagerConfigure( parms, "qmName" + File.separator +
                                              "Queues" + File.separator );
}
...
```

MQeQueueManagerConfigure

```
        qmConfig.close();
    }
    catch (Exception e)
    { ... }
```

MQeQueueManagerConfigure defineDefaultAdminQueue

Syntax

```
public void void defineDefaultAdminQueue( ) throws Exception throws Exception
```

Description

This method defines a standard *administration queue* in the registry for the queue manager. The queue itself will be created the first time it is accessed from the running queue manager. An exception is thrown if the queue already exists.

Parameters

none

Return Values

none

Exceptions

MQeException

Is thrown if the MQeQueueManagerConfigure object has not been activated or if the queue already exists in the queue manager's registry.

Exception

Is thrown for other errors.

Example

```
try
{
    MQeQueueManagerConfigure qmConfig;
    MQeFields parms = new MQeFields();
    // initialize the parameters
    ...
    qmConfig = new MQeQueueManagerConfigure( parms, "qmName" + File.separator +
                                              "Queues" + File.separator );
    qmConfig.defineDefaultAdminQueue();
    ...
    qmConfig.close();
}
catch (Exception e)
{ ... }
```

MQeQueueManagerConfigure defineDefaultAdminReplyQueue

Syntax

```
public void defineDefaultAdminReplyQueue ( ) throws Exception
```

Description

This method defines a standard *administration reply queue* in the registry for the queue manager. The queue itself will be created the first time it is accessed from the running queue manager. An exception is thrown if the queue already exists.

Parameters

none

Return Values

none

Exceptions**MQeException**

Is thrown if the MQeQueueManagerConfigure object has not been activated, or if the queue already exists in the queue manager's registry

Exception

Is thrown for other errors.

Example

```
try
{
    MQeQueueManagerConfigure qmConfig;
    MQeFields parms = new MQeFields();
    // initialize the parameters
    ...
    qmConfig = new MQeQueueManagerConfigure( parms, "qmName" + File.separator +
                                             "Queues" + File.separator );
    qmConfig.defineDefaultAdminReplyQueue();
    ...
    qmConfig.close();
}
catch (Exception e)
{ ... }
```

MQeQueueManagerConfigure defineDefaultDeadLetterQueue**Syntax**

```
public void defineDefaultDeadLetterQueue ( ) throws Exception
```

Description

This method defines a standard *dead letter queue* in the registry for the queue manager. The queue itself will be created the first time it is accessed from the running queue manager. An exception is thrown if the queue already exists.

Parameters

none

Return Values

none

Exceptions**MQeException**

Is thrown if the MQeQueueManagerConfigure object has not been activated, or if the queue already exists in the queue manager's registry

Exception

Is thrown for other errors.

Example

```
try
{
    MQeQueueManagerConfigure qmConfig;
    MQeFields parms = new MQeFields();
    // initialize the parameters
    ...
    qmConfig = new MQeQueueManagerConfigure( parms, "qmName" + File.separator +
                                              "Queues" + File.separator );
    qmConfig.defineDefaultDeadLetterQueue();
    qmConfig.close();
}
catch (Exception e)
{ ... }
```

MQeQueueManagerConfigure

MQeQueueManagerConfigure defineDefaultSystemQueue

Syntax

```
public void defineDefaultSystemQueue( ) throws Exception
```

Description

This method defines a standard local queue, called SYSTEM.DEFAULT.LOCAL.QUEUE, in the registry for the queue manager. The queue itself will be created the first time it is accessed from the running queue manager. An exception is thrown if the queue already exists.

Parameters

none

Return Values

none

Exceptions

MQException

Is thrown if the MQeQueueManagerConfigure object has not been activated, or if the queue already exists in the queue manager's registry

Exception

Is thrown for other errors.

Example

```
try
{
    MQeQueueManagerConfigure qmConfig;
    MQeFields parms = new MQeFields();
    // initialize the parameters
    ...
    qmConfig = new MQeQueueManagerConfigure( parms, "qmName" + File.separator +
                                             "Queues" + File.separator );
    qmConfig.defineDefaultSystemQueue();
    ...
    qmConfig.close();
}
catch (Exception e)
{ ... }
```

MQeQueueManagerConfigure defineQueueManager

Syntax

```
public void defineQueueManager( ) throws Exception
```

Description

This method creates a definition for the queue manager in the registry. This is required before the queue manager itself can be activated. An exception is thrown if the queue manager definition already exists.

Parameters

none

Return Values

none

Exceptions

MQException

Is thrown if the MQeQueueManagerConfigure object has not been activated, or if the queue manager definition already exists in the registry.

MQeQueueManagerConfigure

Exception Is thrown for other errors.

Example

```
try
{
    MQeQueueManagerConfigure qmConfig;
    MQeFields parms = new MQeFields();
    // initialize the parameters
    ...
    qmConfig = new MQeQueueManagerConfigure( parms, "qmName" + File.separator +
                                              "Queues" + File.separator );
    qmConfig.setDescription( "queue manager for " + qmName );
    qmConfig.defineQueueManager();
    qmConfig.close();
}
catch (Exception e)
{ ... }
```

MQeQueueManagerConfigure deleteAdminQueueDefinition

Syntax

```
public void deleteAdminQueueDefinition( ) throws Exception
```

Description

This method deletes the definition of the standard *administration queue* from the registry for the queue manager. No error is generated if the definition does not exist. The queue itself is not removed.

The queue cannot be accessed if it is not defined in the registry. The definition can be recreated with **defineDefaultAdminQueue()**.

Parameters

none

Return Values

none

Exceptions

MQeException

Is thrown if the **MQeQueueManagerConfigure** object has not been activated, or if there is an error deleting the registry entry.

Example

```
try
{
    MQeQueueManagerConfigure qmConfig;
    MQeFields parms = new MQeFields();
    // initialize the parameters
    ...
    qmConfig = new MQeQueueManagerConfigure( parms, null );
    qmConfig.deleteAdminQueueDefinition();
    ...
    qmConfig.close();
}
catch (Exception e)
{ ... }
```

MQeQueueManagerConfigure deleteAdminReplyQueueDefinition

Syntax

```
public void deleteAdminReplyQueueDefinition ( ) throws Exception
```

MQeQueueManagerConfigure

Description

This method deletes the definition of the standard *administration reply queue* from the registry for the queue manager. No error is generated if the definition does not exist. The queue itself is not removed.

The queue cannot be accessed if it is not defined in the registry. The definition can be recreated with **defineDefaultAdminReplyQueue()**.

Parameters

none

Return Values

none

Exceptions

MQeException

Is thrown if the MQeQueueManagerConfigure object has not been activated, or if there is an error deleting the registry entry.

Example

```
try
{
    MQeQueueManagerConfigure qmConfig;
    MQeFields parms = new MQeFields();
    // initialize the parameters
    ...
    qmConfig = new MQeQueueManagerConfigure( parms, null );
    qmConfig.deleteAdminReplyQueueDefinition();
    ...
    qmConfig.close();
}
catch (Exception e)
{ ... }
```

MQeQueueManagerConfigure deleteDeadLetterQueueDefinition

Syntax

```
public void deleteDeadLetterQueueDefinition ( ) throws Exception
```

Description

This deletes the definition of the standard *dead letter queue* from the registry for the queue manager. No error is generated if the definition does not exist. The queue itself is not removed.

The queue cannot be accessed if it is not defined in the registry. The definition can be recreated with **defineDefaultDeadLetterQueue()**.

Parameters

none

Return Values

none

Exceptions

MQeException

Is thrown if the MQeQueueManagerConfigure object has not been activated, or if there is an error deleting the registry entry.

Example

```
try
{
    MQeQueueManagerConfigure qmConfig;
    MQeFields parms = new MQeFields();
    // initialize the parameters
    ...
    qmConfig = new MQeQueueManagerConfigure( parms, null );
    qmConfig.deleteDeadLetterQueueDefinition();
    ...
    qmConfig.close();
}
catch (Exception e)
{ ... }
```

MQeQueueManagerConfigure deleteQueueManagerDefinition

Syntax

```
public void deleteQueueManagerDefinition ( ) throws Exception
```

Description

This method deletes the definition of the queue manager from its registry. No error is generated if the definition does not exist.

The queue cannot be accessed if it is not defined in the registry. The definition can be recreated with **defineQueueManager()**.

Parameters

none

Return Values

none

Exceptions

MQeException

is thrown if the MQeQueueManagerConfigure object has not been activated, or if there is an error deleting the registry entry.

Example

```
try
{
    MQeQueueManagerConfigure qmConfig;
    MQeFields parms = new MQeFields();
    // initialize the parameters
    ...
    qmConfig = new MQeQueueManagerConfigure( parms, null );
    ...
    qmConfig.deleteQueueManagerDefinition();
    qmConfig.close();
}
catch (Exception e)
{ ... }
```

MQeQueueManagerConfigure deleteStandardQMDefinitions

Syntax

```
public void deleteStandardQMDefinitions ( ) throws Exception
```

Description

This deletes the definitions of the standard default queues and the queue manager itself from the registry. No error is generated if the definitions do not exist.

This method is provided for convenience, it is equivalent to:

MQeQueueManagerConfigure

```
deleteDeadLetterQueueDefinition();
deleteSystemQueueDefinition();
deleteAdminQueueDefinition();
deleteAdminReplyQueueDefinition();
deleteQueueManagerDefinition();
```

Parameters

none

Return Values

none

Exceptions

MQeException

Is thrown if the MQeQueueManagerConfigure object has not been activated, or if there is an error deleting the registry entries.

Example

```
try
{
    MQeQueueManagerConfigure qmConfig;
    MQeFields parms = new MQeFields();
    // initialize the parameters
    ...
    qmConfig = new MQeQueueManagerConfigure( parms, null );
    qmConfig.deleteStandardQMDefinitions();
    qmConfig.close();
}
catch (Exception e)
{ ... }
```

MQeQueueManagerConfigure deleteSystemQueueDefinition

Syntax

```
public void deleteSystemQueueDefinition ( ) throws Exception
```

Description

This deletes the definition of the default local queue, SYSTEM.DEFAULT.LOCAL.QUEUE, from the registry for the queue manager. No error is generated if the definition does not exist. The queue itself is not removed.

The queue cannot be accessed if it is not defined in the registry. The definition can be recreated with **defineDefaultSystemQueue()**

Parameters

none

Return Values

none

Exceptions

MQeException

Is thrown if the MQeQueueManagerConfigure object has not been activated, or if there is an error deleting the registry entry.

Example

MQeQueueManagerConfigure

```
try
    MQeQueueManagerConfigure qmConfig;
    MQeFields parms = new MQeFields();
    // initialize the parameters
    ...
    qmConfig = new MQeQueueManagerConfigure( parms, null );
    qmConfig.deleteSystemQueueDefinition();
    ...
    qmConfig.close();
}
catch (Exception e)
{ ... }
```

MQeQueueManagerConfigure queueManagerExists

Syntax

```
public boolean queueManagerExists( ) throws Exception
```

Description

This method checks whether the queue manager definition exists in the registry.

Parameters

none

Return Values

true	If the queue manager definition exists in the registry.
false	If the queue manager definition does not exist in the registry.

Exceptions

MQeException

Is thrown if the MQeQueueManagerConfigure object has not been activated, or if there is an error reading the registry.

Example

```
try
{
    MQeQueueManagerConfigure qmConfig;
    MQeFields parms = new MQeFields();
    // initialize the parameters
    ...
    qmConfig = new MQeQueueManagerConfigure( parms, null );
    if ( queueManagerExists() )
    {
        ...
        qmConfig.close();
    }
    catch (Exception e)
    { ... }
```

MQeQueueManagerConfigure setChannelTimeout

Syntax

```
public void setChannelTimeout( long ChnlTimeout )
```

Description

This sets the channel time-out value for the queue manager.

MQeQueueManagerConfigure

This method must be called before **defineQueueManager()**, otherwise it is ignored.

Parameters

ChnlTimeout The Channel time-out value in milliseconds.

Return Values

none

Exceptions

none

Example

```
try
{
    MQeQueueManagerConfigure qmConfig;
    MQeFields parms = new MQeFields();
    // initialize the parameters
    ...
    qmConfig = new MQeQueueManagerConfigure( parms, "qmName" + File.separator +
                                             "Queues" + File.separator );
    qmConfig.setChannelTimeout( 3600 * 1000 );
    qmConfig.defineQueueManager();
    qmConfig.close();
}
catch (Exception e)
{ ... }
```

MQeQueueManagerConfigure setChnlAttributeName

Syntax

```
public void setChnlAttributeName( String ChnlAttrRuleName ) throws MQeException
```

Description

This method sets the name of the **Channel Attribute Rule** class for the queue manager.

This method must be called before **defineQueueManager()**, otherwise it is ignored.

Parameters

ChnlAttrRuleName

The name of the **Channel Attribute Rule** class.

Return Values

none

Exceptions

MQeException

Is thrown if the name is invalid.

Example

```
try
{
    MQeQueueManagerConfigure qmConfig;
    MQeFields parms = new MQeFields();
    // initialize the parameters
    ...
    qmConfig = new MQeQueueManagerConfigure( parms, "qmName" + File.separator +
                                             "Queues" + File.separator );
    qmConfig.setChnlAttributeName( "Examples.Rules.AttributeRule" );
    qmConfig.defineQueueManager();
```

MQeQueueManagerConfigure

```
    qmConfig.close();
}
catch (Exception e)
{ ... }
```

MQeQueueManagerConfigure setDescription

Syntax

```
public void setDescription (String description )
```

Description

This method sets the description for the queue manager

This method must be called before **defineQueueManager()**, otherwise it is ignored.

Parameters

description The new description

Return Values

none

Exceptions

none

Example

```
try
{
    MQeQueueManagerConfigure qmConfig;
    MQeFields parms = new MQeFields();
    // initialize the parameters
    ...
    qmConfig = new MQeQueueManagerConfigure( parms, "qmName" + File.separator +
                                              "Queues" + File.separator );
    qmConfig.setDescription( "queue manager for " + qmName );
    qmConfig.defineQueueManager();
    qmConfig.close();
}
catch (Exception e)
{ ... }
```

MQeQueueManagerRule

MQeQueueManagerRule

This class contains methods that are invoked when the queue manager performs certain operations. The rules can affect the outcome of these operations. This class contains the default queue manager rules. Typically, these default rules would be overridden to provide appropriate behavior for a given MQe solution.

Package

com.ibm.mqe

Method summary

Method	Purpose
activateQueues	This rule decides whether to activate certain queues at queue manager startup time. The queues that can be activated are remote asynchronous queue definitions, <i>home server queues</i> , and <i>store and forward queues</i> .
addQueue	This rule is called when a new queue is added to the queue manager.
deleteMessage	This rule is called when a delete message operation occurs.
getMessage	This rule is called when a get message operation occurs.
getRetryCount	This rule returns the number of retry attempts for a failed network operation.
peerConnection	This rule is called when the queue manager's peer channel listener receives an incoming connection request.
putMessage	This rule is called when a put message operation occurs.
queueManagerActivate	This rule is called when the queue manager is activated.
queueManagerClose	This rule is called when the queue manager is closed.
removeQueue	This rule is called when a queue is to be removed from the queue manager.
transmit	This rule is called for each remote asynchronous queue definition when a transmission of pending messages is taking place. The rule allows transmission to be disabled on a per-queue basis.
triggerTransmission	This rule returns a boolean value which denotes whether or not to allow, at this time, the transmission of pending messages stored within remote asynchronous queue definitions
undo	This rule is called when an Undo operation occurs.

MQeQueueManagerRule activateQueues

Syntax

```
public boolean activateQueues()
```

Description

This rule determines whether to activate certain queues at queue manager startup time. The queues that can be activated are remote asynchronous queue definitions, *home server queues*, and *store and forward queues*.

Activating these queues means that an attempt is made to transmit any messages that they hold. Queues are normally not activated until an operation is performed on them. It can be useful to activate these queues

MQeQueueManagerRule

immediately on queue manager startup because they may have transmission timer threads, or other functions associated with them.

Parameters

none

Return values

A boolean value denoting whether to activate certain queues at queue manager startup time. The queue manager acts on the value returned

Exceptions

none

Examples

```
class exampleRules extends MQeQueueManagerRule
{
    ...
    /* cheap rate transmission period start and end times */
    protected int cheapRatePeriodStart = 18;      /* 18:00 hrs */
    protected int cheapRatePeriodEnd = 9;           /* 09:00 hrs */

    public boolean activateQueues()
    {
        super.activateQueues();
        if ( timeToTransmit() ) /* if OK to transmit */
            return true; /* then activate queues */
        else /* otherwise*/
            return false; /* don't activate queues */
    }

    /* This method determines if the current time is inside the defined */
    /* cheap rate period of transmission */
    protected boolean timeToTransmit()
    {
        /* get current time */
        long currentTimeLong = System.currentTimeMillis();

        Date date = new Date( currentTimeLong );
        Calendar calendar = Calendar.getInstance();
        calendar.setTime( date );

        /* get hour */
        int hour = calendar.get( Calendar.HOUR_OF_DAY );

        if ( hour >= cheapRatePeriodStart || hour < cheapRatePeriodEnd )
            return true; /* cheap rate */
        else
            return false; /* not cheap rate */
    }
    ...
}
```

MQeQueueManagerRule addQueue

Syntax

```
public void addQueue( MQeQueue queue ) throws Exception
```

Description

This rule is called when a queue is added to the queue manager. The rule is called before the addition of the queue, and so the rule is able to reject the operation by throwing an exception.

Parameters

MQeQueueManagerRule

queue A **MQeQueue** object that is being added to the queue manager.

Return values
none

Exceptions
none

Examples

```
class exampleRules extends MQeQueueManagerRule
{
    ...
    /* Don't allow asynchronous queues to be added to this Queue Manager */
    public void addQueue( MQeQueue queue ) throws Exception
    {
        super.addQueue( queue );
        int accessMode = queue.getAccessMode();
        if ( accessMode == MQeQueue.QueueASynchronous )
            throw new MQeException( Except_Rule, "No Asynch Queues" );
    }
    ...
}
```

Related functions
[removeQueue](#)

MQeQueueManagerRule deleteMessage

Syntax

```
public void deleteMessage( String destQMgrName,
                           String destQName,
                           MQeFields filter ) throws Exception
```

Description

This rule is called when a delete message operation takes place. The rule is called before the operation takes place, and so the rule can stop the operation by throwing an exception.

Parameters

destQMgrName

A String containing the name of the queue manager that owns the queue on which this operation takes place. A value of *null* denotes that the local queue manager is to be used

destQName

A String containing the name of the queue on which this operation takes place

filter

This is the filter to be used for the delete message operation. It is an **MQeFields** object containing message fields (for example, priority and messageID)

Return values
none

Exceptions
none

Examples

```
class exampleRules extends MQeQueueManagerRule
{
    ...
    /* This rule blocks message deletes on 'TopSecretQueue' */
}
```

MQeQueueManagerRule

```
public void deleteMessage( String destQMgr, String destQ, MQeFields filter )
{
    super.deleteMessage( destQMgr, destQ, filter );
    if( destQMgr == null || destQMgr.equals( Owner.GetName() ) )
    {
        if ( destQ.equals( "TopSecretQueue" ) )
            throw new MQeException( Except_Rule, "Can't delete on this Queue" );
    }
}
...
}
```

MQeQueueManagerRule getMessage

Syntax

```
public void getMessage( String destQMgrName,
                        String destQName,
                        MQeFields filter,
                        MQeAttribute attribute,
                        long confirmId ) throws Exception
```

Description

This rule is called when a get message operation takes place. The rule is called before the operation takes place, and so the rule can stop the operation by throwing an exception.

Parameters

destQMgrName

A String containing the name of the queue manager that owns the queue on which this operation takes place. A value of *null* denotes that the local queue manager is to be used

destQName

A String containing the name of the queue on which this operation takes place

filter

This is the filter to be used for the get message operation. It is an **MQeFields** object containing message fields (for example, priority and messageID)

attribute

An **MQe Attribute** object used to provide message-level security

confirmId

A long value denoting whether or not to use guaranteed message delivery. A nonzero value leaves the message locked on the target queue, it is not removed until a subsequent confirm flow. A value of zero removes the message from the target queue without the need for a subsequent confirm.

This value is also used in the event of a get message failure. The application should store the value used, and use it to reset the messages (via the **undo** command) matched by the Get to their previous state.

Return values

none

Exceptions

none

Example

MQeQueueManagerRule

```
class exampleRules extends MQeQueueManagerRule
{
    ...
    /* This rule only allows GETs from 'OutboundQueue', if a password is */
    /* supplied as part of the filter                                         */
    public void getMessage( String destQMGr, String destQ, MQeFields filter,
                           MQeAttribute attr, long confirmId )
    {
        super.getMessage( destQMGr, destQ, filter, attr, confirmId );
        if ( destQMGr.equals( Owner.GetName() ) && destQ.equals( "OutboundQueue" ) )
        {
            if ( !(filter.Contains( "Password" ) ) )
                throw new MQeException( Except_Rule, "Password not supplied" );
            else
            {
                String pwd = filter.getAscii( "Password" );
                if ( !(pwd.equals( "1234" ) ) )
                    throw new MQeException( Except_Rule, "Incorrect password" );
            }
        }
        ...
    }
}
```

Related functions
putMessage

MQeQueueManagerRule getRetryCount

Syntax

```
public int getRetryCount()
```

Description

This rule returns the number of times to retry a network operation. The queue manager calls this rule when creating a new channel object. The value returned by this rule is passed to the channel, and it is used in the event of a network operation failure.

Parameters

none

Return values

An integer value that contains the number of times to retry a network operation. The queue manager acts on the value returned.

Exceptions

none

Examples

```
class exampleRules extends MQeQueueManagerRule
{
    ...
    public int getRetryCount()
    {
        return (2); /* retry a network operation twice */
    }
    ...
}
```

MQeQueueManagerRule peerConnection

Syntax

```
public void peerConnection( String qmGrName )
```

Description

This method is called when a queue manager's peer listener detects an incoming connection request from another MQSeries Everyplace queue manager. The connection must be made over an **MQePeerChannel**, or its descendant.

By throwing an exception the rule can block the connection attempt.

Parameters

qmgrName A String containing the name of the MQSeries Everyplace queue manager that is requesting a connection

Return values

none

Exceptions

none

Examples

```
class exampleRules extends MQeQueueManagerRule
{
    ...
    public void peerConnection( String qmqrName )
    {
        /* block any connection attempt from 'RogueQMgr' */
        if ( qmqrName.equals( "RogueQMgr" ) )
            throw new MQeException( Except_Rule, "Connection not allowed" );
    }
    ...
}
```

MQeQueueManagerRule putMessage**Syntax**

```
public void putMessage( String destQMgrName,
                        String destQName,
                        MQeMsgObject msg,
                        MQeAttribute attribute,
                        long confirmId ) throws Exception
```

Description

This rule is called when a put message operation takes place. The rule is called before the operation takes place, so the rule can stop the operation by throwing an exception.

Parameters**destQMgrName**

A String containing the name of the queue manager that owns the queue on which this operation takes place. A value of *null* denotes that the local queue manager is to be used

destQName

A String containing the name of the queue on which this operation takes place

msg

The message object that is being placed on the target queue

attribute

null, or an **MQeAttribute** object defining the authenticator, cryptor, and compressor to be associated with this message.

confirmId

A long value denoting whether or not to use assures message delivery. A nonzero value locks the message on

MQeQueueManagerRule

the target queue, it is not made visible until a subsequent confirm flow. A value of zero transmits the message without the need for a subsequent confirm.

Also, this value can be used in the event of a put message failure. By passing this value to the undo command, the application can remove any messages that were left in an incomplete state by the failed put operation.

Return values

none

Exceptions

none

Examples

```
class exampleRules extends MQeQueueManagerRule
{
    ...
    /* Only allow msgs containing an ID field to be placed on the Queue */
    public void putMessage( String destQMgr, String destQ, MQeMsgObject msg,
                           MQeAttribute attribute, long confirmId )
    {
        if ( !(msg.Contains( MQe.Msg_MsgId )) )
            throw new MQeException( Except_Rule, "Msg must contain an ID" );
    }
    ...
}
```

Related functions

getMessage

MQeQueueManagerRule queueManagerActivate

Syntax

```
MQeQueueManagerRule queueManagerActivate
```

Description

This rule is called when the queue manager is activated.

Parameters

none

Return values

none

Exceptions

none

Examples

```
class exampleRules extends MQeQueueManagerRule
{
    ...
    /* default interval between triggers is 60 minutes */
    protected int triggerInterval = 360000;
    /* background thread reference */
    protected Thread th = null;
    /* Called when the Queue manager is activated */
    public void queueManagerActivate( ) throws Exception
    {
        super.queueManagerActivate();
        /* background thread which triggers transmission */
        th = new Thread( this, "TriggerThread" );
        th.start(); /* start timer thread */
    }
}
```

MQeQueueManagerRule

```
}

/* Called when a Queue manager Close is called */
public void queueManagerClose( ) throws Exception
{
    super.QueueManagerClose();
    th.stop(); /* stop background thread on QMgr close*/
}

/* Background thread run method */
/* Triggers transmission every interval until thread is stopped */
public void run()
{
    try
    {
        while ( true ) /* sleep for specified interval */
        {
            Thread.sleep( triggerInterval );
            /* check if ok to transmit */
            if ( triggerTransmission( 0, null ) )
                /* trigger transmission on QMgr (which is rule owner) */
                ((MQeQueueManager)Owner).triggerTransmission();
        }
    } catch ( Exception e )
    {
        e.printStackTrace( System.err );
    }
}
...
}
```

Related functions

[queueManagerClose](#)

MQeQueueManagerRule queueManagerClose

Syntax

```
public void queueManagerClose() throws Exception
```

Description

This rule is called when the queue manager is closing.

Parameters

none

Return values

none

Exceptions

none

Examples

```
class exampleRules extends MQeQueueManagerRule
{
    ...
    /* default interval between triggers is 60 minutes */
    protected int triggerInterval = 360000;
    /* background thread reference */
    protected Thread th = null;
    /* Called when the Queue manager is activated */
    public void queueManagerActivate( ) throws Exception
    {
        super.queueManagerActivate();
        /* background thread which triggers transmission */
        th = new Thread( this, "TriggerThread" );
        th.start(); /* start timer thread */
    }
}
```

MQeQueueManagerRule

```
}

/* Called when a Queue manager Close is called */ 
public void queueManagerClose( ) throws Exception
{
    super.queueManagerClose();
    th.stop(); /* stop background thread on QMgr close*/
}

/* Background thread run method */ 
/* Triggers transmission every interval until thread is stopped */
public void run()
{
    try
    {
        while ( true )
        {
            Thread.sleep( triggerInterval ); /* sleep for specified interval */
            /* check if ok to transmit */
            if ( triggerTransmission( 0, null ) )
                /* trigger transmission on QMgr (which is rule owner) */
                ((MQeQueueManagerOwner).triggerTransmission());
        }
    } catch ( Exception e )
    {
        e.printStackTrace( System.err );
    }
}
...
}
```

Related functions

[queueManagerActivate](#)

MQeQueueManagerRule removeQueue

Syntax

```
public void removeQueue( MQeQueue queue) throws Exception
```

Description

This rule is called when a queue is to be removed from the queue manager. The rule is called before the removal of the queue, so the rule is able to reject the operation by throwing an exception.

Parameters

queue	An MQeQueue object that is to be removed from the queue manager
--------------	--

Return values

none

Exceptions

none

Examples

```
class exampleRules extends MQeQueueManagerRule
{
    ...
    /* This rule prevents the removal of the Payroll Queue */
    public void removeQueue( MQeQueue queue ) throws Exception
    {
        if ( queue.getQueueName().equals( "PayrollQueue" ) )
```

MQeQueueManagerRule

```
        throw new MQeException( Except_Rule, "Can't delete this queue" );
    }
    ...
}
```

Related functions
addQueue

MQeQueueManagerRule transmit

Syntax

```
public boolean transmit( MQeQueue queue )
```

Description

When a queue manager attempts to send all its pending messages, this rule is called for each queue that contains messages awaiting transmission. This rule decides whether to allow the transmission of those messages for the supplied queue.

Parameters

queue	A MQeQueue object that holds messages awaiting transmission.
--------------	---

Return values

A boolean value denoting whether to allow the transmission of the messages held on this queue. The queue manager acts on the value returned.

Exceptions

none

Examples

```
class exampleRules extends MQeQueueManagerRule
{
    ...
    /* cheap rate transmission period start and end times */
    protected int cheapRatePeriodStart = 18;           /* 18:00 hrs */
    protected int cheapRatePeriodEnd = 9;               /* 09:00 hrs */

    /* This rule allows queue transmission if current time is during the */
    /* cheap rate transmission period */
    /* If the current time is not during the cheap rate transmission period */
    /* then transmission is only allowed if the queue is high priority */
    public boolean transmit( MQeQueue queue )
    {
        if ( timeToTransmit() )
            return true;                                /* cheap rate */
        else
            if ( queue.GetPriority() > 4 )
                return true;                            /* high priority Q */
    }

    /* This method determines if the current time is inside the defined */
    /* cheap rate period of transmission */
    protected boolean timeToTransmit()
    {
        /* get current time */
        long currentTimeLong = System.currentTimeMillis();

        Date date = new Date( currentTimeLong );
        Calendar calendar = Calendar.getInstance();
        calendar.setTime( date );

        /* get hour */
    }
}
```

MQeQueueManagerRule

```
int hour = calendar.get( Calendar.HOUR_OF_DAY );  
  
if ( hour >= cheapRatePeriodStart || hour < cheapRatePeriodEnd )  
    return true; /* cheap rate */  
else  
    return false; /* not cheap rate */  
}  
...  
}
```

Related functions
triggerTransmission

MQeQueueManagerRule triggerTransmission

Syntax

```
public boolean triggerTransmission( int noofMsgs, MQeFields msgFields )
```

Description

This method authorizes the transmission of pending messages stored on remote asynchronous queue definitions within the queue manager.

This rule is invoked by the queue manager in two situations .

- When the queue manager is instructed to transmit all of its pending messages (using the **MQeQueueManager.triggerTransmission()** method)
- When a message is sent to a remote queue that is defined as asynchronous. The queue manager invokes this rule to see whether to transmit all pending messages

Parameters

noofMsgs The number of messages awaiting transmission on remote asynchronous queues

msgFields This parameter is *null* if this rule has been invoked because the queue manager has been instructed to transmit all of its pending messages (using the **MQeQueueManager.triggerTransmission()** method).

If this rule has been invoked because of the arrival of a message on a remote asynchronous queue definition then this parameter is an **MQeFields** object containing certain fields from the newly-arrived message.

The fields present in the parameter are: .

- Message UID (Origin queue manager + Timestamp)
- Message ID (if present in the original message)
- Correlation ID (if present in the original message)
- Priority (if present in the original message)

.

Return values

A boolean value denoting whether the rule allows transmission of pending messages at this time. The queue manager acts upon the value returned.

Exceptions

none

Examples

MQeQueueManagerRule

```
class exampleRules extends MQeQueueManagerRule
{
    ...
    /* default interval between triggers is 60 minutes */
    protected int triggerInterval = 360000;
    /* background thread reference */
    protected Thread th = null;
    /* Called when the Queue manager is activated */
    public void queueManagerActivate( ) throws Exception
    {
        super.queueManagerActivate();
        /* background thread which triggers transmission */
        th = new Thread( this, "TriggerThread" );
        th.start(); /* start timer thread */
    }

    /* Called when a Queue manager Close is called */
    public void queueManagerClose( ) throws Exception
    {
        super.queueManagerClose();
        th.stop(); /* stop background thread on QMgr close*/
    }

    /* Background thread run method */
    /* Triggers transmission every interval until thread is stopped */
    public void run()
    {
        try
        {
            while ( true )
            {
                /* sleep for specified interval */
                Thread.sleep( triggerInterval );
                /* check if ok to transmit */
                if ( triggerTransmission( 0, null ) )
                    /* trigger transmission on QMgr (which is rule owner) */
                    ((MQeQueueManager)Owner).triggerTransmission();
            }
        } catch ( Exception e )
        {
            e.printStackTrace( System.err );
        }
    }

    /* Decides if transmission of messages is allowed */
    public boolean triggerTransmission( int noOfMsgs, MQeFields msgFields )
    {
        return true; /* always allow transmission */
    }
    ...
}
```

Related functions
transmit

MQeQueueManagerRule undo

Syntax

```
public void undo(String destQMgrName,
                 String destQName,
                 long confirmId ) throws Exception
```

Description

This rule is called when an undo message operation takes place. The rule is called before the operation takes place, so the rule can stop the operation by throwing an exception.

MQeQueueManagerRule

Parameters

destQMgrName

A String containing the name of the queue manager that owns the queue on which this operation takes place. A value of *null* denotes that the local queue manager is to be used

destQName

A String containing the name of the queue on which this operation takes place

confirmId

A long value that was the confirm Id used by the operation which is being undone. All messages matching this confirm Id are restored to their previous state

Return values

none

Exceptions

none

Examples

```
class exampleRules extends MQeQueueManagerRule
{
    ...
    public void undo( String destQMgr, String destQ, long confirmId )
    {
        /* log the undo event */
        log( MQe_Log_Warning, Event_QueueManager_Undo,
              destQMgr + "+" + destQ );
    }
    ...
}
```

MQeQueueRule

Queue rules control the behaviour of MQSeries Everyplace queues. The queue rules are activated by the queue when it is itself activated. During the operation of the queue, the rules are called when certain events occur, for example, when a message is put, a message expires, or a duplicate message arrives. The rules then determine how the queue handles these events.

The base set of queue rules are defined in this class, which should be extended if a solution wishes to alter queue behaviour.

Queues hold messages in a queue store, typically this would be a persistent type of storage, such as a disk drive, but it does not need to necessarily be so. The queue maintains an index entry for each message held in its queue store. The index entry consists of state information for the message, such as whether it is locked or unlocked. Also, certain message fields are stored in the index entry, these are known as index fields. The default index fields are, message unique ID, MQSeries message ID, MQSeries correlation ID, and message priority. These fields are stored because they are present in most messages, and storing the fields in memory yields faster message searching.

The `indexEntry()` rule is called whenever an index entry is created. This occurs whenever a new message is put onto the queue or at queue activation time when the queue reads any messages left in its queue store from a previous session. The rule allows a solution to alter the index entry when it is created, one use for this would be to add an extra field or fields into the index, thus improving message search times.

Queues maintain a use count, this is incremented when the queue is activated, and likewise decremented when the queue is closed. Also, the use count is incremented when a remote queue manager connects to a queue. The use count is decremented when the channel and transporter used to create this connection are destroyed. The `useCountChanged()` rule is called every time the use count is changed.

The messages held on the queue can be protected by an authenticator and cryptor. The messages can also be compressed by using a compressor. Together, the authenticator, cryptor, and compressor are known as the attributes of the queue, and they are defined by specifying an appropriate `MQeAttribute` object to be associated with the queue. The `attributeChange()` rule is called whenever an attempt is made to replace the queue's attribute.

Note: Changing a queue's attribute when it already holds messages stored using another attribute, may cause message loss, since the message may not be recoverable using the new attribute.

If a message has remained on the queue for a length of time greater than the queue's expiry interval, or if a message exceeds its own expiry interval then the `messageExpired()` rule is called. This rule then determines what happens to the message, but typically the message would be either deleted, or placed on a 'dead letter queue'.

Package

com.ibm.mqe

MQeQueueRule

Method summary

Method	Purpose
addListener	This rule is called when a message listener is attached to the queue.
attributeChange	This rule is called when an attempt is made to change the queue's attribute. The attribute defines the authenticator, cryptor and compressor used on the queue. Messages are stored using the attributes defined.
browseMessage	The rule decides whether to allow the message to be included in the set of messages returns to the application that issued the browse request.
deleteMessage	This rule is called when a delete message operation takes place.
duplicateMessage	This rule is called if a duplicate message is put onto the queue.
getMessage	This rule is called when a message is found that satisfies a get message request. The rule can decide whether the message should be allowed to satisfy the get message request.
getPendingMessage	This rule is called when a get pending message request is received.
indexEntry	This rule is called whenever an index entry is created
messageExpired	This rule is called when a message has exceeded either the queue's expiry interval, or it's own expiry interval. The rule then decides whether to expire the message, and what to do with the message if it has expired.
putMessage	This rule is called when a put message request is made.
queueActivate	This rule is called when the queue is activated.
queueClosed	This rule is called when the queue is closed.
removeListener	This rule is called when a message listener is removed from a queue.
resetMessageLock	This rule is called when a request is made to reset the lock state on a message. The message is reset to an unlocked state. This function can only be performed by MQSeries Administration. By throwing an exception the rule can prevent the reset from occurring.
undo	This rule is called when an undo operation occurs and it determines whether the message is to be included in the set of messages processed by the undo operation.
useCountChanged	This rule is called every time the use count is changed

MQeQueueRule addListener

Syntax

```
public void addListener( MQeMessageListenerInterface listener,  
                         MQeFields filter) throws Exception
```

Description

This rule is called when a message listener is attached to a queue. By throwing an exception the rule is able to reject the add listener request.

Parameters

MQeQueueRule

listener A reference to the object that is subscribing to MQSeries Everyplace message events. The object must implement **MQeMessageListenerInterface**.

filter *null* or an **MQeFields** object containing message fields. A value of *null* means that the listener wishes to receive events for all messages on the queue.

Specifying an **MQeFields** object containing message fields means that the listener is only interested in events concerning messages whose fields match those contained in the filter.

Return values

none

Exceptions

none

Examples

```
class exampleQueueRules extends MQeQueueRule
{
    ...
    /* This rule logs the addition of a message listener */
    public void addListener( MQeMessageListenerInterface listener,
                            MQeFields filter ) throws Exception
    {
        log( MQe_Log_Information, Event_Queue_AddMsgListener,
              "Added Listener on queue " +
              ((MQeQueue)owner).getQueueManagerName() + "+" +
              ((MQeQueue)owner).getQueueName() );
    }

    public void queueActivate()
    { /* create a new log file */
        try
        {
            logFile = new LogToDiskFile( "\log.txt" );
        }
        catch( Exception e )
        {
            e.printStackTrace( System.err );
        }
    }

    public void queueClose()
    { /* close log file */
        logFile.close();
    }
    ...
}
```

Related functions

- `removeListener`

MQeQueueRule attributeChange

Syntax

```
public void attributeChange( MQeAttribute attribute ) throws Exception
```

Description

This method is called when an attempt is made to change the queue's attribute. The attribute defines the authenticator, cryptor and compressor used on the queue. All messages are stored using the queue's attribute.

MQeQueueRule

By throwing an exception the rule is able to reject the attribute change request.

Parameters

attribute *null*, or an **MQeAttribute** object that defines the authenticator, cryptor and compressor that will be used on the queue, if the change is allowed. *null* means that no attribute will be used on the queue.

Return values

none

Exceptions

Example

```
class exampleQueueRules extends MQeQueueRule
{
    ...
    /* This rule only allows the queue's attribute to be changed if it was */
    /* not previously set */
    /* The queue object is the owner of the rule */
    public void attributeChange( MQeAttribute attribute ) throws Exception
    {
        if ( ((MQeQueue) owner).getQueueAttribute() != null )
            throw new MQeException( Except_Rule, "Attribute already set" );
    }
    ...
}
```

MQeQueueRule browseMessage

Syntax

```
public boolean browseMessage( MQeMsgObject msg,
                             long confirmId ) throws Exception
```

Description

A Browse Messages operation matches zero or more messages held on a queue. This method is called for every message matched. The rule decides whether to allow the message to be included in the set of messages returned to the application that issued the browse request.

If this rule throws an exception then the browse operation will be terminated.

Parameters

msg An **MQeMsgObject** containing the message being browsed.
confirmId A long value that is the confirm Id used on this browse operation. The confirm Id is used to restore messages in the event of a failure

Return values

A boolean value that denotes whether to allow this message to be included in the set of messages returned to the application that issued the browse request. .

True Allow the message to be included

False Do not allow the message to be included

Exceptions

Examples

```

class exampleQueueRules extends MQeQueueRule
{
    ...
    /* This rule only allows messages of type 'OrderResponse' to be browsed */
    public boolean browseMessage( MQeMsgObject msg,
                                 long confirmID ) throws Exception
    {
        /* get message type field */
        String msgType = msg.getAscii( "MsgType" );
        /* what message type is it? */
        if ( msgType.equals( "OrderResponse" ) )
            return (true); /* allow browse */
        else
            return (false); /* don't allow browse */
    }
    ...
}

```

MQeQueueRule deleteMessage**Syntax**

```
public void deleteMessage( MQeFields filter ) throws Exception
```

Description

This rule is called when a delete message operation takes place. By throwing an exception the rule can reject the delete message request.

Parameters

filter	An MQeFields object containing a message filter. The filter must contain the message's UID for the delete operation to be successful.
---------------	--

Return values

none

Exceptions**Example**

```

class exampleQueueRules extends MQeQueueRule
{
    ...
    /* This rule requires that the filter contain a password */
    public void deleteMessage( MQeFields filter ) throws Exception
    {
        if ( filter != null && filter.contains( "Password" ) )
        {
            String pswd = filter.getAscii( "Password" );
            if ( pswd.equals( "12345678" ) )
            { /* remove password from filter */
                filter.delete( "Password" );
                return;
            }
            else
                throw new MQeException( Except_Rule, "Incorrect password" );
        }
        throw new MQeException( Except_Rule, "No Password" );
    }
    ...
}

```

MQeQueueRule duplicateMessage**Syntax**

MQeQueueRule

```
public void duplicateMessage( MQeMsgObject msg,  
                           long confirmId ) throws Exception
```

Description

This rule is called if a duplicate message is put onto the queue.

Parameters

msg	An MQeMsgObject containing the duplicate message.
confirmId	A long value that is the confirm Id used on this put operation. The confirm Id is used to restore messages in the event of a failure

Return values

none

Exceptions

Examples

```
class exampleQueueRules extends MQeQueueRule  
{  
    ...  
    /* This rule logs the duplicate message exception */  
    public void duplicateMessage( MQeMsgObject msg,  
                                long confirmID ) throws Exception  
    {  
        /* get message UID */  
        MQeFields msgUID = msg.getMsgUIDFields();  
        /* log the duplicate message exception */  
        log( MQe_Log_Warning, Event_Queue_Duplicate,  
              msgUID.getAscii( MQe.Msg_OriginQMgr ) + " " +  
              msgUID.getLong( MQe.Msg_Time ) );  
    }  
  
    public void queueActivate()  
    { /* create a new log file */  
        try  
        {  
            logFile = new LogToDiskFile( "\log.txt" );  
        }  
        catch( Exception e )  
        {  
            e.printStackTrace( System.err );  
        }  
    }  
  
    public void queueClose()  
    { /* close log file */  
        logFile.close();  
    }  
  
    ...  
}
```

MQeQueueRule getMessage

Syntax

```
public boolean getMessage( MQeMsgObject msg,  
                           long confirmId ) throws Exception
```

Description

This rule is called when a message is found which satisfies a get message request. The rule can decide whether that message should be allowed to satisfy the get message request.

MQeQueueRule

If the rule does not allow the message to satisfy the get message request then the queue will search for another message that satisfies the request.

By throwing an exception the rule can terminate the get message request.

Parameters

msg	An MQeMsgObject containing a message that satisfies the get message request..
confirmId	A long value that is the confirm Id used on this get request. The confirm Id is used to restore messages in the event of a failure

Return values

none

Exceptions

none

Examples

```
class exampleRules extends MQeQueueManagerRule
{
    ...
    public void peerConnection( String qmgrName )
    {
        /* block any connection attempt from 'RogueQMgr' */
        if ( qmgrName.equals( "RogueQMgr" ) )
            throw new MQeException( Except_Rule, "Connection not allowed" );
    }
    ...
}
```

Related functions

- [putMessage](#)

MQeQueueRule getPendingMessage

Syntax

```
public void getPendingMessage( String queueManagerName,
                               MQeFields filter,
                               long confirmId ) throws Exception
```

Description

An MQSeries Everyplace queue manager is able to collect messages destined for itself from its home-server through a home-server queue. The home-server stores messages destined for its clients in one or more store-and-forward queues. The home-server queue contacts its home-server's store-and-forward queues using the **MQeStoreAndForwardQueue.getPendingMessage()** method. Any pending messages for that MQSeries Everyplace queue manager are then returned.

This rule is called when a get pending message request is received.

Parameters

queueManagerName

A String containing the name of the MQSeries Everyplace queue manager that initiated the get pending message request.

filter

null or an **MQeFields** object containing a message filter, used to match any pending messages. *null* means return

MQeQueueRule

the first available message addressed to the queue manager specified in queueManagerName.

confirmId A long value that is the confirm ID for this operation. The confirmID is used to restore messages in the event of a failure.

Return values

none

Exceptions

Examples

```
class exampleQueueRules extends MQeQueueRule
{
    ...
    /* This rule requires that the filter contain a password */
    /* (For this rule to work correctly it would be necessary to override */
    /* MQeHomeServerQueue so that the message filter sent to the Store & */
    /* Forward Queue was non-null) */
    public void getPendingMessage( String queueManagerName, MQeFields filter,
                                  long confirmId ) throws Exception
    {
        if ( filter != null && filter.contains( "Password" ) )
        {
            String pswd = filter.getAscii( "Password" );
            if ( pswd.equals( "123456878" ) )
            { /* remove password from filter */
                filter.delete( "Password" );
                return;
            }
        }
        throw new MQeException( Except_Rule, "No Password" );
    }
    ...
}
```

MQeQueueRule indexEntry

Syntax

```
public void indexEntry( MQeFields entry,
                        MQeMsgObject msg ) throws Exception
```

Description

This rule is called when the queue creates an index entry. This occurs when a new message is put onto the queue, and when the queue is activated, if it still holds messages from a previous session.

The index entry contains state information about the message, along with certain index fields that are held to enable faster message searching. These fields are:

- MQe Unique ID (MQe.Msg_OriginQM + MQe.Msg_Time)
- MQ Series Message ID (MQe.Msg_ID)
- MQ Series Correlation ID (MQe.Msg_CorrelID)
- Message Priority(MQe.Msg_Priority)

Parameters

entry A String containing the name of the MQSeries Everyplace queue manager that initiated the get pending message request.

MQeQueueRule

filter An **MQeFields** object containing a blank index entry. The rule can add fields to this object, if it wishes.

msg An **MQeMsgObject** containing the message for which an index entry is being created.

Return values

none

Exceptions

Examples

```
class exampleQueueRules extends MQeQueueRule
{
    ...
    /* if the message contains a customer number field - then add this field */
    /* to the message's index entry. */
    /* This will enable faster message searching */
    public void indexEntry( MQeFields entry,
                           MQeMsgObject msg ) throws Exception
    {
        if ( msg.contains( "Cust_No" ) )
            entry.copy( msg, true, "Cust_No" );
    }
    ...
}
```

MQeQueueRule messageExpired

Syntax

```
public boolean messageExpired( MQeFields entry,
                             MQeMsgObject msg ) throws Exception
```

Description

This rule is called when a message has exceeded either the queue's expiry interval, or it's own expiry interval. The check to see whether the message exceeded the expiry intervals is made every time the message is accessed.

The rule then decides whether to expire the message, and what subsequently happens to the message, if it has expired.

Parameters

entry An **MQeFields** object containing the index entry for the message that has expired.

msg An **MQeMsgObject** containing the message that has expired.

Return values

A boolean value which denotes whether to expire the message.

true The message has expired and can be deleted

false The message has not expired

Exceptions

Examples

```
class exampleQueueRules extends MQeQueueRule
{
    ...
    /* This rule puts a copy of any expired messages to a Dead Letter Queue */
    public boolean messageExpired( MQeFields entry,
                                 MQeMsgObject msg ) throws Exception
    {
```

MQeQueueRule

```
/* Get the reference to the Queue Manager */
MQeQueueManager qmgr = MQeQueueManager.getReference(
    ((MQeQueue)owner).getQueueManagerName() );
/* need to set re-send flag so that put of message to new queue isn't */
/* rejected */
msg.putBoolean( MQe.Msg_Resend, true );
/* if the message contains an expiry interval field - remove it */
if ( msg.contains( MQe.Msg_ExpireTime ) )
    msg.delete( MQe.Msg_ExpireTime );
/* put message onto dead letter queue */
qmgr.putMessage( null, "DEAD.LETTER.QUEUE", msg, null, 0 );
/* return true & the message will be deleted from the queue */
return (true);
}
...
}
```

MQeQueueRule putMessage

Syntax

```
public void putMessage( MQeMsgObject msg,
    long confirmID ) throws Exception
```

Description

This rule is called when a put message request is made. By throwing an exception the rule can prevent the message being put onto the queue.

Parameters

msg	An MQeMsgObject containing the msg to be put onto the queue.
confirmID	A long value containing the confirm ID for this operation. The confirm ID is used to restore locked messages in the event of a failure.

Return values

none

Exceptions

Examples

```
class exampleQueueRules extends MQeQueueRule
{
    ...
    /* This rule blocks a message Put if the message priority is less than 5 */
    public void putMessage( MQeMsgObject msg, long confirmID ) throws Exception
    {
        if ( (msg.contains( MQe.Msg_Priority )) &&
            (msg.getByte( MQe.Msg_Priority ) < 5) )
            throw new MQeException( Except_Rule, "Priority too low" );
    }
    ...
}
```

Related functions

- `getMessage`

MQeQueueRule queueActivate

Syntax

```
public void queueActivate()
```

Description

This rule is called when the queue is activated.

Parameters

none

Return values

none

Exceptions

none

Examples

```
class exampleQueueRules extends MQeQueueRule
{
    ...
    /* This rule logs the activation of the queue */
    public void queueActivate()
    {
        try
        {
            logFile = new LogToDiskFile( \\\log.txt );
            log( MQe_Log_Information, Event_Queue_Activate, "Queue " +
                ((MQeQueue)owner).getQueueManagerName() + " " +
                ((MQeQueue)owner).getQueueName() + " active" );
        }
        catch( Exception e )
        {
            e.printStackTrace( System.err );
        }
    }

    public void queueClose()
    { /* close log file */
        logFile.close();
    }
    ...
}
```

Related functions

- queueClose

MQeQueueRule queueClose**Syntax**

```
public void queueClose()
```

Description

This rule is called when the queue is closed.

Parameters

none

Return values

none

Exceptions

none

Examples

```
class exampleQueueRules extends MQeQueueRule
{
    ...
    /* This rule logs the closure of the queue */
    public void queueClose()
    {
        try
        {
```

MQeQueueRule

```
    log( MQe_Log_Information, Event_Queue_Closed, "Queue " +
        ((MQeQueue)owner).getQueueManagerName() + " " +
        ((MQeQueue)owner).getQueueName() + " closed" );
    /* close log file */
    logFile.close();
}
catch ( Exception e )
{
    e.printStackTrace( System.err );
}
}

public void queueActivate()
{
    try
    {
        logFile = new LogToDiskFile( \\\log.txt );
        log( MQe_Log_Information, Event_Queue_Activate, "Queue " +
            ((MQeQueue)owner).getQueueManagerName() + " " +
            ((MQeQueue)owner).getQueueName() + " active" );
    }
    catch( Exception e )
    {
        e.printStackTrace( System.err );
    }
}
} ...
}
```

Related functions

- queueActivate

MQeQueueRule removeListener

Syntax

```
public void removeListener( MQeMessageListenerInterface listener,
                           MQeFields filter ) throws Exception
```

Description

This rule is called when a message listener is removed from a queue. By throwing an exception the rule can prevent the listener from being removed.

Parameters

listener	The object that is subscribing to MQSeries Everyplace message events. The object must implement MQeMessageListenerInterface .
filter	<i>null</i> or an MQeFields object containing a message filter. The filter must match the filter used in the add listener command that created this listener.

Return values

none

Exceptions

Examples

```
class exampleQueueRules extends MQeQueueRule
{
    ...
    /* This rule logs the removal of the message listener */
    public void removeListener( MQeMessageListenerInterface listener,
                               MQeFields filter ) throws Exception
    {
```

```

    log( MQe_Log_Information, Event_Queue_RemoveMsgListener,
        "Removed listener on queue " +
        ((MQeQueue)owner).getQueueManagerName() + " " +
        ((MQeQueue)owner).getQueueName() );
}

public void queueActivate()
{ /* create a new log file */
try
{
    logFile = new LogToDiskFile( \\\log.txt );
}
catch( Exception e )
{
    e.printStackTrace( System.err );
}
}

public void queueClose()
{ /* close log file */
logFile.close();
}

...
}

```

Related functions

- addListener

MQeQueueRule resetMessageLock**Syntax**

```
public void resetMessageLock( MQeFields filter ) throws Exception
```

Description

This rule is called when a request is made to reset the lock state on a message. The message is reset to an unlocked state. This function can only be performed by MQe Administration. By throwing an exception the rule can prevent the reset from occurring.

Parameters

filter	An MQeFields object containing a message filter. This filter is used to match the message having its lock state reset
---------------	--

Return values

none

Exceptions**Examples**

```

class exampleQueueRules extends MQeQueueRule
{
    ...
/* This rule logs the message lock reset */
public void resetMessageLock( MQeFields filter ) throws Exception
{ /* get message UID */
    if ( filter.contains( MQe.Msg_Time ) &&
        filter.contains( MQe.Msg_OriginQMgr ) )
    {
        String originQMgr = filter.getAscii( MQe.Msg_OriginQMgr );
        long timeStamp      = filter.getLong( MQe.Msg_Time );

        log( MQe_Log_Information, Event_Queue_ResetMessageLock,
            "Message " + originQMgr + ":" + timeStamp + " on queue " +
            ((MQeQueue)owner).getQueueManagerName() + " " +
            ((MQeQueue)owner).getQueueName() );
    }
}

```

MQeQueueRule

```
        ((MQeQueue)owner).getQueueName() + " has been reset" );
    }

    public void queueActivate()
    { /* create a new log file */
        try
        {
            logFile = new LogToDiskFile( \\log.txt );
        }
        catch( Exception e )
        {
            e.printStackTrace( System.err );
        }
    }

    public void queueClose()
    { /* close log file */
        logFile.close();
    }

    ...
}
```

MQeQueueRule undo

Syntax

```
public boolean undo( MQeFields filter ) throws Exception
```

Description

An undo message operation matches zero or more messages held on a queue. This rule is called for each message matched, and the rule determines whether the message is to be included in the set of messages processed by the undo operation.

By throwing an exception the rule can terminate the undo operation.

Parameters

filter	An MQeFields object containing a message filter. Only messages matching the filter are included in the undo operation.
confirmId	A long value that was the confirm Id used by the operation which is being undone. All messages matching this confirm Id are restored to their previous state

Return values

A boolean value denoting whether this message will be included in the set of messages processed by the undo operation.

true Include this message in those processed by the undo operation

false Do not include this message in those processed by the undo operation

Exceptions

Examples

```
class exampleQueueRules extends MQeQueueRule
{
    ...

    /* This rule logs the message reset */
    public boolean undo( MQeFields filter ) throws Exception
    { /* get message UID */
        if ( filter.contains( MQe.Msg_Time ) &&
```

```

        filter.contains( MQe.Msg_OriginQMgr ) )
{
    String originQMgr = filter.getAscii( MQe.Msg_OriginQMgr );
    long timeStamp      = filter.getLong( MQe.Msg_Time );

    log( MQe_Log_Information, Event_Queue_ResetMessageLock,
        "Message " + originQMgr + ":" + timeStamp + " on queue " +
        ((MQeQueue)owner).getQueueManagerName() + " " +
        ((MQeQueue)owner).getQueueName() + " has been reset" );
}
return (true);
}

public void queueActivate()
{ /* create a new log file */
try
{
    logFile = new LogToDiskFile( \\log.txt );
}
catch( Exception e )
{
    e.printStackTrace( System.err );
}
}

public void queueClose()
{ /* close log file */
logFile.close();
}

...
}

```

MQeQueueRule useCountChanged

Syntax

```
public void useCountChanged( int useCount ) throws Exception
```

Description

This rule is called when a queue's use count changes. The use count is a measure of the number of users attached to the queue. The use count changes when the queue is activated or closed, and when remote queue managers connect to, or disconnect from, the queue using an **MQeTransporter**.

Parameters

useCount the queue's current use count.

Return values

none

Exceptions

Examples

```

class exampleQueueRules extends MQeQueueRule
{
    ...
    /* do not allow the use count to exceed ten */
    public void useCountChanged( int useCount ) throws Exception
    {
        if ( useCount == 10 )
            throw new MQeException( Except_Rule, "Too many users" );
    }
    ...
}

```

MQeEventLogInterface

MQeEventLogInterface

All MQSeries Everyplace log handlers must implement this interface.

Package com.ibm.mqe

Method summary

Method	Purpose
activate	Activates the event log handler
close	Terminates the event log function and performs any cleanup as appropriate
logOutput	Outputs data to the event log

MQeEventLogInterface activate

Syntax

```
public void activate( String logName ) throws Exception
```

Description

Is called to activate the event log handler

Parameters

logName A String used to identify this event log

Return values

none

MQeEventLogInterface close

Syntax

```
public void close( )
```

Description

Called to close the event log handler and to perform any cleanup as necessary

Parameters

none

Return values

none

MQeEventLogInterface logOutput

Syntax

```
public void logOutput( String data )
```

Description

Called by MQSeries Everyplace to output a message to the event log handler

Parameters

data The data to be logged

Return values

none

MQeMessageListenerInterface

This interface must be implemented by all objects that wish to receive MQeMessage events.

Package com.ibm.mqe

Method summary

Method	Purpose
messageArrived	Event handler for MQeMessageEvent.MessageArrived events. This event is generated when a message arrives on a queue.

MQeMessageListener messageArrived

Syntax

```
public void messageArrived( MQeMessageEvent msgEvent )
```

Description

This method is called on all listening objects when an MQeMessageEvent.MessageArrived event is generated.

Parameters

msgEvent	An MQeMessageEvent object containing details of the newly arrived message
-----------------	---

Return values

none

Exceptions

none.

Example

```
class MyMQeApplication extends MQSeries Everyplace implements MQeMessageListenerInterface
{
    ...
    public void messageArrived( MQeMessageEvent e )
    {
        ...
        if ( e.getQueueName().equals("MY.QUEUE") )
            MQeFields msgFields = e.getMsgFields(); /* get msg info */
        ...
    }
    ...
}
```

MQeRunListInterface

Two lists of MQSeries Everyplace applications can be passed to an MQSeries Everyplace queue manager as part of the parameter set passed to it when it is activated. The applications contained in the first list are invoked once the queue manager is active. The applications contained in the second list are invoked when the queue manager receives a close request.

All applications should implement MQeRunListInterface, but it is not mandatory.

Package com.ibm.mqe

Method summary

Method	Purpose
activate	called by the queue manager to activate the application.

MQeRunListInterface activate

Syntax

```
public Object activate( Object owner,  
                        Hashtable loadTable,  
                        MQeFields setupData ) throws Exception;
```

Description

Two lists of MQSeries Everyplace applications can be passed to a MQSeries Everyplace queue manager as part of the parameters passed when the queue manager is activated. The first list contains applications that are invoked once the queue manager is active. The second list contains applications that are invoked when the queue manager receives a close request (when the MQeQueueManager.close() method is called).

If the applications contained in the queue manager parameters implement **MQeRunListInterface**, then the queue manager calls this method to activate the application, and pass any set-up information for the application that is contained in the queue manager parameters.

Applications are not forced to implement MQeRunListInterface, but if they do not, the application is just invoked and no set-up information is passed to it

An application that is invoked when a queue manager is activated should return from this method as quickly as possible to allow the queue manager to continue. The application should initialize itself on a different thread from the one on which it is called. The application is responsible for the management of this thread.

An application that is invoked on queue manager close can block the queue manager from shutting down by not returning from this method.

Parameters

owner This is the object that owns the application. Usually this is the MQe queue manager that invoked the application.

loadTable A java.util.Hashtable object that can be used to share data between the applications invoked by the queue manager. All of the applications invoked by the queue manager have a reference to this table.

setupData An **MQeFields** object containing application setup data. This data must have been included in the parameters passed to the queue manager when the queue manager was activated. See the sample INI file below for an example of this.

Return values

An object reference - this is not currently used.

Exceptions

none

Example

Example of an application being launched when the queue manager is activated

```
public class ExampleApp extends MQe implements MQeRunListInterface,
                                             Runnable,
                                             MQeMessageListenerInterface
{
    Thread th = null;
    MQeQueueManager qmgr = null;
    ...
    /* Called by the Queue Manager to activate the application */
    public Object activate( Object owner, Hashtable loadTable,
                           MQeFields setupData )
    {
        qmgr = (MQeQueueManager)owner; /* QMgr is owner of the application */
        processSetupData( setupData ); /* Process the setup information */
        th = new Thread( this ); /* Create a new thread to listen */
        th.start(); /* for incoming messages */
        return (null); /* return control to the QMgr */
    }

    public void run()
    {
        try
        {
            /* Create a message listener for incoming messages */
            qmgr.addMessageListener( this, "MyQueue", null );
            /* Loop indefinitely keeping application alive */
            while( true );
        }
        catch ( Exception e )
        {
            e.printStackTrace( System.err );
        }
    }
    ...
}
```

Example of an application being launched when the queue manager receives a close request

```
public class ExampleCloseApp extends MQe implements MQeRunListInterface
{
    MQeQueueManager qmgr = null;
    ...
    /* Called by the Queue Manager to activate the application */
    public Object activate( Object owner, Hashtable loadTable,
                           MQeFields setupData )
    {
        qmgr = (MQeQueueManager)owner; /* QMgr is owner of the application */
        performAction(); /* Perform some action */
        /* don't return control to the QMgr until application has finished */
        return (null);
    }
}
```

MQeRunListInterface

Sample Queue Manager INI file

```
* Sample Queue Manager INI file

* Queue Manager setup info
[QueueManager]
* Name for this Queue Manager
(ascii)Name=ServerQMgr8082

* Registry setup info
[Registry]
* QueueManager Registry type
(ascii)LocalRegType=com.ibm.mqe.registry.MQePrivateSession
* Location of the registry
(ascii)DirName=d:\development\Rename\Classes\ServerQMgr8082\Registry
* Registry access PIN
(ascii)PIN=12345678

* List of applications to launched at Queue Manager activation-time
[ActivateAppList]
(ascii)App1=examples.queueManager.TestMQeApp
(ascii)App2=examples.administration.AdminApp

* Setup info for App1 - the data in this section is passed to the application
[App1]
(ascii)DefaultMsgPriority = 7
(long)Timeout = 30000

* Setup info for App2 - the data in this section is passed to the application
[App2]
(ascii)DefaultQueueName=AdminReplyQueue
```

MQeSecurityInterface

This is an optional interface that may be implemented by a Java Security manager . The interface methods allow the security manager to authorize or reject the call. MQSeries Everyplace trace handlers must implement this interface.

Package com.ibm.MQe

Method summary

Method	Support
alias	Called whenever a class alias is added or removed
channelCommand	Called whenever a channel command is about to be processed by a channel
newAdapter	Called whenever an adapter definition is about to be defined
mapFileDescriptor	Called whenever a mapping of a file descriptor is about to be set

MQeSecurityInterface alias

Syntax

```
public void alias( String from, String to ) throws Exception
```

Description

Called whenever an alias is about to be set or removed

Parameters

from	A String defining the class alias
to	A String defining the class name for the alias, or <i>null</i> if the alias is to be removed

Return values

none

Exceptions

SecurityException	Request was rejected
--------------------------	----------------------

Example

MQeSecurityInterface channelCommand

Syntax

```
public void channelCommand( String command ) throws Exception
```

Description

Called whenever a channel command is about to be processed

Parameters

command	A string containing the channel command
----------------	---

Return values

none

Exceptions

SecurityException	request was rejected
--------------------------	----------------------

Example

MQeSecurityInterface

MQeSecurityInterface newAdapter

Syntax

```
public void newAdapter( String destination ) throws Exception
```

Description

Called whenever a new adapter definition is about to be set

Parameters

destination A string containing the destination for this adapter. A typical Destination would be of the form:
Tcpip:127.0.0.1:8080

Return values

none

Exceptions

SecurityException request was rejected

Example

MQeSecurityInterface mapFileDescriptor

Syntax

```
public void mMapFileDescriptor( String fileDesc, Object newDesc )
                               throws Exception
```

Description

Called whenever a file descriptor map is to be set

Parameters

fileDesc A string containing the file descriptor that is to be mapped
newDesc A string containing the file descriptor that is the mapped descriptor

Return values

none

Exceptions

SecurityException Request was rejected

Example

MQeTraceInterface

All MQSeries Everyplace trace handlers must implement this interface.

Package com.ibm.mqe

Method summary

Method	Purpose
activate	Called to activate the trace handler
addMessage	Adds a new trace message template
addMessageBundle	Adds a bundle of trace message templates
close	Called to close the trace handler and perform any cleanup as appropriate
getMessage	Return the message template for a given message number
traceMessage	Called to write a trace message to the output stream

MQeTraceInterface activate

Syntax

```
public void activate ( String title, String resource )
```

Description

Called to activate the trace handler

Parameters

title	A String to be used as a title for this trace handler or <i>null</i>
resource	A String used to identify the resource bundle to use for this trace handler

Return values

none

MQeTraceInterface traceMessage

Syntax

```
public String traceMessage( String prefix,
                           int msgNumber,
                           Object insert )
```

Description

Called by MQSeries Everyplace to output a trace message via the trace handler

Parameters

prefix	The calling object name and instance number
msgNumber	An integer containing the trace message number to be used to find the message template
insert	Any inserts to be applied to the message template

Return values

A String containing the expanded trace message text

MQeTraceInterface

MQeTraceInterface addMessage

Syntax

```
1. public void addMessage ( int msgNumber, String msgText ) throws Exception  
2. public void addMessage ( String msgText ) throws Exception
```

Description

Called to add a new trace message template to the trace handler. The template should be of the form:

```
static final Object[][] contents = {  
    /*-----*/  
    /* System messages */  
    /* '_-' message */  
    /* 'i' Information */  
    /* 'w' Warning */  
    /* 'e' Error */  
    /* 'd' Debug */  
    /*-----*/  
    /* Application messages */  
    /* '_-' message */  
    /* 'I' Information */  
    /* 'W' Warning */  
    /* 'E' Error */  
    /* 'D' Debug */  
    /*-----*/  
    /* Modifier */  
    /* ':' no modification applied */  
    /* ';' RESERVED for create/destroy object */  
    /* '+' Log this message via the Log interface */  
    /* '' ignore - Do not display this message */  
    /*-----*/  
    /* Message number */  
    /* "[nnnnn]:" syntax for message number of this message */  
    /*-----*/  
    /* Example: */  
    /* "e+[01000]:Error #0 occurred" */  
    /* "I:[01010]:All is wonderful" */  
    /*-----*/
```

Parameters

msgNumber An integer containing the trace message number to be used to identify the message template

msgText A String containing the trace message template

Return values

none

MQeTraceInterface addMessageBundle

Syntax

```
public void addMessageBundle( String msgBundle ) throws Exception
```

Description

Is called to add a bundle of templates to the trace handler. The templates in the bundle should be of the form:

```
static final Object[][] contents = {  
    /*-----*/  
    /* System messages */  
    /* '_-' message */  
    /*-----*/
```

```

/*      'i'      Information
/*      'w'      Warning
/*      'e'      Error
/*      'd'      Debug
/*
/* Application messages
/*      ' '      message
/*      'I'      Information
/*      'W'      Warning
/*      'E'      Error
/*      'D'      Debug
/*
/* Modifier
/*      ':'      no modification applied
/*      ';'      RESERVED for create/destroy object
/*      '+'      Log this message via the Log interface
/*      ''      ignore - Do not display this message
/*
/* Mwssage number
/*      "[nnnnn]:" syntax for message number of this message
/*
/* Example:
/*          "e+[01000]:Error #0 occurred"
/*          "I:[01010]:All is wonderful"
*/
-----*/

```

Parameters**msgBundle**

A String identifying the bundle of trace messages templates to be added

Return values

none

Standard trace messages

```

static final Object[][] contents = {
/*
/* System messages
/*      ' '      message
/*      'i'      Information
/*      'w'      Warning
/*      'e'      Error
/*      's'      Security
/*      'd'      Debug
/*
/* Application messages
/*      ' '      message
/*      'I'      Information
/*      'W'      Warning
/*      'E'      Error
/*      'S'      Security
/*      'D'      Debug
/*
/* Modifier
/*      ':'      no modification applied
/*      ';'      RESERVED for create/destroy object
/*      '+'      Log this message via the Log interface
/*      ''      ignore - Do not display this message
/*
/* Mwssage number
/*      "[nnnnn]:" syntax for message number of this message
/*
/* Example:
/*          "e+[01000]:Error #0 occurred"
/*          "I:[01010]:All is wonderful"
*/
-----*/

```

MQeTraceInterface

```

/*
 *-----*/
/* common messages */
{ "1", "d:[00001]:Created" },
{ "2", "d:[00002]:Destroyed" },
{ "3", "d:[00003]:Close" },
{ "4", "w:[00004]:Warning:#" },
{ "5", "e:[00005]:Error:#" },
{ "6", "i:[00006]:Command:#" },
{ "7", "i:[00007]:Waiting" },
{ "8", "i:[00008]:# input byte count=#" },
{ "9", "i:[00009]:# output byte count=#" },
/* com.ibm.MQe.MQELoader */
{ "10", "d:[00010]:loadClass #" },
{ "11", "d:[00011]:Loaded (bytes) #" },
{ "12", "d:[00012]:Resolved Class #" },
{ "13", "d:[00013]:DropClass #0" },
/* com.ibm.MQe.MQEChannel & ChannelManager */
{ "20", "d:[00020]:ActivateMaster" },
{ "21", "d:[00021]:ActivateSlave" },
{ "22", "d:[00022]:ActivateSlave Channel ID=#0" },
{ "23", "d:[00023]:Close Channel ID=#0" },
{ "24", "d:[00024]:SlaveResponse" },
{ "25", "d:[00025]:SlaveResponse Channel ID=#0" },
{ "26", "i:[00026]:Timeout channel ID=#0" },
{ "27", "i:[00027]:Forwarding to #0" },
{ "28", "i:[00028]:ID=#0, Command=#1" },
/* com.ibm.MQEChannelListener */
{ "30", "i:[00030]:Starting Listener #0" },
{ "31", "i:[00031]:Stopping Listener" },
{ "32", "d:[00032]:Starting Slave" },
{ "33", "d:[00033]:Stopping Slave" },
{ "34", "d:[00034]:Timer interval" },
/* com.ibm.MQEAttribute */
{ "40", "d:[00040]:Authenticator #0" },
{ "41", "d:[00041]:Compressor #0" },
{ "42", "d:[00042]:Cryptor #0" },
{ "43", "d:[00043]:Attribute(Rule).equals=#0" },
{ "44", "d:[00044]:Attribute Change #0" },
{ "45", "d:[00045]:TargetRegistry=#0" },
{ "46", "s:[00046]:Secure Chnl State=pending, KeyObject=#0" },
/* com.ibm.MQETransporter */
{ "50", "d:[00050]:#0 PID=#1" },
{ "51", "d:[00051]:#0 made persistent PID=#1" },
{ "52", "d:[00052]:#0 Message Request for Queue '#1'" },
{ "53", "d:[00053]:GetPendingMessage for Queue Manager '#0'" },
/* ***** Adapters *****/
/* com.ibm.MQE.Adapters.MQEIniFileAdapter & MQeDisk....Adapter */
{ "110", "d:[00110]:Object #0 - saved" },
{ "111", "d:[00111]:Object #0 - loaded" },
{ "112", "d:[00112]:Object #0 - Selected" },
{ "113", "d:[00113]:Object #0 - matched" },
{ "114", "d:[00114]:Object #0 - deleted" },
/* com.ibm.MQE.Adapters.MQE Tcpip Adapter */
{ "200", "d:[00200]:File descriptor '#0'" },
{ "201", "d:[00201]:Socket pending" },
{ "202", "d:[00202]:Control '#0'" },
/* com.ibm.MQE.Adapters.MQE Tcpip Http Adapter */
{ "203", "d:[00203]:Read Header" },
{ "204", "d:[00204]:Header: #0" },
{ "205", "d:[00205]:Header length=#0" },
{ "206", "d:[00206]:Write Header" },
{ "207", "d:[00207]:Read Content-length=#0" },
{ "208", "d:[00208]:Readln #0" },
...

```

...

};

The full list of messages can be found in the examples.trace.MQeTraceResource.java source file in the trace subdirectory of the examples directory.

MQeTraceInterface close

Syntax**Description****Parameters****Return values**

MQeTraceInterface getMessage

Syntax

```
public String getMessage( int msgNumber )
```

Description

Called to get the String that corresponds to the trace message number supplied in the **msgNumber** parameter

Parameters

msgNumber The number of the trace message String to be returned

Return values

A String containing the trace message template

MQeTraceInterface

Chapter 3. Classes in com.ibm.mqe.administration

This section contains detailed information about the following MQSeries Everyplace classes and interfaces:

Table 12. Classes in package com.ibm.mqe.Administration

Class or interface name	Purpose
MQeAdminQueueAdminMsg	Used to manage queues of type MQeAdminQueue
MQeConnectionAdminMsg	Class used to manage connections of type MQeConnectionDefinition
MQeHomeServerQueueAdminMsg	Used to manage queues of type MQeHomeServerQueue
MQeQueueAdminMsg	Used to manage MQSeries Everyplace local queues of type MQeQueue
MQeQueueManagerAdminMsg	Used to manage queue managers of type MQeQueueManager
MQeRemoteQueueAdminMsg	Used to manage remote queues of type MQeRemoteQueue
MQeStoreAndForwardQueueAdminMsg	Used to manage queues of type MQeStoreAndForwardQueue

MQeAdminQueueAdminMsg

MQeAdminQueueAdminMsg

This class is used to manage queues of type MQeAdminQueue. The class extends **MQeQueueAdminMsg** and provides an implementation for managing administration queues.

This queue is used to provide transparent local/remote administration of MQSeries Everyplace managed resources.

Package com.ibm.mqe.administration

This class is a descendant of **MQeQueueAdminMsg**

Constants and variables

MQeHomeServerQueueAdminMsg provides the following constants and variables in addition to those provided and inherited by **MQeQueueAdminMsg**:

Queue characteristics

QtimerInterval;

Process outstanding administration messages after interval (milliseconds)
(long)

```
public final static String Queue_QtimerInterval;
```

MQeConnectionAdminMsg

This class is used to manage connections of type MQeConnectionDefinition.

The class extends **MQeAdminMsg** and provides the implementation for managing connections. The following actions are applicable on connections:

- **Action_Create**
- **Action_Delete**
- **Action_Inquire**
- **Action_InquireAll**
- **Action_Update**

Connections define how one queue manager establishes a connection to another queue manager. The main characteristics associated with a connection are:

The type of channel to use

The following types of channel are provided:

MQeChannel

Channel for Client to Server or Server to Server

MQPeerChannel

Channel for Peer to Peer

A file descriptor that contains the communications adapter and its parameters

The following adapters are provided:

MQeTcpipLengthAdapter

Simple TCPIP adapter

MQeTcpipHistoryAdapter

TCPIP adapter that provides persistent connections and data compression

MQeTcpipHttpAdapter

HTTP adapter

A file descriptor for an http connection to server "192.168.0.1" on port 8081 would be specified as:

`com.ibm.mqe.Adapters.MQeTcpipHttpAdapter:192.168.0.1:8081`

or if an alias of "Network" had been set up for the HTTP adapter then the following file descriptor could be used:

`Network:192.168.0.1:8081`

Package `com.ibm.mqe.administration`

This class is a descendant of **MQeAdminMsg**

Constants and variables

MQeQueueAdminMsg provides the following constants and variables in addition to those provided by **MQeAdminMsg**:

Additional actions

AddAlias

Add connection aliases

MQeConnectionAdminMsg

```
public final static int Action_AddAlias  
RemoveAlias  
    Remove connection aliases  
public final static int Action_RemoveAlias
```

Connection characteristics

Adapters (fields array)

Set of adapters used to connect to a target queue managers.

Note: In release one only one adapter is allowed.

```
public final static String Con_Adapters
```

The following fields define those allowed in each element of the **adapters** array:

AdapterFileDesc (ascii)

The adapter file descriptor

AdapterAsciiParm (ascii)

Parameters for the adapter

AdapterEncodedParm (byte array)

Encoded parameters

AdapterOptions (ascii)

Options for the adapter

```
public final static String Con_Adapter  
public final static String Con_AdapterAsciiParm  
public final static String Con_AdapterEncodedParm
```

Aliases

Set of aliases for this connection (ascii array)

```
public final static String Con_Aliases
```

Channel

Channel class (ascii) - the type of channel that this connection should use.
For example:

```
com.ibm.mqe.MQeChannel  
com.ibm.mqe.MQePeerChannel
```

the value can also be null meaning that this is a local connection.

```
public final static String Con_Channel
```

Description

Description of the connection (unicode)

```
public final static String Con_Description
```

Method summary

Method	Purpose
create	Sets up the administration message to perform the Action_Create action
update	Sets up the administration message to perform the Action_Update action.

MQeConnectionAdminMsg create

Syntax

```
public void create( String adapter, String parameters,
                    String options, String channel
                    String description ) throws Exception
```

Description

Sets up the administration message to perform the Action_Create action. This version of create adds a simple connection definition for a connection that has one adapter.

Parameters

adapter	File descriptor for the adapter
parameters	Adapter parameters
options	Adapter options
channel	Type of channel to use
description	Description of connection

Return values

none

Exceptions

java.lang.Exception	Various
----------------------------	---------

Example

```
class MyApplication
{
    ...
    MQeConnectionAdminMsg con = new MQeConnectionAdminMsg()
    con.setName("ServerQM123");
    con.create("Network:127.0.0.1:8081",
              null,
              null,
              "DefaultChannel",
              "Con to MQeServer" );
    MQeConnectionAdminMsg con2 = new MQeConnectionAdminMsg()
    con2.setName("ServletQM123");
    con2.create("Network:127.0.0.1:8081",
               "/servlet/MQe",
               null,
               "DefaultChannel",
               "Con to MQeServlet" );
    ...
}
```

MQeConnectionAdminMsg update

Syntax

```
public void update( String adapter, String parameters,
                    String options, String channel
                    String description ) throws Exception
```

Description

Sets up the administration message to perform the Action_Update action. This version of update replaces an existing connection definition with a simple connection definition for a connection that has one adapter.

Parameters

adapter	File descriptor for the adapter
----------------	---------------------------------

MQeConnectionAdminMsg

parameters	Adapter parameters
options	Adapter options
channel	Type of channel to use
description	Description of the connection

Return values

none

Exceptions

java.lang.Exception	Various
----------------------------	---------

Example

```
class MyApplication
{
    ...
    MQeConnectionAdminMsg con = new MQeConnectionAdminMsg()
    con.setName("ServerQM123");
    con.update("Network:127.0.0.1:8082",
               null,
               null,
               "DefaultChannel",
               "Con to MQeServer" );
    ...
}
```

MQeHomeServerQueueAdminMsg

This class is used to manage queues of type MQeHomeServerQueue. The class extends **MQeRemoteQueueAdminMsg** and provides an implementation for managing home server queues

This queue is used in a client to retrieve (using a background thread) pending messages from it's *home* queue on it's *HomeServer*.

Package com.ibm.mqe.administration

This class is a descendant of **MQeRemoteQueueAdminMsg**

Constants and variables

MQeHomeServerQueueAdminMsg provides the following constants and variables in addition to those provided and inherited by **MQeRemoteQueueAdminMsg**:

Queue characteristics

QtimerInterval;

Process pending messages after interval (milliseconds) (long)

```
public final static String Queue_QtimerInterval;
```

MQeQueueAdminMsg

This class is used to manage MQSeries Everyplace local queues of type **MQeQueue**. The class extends **MQeAdminMsg** and provides an implementation for managing local queues. The following actions are applicable on local queues:

- Action_Create
- Action_Delete
- Action_Inquire
- Action_InquireAll
- Action_Update
- Action_AddAlias
- Action_RemoteAlias

Local queues, as the name suggest are local to the owning queue manager. A file descriptor must be set that details where and how the queue is stored. It is formed from two parts, an adapter and parameters to the adapter. The following adapters are provided:

MQeDiskFieldsAdapter

File based adapter for **MQeFields** objects

MQeMemoryFieldsAdapter

Memory based adapter for **MQeFields** objects

For example, if alias **MsgLog** is set to **MQeDiskFieldsAdapter** then to store messages at **d:\ServerQM123\Queues**, the file descriptor would be:

MsgLog:d:\ServerQM123\Queues

Queues allow several characteristics to be set that are not used by the base local queue. These characteristics are made available to a user replaceable queue rules class that can make use of them. For instance **Queue_MaxQSize** can be set but is not checked by **MQeQueue**. It is the responsibility of the queues rules class to perform maximum queue size validation.

This class acts as the base class for managing other types of queues. For instance **MQeRemoteQueueAdminMsg** derives from this class and handles management of remote queues.

Package **com.ibm.mqe.Administration**

This class is a descendant of **MQeAdminMsg**

Constants and variables

MQeQueueAdminMsg provides the following constants and variables in addition to those provided by **MQeAdminMsg**:

Additional actions

AddAlias

Add queue aliases
public final static int Action_AddAlias;

RemoveAlias

Remove queue aliases
public final static int Action_RemoveAlias;

Queue characteristics**Active** Indicates that the queue is active (boolean, Read Only)

public final static String Queue_Active

CreationDateDate queue was created (long Read Only). Time in milliseconds since
midnight Jan 1, 1970 GMT

public final static String Queue_CreationDate

CurrentSize

Current queue depth (int, Read Only)

public final static String Queue_CurrentSize

Description

Description of the queue (unicode)

public final static String Queue_Description

Expiry Messages on queue expire n milliseconds after being stored on the queue
(long)

public final static String Queue_Expiry

FileDesc

File descriptor - the location where queue is stored (ascii)

Once set the file descriptor cannot be changed.

The file descriptor is formed from two parts

- An adapter
- The adapter's parameters

For example, if alias MsgLog is set to MQeDiskFieldsAdapter then to store
messages at d:\ServerQM123\Queues, the filedescriptor would be:

MsgLog:d:\ServerQM123\Queues

public final static String Queue_FileDesc

MaxMsgSize

Maximum length of messages allowed on the queue (int)

public final static String Queue_MaxMsgSize

MaxQSize

Maximum number of messages allowed on the queue (int)

NoLimitpublic final static String Queue_MaxQSize
public final static int Queue_NoLimit**Mode** Type of queue - Is the queue synchronous or asynchronous.

public final static String Queue_Mode

Asynchronous

Queue is asynchronous

public final static byte Queue_Asynchronous

Synchronous

Queue is synchronous

public final static byte Queue_Synchronous

PriorityDefault priority for messages if not already specified in the message (byte)
(min = 0, max = 9)

MQeQueueAdminMsg

```
public final static String Queue_Priority
```

QAliasNameList

Set of alias names for this queue (ascii array)

```
public final static String Queue_QAliasNameList
```

QMgrName

Name of the queue manager that owns the queue (ascii). Once set the queue manager name cannot be changed.

```
public final static String Queue_QMgrName
```

Queue security Characteristics

These fields can only be changed when the queue has 0 messages and is not active.

AttrRule

Name of queue attribute rules class (ascii)

```
public final static String Queue_AttrRule
```

Authenticator

Name of authenticator class (ascii)

```
public final static String Queue_Authenticator
```

Compressor

Name of compressor class (ascii)

```
public final static String Queue_Compressor
```

Cryptor

Name of cryptor class (ascii)

```
public final static String Queue_Cryptor
```

TargetRegistry

Target registry type (byte)

```
public final static String Queue_TargetRegistry
```

One of the following:

RegistryNone

```
public final static byte Queue_RegistryNone
```

RegistryQMgr

```
public final static byte Queue_RegistryQMgr
```

RegistryQueue

```
public final static byte Queue_RegistryQueue
```

Rule

Name of queue rules class (ascii)

```
public final static String Queue_Rule
```

Constructor summary

Constructor	Purpose
MQeQueueAdminMsg	There are two constructors. One creates and initializes a default MQeQueueAdminMsg. The other takes the name of the queue that is to be managed.

Method summary

Constructor	Purpose
addAlias	Sets up an administration message to perform the Admin_AddAlias action.
removeAlias	Sets up an administration message to perform the Admin_RemoveAlias action.
setName	Sets the name of the queue that the action is to be performed against.

MQeQueueAdminMsg

Syntax

1.
public MQeQueueAdminMsg() throws Exception
2.
public MQeQueueAdminMsg(String qMgrName, String queueName)

Description

There are 2 constructors.

1. This version creates and initializes a default MQeAdminMsg
2. This version takes the name of the queue that is to be managed

Parameters

qMgrName	Queue manager name
queueName	Queue name

Return Values

A new MQeQueueAdminMsg

Exceptions

java.lang.Exception	Various
----------------------------	---------

Example

```
class MyApplication
{
    MQeQueueAdminMsg aMsg = new MQeQueueAdminMsg( "ExampleQM", "ExampleQ" );
}
```

MQeQueueAdminMsg addAlias

Syntax

```
public void addAlias( String aliasName ) throws Exception
```

Description

Sets up an administration message to perform the Admin_AddAlias action. A queue can have no aliases, one or several aliases. This method can be called more than once to allow multiple aliases to be added in one administration message.

Parameters

aliasName	Alias name of queue
------------------	---------------------

Return values

none

MQeQueueAdminMsg

Exceptions

java.lang.Exception Various

Example

```
class MyApplication
{
    ...
    // Add aliases to a queue
    MQeQueueAdminMsg msg = new MQeQueueAdminMsg();
    msg.setName( "ExampleQM", "ExampleQ" );

    // Set the action required and its parameters
    // into the message
    msg.addAlias( "PayrollQ" );
    msg.addAlias( "Branch1PayrollQ" );
    ...
}
```

MQeQueueAdminMsg removeAlias

Syntax

```
public void removeAlias( String aliasName ) throws Exception
```

Description

Sets up an administration message to perform the Admin_RemoveAlias action. This action removes the named alias from the queue. This method may be called more than once to allow multiple aliases to be removed using one administration message.

Parameters

aliasName Alias name of queue

Return values

none

Exceptions

java.lang.Exception Various

Example

```
class MyApplication
{
    ...
    // Add aliases to a queue
    MQeQueueAdminMsg msg = new MQeQueueAdminMsg();
    msg.setName( "ExampleQM", "ExampleQ" );

    // Set the action required and its parameters
    // into the message
    msg.removeAlias( "PayrollQ" );
    msg.removeAlias( "Branch1PayrollQ" );
    ...
}
```

MQeQueueAdminMsg setName

Syntax

```
public void setName( String qMgrName, String queueName ) throws Exception
```

Description

Sets the name of the queue that the action is to be performed on.

Parameters

MQeQueueAdminMsg

qMgrName Name of the queue manager that owns the queue
queueName Name of the queue

Return values

none

Exceptions

java.lang.Exception Various

Example

```
class MyApplication
{
    ...
    // Delete a queue
    MqeFields parms = new MQeFields();

    // Set the action required and its parameters
    // into the message
    msg.delete( parms );
    msg.setName( "ExampleQM", "ExampleQ" );
    ....
}
```

MQeQueueManagerAdminMsg

MQeQueueManagerAdminMsg

This section describes the Java class used to create a basic MQeQueueManagerAdminMsg.

The class extends **MQeAdminMsg** and provides the implementation for managing MQSeries Everyplace queue managers. The following actions are applicable on queue managers:

- **Action_Inquire**
- **Action_InquireAll**
- **Action_Update**

Note: **Create** and **Delete** actions are not supported on queue managers as a queue manager has to be in place and have an administration queue initialized on it before administration can take place, and only one queue manager per Java virtual machine is supported.

Package com.ibm.mqe.administration

This class is a descendant of **MQeAdminMsg**

Constants and variables

MQeQueueManagerAdminMsg provides the following constants and variables in addition to those provided and inherited by **MQeAdminMsg**

Queue manager characteristics

ChnlAttrRules

Channel attribute rules.

```
public final static String QMgr_ChnlAttrRules
```

ChnlTimeout

Maximum amount of time in milliseconds that a channel remains open (long).

```
public final static String QMgr_ChnlTimeout
```

Connections

Connections known by queue manager (ascii array - Read only)

```
public final static String QMgr_Connections
```

Description

Description of queue manager (unicode)

```
public final static String QMgr_Description
```

Queues

Queues known by queue manager (fields array - Read Only)

```
public final static String QMgr_Queues
```

QueueName

Queue name (ascii)

```
public final static String QMgr_QueueName
```

QueueQMgrName

Queue manager name (ascii)

```
public final static String QMgr_QueueQMgrName
```

QueueType

Queue type (ascii)

MQeQueueManagerAdminMsg

```
public final static String QMgr_QueueType
```

Rules User replaceable rules which control the capability of the queue manager (ascii).

```
public final static String QMgr_Rules
```

MQeRemoteQueueAdminMsg

MQeRemoteQueueAdminMsg

This class is used to manage remote queues of type MQeRemoteQueue. The class extends **MQeQueueAdminMsg** and provides an implementation for managing remote queues.

There are two types of remote queue:

Synchronous

When a request is made to a remote queue that is set for synchronous access, a channel is opened to the node where the queue is local. Hence all actions on a synchronous queue are shipped to the location where the queue is local at the time the request is made. Hence networking capability must be available between the remote queue and local queue at the time the request is made.

Asynchronous

When a request is made to a remote queue that is set for asynchronous access, the message is temporarily stored in the remote queue. Based on user replaceable rules, the message is moved from the remote queue to the location where the queue is local at some point in the future. Hence remote asynchronous queues require a file descriptor that describes where the messages are stored before they are moved.

Package **com.ibm.mqe.administration**

This class is a descendant of **MQeQueueAdminMsg**

Constants and variables

MQeRemoteQueueAdminMsg provides the following constants and variables in addition to those provided and inherited by **MQeQueueAdminMsg**:

Queue characteristics

Transporter

Name of the transporter class to use (ascii)

DefaultTransporter

```
public final static String Queue_Transporter  
public final static String Queue_DefaultTransporter
```

TransporterXOR

Allow transporter to use xor compression (boolean).

This provides intelligent compression of messages when they are moved across a network by XORing each field in a message with a field of the same name (if it exists) in the previous message that the transporter moved.

```
public final static String Queue_TransporterXOR
```

MQeStoreAndForwardQueueAdminMsg

This class is used to manage queues of type MQeStoreAndForwardQueue. The class extends MQeRemoteQueueAdminMsg and provides an implementation for managing store and forward queues.

This type of queue is used in intermediate nodes to hold messages that are just passing through i.e. that are not destined for any queues on this system.

Package com.ibm.mqe.administration

This class is a descendant of **MQeRemoteQueueAdminMsg**

Constants and variables

MQeStoreAndForwardQueueAdminMsg provides the following constants and variables in addition to those provided and inherited by **MQeRemoteQueueAdminMsg**:

Additional actions

AddQueueManager

Add queue manager
`public final static int Action_AddQueueManager;`

RemoveQueueManager

Remove queue manager
`public final static int Action_RemoveQueueManager;`

Remote queue characteristics

QMgrNameList

List of queue manager targets handled by this store and forward queue messages for the target queue managers are temporarily stored in this queue until they are collected by the target queue manager or until communication can be established.

`public final static String Queue_QMgrNameList`

Method summary

Method	Purpose
<code>addQueueManager</code>	Sets up an administration message to perform the Admin_AddQueueManager action
<code>removeQueueManager</code>	Sets up an administration message to perform the Admin_RemoveQueueManager action

MQeStoreAndForwardQueueAdminMsg addQueueManager

Syntax

```
public void addQueueManager( String targetQMgrName ) throws Exception
```

Description

Sets up an administration message to perform the Admin_AddQueueManager action. A queue may have one or more target queue managers. This method may be called more than once to allow multiple targets be added in one administration message.

Parameters

MQeStoreAndForwardQueueAdminMsg

targetQMgrName

Target queue manager name

Return values

none

Exceptions

java.lang.Exception

Various

Example

```
class MyApplication
{
    ...
    // Add target queue managers to a S&F queue
    MQeStoreAndForwardQueueAdminMsg msg =
        new MQeStoreAndForwardQueueAdminMsg();
    msg.setName( "ExampleQM", "ExampleQ" );

    // Set the action required and its parameters
    // into the message
    msg.addQueueManager( "Client129345" );
    msg.addQueueManager( "Client129387" );
    ...
}
```

MQeStoreAndForwardQueueAdminMsg removeQueueManager

Syntax

```
public void removeQueueManager( String targetQMgrName ) throws Exception
```

Description

Sets up an administration message to perform the Admin_RemoveQueueManager action. This method may be called more than once to allow multiple targets be removed in one administration message.

Parameters

targetQMgrName

target queue manager name

Return values

none

Exceptions

java.lang.Exception

Various

Example

```
class MyApplication
{
    ...
    // Remove target queue managers from S&F queue
    MQeStoreAndForwardQueueAdminMsg msg =
        new MQeStoreAndForwardQueueAdminMsg();
    msg.setName( "ExampleQM", "ExampleQ" );

    // Set the action required and its parameters
    // into the message
    msg.removeQueueManager( "Client129345" );
    msg.removeQueueManager( "Client129387" );
    ...
}
```

Chapter 4. Classes in com.ibm.mqe.attributes

This section contains detailed information about the following MQSeries Everyplace classes:

Table 13. Classes in package com.ibm.mqe.attributes

Class name	Purpose
**MQe3DESCryptor	Provides mechanisms for 3DES encryption
MQeDESCryptor	Provides mechanisms for DES encryption
MQeGenDH	Creates an MQeDHk.java file from which solution unique MQeDHk class objects can be created
MQeLocalSecure	Provides a simple local security service
MQeLZWCompressor	Provides mechanisms for LZW compression
**MQeMARSCryptor	Provides mechanisms for MARS encryption
MQeMAttribute	Provide simple message-level protection
**MQeMTrustAttribute	Provides more advanced message-level protection
**MQeRC4Cryptor	Provides mechanisms for RC4 encryption
**MQeRC6Cryptor	Provides mechanisms for RC6 encryption
MQeRleCompressor	Provides mechanisms for Run Length encoded compression
**MQeWTLSCertAuthenticator	Provides mechanisms for mini-certificate authentication
MQeXORCryptor	Provides mechanisms for XOR encryption

Note: Classes marked ** are available only in the high security version of MQSeries Everyplace Version 1.0.

MQe3DESCryptor

MQe3DESCryptor

Note: This class is only available in the high security version of MQSeries Everyplace Version 1.0.

This class is used to create a triple DES cryptor object that, when used by an attribute object, provides the attribute object with the mechanisms to perform triple DES encryption. Attribute objects are associated with channel and **MQeFields** objects.

Package com.ibm.mqe.attributes

This class is a descendant of **MQeCryptor**

MQe3DESCryptor

Syntax

```
public MQe3DESCryptor( )
```

Description

Constructs an MQe3DESCryptor object

Parameters

none

Return values

none

Exceptions

MQeException	Except_S_Cipher, "cip3DES, wrong cipher or key"
---------------------	---

Example

```
try
{
    MQe3DESCryptor tripledes = new MQe3DESCryptor();
    MQeAttribute tripledesA = new MQeAttribute(null, tripledes, null);
    ...
}
catch ( Exception e )
{
    ...
}
```

Related functions

- **MQeCryptor**
- **MQeAttribute**
- **MQeLocalSecure**
- **MQeMAttribute**
- **MQeMTrustAttribute**

MQeDESCryptor

This class is used to create a DES Cryptor object that, when used by an attribute object, provides the attribute object with the mechanisms to perform DES encryption. Attribute objects are associated with channel and **MQeFields** objects.

Package com.ibm.mqe.attributes

This class is a descendant of **MQeCryptor**

MQeDESCryptor

Syntax

```
public MQeDESCryptor( )
```

Description

Constructs an MQeDESCryptor object

Parameters

none

Return values

none

Exceptions

MQeException

Except_S_Cipher, "cipDES, wrong cipher or key"

Example

```
try
{
    MQeDESCryptor des = new MQeDESCryptor();
    MQeAttribute desA = new MQeAttribute(null, des, null);
    ...
}
catch ( Exception e )
{
    ...
}
```

Related functions

- **MQeCryptor**
- **MQeAttribute**
- **MQeLocalSecure**
- **MQeMAttribute**
- **MQeMTrustAttribute**

MQeGenDH

This class is used to create an MQeDHk.java file from which solution unique **MQeDHk** class objects can be created.

Package **com.ibm.mqe.attributes**

This class is a descendant of **MQe**

Method summary

Method	Purpose
main	Invokes a utility to generate a new MQDHk.java file
genParams	Generates a new DH pair and uses the new pair to create a new MQeDHk.java file

Part of the data flowed in *secure channel* establishment is Diffie Hellman partial key data. This data is used to generate a shared secret key, derivatives of which are subsequently used, to protect the confidentiality of the channel data, by the channel cryptor's encrypt and decrypt methods . The example shows how to use the utility to create a 512 bit Diffie Hellman key pair. To make this available to MQe, the resulting MQeDHk.java file must be compiled and installed as part of the com.ibm.mqe.attributes package.

MQeGenDH main

Syntax

```
java com.ibm.mqe.attributes.MQeGenDH <parameter1><parameter2>
```

Description

Invokes a utility to generate a new DH key pair and create a new MQeDHk.java file.

Parameters

<parameter 1> Optional, DH parameter length, defaults to 512

<parameter 2> Optional, Trace class name, e.g. examples.awt.AwtMQeTrace, defaults to use System Console

Return values


none - new MQeDHk file created in the current directory

Exceptions

none

Example

```
java com.ibm.mqe.attributes.MQeGenDH 512 examples.awt.AwtMQeTrace
```



MQeGenDH genParams

Syntax

```
public void genParams(int length)
```

Description

Invokes the utility to generate a new DH key pair and create a new MQeDHk.java file.

Parameters

length	Parameter bit length
--------	----------------------

Return Values

none - new MQeDHk file created in the current directory

Exceptions

none

MQeLocalSecure

MQeLocalSecure

This class is used to create a LocalSecure object that provides a simple local security service enabling a using application to apply a given attribute's (cryptor and compressor) components to protect local data

Package com.ibm.mqe.attributes

This class is a descendant of MQe

Constructor summary

Constructor	Purpose
MQeLocalSecure	Constructs an MQeLocalSecure object

Method summary

Method	Purpose
open	Enables the using application to identify the target File
read	Reads, unprotects and returns data from the target file
write	Protects and writes the given data to the target file

MQeLocalSecure

Syntax

```
public MQeLocalSecure( )
```

Description

Constructs an MQeLocalSecure object

Parameters

none

Return values

none

Exceptions

none

Example

```
MQeLocalSecure ls = new MQeLocalSecure( );
```

Related functions

- MQeAttribute

MQeLocalSecure open

Syntax

```
public void open( String directory,  
                  Object fileName )
```

Description

Sets the target filename.

Parameters

directory A string identifying the target File Directory

fileName A string identifying the target file name

Return Values

none

Exceptions

none

Related functions

- write
- read

MQeLocalSecure read

Syntax

```
Public byte[] read( MQeAttribute attr,
                    String localCipherKey ) throws Exception
```

Description

Reads and unprotects data from the given target filename

Parameters

attr **MQeAttribute** to be applied to unprotect data

localCipherKey Password or passphrase String to be used to unprotect data

Return Values

none

Exceptions

MQeException	Except_S_InvalidAttribute, "no cryptor" Except_S_InvalidAttribute, "illegal cryptor" Except_S_InvalidAttribute, "illegal authenticator or compressor" MQe.Except_Data, "wrong cipher"
Exception	java.io

Example

```
try
{
    MQeDESCryptor des = new MQeDESCryptor();
    MQeAttribute desA = new MQeAttribute( null, des, null );
    MQeLocalSecure ls = new MQeLocalSecure();
    ls.open( ".\\\" , "TestSecureData.txt" );
    String outData = byteToAscii( ls.read( A,
                                         "It_is_a_secret" ) );
    Trace ( "i: unprotected data = " + outData );
}
catch ( Exception e )
{
}
...
```

MQeLocalSecure write

Syntax

MQeLocalSecure

```
Public void write ( byte[] data,
                   MQeAttribute attr,
                   String localCipherKey) throws Exception
```

Description

Protects data and writes it to the given target filename.

Parameters

data Data to protect

attr **MQeAttribute** to be applied to protect data

localCipherKey

Password or passphrase String to be used to protect data

Return Values

none

Exceptions

MQeException	Except_S_InvalidAttribute, "no cryptor" Except_S_InvalidAttribute, "illegal cryptor" Except_S_InvalidAttribute, "illegal authenticator or compressor"
Exception	java.io

Example

```
try
{
    MQeDESCryptor des = new MQeDESCryptor();
    MQeAttribute desA = new MQeAttribute( null, des, null);
    MQeLocalSecure ls = new MQeLocalSecure();
    ls.open( ".\\\" , "TestSecureData.txt" );
    ls.write( asciiToByte( "0123456789abcdef..." ),
              desA, "It_is_a_secret" );
    ...
}
catch ( Exception e )
{
    ...
}
```

MQeLZWCompressor

This class is used to create an LZW Compressor object that, when used by an attribute object, provides the attribute object with the mechanisms to perform LZW compression. Attribute objects are associated with channel and **MQeFields** objects.

Package com.ibm.mqe.attributes

This class is a descendant of **MQeCompressor**

MQeLZWCompressor

Syntax

```
public MQeLZWCompressor()
```

Description

Constructs an MQeLZWCompressor object

Parameters

none

Return values

none

Exceptions

none

Example

```
try
{
    MQeLZWCompressor lzw = new MQeLZWCompressor();
    MQeAttribute lzwA     = new MQeAttribute(null, null, lzw);
    ...
}
catch ( Exception e )
{
    ...
}
```

Related functions

- **MQeCompressor**
- **MQeAttribute**
- **MQeLocalSecure**
- **MQeMAttribute**
- **MQeMTrustAttribute**

MQeMARSCryptor

Note: This class is only available in the high security version of MQSeries Everyplace Version 1.0.

This class is used to create a MARS cryptor object that, when used by an attribute object, provides the attribute object with the mechanisms to perform MARS encryption. Attribute objects are associated with channel and **MQeFields** objects.

Package com.ibm.mqe.attributes

This class is a descendant of **MQeCryptor**

MQeMARSCryptor

Syntax

```
public MQeMARSCryptor( )
```

Description

Constructs an MQeMARS cryptor object

Parameters

none

Return values

none

Exceptions

none

Example

```
try
{
    MQeMARSCryptor mars      = new MQeMARSCryptor();
    MQeAttribute marsA       = new MQeAttribute(null, mars, null);
    ...
}
catch ( Exception e )
{
    ...
}
```

Related functions

- **MQeCryptor**
- **MQeAttribute**
- **MQeLocalSecure**
- **MQeMAttribute**
- **MQeMTrustAttribute**

MQeMAttribute

This class is used to create an attribute object enabling simple message-level protection when attached to a message.

Package com.ibm.mqe.attributes

This class is a descendant of **MQeAttribute**

Constructor summary

Constructor	Purpose
MQeMAttribute	Constructs an MQeMAttribute object

Method summary

Method	Purpose
decodeData	Decrypt and/or decompress the supplied data
encodeData	Compress and/or encrypt the supplied data

MQeMAttribute

Syntax

1.
public MQeMAttribute()
2.
public MQeMAttribute(MQeAuthenticator authenticator,
MQeCryptor cryptor,
MQeCompressor compressor) throws Exception

Description

Constructs an **MQeMAttribute** object

Parameters

- authenticator** null or an object reference to an **MQeAuthenticator** object
- cryptor** An object reference to a symmetric **MQeCryptor** object (**MQeDESCryptor**, **MQe3DESCryptor**, **MQeRC4Cryptor**, **MQeRC6Cryptor** or **MQeMARSCryptor**)
- compressor** null or an object reference to a **MQeCompressor** object (**MQeRleCompressor** or **MQeLZWCompressor**)

Return values

none

Exceptions

- | | |
|---------------------|--|
| MQeException | Except_ Not Supported, "invalid authenticator" |
| | Except_ Not Supported, "invalid cryptor" |
| | Except_ Not Supported, "invalid compressor" |

Example

MQeMAttribute

```
class MySampleClass extends MQe
{
    /* application on initiating QueueManager:
     * -prepare to use MQeMAttribute with Rle Compressor
     * and DES Cryptor with key = It_is_a_secret */
    MQeKey localkey      = new MQeKey();
    localkey.setLocalKey( "It_is_a_secret");
    MQeDESCryptor des    = new MQeDESCryptor();
    MqeRleCompressor rle   = new MQeRleCompressor();
    MQeMAttribute protMAttr = new MQeMAttribute( null, des, rle );
    protMAttr.setKey( localkey );
    /* construct Message and protect with the MQeMAttribute */
    MQeMessageObj MsgObj   = new MQeMessageObject();
    MsgObj.setAttribute( protMAttr ); /* add test message data */
    MsgObj.putAscii("MsgData", "0123456789abcdef....");
    trace ("i: input message data = " + MsgObj.getAscii("MsgData") );
    /* assume MQeQueueManager instance initQM started, PutMessage */
    initQM.putMessage( targetQMName, targetQName, MsgObj ,null, 0);
    ...
    ...///
    .../.
    .../.
    /* application on recipient QueueManager:
     * -prepare to use MQeMAttribute with key = It_is_a_secret */
    MQeKey localkey      = new MQeKey();
    localkey.setLocalKey( "It_is_a_secret");
    MQeDESCryptor des    = new MQeDESCryptor();
    MqeRleCompressor rle   = new MQeRleCompressor();
    MQeMAttribute protMAttr = new MQeMAttribute( null, des, rle );
    protMAttr.setKey( localkey );
    /* assume MQeQueueManager instance recipQM started, GetMessage */
    MQeMsgObject MsgObj   = recipQM.getMessage(thisQMName,
                                                thisQName, null, protMAttr, 0);
    trace ("i: output message data = " + MsgObj.getAscii( "MsgData" ) );
}

}
```

Related functions
[MQeAttribute](#)

MQeMAttribute decodeData

Syntax

```
public byte[] decodeData( MQeChannel channel,
                           byte data[],
                           int offset,
                           int count ) throws Exception
```

Description

Is called to decode (decrypt and/or decompress) the bytes referenced by **data**, **offset** and for length **count**.

Note: This method is intended for internal use and is not normally called by applications.

Parameters

channel	<i>null</i> , not used
data	An object reference to a byte array containing the data to be decoded
offset	An integer index specifying the start byte in the data array

MQeMAttribute

count An integer count of the number of bytes to decode

Return Values

Decoded data

Exceptions

MQeException Except_Data, "data tampering detected"

Except_S_NoPresetKeyAvailable

MQeMAttribute encodeData

Syntax

```
public byte[] encodeData( MQeChannel channel,  
                           byte data[],  
                           int offset,  
                           int count ) throws Exception
```

Description

Encodes (encrypts and/or compresses) the bytes referenced by *data*, **offset** and for length **count**.

Note: This method is intended for internal use and is not normally called by applications.

Parameters

channel *null*, not used

data An object reference to a byte array containing the data to be encoded

offset An integer index specifying the start byte in the **data** array

count An integer count of the number of bytes to encode

Return Values

none

Exceptions

MQeException Except_Non_Supported, "invalid cryptor"

Except_Non_Supported, "invalid compressor"

Except_S_NoPresetKeyAvailable

MQeMTrustAttribute

MQeMTrustAttribute

Note: This class is only available in the high security version of MQSeries Everyplace Version 1.0.

This class is used to create an attribute object enabling message-level protection of message objects in such a way that :

- Validation of the originator's (ISO9796) digital signature enables the recipient to establish the message's origin (nonrepudiation)
- Message confidentiality is protected using the attribute's cryptor
- Message integrity is validated
- Message data can only be restored by the intended recipient

Package **com.ibm.mqe.attributes**

This class is a descendant of **MQeAttribute**

Constructor summary

Constructor	Purpose
MQeMTrustAttribute	Constructs an MQeMTrustAttribute object

Method summary

Method	Purpose
decodeData	Decodes the supplied data
encodeData	Encodes the supplied data.
setHomeServer	Sets address of home server/alternative MQeNode
setPrivateRegistry	Sets active private registry
setPublicRegistry	Sets active public registry

MQeMTrustAttribute

Syntax

1.

```
public MQeMTrustAttribute( )
```
2.

```
public MQeMTrustAttribute( MQeAuthenticator authenticator,
                           MQeCryptor cryptor,
                           MQeCompressor compressor) throws Exception
```

Description

Constructs an MQeMTrustAttribute object

Parameters

authenticator *null*, not used

cryptor An object reference to a symmetric **MQeCryptor** object (**MQeDESCryptor**, **MQe3DESCryptor**, **MQeRC4Cryptor**, **MQeRC6Cryptor** or **MQeMARSCryptor**)

compressor *null*, not used

Return values

none

Exceptions**MQeException**

Except_ Not Supported, "invalid cryptor"

Example

```

class MySampleClass extends MQe
{
    /* application on initiating QueueManager: */ 
    /* use MQeMTrustAttribute to protect a message between */ 
    /* pre-reg'd initiator 'Bruce1' and recipient 'Bruce8' */ 
    /* assume initiator's QueueManager initQM started */ 
    /* setup MTrustAttribute */ 
    MQeMARSCryptor mars      = new MQeMARSCryptor( ); 
    MQeMTrustAttribute msgA = new MQeMTrustAttribute( null, mars, null ); 

    /* setup instantiate & activate sender (Bruce1) PrivReg */ 
    String EntityName      = "Bruce1"; 
    String EntityPIN       = "12345678"; 
    Object KeyRingPassword = "It_is_a_secret"; 
    MQePrivateRegistry sendreg = new MQePrivateRegistry( ); 
    sendreg.activate( EntityName, "./MQeNode_PrivateRegistry", 
                      EntityPIN, KeyRingPassword, null, null ); 

    /* set target entity's registry name into sender's reg */ 
    sendreg.setTargetRegistryName("Bruce8"); 
    /* set MTrustAttribute's PrivateRegistry = sendreg */ 
    msgA.setPrivateRegistry( sendreg ); 
    /* instantiate and activate Public Registry which has */ 
    /* (or gets) MiniCert of intended recipient (Bruce8) */ 
    MQePublicRegistry pr     = new MQePublicRegistry( ); 
    pr.activate( "MQeNode_PublicRegistry", "./" ); 
    /* set MTrustAttribute's PublicRegistry & HomeServer */ 
    msgA.setPublicRegistry(pr); 
    msgA.setHomeServer( MyHomeServer + ":8081" ); 

    /* create message object and add some test data */ 
    MQeMsgObject msgObj     = new MQeMsgObject( ); 
    msgObj.putArrayOfByte( "TestData", 
                          asciiToByte("0123456789abcdef....") ); 
    /* protect with MQeMTrustAttribute and PutMessage */ 
    msgObj.setAttribute( msgA ); 
    initQM.putMessage( targetQMgrName, targetQName, msgObj, null, 0 ); 

    ...
    /* application on recipient QueueManager: */ 
    /* use MQeMTrustAttribute to recover the message from. */ 
    /* pre-registered initiator 'Bruce1' and recipient 'Bruce8' */ 
    /* assume recipient's QueueManager recipQM started */ 
    ...
    /* setup MQeMTrustAttribute */ 
    MQeMARSCryptor mars      = new MQeMARSCryptor( ); 
    MQeMTrustAttribute msgA = new MQeMTrustAttribute(null, mars, null); 

    /* setup recipient's Private Registry */ 
    String EntityName      = "Bruce8"; 
    String EntityPIN       = "12345678"; 
    Object KeyRingPassword = "It_is_a_secret"; 

    /* instantiate and activate recipient's Private Registry */ 
    MQePrivateRegistry recipreg = new MQePrivateRegistry( ); 
    recipreg.activate( EntityName, "./MQeNode_PrivateRegistry", 
                      EntityPIN, KeyRingPassword, null, null ); 
    /* set MTrustAttribute PrivateRegistry = recipreg */ 

```

MQeMTrustAttribute

```
msgA.setPrivateRegistry( recipreg );
/* instantiate and activate Public Registry which has */
/* (or gets) MiniCert of originator (Bruce1) */
MQePublicRegistry pr      = new MQePublicRegistry( );
pr.activate( "MQeNode_PublicRegistry", "./" );
/* set MTrustAttribute's PublicRegistry & HomeServer */
msgA.setPublicRegistry( pr );
msgA.setHomeServer( MyHomeServer + ":8081" );
/* use MQeMTrustAttribute with GetMessage to recover msg */
MQeMsgObject MsgObj = SvrQM.getMessage( TargetQMgrName,
                                         TargetQName,null, msgA, 0 );
trace("i: Data restored from MTrustAttr protected Msg =" +
      byteToAscii(MsgObj.getArrayOfByte("TestData") ) );
}
```

Related functions

- MQePrivateRegistry
- MQePublicRegistry

MQeMTrustAttribute decodeData

Syntax

```
public byte[] decodeData( MQeChannel channel,
                         byte data[],
                         int offset,
                         int count ) throws Exception
```

Description

Is called to decode (decrypt and/or decompress) the bytes referenced by **data**, **offset** and for length **count**.

Note: This method is intended for internal use and is not normally called by applications.

Parameters

channel	<i>null</i> , not used
data	An object reference to a byte array containing the data to be decoded
offset	An integer index specifying the start byte in the data array
count	An integer count of the number of bytes to decode

Return Values

Decoded data

Exceptions

MQException	Except_S_RegistryNotAvailable "intended recipient's PrivateRegistry not available"
	Except_S_MiniCertNotAvailable "cannot recover data, sender's MiniCert not available"
	Except_S_RegistryNotAvailable "cannot recover data target(recipient) PrivateRegistry not available"
	Except_S_BadIntegrity, "validating data from < Sender> data tampering detected"

MQeMTrustAttribute

Except_S_InvalidSignature, "validating data from < Sender > bad signature"

MQeMTrustAttribute encodeData

Syntax

```
public byte[] encodeData( MQeChannel channel,  
                           byte data[],  
                           int offset,  
                           int count ) throws Exception
```

Description

Encodes (encrypts and/or compresses) the bytes referenced by **data**, **offset** and for length **count**.

Note: This method is intended for internal use and is not normally called by applications.

Parameters

channel	<i>null</i> , not used
data	An object reference to a byte array containing the data to be encoded
offset	An integer index specifying the start byte in the data array
count	An integer count of the number of bytes to encode

Return Values

none

Exceptions

MQeException	Except_S_MiniCertNotAvailable, "cannot protect data, target Mini Certificate not available" Except_S_RegistryNotAvailable "sender's PrivateRegistry not available"
---------------------	---

MQeMTrustAttribute setHomeServer

Syntax

```
public void setHomeServer( String homeServerAddrPort)  
                           throws Exception
```

Description

Called to set an MQeMTrustAttribute's *home server* address. When used to protect a message, **encodeData** attempts to get the intended recipient's Mini-Certificate recipient from its active public registry. If not found but the *home server* address is set, it requests the Mini-Certificate from the *home server*, and saves it for subsequent use in the active public registry. When used to recover a message, **decodeData** attempts to gets the initiator's Mini-Certificate from its active public registry. If not found but the *home server* address is set, it requests the Mini-Certificate from the *home server* and saves it for subsequent use in its active public registry.

Parameters

homeServerAddrPort	The address of another MQeNode (for example HomeServer) with a public registry containing a larger set of
---------------------------	---

MQeMTrustAttribute

authenticatable entities' Mini-Certificates.
The format used is tcpname:port, or
tcpaddress:port

Return Values

none

Exceptions

MQeException

Except_NotAllowed, "illegal
SetPublicRegistry"

MQeMTrustAttribute setPrivateRegistry

Syntax

```
public void setPrivateRegistry( MQePrivateRegistry privreg)  
throws Exception
```

Description

Called to set an MQeMTrustAttribute's active private registry. When used to protect a message this is the private registry of the sender and when recovering a message this is the private registry of the recipient.

Parameters

privreg The activated **MQePrivateRegistry** of the sender or recipient authenticatable entity

Return Values

none

Exceptions

MQeException

Except_NotAllowed, "illegal
SetPrivateRegistry"

MQeMTrustAttribute setPublicRegistry

Syntax

```
public void setPublicRegistry( MQePublicRegistry pubreg)  
throws Exception
```

Description

Called to set an MQeMTrustAttribute's active public registry. When used to protect a message this is a public registry that has (or gets) the Mini-Certificate of the intended recipient, and when recovering a message this is a public registry that has (or gets) the Mini-Certificate of the sender.

Parameters

pubreg An activated **MQePublicRegistry** containing the Min-Certificate of the intended recipient, when used to protect, or the Mini-Certificate of the sender, when used to recover.

Return Values

none

Exceptions

MQeException

Except_NotAllowed, "illegal
SetPublicRegistry"

MQeRC4Cryptor

Note: This class is only available in the high security version of MQSeries Everyplace Version 1.0.

This class is used to create a RC4 cryptor object that, when used by an attribute object, provides the attribute object with the mechanisms to perform RC4 encryption. Attribute objects are associated with channel and **MQeFields** objects.

Package com.ibm.mqe.attributes

This class is a descendant of **MQeCryptor**

MQeRC4Cryptor

Syntax

```
public MQeRC4Cryptor( )
```

Description

Constructs an MQeRC4Cryptor object

Parameters

None

Return values

none

Exceptions

MQeException

Except_S_Cipher, "cipRC4, wrong cipher or key"

Example

```
try
{
    MQeRC4Cryptor rc4      = new MQeRC4Cryptor();
    MQeAttribute rc4A      = new MQeAttribute(null, rc4, null);
    ...
}
catch ( Exception e )
{
    ...
}
```

Related functions

- **MQeCryptor**
- **MQeAttribute**
- **MQeLocalSecure**
- **MQeMAttribute**
- **MQeMTrustAttribute**

MQeRC6Cryptor

Note: This class is only available in the high security version of MQSeries Everyplace Version 1.0.

This class is used to create a RC6 cryptor object that, when used by an attribute object, provides the attribute object with the mechanisms to perform RC6 encryption. Attribute objects are associated with channel and **MQeFields** objects.

Package com.ibm.mqe.attributes

This class is a descendant of **MQeCryptor**

MQeRC6Cryptor

Syntax

```
public MQeRC6Cryptor( )
```

Description

Constructs an MQeRC6Cryptor object

Parameters

none

Return values

none

Exceptions

MQeException	Except_S_Cipher, "cipRC6, wrong cipher or key"
---------------------	--

Example

```
try
{
    MQeRC6Cryptor rc6 = new MQeRC6Cryptor();
    MQeAttribute rc6A = new MQeAttribute(null, rc6, null);
    ...
}
catch ( Exception e )
{
    ...
}
```

Related functions

- **MQeCryptor**
- **MQeAttribute**
- **MQeLocalSecure**
- **MQeMAttribute**
- **MQeMTrustAttribute**

MQeRleCompressor

This class is used to create an Rle compressor object that, when used by an attribute object, provides the attribute object with the mechanisms to perform Rle compression. Attribute objects are associated with channel and **MQeFields** objects.

Package com.ibm.mqe.attributes

This class is a descendant of **MQeCompressor**

MQeRleCompressor

Syntax

```
public MQeRleCompressor( )
```

Description

Constructs an MQeRleCompressor object

Parameters

none

Return values

none

Exceptions

none

Example

```
try
{
    MQeRleCompressor rle = new MQeRleCompressor();
    MQeAttribute rleA     = new MQeAttribute(null, null, rle);
    ...
}
catch ( Exception e )
{
    ...
}
```

Related functions

- **MQeCompressor**
- **MQeAttribute**
- **MQeLocalSecure**
- **MQeMAttribute**
- **MQeMTrustAttribute**

MQeWTLSCertAuthenticator

Note: This class is only available in the high security version of MQSeries Everyplace Version 1.0.

This class is used to create a WTLSCertAuthenticator object that, when used by an attribute object, provides the attribute object with the mechanisms to perform Mini-Certificate based mutual authentication. This applies to **Attribute** objects associated with channel objects.

Package com.ibm.mqe.attributes

This class is a descendant of **MQeAuthenticator**

MQeWTLSCertAuthenticator

Syntax

```
public MQeWTLSCertAuthenticator( )
```

Description

Constructs an MQeWTLSCertAuthenticator object

Parameters

none

Return values

none

Exceptions

none

Example

```
try
{
    MQeWTLSCertAuthenticator wtls = new MQeWTLSCertAuthenticator( );
    MQeDESCryptor des           = new MQeDESCryptor( );
    MQeAttribute wtlsA          = new MQeAttribute(wtls, des, null);
    ...
}
catch ( Exception e )
{
    ...
}
```

Related functions

- **MQeAuthenticator**
- **MQeAttribute**

MQeXORCryptor

This class is used to create an XOR cryptor object that, when used by an attribute object, provides the attribute object with the mechanisms to perform XOR encoding. Attribute objects are associated with channel and **MQeFields** objects.

Package com.ibm.mqe.attributes

This class is a descendant of **MQeCryptor**

Constructor summary

Constructor	Purpose
MQeXORCryptor	Constructs an MQeXORCryptor object

Method summary

Method	Purpose
setDecryptKey	Explicitly sets the cryptor's decrypt key
setEncryptKey	Explicitly sets the cryptor's encrypt key

MQeXORCryptor

Syntax

```
public MQeXORCryptor( )
```

Description

Constructs an MQeXORCryptor object

Parameters

none

Return values

none

Exceptions

none

Example

```
try
{
    MQeXorCryptor xor = new MQeXorCryptor( );
    xor.setEncryptKey( asciiToByte("It_is_a_secret") );
    NTAuthenticator nt = new NTAuthenticator();
    String inData      = "0123456789abcdef...";
    trace("i: TestXOR, indata = " + inData);
    MQeFields tempf   = new MQeFields();
    tempf.putAscii( "testdata", inData);
    MQeAttribute attr1 = new MQeAttribute();
    attr1.activate( null, nt, xor, null );
    tempf.setAttribute( attr1 );
    byte[] temp = tempf.dump();

    //

    MQeFields tempf2   = new MQeFields();
    MQeXorCryptor xor2 = new MQeXorCryptor( );
    xor2.setDecryptKey( asciiToByte("It_is_a_secret") );
    NTAuthenticator nt2 = new NTAuthenticator();
}
```

MQeXORCryptor

```
MQeAttribute attr2 = new MQeAttribute( );
attr2.activate( null, nt2, xor2, null );
tempf2.setAttribute ( attr2 );
tempf2.restore( temp );
trace("i: TestXORSecure, outdata = " + tempf2.getAscii("testdata"));
}
catch ( Exception e )
{
//
}
```

Related functions

- [MQeCryptor](#)
- [MQeAttribute](#)

MQeXORCryptor setDecryptKey

Syntax

```
Public void setDecryptKey ( Object newKey) throws Exception
```

Description

Explicitly sets the cryptor's decrypt key

Parameters

newKey	byte[] seed from which the cryptor's decrypt key is derived.
---------------	--

Return values

none

Exceptions

none

MQeXORCryptor setEncryptKey

Syntax

```
Public void setEncryptKey ( Object newKey) throws Exception
```

Description

Explicitly sets the cryptor's encrypt key

Parameters

newKey	byte[] seed from which the cryptor's encrypt key is derived.
---------------	--

Return values

none

Exceptions

none

Chapter 5. Classes in com.ibm.mqe.registry

This section contains detailed information about the following MQSeries Everyplace classes:

Table 14. Classes in package com.ibm.mqe.registry

Class name	Purpose
MQePrivateRegistry	Creates a private registry object that provides controlled access to a set of private and public objects
MQePrivateRegistryConfigure	Used to configure a private registry
MQePublicRegistry	Creates a public registry object that provides controlled access to a set of private and public objects

MQePrivateRegistry

MQePrivateRegistry

This class is used to create an MQePrivateRegistry object. MQePrivateRegistry class is a descendent of **MQeRegistry** and provides controlled access to a set of private and public objects (for example certificates). MQePrivateRegistry objects also support digital signing and decryption services which can use the registry's private objects (for example an authenticatable entity's private key) internally, so they do not leave the *private registry*.

Package com.ibm.mqe.registry

This class is a descendant of **MQeRegistry**

Constructor summary

Constructor	Purpose
MQePrivateRegistry	Constructs an MQePrivateRegistry object

Method summary

Method	Purpose
activate	Opens and activates the MQePrivateRegistry instance.
deleteCertificate	Deletes the certificate owner's Mini-Certificate
getCertificate	Returns the certificate owner's Mini-Certificate
getRegistryName	Gets the private registry's authenticatable entity name.
resetPIN	Resets the PIN that controls private access.
setTargetRegistryName	Sets the name of the intended recipient (authenticatable entity) private registry

MQePrivateRegistry

Syntax

```
public MQePrivateRegistry( )
```

Description

Constructs an MQePrivateRegistry object

Parameters

none

Return values

none

Exceptions

none

Related functions

- MQePublicRegistry

MQePrivateRegistry activate

Syntax

```
Public void activate (String entityName,  
                      String dirName,  
                      String pin,
```

MQePrivateRegistry

```
Object keyRingPassword,  
Object certReqPIN,  
Object caIPAddrPort ) throws Exception
```

Description

If a private registry with this **entityName** exists, **activate** attempts to open the private registry using the given **pin**. If it does not exist, **activate** creates and opens a new private registry and makes it accessible with the given **pin**.

If a non-null Mini-Certificate server address (**caIPAddrPort**) is provided, **activate** searches the private registry to discover if the owner is already registered (already has its own Mini-Certificate). If it is not registered (no Mini-Certificate), **activate** executes autoregistration. This autoregisters the **entityName**, performing the following tasks:

- Generates a new RSA key pair for the owning **entityName**
- Saves the private key(CRTKey) in the private registry after protecting using a derivative of the given **keyRingPassword**
- Packages the public key in a **newCertificateRequest** to the Mini-Certificate server address given, identifying the request with the **entityName** and the given (pre-allocated) Mini-Certificate request pin (**certReqPIN**)
- Saves the issued Mini-Certificate in the private registry then sends a **getCertificate** request to get the Mini-Certificate server's (own) Mini-Certificate, and saves it in the private registry

Parameters

entityName	PrivateRegistry owner EntityName
dirName	Path to PrivateRegistry
pin	Number, password or passphrase to be used to open the private registry
keyRingPassword	String password or passphrase used to protect the entity's private key
certReqPIN	String with one-time-use <i>Certificate Request Number</i> preallocated for the entity by the Mini-Certificate server administrator to enable it to autoregister
caIPAddrPort	String with the TCP address and port of the solution's Mini-Certificate server, for example aname.hursley.ibm.com:8081

Return Values

none

Exceptions

MQeException	Except_PrivateReg_BadPIN, "Activating_EntityName_PrivateRegistry" Except_PrivateReg_ActivateFailed Except_PrivateReg_ActivateFailed, "Registration exception "
---------------------	--

Example

MQePrivateRegistry

```
class MySampleClass extends MQe
{
    try
    {
        /* setup Private Registry activate parameters */
        String entityName      = "Bruce";
        String dirName          = "./" + EntityName;
        String entityPIN        = "12345678";
        Object keyRingPassword  = "It_is_a_secret";
        Object certReqPIN      = "12345678";
        Object caIPAddrPort     = "aname.hursley.ibm.com:8081";
        /* instantiate and activate a Private Registry... */
        MQePrivateRegistry preg = new MQePrivateRegistry( );
        /* instantiate and activate the Private Registry */
        preg.Activate( entityName, /* name of entity owning privreg */
                       dirName,   /* params to open file regsess'n */
                       entityPIN, /* Private Registry access PIN */
                       keyRingPassword,/* pwd/phrase protecting CRTKey */
                       certReqPIN, /* prereg MiniCertSvr certreqPIN */
                       caIPAddrPort); /* trusted MiniCertSvr addr:port */
    }
    catch ( Exception e )
    {
    }
}
```

Related functions
[MqeLocalSecure](#)

MQePrivateRegistry deleteCertificate

Syntax

```
Public MQeFields deleteCertificate( String certificateOwner )
                                         throws MQeException
```

Description

Deletes the certificate owner's Mini-Certificate.

Parameters

certificateOwner

Private registry owner's name

Return Values

none

Exceptions

MQeException

Except_Reg_DoesNotExist, "Entry does not exist"

Except_Reg_DeleteFailed, "Error deleting entry"

Related functions
[getCertificate](#)

MQePrivateRegistry getCertificate

Syntax

```
Public MQeFields getCertificate( String certificateOwner )
                                         throws MQeException
```

Description

Returns the certificate owner's Mini-Certificate.

Parameters

MQePrivateRegistry

certificateOwner

Private registry owner's name

Return Values

Mini-Certificate

Exceptions

MQeException

Except_Reg_ReadFailed, "Error reading entry"

Related functions

deleteCertificate

MQePrivateRegistry getRegistryName

Syntax

```
Public String getRegistryName( )
```

Description

Returns the owning entity name

Parameters

none

Return Values

Owning entity name

Exceptions

none

MQePrivateRegistry resetPIN

Syntax

```
Public void resetPIN(String currentPIN,  
                      String newPIN ) throws Exception
```

Description

Enables a valid private registry owner to change the access PIN

Parameters

currentPIN Current valid PIN (password or passphrase) for private registry

newPIN New PIN (password or passphrase)

Return Values

none

Exceptions

MQeException

Except _PrivateReg_BadPIN , "PIN not reset, bad current PIN provided"

MQePrivateRegistry setTargetRegistryName

Syntax

```
Public void setTargetRegistryName( String registryName)
```

Description

Adds the name of the intended recipient's private registry.

Parameters

MQePrivateRegistry

registryName Current valid PIN (password or passphrase) for private registry

newPIN recipient's Private Registry name

Return Values

none

Exceptions

none

Examples

See "MQeMTrustAttribute" on page 240

Related functions

- **MQeMTrustAttribute**

MQePrivateRegistryConfigure

This class is used to configure a Private Registry. The class is used to get new credentials (private and public certificates) for the registry.

Package com.ibm.mqe.registry

This class is a descendant of **MQeRegistry**

Constructor summary

Constructor	Purpose
MQePrivateRegistryConfigure	Instantiates the registry configuration object

Method summary

Method	Purpose
activate	Initializes the class and opens the registry
close	Closes the registry and tidies up
credentialsExist	Checks whether credentials already exist for the registry
getCredentials	Obtains new credentials for the registry
isPrivate	Checks whether the registry is a private registry

MQePrivateRegistryConfigure

Syntax

1.
public MQePrivateRegistryConfigure()
2.
public MQePrivateRegistryConfigure(String name,
 MQeFields parms,
 String PIN) throws Exception

Description

The constructor instantiates the registry configuration object, there are two versions.

1. This is an empty constructor that is designed for dynamic loading and must be followed by a call to **activate()**
2. This version saves the name and opens the registry; it is equivalent to the empty constructor followed by **activate()**

Parameters

- name** The name associated with this registry
regParams An **MQeFields** object containing the initialization parameters for the registry:

MQeRegistry.LocalRegType (ascii)

This determines the type of the registry being opened. Because this should be a private registry, this parameter should be set to `com.ibm.mqe.registry.MQePrivateSession`, or an equivalent alias.

MQePrivateRegistryConfigur

MQeRegistry.DirName (ascii)

The name of the directory holding the registry files

MQeRegistry.PIN (ascii)

The PIN for the private registry. This is used if the `regPIN` parameter on `activate()` is *null*.

MQeRegistry.KeyRingPassword (ascii)

The password or passphrase used to protect the registry's private key.

MQeRegistry.Separator (ascii)

The character to be used as a separator between the components of an entry name, for example `<QueueManager><Separator><Queue>`.

This is specified as a string but it should contain a single character, if it contains more than one only the first character is used.

The same separator character should be used every time a registry is opened, it should not be changed once a registry is in use and contains entries.

If this value is not specified it defaults to "+".

regPIN The PIN required to open the registry. If this is *null*, the PIN is taken from the `regParams` parameter.

Return values

none

Exceptions

Exception	Thrown if there is a problem opening the registry
------------------	---

Example

```
MQePrivateRegistryConfigure regConfig1;
regConfig1 = new MQePrivateRegistryConfigure();

try
{
    MQePrivateRegistryConfigure regConfig2;
    MQeFields parms = new MQeFields();
    parms.putUnicode(MQeRegistry.DirName, "Registry_Dir");
    ...
    regConfig2 = new MQePrivateRegistryConfigure("Reg2", parms, null);
}
catch (Exception e)
{ ... }
```

MQePrivateRegistryConfigure activate

Syntax

```
public void activate( String name,
                     MQeFields regParams,
                     String regPIN ) throws Exception
```

Description

This saves the registry name and opens the registry. If the `regPIN`

MQePrivateRegistryConfigur

parameter is not *null* it is used to open the registry, otherwise the registry's PIN is obtained from the **regParams** parameter.

Parameters

name The name associated with this registry

regParams An **MQeFields** object containing the initialization parameters for the registry.

MQeRegistry.LocalRegType (ascii)

This determines the type of the registry being opened. Because this should be a private registry, this parameter should be set to `com.ibm.mqe.registry.MQePrivateSession`, or an equivalent alias.

MQeRegistry.DirName (ascii)

The name of the directory holding the registry files

MQeRegistry.PIN (ascii)

The PIN for the private registry. This will be used if the **regPIN** parameter is *null*.

MQeRegistry.KeyRingPassword (ascii)

The password or passphrase used to protect the registry's private key.

MQeRegistry.Separator (ascii)

The character to be used as a separator between the components of an entry name, for example `<QueueManager><Separator><Queue>`.

This is specified as a string but it should contain a single character, if it contains more than one only the first character is used.

The same separator character should be used every time a registry is opened, it should not be changed once a registry is in use and contains entries.

If this value is not specified it defaults to "+".

regPIN The PIN required to open the registry. If this is *null*, the PIN is taken from the **regParams** parameter.

Return Values

none

Exceptions

MQeException

Is thrown if there is a problem opening the registry.

Exception

Is thrown if there are any other problems

Example

```
try
{
    MQePrivateRegistryConfigure regConfig;
    MQeFields parms = new MQeFields();
    parms.putUnicode(MQeRegistry.DirName, "Registry_Dir");
    ...
}
```

MQePrivateRegistryConfigur

```
    regConfig = new MQePrivateRegistryConfigure();
    regConfig.activate("Reg", parms, null);
}
catch (Exception e)
{ ... }
```

Related functions
[MQeLocalSecure](#)

MQePrivateRegistryConfigure close

Syntax

```
public void close()
```

Description

This closes the configuration object and the associated registry. An attempt to use the object after it has been closed results in an exception.

Parameters

none

Return Values

none

Exceptions

none

Example

```
try
{
    MQePrivateRegistryConfigure regConfig;
    MQeFields parms = new MQeFields();
    parms.putUnicode(MQeRegistry.DirName, "Registry_Dir");
    ...
    regConfig = new MQePrivateRegistryConfigure("Reg", parms, null);
    if ( regConfig.credentialsExist() )
    {
        ...
        regConfig.close();
    }
    catch (Exception e)
    { ... }
```

MQePrivateRegistryConfigure credentialsExist

Syntax

```
public boolean credentialsExist ( ) throws MQeException
```

Description

This method checks whether the registry already contains credentials.

Parameters

none

Return Values

true	If the registry already contains credentials
false	If the registry does not contain credentials

Exceptions

MQeException	Is thrown if the class has not been activated
---------------------	---

Example

```

try
{
    MQePrivateRegistryConfigure regConfig;
    MQeFields parms = new MQeFields();
    parms.putUnicode(MQeRegistry.DirName, "Registry_Dir");
    ...
    regConfig = new MQePrivateRegistryConfigure("Reg", parms, null);
    if ( regConfig.credentialsExist() )
    {
        ...
    }
    catch (Exception e)
    { ... }
}

```

MQePrivateRegistryConfigure getCredentials**Syntax**

```

public void getCredentials( MQeFields regParams,
                           String regPIN,
                           String minCertServer,
                           String miniCertPIN,
                           String renamePrefix ) throws Exception

```

Description

This creates new credentials for the registry.

If the registry already contains credentials, they are renamed using the **renamePrefix**. If the rename fails, for example because the new name already exists in the registry, an exception is thrown and new credentials are not obtained. If an error occurs after the credentials have been renamed, they are changed back to their original names before **getCredentials()** returns.

This method calls the Mini-Certificate server and can take some time to complete.

Parameters

regParams An **MQeFields** object containing the initialization parameters for the registry.

MQeRegistry.LocalRegType (ascii)

This determines the type of the registry being opened. Because this should be a private registry, this parameter should be set to `com.ibm.mqe.registry.MQePrivateSession`, or an equivalent alias.

MQeRegistry.DirName (ascii)

The name of the directory holding the registry files

MQeRegistry.PIN (ascii)

The PIN for the private registry. This is used if the **regPIN** parameter on **activate()** is *null*.

MQeRegistry.KeyRingPassword (ascii)

The password or passphrase used to protect the registry's private key.

MQeRegistry.Separator (ascii)

MQePrivateRegistryConfigur

The character to be used as a separator between the components of an entry name, for example <QueueManager><Separator><Queue>.

This is specified as a string but it should contain a single character, if it contains more than one only the first character is used.

The same separator character should be used every time a registry is opened, it should not be changed once a registry is in use and contains entries.

If this value is not specified it defaults to "+".

regPIN The PIN required to open the registry. If this is *null*, the PIN is taken from the **regParams** parameter.

minCertServer The TCP address and port number of a Mini-Certificate server

miniCertPIN The *Certificate Request Number* pre-allocated by the Mini-Certificate administrator to allow the registry to obtain its credentials

renamePrefix A prefix used to rename the existing credentials, if there are any

Return Values

none

Exceptions

MQeException Is thrown if the class has not been activated, if it is not a Private Registry, if the rename fails, or if there is an error obtaining the credentials (e.g. contacting the Issuing Server).

Exception Is thrown for other errors

Example

```
try
{
    MQePrivateRegistryConfigure regConfig;
    MQeFields parms = new MQeFields();
    parms.putUnicode(MQeRegistry.DirName, "Registry_Dir");
    ...
    regConfig = new MQePrivateRegistryConfigure("Reg", parms, null);
    if ( regConfig.isPrivate() )
    {
        String renamePref = Long.toString(new Date().getTime()) + "_";
        regConfig.getCredentials( parms,
                                  "MYPIN 123",
                                  "certServer.hursley.ibm.com:8081",
                                  "12345678",
                                  renamePref );
    }
}
catch (Exception e)
{ ... }
```

MQePrivateRegistryConfigure isPrivate

Syntax

```
public boolean isPrivate( ) throws MQeException
```

Description

This method checks whether the registry that has been opened is a private registry.

Parameters

none

Return Values

true	If it is a private registry
-------------	-----------------------------

false	If it is not a private registry
--------------	---------------------------------

Exceptions

MQeException	Is thrown if the class has not been activated
---------------------	---

Example

```
try
{
    MQePrivateRegistryConfigure regConfig;
    MQeFields parms = new MQeFields();
    parms.putUnicode(MQeRegistry.DirName, "Registry_Dir");
    ...
    regConfig = new MQePrivateRegistryConfigure("Reg", parms, null);
    if ( regConfig.isPrivate() )
    {
        ...
    }
    catch (Exception e)
    { ... }
```

MQePublicRegistry

MQePublicRegistry

This class is used to create a MQePublicRegistry object.

Package com.ibm.mqe.registry

This class is a descendant of **MQeRegistry**

Constructor summary

Constructor	Purpose
MQePublicRegistry	Constructs an MQePublicRegistry object

Method summary

Method	Purpose
activate	Opens and activates the MQePublicRegistry instance.
deleteCertificate	Deletes the certificate owner's Mini-Certificate
getCertificate	Returns the certificate owner's Mini-Certificate
putCertificate	Adds the certificate owner's Mini-Certificate to the public registry
requestCertificate	Requests a Mini-Certificate from the public registry of another MQeNode
shareCertificate	Replicates the certificate owner's Mini-Certificate to a public registry on another MQeNode

MQePublicRegistry

Syntax

```
public MQePublicRegistry( )
```

Description

Constructs an MQePublicRegistry object

Parameters

none

Return values

none

Exceptions

none

Related functions

- **MQePrivateRegistry**

MQePublicRegistry activate

Syntax

```
Public void activate (String name,  
                      String dirName) throws Exception
```

Description

If a public registry with this entity name exists, **activate** opens the existing public registry, if not it creates a new public registry with name **name**.

Parameters

name	Public registry name, normally MQeNode_PublicRegistry
dirName	Path to public registry

Return Values

none

Exceptions

MQeException	Except_Public_ActivateFailed, "exception reason"
---------------------	--

Example

```
class MySampleClass extends MQe
{
    try
    {
        /* setup Public Registry activate parameters */
        String name      = "MQeNode_PublicRegistry";
        String dirName   = ".//"
        /* instantiate and activate Public Registry */
        MQePublicRegistry pubreg = new MQePublicRegistry( );
        pubreg.activate( name, dirName );
    }
    catch ( Exception e )
    {
        ...
    }
}
```

Related functions**MQePrivateRegistry****MQePublicRegistry deleteCertificate****Syntax**

```
Public void deleteCertificate( String certificateOwner )
                           throws MQeException
```

Description

Deletes the certificate owner's Mini-Certificate.

Parameters**certificateOwner**

Mini-Certificate owner's name

Return Values

none

Exceptions

MQeException	Except_Reg_DoesNotExist, "Entry does not exist" Except_Reg_DeleteFailed, "Error deleting entry"
---------------------	--

Related functions

- **getCertificate**
- **putCertificate**

MQePublicRegistry

MQePublicRegistry getCertificate

Syntax

```
Public MQeFields getCertificate( String certificateOwner )
                                throws MQeException
```

Description

Returns the certificate owner's Mini-Certificate.

Parameters

certificateOwner

Authenticatable entity's (Mini-Certificate owner's) name

Return Values

Mini-Certificate

Exceptions

MQeException

Except_Reg_ReadFailed, "Error reading entry"

Related functions

- deleteCertificate
- putCertificate

MQePublicRegistry putCertificate

Syntax

```
Public void putCertificate( String certificateOwner,
                           MQeFields certificate ) throws MQeException
```

Description

Adds the certificate owner's Mini-Certificate to the public registry

Parameters

certificateOwner

Authenticatable entity's (Mini-Certificate owner's) name

certificate

Owner's Mini-Certificate

Return Values

none

Exceptions

MQeException

Except_Reg_AlreadyExists, "Entry already exists"

Except_Reg_AddFailed, "Error adding entry"

Related functions

- getCertificate
- deleteCertificate

MQePublicRegistry requestCertificate

Syntax

```
Public MQeFields requestCertificate( String certificateOwner,
                                     String mqeNodeAddrPort)
                                         throws MQeException
```

Description

Requests a Mini-Certificate from the public registry of another MQeNode and, if returned, saves it in this publicrRegistry.

Parameters**certificateOwner**

Mini-Certificate owner's name

mqeNodeAddrPort

TCP address and port of *home server* or alternative MQeNode

Return Values

Mini-Certificate

Exceptions**MQeException**

Except_Reg_DoesNotExist, "Entry does not exist"
Except_Reg_ReadFailed, "Error reading entry"
Except_Reg_AddFailed, "Error adding entry"

Example

```
class MySampleClass extends MQe
{
    try
    {
        /* setup RequestCertificate parameters */
        String homeServerAddrPort = "homeServer.hursley.ibm.com:8081";
        entityName = "Bruce";
        /* instantiate and activate Public Registry */
        MQePublicRegistry pubreg = new MQePublicRegistry( );
        pubreg.activate("MQeNode_PublicRegistry", ".\\\" );
        /* request Bruce's MiniCert from Public Reg on another MQeNode */
        MQeFields minicertf = pubreg.getCertificate( entityName,
                                                    homeServerAddrPort);
        pubreg.close();
    }
    catch ( Exception e )
    {
        ...
    }
}
```

Related functions

`shareCertificate`

MQePublicRegistry shareCertificate**Syntax**

```
Public void shareCertificate( String certificateOwner,
                            MQeFields certificate,
                            String mqeNodeAddrPort) throws MQeException
```

Description

Replicates the certificate owner's Mini-Certificate to a public registry on another MQeNode.

Parameters**certificateOwner**

Mini-Certificate owner's name

certificate

Mini-Certificate

MQePublicRegistry

mqeNodeAddrPort

TCP address and port of *home server* or alternative MQeNode

Return Values

none

Exceptions

MQeException

Except_Reg_DoesNotExist, "Entry does not exist"

Except_Reg_ReadFailed, "Error reading entry"

Except_Reg_AddFailed, "Error adding entry"

Example

```
{  
try  
{  
    /* instantiate & activate a Private Reg for Auth Entity Bruce */  
    entityName      = "Bruce";  
    caIPAddrPort   = "aname.hursley.ibm.com:8081";  
    MQePrivateRegistry preg  = new MQePrivateRegistry( );  
    preg.activate( entityName, ".\\MQeNode_PrivateRegistry",  
                  "12345678", "It_is_a_secret", "12345678", caIPAddrPort);  
    /* instantiate and activate Public Reg & save Bruce's MiniCert */  
    MQePublicRegistry pubreg = new MQePublicRegistry( );  
    pubreg.activate("MQeNode_PublicRegistry",  
                   ".\\MQeNode_PublicRegistry" );  
    pubreg.putCertificate( entityName,  
                          preg.getCertificate( entityName ) );  
    /* share Bruce's MiniCert with Public Reg on another MQeNode */  
    String homeServerAddrPort = "homeServer.hursley.ibm.com:8081";  
    pubreg.shareCertificate( entityName,  
                            preg.getCertificate( entityName ), homeServerAddrPort);  
    preg.close();  
    pubreg.close();  
}  
catch ( Exception e )  
{  
}
```

Related functions

requestCertificate

Chapter 6. Classes in com.ibm.mqe.server

This section contains detailed information about the following MQSeries Everyplace classes:

Table 15. Classes in package com.ibm.mqe.server

Class name	Purpose
**MQeMiniCertIssuanceInterface	Used to define the way in which instances of MQeMiniCertificateServerGUI manages new Mini-Certificate issuance

Note: Classes marked ** are available only in the high security version of MQSeries Everyplace Version 1.0.

MQeMiniCertIssuanceInterface

Note: This class is only available in the high security version of MQSeries Everyplace Version 1.0.

Implementations of this interface are used to define the way in which instances of MQeMiniCertificateServerGUI manage new Mini-Certificate issuance. The default implementation, **MQeMiniCertIssuanceManager** uses an **MQeMiniCertificateRegistry** as the repository for definitions of a valid set of authenticatable entities that can request Mini-Certificates. It is recognized that MQSeries Everyplace solutions may want to use different repositories for this data, for example other registry or database services.

Package com.ibm.mqe.server

Method summary

Method	Purpose
addAuthenticatableEntity	Add the name and one-time-use <i>certificate request PIN</i> for a valid MQSeries Everyplace solution authenticatable entity
addEntityRegisteredAddress	Add the registered address for a valid MQSeries Everyplace solution authenticatable entity
authoriseMiniCertRequest	Authorize a new Mini-Certificate request.
deleteAuthenticatableEntity	Delete the name and one-time-use <i>certificate request PIN</i> of a valid MQSeries Everyplace solution authenticatable entity
deleteEntityRegisteredAddress	Delete the registered address of a valid MQSeries Everyplace solution authenticatable entity
readAuthenticatableEntity	Read the name and one-time-use <i>certificate request PIN</i> of a valid MQSeries Everyplace solution authenticatable entity
readEntityRegisteredAddress	Read the registered address of a valid MQSeries Everyplace Solution authenticatable entity
setRegistry	Set the reference to the MQeRegistry repository instance
updateAuthenticatableEntity	Update the name and one-time-use <i>certificate request PIN</i> of a valid MQSeries Everyplace solution authenticatable entity
updateEntityRegisteredAddress	Update the registered address of a valid MQSeries Everyplace solution authenticatable entity.

MQeMiniCertIssuanceInterface addAuthenticatableEntity

Syntax

```
public int addAuthenticatableEntity (String entityName, String certReqPIN )
```

Description

Add the name and one-time-use *certificate request PIN* for a valid MQSeries Everyplace solution authenticatable entity

Parameters

entityName A String used to identify the authenticatable entity's name

MQeMiniCertIssuanceInterface

certReqPIN A String used to identify the authenticatable entity's one-time-use *certificate request PIN*

Return Values

An integer indicating success or failure

Exceptions

none

MQeMiniCertIssuanceInterface addEntityRegisteredAddress

Syntax

```
public int addEntityRegisteredAddress (String entityName,  
                                     MQeFields entityRegAddr )
```

Description

Add the registered address for a new authenticatable entity

Parameters

entityName A String used to identify the authenticatable entity's name

entityRegAddr

An MQeFields object containing the authenticatable entity's registered address

Return Values

An integer indicating success or failure

Exceptions

none

MQeMiniCertIssuanceInterface authoriseMiniCertRequest

Syntax

```
public int authoriseMiniCertRequest (String entityName, String certReqPIN )
```

Description

Authorize a new Mini-Certificate request

Parameters

entityName A String used to identify the authenticatable entity's name

certReqPIN A String used to identify the authenticatable entity's one-time-use *certificate request PIN*

Return Values

An integer indicating authorization success or failure

Exceptions

none

MQeMiniCertIssuanceInterface deleteAuthenticatableEntity

Syntax

```
public int deleteAuthenticatableEntity (String entityName)
```

Description

Delete the name and one-time-use *certificate request PIN* of a valid MQSeries Everyplace solution authenticatable entity.

Parameters

entityName A String used to identify the authenticatable entity's name

MQeMiniCertIssuanceInterface

Return Values

An integer indicating success or failure

Exceptions

none

MQeMiniCertIssuanceInterface deleteEntityRegisteredAddress

Syntax

```
public int deleteEntityRegisteredAddress (String entityName)
```

Description

Delete the registered address of a valid MQSeries Everyplace solution authenticatable entity.

Parameters

entityName A String used to identify the authenticatable entity's name

Return Values

An integer indicating success or failure

Exceptions

none

MQeMiniCertIssuanceInterface readAuthenticatableEntity

Syntax

```
public int authoriseMiniCertRequest (String entityName, String certReqPIN )
```

Description

Read the name and one-time-use *certificate request PIN* of a valid MQSeries Everyplace solution authenticatable entity

Parameters

entityName A String used to identify the authenticatable entity's name

byte< > A String used to identify the authenticatable entity's one-time-use *certificate request PIN*

Return Values

A byte array containing authenticatable entity's identity, or *null*

Exceptions

none

MQeMiniCertIssuanceInterface readEntity RegisteredAddress

Syntax

```
public MQeFields readEntityRegisteredAddress (String entityName)
```

Description

Read the registered address of a valid MQSeries Everyplace solution authenticatable entity.

Parameters

entityName A String used to identify the authenticatable entity's name

Return Values

An **MQeFields** object containing the authenticatable entity's registered address or *null*

Exceptions
none

MQeMiniCertIssuanceInterface SetRegistry

Syntax

```
public void setRegistry (MQeRegistry registry)
```

Description

Set the reference to a MQeRegistry repository instance

Parameters

registry MQeRegistry instance

Return Values

none

Exceptions

none

MQeMiniCertIssuanceInterface updateAuthenticatableEntity

Syntax

```
public int updateAuthenticatableEntity (String entityName,  
                                         String certReqPIN )
```

Description

Update the name and one-time-use *certificate request PIN* of a valid MQSeries Everyplace solution authenticatable entity

Parameters

entityName A String used to identify the authenticatable entity's name

certReqPIN A String used to identify the authenticatable entity's one-time-use *certificate request PIN*

Return Values

An integer indicating success or failure

Exceptions

none

MQeMiniCertIssuanceInterface updateEntityRegisteredAddress

Syntax

```
public int updateEntityRegisteredAddress (String entityName,  
                                         MQeFields entityRegAddr )
```

Description

Update the registered address of a registered address for a new authenticatable entity authenticatable entity.

Parameters

entityName A String used to identify the authenticatable entity's name

entityRegAddr An MQeFields object containing the authenticatable entity's registered address

Return Values

An integer indicating success or failure

MQeMiniCertIssuanceInterface

Exceptions
none

Chapter 7. Classes in com.ibm.mqe.mqemqmmessage

This section contains detailed information about the following MQSeries Everyplace classes:

Table 16. Classes in package com.ibm.mqe.mqemqmmessage

Class name	Purpose
MQeMQMsgObject	Used to represent an MQSeries style message object within MQSeries Everyplace

MQeMQMsgObject class

This section describes the Java class used to represent an MQSeries style message object within MQSeries Everyplace. It can be used to create and read MQSeries style message objects.

The class has `getxxx()` and `setxxx()` methods for all the MQSeries message header fields. For efficiency however, only fields that have been set to a non-default value are actually contained in the message object .

Package com.ibm.mqe.mqemqmessage

This class is a descendant of `MQeMsgObject`

Constructor summary

Constructor	Purpose
<code>MQeMQMsgObject</code>	Creates a new <code>MQeMQMsgObject</code>

Method summary

Method	Purpose
<code>dumpAllToString</code>	Dumps all the field values from the message to a string
<code>dumpToString</code>	Dumps the field values in the message object to a string
<code>equals</code>	Compares to byte arrays for equality
<code>getAccountingToken</code>	Gets the value of the Accounting Token from the message header
<code>getApplicationIdData</code>	Gets the Application Id Data from the message header
<code>getApplicationOriginData</code>	GetApplicationOriginData
<code>getBackoutCount</code>	Gets the Backout Count from the message header
<code>getCharacterSet</code>	Gets the coded Character Set Identifier from the message header
<code>getCorrelationId</code>	Gets the Correlation Id from the message header
<code>getdata</code>	Gets the message Data
<code>getEncoding</code>	Gets the Encoding value from the message header
<code>getExpiry</code>	Gets the Expiry value from the message header
<code>getFeedback</code>	Gets the Feedback value from the message header
<code>getFormat</code>	Gets the Format value from the message header
<code>getGroupId</code>	Gets the value of the Group Id from the message header
<code>getMessageFlags</code>	Gets the value of the Message Flags from the message header
<code>getMessageId</code>	Gets the Message Id from the message header
<code>getMessageSequenceNumber</code>	Gets the Message Sequence Number from the message header
<code>getMessageType</code>	Gets the Message Type from the message header
<code>getOffset</code>	Gets the value of the Offset from the message header

Method	Purpose
<code>getOriginalLength</code>	Gets the Original Length from the message header
<code>getPersistence</code>	Gets the Persistence value from the message header
<code>getPriority</code>	Gets the Priority from the message header
<code>getPutApplicationName</code>	Gets the Put Application Name from the message header
<code>getPutApplicationType</code>	Gets the Put Application Type from the message header
<code>getPutDateTime</code>	Gets the Put Date and Time from the message header
<code>getReplyToQueueManagerName</code>	Gets the ReplyTo Queue Manager Name from the message header
<code>getReplyToQueueName</code>	Gets the ReplayTo Queue Name from the message header
<code>getReport</code>	Gets the Report value from the message header
<code>getUserId</code>	Gets the User Id from the message header
<code>setAccountingToken</code>	Sets the value of the Accounting Token in the message header
<code>setApplicationIdData</code>	Sets the Application Id Data in the message header
<code>setApplicationOriginData</code>	Sets the Application Origin Data in the message header
<code>setBackoutCount</code>	Sets the Backout Count in the message header
<code>setCharacterSet</code>	Sets the coded Character Set Identifier in the message header
<code>setCorrelationId</code>	Sets the Correlation Id in the message header
<code>setdata</code>	Sets the message Data
<code>setEncoding</code>	Sets the Encoding value in the message header
<code>setExpiry</code>	Sets the Expiry value in the message header
<code>setFeedback</code>	Sets the Feedback value in the message header
<code>setFormat</code>	Sets the Format value in the message header
<code>setGroupId</code>	Sets the value of the Group Id in the message header
<code>setMessageFlags</code>	Sets the value of the Message Flags in the message header
<code>setMessageId</code>	Sets the Message Id in the message header
<code>setMessageSequenceNumber</code>	Sets the Message Sequence Number in the message header
<code>setMessageType</code>	Sets the Message Type in the message header
<code>setOffset</code>	Sets the value of the Offset in the message header
<code>setOriginalLength</code>	Sets the Original Length in the message header
<code>setPersistence</code>	Sets the Persistence value in the message header
<code>setPriority</code>	Sets the Priority in the message header
<code>setPutApplicationName</code>	Sets the Put Application Name in the message header
<code>setPutApplicationType</code>	Sets the Put Application Type in the message header
<code>setPutDateTime</code>	Sets the Put Date and Time in the message header
<code>setReplyToQueueManagerName</code>	Sets the ReplyTo Queue Manager Name in the message header
<code>setReplyToQueueName</code>	Sets the ReplayTo Queue Name in the message header

MQeMQMsgObject

Method	Purpose
setReport	Sets the Report value in the message header
setUserId	Sets the User Id in the message header

MQeMQMsgObject

Syntax

```
public MQeMQMsgObject( ) throws Exception
```

Description

This creates a new MQeMQMsgObject

Parameters

none

Return values

none

Exceptions

java.lang.Exception

Propagated from the super-class
constructor, MQeMsgObject()

Example

```
...
MQeMQMsgObject MQMsg = new MQeMQMsgObject();
...
}
catch (Exception e)
{
    ...
}
```

MQeMQMsgObject dumpAllToString

Syntax

```
public String dumpAllToString()
```

Description

This method dumps all the header fields from the MQSeries style message with their corresponding field values to a string, together with the value of the data field. It is useful when debugging.

This method dumps all the header fields to a string. The `dumpToString()` method dumps only the fields that have been set to non-default values.

Parameters

none

Return values

A String containing the field names and values and the data value.

Exceptions

none

Example

```
if (msgObj instanceof MQeMQMsgObject)
{
    System.out.println(((MQeMQMsgObject)msgObj).dumpAllToString());
}
```

MQeMQMsgObject dumpToString

Syntax

```
public String dumpToString()
```

Description

This method dumps header fields from the &mq; style message with their corresponding field values to a string, together with the value of the data field. It is useful when debugging.

This method dumps only the fields that have been set to non-default values. The `dumpAllToString()` method dumps all the header fields to a string

Parameters

none

Return values

A String containing the field names and values and the data value.

Exceptions

none

Example

```
if (msgObj instanceof MQeMQMsgObject)
{
    System.out.println(((MQeMQMsgObject)msgObj).dumpToString());
```

MQeMQMsgObject equals

Syntax

```
public boolean equals(byte [] b1, byte [] b2)
```

Description

This compares two byte arrays for equality. They are considered equal if they are the same length and each byte in one array is equal to the corresponding byte in the other array.

Parameters

b1	The first byte array for comparison
b2	The second byte array for comparison

Return values

'true' if the byte arrays are equal in length and content, otherwise 'false'

Exceptions

none

Example

```
byte [] correId = ...
if ( mqMsgObj.equals(mqMsgObj.getCorrelationId(), correId) )
{
    ...
}
```

MQeMQMsgObject getAccountingToken

Syntax

```
public byte [] getAccountingToken() throws Exception
```

MQeMQMsgObject

Description

This method returns the value of the Accounting Token header field.

Parameters

none

Return values

A byte array containing the value of the Accounting Token.

Exceptions

java.lang.Exception if there is an error reading the value from the message object

Examples

```
try
{
    if (msgObj instanceof MQeMQMsgObject)
    {
        MQeMQMsgObject mqMsgObj = (MQeMQMsgObject)msgObj;
        byte [] accountToken = mqMsgObj.getAccountingToken();
        ...
    }
    catch (Exception e)
    {
        ...
    }
}
```

MQeMQMsgObject getApplicationIdData

Syntax

```
MQeMQMsgObject getApplicationOriginData
```

Description

This method returns the value of the Application Id Data header field.

Parameters

none

Return values

A string containing the value of the Application Id Data.

Exceptions

java.lang.Exception if there is an error reading the value from the message object

Example

```
try
{
    if (msgObj instanceof MQeMQMsgObject)
    {
        MQeMQMsgObject mqMsgObj = (MQeMQMsgObject)msgObj;
        String appIdData = mqMsgObj.getApplicationIdData();
        ...
    }
    catch (Exception e)
    {
        ...
    }
}
```

MQeMQMsgObject getApplicationOriginData

Syntax

```
public String getApplicationOriginData() throws Exception
```

Description

This method returns the value of the Application Origin Data header field.

Parameters

none

Return values

A string containing the value of the Application Origin Data

Exceptions

<code>java.lang.Exception</code>	if there is an error reading the value from the message object
----------------------------------	--

Example

```
try
{
    if (msgObj instanceof MQeMQMsgObject)
    {
        MQeMQMsgObject mqMsgObj = (MQeMQMsgObject)msgObj;
        String appOriginData = mqMsgObj.getApplicationOriginData();
        ...
    }
}
catch (Exception e)
{
    ...
}
```

MQeMQMsgObject getBackoutCount

Syntax

```
public int getBackoutCount() throws Exception
```

Description

This method returns the value of the Backout Count header field.

Parameters

none

Return values

An int containing the value of the Backout Count.

Exceptions

<code>java.lang.Exception</code>	if there is an error reading the value from the message object
----------------------------------	--

Example

```
try
{
    if (msgObj instanceof MQeMQMsgObject)
    {
        MQeMQMsgObject mqMsgObj = (MQeMQMsgObject)msgObj;
        int backoutCount = mqMsgObj.getBackoutCount();
        ...
    }
}
```

MQeMQMsgObject

```
        catch (Exception e)
        {
            ...
        }
```

MQeMQMsgObject getCharacterSet

Syntax

```
    public int getCharacterSet() throws Exception
```

Description

This method returns the value of the coded Character Set Identifier header field

Parameters

none

Return values

An int containing the value of the coded Character Set Identifier

Exceptions

java.lang.Exception	if there is an error reading the value from the message object
----------------------------	---

Example

```
try
{
    if (msgObj instanceof MQeMQMsgObject)
    {
        MQeMQMsgObject mqMsgObj = (MQeMQMsgObject)msgObj;
        int charSet = mqMsgObj.getCharacterSet();

        ...
    }
}
catch (Exception e)
{
    ...
}
```

MQeMQMsgObject getData

Syntax

```
    public byte [] getData() throws Exception
```

Description

This method returns the message data. The application must know how to interpret the data.

Parameters

none

Return values

A byte array containing the message data

Exceptions

java.lang.Exception	if there is an error reading the value from the message object
----------------------------	---

Example

```
try
{
    if (msgObj instanceof MQeMQMsgObject)
    {
```

```
MQeMQMsgObject mqMsgObj = (MQeMQMsgObject)msgObj;
byte [] msgData = mqMsgObj.getData();
...
}
}
catch (Exception e)
{
...
}
```

MQeMQMsgObject getCorrelationId

Syntax

```
public byte [] getCorrelationId() throws Exception
```

Description

This method returns the value of the Correlation Id header field.

Parameters

none

Return values

A byte array containing the value of the Correlation Id.

Exceptions

java.lang.Exception	if there is an error reading the value from the message object
----------------------------	---

Example

```
try
{
    if (msgObj instanceof MQeMQMsgObject)
    {
        MQeMQMsgObject mqMsgObj = (MQeMQMsgObject)msgObj;
        byte [[ correlId = mqMsgObj.getCorrelationId();
        ...
    }
}
catch (Exception e)
{
    ...
}
```

MQeMQMsgObject getEncoding

Syntax

```
MQeMQMsgObject getEncoding
```

Description

This method returns the value of the Encoding header field

Parameters

none

Return values

An int containing the Encoding value

Exceptions

java.lang.Exception	if there is an error reading the value from the message object
----------------------------	---

Example

MQeMQMsgObject

```
try
{
    if (msgObj instanceof MQeMQMsgObject)
    {
        MQeMQMsgObject mqMsgObj = (MQeMQMsgObject)msgObj;
        int encode = mqMsgObj.getEncoding();
        ...
    }
}
catch (Exception e)
{
    ...
}
```

MQeMQMsgObject getExpiry

Syntax

```
public int getExpiry() throws Exception
```

Description

This method returns the value of the Expiry header field. The value is in tenths of a second, as is used in MQSeries messages (it is not in milliseconds, which is used for the MQSeries Everyplace expiry time).

Parameters

none

Return values

An int containing the Expiry value.

Exceptions

`java.lang.Exception`

if there is an error reading the value from the message object

Example

```
try
{
    if (msgObj instanceof MQeMQMsgObject)
    {
        MQeMQMsgObject mqMsgObj = (MQeMQMsgObject)msgObj;
        int expiry = mqMsgObj.getExpiry();
        ...
    }
}
catch (Exception e)
{
    ...
}
```

MQeMQMsgObject getFeedback

Syntax

```
MQeMQMsgObject getFeedback
```

Description

This method returns the value of the Feedback header field.

Parameters

none

Return values

An int containing the Feedback value.

Exceptions

java.lang.Exception	if there is an error reading the value from the message object
----------------------------	--

Example

```

try
{
    if (msgObj instanceof MQeMQMsgObject)
    {
        MQeMQMsgObject mqMsgObj = (MQeMQMsgObject)msgObj;
        int feedback = mqMsgObj.getFeedback();
        ...
    }
}
catch (Exception e)
{
    ...
}

```

MQeMQMsgObject getFormat**Syntax**

```
public String getFormat() throws Exception
```

Description

This method returns the value of the Format header field.

Parameters

none

Return values

A String containing the Format value

Exceptions

java.lang.Exception	if there is an error reading the value from the message object
----------------------------	--

Example

```

try
{
    if (msgObj instanceof MQeMQMsgObject)
    {
        MQeMQMsgObject mqMsgObj = (MQeMQMsgObject)msgObj;
        String format = mqMsgObj.getFormat();
        ...
    }
}
catch (Exception e)
{
    ...
}

```

MQeMQMsgObject getGroupId**Syntax**

```
public byte [] getGroupId() throws Exception
```

Description

This method returns the value of the Group Id header field

Parameters

none

MQeMQMsgObject

Return values

A byte array containing the value of the Group Id.

Exceptions

java.lang.Exception if there is an error reading the value from the message object

Example

```

try
{
    if (msgObj instanceof MQeMQMsgObject)
    {
        MQeMQMsgObject mqMsgObj = (MQeMQMsgObject)msgObj;
        byte [] groupId = mqMsgObj.getGroupId();
        ...
    }
}
catch (Exception e)
{
    ...
}

```

MQeMQMsgObject getMessageFlags

Syntax

```
public int getMessageFlags() throws Exception
```

Description

This method returns the value of the Message Flags header field

Parameters

none

Return values

This method returns the value of the Message Flags header field

Exceptions

java.lang.Exception if there is an error reading the value from the message object

Example

```

try
{
    if (msgObj instanceof MQeMQMsgObject)
    {
        MQeMQMsgObject mqMsgObj = (MQeMQMsgObject)msgObj;
        int msgFlags = mqMsgObj.getMessageFlags();
        ...
    }
}
catch (Exception e)
{
    ...
}

```

MQeMQMsgObject getMessageId

Syntax

```
public byte [] getMessageId() throws Exception
```

Description

This method returns the value of the Message Id header field.

Parameters

none

Return values

A byte array containing the value of the Message Id.

Exceptions**java.lang.Exception**if there is an error reading the value from
the message object**Example**

```

try
{
    if (msgObj instanceof MQeMQMsgObject)
    {
        MQeMQMsgObject mqMsgObj = (MQeMQMsgObject)msgObj;
        byte [] msgId = mqMsgObj.getMessageId();
        ...
    }
}
catch (Exception e)
{
    ...
}
...
}

```

MQeMQMsgObject getMessageSequenceNumber**Syntax**

```
public int getMessageSequenceNumber() throws Exception
```

Description

This method returns the value of the Message Sequence Number header field.

Parameters

none

Return values

An int containing the value of the Message Sequence Number.

Exceptions**java.lang.Exception**if there is an error reading the value from
the message object**Example**

```

try
{
    if (msgObj instanceof MQeMQMsgObject)
    {
        MQeMQMsgObject mqMsgObj = (MQeMQMsgObject)msgObj;
        int msgSeqNo = mqMsgObj.getMessageSequenceNumber();
        ...
    }
}
catch (Exception e)
{
    ...
}
...
}

```

MQeMQMsgObject getMessageType**Syntax**

```
public int getMessageType() throws Exception
```

MQeMQMsgObject

Description

This method returns the value of the Message Type header field.

Parameters

none

Return values

An int containing the value of the Message Type

Exceptions

java.lang.Exception if there is an error reading the value from the message object

Example

```
try
{
    if (msgObj instanceof MQeMQMsgObject)
    {
        MQeMQMsgObject mqMsgObj = (MQeMQMsgObject)msgObj;
        int msgType = mqMsgObj.getMessageType();
        ...
    }
    catch (Exception e)
    {
        ...
    }
}
```

MQeMQMsgObject getOffset

Syntax

```
public int getOffset() throws Exception
```

Description

This method returns the value of the Offset header field.

Parameters

none

Return values

An int containing the Offset value

Exceptions

java.lang.Exception if there is an error reading the value from the message object

Example

```
try
{
    if (msgObj instanceof MQeMQMsgObject)
    {
        MQeMQMsgObject mqMsgObj = (MQeMQMsgObject)msgObj;
        int offset = mqMsgObj.getOffset();
        ...
    }
    catch (Exception e)
    {
        ...
    }
}
```

MQeMQMsgObject getOriginalLength

Syntax

```
public int getOriginalLength() throws Exception
```

Description

This method returns the value of the Original Length header field

Parameters

none

Return values

An int containing the value of the Original Length

Exceptions

java.lang.Exception	if there is an error reading the value from the message object
----------------------------	---

Example

```
try
{
    if (msgObj instanceof MQeMQMsgObject)
    {
        MQeMQMsgObject mqMsgObj = (MQeMQMsgObject)msgObj;
        int originalLength = mqMsgObj.getOriginalLength();
        ...
    }
}
catch (Exception e)
{
    ...
}
```

MQeMQMsgObject getPersistence

Syntax

```
public int getPersistence() throws Exception
```

Description

This method returns the value of the Persistence header field

Parameters

none

Return values

An int containing the Persistence value.

Exceptions

java.lang.Exception	if there is an error reading the value from the message object
----------------------------	---

Example

```
try
{
    if (msgObj instanceof MQeMQMsgObject)
    {
        MQeMQMsgObject mqMsgObj = (MQeMQMsgObject)msgObj;
        int persistence = mqMsgObj.getPersistence();
        ...
    }
}
```

MQeMQMsgObject

```
        catch (Exception e)
        {
            ...
        }
```

MQeMQMsgObject getPriority

Syntax

```
    public int getPriority() throws Exception
```

Description

This method returns the value of the Priority header field.

Parameters

none

Return values

An int containing the Priority value

Exceptions

java.lang.Exception	if there is an error reading the value from the message object
----------------------------	---

Example

```
try
{
    if (msgObj instanceof MQeMQMsgObject)
    {
        MQeMQMsgObject mqMsgObj = (MQeMQMsgObject)msgObj;
        int priority = mqMsgObj.getPriority();
        ...
    }
}
catch (Exception e)
{
    ...
}
```

MQeMQMsgObject getPutApplicationName

Syntax

```
    public String getPutApplicationName() throws Exception
```

Description

This method returns the value of the Put Application Name header field

Parameters

none

Return values

A String containing the value of the Put Application Name

Exceptions

java.lang.Exception	if there is an error reading the value from the message object
----------------------------	---

Example

```
try
{
    if (msgObj instanceof MQeMQMsgObject)
    {
        MQeMQMsgObject mqMsgObj = (MQeMQMsgObject)msgObj;
        String putAppName = mqMsgObj.getPutApplicationName();
```

```
    } ...
}
catch (Exception e)
{
...
}
```

MQeMQMsgObject getPutApplicationType

Syntax

```
public int getPutApplicationType() throws Exception
```

Description

This method returns the value of the Put Application Type header field.

Parameters

none

Return values

An int containing the value of the Put Application Type

Exceptions

java.lang.Exception	if there is an error reading the value from the message object
----------------------------	---

Example

```
try
{
    if (msgObj instanceof MQeMQMsgObject)
    {
        MQeMQMsgObject mqMsgObj = (MQeMQMsgObject)msgObj;
        int putApp1Type = mqMsgObj.getPutApplicationType();
        ...
    }
    catch (Exception e)
    {
        ...
    }
}
```

MQeMQMsgObject getPutDate Time

Syntax

```
public GregorianCalendar getPutDate Time() throws Exception
```

Description

This method returns the value of the Put Date Time header field. The value is returned as a Gregorian Calendar object, for consistency with the MQSeries Java Client.

Parameters

none

Return values

A Grogorian Calendar object containing the Put Date and Time value

Exceptions

java.lang.Exception	if there is an error reading the value from the message object
----------------------------	---

Example

MQeMQMsgObject

```
try
{
    if (msgObj instanceof MQeMQMsgObject)
    {
        MQeMQMsgObject mqMsgObj = (MQeMQMsgObject)msgObj;
        GregorianCalendar putDateTime = mqMsgObj.getPutDateTime();
        ...
    }
}
catch (Exception e)
{
    ...
}
```

MQeMQMsgObject getReplyToQueueManagerName

Syntax

```
MQeMQMsgObject getReplyToQueueManagerName
```

Description

This method returns the value of the Reply To Queue Manager Name header field.

Parameters

none

Return values

A String containing the value of the Reply To Queue Manager Name.

Exceptions

java.lang.Exception	if there is an error reading the value from the message object
----------------------------	--

Example

```
try
{
    if (msgObj instanceof MQeMQMsgObject)
    {
        MQeMQMsgObject mqMsgObj = (MQeMQMsgObject)msgObj;
        String replyToQueueMgrName = mqMsgObj.getReplyToQueueManagerName();
        ...
    }
}
catch (Exception e)
{
    ...
}
```

MQeMQMsgObject getReplyToQueueName

Syntax

```
public String getReplyToQueueName() throws Exception
```

Description

This method returns the value of the Reply To Queue Name header field.

Parameters

none

Return values

A String containing the value of the Reply To Queue Name.

Exceptions

MQeMQMsgObject

java.lang.Exception

if there is an error reading the value from the message object

Example

```

try
{
    if (msgObj instanceof MQeMQMsgObject)
    {
        MQeMQMsgObject mqMsgObj = (MQeMQMsgObject)msgObj;
        String replyToQueueName = mqMsgObj.getReplyToQueueName();
        ...
    }
}
catch (Exception e)
{
    ...
}

```

MQeMQMsgObject getReport

Syntax

```
public int getReport() throws Exception
```

Description

This method returns the value of the Report header field.

Parameters

none

Return values

An int containing the Report value.

Exceptions

java.lang.Exception

if there is an error reading the value from the message object

Example

```

try
{
    if (msgObj instanceof MQeMQMsgObject)
    {
        MQeMQMsgObject mqMsgObj = (MQeMQMsgObject)msgObj;
        int report = mqMsgObj.getReport();
        ...
    }
}
catch (Exception e)
{
    ...
}

```

MQeMQMsgObject getUserId

Syntax

```
public String getUserId() throws Exception
```

Description

This method returns the value of the User Id header field.

Parameters

none

Return values

A String containing the value of the User Id.

MQeMQMsgObject

Exceptions

java.lang.Exception	if there is an error reading the value from the message object
----------------------------	--

Example

```

try
{
    if (msgObj instanceof MQeMQMsgObject)
    {
        MQeMQMsgObject mqMsgObj = (MQeMQMsgObject)msgObj;
        String userId = mqMsgObj.getUserId();
        ...
    }
}
catch (Exception e)
{
    ...
}

```

MQeMQMsgObject setAccountingToken

Syntax

```
public void setAccountingToken(byte [] accountingToken) throws Exception
```

Description

This method sets the value of the Accounting Token header field in the MQSeries style message.

Parameters

accountingToken

a byte array containing the value to be set in the Accounting Token field

Return values

none

Exceptions

java.lang.Exception	if there is an error setting the value in the message object
----------------------------	--

Example

```

try
{
    MQeMQMsgObject mqeMsgObj = new MQeMQMsgObject();
    byte [] accountingToken = ...;
    mqeMsgObj.setAccountingToken(accountingToken);
    ...
}
catch (Exception e)
{
    ...
}

```

MQeMQMsgObject setApplicationIdData

Syntax

```
public void setApplicationIdData(String applicationIdData) throws Exception
```

Description

This method sets the value of the Application Id Data header field in the MQSeries style message.

Parameters**applicationIdData**

a String containing the value to be set in the Application Id Data field.

Return values

none

Exceptions**java.lang.Exception**

if there is an error setting the value in the message object

Example

```
try
{
    MQeMQMsgObject mqeMsgObj = new MQeMQMsgObject();
    String applIdData = ...;
    mqeMsgObj.setApplicationIdData(applIdData);
    ...
}
catch (Exception e)
{
    ...
}
```

MQeMQMsgObject setApplicationOriginData**Syntax**

```
public void setApplicationOriginData(String applicationOriginData) throws Exception
```

Description

This method sets the value of the Application Origin Data header field in the MQSeries style message

Parameters**applicationOriginData**

a String containing the value to be set in the Application Origin Data field.

Return values

none

Exceptions**java.lang.Exception**

if there is an error setting the value in the message object

Example

```
try
{
    MQeMQMsgObject mqeMsgObj = new MQeMQMsgObject();
    String applOriginData = ...;
    mqeMsgObj.setApplicationOriginData(applOriginData);
    ...
}
catch (Exception e)
{
    ...
}
```

MQeMQMsgObject

MQeMQMsgObject setBackoutCount

Syntax

```
public void setBackoutCount(int backoutCount) throws Exception
```

Description

This method sets the value of the Backout Count header field in the MQSeries style message.

Parameters

backoutCount an int containing the value to be set in the Backout Count field

Return values

none

Exceptions

java.lang.Exception if there is an error setting the value in the message object

Example

```
try
{
    MQeMQMsgObject mqeMsgObj = new MQeMQMsgObject();
    int backoutCount = ...;
    mqeMsgObj.setBackoutCount(backoutCount);
    ...
}
catch (Exception e)
{
    ...
}
```

MQeMQMsgObject setCharacterSet

Syntax

```
public void setCharacterSet(int characterSet) throws Exception
```

Description

This method sets the value of the coded Character Set Identifier header field in the MQSeries style message

Parameters

characterSet an int containing the value to be set in the coded Character Set Identifier field

Return values

none

Exceptions

java.lang.Exception if there is an error setting the value in the message object

Example

```
try
{
    MQeMQMsgObject mqeMsgObj = new MQeMQMsgObject();
    int characterSet = ...;
    mqeMsgObj.setCharacterSet(characterSet);
    ...
}
```

```
    catch (Exception e)
    {
        ...
    }
```

MQeMQMsgObject setCorrelationId

Syntax

```
    public void setCorrelationId(byte [] correlationId) throws Exception
```

Description

This method sets the value of the Correlation Id header field in the MQSeries style message. It also sets the Correlation Id for use within the MQSeries Everyplace system itself

Parameters

correlationId a byte array containing the value to be set in the Correlation Id field.

Return values

none

Exceptions

java.lang.Exception	if there is an error setting the value in the message object
----------------------------	--

Example

```
try
{
    MQeMQMsgObject mqeMsgObj = new MQeMQMsgObject();
    byte [] correlationId = ...;
    mqeMsgObj.setCorrelationId(correlationId);
    ...
}
catch (Exception e)
{
    ...
}
```

MQeMQMsgObject setData

Syntax

```
    public void setData(byte [] data) throws Exception
```

Description

This method sets the message data in the MQSeries style message.

Parameters

data if there is an error setting the value in the message object

Return values

none

Exceptions

java.lang.Exception	if there is an error setting the value in the message object
----------------------------	--

Example

```
try
{
    MQeMQMsgObject mqeMsgObj = new MQeMQMsgObject();
    byte [] data = ...;
```

MQeMQMsgObject

```
    mqeMsgObj.setData(data);
    ...
}
```

```
catch (Exception e)
{
    ...
}
```

MQeMQMsgObject setEncoding

Syntax

```
public void setEncoding(int encoding) throws Exception
```

Description

This method sets the value of the Encoding header field in the MQSeries style message

Parameters

encoding an int containing the value to be set in the Encoding field

Return values

none

Exceptions

java.lang.Exception if there is an error setting the value in the message object

Example

```
try
{
    MQeMQMsgObject mqeMsgObj = new MQeMQMsgObject();
    int encoding = ...;
    mqeMsgObj.setEncoding(encoding);
    ...
}
catch (Exception e)
{
    ...
}
```

MQeMQMsgObject setExpiry

Syntax

```
public void setExpiry(int expiry) throws Exception
```

Description

This method sets the value of the Expiry header field in the MQSeries style message. It also sets the expiry time of the message for use within the MQSeries Everyplace system itself.

Parameters

expiry an int containing the value to be set in the expiry field. The value should be in tenths of a second, as is used in MQSeries messages (not in milliseconds, which is used for MQSeries Everyplace expiry time)..

Return values

none

Exceptions

MQeMQMsgObject

java.lang.Exception

if there is an error setting the value in the message object

Example

```
try
{
    MQeMQMsgObject mqeMsgObj = new MQeMQMsgObject();
    int expiry = ...;
    mqeMsgObj.setExpiry(expiry);
    ...
} catch (Exception e)
{
    ...
}
```

MQeMQMsgObject setFeedback

Syntax

```
public void setFeedback(int feedback) throws Exception
```

Description

This method sets the value of the Feedback header field in the MQSeries style message.

Parameters

feedback an int containing the value to be set in the Feedback field.

Return values

none

Exceptions

java.lang.Exception

if there is an error setting the value in the message object

Example

```
try
{
    MQeMQMsgObject mqeMsgObj = new MQeMQMsgObject();
    int feedback = ...;
    mqeMsgObj.setFeedback(feedback);
    ...
} catch (Exception e)
{
    ...
}
```

MQeMQMsgObject setFormat

Syntax

```
public void setFormat(String format) throws Exception
```

Description

This method sets the value of the Format header field in the MQSeries style message

Parameters

format a String containing the value to be set in the Format field.

Return values

none

MQeMQMsgObject

Exceptions

java.lang.Exception	if there is an error setting the value in the message object
----------------------------	--

Example

```
try
{
    MQeMQMsgObject mqeMsgObj = new MQeMQMsgObject();
    String format = ...;
    mqeMsgObj.setFormat(format);
    ...
}
catch (Exception e)
{
    ...
}
```

MQeMQMsgObject setGroupId

Syntax

```
public void setGroupId(byte [] groupId) throws Exception
```

Description

This method sets the value of the Group Id header field in the MQSeries style message.

Parameters

groupId	a byte array containing the value to be set in the Group Id field.
----------------	--

Return values

none

Exceptions

java.lang.Exception	if there is an error setting the value in the message object
----------------------------	--

Example

```
try
{
    MQeMQMsgObject mqeMsgObj = new MQeMQMsgObject();
    byte [] groupId = ...;
    mqeMsgObj.setGroupId(groupId);
    ...
}
catch (Exception e)
{
    ...
}
```

MQeMQMsgObject setMessageFlags

Syntax

```
public void setMessageFlags(int messageFlags) throws Exception
```

Description

This method sets the value of the Message Flags header field in the MQSeries style message

Parameters

format	a String containing the value to be set in the Format field.
---------------	--

Return values

none

Exceptions**java.lang.Exception**

if there is an error setting the value in the message object

Example

```

try
{
    MQeMQMsgObject mqeMsgObj = new MQeMQMsgObject();
    int messageFlags = ...;
    mqeMsgObj.setMessageFlags(messageFlags);
    ...
}
catch (Exception e)
{
    ...
}

```

MQeMQMsgObject setMessageId**Syntax**

```
public void setMessageId(byte [] messageId) throws Exception
```

Description

This method sets the value of the Message Id header field in the MQSeries style message

Parameters

messageId	a byte array containing the value to be set in the Message Id field.
------------------	--

Return values

none

Exceptions**java.lang.Exception**

if there is an error setting the value in the message object

Example

```

try
{
    MQeMQMsgObject mqeMsgObj = new MQeMQMsgObject();
    byte [] messageId = ...;
    mqeMsgObj.setMessageId(messageId);
    ...
}
catch (Exception e)
{
    ...
}

```

MQeMQMsgObject setMessageSequenceNumber**Syntax**

```
public void setMessageSequenceNumber(int seqNo) throws Exception
```

Description

This method sets the value of the Message Sequence Number header field in the MQSeries style message

MQeMQMsgObject

Parameters

seqNo an int containing the value to be set in the Message Sequence Number field.

Return values

none

Exceptions

java.lang.Exception if there is an error setting the value in the message object

Example

```
try
{
    MQeMQMsgObject mqeMsgObj = new MQeMQMsgObject();
    int seqNo = ...;
    mqeMsgObj.setMessageSequenceNumber(seqNo);
    ...
}
catch (Exception e)
{
    ...
}
```

MQeMQMsgObject setMessageType

Syntax

```
public void setMessageType(int messageType) throws Exception
```

Description

This method sets the value of the Message Type header field in the MQSeries style message. It also sets the message style for use within the MQSeries Everyplace system itself.

Parameters

messageType an int containing the value to be set in the Message Type field.

Return values

none

Exceptions

java.lang.Exception if there is an error setting the value in the message object

Example

```
try
{
    MQeMQMsgObject mqeMsgObj = new MQeMQMsgObject();
    int messageType = ...;
    mqeMsgObj.setMessageType(messageType);
    ...
}
catch (Exception e)
{
    ...
}
```

MQeMQMsgObject setOffset

Syntax

```
public void setOffset(int offset) throws Exception
```

Description

This method sets the value of the Offset header field in the MQSeries style message

Parameters

offset an int containing the value to be set in the Offset field

Return values

none

Exceptions

java.lang.Exception if there is an error setting the value in the message object

Example

```
try
{
    MQeMQMsgObject mqeMsgObj = new MQeMQMsgObject();
    int offset = ...;
    mqeMsgObj.setOffset(offset);
    ...
}
catch (Exception e)
{
    ...
}
```

MQeMQMsgObject setOriginalLength

Syntax

```
public void setOriginalLength(int len) throws Exception
```

Description

This method sets the value of the Original Length header field in the MQSeries style message.

Parameters

len an int containing the value to be set in the Original Length field.

Return values

none

Exceptions

java.lang.Exception if there is an error setting the value in the message object

Example

```
try
{
    MQeMQMsgObject mqeMsgObj = new MQeMQMsgObject();
    int len = ...;
    mqeMsgObj.setOriginalLength(len);
    ...
}
```

MQeMQMsgObject

```
    catch (Exception e)
    {
        ...
    }
```

MQeMQMsgObject setPersistence

Syntax

```
public void setPersistence(int persistence) throws Exception
```

Description

This method sets the value of the Persistence header field in the MQSeries style message.

Parameters

persistence an int containing the value to be set in the Persistence field

Return values

none

Exceptions

java.lang.Exception if there is an error setting the value in the message object

Example

```
try
{
    MQeMQMsgObject mqeMsgObj = new MQeMQMsgObject();
    int persistence = ...;
    mqeMsgObj.setPersistence(persistence);
    ...
}
catch (Exception e)
{
    ...
}
```

MQeMQMsgObject setPriority

Syntax

```
public void setPriority(int priority) throws Exception
```

Description

This method sets the value of the Priority header field in the MQSeries style message. It also sets the priority of the message for use within the MQSeries Everyplace system itself.

Parameters

priority an int containing the value to be set in the Priority field. The value should be between 0 and 9 (inclusive).

Return values

none

Exceptions

java.lang.Exception if there is an error setting the value in the message object

Example

```
try
{
    MQeMQMsgObject mqeMsgObj = new MQeMQMsgObject();
    int priority = ...;
    mqeMsgObj.setPriority(priority);
    ...
}
catch (Exception e)
{
    ...
}
```

MQeMQMsgObject setPutApplicationName

Syntax

```
public void setPutApplicationName(String putApplicationName) throws Exception
```

Description

This method sets the value of the Put Application Name header field in the MQSeries style message.

Parameters

putApplicationName

a String containing the value to be set in the Put Application Name field.

Return values

none

Exceptions

java.lang.Exception

if there is an error setting the value in the message object

Example

```
try
{
    MQeMQMsgObject mqeMsgObj = new MQeMQMsgObject();
    String putAppName = ...;
    mqeMsgObj.setPutApplicationName(putAppName);
    ...
}
catch (Exception e)
{
    ...
}
```

MQeMQMsgObject setPutApplicationType

Syntax

```
public void setPutApplicationType(int putApplicationType) throws Exception
```

Description

This method sets the value of the Put Application Type header field in the MQSeries style message.

Parameters

putApplicationType

an int containing the value to be set in the Put Application Type field

Return values

none

MQeMQMsgObject

Exceptions

java.lang.Exception	if there is an error setting the value in the message object
----------------------------	--

Example

```
try
{
    MQeMQMsgObject mqeMsgObj = new MQeMQMsgObject();
    int putApplType = ...;
    mqeMsgObj.setPutApplicationType(putApplType);
    ...
}
catch (Exception e)
{
    ...
}
```

MQeMQMsgObject setPutDateTime

Syntax

```
public void setPutDateTime(GregorianCalendar calendar) throws Exception
```

Description

This method sets the value of the Put Date Time header field in the MQSeries style message. A GregorianCalendar object is used to specify the date and time, for consistency with the MQSeries Java Client.

Parameters

calendar	a GregorianCalendar object containing the value to be set in the Put Date Time field.
-----------------	---

Return values

none

Exceptions

java.lang.Exception	if there is an error setting the value in the message object
----------------------------	--

Example

```
try
{
    MQeMQMsgObject mqeMsgObj = new MQeMQMsgObject();
    GregorianCalendar calendar = ...;
    mqeMsgObj.setPutDateTime(calendar);
    ...
}
catch (Exception e)
{
    ...
}
```

MQeMQMsgObject setReplyToQueueManagerName

Syntax

```
public void setReplyToQueueManagerName(String replyToQName) throws Exception
```

Description

This method sets the value of the Reply To Queue Manager Name header field in the MQSeries style message.

Parameters

replyToQMName

a String containing the value to be set in the Reply To Queue Manager Name field.

Return values

none

Exceptions**java.lang.Exception**

if there is an error setting the value in the message object

Example

```
try
{
    MQeMQMsgObject mqeMsgObj = new MQeMQMsgObject();
    String replyToQMName = ...;
    mqeMsgObj.setReplyToQueueManagerName(replyToQMName);
    ...
}
catch (Exception e)
{
    ...
}
```

MQeMQMsgObject setReplyToQueueName**Syntax**

```
public void setReplyToQueueName(String replyToQueueName) throws Exception
```

Description

This method sets the value of the Reply To Queue Name header field in the MQSeries style message.

Parameters**replyToQueueName**

a String containing the value to be set in the Reply To Queue Name field.

Return values

none

Exceptions**java.lang.Exception**

if there is an error setting the value in the message object

Example

```
try
{
    MQeMQMsgObject mqeMsgObj = new MQeMQMsgObject();
    String replyToQueueName = ...;
    mqeMsgObj.setReplyToQueueName(replyToQueueName);
    ...
}
catch (Exception e)
{
    ...
}
```

MQeMQMsgObject setReport**Syntax**

```
public void setReport(int report) throws Exception
```

MQeMQMsgObject

Description

This method sets the value of the Report header field in the MQSeries style message.

Parameters

report an int containing the value to be set in the Report field

Return values

none

Exceptions

java.lang.Exception if there is an error setting the value in the message object

Example

```
try
{
    MQeMQMsgObject mqeMsgObj = new MQeMQMsgObject();
    int report = ...;
    mqeMsgObj.setReport(report);
    ...
}
catch (Exception e)
{
    ...
}
```

MQeMQMsgObject setUserId

Syntax

```
public void setUserId(String userId) throws Exception
```

Description

This method sets the value of the User Id header field in the MQSeries style message.

Parameters

userId a String containing the value to be set in the User Id field

Return values

none

Exceptions

java.lang.Exception if there is an error setting the value in the message object

Example

```
try
{
    MQeMQMsgObject mqeMsgObj = new MQeMQMsgObject();
    String userId = ...;
    mqeMsgObj.setUserId(userId);
    ...
}
catch (Exception e)
{
    ...
}
```

Chapter 8. Classes in com.ibm.mqe.mqbridge

This section contains detailed information about the following MQSeries Everyplace classes and interfaces:

Table 17. Classes in package com.ibm.mqe.mqbridge

Class or Interface name	Purpose
MQeCharacteristicLabels	Groups together all the <i>labels</i> used in any MQeFields object used in the bridge code
MQeClientConnectionAdminMsg	Used to encapsulate an administration command that acts on the MQeClientConnection object.
MQeListenerAdminMsg	Used to encapsulate an administration command that acts on the MQeListener object.
MQeMQBridgeAdminMsg	Used to encapsulate an administration command that acts on the MQeBridge object.
MQeMQBridgeQueue	This queue is used as the interface to the MQS bridge
MQeMQBridgeQueueAdminMsg	Used to administer an MQBridge queue
MQeMQBridges	Loads and maintains all bridge objects associated with a given MQe server"
MQeMQBridgesAdminMsg	Used to encapsulate an administration command that acts on the MQeBridges object.
MQeMQQMgrProxyAdminMsg	Used to encapsulate an administration command that acts on the MQeQMgrProxy object.
MQeRunState	Holds the <i>run state</i> of an administered object
MQeTransformerInterface	All classes that can transform MQMessages to MQeMsgObjects (and vice versa) must conform to this interface

Licence warning

The use of any of the classes in com.ibm.mqe.mqbridge requires a **gateway (server)** licence.

MQeCharacteristicLabels

MQeCharacteristicLabels

This class groups together all the *labels* used in any **MQeFields** object used in the bridge code.

These labels are used by administration messages, and by the administered object runtime characteristics, and persistent registry entry objects.

Package com.ibm.mqe.mqbridge

This class extends **Object**

Constants and variables

MQeCharacteristicLabels provides the following constants and variables :

MQE_FIELD_LABEL_ADMINISTERED_OBJECT_CLASS

Used by all administered object registry entries. Indicates the class that should be loaded when you want to instantiate the administered object.

```
public static final String MQE_FIELD_LABEL_ADMINISTERED_OBJECT_CLASS
```

MQE_FIELD_LABEL_AFFECT_CHILDREN

Used to control whether a start or delete action affects child objects when applied to an administered object.

```
public static final String MQE_FIELD_LABEL_AFFECT_CHILDREN
```

MQE_FIELD_LABEL_BRIDGE_NAME

```
public static final String MQE_FIELD_LABEL_BRIDGE_NAME
```

MQE_FIELD_LABEL_CCSID

The label for the field holding the CCSID used on the underlying MQS java client channel.

```
public static final String MQE_FIELD_LABEL_CCSID
```

MQE_FIELD_LABEL_CHILD

The label of the MQSeries Everyplace field that holds the name of the child of an administered object

```
public static final String MQE_FIELD_LABEL_CHILD
```

MQE_FIELD_LABEL_CHILDREN

The label associated with the children of the MQSeries Everyplace field.

The value of the field holds a list of proxy object names

```
public static final String MQE_FIELD_LABEL_CHILDREN
```

MQE_FIELD_LABEL_CLIENT_CONNECTION_NAME

Label for the MQSeries Everyplace field that holds the name of the client connection that the administration message is being sent to.

```
public static final String MQE_FIELD_LABEL_CLIENT_CONNECTION_NAME
```

MQE_FIELD_LABEL_DEAD_LETTER_Q_NAME

Label for the field holding the name of the dead letter queue on the MQS system.

```
public static final String MQE_FIELD_LABEL_DEAD_LETTER_Q_NAME
```

MQE_FIELD_LABEL_DEFAULT_TRANSFORMER

Label holding the name of the MQSeries Everyplace field that holds the name of the default transformer class that is used to convert from MQSeries Everyplace to MQS and from MQS to MQSeries Everyplace message formats. This value is used if no transformer is specified on the target queue definition.

```
public static final String MQE_FIELD_LABEL_DEFAULT_TRANSFORMER
```

MQE_FIELD_LABEL_FLOWS_PER_COMMIT

Label indicating how many times through the listener flows the listener is allowed to go before the sync queue on the MQS system is cleaned up.

This is only relevant when the listener is using the MQS sync queue as its state store.

```
public static final String MQE_FIELD_LABEL_FLOWS_PER_COMMIT
```

MQE_FIELD_LABEL_HEARTBEAT_INTERVAL

The label holding the value of the time interval (in units of 1minute) that dictates the period of each "heartbeat" event coming from the **MQeHeart** class. This affects the accuracy of any timer mechanisms in the bridge, as these all use the heartbeat as a "tick" of their timer.

```
public static final String MQE_FIELD_LABEL_HEARTBEAT_INTERVAL
```

MQE_FIELD_LABEL_HOST_NAME

MQSeries Everyplace field label for the hostname field.

```
public static final String MQE_FIELD_LABEL_HOST_NAME
```

MQE_FIELD_LABEL_LISTENER_NAME

Label for the field holding the MQS transmission queue listener name (the name of the transmit queue on MQS).

```
public static final String MQE_FIELD_LABEL_LISTENER_NAME
```

MQE_FIELD_LABEL_LISTENER_STATE_STORE_ADAPTER

Label holding the name of the MQSeries Everyplace field that holds the name of the adapter class used by the listener to store its state.

```
public static final String MQE_FIELD_LABEL_LISTENER_STATE_STORE_ADAPTER
```

MQE_FIELD_LABEL_MAX_CONNECTION_IDLE_TIME

The label for the field holding the maximum time value that an MQS client connection is kept open if it is idle. Connections that are idle for more than this time are closed by the bridge.

```
public static final String MQE_FIELD_LABEL_MAX_CONNECTION_IDLE_TIME
```

MQE_FIELD_LABEL_MQ_BRIDGE_ADAPTER_CLASS

The label for the field holding the name of the bridge adapter class. The bridge adapter is a java class that allows messages sent to an MQS bridge queue to be moved to the MQS system.

```
public static final String MQE_FIELD_LABEL_MQ_BRIDGE_ADAPTER_CLASS
```

MQE_FIELD_LABEL_MQ_Q_MGR_PROXY_NAME

Label of the MQSeries Everyplace field holding the name of the MQS queue manager proxy object.

```
public static final String MQE_FIELD_LABEL_MQ_Q_MGR_PROXY_NAME
```

MQE_FIELD_LABEL_NAME

Label holding the name of the MQSeries Everyplace field that holds the name of the bridge, proxy, client connection, or listener.

```
public static final String MQE_FIELD_LABEL_NAME
```

MQE_FIELD_LABEL_PASSWORD

Label holding the password used with the userid when the bridge talks to MQS.

```
public static final String MQE_FIELD_LABEL_PASSWORD
```

MQE_FIELD_LABEL_PORT

Label for the MQSeries Everyplace field that holds the port number of the MQS channel listener

MQeCharacteristicLabels

```
public static final String MQE_FIELD_LABEL_PORT
```

MQE_FIELD_LABEL_RECEIVE_EXIT

Label for the field holding the receive exit used on the underlying MQS java client channel.

```
public static final String MQE_FIELD_LABEL_RECEIVE_EXIT
```

MQE_FIELD_LABEL_RUN_STATE

The label of the MQSeries Everyplace field that holds the snapshot of the current state of the administered object.

```
public static final String MQE_FIELD_LABEL_RUN_STATE
```

MQE_FIELD_LABEL_SECONDS_WAIT_FOR_MSG

Label for the field holding the seconds that the MQS transmission queue listener uses in the MQS java client GetMessage(wait) method. (For development use only).

```
public static final String MQE_FIELD_LABEL_SECONDS_WAIT_FOR_MSG
```

MQE_FIELD_LABEL_SECURITY_EXIT

Label for the field holding the security exit used on the underlying MQS java client channel.

```
public static final String MQE_FIELD_LABEL_SECURITY_EXIT
```

MQE_FIELD_LABEL_SEND_EXIT

Label for the field holding the send exit used on the underlying MQS java client channel.

```
public static final String MQE_FIELD_LABEL_SEND_EXIT
```

MQE_FIELD_LABEL_STARTUP_RULE_CLASS

Used by all the administered object registry entries. Indicates the class that should be used to decide whether or not the administered object is started up when it is loaded.

```
public static final String MQE_FIELD_LABEL_STARTUP_RULE_CLASS
```

MQE_FIELD_LABEL_SYNC_Q_NAME

MQSeries Everyplace field label for the SyncQName field. Used to keep track of the state of progress through the assured delivery flows.

```
public static final String MQE_FIELD_LABEL_SYNC_Q_NAME
```

MQE_FIELD_LABEL_SYNC_Q_PURGE_INTERVAL

The time interval between successive purges of the sync queue

```
public static final String MQE_FIELD_LABEL_SYNC_Q_PURGE_INTERVAL
```

MQE_FIELD_LABEL_SYNC_Q_PURGER_RULES_CLASS

MQSeries Everyplace field label for the SyncQPurgerRulesClass field

```
public static final String MQE_FIELD_LABEL_SYNC_Q_PURGER_RULES_CLASS
```

MQE_FIELD_LABEL_TRANSFORMER

Label indicating which transformer class should be used to convert the MQS message to an MQSeries Everyplace message before it is dispatched to the MQSeries Everyplace network.

```
public static final String MQE_FIELD_LABEL_TRANSFORMER
```

MQE_FIELD_LABEL_UNDELIVERED_MESSAGE_RULE_CLASS

Label for the field holding the java class name of the rule to use when the message cannot be delivered to its destination.

```
public static final String MQE_FIELD_LABEL_UNDELIVERED_MESSAGE_RULE_CLASS
```

MQE_FIELD_LABEL_USER_ID

Label for the userid assumed by the bridge when talking to MQS

MQeCharacteristicLabels

```
public static final String MQE_FIELD_LABEL_USER_ID  
version  
public static short version[]
```

MQeCharacteristicLabels

Syntax

```
public MQeCharacteristicLabels()
```

Description

Creates an MQeCharacteristicLabels object

Parameters

none

Return values

none

Exceptions

none

Example

MQeClientConnectionAdminMsg

MQeClientConnectionAdminMsg

This is a special type of MQSeries Everyplace message that is used to encapsulate an administration command. The message is created by the application that is doing the administration.

The logic performed on the target MQSeries Everyplace system is also in this class.

The administration queue invokes the `performAction` method.

Package com.ibm.mqe.mqbridge

This class extends `MQeMQQMgrProxyAdminMsg`

Constants and variables

`MQeQueueAdminMsg` provides the following constants and variables in addition to those provided by `MQeMQQMgrProxyAdminMsg`:

Constructor summary

Constructor	Purpose
<code>MQeClientConnectionAdminMsg</code>	Creates and initializes an <code>MQeClientConnectionAdminMsg</code> .

Method summary

Method	Purpose
<code>characteristics</code>	Creates an MQSeries Everyplace fields object containing all the MQe fields required for an administration message of this type.
<code>getClientConnectionName</code>	Gets the client connection name from the administered object.
<code>getName</code>	Gets the name of the object to be administered.
<code>putClientConnectionName</code>	Puts the client connection name in an MQSeries Everyplace field in the MQSeries Everyplace fields administration message object.
<code>setName</code>	Puts the name information in an MQSeries Everyplace field in the MQe fields administration message object and also sets the name of the MQSeries Everyplace queue manager that is associated with this bridge.

MQeClientConnectionAdminMsg

Syntax

1.

```
public MQeClientConnectionAdminMsg() throws Exception
```
2.

```
public MQeClientConnectionAdminMsg(String bridgeName,
                                    String nameOfMQQMgrProxy,
                                    String clientConnectionName,
                                    boolean affectChildren)
                                    throws Exception
```

Description

There are two constructors:

1. This version creates and initializes a default MQeClientConnectionAdminMsg
2. This version includes fields that are needed to initialize the administration message. It does not include the action that the administration message will hold

Parameters

bridgeName A String containing the name of the bridge to which the administration message is directed. If set to *null*, or "", it is not set.

nameOfMQQMProxy

A String containing the name of the proxy to which the administration message is directed. If set to *null*, or "", it is not set.

clientConnectionName

A String containing the name of the client connection to which the administration message is directed. If set to *null*, or "", it is not set.

affectChildren A boolean flag indicating whether or not this administration message affects all the children. This is only applicable if the action is **start** or **delete**.

Return Values

none

Exceptions

Fails if any of the parameters contain invalid characters

Example

```
MQeClientConnectionAdminMsg msg ;
msg = new MQeClientConnectionAdminMsg( "ExampleQM.MQBridgeV100"
                                         , "MQA"
                                         , "MQ.to.ExampleQM"
                                         , false
                                         );
```

MQeClientConnectionAdminMsg characteristics**Syntax**

```
public MQeFields characteristics() throws Exception
```

Description

Creates an **MQefields** object containing all the fields required for an administration message of this type.

Overrides **characteristics** in class **MQeMQQMProxyAdminMsg** .

Parameters

none

Return values

An MQeFields object containing the characteristics of the resource. The complete set of field names and types for the resource can be determined from the resulting fields object.

Exceptions

MQeClientConnectionAdminMsg

java.lang.Exception

Iif the **MQeFields** object cannot be created

Example

```
MQeClientConnectionAdminMsg msg;
msg = new MQeClientConnectionAdminMsg( "ExampleQM.MQBridgeV100",
                                       "MQA",
                                       "MQ.to.ExampleQM",
                                       false);
MQeFields cconAdminCharacteristics = msg.characteristics();
```

MQeClientConnectionAdminMsg getClientConnectionName

Syntax

```
public String getClientConnectionName() throws Exception
```

Description

Gets the client connection name from the administered object. This method can be issued against an **MQeClientConnectionAdminMsg** or one of its descendants.

Parameters

none

Return values

The name of the client connection to which this administration message is to be sent.

Exceptions

java.lang.Exception

Iif the name has not been set in this administration message, or if the name that has been set is invalid

Example

```
MQeClientConnectionAdminMsg msg;
msg = new MQeClientConnectionAdminMsg( "ExampleQM.MQBridgeV100",
                                       "MQA",
                                       "MQ.to.ExampleQM",
                                       false);
String cconName = msg.getClientConnectionName();
```

MQeClientConnectionAdminMsg getName

Syntax

```
public String getName()
```

Description

Gets the name of the client connection that is to be administered. In this case it's the name of the client connection that has been set by the **setName** or **putClientConnectionName** methods. When issued against an object of this class it is identical to **getClientConnectionName()**.

Overrides **getName** in class **MQeMQQMProxyAdminMsg**.

Parameters

none

Return values

A String containing the name of the administered object we want to create, or *null* if the name is not set.

MQeClientConnectionAdminMsg

Exceptions

none

Example

```
MQeClientConnectionAdminMsg msg;
msg = new MQeClientConnectionAdminMsg( "ExampleQM.MQBridgeV100",
                                       "MQA",
                                       "MQ.to.ExampleQM",
                                       false);
String cconName = msg.getName();
```

MQeClientConnectionAdminMsg putClientConnectionName

Syntax

```
public void putClientConnectionName(String clientConnectionName)
                                     throws Exception
```

Description

This is used to add the MQSeries queue manager name to the administration message. It puts the client connection name in an MQSeries Everyplace field in the MQSeries Everyplace fields administration message object.

Parameters

clientConnectionName

A String containing the name of the client connection to which the administration message is directed. This string is validated using the validateName() method to make sure it contains only legal characters.

Return values

none

Exceptions

java.lang.Exception

If there are any invalid characters in the name parameters

Example

```
MQeClientConnectionAdminMsg msg = new MQeClientConnectionAdminMsg();
msg.setName( "ExampleQM.MQBridgeV100" ,
              "MQA" ,
              "MQ.to.ExampleQM" );
```

MQeClientConnectionAdminMsg setName

Syntax

```
public void setName(String bridgeName,
                    String mqQMgrProxyName,
                    String ClientConnectionName) throws Exception
```

Description

Puts the name information in an MQSeries Everyplace field in the MQSeries Everyplace fields administration message object and also sets the name of the MQSeries Everyplace queue manager that is associated with this bridge.

Parameters

bridgeName A String containing the name of the bridge to which the administration message is directed. If set to *null*, or "", it is not set.

MQeClientConnectionAdminMsg

mqQMgrProxyName

A String containing the name of the proxy to which the administration message is directed. If set to *null*, or "", it is not set.

clientConnectionName

A String containing the name of the client connection to which the administration message is directed. If set to *null*, or "", it is not set.

Return values

none

Exceptions

java.lang.Exception

If there are any invalid characters in the name parameters.

Example

```
MQeClientConnectionAdminMsg msg = new MQeClientConnectionAdminMsg();
msg.setName( "ExampleQM.MQBridgeV100" ,
              "MQA" ,
              "MQ.to.ExampleQM" )
```

MQeListenerAdminMsg

This is a special type of MQSeries Everyplace message used to encapsulate an administration command. The message is created by the application that is doing the administration.

The logic performed on the target MQSeries Everyplace system is also in this class.

The administration queue invokes the `performAction` method.

Package com.ibm.mqe.mqbridge

This class extends `MQeClientConnectionAdminMsg`

Constructor summary

Constructor	Purpose
<code>MQeListenerAdminMsg</code>	Creates and initializes an <code>MQeListenerAdminMsg</code> .

Method summary

Method	Purpose
<code>characteristics</code>	Creates an MQSeries Everyplace fields object containing all the MQe fields required for an administration message of this type.
<code>getListenerName</code>	Gets the listener name from the administered object.
<code>getName</code>	Gets the name of the administered object to be created.
<code>putListenerName</code>	Puts the listener name in an MQSeries Everyplace field in the MQSeries Everyplace fields administration message object.
<code>setName</code>	Puts the name information in an MQSeries Everyplace field in the MQe fields administration message object and also sets the name of the MQSeries Everyplace queue manager that is associated with this bridge.

MQeListenerAdminMsg

Syntax

1.

```
public MQeListenerAdminMsg() throws Exception
```
2.

```
public MQeListenerAdminMsg(String bridge,
                           String MQQMgrProxy,
                           String clientConnection,
                           String listener
                           boolean affectChildren) throws Exception
```

Description

There are two constructors.

1. This version creates and initializes a default `MQeListenerAdminMsg`
2. This version includes the MQSeries Everyplace queue manager name, the name of the bridge, the name of the proxy, the name of the client connection, and the name of the listener

Parameters

MQeListenerAdminMsg

bridge	A String containing the name of the bridge to which the administration message is directed. If set to <i>null</i> , or "", it is not set.
MQQMgrProxy	A String containing the name of the MQS queue manager that owns the transmission queue that the listener is set up to read from. If set to <i>null</i> , or "", it is not set.
clientConnection	A String containing the name of the client connection used to talk to the MQS queue manager. If set to <i>null</i> , or "", it is not set.
listener	A string containing the name of the listener. This matches the name of the transmission queue on MQS to which the listener "listens", for messages to be ready to move to the MQSeries Everyplace network.
affectChildren	A boolean flag indicating whether or not this administration message affects the children of the listener.

Return Values

none

Exceptions

Fails if any of the parameters contain invalid characters

Example

```
MQeListenerAdminMsg msg = new MQeListenerAdminMsg( "MQBridgeV100",
    "lizzieQM",
    "svrconn",
    "MQE.XMITQ",
    true);
```

MQeListenerAdminMsg characteristics

Syntax

```
public MQeFields characteristics() throws Exception
```

Description

Creates an MQSeries Everyplace fields object containing all the MQSeries Everyplace fields required for an administration message of this type.

Returns a fields object containing the characteristics of the resource. The complete set of field names and types for the resource can be determined from the resulting fields object.

Overrides **characteristics** in class **MQeClientConnectionAdminMsg**.

Parameters

none

Return values

An **MQeFields** object containing the characteristics of the resource.

Exceptions

java.lang.Exception

If the **MQeFields** object cannot be created

Example

MQeListenerAdminMsg

```
MQeListenerAdminMsg msg = new MQeListenerAdminMsg( "MQBridgeV100",
    "lizzieQM",
    "svrconn",
    "MQE.XMITQ",
    true );
MQeFields characteristics = msg.characteristics();
```

MQeListenerAdminMsg getListenerName

Syntax

```
public String getListenerName() throws Exception
```

Description

Gets the listener name from the administered object.

Can be issued only against an MQeListenerAdminMsg object.

Parameters

none

Return values

The name of the listener.

Exceptions

java.lang.Exception

If the name has not been set in this administration message, or if the name that has been set is invalid

Example

```
MQeListenerAdminMsg msg = new MQeListenerAdminMsg( "MQBridgeV100",
    "lizzieQM",
    "svrconn",
    "MQE.XMITQ",
    true);
String listenerName = msg.getListenerName();
```

MQeListenerAdminMsg getName

Syntax

```
public String getName()
```

Description

Gets the name of the client connection that is to be administered.

When issued against an object of this class it is identical to getListenerName().

Overrides getName in class MQeClientConnectionAdminMsg.

Parameters

none

Return values

A String containing the name of the administered object to be created, or null if the name is not set.

Exceptions

none

Example

MQeListenerAdminMsg

```
MQeListenerAdminMsg msg = new MQeListenerAdminMsg( "MQBridgeV100",
                                                 "lizzieQM",
                                                 "svrconn",
                                                 "MQE.XMITQ",
                                                 true);

String listenerName = msg.getName();
```

MQeListenerAdminMsg putListenerName

Syntax

```
public void putListenerName(String listener) throws Exception
```

Description

Used to add the MQS Queue Manager name to the administration message. Puts the listener name in an MQSeries Everyplace field in the MQSeries Everyplace fields administration message object.

This method is used by the source of the administration message.

Parameters

listener	A string containing the name of the listener. This matches the name of the transmission queue on MQS to which the listener "listens", for messages to be ready to move to the MQSeries Everyplace network.
-----------------	--

Return values

none

Exceptions

java.lang.Exception	If there are any invalid characters in the name parameters.
----------------------------	---

Example

```
MQeListenerAdminMsg msg = new MQeListenerAdminMsg();
msg.putListenerName("MQE.XMITQ");
```

MQeListenerAdminMsg setName

Syntax

```
public void setName(String bridge,
                    String mqQMgrProxy,
                    String clientConnection
                    String listener) throws Exception
```

Description

Puts the name information in an MQSeries Everyplace field in the MQSeries Everyplace fields administration message object and also sets the name of the MQSeries Everyplace queue manager that is associated with this bridge.

This method is used by the source of the administration message.

Parameters

bridge	A String containing the name of the bridge to which the administration message is directed. If set to <i>null</i> , or "", it is not set.
---------------	---

MQQMProxy

MQQMProxy	A String containing the name of the MQS queue manager that owns the transmission queue the listener is set up to read from. If set to <i>null</i> , or "", it is not set.
------------------	---

clientConnection

A String containing the name of the client connection used to talk to the MQSeries queue manager. If set to *null*, or "", it is not set.

listener

A string containing the name of the listener. This matches the name of the transmission queue on MQSeries to which the listener "listens", for messages to be ready to move to the MQSeries Everyplace network.

Return values

none

Exceptions**java.lang.Exception**

If there are any invalid characters in the name parameters.

Example

```
MQeListenerAdminMsg msg = new MQeListenerAdminMsg();
msg.setName("MQBridgeV100", "lizzieQM", "svrconn", "MQE.XMITQ");
```

MQeMQBridgeAdminMsg

MQeMQBridgeAdminMsg

This is a special type of MQSeries Everyplace message that is used to encapsulate an administration command. The message is created by the application that is doing the administration.

The logic performed on the target MQSeries Everyplace system is also in this class.

The administration queue invokes the `performAction` method.

Package `com.ibm.mqe.mqbridge`

This class extends `MQeMQBridgesAdminMsg`

Constants and variables

`MQeQueueAdminMsg` provides the following constants and variables in addition to those provided by `MQeMQBridgesAdminMsg`:

`DEFAULT_MQBRIDGE_NAME`

```
public static final String DEFAULT_MQBRIDGE_NAME
```

Constructor summary

Constructor	Purpose
<code>MQeMQBridgeAdminMsg</code>	Creates and initializes an <code>MQeBridgeAdminMsg</code> .

Method summary

Method	Purpose
<code>characteristics</code>	Creates an MQSeries Everyplace fields object containing all the MQSeries Everyplace fields required for an administration message of this type.
<code>create</code>	Causes this administration message to be a "create" message.
<code>delete</code>	Causes this administration message to be a "delete" message.
<code>getBridgeName</code>	Gets the bridge name from the administered object.
<code>getName</code>	Gets the name of the administered object to be created.
<code>putBridgeName</code>	Puts the bridge connection name in an MQSeries Everyplace field in the MQSeries Everyplace fields administration message object.
<code>setName</code>	Puts the name information in an MQSeries Everyplace field in the MQSeries Everyplace fields administration message object and also sets the name of the MQSeries Everyplace queue manager that is associated with this bridge.

MQeMQBridgeAdminMsg

Syntax

1.

```
public MQeMQBridgeAdminMsg() throws Exception
```

2.

MQeMQBridgeAdminMsg

```
public MQeMQBridgeAdminMsg(String bridgeName,  
                           boolean affectChildren) throws Exception
```

Description

There are two constructors.

1. This version creates and initializes a default MQeBridgeAdminMsg
2. This version includes the name of the bridge and a flag to determine whether children should be affected by the administration commands

Parameters

bridge	A String containing the name of the bridge to which the administration message is directed. If set to <i>null</i> , or "", it is not set.
affectChildren	A boolean flag indicating whether or not this administration message affects the children of the listener.

Return Values

none

Exceptions

java.lang.Exception	If any of the parameters contain invalid characters
----------------------------	---

Example

1.

```
MQeMQBridgeAdminMsg msg = new MQeMQBridgeAdminMsg();
```
2.

```
public MQeMQBridgeAdminMsg(java.lang.String bridge,  
                           boolean affectChildren) Exception
```

MQeMQBridgeAdminMsg characteristics

Syntax

```
public MQeFields characteristics() throws Exception
```

Description

Creates an MQSeries Everyplace fields object containing all the MQSeries Everyplace fields required for an administration message of this type.

Returns a fields object containing the characteristics of the resource. The complete set of field names and types for the resource can be determined from the resulting fields object.

Overrides **characteristics** in class **MQeBridgesAdminMsg**.

Parameters

none

Return values

An MQeFields object containing the characteristics of the resource.

Exceptions

java.lang.Exception	If the MQeFields object cannot be created.
----------------------------	---

Example

```
MQeMQBridgeAdminMsg msg = new MQeMQBridgeAdminMsg("MQBridgeV100", true);  
MQeFields bridgeCharacteristics = msg.characteristics();
```

MQeMQBridgeAdminMsg

MQeMQBridgeAdminMsg create

Syntax

```
public void create(MQeFields parms) throws Exception
```

Description

Used by the source of the administration message.

Causes this administration message to be a "create" message. When the target MQSeries Everyplace system processes this message, it creates an MQSeries queue manager entry.

Overrides **create** in class **MQeAdminMsg**.

Parameters

parms	Any extra parameters you want to add to the message, or <i>null</i> .
--------------	---

Return values

none

Exceptions

java.lang.Exception	If the MQeFields object cannot be created
----------------------------	--

Example

```
// Form a message that will create a new MQBridge.  
MQeMQBridgeAdminMsg msg = new MQeMQBridgeAdminMsg();  
msg.create( new MQeFields() );
```

MQeMQBridgeAdminMsg getBridgeName

Syntax

```
public String getBridgeName() throws Exception
```

Description

Gets the bridge name from the administered object.

Can be issued against an **MQeMQBridgeAdminMsg** or one of its descendants.

Parameters

none

Return values

The name of the bridge.

Exceptions

java.lang.Exception	If the name has not been set in this administration message, or if the name that has been set is invalid
----------------------------	--

Example

```
MQeMQBridgeAdminMsg msg = new MQeMQBridgeAdminMsg("MQBridgeV100", true);  
String bridgeName = msg.getBridgeName();
```

MQeMQBridgeAdminMsg getName

Syntax

```
public String getName()
```

Description

Gets the name of the bridge that is to be administered. When issued against an object of this class it is identical to getBridgeName().

Overrides `getName` in class `MQeBridgesAdminMsg`.

Parameters

none

Return values

A String containing the name of the administered object to be created, or *null* if the name is not set.

Exceptions

none

Example

```
MQeMQBridgeAdminMsg msg = new MQeMQBridgeAdminMsg("MQBridgeV100", true);
String bridgeName = msg.getName();
```

MQeMQBridgeAdminMsg delete

Syntax

- 1.
- public void delete(MQeFields parms,
 boolean affectChildren) throws Exception
- 2.
- public void delete(MQeFields parms) throws Exception

Description

There are two versions of this method:

1. This version is used by the source of the administration message and it causes this administration message to be a "delete" message. When the target MQSeries Everyplace system processes this message, it finds the specified bridge object, and deletes it. This operation is inherited by the other bridge object types.
2. This version is equivalent to `delete((MQeFields) parms, false)`. When the target MQSeries Everyplace system processes this message, it finds the specified bridge object, and deletes it. This operation is inherited by the other bridge object types.

Overrides `delete` in class `MQeAdminMsg`

Parameters

parms	Any extra parameters you want to add to the message, or <i>null</i> .
affectChildren	A boolean flag indicating whether or not this administration message affects the children of the listener.

Return values

none

Exceptions

<code>java.lang.Exception</code>	If the delete fails
----------------------------------	---------------------

MQeMQBridgeAdminMsg

Example

1.

```
// Form a message that will delete an MQBridge and its children.
MQeMQBridgeAdminMsg msg = new MQeMQBridgeAdminMsg();
msg.delete( new MQeFields(), true );
```
2.

```
// Form a message that will delete an MQBridge.
MQeMQBridgeAdminMsg msg = new MQeMQBridgeAdminMsg();
msg.delete( new MQeFields() );
```

MQeMQBridgeAdminMsg putBridgeName

Syntax

```
public void putBridgeName(String bridge) throws Exception
```

Description

Used by the source of the administration message to add the MQSeries queue manager name to the administration message.

Puts the bridge name in an MQSeries Everyplace field in the MQSeries Everyplace fields administration message object.

Parameters

bridge A String containing the name of the bridge to which the administration message is directed. If set to *null*, or "", it is not set.

Return values

none

Exceptions

java.lang.Exception	If there are any invalid characters in the name parameters
----------------------------	--

Example

```
MQeMQBridgeAdminMsg msg = new MQeMQBridgeAdminMsg();
msg.putBridgeName("MQBridgeV100");
```

MQeMQBridgeAdminMsg setName

Syntax

```
public void setName(String bridge) throws Exception
```

Description

Used by the source of the administration message to add the bridge name to the administration message.

Puts the name information in an MQSeries Everyplace field in the MQSeries Everyplace fields administration message object and also sets the name of the MQSeries Everyplace queue manager that is associated with this bridge.

Overrides **setName** in class **MQeAdminMsg**

Parameters

bridge A String containing the name of the bridge to which the administration message is directed. If set to *null*, or "", it is not set.

MQeMQBridgeAdminMsg

Return values

none

Exceptions

java.lang.Exception

If there are any invalid characters in the name parameters

Example

```
MQeMQBridgeAdminMsg msg = new MQeMQBridgeAdminMsg();
msg.setName("MQBridgeV100");
```

MQeMQBridgeQueue

MQeMQBridgeQueue

This queue is used as the interface to the MQSeries bridge and is passed into the user-written "transformer" code.

The transformer is responsible for conversion from MQSeries Everyplace to MQSeries message formats, and vice-versa, but a reference to the MQeMQBridgeQueue class is passed to the transformer code only when the message is moving from MQSeries Everyplace to MQSeries.

The class holds details that the user-written transformer class implementation may wish to use when performing a transform operation on the message data.

Package com.ibm.mqe.mqbridge

This class extends **MQeRemoteQueue**

Method summary

Method	Purpose
getMQQMgr	Gets the name of the MQS queue manager that is used to convey messages onto the MQS network.
getQueueAttribute	Gets the attribute attached to the bridge queue.
getQueueManagerName	Gets the owning queue manager name.
getQueueName	Gets the name of the bridge queue.
getRemoteQName	Gets the name of the queue on MQS where the message is put after it has been transformed.

MQeMQBridgeQueue getMQQMgr

Syntax

```
public String getMQQMgr() throws Exception
```

Description

Gets the name of the MQSeries queue manager that is used to convey messages onto the MQSeries network.

Parameters

none

Return Values

A String containing the name of the MQSeries queue manager which will be used to convey queue messages onto the MQSeries network..

If the administrator specified "" or a *null* in the MQBridge queue parameter, the value returned by this string matches that returned by the **getQueueManagerName()** method.

Exceptions

java.lang.Exception

If the name get fails, or if the name is invalid.

Example

```
String mqQMgrName = transformersBridgeQueue.getMQQMgr();
```

MQeMQBridgeQueue getQueueAttribute

Syntax

```
public MQeAttribute getQueueAttribute() throws Exception
```

Description

Gets the attribute attached to the MQbridge queue.

Overrides **getQueueAttribute** in class **MQeQueue**

Parameters

none

Return values

An **MQeAttribute** object containing the attribute the bridge queue is configured with.

Exceptions

java.lang.Exception	If the get fails
----------------------------	------------------

Example

```
MQeAttribute attribute = transformersBridgeQueue.getQueueAttribute();
```

MQeMQBridgeQueue getQueueManagerName

Syntax

```
public String getQueueManagerName() throws Exception
```

Description

Gets the name of the owning MQSeries queue manager.

Overrides **getQueueManagerName** in class **MQeQueue**.

Parameters

none

Return values

A String containing the name of the owning queue manager.

Exceptions

java.lang.Exception	If the get fails or the name is invalid
----------------------------	---

Example

```
String qMgrName = transformersBridgeQueue.getQueueManagerName();
```

MQeMQBridgeQueue getQueueName

Syntax

```
public String getQueueName() throws Exception
```

Description

Gets the name of the bridge queue as it is known on MQSeries Everyplace.

Overrides **getQueueName** in class **MQeQueue**.

Parameters

none

Return values

A string containing the name of the bridge queue.

Exceptions

MQeMQBridgeQueue

java.lang.Exception

If the get fails or the name is invalid

Example

```
String mqQName = transformersBridgeQueue.getQueueName();
```

MQeMQBridgeQueue getRemoteQName

Syntax

```
public String getRemoteQName() throws Exception
```

Description

Gets the name of the queue on MQS that the message is put to after it has been transformed.

Parameters

none

Return values

A String containing the string contents of the remote queue name configuration information that was specified when the queue was configured by the administrator.

If the remote queue name is blank or *null*, then the value returned is the queue name of the MQSeries bridge queue itself.

Exceptions

java.lang.Exception

If the get fails or the name is invalid

Example

```
String remoteQName = transformersBridgeQueue.getRemoteQName();
```

MQeMQBridgeQueueAdminMsg

Used to administer an MQBridge queue.

Package com.ibm.mqe.mqbridge

This class extends **MQeRemoteQueueAdminMsg**

Constants and variables

MQeQueueAdminMsg provides the following constants and variables :

Queue_BridgeName

Constant used when dumping this queue's details to the registry. The MQeField holds the name of the bridge.

```
public static final String Queue_BridgeName
```

Queue_ClientConnection

Constant used when dumping this queue's details to the registry. The MQeField holds the name of the client connection.

```
public static final String Queue_ClientConnection
```

Queue_MaxIdleTime

The name of the MaxIdleTime config parameter field that indicates how long an MQSeries bridge queue is allowed to keep an idle connection, before the connection is returned to the connection pool.

```
public static final String Queue_MaxIdleTime[]
```

Queue_MQQMgr

Constant used when dumping this queue's details to the registry. The MQeField holds the name of the MQS Queue Manager.

```
public static final String Queue_MQQMgr
```

Queue_RemoteQName

Constant used when dumping this queue's details to the registry. The MQeField holds the remote queue name.

```
public static final String Queue_MQQMgr
```

Queue_Transformer

The name of the transformer to use when converting an MQSeries Everyplace message into an MQS message.

```
public static final String Queue_Transformer
```

Queue characteristics

Name The name of the queue.

For an MQBridge queue it is the name by which the MQSeries queue is known on the MQSeries Everyplace system. (Ascii)

This characteristic is mandatory.

MQeField label: MQeMQBridgeQueueAdminMsg.Admin_Name

QMgrName

As described in the com.ibm.mqe.administration.MQEQueueAdminMsg class.

For an MQSeries bridge queue, this should hold the name of the MQSeries queue manager on which the queue is located locally, not necessarily the queue manager to which the bridge has a direct connection.

MQeField label: MQeMQBridgeQueueAdminMsg.Queue_QMngrName

MQeMQBridgeQueueAdminMsg

Active

CreationDate

As described in the com.ibm.mqe.administration.MQeQueueAdminMsg class.

MQeField label: MQeMQBridgeQueueAdminMsg.Queue_CreationDate

Description

As described in the com.ibm.mqe.administration.MQeQueueAdminMsg class.

MQeField label: MQeMQBridgeQueueAdminMsg.Queue_Description

Expiry As described in the com.ibm.mqe.administration.MQeQueueAdminMsg class.

The Message expiry time.

This value is available to the transformer of the message, so the transformer can use it to set the message expiry time of the MQSeries message that is sent to the MQSeries system.

A value of less than 1 means "never expire".

The transformer (being user customized) may choose not to use this information.

The MQSeries Everyplace message may itself contain an expiry time which over-rides this value also.

MQeField label: MQeMQBridgeQueueAdminMsg.Queue_Expiry

MaxMsgSize

As described in the com.ibm.mqe.administration.MQeQueueAdminMsg class.

The Maximum message length is an optional field. It is NOT used by the base MQBridge code at all, but is available to the rules class to decide whether the message should be sent to the MQSeries queue or not.

Checking is not performed to make sure this value is the same as that specified by the MQSeries queue this MQBridge queue refers to. For example, the rule may use this value to prevent messages over a certain length being sent to MQ, even though the MQSeries queue could accept bigger messages.

MQeField label: MQeMQBridgeQueueAdminMsg.Queue_MaxMsgSize

Mode Type

As described in the com.ibm.mqe.administration.MQeQueueAdminMsg class.

MQeField label: MQeMQBridgeQueueAdminMsg.Queue_Mode

Note: The Cryptor, Authenticator and compressor characteristics (below) define a set of queue attributes that dictate the level of security for any message being passed to this queue. From the point in MQSeries Everyplace where the message is sent initially, to the point where the message is passed to the MQBridge queue, the message is protected with at least the specified level of security, enforced by MQe. These values are NOT applicable when the MQBridge queue passes the message to the MQSeries system. The security, send and receive exits specified on the client connection configuration object

MQeMQBridgeQueueAdminMsg

on the bridge are used to protect the message as it passes to MQ. There is no checking that the link between the MQBridge queue and the MQSeries system is at least as secure as the security attributes specified in the Cryptor, Authenticator and compressor classes here.

AttrRule

As described in the com.ibm.mqe.administration.MQEQueueAdminMsg class.

MQeField label: MQeMQBridgeQueueAdminMsg.Queue_AttrRule

Authenticator

As described in the com.ibm.mqe.administration.MQEQueueAdminMsg class.

MQeField label: MQeMQBridgeQueueAdminMsg.Queue_Authenticator

Compressor

As described in the com.ibm.mqe.administration.MQEQueueAdminMsg class.

MQeField label: MQeMQBridgeQueueAdminMsg.Queue_Compressor

Cryptor

As described in the com.ibm.mqe.administration.MQEQueueAdminMsg class.

MQeField label: MQeMQBridgeQueueAdminMsg.Queue_Cryptor

TargetRegistry

As described in the com.ibm.mqe.administration.MQEQueueAdminMsg class.

MQeField label: MQeMQBridgeQueueAdminMsg.Queue_TargetRegistry

Rule

As described in the com.ibm.mqe.administration.MQEQueueAdminMsg class.

MQeField label: MQeMQBridgeQueueAdminMsg.Queue_Rule

Bridge Name

The MQBridge is the name of the MQSeries bridge that should be used to convey MQSeries Everyplace messages onto the MQSeries network. (Ascii)

This field is mandatory.

MQeField label: MQeMQBridgeQueueAdminMsg.Queue_BridgeName

MQSeries Queue Manager Proxy

The MQSeries queue manager proxy is the name of the MQSeries queue manager proxy in the MQbridge that is used to convey MQSeries Everyplace messages onto the MQSeries network.

This field is mandatory.

(This is the same as the name of the MQSeries queue manager to which the message is initially sent using a client connection).

MQeField label: MQeMQBridgeQueueAdminMsg.Queue_ClientConnection

MQSeries Remote Q name

The remote MQSeries queue name is optional.

It indicates the name of the queue to which messages are put on the MQSeries queue manager.

MQeMQBridgeQueueAdminMsg

If set to blank or *null*, it indicates that the queue name on the MQSeries queue manager (at the other end of the specified client connection) has the same name as this MQSeries bridge queue definition (so the value is derived from the "Name" field above).

This parameter provides a form of name change to allow two similarly-named queues on two MQSeries queue managers, to have different MQSeries Bridge queue names on the MQSeries Everyplace system.

MQeField label: MQeMQBridgeQueueAdminMsg.Queue_RemoteQName

Transformer class

The Transformer class is the name of the java class used to convert an MQSeries Everyplace message into an MQSeries message, before the MQSeries message is put onto the MQSeries network.

If this parameter is left blank, or is *null*, then the default transformer class for the specified MQSeries bridge (from the MQSeries Bridge field above) is used.

This parameter is optional.

MQeField label: MQeMQBridgeQueueAdminMsg.Queue_Transformer

Return idle connection timeout

The "idle time" parameter indicates the maximum number of minutes that the queue can hold an idle MQSeries connection, before it has to be released back to an idle connection pool maintained by the bridge.

If the queue is unused for a while, the underlying MQSeries connection is released back to a pool where another queue could pick it up, and use it. When the original idle queue has any message activity, it can go to the pool for another (possibly different) connection, to use.

The fact that the MQSeries connections logically underpinning an MQSeries bridge queue may be freed, and re-allocated, is transparent to users of the queue, except that a small time penalty is incurred releasing and getting an idle connection to/from the connection pool.

The idle time is in units of 1 minute.

The timer parameter is directly dependent on the granularity of the bridge heartbeat parameter.

See bridge object configuration parameters in the *MQSeries Everyplace Programming Guide*.

In the extreme case, specifying an idle time of 0 means "always free a connection to the pool once you have used it". Although this allows a very small number of MQSeries client connection channels to be effectively "shared" between a large number of MQBridge queues (provided they all use the same Bridge/MQProxy/ClientConnection details) it is at the cost of the release-to-pool and acquire-from-pool operations for each message.

A default of 5 minutes is recommended.

MQeField label: MQeMQBridgeQueueAdminMsg.Queue_MaxIdleTime

Constructor summary

Constructor	Purpose
MQeMQBridgeQueueAdminMsg	Create the administration message to administer the bridge queue.

Method summary

Method	Purpose
characteristics	Create a fields object containing the valid characteristics of a queue.

MQeMQBridgeQueueAdminMsg

Syntax

1.
public MQeMQBridgeQueueAdminMsg() throws Exception
2.
public MQeMQBridgeQueueAdminMsg(String bridge,
 String mqQMgrProxy,
 String clientConnection) throws Exception

Description

There are two constructors:

1. This version creates and initializes a default administration message to administer the bridge queue
2. This version includes initial values for the name of the bridge, the name of the proxy, and the name of the client connection

Parameters

bridge A String containing the name of the bridge to which the administration message is directed. If set to null, or "", it is not set.

MQQMProxy

A String containing the name of the MQS queue manager that owns the transmission queue the bridge queue is set up to read from. If set to *null* or "", it is not set.

clientConnection

A String containing the name of the client connection used to talk to the MQSeries queue manager. If set to *null* or "", it is not set.

maxIdleTimeout

The number of minutes the queue is allowed to keep hold of a connection to the MQSeries system without using it. When the queue has been unused for this duration, the connection is returned to the connection pool. If 0, the connection is returned to the connection pool immediately it has been used.

Return Values

none

Exceptions

MQeMQBridgeQueueAdminMsg

java.lang.Exception

If the message cannot be created

Example

1.

```
MQeMQBridgeQueueAdminMsg msg;  
msg = new MQeMQBridgeQueueAdminMsg( );
```

2.

```
MQeMQBridgeQueueAdminMsg msg;  
msg = new MQeMQBridgeQueueAdminMsg( "MQBridgeV100",  
                                    "lizzieQM",  
                                    "svrconn",  
                                    5 );
```

MQeMQBridgeQueueAdminMsg characteristics

Syntax

```
public MQeFields characteristics() throws Exception
```

Description

Creates a fields object containing the valid characteristics of a queue. The **MQeFields** object contains the valid field names, it does not contain the value of each characteristic. It can be used to determine the name and type of all valid characteristics.

Overrides **characteristics** in class **MQeRemoteQueueAdminMsg**.

Parameters

none

Return values

An **MQeFields** object containing the characteristics of the queue.

Exceptions

java.lang.Exception

If the **MQeFields** object cannot be created

Example

```
MQeMQBridgeQueueAdminMsg msg;  
msg = new MQeMQBridgeQueueAdminMsg( "MQBridgeV100",  
                                    "lizzieQM",  
                                    "svrconn",  
                                    5 );  
MQeFields adminMsgChars = msg.characteristics();
```

MQeMQBridges

The bridges class acts as a "loader" for all the bridges. It is the class that is specified as the MQBridge class alias in the ini file and causes an instance of this class to be loaded dynamically by the MQSeries Everyplace server.

The aim of the bridges class is to load bridge objects from the registry into memory and to maintain a list of bridges that are available within the JVM. There is only ever one bridges object in a single JVM.

The server code calls the activate() method just after the constructor() and calls the close() method when the bridges should all be cleanly shut down. Between starting the bridges object and shutting it down, the server must retain a reference to the bridges object to stop it from being garbage-collected.

Package com.ibm.mqe.mqbridge

This class extends **MQeAdministeredObject**

Constructor summary

Constructor	Purpose
MQeMQBridges	Creates an MQBridges object

Method summary

Method	Purpose
activate	Called by the gateway/bridge server just after the constructor to activate the bridges object
close	Closes the bridges object

MQeMQBridges

Syntax

Syntax: public MQeMQBridges() throws Exception

Description

Simple constructor.

The gateway server should load this class using the MQSeries Everyplace class loader, and so the constructor is not called directly. The server should then call the activate() method passing in any configuration parameters.

Parameters

none

Return Values

none

Exceptions

java.lang.Exception

Example

```
MQeMQBridges mqBridges = (MQeMQBridges) MQe.loader.loadObject( "MQBridge" );
```

MQeMQBridges

MQeMQBridges activate

Syntax

```
public void activate(com.ibm.mqe.MQeFields config) throws Exception
```

Description

Called by the MQSeries Everyplace server just after the null constructor.
Used to pass configuration to the bridges object, so the bridges object can
load any bridges specified in the configuration

Parameters

config An MQeFields object that contains the complete contents of
the ini file with which the MQSeries Everyplace server
was initialized.

Fields=Aliases

...
(ascii)MQBridge=com.ibm.mqe.mqbridge.MQeMQBridges
Fields=ChannelManager

...
Fields=Listener

...
Fields=QueueManager

...
Fields=MQBridge
(ascii)LoadBridgeRule=RuleClass

Return values

none

Exceptions

java.lang.Exception

Fails if the underlying server could not
activate the bridges object, or the
configuration parameters supplied were
invalid.

Example

```
mqBridges.activate( myConfigFields );
```

MQeMQBridges close

Syntax

```
public void close() throws Exception
```

Description

Closes the bridges objects as cleanly as possible.

Parameters

none

Return values

none

Exceptions

java.lang.Exception

If the objects could not be shut down
cleanly.

Example

```
mqBridges.close( );
```

MQeMQBridgesAdminMsg

MQeMQBridgesAdminMsg

Used to encapsulate an administration command that acts on the MQeBridges object.

This message is created by the application doing the administration.

The logic performed on the target MQSeries Everyplace system is also in this class.

The administration queue invokes the `performAction` method.

Package com.ibm.mqe.mqbridge

This class extends `MQeAdminMsg`

Constants and variables

`MQeQueueAdminMsg` provides the following constants and variables in addition to those provided by `MQeAdminMsg`:

Action_Start

Operation code for starting an administered object

```
public static final int Action_Start
```

Action_Stop

Operation code for stopping an administered object.

```
public static final int Action_Stop
```

Constructor summary

Constructor	Purpose
<code>MQeMQBridgesAdminMsg</code>	Creates and initializes an <code>MQeBridgesAdminMsg</code> object.

Method summary

Method	Purpose
<code>characteristics</code>	Creates an MQSeries Everyplace fields object containing all the MQe fields required for an administration message of this type.
<code>getName</code>	Gets the name of the administered object to be created.
<code>start</code>	Tells the administered object to start.
<code>stop</code>	Tells the administered object to stop

MQeMQBridgesAdminMsg

Syntax

1.

```
public MQeMQBridgesAdminMsg() throws Exception
```

2.

```
public MQeMQBridgesAdminMsg(boolean affectChildren) throws Exception
```

Description

There are two constructors:

1. This version creates and initializes a default `MQeMQBridgesAdminMsg`

MQeMQBridgesAdminMsg

2. This version includes a flag to determine whether children should be affected by the administration commands

Parameters

affectChildren A boolean flag indicating whether or not this administration message affects the children of the bridges object.

true means it is allowed to affect the children, **false** indicates that the children should not be affected.

Some commands ALWAYS affect the children (Stop for example).

This flag is sometimes transferred into the **MQEvent** that is sent to the bridges administered object.

Return Values

none

Exceptions

java.lang.Exception	If the MQField holding the affectChildren flag cannot be created.
----------------------------	---

Example

```
MQeMQBridgesAdminMsg msg = new MQeMQBridgesAdminMsg(true);
```

Related functions

MQEvent

MQeMQBridgesAdminMsg characteristics

Syntax

```
public MQeFields characteristics() throws Exception
```

Description

Creates an MQSeries Everyplace fields object containing all the MQSeries Everyplace fields required for an administration message of this type.

Overrides **characteristics** in class **MQeBridgesAdminMsg**.

Parameters

none

Return values

An **MQeFields** object containing the characteristics of the resource.

Exceptions

java.lang.Exception	If the MQeFields object cannot be created
----------------------------	--

Example

```
MQeMQBridgesAdminMsg msg = new MQeMQBridgesAdminMsg(true);
MQeFields theseCharacteristics = msg.characteristics();
```

MQeMQBridgesAdminMsg getName

Syntax

```
public String getName()
```

Description

MQeMQBridgesAdminMsg

Returns the name of the administered object we want to create.

Overrides **getName** in class **MQeAdminMsg**

Parameters

none

Return values

null if the name was not set, otherwise a string.

Exceptions

none

Example

```
MQeMQBridgesAdminMsg msg = new MQeMQBridgesAdminMsg(true);
String name = msg.getName();
```

MQeMQBridgesAdminMsg start

Syntax

1.
public void start() throws Exception
2.
public void start(boolean affectChildren) throws Exception
3.
public void start(MQeFields fields) throws Exception

Description

There are three versions:

1.
This version is used by the source of the administration message and tells the administered object to start. It also tells all its child objects to start.
2.
This version is used by the source of the administration message and tells the administered object to start. It also tells all its child objects to start depending on the value of a parameter.
3.
This version tells the administered object to start and also tells all its child objects to start or not, depending on the value of the **affectChildren** field.
Other bridge related parameters can also be passed in the MQeFields object.

Parameters

affectChildren A boolean that indicates whether the command operation set in this administration message is allowed to affect the children of the bridges object.

true means it is allowed to affect the children, **false** indicates that the children should not be affected.

Some commands ALWAYS affect the children (stop for example).

MQeMQBridgesAdminMsg

This flag is sometimes transferred into the **MQeEvent** that is sent to the bridges administered object.

fields

An **MQeFields** object that contains a set of fields that can contain the bridge name, the **affectChildren** flag, and other bridge related parameters.

These fields are blindly copied into this administration message ready for transmission. No validation is performed on these field parameters.

If the **affectChildren** flag is present in the fields parameter, it overrides the default value of **true**.

Return values

none

Exceptions

java.lang.Exception

If the start action or the **affectChildren** flag, or any of the passed fields cannot be set into **MQeFields** in this administration message

Example

1.

```
MQeMQBridgesAdminMsg msg = new MQeMQBridgesAdminMsg();
msg.start();
```
2.

```
MQeMQBridgesAdminMsg msg = new MQeMQBridgesAdminMsg();
msg.start(true);
```
3.

```
MQeMQBridgesAdminMsg msg = new MQeMQBridgesAdminMsg();
MQeFields fields = new MQeFields();
fields.putBoolean( MQeCharacteristicLabels.MQE_FIELD_LABEL_AFFECT_CHILDREN,
true );
msg.start(fields);
```

MQeMQBridgesAdminMsg stop

Syntax

1.

```
public void stop() throws Exception
```
2.

```
public void stop(MQeFields fields) throws Exception
```

Description

There are two versions:

1.

This version is used by the source of the administration message and tells the administered object to stop. It also tells all its child objects to stop.

2.

This version tells the administered object to stop and also tells all its child objects to stop.

MQeMQBridgesAdminMsg

This version accepts a set of fields that can contain the fields that identify which **MQeAdministeredObject** should be stopped.

Parameters

fields An **MQeFields** object. These fields are copied into the administration message fields, overriding any current field values.

Return values

none

Exceptions

java.lang.Exception If the action cannot be set into this administration message

Example

1.

```
MQeMQBridgesAdminMsg msg = new MQeMQBridgesAdminMsg();
msg.start();
```

2.

```
MQeMQBridgesAdminMsg msg = new MQeMQBridgesAdminMsg();
MQeFields fields = new MQeFields();
fields.putBoolean( MQeCharacteristicLabels.MQE_FIELD_LABEL_AFFECT_CHILDREN,
                  true );
msg.start(fields);
```

MQeMQQMgrProxyAdminMsg

This message is created by the application doing the administration and is used to encapsulate an administration command that acts on the MQeMQQMgrProxy object.

The logic performed on the target MQSeries Everyplace system is also in this class.

The administration queue invokes the `performAction` method.

Package com.ibm.mqe.mqbridge

This class extends `MQeMQBridgeAdminMsg`

Constructor summary

Constructor	Purpose
<code>MQeMQQMgrProxyAdminMsg</code>	Creates and initializes an <code>MQeMQQMgrProxyAdminMsg</code> object.

Method summary

Method	Purpose
<code>characteristics</code>	Creates an MQSeries Everyplace fields object containing all the MQe fields required for an administration message of this type.
<code>getMQQMgrProxyName</code>	Gets the MQS queue manager proxy name from the administered object.
<code>getName</code>	Gets the name of the administered object to be created.
<code>putMQQMgrProxyName</code>	Puts the MQS queue manager proxy name in an MQSeries Everyplace field in the MQSeries Everyplace fields administration message object
<code>setName</code>	Puts the name information in an MQSeries Everyplace field in the MQe fields administration message object

MQeMQQMgrProxyAdminMsg

Syntax

1.

```
public MQeMQQMgrProxyAdminMsg() throws Exception
```
2.

```
public MQeMQQMgrProxyAdminMsg(String bridge,
                               String MQQMgrProxy,
                               boolean affectChildren) throws Exception
```

Description

There are two constructors:

1. This version creates and initializes a default `MQeMQQMgrProxyAdminMsg`
2. This version includes the MQSeries Everyplace queue manager name, the name of the bridge, and the name of the proxy

Parameters

MQeMQQMgrProxyAdminMsg

bridge A String containing the name of the bridge to which the administration message is directed. If set to *null*, or "", it is not set.

MQQMgrProxy

A String containing the name of the proxy to which the administration message is directed. If set to *null*, or "", it is not set.

affectChildren A boolean flag indicating whether or not this administration message affects the children of the bridges object.

true means it is allowed to affect the children, **false** indicates that the children should not be affected.

Return Values

none

Exceptions

java.lang.Exception If any fields could not be set or if the MQSeries queue manager name is invalid.

Example

1.

```
MQeMQQMgrProxyAdminMsg msg = new MQeMQQMgrProxyAdminMsg();
```

2.

```
MQeMQQMgrProxyAdminMsg msg;  
msg = new MQeMQQMgrProxyAdminMsg("MQBridgeV100", "lizzieQM");
```

MQeMQQMgrProxyAdminMsg characteristics

Syntax

```
public MQeFields characteristics() throws Exception
```

Description

Creates an MQSeries Everyplace fields object containing all the MQSeries Everyplace fields required for an administration message of this type.

Returns a fields object containing the characteristics of the resource. The complete set of field names and types for the resource can be determined from the resulting fields object.

Overrides **characteristics** in class **MQeBridgeAdminMsg**.

Parameters

none

Return values

An MQeFields object containing the characteristics of the resource.

Exceptions

java.lang.Exception If the **MQeFields** object cannot be created

Example

```
MQeMQQMgrProxyAdminMsg msg;  
msg = new MQeMQQMgrProxyAdminMsg("MQBridgeV100", "lizzieQM");  
MQeFields proxyChars = msg.characteristics();
```

MQeMQQMgrProxyAdminMsg getMQQMgrProxyName

Syntax

```
public String getMQQMgrProxyName() throws Exception
```

Description

Gets the MQSeries queue manager proxy name from the administration object.

This method also checks the field for validity. It can be issued against an MQeMQQMgrProxyAdminMsg or one of its descendants.

Parameters

none

Return values

none

Exceptions

java.lang.Exception	If the get fails
----------------------------	------------------

Example

```
MQeMQQMgrProxyAdminMsg msg;  
msg = new MQeMQQMgrProxyAdminMsg("MQBridgeV100", "lizzieQM");  
String proxyName = msg.getMQQMgrProxyName();
```

MQeMQQMgrProxyAdminMsg getName

Syntax

```
public String getName()
```

Description

Returns the name of the current administration object. When issued against an object of this class it is identical to getMQQMgrProxyName().

Overrides **getName** in class **MQeMQBridgeAdminMsg**

Parameters

none

Return values

null if the name was not set, a string otherwise.

Exceptions

none

Example

```
MQeMQQMgrProxyAdminMsg msg;  
msg = new MQeMQQMgrProxyAdminMsg("MQBridgeV100", "lizzieQM");  
String proxyName = msg.getName();
```

MQeMQQMgrProxyAdminMsg putMQQMgrProxyName

Syntax

```
public void putMQQMgrProxyName(String mqMgrProxy) throws Exception
```

Description

Puts the MQSeries queue manager proxy name in an MQSeries Everyplace field in the MQSeries Everyplace fields administration message object.

Parameters

MQeMQQMgrProxyAdminMsg

mqQMgrProxy

A String containing the name of the proxy to which the administration message is directed. If set to *null*, or "", it is not set.

Return values

none

Exceptions

java.lang.Exception

If any fields could not be set or if the MQSeries queue manager name is invalid

Example

```
MQeMQQMgrProxyAdminMsg msg = new MQeMQQMgrProxyAdminMsg();
msg.putMQQMgrProxyName("lizzieQM");
```

MQeMQQMgrProxyAdminMsg setName

Syntax

```
public void setName(String bridge,
                    String mqQMgrProxy) throws Exception
```

Description

Puts the bridge name and proxy name into the administration message object.

Parameters

bridge A String containing the name of the bridge to which the administration message is directed. If set to *null*, or "", it is not set.

mqQMgrProxy

A String containing the name of the proxy to which the administration message is directed. If set to *null*, or "", it is not set.

Return values

none

Exceptions

java.lang.Exception

If any fields could not be set or if the MQSeries queue manager name is invalid.

Example

```
MQeMQQMgrProxyAdminMsg msg = new MQeMQQMgrProxyAdminMsg();
msg.setName("MQBridgeV100", "lizzieQM");
```

MQeRunState

A class that holds the "run state" of an administered object, for example whether it's running, stopped, quiescing, or starting.

Package com.ibm.mqe.mqbridge

This class extends **MQeBridgeServices**

Constants and variables

MQeQueueAdminMsg provides the following constants and variables in addition to those supplied by **MQeBridgeServices**:

RUN_STATE_RUNNING

Administered objects have this state when they are active.

```
public static final int RUN_STATE_RUNNING
```

RUN_STATE_STOPPED

Administered objects have this state when they are inactive.

```
public static final int RUN_STATE_STOPPED
```

MQeTransformerInterface

MQeTransformerInterface

All classes that transform MQMessages to MQeMsgObjects, and vice versa, must conform to this interface.

Package com.ibm.mqe.mqbridge

Method summary

Method	Purpose
activate	Tells the class implementing this interface any parameters that may have been supplied with the transformer definition
transform	Converts the given MQMessage into an MQeMsgObject and vice versa.

MQeTransformerInterface activate

Syntax

```
public abstract void activate(StringTokenizer params) throws Exception
```

Description

Tells the class implementing this interface any parameters that may have been supplied with the transformer definition

Parameters

params StringTokenizer containing the transformer definition parameters.

Return values

none

Exceptions

java.lang.Exception If the parameters are not correct, valid, or if there is a problem initializing the transformer.

MQeTransformerInterface transform

Syntax

1.

```
public abstract MQeMsgObject transform(MQMessage msg,  
                                         String remoteQMgrName,  
                                         String remoteQName) throws Exception
```

2.

```
public abstract MQMessage transform(MQeMsgObject msg,  
                                    MQeMQBridgeQueue queue,  
                                    MQPutMessageOptions pmo) throws Exception
```

Description

There are two versions of this method:

1. This version converts the given MQMsg into an MQeMessageObject
2. This version converts the given MQeMsgObject into an MQMessage

Parameters

msg The MQSeries or MQSeries Everyplace message that is to be transformed.

remoteQMgrName

The name of the destination MQSeries Everyplace queue manager (obtained from the remote queue definition on MQSeries).

remoteQName

The name of the destination MQSeries Everyplace queue (obtained from the remote queue definition on MQSeries).

msg

The MQSeries Everyplace message that is to be transformed.

queue

A reference to the bridge queue that accepted the message

remoteQName

The name of the destination MQSeries Everyplace queue (obtained from the remote queue definition on MQSeries).

pmo

A reference to a blank MQPutMessageOptions object that can be modified by the transformer. This parameter enables the user to specify any context options that are needed to put the new MQSeries Everyplace message to MQSeries.

Return values

1. The transformed message in the form of an **MQeMsgObject**
2. The transformed message in the form of an **MQMessage**

Exceptions**java.lang.Exception**

If any of the parameters are invalid, if the message is in a format that this transformer does not understand, or if there is a problem when the transformation is taking place.

Example

Appendix. Notices

This information was developed for products and services offered in the U.S.A. IBM® may not offer the products, services, or features discussed in this document in other countries. Consult your local IBM representative for information on the products and services currently available in your area. Any reference to an IBM product, program, or service is not intended to state or imply that only that IBM product, program, or service may be used. Any functionally equivalent product, program, or service that does not infringe any IBM intellectual property right may be used instead. However, it is the user's responsibility to evaluate and verify the operation of any non-IBM product, program, or service.

IBM may have patents or pending patent applications covering subject matter described in this document. The furnishing of this document does not give you any license to these patents. You can send license inquiries, in writing, to:

IBM Director of Licensing
IBM Corporation
North Castle Drive
Armonk, NY 10504-1785
U.S.A.

The following paragraph does not apply to the United Kingdom or any other country where such provisions are inconsistent with local law:

INTERNATIONAL BUSINESS MACHINES CORPORATION PROVIDES THIS PUBLICATION "AS IS" WITHOUT WARRANTY OF ANY KIND, EITHER EXPRESS OR IMPLIED, INCLUDING, BUT NOT LIMITED TO, THE IMPLIED WARRANTIES OF NON-INFRINGEMENT, MERCHANTABILITY OR FITNESS FOR A PARTICULAR PURPOSE. Some states do not allow disclaimer of express or implied warranties in certain transactions, therefore, this statement may not apply to you.

This information could include technical inaccuracies or typographical errors. Changes are periodically made to the information herein; these changes will be incorporated in new editions of the publication. IBM may make improvements and/or changes in the product(s) and/or the program(s) described in this publication at any time without notice.

Any references in this information to non-IBM Web sites are provided for convenience only and do not in any manner serve as an endorsement of those Web sites. The materials at those Web sites are not part of the materials for this IBM product and use of those Web sites is at your own risk.

IBM may use or distribute any of the information you supply in any way it believes appropriate without incurring any obligation to you.

Licensees of this program who wish to have information about it for the purpose of enabling: (i) the exchange of information between independently created programs and other programs (including this one) and (ii) the mutual use of the information which has been exchanged, should contact:

IBM United Kingdom Laboratories,
Mail Point 151,
Hursley Park,

notices

Winchester,
Hampshire
England
SO21 2JN

Such information may be available, subject to appropriate terms and conditions, including in some cases, payment of a fee.

The licensed program described in this information and all licensed material available for it are provided by IBM under terms of the IBM Customer Agreement, IBM International Program License Agreement, or any equivalent agreement between us.

COPYRIGHT LICENSE:

This information contains sample application programs in source language, which illustrates programming techniques on various operating platforms. You may copy, modify, and distribute these sample programs in any form without payment to IBM, for the purposes of developing, using, marketing or distributing application programs conforming to the application programming interface for the operating platform for which the sample programs are written. These examples have not been thoroughly tested under all conditions. IBM, therefore, cannot guarantee or imply reliability, serviceability, or function of these programs. You may copy, modify, and distribute these sample programs in any form without payment to IBM for the purposes of developing, using, marketing, or distributing application programs conforming to IBM's application programming interfaces.

Trademarks

The following terms are trademarks of International Business machines Corporation in the United States, or other countries, or both.

IBM
MQSeries

Java and all Java-based trademarks and logos are trademarks or registered trademarks of Sun Microsystems, Inc. in the United States and/or other countries.

Windows NT is a registered trademark of Microsoft Corporation in the United States and in the United States and/or other countries other countries.

Other company, product, and service names may be trademarks or service marks of others.

Bibliography

Related publications:

- *MQSeries Everyplace Introduction*, GC34-5843-00
- *MQSeries Everyplace Programming Guide*, SC34-5845-00
- *MQSeries An Introduction to Messaging and Queuing*, GC33-0805-01
- *MQSeries for Windows NT V5R1 Quick Beginnings*, GC34-5389-00

IBM[®]



Printed in the United States of America
on recycled paper containing 10%
recovered post-consumer fiber.

SC34-5846-00

