

MQSeries®



Planning Guide

MQSeries®



Planning Guide

Note!

Before using this information and the product it supports, be sure to read the general information under Appendix, "Notices" on page 267.

Eighth edition (January 1999)

This edition applies to the following products:

- MQSeries for AIX® Version 5.1
- MQSeries for AS/400® Version 4 Release 2.1
- MQSeries for AT&T GIS UNIX® Version 2 Release 2
- MQSeries for Digital OpenVMS AXP Version 2 Release 2
- MQSeries for Digital OpenVMS VAX Version 2 Release 2
- MQSeries for HP-UX Version 5.1
- MQSeries for OS/2® Warp Version 5.1
- MQSeries for OS/390® Version 2 Release 1
- MQSeries for SINIX and DC/OSx Version 2 Release 2
- MQSeries for Sun Solaris Version 5.1
- MQSeries for Tandem NonStop Kernel Version 2 Release 2
- MQSeries for UnixWare Version 1 Release 4.1
- MQSeries for VSE/ESA™ Version 2 Release 1
- MQSeries for Windows NT® Version 5.1
- MQSeries for Windows® Version 2 Release 0
- MQSeries for Windows Version 2 Release 1
- MQSeries link for R/3 for AIX Version 1.2
- MQSeries link for R/3 for AS/400 Version 1.2
- MQSeries link for R/3 for HP-UX Version 1.2
- MQSeries link for R/3 for Sun Solaris Version 1.2
- MQSeries link for R/3 for Windows NT Version 1.2

and to any subsequent releases and modifications until otherwise indicated in new editions.

Order publications through your IBM® representative or the IBM branch office serving your locality. Publications are not stocked at the address given below.

At the back of this publication is a page titled "Sending your comments to IBM". If you want to make comments, but the methods described are not available to you, please address them to:

IBM United Kingdom Laboratories,
Information Development,
Mail Point 095,
Hursley Park,
Winchester,
Hampshire,
England,
SO21 2JN

When you send information to IBM, you grant IBM a nonexclusive right to use or distribute the information in any way it believes appropriate without incurring any obligation to you.

© Copyright International Business Machines Corporation 1993,1999. All rights reserved.

US Government Users Restricted Rights – Use, duplication or disclosure restricted by GSA ADP Schedule Contract with IBM Corp.

Contents

About this book	xiii
Who this book is for	xiii
What you need to know to understand this book	xiii
Terms used in this book	xiii
MQSeries functional levels	xiii
MQSeries publications	xiv
MQSeries cross-platform publications	xiv
MQSeries platform-specific publications	xvii
MQSeries Level 1 product publications	xix
Softcopy books	xix
MQSeries information available on the Internet	xx
 Summary of changes	 xxi
Changes for this edition	xxi
MQSeries for OS/390 V2.1	xxi
MQSeries V5.1	xxii
MQSeries for VSE/ESA V2.1	xxv
MQSeries for AS/400 V4R2M1	xxvi
Changes for the seventh edition	xxvi

Part 1. Introduction to MQSeries 1

Chapter 1. Introduction to IBM MQSeries	3
MQSeries and message queuing	3
Messages and queues	5
MQSeries objects	9
Clients and servers	14
Where to find more information	14
 Chapter 2. Introduction to distributed queuing	 15
How queue managers communicate	15
Setting up distributed queuing	16
Application data conversion	17
Assured delivery	18
Recovering from errors	18
Using MQSeries clusters	19
Where to find more information	20
 Chapter 3. Introduction to MQSeries security	 21
MQSeries level 1 function	22
MQSeries level 2 function	22
Where to find more information	25
 Chapter 4. Introduction to MQSeries recovery concepts	 27
How changes are made to data	27
How consistency is maintained	29
MQSeries as a transaction manager	30
Where to find more information	31

Chapter 5. Introduction to MQSeries administration	33
Introducing commands	33
Formats of command	34
Administration application programs	36
The MQSeries Administration Interface	37
Command summary	38
Where to find more information	43
 Chapter 6. Introduction to MQSeries instrumentation events	 45
Monitoring queue managers	45
What is an instrumentation event?	45
Format of event messages	48
Where to find more information	48
 Chapter 7. Introduction to MQSeries clients and servers	 49
What are MQSeries clients and servers?	49
Communication between clients and servers	50
Installing clients and servers	51
Product support for MQSeries clients	52
Migrating from MQSeries Version 2 products to Version 5	53
Applications on Version 5 clients	53
Where to find more information	53
 Chapter 8. Introduction to the MQSeries Framework	 55
Why the MQSeries Framework?	55
Services and components provided	56
<hr/>	
Part 2. Planning for MQSeries for AS/400	63
 Chapter 9. Introduction to MQSeries for AS/400	 65
Planning for MQSeries	65
Support for R/3 with MQSeries	67
Concurrent use-based pricing and MQSeries	67
Installing and setting up MQSeries	68
 Chapter 10. Backup and recovery planning for MQSeries for AS/400	 69
Journal control with MQSeries	69
 Chapter 11. Security planning for MQSeries for AS/400	 71
Naming differences between OS/400 and MQSeries for AS/400	71
Security planning and MQSeries	71
Security exits with MQSeries	72
 Chapter 12. Administration of MQSeries for AS/400	 73
Managing objects with MQSeries	73
Remote administration with MQSeries	74
Using the MQSeries administration utility	75
 Chapter 13. Storage planning for MQSeries for AS/400	 77
Product storage for MQSeries	77
Journal storage for MQSeries	77
Storage for other data sets used by MQSeries	78
Performance information for MQSeries	78

Part 3. Planning for MQSeries on Digital OpenVMS	79
Chapter 14. Introduction to MQSeries on Digital OpenVMS	81
Planning for MQSeries	81
Migration from MQSeries Version 1	84
Chapter 15. Backup and recovery planning for MQSeries for Digital OpenVMS	85
Logging with MQSeries	85
Recovering from problems with MQSeries	87
Chapter 16. Security planning for MQSeries for Digital OpenVMS	89
Controlling access to resources for MQSeries	89
Security exits with MQSeries	91
Chapter 17. Administration of MQSeries for Digital OpenVMS	93
Managing objects with MQSeries	93
Remote administration with MQSeries	94
Chapter 18. Storage planning for MQSeries for Digital OpenVMS	95
RAM considerations for MQSeries	95
Disk space considerations for MQSeries	95
Sample configuration for MQSeries	97
Capacity planning figures for MQSeries	97
 Part 4. Planning for MQSeries for OS/2 Warp	 99
Chapter 19. Introduction to MQSeries for OS/2 Warp	101
Planning for MQSeries	101
Migration from previous versions of MQSeries	104
Chapter 20. Backup and recovery planning for MQSeries for OS/2 Warp	105
Logging with MQSeries	105
Resource management with MQSeries	107
Recovering from problems with MQSeries	108
Chapter 21. Security planning for MQSeries for OS/2 Warp	109
Setting user IDs with MQSeries	109
Security exits for MQSeries	109
Chapter 22. Administration of MQSeries for OS/2 Warp	111
Managing objects with MQSeries	111
Remote administration with MQSeries	112
Chapter 23. Storage planning for MQSeries for OS/2 Warp	113
RAM considerations for MQSeries	113
Disk space considerations for MQSeries	113
Capacity planning and performance figures for MQSeries	114

Part 5. Planning for MQSeries for OS/390	115
Chapter 24. Introduction to MQSeries for OS/390	117
Planning for MQSeries	117
Installing and customizing MQSeries	121
Migrating from MQSeries for MVS/ESA	122
Chapter 25. Data sets used by MQSeries for OS/390	123
Page sets for MQSeries	123
Log data sets for MQSeries	124
Bootstrap data set for MQSeries	125
What a log contains for MQSeries	125
Checkpoint records for MQSeries	126
Chapter 26. Backup and recovery planning for MQSeries for OS/390	127
Planning your logging environment with MQSeries	127
Planning your archive storage with MQSeries	127
Other recovery considerations with MQSeries	128
General tips for backup and recovery with MQSeries	130
Chapter 27. Security planning for MQSeries for OS/390	133
MQSeries security overview	134
Security exits with MQSeries	135
Things to consider when setting up security	135
Chapter 28. Administration of MQSeries for OS/390	137
Managing objects with MQSeries	137
Remote administration with MQSeries	138
Managing accounting information with MQSeries	139
Using the MQSeries utilities	139
Chapter 29. Storage planning for MQSeries for OS/390	141
MQSeries address space storage	141
Logs and archive storage for MQSeries	142
Storage for page data sets and messages	143
Storage for bootstrap data sets (BSDS)	143
Planning your library storage for MQSeries	143
Further information for MQSeries	143
Chapter 30. Performance of MQSeries for OS/390	145
Impact of logging for MQSeries	145
Causes of I/O to log for MQSeries	148
Buffer pools, page sets, storage classes, and queues for MQSeries	149
Monitoring performance for MQSeries	150
Where to find more information	150
Chapter 31. Measured usage license charges with MQSeries for OS/390	151

Part 6. Planning for MQSeries for Tandem NSK	153
Chapter 32. Introduction to MQSeries on Tandem NSK	155
Planning for MQSeries	155
Migration from MQSeries for Tandem NSK Version 1.5.1	158
Chapter 33. Backup and recovery planning for MQSeries for Tandem NSK	159
Recovery facilities with MQSeries	159
Chapter 34. Security planning for MQSeries for Tandem NSK	161
Controlling access to resources with MQSeries	161
Resources you can protect with MQSeries	162
Using the Object Authority Manager (OAM) commands with MQSeries	163
Security exits with MQSeries	163
Chapter 35. Administration of MQSeries for Tandem NSK	165
Managing objects with MQSeries	165
Remote administration with MQSeries	166
Part 7. Planning for MQSeries on UNIX systems	167
Chapter 36. Introduction to MQSeries on UNIX systems	169
Planning for MQSeries	170
Support for R/3 with MQSeries	173
Migration from MQSeries Version 1	173
Migration from MQSeries Version 2	174
Euro symbol support	174
Chapter 37. Backup and recovery planning for MQSeries on UNIX systems	175
Logging with MQSeries	175
Resource management with MQSeries	177
Recovering from problems with MQSeries	178
High availability with MQSeries	178
Chapter 38. Security planning for MQSeries on UNIX systems	179
Controlling access to resources with MQSeries	179
Security exits with MQSeries	181
Chapter 39. Administration of MQSeries on UNIX systems	183
Managing objects with MQSeries	183
Remote administration with MQSeries	184
Chapter 40. Storage planning for MQSeries on UNIX systems	185
RAM considerations for MQSeries	185
Disk space considerations for MQSeries	185
Capacity planning and performance figures for MQSeries	186

Part 8. Planning for MQSeries for VSE/ESA	187
Chapter 41. Introduction to MQSeries on VSE/ESA	189
Planning for MQSeries	189
Migration from MQSeries Version 1.4	191
Part 9. Planning for MQSeries on Windows NT	193
Chapter 42. Introduction to MQSeries for Windows NT	195
Planning for MQSeries	195
Support for R/3 with MQSeries	198
Migration from previous versions of MQSeries	198
Chapter 43. Backup and recovery planning for MQSeries for Windows NT	201
Logging with MQSeries	201
Resource management with MQSeries	203
Recovering from problems with MQSeries	204
Chapter 44. Security planning for MQSeries for Windows NT	205
User ID support with MQSeries	205
Security exits with MQSeries	206
MQAdmin user ID	206
Chapter 45. Administration of MQSeries for Windows NT	207
Managing objects with MQSeries	207
Remote administration with MQSeries	209
Chapter 46. Storage planning for MQSeries for Windows NT	211
RAM considerations for MQSeries	211
Disk space considerations for MQSeries	211
Capacity planning and performance figures for MQSeries	212
Part 10. Planning for MQSeries for Windows	213
Chapter 47. Introduction to MQSeries for Windows	215
Where to use MQSeries for Windows	216
The features of MQSeries for Windows	218
Comparing queue managers, clients, and servers	219
How MQSeries for Windows differs from the other MQSeries products	219

Part 11. The MQSeries family	223
Chapter 48. MQSeries product summaries	225
Lists of MQSeries products	225
MQSeries interoperability summary	226
MQSeries product functional comparison	228
Chapter 49. MQSeries at a glance	231
MQSeries for AIX	232
MQSeries for AS/400	235
MQSeries for AT&T GIS UNIX	236
MQSeries for Digital OpenVMS	237
MQSeries client for DOS	238
MQSeries for HP-UX	239
MQSeries for OS/2 Warp	241
MQSeries for OS/390	243
MQSeries for SINIX and DC/OSx	245
MQSeries for Sun Solaris	247
MQSeries for Tandem NSK	249
MQSeries for UnixWare	251
MQSeries client for VM/ESA	253
MQSeries for VSE/ESA	254
MQSeries for Windows Version 2.0	255
MQSeries for Windows Version 2.1	257
MQSeries for Windows NT	259
MQSeries client for Windows 3.1	262
MQSeries client for Windows 95 and Windows 98	263
MQSeries link for R/3	264
Part 12. Appendix	265
Appendix. Notices	267
Trademarks	269
Part 13. Glossary and Index	271
Glossary of terms and abbreviations	273
Index	283

Figures

1.	Representation of a message	5
2.	Example of messaging and queuing using MQSeries products	10
3.	A cluster of queue managers	19
4.	MQSeries and the Open Blueprint	21
5.	A unit of recovery within an application	27
6.	Queue manager and database server configuration 1	30
7.	Queue manager and database server configuration 2	30
8.	Queue manager and database server configuration 3	31
9.	The MQSeries Framework	56
10.	Journaling and date messages	70
11.	Impact of logging on response time	146
12.	Impact of dual logging on response time	147
13.	Impact of using 3990 fast write on response time	148
14.	A network of server queue managers and three leaf-node queue managers	217

Tables

1.	MQI calls	3
2.	MQSeries and cooperating products	28
3.	XA-compliant database managers supported by MQSeries	30
4.	Commands for queue manager administration	38
5.	Commands for queue administration	39
6.	Commands for process definition administration	39
7.	Commands for namelist administration	40
8.	Commands for channel administration	40
9.	Commands for cluster administration	41
10.	Commands for security administration	41
11.	Commands for system-dependent function	42
12.	Other control commands in MQSeries for Tandem NonStop Kernel	43
13.	Event queue contents	46
14.	MQSeries for Digital OpenVMS, capacity planning	97
15.	MQSeries on UNIX systems: system administration manuals	169
16.	Comparison of supported features on MQSeries for Windows	219
17.	MQSeries products, Level 1	225
18.	MQSeries products, Level 2	225
19.	Message channels, transmission protocols supported	226
20.	MQI channels, transmission protocols supported by servers	227
21.	MQI channels, transmission protocols supported by clients	227
22.	MQSeries product functional comparison	228
23.	MQSeries products at a glance	231
24.	Suggested hardware configurations for MQSeries for Windows Version 2.0	255
25.	Suggested hardware configurations for MQSeries for Windows Version 2.1	257

About this book

The MQSeries family of products provides application programming services that:

- Enable you to code indirect program-to-program communication using *message queues*.
- Are independent of the platform, for example, OS/390 or OS/400.

This book explains the planning necessary for the incorporation of MQSeries products into your enterprise.

Who this book is for

This book is for:

- Planners of systems that will use MQSeries message-queuing techniques.
- System programmers who have to install and customize MQSeries products for these systems.

What you need to know to understand this book

To understand this book, you should be familiar with the system facilities for the platform on which you are installing the MQSeries product.

If you are unfamiliar with the concepts of messaging and queuing, you should read *MQSeries: An Introduction to Messaging and Queuing*.

Terms used in this book

This book uses the following shortened names:

MQSeries	General term for IBM MQSeries products.
CICS®	General term for CICS and CICS Transaction Server on all platforms.
UNIX systems	General term referring to the following UNIX systems: <ul style="list-style-type: none"> • AIX • AT&T GIS UNIX¹ • HP-UX • SINIX and DC/OSx • Sun Solaris

MQSeries functional levels

MQSeries is provided at two functional levels, referred to in this book as Level 1 and Level 2.

- Level 1 function is provided by the following MQSeries products:
 - MQSeries for UnixWare Version 1.4.1

¹ This platform has become NCR UNIX SVR4 MP-RAS, R3.0

MQSeries publications

- Level 2 function is provided by the following products:
 - MQSeries for AS/400 Version 4.2.1
 - MQSeries for Digital OpenVMS Version 2.2
 - MQSeries for OS/2 Warp Version 5.1
 - MQSeries for OS/390 Version 2.1
 - MQSeries for Tandem NSK Version 2.2
 - MQSeries products on UNIX systems:
 - MQSeries for AIX Version 5.1
 - MQSeries for AT&T GIS UNIX Version 2.2
 - MQSeries for HP-UX Version 5.1
 - MQSeries for SINIX and DC/OSx Version 2.2
 - MQSeries for Sun Solaris Version 5.1
 - MQSeries for VSE/ESA Version 2.1
 - MQSeries for Windows NT Version 5.1

The differences in function are fully documented in “MQSeries product functional comparison” on page 228.

MQSeries publications

This section describes the documentation available for all current MQSeries products.

MQSeries cross-platform publications

Most of these publications, which are sometimes referred to as the MQSeries “family” books, apply to all MQSeries Level 2 products. The latest MQSeries Level 2 products are:

- MQSeries for AIX V5.1
- MQSeries for AS/400 V4R2M1
- MQSeries for AT&T GIS UNIX V2.2
- MQSeries for Digital OpenVMS V2.2
- MQSeries for HP-UX V5.1
- MQSeries for OS/2 Warp V5.1
- MQSeries for OS/390 V2.1
- MQSeries for SINIX and DC/OSx V2.2
- MQSeries for Sun Solaris V5.1
- MQSeries for Tandem NonStop Kernel V2.2
- MQSeries for VSE/ESA V2.1
- MQSeries for Windows V2.0
- MQSeries for Windows V2.1
- MQSeries for Windows NT V5.1

Any exceptions to this general rule are indicated. (Publications that support the MQSeries Level 1 products are listed in “MQSeries Level 1 product publications” on page xix. For a functional comparison of the Level 1 and Level 2 MQSeries products, see Chapter 48, “MQSeries product summaries” on page 225.)

MQSeries Brochure

The *MQSeries Brochure*, G511-1908, gives a brief introduction to the benefits of MQSeries. It is intended to support the purchasing decision, and describes some authentic customer use of MQSeries.

MQSeries: An Introduction to Messaging and Queuing

MQSeries: An Introduction to Messaging and Queuing, GC33-0805, describes briefly what MQSeries is, how it works, and how it can solve some classic interoperability problems. This book is intended for a more technical audience than the *MQSeries Brochure*.

MQSeries Planning Guide

The *MQSeries Planning Guide*, GC33-1349, describes some key MQSeries concepts, identifies items that need to be considered before MQSeries is installed, including storage requirements, backup and recovery, security, and migration from earlier releases, and specifies hardware and software requirements for every MQSeries platform.

MQSeries Intercommunication

The *MQSeries Intercommunication* book, SC33-1872, defines the concepts of distributed queuing and explains how to set up a distributed queuing network in a variety of MQSeries environments. In particular, it demonstrates how to (1) configure communications to and from a representative sample of MQSeries products, (2) create required MQSeries objects, and (3) create and configure MQSeries channels. The use of channel exits is also described.

MQSeries Clients

The *MQSeries Clients* book, GC33-1632, describes how to install, configure, use, and manage MQSeries client systems.

MQSeries System Administration

The *MQSeries System Administration* book, SC33-1873, supports day-to-day management of local and remote MQSeries objects. It includes topics such as security, recovery and restart, transactional support, problem determination, and the dead-letter queue handler. It also includes the syntax of the MQSeries control commands.

This book applies to the following MQSeries products only:

- MQSeries for AIX V5.1
- MQSeries for HP-UX V5.1
- MQSeries for OS/2 Warp V5.1
- MQSeries for Sun Solaris V5.1
- MQSeries for Windows NT V5.1

MQSeries Command Reference

The *MQSeries Command Reference*, SC33-1369, contains the syntax of the MQSC commands, which are used by MQSeries system operators and administrators to manage MQSeries objects.

MQSeries Programmable System Management

The *MQSeries Programmable System Management* book, SC33-1482, provides both reference and guidance information for users of MQSeries events, Programmable Command Format (PCF) messages, and installable services.

MQSeries Messages

The *MQSeries Messages* book, GC33-1876, which describes “AMQ” messages issued by MQSeries, applies to these MQSeries products only:

- MQSeries for AIX V5.1
- MQSeries for HP-UX V5.1
- MQSeries for OS/2 Warp V5.1
- MQSeries for Sun Solaris V5.1
- MQSeries for Windows NT V5.1

- MQSeries for Windows V2.0
- MQSeries for Windows V2.1

This book is available in softcopy only.

MQSeries Application Programming Guide

The *MQSeries Application Programming Guide*, SC33-0807, provides guidance information for users of the message queue interface (MQI). It describes how to design, write, and build an MQSeries application. It also includes full descriptions of the sample programs supplied with MQSeries.

MQSeries Application Programming Reference

The *MQSeries Application Programming Reference*, SC33-1673, provides comprehensive reference information for users of the MQI. It includes: data-type descriptions; MQI call syntax; attributes of MQSeries objects; return codes; constants; and code-page conversion tables.

MQSeries Application Programming Reference Summary

The *MQSeries Application Programming Reference Summary*, SX33-6095, summarizes the information in the *MQSeries Application Programming Reference* manual.

MQSeries Using C++

MQSeries Using C++, SC33-1877, provides both guidance and reference information for users of the MQSeries C++ programming-language binding to the MQI. MQSeries C++ is supported by these MQSeries products:

- MQSeries for AIX V5.1
- MQSeries for AS/400 V4R2M1
- MQSeries for HP-UX V5.1
- MQSeries for OS/2 Warp V5.1
- MQSeries for OS/390 V2.1
- MQSeries for Sun Solaris V5.1
- MQSeries for Windows NT V5.1

MQSeries C++ is also supported by MQSeries clients supplied with these products and installed in the following environments:

- AIX
- HP-UX
- OS/2
- Sun Solaris
- Windows NT
- Windows 3.1
- Windows 95 and Windows 98

MQSeries Using Java®

MQSeries Using Java, SC34-5456, provides both guidance and reference information for users of the MQSeries Bindings for Java and the MQSeries Client for Java. MQSeries Java is supported by these MQSeries products:

- MQSeries for AIX V5.1
- MQSeries for HP-UX V5.1
- MQSeries for OS/2 Warp V5.1
- MQSeries for Sun Solaris V5.1
- MQSeries for Windows NT V5.1

MQSeries Administration Interface Programming Guide and Reference

The *MQSeries Administration Interface Programming Guide and Reference*, SC34-5390, provides information for users of the MQAI. The MQAI is a

programming interface that simplifies the way in which applications manipulate Programmable Command Format (PCF) messages and their associated data structures.

This book applies to the following MQSeries products only:

- MQSeries for AIX V5.1
- MQSeries for HP-UX V5.1
- MQSeries for OS/2 Warp V5.1
- MQSeries for Sun Solaris V5.1
- MQSeries for Windows NT V5.1

MQSeries Queue Manager Clusters

MQSeries Queue Manager Clusters, SC34-5349, describes MQSeries clustering. It explains the concepts and terminology and shows how you can benefit by taking advantage of clustering. It details changes to the MQI, and summarizes the syntax of new and changed MQSeries commands. It shows a number of examples of tasks you can perform to set up and maintain clusters of queue managers.

This book applies to the following MQSeries products only:

- MQSeries for AIX V5.1
- MQSeries for HP-UX V5.1
- MQSeries for OS/2 Warp V5.1
- MQSeries for OS/390 V2.1
- MQSeries for Sun Solaris V5.1
- MQSeries for Windows NT V5.1

MQSeries platform-specific publications

Each MQSeries product is documented in at least one platform-specific publication, in addition to the MQSeries family books.

MQSeries for AIX

MQSeries for AIX Version 5 Release 1 Quick Beginnings, GC33-1867

MQSeries for AS/400

MQSeries for AS/400 Version 4 Release 2.1 Administration Guide, GC33-1956
MQSeries for AS/400 Version 4 Release 2 Application Programming Reference (RPG), SC33-1957

MQSeries for AT&T GIS UNIX

MQSeries for AT&T GIS UNIX Version 2 Release 2 System Management Guide, SC33-1642

MQSeries for Digital OpenVMS

MQSeries for Digital OpenVMS Version 2 Release 2 System Management Guide, GC33-1791

MQSeries for Digital UNIX

MQSeries for Digital UNIX Version 2 Release 2.1 System Management Guide, GC34-5483

MQSeries for HP-UX

MQSeries for HP-UX Version 5 Release 1 Quick Beginnings, GC33-1869

MQSeries for OS/2 Warp

MQSeries for OS/2 Warp Version 5 Release 1 Quick Beginnings, GC33-1868

MQSeries for OS/390

MQSeries for OS/390 Version 2 Release 1 Licensed Program Specifications, GC34-5377

MQSeries for OS/390 Version 2 Release 1 Program Directory

MQSeries for OS/390 Version 2 Release 1 System Management Guide, SC34-5374

MQSeries for OS/390 Version 2 Release 1 Messages and Codes, GC34-5375

MQSeries for OS/390 Version 2 Release 1 Problem Determination Guide, GC34-5376

MQSeries link for R/3

MQSeries link for R/3 Version 1 Release 2 User's Guide, GC33-1934

MQSeries for SINIX and DC/OSx

MQSeries for SINIX and DC/OSx Version 2 Release 2 System Management Guide, GC33-1768

MQSeries for Sun Solaris

MQSeries for Sun Solaris Version 5 Release 1 Quick Beginnings, GC33-1870

MQSeries for Tandem NonStop Kernel

MQSeries for Tandem NonStop Kernel Version 2 Release 2 System Management Guide, GC33-1893

MQSeries for VSE/ESA

MQSeries for VSE/ESA Version 2 Release 1 Licensed Program Specifications, GC34-5365

MQSeries for VSE/ESA Version 2 Release 1 System Management Guide, GC34-5364

MQSeries for Windows

MQSeries for Windows Version 2 Release 0 User's Guide, GC33-1822

MQSeries for Windows Version 2 Release 1 User's Guide, GC33-1965

MQSeries for Windows NT

MQSeries for Windows NT Version 5 Release 1 Quick Beginnings, GC34-5389

MQSeries for Windows NT Using the Component Object Model Interface, SC34-5387

MQSeries LotusScript Extension, SC34-5404

MQSeries Level 1 product publications

For information about the MQSeries Level 1 products, see the following publications:

MQSeries: Concepts and Architecture, GC33-1141

MQSeries Version 1 Products for UNIX Operating Systems Messages and Codes, SC33-1754

MQSeries for UnixWare Version 1 Release 4.1 User's Guide, SC33-1379

Softcopy books

Most of the MQSeries books are supplied in both hardcopy and softcopy formats.

BookManager format

The MQSeries library is supplied in IBM BookManager® format on a variety of online library collection kits, including the *Transaction Processing and Data* collection kit, SK2T-0730. You can view the softcopy books in IBM BookManager format using the following IBM licensed programs:

BookManager READ/2
 BookManager READ/6000
 BookManager READ/DOS
 BookManager READ/MVS
 BookManager READ/VM
 BookManager READ for Windows

HTML format

Relevant MQSeries documentation is provided in HTML format with these MQSeries products:

- MQSeries for AIX V5.1
- MQSeries for HP-UX V5.1
- MQSeries for OS/2 Warp V5.1
- MQSeries for Sun Solaris V5.1
- MQSeries for Windows NT V5.1 (compiled HTML)
- MQSeries link for R/3 V1.2

The MQSeries books are also available in HTML format from the MQSeries product family Web site at:

<http://www.software.ibm.com/ts/mqseries/>

Portable Document Format (PDF)

PDF files can be viewed and printed using the Adobe Acrobat Reader.

If you need to obtain the Adobe Acrobat Reader, or would like up-to-date information about the platforms on which the Acrobat Reader is supported, visit the Adobe Systems Inc. Web site at:

<http://www.adobe.com/>

PDF versions of relevant MQSeries books are supplied with these MQSeries products:

- MQSeries for AIX V5.1
- MQSeries for HP-UX V5.1
- MQSeries for OS/2 Warp V5.1

MQSeries on the Internet

- MQSeries for Sun Solaris V5.1
- MQSeries for Windows NT V5.1
- MQSeries link for R/3 V1.2

PDF versions of all current MQSeries books are also available from the MQSeries product family Web site at:

<http://www.software.ibm.com/ts/mqseries/>

PostScript format

The MQSeries library is provided in PostScript (.PS) format with many MQSeries Version 2 products. Books in PostScript format can be printed on a PostScript printer or viewed with a suitable viewer.

Windows Help format

The *MQSeries for Windows User's Guide* is provided in Windows Help format with MQSeries for Windows Version 2.0 and MQSeries for Windows Version 2.1.

MQSeries information available on the Internet

MQSeries Web site

The MQSeries product family Web site is at:

<http://www.software.ibm.com/ts/mqseries/>

By following links from this Web site you can:

- Obtain latest information about the MQSeries product family.
- Access the MQSeries books in HTML and PDF formats.
- Download MQSeries SupportPacs.

Summary of changes

This section lists the changes that have been made to this book since previous editions. Changes for this edition are marked with vertical bars in the left-hand margin.

Changes for this edition

This edition of *MQSeries Planning Guide* applies to these new versions and releases of MQSeries products:

- MQSeries for AIX V5.1
- MQSeries for AS/400 V4R2M1
- MQSeries for HP-UX V5.1
- MQSeries for OS/2 Warp V5.1
- MQSeries for OS/390 V2.1
- MQSeries for Sun Solaris V5.1
- MQSeries for VSE/ESA V2.1
- MQSeries for Windows NT V5.1

Major new function supplied with each of these MQSeries products is summarized here.

MQSeries for OS/390 V2.1

MQSeries for OS/390 V2.1 is a new product for the OS/390 platform that offers functional enhancements over MQSeries for MVS/ESA™ V1.2. Those functional enhancements specific to MQSeries for OS/390 are summarized here. As a general rule, other function described in this book as supported by MQSeries for OS/390 is also supported by MQSeries for MVS/ESA V1.2.

MQSeries queue manager clusters

MQSeries queue managers can be connected to form a *cluster* of queue managers. Within a cluster, queue managers can make the queues they host available to every other queue manager. Any queue manager can send a message to any other queue manager in the same cluster without the need for explicit channel definitions, remote queue definitions, or transmission queues for each destination. The main benefits of MQSeries clusters are:

- Fewer system administration tasks
- Increased availability
- Workload balancing

Clusters are supported by these MQSeries products:

- MQSeries for AIX V5.1
- MQSeries for HP-UX V5.1
- MQSeries for OS/2 Warp V5.1
- MQSeries for OS/390 V2.1
- MQSeries for Sun Solaris V5.1
- MQSeries for Windows NT V5.1

See the book *MQSeries Queue Manager Clusters*, SC34-5349, for a complete description of this function.

OS/390 Automatic Restart Manager (ARM)

If an MQSeries queue manager or channel initiator fails, the OS/390 Automatic Restart Manager (ARM) can restart it automatically on the same OS/390 image. If the OS/390 image itself fails, ARM can restart that image's subsystems and applications automatically on another OS/390 image in the sysplex, provided that the LU 6.2 communication protocol is being used. By removing the need for operator intervention, OS/390 ARM improves the availability of your MQSeries subsystems.

OS/390 Resource Recovery Services (RRS)

MQSeries Batch and TSO applications can participate in two-phase commit protocols with other RRS-enabled products, such as DB2®, coordinated by the OS/390 RRS facility.

MQSeries Workflow

MQSeries Workflow allows applications on various network clients to perform business functions through System/390® by driving one or more CICS, IMS™, or MQSeries applications. This is achieved through format, rule, and table definition, rather than through application programming.

Support for C++

MQSeries for OS/390 V2.1 applications can be written in C++.

Euro support

MQSeries supports new and changed code pages that use the euro currency symbol. Details of code pages that include the euro symbol are provided in the *MQSeries Application Programming Reference* book.

MQSeries V5.1

The MQSeries Version 5 Release 1 products are:

- MQSeries for AIX V5.1
- MQSeries for HP-UX V5.1
- MQSeries for OS/2 Warp V5.1
- MQSeries for Sun Solaris V5.1
- MQSeries for Windows NT V5.1

The following new function is provided in all of the V5.1 products:

MQSeries queue manager clusters

MQSeries queue managers can be connected to form a *cluster* of queue managers. Within a cluster, queue managers can make the queues they host available to every other queue manager. Any queue manager can send a message to any other queue manager in the same cluster without the need for explicit channel definitions, remote queue definitions, or transmission queues for each destination. The main benefits of MQSeries clusters are:

- Fewer system administration tasks
- Increased availability
- Workload balancing

Clusters are supported by these MQSeries products:

- MQSeries for AIX V5.1
- MQSeries for HP-UX V5.1
- MQSeries for OS/2 Warp V5.1
- MQSeries for OS/390 V2.1
- MQSeries for Sun Solaris V5.1

- MQSeries for Windows NT V5.1

See the book *MQSeries Queue Manager Clusters*, SC34-5349, for a complete description of this function.

MQSeries Administration Interface (MQAI)

The MQSeries Administration Interface is an MQSeries programming interface that simplifies manipulation of MQSeries PCF messages for administrative tasks. It is described in a new book, *MQSeries Administration Interface Programming Guide and Reference*, SC34-5390.

Support for Windows 98 clients

A Windows 98 client can connect to any MQSeries V5.1 server.

Message queue size

A message queue can be up to 2 GB.

Controlled, synchronous shutdown of a queue manager

A new option has been added to the **endmqm** command to allow controlled, synchronous shutdown of a queue manager.

Java support

The MQSeries Client for Java and MQSeries Bindings for Java are provided with all MQSeries V5.1 products. The client, bindings, and common files have been packaged into .jar files for ease of installation.

Euro support

MQSeries supports new and changed code pages that use the euro currency symbol. Details of code pages that include the euro symbol are provided in the *MQSeries Application Programming Reference* book.

Conversion of the EBCDIC new-line character

You can control the conversion of EBCDIC new-line characters to ensure that data transmitted from EBCDIC systems to ASCII systems and back to EBCDIC is unaltered by the ASCII conversion.

Client connections via MQCONN

A client application can specify the definition of the client-connection channel at run time in the MQCNO structure of the MQCONN call.

Additional new function in MQSeries for AIX V5.1

- The UDP transport protocol is supported.
- Sybase databases can participate in global units of work.
- Multithreaded channels are supported.

Additional new function in MQSeries for HP-UX V5.1

- MQSeries for HP-UX V5.1 runs on both HP-UX V10.20 and HP-UX V11.0.
- Multithreaded channels are supported.
- Both HP-UX kernel threads and DCE threads are supported.

Additional new function in MQSeries for OS/2 Warp V5.1

OS/2 high memory support is provided.

Additional new function in MQSeries for Sun Solaris V5.1

- MQSeries for Sun Solaris V5.1 runs on both Sun Solaris V2.6 and Sun Solaris 7.
- Sybase databases can participate in global units of work.
- Multithreaded channels are supported.

Additional new function in MQSeries for Windows NT V5.1

MQSeries for Windows NT V5.1 is part of the IBM Enterprise Suite for Windows NT. New function in this release includes:

- Close integration with Microsoft® Windows NT Version 4.0, including exploitation of extra function provided by additional Microsoft offerings. The main highlights are:
 - Graphical tools and applications for managing, controlling, and exploring MQSeries:
 - MQSeries Explorer—a snap-in for the Microsoft management console (MMC) that allows you to query, change, and create the local, remote, and cluster objects across an MQSeries network.
 - MQSeries Services—an MMC snap-in that controls the operation of MQSeries components, either locally or remotely within the Windows NT domain. It monitors the operation of MQSeries servers and provides extensive error detection and recovery functions.
 - MQSeries API Exerciser—a graphical application for exploring the messaging and queuing programming functions that MQSeries provides. It can also be used in conjunction with the MQSeries Explorer to gain a deeper understanding of the effects of MQSeries operations on objects and messages.
 - MQSeries Postcard—a sample application that can be used to verify an MQSeries installation, for either local or remote messaging.
 - Support for the following features of Windows NT has been added:
 - Windows NT performance monitor—used to access and display MQSeries information, such as the current depth of a queue and the rate at which message data is put onto and taken off queues.
 - ActiveDirectory—programmable access to MQSeries objects is available through the Active Directory Service Interfaces (ADSI).
 - Windows NT user IDs—previous MQSeries restrictions on the validity of Windows NT user IDs have been removed. All valid Windows NT user IDs are now valid identifiers for MQSeries operations. MQSeries uses the associated Windows NT Security Identifier (SID) and the Security Account Manager (SAM). The SID allows the MQSeries Object Authority Manager (OAM) to identify the specific user for an authorization request.
 - Windows NT registry—now used to hold all configuration and related data. The contents of any configuration (.INI) files from previous MQSeries installations of MQSeries for Windows NT products are migrated into the registry; the .INI files are then deleted.

- A set of Component Object Model (COM) classes, which allow ActiveX applications to access the MQSeries Message Queue Interface (MQI) and the MQSeries Administration Interface (MQAI).
- An online Quick Tour of the product concepts and functions.
- An online Information Center that gives you quick access to task help information, reference information, and Web-based online books and home pages.
- Simplified installation of MQSeries for Windows NT, with default options and automatic configuration.
- Support for web-based administration of an MQSeries network, which provides a simplified way of using the MQSC commands and scripts and allows you to create powerful macros for standard administration tasks.
- Support for MQSeries LotusScript Extension (MQLSX), which allows Lotus® Notes® applications that are written in LotusScript to communicate with applications that run in non-Notes environments.
- Support for Microsoft Visual Basic for Windows Version 5.0.
- Performance improvements over the MQSeries for Windows NT Version 5.0 product.
- Information and examples on how MQSeries applications can interface with and exploit the lightweight directory access protocol (LDAP) directories.
- Support for Sybase participation in global units of work.

MQSeries for VSE/ESA V2.1

MQSeries for VSE/ESA joins the MQSeries Level 2 products. New function in Version 2 Release 1 of MQSeries for VSE/ESA includes:

- Transmission Control Protocol/Internet Protocol (TCP/IP) is supported.
- MQSeries clients can connect to the MQSeries for VSE/ESA server via the TCP/IP protocol. (Note, however, that there is no MQSeries for VSE/ESA client.)
- Messages may be up to 4 MB in size.
- A user-selected, coded character set ID (CCSID) can be specified for all messages written locally.
- Messages sent to remote, non-VSE/ESA systems can be flagged as nonpersistent.
- Confirmation-on-delivery (COD) and confirmation-on-arrival (COA) messages are supported.
- A message priority, in the range 0 through 9, can be specified on MQPUT and MQPUT1 calls.
- Automated reorganization of queue storage is supported.
- Messages can be sent and received in batches of a user-specified size.
- Support has been added for the C and PL/I application-programming languages. Copy books, macros, and include files are provided for each language.

Summary of changes

- Messages can be retrieved from queues by message identifier (*MsgID*) and correlation identifier (*CorrelId*).
- Message Channel Agents (MCAs) record more diagnostic information in the SYSTEM.LOG when communications failures occur.

MQSeries for AS/400 V4R2M1

New function in MQSeries for AS/400 V4R2M1 includes:

- Support for the MQSeries dead-letter queue handler
- Improvements to installation and migration procedures

Changes for the seventh edition

Changes for edition number GC33-1349-06 include:

- The book has been updated to contain information about the following new functions of the MQSeries for AS/400 Version 4 Release 2 product:
 - Distribution lists
 - Message segmentation
 - Fast channels for nonpersistent messages
 - Auto-definition of server-connection and receiver channels
 - Reference messages
 - C++ programming
- The book has been updated to contain revised information about MQSeries for Digital OpenVMS, Version 2 Release 2.
- The book has been updated to contain information about MQSeries for Tandem NSK, Version 2 Release 2.
- The book has been updated to contain information about the MQSeries client for VM/ESA®, Version 2 Release 3.

Part 1. Introduction to MQSeries

Chapter 1. Introduction to IBM MQSeries	3
MQSeries and message queuing	3
MQI – a common application programming interface	3
Time-independent applications	4
Message-driven processing	4
Data integrity and resource protection	4
Messages and queues	5
What is a message	5
What is a queue	5
Message attributes	6
Some queues used with MQSeries	7
MQSeries objects	9
Queue managers	10
Queues	11
Namelists	12
Distribution lists	12
Process definitions	13
Channels	13
Storage classes	14
Clients and servers	14
Where to find more information	14
 Chapter 2. Introduction to distributed queuing	15
How queue managers communicate	15
Channel speed	16
Setting up distributed queuing	16
Application data conversion	17
Assured delivery	18
Recovering from errors	18
Using MQSeries clusters	19
How can I use MQSeries clusters	20
Where to find more information	20
 Chapter 3. Introduction to MQSeries security	21
MQSeries level 1 function	22
MQSeries level 2 function	22
MQSeries applications	22
MQSeries messages	24
Point-to-point security	24
End-to-end security	25
Where to find more information	25
 Chapter 4. Introduction to MQSeries recovery concepts	27
How changes are made to data	27
Units of recovery	27
How consistency is maintained	29
MQSeries as a transaction manager	30
Where to find more information	31

Chapter 5. Introduction to MQSeries administration	33
Introducing commands	33
Formats of command	34
MQSC commands	34
Programmable Command Format commands	34
Command queues	35
Administration application programs	36
MQSeries product administration facilities	36
The MQSeries Administration Interface	37
Command summary	38
Where to find more information	43
 Chapter 6. Introduction to MQSeries instrumentation events	45
Monitoring queue managers	45
What is an instrumentation event?	45
What types of event are there?	46
Event notification through event queues	46
Enabling and disabling events	47
Format of event messages	48
Where to find more information	48
 Chapter 7. Introduction to MQSeries clients and servers	49
What are MQSeries clients and servers?	49
Communication between clients and servers	50
Installing clients and servers	51
MQSeries clients from IBM Transaction Processing SupportPacs	51
National language considerations for clients	51
Data conversion considerations for clients	51
Product support for MQSeries clients	52
MQSeries clients on other platforms	53
Migrating from MQSeries Version 2 products to Version 5	53
Applications on Version 5 clients	53
Where to find more information	53
 Chapter 8. Introduction to the MQSeries Framework	55
Why the MQSeries Framework?	55
Invoking MQSeries Framework components	56
Services and components provided	56
Trigger monitor interface (TMI)	56
Message channel interface (MCI)	57
Name service interface (NSI)	57
Security enabling interface (SEI)	58
Data conversion interface (DCI)	60

Chapter 1. Introduction to IBM MQSeries

This chapter introduces IBM MQSeries and describes its relationship with other products. It contains basic explanations of the following topics:

- “MQSeries and message queuing”
- “Messages and queues” on page 5
- “MQSeries objects” on page 9
- “Clients and servers” on page 14
- “Where to find more information” on page 14

For more detailed explanations of these topics, refer to Chapter 1, “Introduction to message queuing” in the *MQSeries Application Programming Guide*.

MQSeries and message queuing

MQSeries products enable applications to use message queuing to participate in *message-driven processing*. With message-driven processing, applications can communicate with each other on the same or different platforms, by using the appropriate message queuing software products. For example, OS/390 and OS/400® applications can communicate through MQSeries for OS/390 and MQSeries for AS/400 respectively. With MQSeries products, all applications use the same kind of messages; communications protocols are hidden from the applications.

MQI – a common application programming interface

MQSeries products implement a common application programming interface, the *message queue interface* (MQI), that is used on whatever platform the applications run on. The calls made by the applications and the messages they exchange are common. This makes it much easier to write and maintain applications than using traditional methods. It also facilitates the migration of message queuing applications from one platform to another.

The MQI calls are shown in the following table.

Table 1 (Page 1 of 2). MQI calls		
Call name	Description	Platforms
MQBEGIN	Begin a unit of work to be coordinated by the queue manager	AIX, HP-UX, OS/2 Warp, Sun Solaris, and Windows NT
MQCONN	Connect to a queue manager	All platforms
MQCONNX	Connect to a queue manager and specify some options	AIX, HP-UX, OS/2 Warp, Sun Solaris, and Windows NT
MQDISC	Disconnect from a queue manager	All platforms
MQOPEN	Open an object	All platforms
MQCLOSE	Close an object	All platforms
MQPUT	Put a message (queue already open)	All platforms

Table 1 (Page 2 of 2). MQI calls		
Call name	Description	Platforms
MQPUT1	Put one message	All platforms
MQGET	Get a message	All platforms
MQCMIT	Commit changes	OS/2 Warp, OS/390, Windows NT, and UNIX systems
MQBACK	Back out changes	OS/2 Warp, OS/390, Windows NT, and UNIX systems
MQINQ	Inquire about object attributes	All platforms
MQSET	Set object attributes	All platforms

Time-independent applications

With message queuing, the exchange of messages between the sending and receiving programs is time independent. This means that the sending and receiving applications are decoupled so that the sender can continue processing without having to wait for the receiver to acknowledge the receipt of the message. The receiving application might be busy when the message is sent. Indeed, the receiving application doesn't even need to be running. MQSeries holds the message in the queue until it can be processed.

Message-driven processing

Message-driven processing is a style of application design.

With this style, the application is divided into a number of separate, discrete, functional blocks, with each block having well-defined input and output parameters. Each functional block is coded as an application program, with its input and output parameters being interchanged between other application programs by placing their values in messages, which are then put on queues.

By use of the appropriate MQSeries programming mechanisms, an application program can start executing as a result of one or more messages arriving on a queue. If required, the program can terminate when all the messages in a queue have been processed.

This style of application design allows new applications to be built, or existing applications to be modified, more quickly than with some other application design styles.

Data integrity and resource protection

MQSeries applications can transfer data with an extremely high degree of confidence. Message delivery can be implemented using a syncpoint mechanism—and the MQSeries logs or journals—for the recovery of important data in the event of system failure. See Chapter 4, "Introduction to MQSeries recovery concepts" on page 27.

All resources, such as message queues, can be protected using the security facilities available on the operating platform. For example, Resource Access Control Facility (RACF) on OS/390, or the security facilities provided by OS/400.

Messages and queues

Messages and queues are basic to any queuing system.

What is a message

A *message* is a string of bytes that has meaning to the applications that use the message.

In MQSeries, messages have two parts, a *message descriptor* and *application data*. The content and structure of the application data are defined by the application programs that use them. The message descriptor identifies the message and contains other control information or attributes, such as the date and time the message was created, the type of message, and the priority assigned to the message by the sending application.

Figure 1 represents a message and shows how the message is logically divided into message data and application data.




Figure 1. Representation of a message. The message descriptor and application data are shown as separate parts. Information that is specific to the application, such as Account name in this example, is in the application data part of the message.

What is a queue

In physical terms, a *queue* is a type of list that is used to store messages until they are retrieved by an application.

Queues exist independently of the applications that use them. A queue can exist:

- In main storage if it is temporary
- On disk or similar auxiliary storage if it must be kept in case of recovery
- In both places if it is currently being used, and must also be kept for recovery

Each queue belongs to a *queue manager*, which is responsible for maintaining it. The queue manager puts the messages it receives onto the appropriate queue.

Queues can exist either in your local system, in which case they are called *local queues*, or at another queue manager, in which case they are called *remote queues*.

In MQSeries, messages can be retrieved from a queue by suitably authorized applications according to these retrieval algorithms:

- First-in-first-out (FIFO).
- Message priority, as defined in the message descriptor. Messages having the same priority are retrieved on a FIFO basis.

- A program request for a specific message.

For more information about queues and their attributes, refer to Chapter 4, “MQSeries objects” in the *MQSeries Application Programming Guide*.

Message attributes

For system administrators, messages have two important attributes that are defined in the message descriptor: *persistence* and *priority*.

A message is termed persistent if it survives when MQSeries restarts. This implies that the message must be logged, or saved, and can be reinstated as part of the recovery procedure.

Each MQSeries message has a priority assigned to it by the sending application. The priority, which is a number in the range 0 through 9, can affect the order in which a message is retrieved from a queue, and also the way that *trigger events* are generated.

Triggering is a facility in some MQSeries products. It allows an application to be started automatically when predefined conditions on a queue are met. These conditions include reception of any message or of messages over a particular priority, the number of messages on a queue, and so on. For more information about triggering, see Chapter 14, “Starting MQSeries applications using triggers” in the *MQSeries Application Programming Guide*.

Message sizes

The maximum message size supported by MQSeries varies. Section “MQSeries product functional comparison” on page 228 gives details of the size of message supported by each of the MQSeries products.

In practice, the size of message that an application program can put on a queue is limited by:

- The maximum message length defined for the receiving queue
- The maximum message length defined for the queue manager
- The maximum message length supported by the platform

If the size of the data that an application program requires to place on a queue exceeds this limit, the program must split the data into a number of pieces, and put each piece on the queue as a separate message.

Dealing with large messages

On some platforms, there are several methods available for dealing with very large messages.

Maximum message length

On AIX, HP-UX, OS/2 Warp, Sun Solaris, and Windows NT, you can use the maximum message length attribute to set the maximum length allowed for messages on a queue manager; this can be up to 100 MB. The maximum message length used for communication between two queue managers is the lower of the maximum length for each queue manager, so you can use 100 MB messages only if both queue managers support this. The maximum size for queues on these platforms is 2 GB.

Message segmentation

On AIX, HP-UX, OS/2 Warp, OS/400, Sun Solaris, and Windows NT, MQSeries allows you to divide large messages into several parts (that is, one logical message into several physical messages). Your application can define the size of physical messages, to allow for the maximum message size permitted at intermediate queue managers. MQSeries can start transmitting or receiving the physical messages before the whole of the logical message has arrived on the queue.

Reference messages

On AIX, HP-UX, OS/2 Warp, OS/400, Sun Solaris, and Windows NT, reference messages allow you to transfer a large data object from one queue manager to another without storing the object on a queue at either the source or destination node. A message exit program is used to add the data object to the message when it is transmitted. At the receiving end, another message exit program is used to create a data object from the data in the message. The reference message, without the data, is then put on the destination queue. Sample exit programs that do this are provided with MQSeries.

Some queues used with MQSeries

MQSeries uses the following types of queues.

Message queues

A *message queue* is a queue that is used to receive messages from applications as distinct from those queues that have a special purpose. Special purpose queues are defined in the same way as message queues, although they can have their attributes set in specific ways. The system administrator is the person responsible for defining and maintaining all queues in your enterprise.

Event queues

An *event queue* is a queue that is used to receive *event messages*, which indicate that a particular type of instrumentation event has occurred during the execution of an application program. Instrumentation events help you to monitor your system. There are three system administration event queues, one for each of the three categories of instrumentation event that can be generated:

- SYSTEM.ADMIN.QMGR.EVENT - for queue manager events
- SYSTEM.ADMIN.PERFM.EVENT - for performance events
- SYSTEM.ADMIN.CHANNEL.EVENT - for channel events

When an event is generated, it is put on one of these queues.

Initiation queues

An *initiation queue* receives *trigger messages*, which indicate that a trigger event has occurred. A trigger event is caused by a message that satisfies the specified conditions being put onto a queue. Messages are read from the initiation queue by a trigger monitor application which then starts the appropriate application to process the message. If triggers are active, at least one initiation queue must be defined for each queue manager.

Transmission queues

A *transmission queue* temporarily stores messages that are destined for a remote queue manager. You must define a transmission queue for each remote queue manager to which the local queue manager is to send messages. It is possible to associate several transmission queues with different characteristics with a remote queue manager. This allows different classes of transmission service.

Reply-to queues

If a message is a request message and so requires a reply, the sender of the message must specify the name of the queue to which the reply should be sent; this is called the *reply-to queue*. It is also the queue to which report messages are usually sent, if any are generated.

Dead-letter queues

A *dead-letter queue* (also known as an *undelivered-message queue*) receives messages that cannot be routed to their correct destinations. This occurs when, for example:

- The destination queue is full
- The message cannot be put on the destination queue
- The sender is not authorized to use the destination queue
- The destination queue does not exist

If you do not have a dead-letter queue, undelivered messages will remain on the transmission queue and the *message channel* will be stopped. You are therefore recommended to define a dead-letter queue for each queue manager in your system.

You also have to decide how to handle any message placed on a dead-letter queue. Such handling might be by the system administrator examining the queue and redirecting the message, or perhaps by an application which you create for the purpose of monitoring and handling dead-letter queues.

A dead-letter queue handler is provided with some MQSeries products to assist the system administrator with the task of dealing with messages placed on a dead-letter queue.

Command queues

A *command queue* is a queue owned by a queue manager to which suitably authorized applications can send messages containing MQSeries administration commands. The commands in these messages are processed by the *command server* part of the queue manager.

You can find more information on command queues in Chapter 5, "Introduction to MQSeries administration" on page 33.

Cluster queues

You can group queue managers together to form a cluster. The following queues are required to support clustering:

- A local queue is needed to hold a persistent copy of the repository. (The repository is a collection of information about the queue managers that are members of the cluster, held on some of the queue managers in the cluster and replicated on the other queue managers.) This queue is called `SYSTEM.CLUSTER.REPOSITORY.QUEUE`.

- A local queue is needed to communicate repository changes between queue managers. This queue is used for information about updates to the repository data to be applied to the local repository, or requests for repository data. This queue is called `SYSTEM.CLUSTER.COMMAND.QUEUE`.
- A local queue is needed as the transmission queue for all destinations in the cluster. This queue is called `SYSTEM.CLUSTER.TRANSMIT.QUEUE`.

System default queues

The *system default queues* are a set of queue definitions supplied with MQSeries. They are used to set default values for any attributes that you do not specify when defining your own queues. By modifying the supplied queue definitions you can vary the default queue attributes used at your installation.

MQSeries objects

An MQSeries object is a recoverable resource managed by MQSeries. Many of the tasks described in this book involve manipulating the following types of MQSeries object:

- Queue managers
- Queues
- Namelists
- Distribution lists
- Process definitions
- Channels
- Storage classes

These objects are common across different MQSeries platforms.

For system administrators, commands are available to manipulate objects. The format of the commands is dependent on the platform. For example, the MQSeries for OS/390 command `DEFINE QLOCAL` (with the appropriate attributes) defines a local queue object for MQSeries for OS/390. On MQSeries for AS/400, the equivalent command is `CRTMQMQ`.

On AIX, HP-UX, OS/2 Warp, Sun Solaris, and Windows NT, default objects are created for you when you create a queue manager. Default objects are supplied with the other MQSeries products, to help you define the objects that you need.

Each object has a *name* associated with it and can be referenced in MQSeries commands and MQI calls by that name. In general, names must be unique within each of these object types. For example, you can have a queue and a process with the same name, but you cannot have two queues with the same name. This means that you cannot have a local queue with the same name as a model queue, a remote queue, or an alias queue. There are a few exceptions to this rule; these are described where they arise.

Note: The characters within the names given to all MQSeries objects are case sensitive. Therefore, be very careful when defining the names of objects, to select the appropriate uppercase or lowercase characters.

Queue managers

A *queue manager* is that part of an MQSeries product that provides the messaging and queuing services to application programs, through the Message Queue Interface (MQI) program calls.

In some environments, for example with MQSeries for AS/400, only one queue manager can be in use in one machine at any one time; in other environments, for example with MQSeries for OS/390, more than one queue manager can be executing in one machine at one time.

In the OS/390 environment, applications are connected to a queue manager through adapters which are part of the MQSeries for OS/390 product. In the example shown in Figure 2, there are two applications on OS/390, one is a CICS transaction that is connected to the MQSeries queue manager by the CICS adapter, and the other a batch application connected to the queue manager by the batch adapter. Each application has access to local queues A1 and A2.




Figure 2. Example of messaging and queuing using MQSeries products

The applications issue the MQI calls that are implemented by the queue manager. For incoming messages, the queue manager directs them onto their respective destination queues; for outgoing messages, the queue manager sends the message to the destination queue manager. The destination queue manager ensures that the message is put onto the correct queue.

A queue is a *local queue* if it is managed by the same queue manager that is connected to the application. If the queue is managed by a different queue manager, it is called a *remote queue*.

In Figure 2, queues A1 and A2 are local queues to both batch application 1, CICS application 2, and to any other application connected directly to queue manager A. The figure also illustrates remote queues B1 and B2 controlled by queue manager B, and C1 and C2 controlled by queue manager C. Application 3 can put messages either to its local queues B1 and B2 controlled by MQSeries for AS/400, or to remote queues A1, A2, C1, or C2, as it requires.

Queues

A queue is an MQSeries object that can store messages. Each queue has *queue attributes* that determine what happens when applications reference the queue in MQI calls. The attributes indicate:

- Whether applications can retrieve messages from the queue (get enabled)
- Whether applications can put messages onto the queue (put enabled)
- Whether access to the queue is exclusive to one application or shared between applications
- The maximum number of messages that can be stored on the queue at the same time (maximum queue depth)
- The maximum size of messages that can be put on the queue (maximum message size)

Using queue objects

In MQSeries, there are several types of queue object. This does not mean that there are several different types of queue; essentially there is only one type of queue. Each type of queue object can be manipulated by MQSeries commands and is associated with queues in different ways:

1. A *local queue object* defines a local queue belonging to the queue manager to which the application is connected.
2. A *remote queue object* identifies a queue belonging to another queue manager. The remote queue is usually given a local definition. The definition specifies the name of the remote queue manager where the queue exists as well as the name of the remote queue itself. The information you specify when you define a remote queue object enables the queue manager to find the remote queue manager, so that any messages destined for the remote queue go to the correct queue manager.
3. An *alias queue object* enables applications to access queues by referring to them indirectly in MQI calls. When an alias queue name is used in an MQI call, the name is resolved to the name of a message queue at run time. This enables you to change the queues that applications use without changing the application in any way; you merely change the alias definition.
4. The *model queue object* defines a set of queue attributes that are used as a template for a *dynamic queue*. Dynamic queues are created by the queue manager when an application makes an open queue request specifying a queue that is a model queue. The dynamic queue that is created in this way is a local queue whose attributes are those of the model queue. You can specify a name (in full) for the dynamic queue, or the stem of a name (for example, ABC) and let the queue manager add a unique part to this, or you can let the queue manager assign a complete unique name for you.

Dynamic queues can be of two types:

- *Temporary*

This type of queue is deleted when the queue is closed, and does not survive a restart of a queue manager. The queues can be used to store nonpersistent messages only.

- *Permanent*

This type of queue is not deleted when the queue is closed, unless the application program specifically requests it to be deleted. The queue survives a restart of a queue manager, and can be used to store persistent and nonpersistent messages.

Note: Some MQSeries products do not support all the different types of queue object given above. Refer to “MQSeries product functional comparison” on page 228 for a summary of the functions offered on the different platforms.

Queue naming convention

If your applications operate within one local system, your application designers will specify the names of each queue they want to use. These queues will be named either to some local protocol or at the programmer's whim. In the latter case, it is immediately obvious that names chosen at random by individuals could be duplicates, causing all sorts of problems.

When your applications start to deal with remote queues, the need to know and understand a naming convention becomes essential. It is no good sending a message to a remote queue manager if the name of the desired queue is not known.

For all of the above reasons, it is recommended that you develop a naming convention for your enterprise which is known to, and understood by, all your application designers and developers. The end users of your applications probably do not need to know the convention because they will usually have no need to know the queue names.

Namelists

A *namelist* is an MQSeries object that contains a list of other MQSeries objects. Typically, namelists are used by applications such as trigger monitors, where they are used to identify a group of queues. The advantage of using a namelist is that it is maintained independently of applications; that is, it can be updated without stopping any of the applications that use it. Also, if one application fails, the namelist is not affected and other applications can continue using it.

Note: Not all MQSeries products support namelists. Refer to “MQSeries product functional comparison” on page 228 for a summary of the functions offered on the different platforms.

Distribution lists

A *distribution list* provides a way for an application to send a message to several destinations with a single MQPUT call. The list of destinations is supplied by the application. If more than one of these destinations uses the same transmission queue, only one copy of the message data is kept on the transmission queue, and sent down the channel.

Note: Not all MQSeries products support distribution lists. Refer to “MQSeries product functional comparison” on page 228 for a summary of the functions offered on the different platforms.

Process definitions

A *process definition object* defines an application to an MQSeries queue manager. Typically, in MQSeries, an application puts or gets messages from one or more queues and processes them. A process definition object is used for defining applications to be started by a trigger monitor. The definition includes the application ID, the application type, and application specific data.

Trigger monitors

A *trigger monitor* is an application that monitors an initiation queue (see “Initiation queues” on page 7) associated with a queue manager. When a trigger message arrives on the initiation queue, it is retrieved by the trigger monitor. Typically, the trigger monitor then starts an application that is specified in the message on the initiation queue. For more information on triggering and trigger monitors see Chapter 14, “Starting MQSeries applications using triggers” in the *MQSeries Application Programming Guide*.

Notes:

1. Triggering is supported on MQSeries for VSE/ESA, but it does not use process objects. See the information about triggers in the *MQSeries for VSE/ESA System Management Guide* for more information about this.
2. Process definition objects and triggering are not supported by MQSeries for UnixWare.

Channels

A channel provides a communication path. There are two types of channel, message channels and MQI channels.

Message channels

A *message channel* provides a communication path between two queue managers on the same, or different, platforms. The message channel is used for the transmission of messages from one queue manager to another, and shields the application programs from the complexities of the underlying networking protocols.

A message channel can transmit messages in one direction only. If two-way communication is required between two queue managers, two message channels are required.

In order to set up a channel, you usually define one channel definition for each end of the channel. There are six types of message channel; Sender, Server, Receiver, Requester, Cluster-sender and Cluster-receiver. On some platforms, some types of message channel can be defined automatically.

MQI channels

An *MQI channel* connects an MQSeries client to a queue manager on a server machine. It is for the transfer of MQI calls and responses only and is bidirectional. A channel definition exists for each end of the link. There are two types of MQI channel; Server-connection and Client-connection. On some platforms, some types of MQI channel can be defined automatically.

Storage classes

A *storage class* is used on OS/390 to map one or more queues to a page set. See the *MQSeries for OS/390 System Management Guide* for more information about storage classes.

Clients and servers

An *MQSeries client* is a part of an MQSeries product that can be installed on a machine without installing the full queue manager. It accepts Message Queue Interface (MQI) calls from application programs, and passes MQI requests to an *MQSeries server* that is usually executing on another processor.

The *MQSeries server* is a full queue manager, which can accept MQI calls directly from application programs that are running on the server processor; in addition, it can accept MQI requests from MQSeries clients.

This allows you to have an application that uses the MQI running on one machine, the client machine, and the queue manager itself running on a different machine.

For further information, see Chapter 7, "Introduction to MQSeries clients and servers" on page 49.

Where to find more information

For an introduction to MQSeries on your platform, see the following chapters:

- Chapter 9, "Introduction to MQSeries for AS/400" on page 65
- Chapter 14, "Introduction to MQSeries on Digital OpenVMS" on page 81
- Chapter 19, "Introduction to MQSeries for OS/2 Warp" on page 101
- Chapter 24, "Introduction to MQSeries for OS/390" on page 117
- Chapter 32, "Introduction to MQSeries on Tandem NSK" on page 155
- Chapter 36, "Introduction to MQSeries on UNIX systems" on page 169
- Chapter 41, "Introduction to MQSeries on VSE/ESA" on page 189
- Chapter 42, "Introduction to MQSeries for Windows NT" on page 195
- Chapter 47, "Introduction to MQSeries for Windows" on page 215

Chapter 2. Introduction to distributed queuing

The MQSeries distributed queuing facility moves messages between queue managers. To allow MQSeries to do this, you must ensure that you define and install the platform-dependent connections that provide the physical links between the local queue manager and any remote queue managers that you want to exchange messages with.

This chapter describes how to plan for communication between local and remote queue managers. It contains basic information about:

- “How queue managers communicate”
- “Setting up distributed queuing” on page 16
- “Application data conversion” on page 17
- “Assured delivery” on page 18
- “Recovering from errors” on page 18
- “Using MQSeries clusters” on page 19
- “Where to find more information” on page 20

How queue managers communicate

There are two ways in which a queue manager can be connected to other queue managers. These queue managers might be on the same or different platforms. The connections can allow:

- Simple transfer
- Staged transfer

Simple transfer is used between two queue managers that are connected by an MQSeries message channel.

Staged transfer is used to interconnect queue managers that are located in nodes that are not adjacent to the sending node, and can only be reached by staging through an adjacent queue manager. A remote queue manager might find that some messages received are not for its local queues but, instead, are to be passed on to another queue manager that performs the same process of delivering the messages or, passing them on again.

In each of the models introduced above, you need to define transmission queues and links to the adjacent nodes. The adjacent, or neighboring, nodes on your network must also have queue managers available that can handle your messages. Such handling places the message on one of the receiving node's local queues when that node recognizes the queue name as one of its own queues, or forwards the message to another queue manager when a queue manager name other than its own is received.

You must ensure that neighboring nodes with which your system communicates either have links to the intended destination or, at least, links to the next step toward the intended destination.

Distributed queuing

The communication between two queue managers is by means of a message channel; this consists of:

- A *transmission queue*
- A *message channel agent* for each queue manager
- A *communications link*

A *message channel agent* is a program controlling communications and is part of the queue manager.

For a detailed description of how these components allow messages to be exchanged between systems, and how to define them, refer to Chapter 1, “Concepts of intercommunication” in the *MQSeries Intercommunication* manual.

Channel speed

For a normal channel, all messages travel through the message channel at the same speed. Persistent and nonpersistent messages on the same transmission queue maintain their order relative to each other. None of the messages are lost if there is a channel failure.

On AIX, HP-UX, OS/2 Warp, OS/390, OS/400, Sun Solaris, and Windows NT, you can define ‘fast’ channels. If a channel is defined to be fast, nonpersistent messages travel through the channel outside syncpoint. This improves the throughput of the channel, but means that nonpersistent messages are lost if there is a channel failure. (Persistent messages are never lost if a channel failure occurs.)

For a fast channel, it is possible for nonpersistent messages to jump ahead of persistent messages waiting on the same transmission queue, that is, the order of nonpersistent messages is not maintained relative to persistent messages. However the order of nonpersistent messages relative to each other is maintained. Similarly, the order of persistent messages relative to each other is maintained.

Setting up distributed queuing

To understand what you need to plan for, it is first necessary to review the queuing process.

When an application attempts to put a message to a queue, it must specify the destination queue. This is done by addressing the message to:

- An alias name
- A queue name, plus a queue manager name

If an alias name is used, the queue manager resolves that name to one of two destinations, either a local queue name, or the name of a remote queue. In the first case, the message is placed on the named local queue; in the second, the message is placed on the appropriate transmission queue.

In the case where the queue name, and the queue manager name are supplied, the queue manager name can be either that of the local queue manager, which is the default condition, or a remote queue manager name.

When a message is created by the queue manager as a result of an MQPUT call, the destination queue name, and queue manager name, are placed in the message descriptor part of the message.

When the queue manager sees that the queue manager name in a message is not its own name, it places the message on a special local queue called a transmission queue. From the transmission queue, the message is transferred to the next node in the network by the queue manager, using the message channel associated with that transmission queue. At the next node, the queue manager finds that the message is addressed to one of its local queues and accordingly places it on the destination queue, which can be another transmission queue giving further transmission to another node. You should note that there can be more than one transmission queue for each remote queue manager that you have defined. Refer to “What is intercommunication?” in the *MQSeries Intercommunication* manual for more information about transmission queues.

A special case exists where a queue manager is called to handle a message that, though sent to, or defaulting to, this queue manager, does not have a known queue name. In this case the message is placed on the dead-letter queue. Special actions are required to recover or dispose of messages placed on the dead-letter queue. See “Dead-letter queues” on page 8 for more information.

To enable remote queuing, you might need to define remote queues. (This step is not essential; there are cases where the application can place the message directly to a queue manager and queue name combination.) The queue manager, when handling a request to place a message on a queue with either an alias name or a remote queue manager and queue name combination, uses the information to determine that the name refers to a remote queue manager. If so, the message is placed on a transmission queue associated with the remote queue manager. MQSeries then moves the message from the transmission queue to the remote queue manager.

You need to plan alias names for remote queues that you communicate with. You should consider the naming conventions that you wish to apply to these names, and also how you will ensure that your total network complies with your naming convention.

You must also plan the message *channels* that you will create for message transmission to remote queue managers. You might choose to define multiple channels to these remote queue managers to allow for high message traffic, different message priorities, or for different message types.

Application data conversion

The representation of character and numeric data is different on the various platforms for which MQSeries products are available. Because of this, you might need to plan for the conversion of the data within your messages, from one representation to another, when writing applications that span multiple platforms.

The message descriptor in all messages contains the coded character set identifier (CCSID) and encoding information; this identifies the representation used for the character and numeric data that is in the data portion of the message.

Some MQSeries products convert the data within messages from one representation to another, provided the format of the data conforms to one of the MQI built-in formats. This conversion can be performed at the following times:

- By a queue manager during the processing of an MQGET call, if the data conversion option is included in the call.
- By a message channel as it transmits a message to a remote queue manager, if the data conversion option is included in the channel definition. The channel converts the message data to the representation used by the platform at the receiving end of the channel.

For application defined formats that do not conform to the built-in formats, the conversion can be performed by user exit programs.

For further information about data conversion, refer to Chapter 11, “Writing data-conversion exits” in the *MQSeries Application Programming Guide*.

Assured delivery

MQSeries products are designed for assured message delivery. Processing is such that when messages are being transmitted to remote queue managers, the messages are moved in discrete transaction units, or batches, where confirmation of receipt is always obtained before a particular message is deleted at the transmitting queue manager. To achieve this, the sending and receiving ends of the link commit batches of messages in unison.

Recovering from errors

If a remote queuing error or session error occurs, error messages are sent to the local system operator or console, the local system being that where the queue manager detecting the error is running.

If any error occurs while sending or receiving a message, the transaction is terminated, and error messages are sent to both the local and remote system consoles. When you restart remote queuing, the queue manager checks for, and resolves, any in-doubt messages caused by the previous termination. An in-doubt message is one where the point of consistency prior to the message is known, but it is not known with certainty whether the new point of consistency that the message creates has been reached, or that a backout to a previous point of consistency has been completed. The application must decide what action to take to resolve the in-doubt situation.

If a message cannot be put on the queue on the remote queue manager, the message is written to the dead-letter queue on that queue manager and a report is sent back to the message sender (if so requested in the message).

Remember that it is important to ensure that there is a dead-letter queue defined for each queue manager, and that this queue is not allowed to fill completely. Otherwise, when an error is detected by the channel, the channel will stop transmission. See “Dead-letter queues” on page 8 for more information.

Using MQSeries clusters

As already discussed, every queue manager in a traditional MQSeries network is independent. If one queue manager needs to send messages to another it must define a transmission queue, a channel to the remote queue manager, and a remote queue definition for every queue to which it wants to send messages.

If you group queue managers in a cluster, the queue managers can make the queues that they host available to every other queue manager in the cluster. Then, assuming you have the necessary network infrastructure in place, any queue manager can send a message to any other queue manager in the same cluster without the need for explicit channel definitions, remote-queue definitions, or transmission queues for each destination. Every queue manager in a cluster has a single transmission queue that transmits messages to any other queue manager in the cluster. Each queue manager needs to define only one cluster-receiver channel on which to receive messages and one cluster-sender channel on which to send messages.

Figure 3 shows the components of a cluster called CLUSTER. In this cluster there are three queue managers, QM1, QM2, and QM3. QM1 and QM2 host repositories of information about the queue managers and queues in the cluster. QM2 and QM3 host some cluster queues, that is, queues that are accessible to any other queue manager in the cluster. Each queue manager has a cluster-receiver channel called *TO.qmgr* on which it can receive messages. Each queue manager also has a cluster-sender channel on which it can send cluster information and messages to one of the repository queue managers. In Figure 3, QM1 and QM3 send to the repository at QM2, and QM2 sends to the repository at QM1.




Figure 3. A cluster of queue managers

As you can see, the amount of system administration is greatly reduced, even with just a small cluster, containing two or three queue managers.

In addition to the reduction in system administration, clusters enable you to increase the availability of your queues and to distribute workload between your queue managers. Many queue managers can have definitions for the same queue. Any one of these queue managers can receive the message and so the workload can be shared between the queue managers.

MQSeries clusters are available on Version 5.1 of MQSeries for AIX, HP-UX, OS/2 Warp, Sun Solaris, and Windows NT, and MQSeries for OS/390 Version 2.1. On Windows NT, it is not advisable to use clustering in an environment where IP addresses change on an unpredictable basis such as on machines where Dynamic Host Configuration Protocol (DHCP) is being used.

How can I use MQSeries clusters

You can set up a cluster, or convert an existing network of queue managers into a cluster, using a small number of definitions. Typically, a cluster contains queue managers that are logically related in some way and need to share some data or applications. For example, you might group all the departments in your company so that they all feed into the PAYROLL application, or you might group the branches of your department store so that they all feed into the SALES and PURCHASES applications. Once a cluster has been set up, the queue managers within it can communicate with each other without the need for any channel or remote queue definitions.

For more information about MQSeries clusters, see the *MQSeries Queue Manager Clusters* manual.

Where to find more information

You can find more information in the *MQSeries Intercommunication* manual and the *MQSeries Queue Manager Clusters* manual.

Also, you might find it useful to read the following redbooks published by the IBM International Technical Support Organization:

- *Examples of Using MQSeries on S/390, RISC System/6000, AS/400, and PS/2*, GG24-4326
- *Multiplatform APPC Configuration Guide*, GG24-4485

Request these books through your IBM representative.

Chapter 3. Introduction to MQSeries security

This chapter gives an overview of the security facilities that are provided by MQSeries products. The ways of using these facilities as part of the MQSeries framework are described under “Security enabling interface (SEI)” on page 58.

This chapter contains basic information about:

- “MQSeries level 1 function” on page 22
- “MQSeries level 2 function” on page 22
- “Where to find more information” on page 25

To understand the security functions provided by MQSeries, you need to understand the logical positioning of MQSeries relative to other components within a system and to understand the security services that are under discussion. The relative positioning of MQSeries is illustrated in Figure 4, which is an extract from the Open Blueprint®, where MQSeries is represented by the Messaging and Queuing component.

Figure 4 shows that security services are separated from other components such as application services, resource managers, and communications. This separation means that security services need only be provided by one component in the node and other components simply call the appropriate services when needed.




Figure 4. MQSeries and the Open Blueprint

The security services that can be provided by the (separate) security component are:

- Identification and authentication (I&A)

This service forms the basis of many of the other services and involves the provision of a user identifier (user ID or principal) and the verification that the identifier is valid (that is, it represents the actual user and is not some intruder impersonating a valid user).

- Authorization

This is access control and relies upon the availability of some user identifier to compare against access control lists (ACLs).

Note that the authorization service is only useful if it is used; an intruder might attempt to bypass (and neutralize) the authorization service.

- Data confidentiality, or encryption
- Data integrity

Even though data might be visible (that is, not encrypted), the data integrity service ensures that data is not altered.

- Non-repudiation

This is the provision of some form of token (such as a digital signature) which guarantees that a particular piece of data originated from a particular user.

Note that although the Security component is positioned as one of the distribution services, it also provides services within the node (particularly authorization but all of the other services as well).

The way in which these security services are used by the various aspects of MQSeries is explained in the following sections.

MQSeries level 1 function

MQSeries for UnixWare does not provide any support for security. There is no attempt to recognize the user identifier associated with an application and no attempt to provide an authorization service or pass security information to other queue managers. This means that any security services that are required must be provided at the application level.

MQSeries level 2 function

The following sections refer to all MQSeries products except MQSeries for UnixWare.

MQSeries applications

Before an application connects to a queue manager, it will have undergone some form of I&A procedure. This might be the provision of a user ID and password or might be some more elaborate process (such as smart card identification). Alternatively, it might be that there is no requirement for the I&A procedure and, thus, no user identifier associated with the application (for example, the building that houses the system might be physically secure and user identifiers might not be considered necessary).

The consequence of this is that each application that issues MQI calls has an associated user identifier (which might be null) that is used to authorize the use of certain MQI functions (primarily **MQCONN** and **MQOPEN**) and options (such as PUT and GET) against particular objects (usually queues). This means that any application user identifier trying to access MQSeries resources must be suitably authorized.

Because the I&A procedure takes place before the application connects to the queue manager, it is the responsibility of components other than MQSeries to provide the I&A service. MQSeries is responsible only for capturing the user identifier for use in providing other security services, such as authorization. (The user identifier is captured when the application connects to the queue manager.)

OS/2 Warp is the exception to this scope of responsibility, where MQSeries provides a service to provide a user identifier for applications when they connect to the queue manager. This is called the user identifier service and is documented in Chapter 14, “User identifier service” in the *MQSeries Programmable System Management* manual. The user identifier service is part of the MQSeries framework; see “Security enabling interface (SEI)” on page 58 for further details. This service is provided because there are no security functions on this platform.

Similarly, it is generally the responsibility of some other component to provide the authorization service, with MQSeries having responsibility for calling that service. This works satisfactorily for systems such as OS/390 and OS/400 where there is a standardized interface to the authorization service (for example, SAF on OS/390). For the OS/2 Warp, Windows NT, and UNIX platforms, however, there is no standard authorization service or interface provided and so MQSeries provides its own interface. This is called the authorization service and is documented in Chapter 12, “Authorization service” in the *MQSeries Programmable System Management* manual. The authorization service is part of the MQSeries framework; see “Security enabling interface (SEI)” on page 58 for further details.

For MQSeries for Digital OpenVMS, MQSeries for Tandem NSK, MQSeries on UNIX systems, and MQSeries for Windows NT, there is an additional component written to this interface that provides authorization service. This is called the object authority manager (OAM) and it restricts access to MQSeries objects based upon the ACLs that it manages.

The OAM is documented in the *MQSeries for Digital OpenVMS System Management Guide*, the *MQSeries for Tandem NonStop Kernel System Management Guide*, the *MQSeries for VSE/ESA System Management Guide*, and “Understanding the Object Authority Manager” in the *MQSeries System Administration* manual. The object authority manager is part of the MQSeries framework; see “Security enabling interface (SEI)” on page 58 for further details.

MQSeries messages

The basic function of MQSeries is to pass messages between applications. The message header (the message descriptor, MQMD) contains a field (named *UserIdentifier*) where a user identifier can be placed, allowing the application that gets the message to know from which user the message originated. The user identifier can be placed in the MQMD in one of three ways:

- The user identifier from a previous message (that is, one for which an **MQGET** has been performed) can be passed to a subsequent message. This is known as passing the security context.
- A suitably authorized (that is, trusted) application can place *any* user identifier in the field.
- If neither of the above is used, MQSeries automatically places in this field the user identifier of the application that did the **MQPUT**.

Therefore, this aspect of MQSeries operation provides an identification service (associating a user identifier with the message); it does *not* provide an authentication service. It is currently the responsibility of MQSeries applications both to provide any required authentication token (on the **MQPUT** side) and to verify that token (on the **MQGET** side).

Note also that, when an application does an **MQGET** for a message, there is no attempt to reset the application's user identifier to that contained in the message header. This function is called context management and is not supported by MQSeries.

Point-to-point security

In addition to providing services as a local resource manager, a queue manager also provides distributed queuing, enabling messages to be distributed around a network of queue managers. This distributed messaging function is provided by means of MQSeries channels. Each channel is composed of a pair of message channel agent programs (MCAs), which provide the protocol for assured, once-only message delivery using an underlying transport mechanism to exchange messages.

When the two MCAs establish communication, it might be necessary for each to verify the identity of the other. This would be the case if one queue manager did not trust the connection or the identity of the partner queue manager (for example, if they were owned by separate enterprises). This verification can be accomplished in one of the following ways:

1. Some transport mechanisms (in particular APPC) provide security features such as session authentication. Note that this provides verification of the partner system (the partner logical unit), rather than the partner application (the MCA) but this might satisfy the security requirements of the queue manager.
2. The MCAs each provide a security exit point which can be used to call user-written security exits for the exchange of user identifiers and associated authentication tokens (password, ticket, and so on). This allows each MCA to verify the identity of its partner.

Using the MCA security exit allows the channel to be independent of the underlying transport mechanism and to provide a consistent service across many transports. This is especially important when providing a service (like security) that is available only on a limited set of transports.

This aspect of MQSeries operation provides support for the I&A service. If required, the security exit can use the central security services to provide authentication tokens but this is not a requirement. See “Security enabling interface (SEI)” on page 58 for more information about MCA exits.

3. On AIX, HP-UX, OS/2 Warp, Sun Solaris, Windows NT, and Windows 95, MQSeries provides exits relating to DCE security. Source code is also provided to help you understand the program, and to assist you in creating your own.

Note that it is possible to use any or all of the above mechanisms for point-to-point security, enabling an MCA to be assured that it is exchanging messages with the correct queue manager.

End-to-end security

End-to-end security refers to security services that can be provided when a message is PUT by an application and to the corresponding services that are available when the target application performs a GET. The relevant services are identification and authentication (possibly across the network), data confidentiality, data integrity, and non-repudiation.

MQSeries is not responsible for the provision of these services but it is responsible for providing appropriate interfaces to call these services.

Today, the only aspect of end-to-end security that is (directly) supported by MQSeries is Identification, where a user identifier can be placed in a message header. MQSeries does not provide (direct) support for any of the other services. However, these services can be implemented in either MQSeries application programs or the MCA message exit, which is a customer exit invoked each time a message is passed between two queue managers.

Where to find more information

For information about MQSeries security on your platform, see the following chapters:

- Chapter 11, “Security planning for MQSeries for AS/400” on page 71
- Chapter 16, “Security planning for MQSeries for Digital OpenVMS” on page 89
- Chapter 21, “Security planning for MQSeries for OS/2 Warp” on page 109
- Chapter 27, “Security planning for MQSeries for OS/390” on page 133
- Chapter 34, “Security planning for MQSeries for Tandem NSK” on page 161
- Chapter 38, “Security planning for MQSeries on UNIX systems” on page 179
- Chapter 41, “Introduction to MQSeries on VSE/ESA” on page 189
- Chapter 44, “Security planning for MQSeries for Windows NT” on page 205

For information about the security enabling interface, see Chapter 8, “Introduction to the MQSeries Framework” on page 55.

Chapter 4. Introduction to MQSeries recovery concepts

MQSeries products provide facilities for applications to be able to keep related sets of data consistent when changes are made to them. This chapter describes the background concepts of recovery and restart that you will need to understand before going on to the later chapters in this book.

This chapter gives basic information about:

- “How changes are made to data”
- “How consistency is maintained” on page 29
- “MQSeries as a transaction manager” on page 30
- “Where to find more information” on page 31

How changes are made to data

You need to understand how MQSeries queue managers interact with other programs to keep all the data consistent. This section discusses *units of recovery*.

Units of recovery

In a single queue manager, a *unit of recovery* is a piece of work that changes data from one point of consistency to another. A *point of consistency* (also called a *syncpoint* or *commit point*) is a moment at which all the recoverable data that an application program accesses is consistent. This means that a unit of recovery begins with an attempt to change data and ends at a point of consistency. An example of a unit of recovery within an application program is shown in Figure 5.




Figure 5. A unit of recovery within an application

In this example, the application process makes changes to queues at *MQI call 1* and *MQI call 2*. The application process can include a number of units of recovery or just one, but any complete unit of recovery ends with a commit point.

For example, a bank transaction might transfer funds from account A to account B. First, a debit program subtracts the amount from account A. Next, account B must

be credited with the amount. After subtracting the amount from account A, the two accounts are inconsistent and the queue manager cannot commit. The next step in the process is for the debit program to put a message on a queue to the credit program, giving information about the amount of money and the account to be credited. When the credit program gets the message from the queue, it performs the credit to account B and informs the debit program that it has completed the task. The data is now consistent. The application can announce a point of consistency and make the changes visible to other applications.

A point of consistency should be created by an application before it terminates. It can do this by issuing a commit call. Normal termination of an application on some platforms automatically causes a point of consistency, but you should verify that this will occur on your platform.

If an error occurs within a unit of recovery, you can use the queue manager to remove changes to data, returning the data to its state at the start of the unit of recovery; that is, the queue manager undoes the work.

Some systems have syncpoint facilities. In these cases it is the system function that causes a syncpoint to be created for both that system's data, and the data that is being managed by MQSeries queue managers, simultaneously.

MQSeries products can operate with a number of others, to provide coordination between MQSeries and non-MQSeries resources. The MQSeries products where this is possible include:

<i>Table 2. MQSeries and cooperating products</i>	
MQSeries product	Cooperating products
MQSeries for AIX	Tuxedo, TXSeries™ for AIX
MQSeries for AS/400	CICS for OS/400
MQSeries for AT&T GIS UNIX	Tuxedo
MQSeries for HP-UX	Encina, Tuxedo, TXSeries for HP-UX
MQSeries for OS/2 Warp	CICS Transaction Server for OS/2
MQSeries for OS/390	CICS for MVS/ESA, IMS/ESA®, OS/390 RRS, CICS Transaction Server for OS/390
MQSeries for SINIX and DC/OSx	CICS, Encina, Tuxedo
MQSeries for Sun Solaris	Tuxedo, TXSeries for Sun Solaris
MQSeries for VSE/ESA	CICS/VSE
MQSeries for Windows NT	Tuxedo, TXSeries for Windows NT

How consistency is maintained

If the data being managed by a queue manager is to be consistent with the data in other subsystems, any data changed in one must be matched by a change in the others. Before one system commits the changed data, it must know that the other system, or systems, can make the corresponding changes. So, the systems must communicate.

During a *two-phase commit* one subsystem coordinates the process. That subsystem is called the *coordinator*, the others are the *participants*. On AIX, HP-UX, OS/2 Warp, Sun Solaris, and Windows NT, MQSeries can be either the coordinator or a participant. On other platforms, CICS, IMS, or RRS is always the coordinator in interactions with MQSeries, and MQSeries is always a participant. The coordinator first checks that all participants are ready to perform the commit; that is phase one. When the coordinator receives positive replies from the participants that they are ready to commit, it issues the commit request, this being phase 2. Together with the coordinator, all participants now commit the changed data. All data is once again consistent.

During a *one-phase commit* there is no coordinator as such in the interactions. When the commit call is issued, the response to the call is that:

- The commit was successful
- The call was partially complete
- The call failed

It is up to the application issuing the call to decide what further action, if any, needs to be taken.

When the queue manager is restarted after an abnormal termination, it must determine whether to commit or to back out units of recovery that were active at the time of the error. For certain units of recovery, the queue manager has enough information to make the decision. For others, it does not, and must get information from the coordinator when the connection is reestablished.

Syncpointing cannot occur directly across remote links. Instead, use is made of the assured message delivery feature of the MQSeries products. A commit request is sent in a message to a remote system by an application with the assurance that the message will be delivered. The application designers must ensure that they create, and respond to, commit requests. They must also allow for situations where the commit cannot be accepted, and respond accordingly to the commit requester.

An example of the problems of remote commits is when the remote system is not available. The messages to it will remain on the transmission queues until they can be delivered. When delivery eventually occurs, any desired commitments can then be made. In this situation, we are dealing with time independent applications. It is for the application designers to consider how, and when, they require the data shared between their remote systems to be consistent.

MQSeries as a transaction manager

On some platforms, MQSeries can act as a transaction manager and will coordinate updates made by external resource managers within MQSeries units of work. These external resource managers must comply to the X/Open XA interface.

Table 3 shows the MQSeries platforms that can act as a transaction manager, and the XA-compliant database managers they support. Figure 6 through Figure 8 on page 31 show how you must configure your queue manager and database servers to enable this.

Table 3. XA-compliant database managers supported by MQSeries

Platform	DB2	Oracle	Sybase
AIX	✓	✓	✓
HP-UX	✓	✓	
OS/2 Warp	✓		
Sun Solaris	✓	✓	✓
Windows NT	✓		✓

The following figures describe the possible configurations for your queue manager and database. The configuration shown in Figure 6 is allowed:




Figure 6. Queue manager and database server configuration 1. Queue manager server and database server on the same machine

The configuration shown in Figure 7 is also allowed provided that you use appropriate database connection features (for example, CAE/DDCS for DB2):




Figure 7. Queue manager and database server configuration 2. Queue manager server and database client on the same machine

The configuration shown in Figure 8 on page 31 is not allowed because coordination can be provided only by the MQSeries server, not the client:




Figure 8. Queue manager and database server configuration 3. Queue manager server and database server on different machine

Where to find more information

For information about MQSeries recovery on your platform, see the following chapters:

- Chapter 10, “Backup and recovery planning for MQSeries for AS/400” on page 69
- Chapter 15, “Backup and recovery planning for MQSeries for Digital OpenVMS” on page 85
- Chapter 20, “Backup and recovery planning for MQSeries for OS/2 Warp” on page 105
- Chapter 26, “Backup and recovery planning for MQSeries for OS/390” on page 127
- Chapter 33, “Backup and recovery planning for MQSeries for Tandem NSK” on page 159
- Chapter 37, “Backup and recovery planning for MQSeries on UNIX systems” on page 175
- Chapter 41, “Introduction to MQSeries on VSE/ESA” on page 189
- Chapter 43, “Backup and recovery planning for MQSeries for Windows NT” on page 201

Chapter 5. Introduction to MQSeries administration

This chapter gives a summary of the administration facilities that are provided by the MQSeries products.

Administration of an application that uses MQSeries products is performed by a system administrator, system programmer, or computer operator who has the appropriate authority. It is the administrator's responsibility to monitor the MQSeries products, and the resources that they are using, and make any changes that might be necessary to keep the applications running without problems.

This chapter has the following sections:

- "Introducing commands"
- "Formats of command" on page 34
- "Administration application programs" on page 36
- "The MQSeries Administration Interface" on page 37
- "Command summary" on page 38
- "Where to find more information" on page 43

Some of the facilities described in this chapter are not supported by all MQSeries products.

Introducing commands

MQSeries products provide a set of commands, command interfaces, and utilities that provide messaging and queuing administration functions, including, for example:

Queue administration	Creating and deleting queues
Channel administration	Stopping or starting channels
Security administration	Changing the access authority to queues

These functions are provided by *commands* in MQSeries, which are processed, by the queue manager, in the following ways:

- **Entered by the system administrator.**

A command is entered by a system administrator and processed immediately by the queue manager. A response is given to the administrator.

The method used to enter the commands is platform dependent, and is the normal method that is used for entering commands on the platform. This could be a command console, a command line, a display panel utility, or some other technique.

- **Stored as a list of commands.**

The commands are stored as a list in a file. Later, the administrator can cause the queue manager to read the commands in the file, process them, and generate responses.

- **Stored as messages in a queue.**

An application program generates a command, and puts it to a queue manager *command queue*, using the MQPUT call. The queue manager gets the message off the queue, processes the command that is contained in the message, and generates a response.

Formats of command

The MQSeries products provide the following types of command:

- **MQSeries commands (MQSC)** - human-readable
- **Programmable Command Format (PCF) commands** - machine-readable

Both sets of commands perform similar functions, but are intended for use in different situations.

In addition to the MQSC and PCF commands, the MQSeries products provide *control commands*. These are the commands used by the system administrator to pass control information to the queue manager, and are designed to be compatible with the other administrative commands used on a particular platform. Because of the differences in the way that administrative commands are processed by the various operating systems in which the MQSeries products operate, the technique used to enter control commands varies with the particular MQSeries product.

MQSC commands

MQSeries commands (MQSC) provide a uniform method of issuing commands in a human-readable form across MQSeries platforms. They are intended for use in those situations where people have to be able to read the commands, for example, whenever commands are entered through a command line. The responses to these commands are also human-readable, however the content and format depends on the platform in which they are used.

The commands can be issued from the following sources:

- Entered through the command line
- Stored in a file, and processed by the queue manager
- Stored within messages on a command queue

MQSC commands are described in the *MQSeries Command Reference* manual. They are not available on MQSeries for UnixWare or MQSeries for VSE/ESA.

Programmable Command Format commands

MQSeries Programmable Command Format (PCF) commands are intended for use by application programs that provide facilities for the administration of queue managers and the resources that they are using (for example, queues and channels), from a single point within the network. The format of these commands, and their responses, is independent of the environment in which they are used.

PCFs define commands and reply messages that can be exchanged between a program and any queue manager in a network.

You can use PCF commands in a systems-management application program for administration of MQSeries objects: queue managers, process definitions, queues,

and channels. The application can operate from a single point in the network to communicate command and reply information with any queue manager, local or remote, via the local queue manager.

It is possible, by using the PCF **escape** command, to include the MQSC command as character strings within a PCF command.

PCF commands are described in the *MQSeries Programmable System Management* manual. They are not available on MQSeries for OS/390, MQSeries for UnixWare, or MQSeries for VSE/ESA.

Command queues

Some MQSeries products have a command queue that accepts administration messages containing commands, called *command messages*. The queue manager has a *command server* that processes the command messages from the command queue.

Command messages can be placed on the queue by any local or remote application program. The command messages are processed by the command server, and a response is returned to the application program using the name of the reply-to queue that is contained within the original command message. PCF commands and reply messages are sent and received using the MQPUT and MQGET calls defined in the Message Queue Interface (MQI).

There are two types of command queue, each with system-defined queue names.

1. SYSTEM.ADMIN.COMMAND.QUEUE

This queue accepts PCF commands only, including the **escape** command. This type of queue is supported by the following:

- MQSeries for AS/400
- MQSeries for Digital OpenVMS
- MQSeries for OS/2 Warp
- MQSeries for Tandem NSK
- MQSeries on UNIX systems
- MQSeries for Windows NT
- MQSeries for Windows (Version 2.1)

2. SYSTEM.COMMAND.INPUT

This queue accepts MQSC commands only. This type of queue is supported by MQSeries for OS/390 only.

The MQSeries products that are not mentioned above do not have command queues.

Administration application programs

MQSeries products provide application programs, called *administration utilities*, that allow the system administrator on one processor to control the MQSeries product that is running on that processor. Some of these utilities also allow the administrator to control MQSeries products that are running on other processors, so-called *remote administration*.

The MQSeries Explorer, supplied with MQSeries for Windows NT, provides a graphical user interface for administering your MQSeries network. The MQSeries Explorer cannot be used to control queue managers on OS/390 or VSE/ESA.

In those situations where no administration utility is available, you can write your own application program to provide those functions. This application can manage any queue manager (local or remote) that has a command queue, by putting command messages to that queue using the MQPUT call. When a command is processed, a response message is returned to the reply-to queue that your application program specified in the original command message.

MQSeries product administration facilities

Details of the control commands and administration facilities provided by some of the MQSeries products are given in later sections of this manual, as follows:

- **MQSeries for AS/400** – see Chapter 12, “Administration of MQSeries for AS/400” on page 73, and the *MQSeries for AS/400 Administration Guide* for more detail.
- **MQSeries for Digital OpenVMS** – see Chapter 17, “Administration of MQSeries for Digital OpenVMS” on page 93, and the *MQSeries for Digital OpenVMS System Management Guide* for more detail.
- **MQSeries for OS/2 Warp** – see Chapter 22, “Administration of MQSeries for OS/2 Warp” on page 111, and Chapter 2, “An introduction to MQSeries administration” in the *MQSeries System Administration* manual for more detail.
- **MQSeries for OS/390** – see Chapter 28, “Administration of MQSeries for OS/390” on page 137, and the *MQSeries for OS/390 System Management Guide* for more detail. MQSeries for OS/390 does not support PCF commands.
- **MQSeries for Tandem NonStop Kernel** – see Chapter 35, “Administration of MQSeries for Tandem NSK” on page 165, and the *MQSeries for Tandem NonStop Kernel System Management Guide* for more detail.
- **MQSeries on UNIX systems** – see Chapter 39, “Administration of MQSeries on UNIX systems” on page 183, and Chapter 2, “An introduction to MQSeries administration” in the *MQSeries System Administration* manual for more detail.
- **MQSeries for VSE/ESA** – see “Administration of MQSeries for VSE/ESA” on page 191, and the *MQSeries for VSE/ESA System Management Guide* for more detail.
- **MQSeries for Windows NT** – see Chapter 45, “Administration of MQSeries for Windows NT” on page 207, and Chapter 2, “An introduction to MQSeries administration” in the *MQSeries System Administration* manual for more detail.
- **MQSeries for Windows** – see Chapter 47, “Introduction to MQSeries for Windows” on page 215, and the *MQSeries for Windows User’s Guide* for more detail.

A tabular summary of the commands supported by these products is given in “Command summary” on page 38.

Administration for other MQSeries products

The MQSeries products that are not mentioned above have utility programs that use display panels to provide a user-friendly interface for the administration of the product. Details of these programs, and the administration facilities that they provide, can be found in the *User Guide* that is available for each of the products.

None of these products has an administration queue to which commands (MQSC or PCF) can be sent. Therefore administration of these products by local or remote application programs is not possible.

The MQSeries Administration Interface

The MQSeries Administration Interface (MQAI) is a programming interface to MQSeries. It performs administration tasks on an MQSeries queue manager using *data bags*. Data bags allow you to handle properties (or parameters) of objects in a way that is simpler than using the Programmable Command Format (PCF) administration interface.

The MQAI is available on MQSeries for AIX, HP-UX, OS/2 Warp, Sun Solaris, and Windows NT. It can be used for the following tasks:

- To simplify the use of PCF messages. The MQAI is an easy way to administer MQSeries; you do not have to write your own PCF messages and this avoids the problems associated with complex data structures.
- To implement self-administering applications and administration tools. For example, the Active Directory Service Interfaces provided on Windows NT uses the MQAI.
- To handle error conditions more easily. It is difficult to get return codes back from the MQSeries commands (MQSC), but the MQAI makes it easier for the program to handle error conditions.

For more information about using the MQAI, see the *MQSeries Administration Interface Programming Guide and Reference* manual.

Command summary

The following tables show how the various command formats in MQSeries relate to each other. The command formats available are:

- Programmable command format (PCF) commands
- MQSeries (MQSC) commands
- MQSeries for OS/400 CL commands
- Control commands for MQSeries products on distributed platforms, that is, MQSeries on UNIX systems, MQSeries for Digital OpenVMS, MQSeries for Tandem NonStop Kernel, MQSeries for OS/2 Warp, and MQSeries for Windows NT

Notes:

1. The PCF commands are not supported on OS/390 or VSE/ESA.
2. Unless otherwise specified, the MQSC commands are supported on all platforms, except VSE/ESA.
3. An empty cell indicates that there is no equivalent command in the specified format.

Table 4. Commands for queue manager administration

Operation	PCF	MQSC	OS/400 CL	Commands for distributed platforms
Change Queue Manager attributes	Change Queue Manager	ALTER QMGR DEFINE MAXSMGS (See note 1)	CHGMQM	
Display Queue Manager attributes	Inquire Queue Manager	DISPLAY QMGR DISPLAY MAXSMGS (See note 1)	DSPMQM	
Connect a Queue Manager			CCTMQM	
Create a Queue Manager			CRTMQM	crtmqm
Delete a Queue Manager			DLTMQM	dltmqm
Disconnect a Queue Manager			DSCMQM	
Stop a Queue Manager		STOP QMGR (See note 1)	ENDMQM	endmqm
Ping a Queue Manager	Ping Queue Manager	PING QMGR (See note 2)		
Start a Queue Manager		START QMGR (See note 1)	STRMQM	strmqm
Notes: 1. Applies on OS/390 only 2. Does not apply on OS/390				

Table 5. Commands for queue administration

Operation	PCF	MQSC	OS/400 CL	Commands for distributed platforms
Change queue attributes	Change Queue	ALTER QALIAS ALTER QLOCAL ALTER QMODEL ALTER QREMOTE	CHGMQMQ	
Clear a queue	Clear Queue	CLEAR QLOCAL (See note 1) The following sequence: DELETE QLOCAL(x), DEFINE QLOCAL(x) or the following sequence: DEFINE QLOCAL(y) LIKE(x), DELETE QLOCAL(x), DEFINE QLOCAL(x) LIKE(y), DELETE QLOCAL(y)	CLRMQMQ	
Copy a queue definition	Copy Queue	DEFINE QALIAS(x) LIKE(y) DEFINE QLOCAL(x) LIKE(y) DEFINE QMODEL(x) LIKE(y) DEFINE QREMOTE(x) LIKE(y)	CPYMQMQ	
Create a queue	Create Queue	DEFINE QALIAS DEFINE QLOCAL DEFINE QMODEL DEFINE QREMOTE	CRTMQMQ	
Delete a queue	Delete Queue	DELETE QALIAS DELETE QLOCAL DELETE QMODEL DELETE QREMOTE	DLTMQMQ	
Display queue attributes	Inquire Queue	DISPLAY QUEUE DISPLAY QALIAS (See note 2) DISPLAY QCLUSTER (See note 2) DISPLAY QLOCAL (See note 2) DISPLAY QMODEL (See note 2) DISPLAY QREMOTE (See note 2)	DSPMQMQ	
Display queue names	Inquire Queue Names	DISPLAY QUEUE	WRKMQMQ	
Work with a queue			WRKMQMQ	
Work with messages			WRKMQMMSG	
Reset queue statistics	Reset Queue Statistics (See note 3)			
Notes: 1. Does not apply on OS/390 2. Applies on AIX, HP-UX, OS/2 Warp, OS/390, Sun Solaris, and Windows NT only 3. Does not apply on Tandem NSK				

Table 6 (Page 1 of 2). Commands for process definition administration

Operation	PCF	MQSC	OS/400 CL	Commands for distributed platforms
Change process attributes	Change Process	ALTER PROCESS	CHGMQMPPRC	

Administration overview

Table 6 (Page 2 of 2). Commands for process definition administration

Operation	PCF	MQSC	OS/400 CL	Commands for distributed platforms
Copy a process	Copy Process	DEFINE PROCESS(x) LIKE(y)	CPYMQMPRC	
Create a process	Create Process	DEFINE PROCESS	CRTMQMPRC	
Delete a process	Delete Process	DELETE PROCESS	DLTMQMPPRC	
Display process attributes	Inquire Process	DISPLAY PROCESS	DSPMQMPRC	
Display process names	Inquire Process Names	DISPLAY PROCESS	WRKMQMPRC	
Work with a process			WRKMQMPRC	

Table 7. Commands for namelist administration. (See note 1)

Operation	PCF	MQSC	OS/400 CL	Commands for distributed platforms
Change a namelist	Change Namelist	ALTER NAMESPACE		
Copy a namelist	Copy namelist	DEFINE NAMESPACE(x) LIKE(y)		
Define a namelist	Create Namelist	DEFINE NAMESPACE		
Delete a namelist	Delete Namelist	DELETE NAMESPACE		
Display a namelist	Inquire Namelist	DISPLAY NAMESPACE		

Note:

1. Applies on AIX, HP-UX, OS/2 Warp, OS/390, Sun Solaris, and Windows NT only

Table 8 (Page 1 of 2). Commands for channel administration

Operation	PCF	MQSC (See note 1)	OS/400 CL	Commands for distributed platforms
Change channel attributes	Change Channel	ALTER CHANNEL	CHGMQMCHL	
Copy channel attributes	Copy Channel	DEFINE CHANNEL (x) LIKE (y)	CPYMQMCHL	
Create a channel	Create Channel	DEFINE CHANNEL	CRTMQMCHL	
Delete a channel	Delete Channel	DELETE CHANNEL	DLTMQMCHL	
Display a channel	Inquire Channel	DISPLAY CHANNEL	DSPMQMCHL	
Display channel names	Inquire Channel Names	DISPLAY CHANNEL	WRKMQMCHL	
Display channel status	Inquire Channel Status	DISPLAY CHSTATUS	WRKMQMCHST	
Display distributed queuing		DISPLAY DQM (See note 2)		
Ping a channel	Ping Channel	PING CHANNEL	PNGMQMCHL	
Reset a channel	Reset Channel	RESET CHANNEL	RSTMQMCHL	
Resolve a channel	Resolve Channel	RESOLVE CHANNEL	RSVMQMCHL	
Start a channel	Start Channel	START CHANNEL	STRMQMCHL	runmqchl
Start a channel initiator	Start Channel Initiator	START CHINIT (See note 2)	STRMQMCHLI	runmqchi
Start a channel listener	Start Channel Listener	START LISTENER (See note 3)	STRMQMLSR	runmqslr (See note 4)
Stop a channel	Stop Channel	STOP CHANNEL	ENDMQMCHL	

Table 8 (Page 2 of 2). Commands for channel administration

Operation	PCF	MQSC (See note 1)	OS/400 CL	Commands for distributed platforms
Stop a channel initiator		STOP CHINIT (See note 2)		
Stop a channel listener		STOP LISTENER (See note 2)		endmqlsr (See note 5)
Work with channels			WRKMQMCHL	
Work with channel status			WRKMQMCHST	
Notes: <ol style="list-style-type: none"> Does not apply on OS/390 if you are using CICS for distributed queuing Applies on OS/390 only Applies on AIX, HP-UX, OS/2 Warp, OS/390, OS/400, Sun Solaris, and Windows NT only Applies on AIX, Digital OVMS, HP-UX, OS/2 Warp, Sun Solaris, Tandem NSK, and Windows NT only Applies on AIX, HP-UX, OS/2 Warp, Sun Solaris, and Windows NT only <p>In MQSeries for Tandem NonStop Kernel, use TS/MP or the control command runmqlsr to start TCP channel listeners.</p>				

Table 9. Commands for cluster administration. (See Note 1)

Operation	PCF	MQSC	OS/400 CL	Commands for distributed platforms
Display cluster information	Inquire Cluster Queue Manager	DISPLAY CLUSQMGR		
Refresh cluster information	Refresh Cluster	REFRESH CLUSTER		
Reset cluster	Reset Cluster	RESET CLUSTER		
Resume cluster processing	Resume Queue Manager Cluster	RESUME QMGR		
Suspend cluster processing	Suspend Queue Manager Cluster	SUSPEND QMGR		
Note: <ol style="list-style-type: none"> Applies on AIX, HP-UX, OS/2 Warp, OS/390, Sun Solaris, and Windows NT only 				

Table 10. Commands for security administration

Operation	PCF	MQSC (See note 1)	OS/400 CL	Commands for distributed platforms
Display object authority			DSPMQMAUT	dspmqaut
Grant object authority			GRTMQMAUT	setmqaut
Revoke object authority			RVKMMAUT	setmqaut
Alter security options		ALTER SECURITY		
Display security settings		DISPLAY SECURITY		dspmqaut
Refresh security		REFRESH SECURITY		
Set a reverification flag		RVERIFY SECURITY		
Note: <ol style="list-style-type: none"> Applies on OS/390 only 				

Table 11 (Page 1 of 2). Commands for system-dependent function

Operation	PCF	MQSC (see note 1)	OS/400 CL	Commands for distributed platforms
Alter trace parameters		ALTER TRACE		
Display trace activity		DISPLAY TRACE		
Start a trace		START TRACE	TRCMQM	strmqtrc (See note 2)
Stop a trace		STOP TRACE	TRCMQM	endmqtrc (See note 2)
Archive a log		ARCHIVE LOG		
Define a buffer pool		DEFINE BUFFPOOL		
Define a page set		DEFINE PSID		
Display page set information		DISPLAY USAGE		
Alter a storage class		ALTER STGCLASS		
Define a storage class		DEFINE STGCLASS		
Delete a storage class		DELETE STGCLASS		
Display storage class information		DISPLAY STGCLASS		
Display a thread		DISPLAY THREAD		
Recover a bootstrap data set		RECOVER BSDS		
Resolve in-doubt threads		RESOLVE INDOUBT		
Display the command server		DISPLAY CMDSERV	DSPMQMCSVR	dspmqcsv
Start the command server		START CMDSERV	STRMQMCSVR	strmqcsv
Stop the command server		STOP CMDSERV	ENDMQMCSVR	endmqcsv
Reset an IMS transaction pipe		RESET TPIPE		
Display an object name			DSPMQMOBJN	
Start a service job			STRMQMSRV	
End a service job			ENDMQMSRV	
Start the administrator			STRMQMADM	
Record an object image			RCDMQMIMG	rcdmqimg (See note 3)
Recreate an object			RCRMQMOBJ	rcrmqobj (See note 3)
Display MQSeries formatted trace output				dspmqtrc (See note 4)
Dump contents of MQSeries log				dmpmqlog (See note 5)

Table 11 (Page 2 of 2). Commands for system-dependent function

Operation	PCF	MQSC (see note 1)	OS/400 CL	Commands for distributed platforms
Run dead-letter queue handler			STRMQMDLQ	runmqdlq (See note 6)
Notes: <ol style="list-style-type: none"> 1. Applies on OS/390 only 2. Does not apply on AIX 3. Does not apply on Tandem NSK 4. Applies on AT&T, HP-UX, SINIX and DC/OSx, Sun Solaris, and Tandem NSK 5. Applies on AIX, HP-UX, OS/2 Warp, Sun Solaris, and Windows NT 6. Applies on AIX, HP-UX, OS/2 Warp, Sun Solaris, Tandem NSK, and Windows NT <p>In MQSeries for Tandem NonStop Kernel, as an alternative to the control commands dspmqcsv, strmqcsv, and endmqcsv, you can use PATHCOM commands.</p>				

Table 12. Other control commands in MQSeries for Tandem NonStop Kernel

Operation	Commands
Alter queue volume	altmqfls
Perform housekeeping on a queue manager	cleanqmq
Convert V1.5.1 queues and channels to V2.2	cnv1520
Convert V1.5.1 messages to V2.2	cnvmgs
Convert client channel definition table	cnvclchl
Install MQSeries for Tandem NonStop Kernel	instmqmq
Note: As an alternative to the control command runmqtrm , you can use PATHCOM commands. There are no MQSC or PCF equivalents of commands in this group.	

Where to find more information

For information about MQSeries administration on your platform, see the following chapters:

- Chapter 12, “Administration of MQSeries for AS/400” on page 73
- Chapter 17, “Administration of MQSeries for Digital OpenVMS” on page 93
- Chapter 22, “Administration of MQSeries for OS/2 Warp” on page 111
- Chapter 28, “Administration of MQSeries for OS/390” on page 137
- Chapter 47, “Introduction to MQSeries for Windows” on page 215
- Chapter 35, “Administration of MQSeries for Tandem NSK” on page 165
- Chapter 39, “Administration of MQSeries on UNIX systems” on page 183
- Chapter 41, “Introduction to MQSeries on VSE/ESA” on page 189
- Chapter 45, “Administration of MQSeries for Windows NT” on page 207

Chapter 6. Introduction to MQSeries instrumentation events

You can use the MQSeries instrumentation events to monitor the operation of queue managers. This chapter tells you what these events are, and describes how they can be used for system measurement and system management purposes.

The chapter contains these sections:

- “Monitoring queue managers”
- “What is an instrumentation event?”
- “Format of event messages” on page 48
- “Where to find more information” on page 48

Instrumentation events are supported by the following:

- MQSeries for AS/400
- MQSeries for Digital OpenVMS
- MQSeries for OS/2 Warp
- MQSeries for OS/390
- MQSeries for Tandem NSK
- MQSeries on UNIX systems
- MQSeries for Windows NT
- MQSeries for Windows Version 2.1

Monitoring queue managers

An *instrumentation event* causes a special message, called an *event message*, to be generated by a queue manager whenever a set of predefined conditions occurs within the execution of your application.

You can write a system-monitoring application that collects event messages from many queue managers on different platforms, analyses them, and presents them to an administrator in summary form. This would allow you to monitor all the MQSeries products in your system from a single node.

Instrumentation events also enable applications acting as agents for other administration networks, for example NetView®, to monitor events and create the appropriate alerts.

What is an instrumentation event?

In MQSeries an instrumentation event is a logical combination of conditions that is detected by a queue manager. The result of such an event is that the queue manager puts a special message, called an *event message*, on an event queue.

For example, the conditions giving rise to a *queue full* event are:

- Queue full events are enabled for a specified queue, and
- An application issues an **MQPUT** call to put a message on that queue, but the call fails because the queue is full

Other conditions can also give rise to instrumentation events. For example:

- A threshold for the number of messages on a queue is reached
- A channel instance is started or stopped
- An application attempts to open a queue specifying a user ID that is not authorized

Some instrumentation events must be enabled before they can be generated; this is described in “Enabling and disabling events” on page 47.

What types of event are there?

MQSeries events can be categorized as follows:

Queue manager events

These events are related to the definitions of resources within queue managers. For example, when an application attempts to put a message to a queue that does not exist.

Performance events

These events are notifications that a threshold has been reached by a resource. For example, when a queue depth threshold has been reached or, following a get, when the queue was not serviced within a predefined time limit.

Channel events

These events are reported by channels as a result of conditions detected during their operation. For example, when a channel instance is stopped.

Event notification through event queues

When an event occurs, the queue manager puts an event message on the appropriate event queue. The event message contains information about the event that you can retrieve by writing a suitable MQSeries application program that:

- Gets the message from the queue
- Processes the message to extract the event data

Each category of event has its own event queue. All events in that category result in an event message being put onto the same queue.

Table 13. Event queue contents	
This event queue...	Contains messages from...
SYSTEM.ADMIN.QMGR.EVENT	Queue manager events
SYSTEM.ADMIN.PERFM.EVENT	Performance events
SYSTEM.ADMIN.CHANNEL.EVENT	Channel events

You can define event queues as either local or remote queues. If you define all your event queues as remote queues on the same queue manager, you can centralize your monitoring activities.

You must not define event queues as transmission queues, or initiation queues, because event messages have formats that are incompatible with the formats of messages required for those queues.

Using triggered event queues

You can set up the event queues with triggers, so that when an event is generated, the event message being put onto the event queue starts a (user-written) monitoring application. This application can process the event messages and take appropriate action. For example, certain events might require that an operator be informed, while other events might start off an application that performs some administration tasks automatically.

When an event queue is unavailable

If an event occurs when the event queue is not available, the event message is lost. For example, if you do not define an event queue for a category of event, all event messages for that category will be lost. The event messages are *not*, for example, saved on the dead-letter queue. An event queue might be unavailable for many different reasons, for example:

- The queue has not been defined
- The queue has been deleted
- The queue is full
- The queue has been put-inhibited

The absence of an event queue does not prevent the event from occurring. For example, after a performance event, the queue manager changes the queue attributes and might, depending on the event, reset the queue statistics. This happens whether or not the event message is put on the performance event queue.

Enabling and disabling events

You can enable and disable events by specifying the appropriate values for queue manager or queue attributes, or both, depending on the type of event. Commands are provided with the appropriate MQSeries products to allow you to set these attributes.

Note: Attributes related to events for both queues and queue managers can be set and inquired upon by command only. They are not supported by the MQI functions **MQSET** and **MQINQ**.

How you enable and disable events depends on the category of the event:

- Queue manager events are enabled by setting attributes on the queue manager.
- Performance events as a whole must be enabled on the queue manager, otherwise no performance events can occur. Then, you enable the specific performance events by setting the appropriate queue attribute. You also have to specify the conditions that give rise to the event.
- Channel events do not require enabling, they occur automatically. Similarly, channel events cannot be disabled.

Format of event messages

Event messages contain information about the event and its origin. Typically, these messages are processed by a system-management application program that is tailored to meet the requirements of the site at which it runs.

As with all MQSeries messages, an event message has two parts: a message descriptor, and the message data.

Message descriptor

The descriptor of an event message is a standard descriptor, as defined in “MQMD - Message descriptor” in the *MQSeries Application Programming Reference* manual. Some of the values in the descriptor might be of particular interest to a system-monitoring application, for example, the date and time when the event message was put on the event queue.

Event message data

The message data specifies:

- That the message is an event message.
- The category of the event, that is, whether the event is a queue manager, performance, or channel event.
- A reason code specifying the cause of the event.
- Event data specific to the event. This includes the name of the queue manager and, where appropriate, the name of the queue.

Where to find more information

More information on how to use events and details on the various types of event message, can be found in Part 1, “Event monitoring” in the *MQSeries Programmable System Management* manual.

Information about enabling events can be found in “ALTER QMGR” in the *MQSeries Command Reference* manual.

Chapter 7. Introduction to MQSeries clients and servers

This chapter introduces the concept of MQSeries clients and servers and describes how they can be of benefit in your MQSeries installation. It gives you information about some of the items that you need to consider when you are planning your applications.

The chapter has the following sections:

- “What are MQSeries clients and servers?”
- “Communication between clients and servers” on page 50
- “Installing clients and servers” on page 51
- “Product support for MQSeries clients” on page 52
- “Migrating from MQSeries Version 2 products to Version 5” on page 53
- “Applications on Version 5 clients” on page 53
- “Where to find more information” on page 53

What are MQSeries clients and servers?

An *MQSeries client* is a part of an MQSeries product that can be installed on a machine without installing the full queue manager. It accepts Message Queue Interface (MQI) calls from application programs, and passes MQI requests to an *MQSeries server* that is executing on another processor.

The *MQSeries server* is a full queue manager, which can accept MQI calls directly from application programs that are running on the server processor; in addition, it can accept MQI requests from MQSeries clients.

This allows you to have an application that uses the MQI running on one machine, the client machine, and the queue manager itself running on a different machine.

Clients and servers can be useful in a number of situations:

- Where there is no full MQSeries implementation for the machine (for example, because it is a DOS platform)
- Where the client machine is too small, or of insufficient processing power, to run a full queue manager with good performance
- Where you want to allow the application program on the client processor to connect to multiple queue managers on different server processors
- Where you might want to reduce systems administration effort

You can run an MQSeries application in both a full MQSeries environment and in a MQSeries client environment without changing your code. However, the libraries you use at link-edit time determine the environment your application must run in.

When an application program in the client issues an MQI call, the client formats the parameter values of the call into an MQI request, and sends the request to the server. The server receives the request, performs the action specified in the request, and sends a response back to the client. The response is used by the client to generate information that is returned to the application program using the normal MQI return mechanism.

An additional function supported by MQSeries clients is the ability of an application program to be connected to more than one queue manager at a time, with the queue managers being on different processors or on the same processor.

Communication between clients and servers

An MQSeries client communicates with an MQSeries server, using an *MQI channel*, which is used to transfer MQI call requests from the client to the server, and responses from the server back to the client.

MQI channels differ from *message channels* (that are used to connect queue managers) in two ways:

- **An MQI channel is bidirectional.** One MQI channel can be used to send requests in one direction, and responses in the opposite direction.

With message channels, data can be passed in one direction only. If two-way communication is required between two queue managers (for example, in the situation where reply messages are to be sent to the same queue manager that handled an initial request message), then two message channels are required, one to handle messages travelling in one direction, and another for messages travelling in the other direction.

- **Communication on an MQI channel is synchronous.** When an MQI request is transmitted from a client to a server, the MQSeries client product must wait for a response from the server before it can send the next MQI request.

With message channels, the message traffic on the channel is time-independent. Multiple messages can be sent from one queue manager to the other, without the sending queue manager having to wait for any replies from the receiving queue manager.

The transmission protocol that is to be used on an MQI channel is specified as part of the channel definition. The MQSeries application program is unaware of the particular protocol that is being used on the channel. Furthermore, in the situation where an application program is connected to more than one MQSeries server, the MQI channels that are used for these connections could use different protocols. For example, an application program could connect to one queue manager using TCP on one channel, and to another queue manager using NetBIOS on a different channel.

With both MQI and message channels, a channel definition is required at each end of the channel, and each of these definitions must include a *channel type* and a *channel name*. You can choose to use different channel types according to the application you are designing, but the same channel name must be used at both ends of the channel.

Installing clients and servers

For those products that support both clients and servers, the product, as delivered, contains the files for the MQSeries server, together with the client files for the server platform and several other platforms.

For example, if you order MQSeries for AIX, in addition to the base product you will receive files for the AIX, DOS, HP-UX, OS/2 Warp, Sun Solaris, and Windows clients.

The client software can be loaded to memory in the client processor either from the disk on the client or server machine, or from a disk on a LAN file server.

You can install the client and the server either by installing from the media on which the products are supplied, to the client or server disk, or by installing to a LAN file server, and loading the client or server from there.

MQSeries for AS/400, MQSeries for OS/390, MQSeries for Tandem NSK, and MQSeries for VSE/ESA cannot be used as MQSeries clients and do not include any client files. However, they do include the MQSeries server code needed to support any clients that you might choose to install, either from another MQSeries product or from the Internet.

MQSeries clients from IBM Transaction Processing SupportPacs

You can install the MQSeries client files from an IBM Transaction Processing SupportPac™.

The IBM Transaction Processing SupportPacs library consists of material that complements the family of CICS and MQSeries products marketed by IBM. The Transaction Processing SupportPacs library is available on the Internet at:

<http://www.software.ibm.com/ts/mqseries/txppacs/txpsumm.html>

MQSeries client software is available at no charge but is subject to the IPLA and License Information terms defined when requesting the MQSeries clients on the Internet. You have the right to make as many copies of the MQSeries client as necessary.

The VM/ESA client is shipped with the VM/ESA product; it is not available as a SupportPac.

National language considerations for clients

The client part of an MQSeries product includes a file that contains all the program and operator messages that are used by the product. This file has been translated to the national languages of the server product, so that no further translation of these messages is required.

Data conversion considerations for clients

The data conversion facilities provided for MQSeries application programs are the same as those that are available for application programs that are executing with MQSeries servers:

- For certain built-in formats, conversion can be performed during the processing of an **MQGET** call, if the data conversion option is included in the call.

- For application defined formats, the conversion can be performed by a user-exit program, called during the processing of an **MQGET** call.

For further information about data conversion with MQSeries clients and servers, refer to Chapter 11, “Writing data-conversion exits” in the *MQSeries Application Programming Guide*.

Product support for MQSeries clients

The platform support for MQSeries clients and servers is as follows. Any of the MQSeries products listed is installed as a *Base product and Server (Base product and Client Attachment feature* on MQSeries for OS/390). These MQSeries products can accept connections from the MQSeries clients on the platforms listed, subject to differences in coded character set identifier (CCSID) and communications protocol.

Note: If you are using previous versions of MQSeries products, make sure that code conversion from the CCSID of your client is supported by the server. See the language support tables in Appendix F, “Code page conversion tables” in the *MQSeries Application Programming Reference* manual.

The following MQSeries products:

- MQSeries for AIX Version 5.1
- MQSeries for AS/400 Version 4 Release 2.1
- MQSeries for AT&T GIS UNIX Version 2.2
- MQSeries for Digital OpenVMS Version 2.2
- MQSeries for HP-UX Version 5.1
- MQSeries for OS/2 Warp Version 5.1
- MQSeries for OS/390 Version 2 Release 1
- MQSeries for SINIX and DC/OSx Version 2.2
- MQSeries for Sun Solaris Version 5.1
- MQSeries for Tandem NSK Version 2.2
- MQSeries for VSE/ESA Version 2.1
- MQSeries for Windows NT Version 5.1

can accept connections from MQSeries clients on:

- AIX
- AT&T GIS UNIX (this platform has become NCR UNIX)
- Digital OpenVMS
- DOS
- HP-UX
- OS/2
- SINIX and DC/OSx
- Sun Solaris
- VM/ESA
- Windows 3.1
- Windows 95
- Windows 98
- Windows NT

MQSeries clients on other platforms

Further MQSeries clients that can connect to the MQSeries products listed above are available through the Internet. For details of the platform and support status, see:

<http://www.software.ibm.com/ts/mqseries/txppacs/txpsumm.html>

Migrating from MQSeries Version 2 products to Version 5

The internal format of the channel definition table has been changed in the MQSeries Version 5 products for AIX, HP-UX, OS/2 Warp, Sun Solaris, and Windows NT.

A Version 5 client will continue to work with a Version 2 client channel definition table (by default, the client channel definition table is called AMQCLCHL.TAB). However, a Version 2 client cannot read a Version 5 client channel definition table. If your client channel definition table is produced by a Version 5 server, you must use Version 5 clients. In this case, reinstall the MQSeries client code from an MQSeries Version 5 server.

Applications on Version 5 clients

A Version 5 client can connect to all queue managers, non-version 5 as well as Version 5. If you are connecting to a non-version 5 queue manager you cannot use the new Version 5 features and structures in your MQSeries application on the client.

Where to find more information

More information about MQSeries clients can be found in the *MQSeries Clients* manual.

Chapter 8. Introduction to the MQSeries Framework

This chapter describes the MQSeries Framework. It contains the following sections:

- “Why the MQSeries Framework?”
- “Services and components provided” on page 56

Why the MQSeries Framework?

The MQSeries Framework offers users and independent software vendors the opportunity to extend or replace queue manager functionality, using defined interfaces.

These interfaces are provided in various forms. Some, for example the MQSeries name service interface, are provided by user-supplied modules that interface to the queue manager through an application programming interface. The trigger monitor interface, on the other hand, is provided by means of trigger messages that are written to a special queue.

In some cases components are shipped ready for you to use. You can choose whether to make use of them, and you can also decide to use your own versions instead of, or as well as, the supplied versions.

Not all MQSeries products provide all of the interfaces defined by the MQSeries framework. When an interface has been provided by an MQSeries product on a particular platform, it will be retained for future releases on that platform.

The major reasons for allowing modifications of the functions are:

- To provide the flexibility of choosing whether to use components provided by MQSeries products, or to replace or augment them with others
- To allow independent software vendors to participate, by providing components that might be using new technologies, without requiring internal changes to MQSeries products
- To allow MQSeries to exploit new technologies faster, and so provide products sooner

The components of the MQSeries Framework are:

- Trigger monitor interface (TMI)
- Message channel interface (MCI)
- Name service interface (NSI)
- Security enabling interface (SEI)
- Data conversion interface (DCI)

These are shown in Figure 9, and are outlined in the following text. A detailed definition of each interface can be found in the book or books indicated.




Figure 9. The MQSeries Framework

Invoking MQSeries Framework components

Where components are supported, they can be installed as necessary to provide some, or all, of the available function.

The queue manager refers to an initialization file to determine the particular components installed, and to get the information that it requires to invoke these components.

Services and components provided

This section gives information on the MQSeries Framework components and on the particular components that are provided by the MQSeries products.

Trigger monitor interface (TMI)

When messages arrive on a queue, the queue manager can generate trigger messages on a special kind of queue called an initiation queue. The generation of these messages is controlled by setting attributes of the queue.

The structure of the data in a trigger message is defined by the TMI. Trigger messages can be read by a long-running transaction called a trigger monitor, which starts applications to process the messages that have arrived on the queue.

MQSeries provides trigger monitors for use in various environments. When they start applications, they pass a defined structure as a parameter to the application. You can also provide your own trigger monitors, making use of the defined format of the trigger message. Your trigger monitors can pass the same structure as the supplied ones, or you can choose to do something different.

See the information on the trigger monitor interface (TMI) in Chapter 14, "Starting MQSeries applications using triggers" in the *MQSeries Application Programming Guide* for more information.

Message channel interface (MCI)

If a message is destined to go to a remote queue manager, the queue manager places it on a special kind of queue called a transmission queue. The message data has a header that includes the names of the destination queue manager and queue.

Triggering (see “Trigger monitor interface (TMI)” on page 56) can be used to start a process that reads the messages from a transmission queue, and sends them to their destination. Alternatively, this process can be started by an administrator.

MQSeries provides message channel agent (MCA) programs that transmit messages to MCAs on other queue managers. Commands are also provided to carry out channel administration.

You can provide alternative processes to take messages from transmission queues, and:

- Transmit the messages to similar processes you have provided on other queue managers, or
- Insert the messages into some other messaging system.

For details of how to implement the MCI, refer to the information on the transmission queue header structure (MQXQH) in “MQXQH - Transmission queue header” in the *MQSeries Application Programming Reference* manual to see how to write a message channel agent (MCA) program.

You can take advantage of triggering to initiate your process. You might need to provide administrative functions, similar to those available for MQSeries channels, for defining and monitoring the activity of your processes.

Note that the MCAs you write cannot communicate with MQSeries-supplied MCAs.

Name service interface (NSI)

Queue managers provide functions that allow administrators to define and manipulate queue definitions. Each queue manager maintains a directory of the queues that have been defined to it.

When an application opens a queue, the local queue manager looks up the queue in its directory if the application does not provide the name of a remote queue manager to which the queue belongs. If the queue is not found in that directory, the open normally fails.

However, you can install a naming service, which will be invoked if the queue manager is unable to resolve a queue name. Your service is passed the name of the queue that cannot be resolved. If your service recognizes the name, it returns the name of the queue manager to which the queue belongs.

The service provides the following functions:

- Lookup queue - given a queue name, finds the directory entry that contains that name, and returns the queue manager name
- Insert queue - inserts a new entry into the directory
- Delete queue - deletes an entry from the directory

The interface to the naming service is a programming interface, called the NSI. It is described in Chapter 13, “Name service” in the *MQSeries Programmable System Management* manual.

The NSI is available on MQSeries for OS/2 Warp, MQSeries for Windows NT, and MQSeries on UNIX systems.

DCE naming component

The *DCE naming* installable component provides naming services for queues within one DCE cell.

Details of this component can be found in Chapter 13, “Name service” in the *MQSeries Programmable System Management* manual.

The component is provided with MQSeries for AIX, Digital OpenVMS, HP-UX, OS/2 Warp, Sun Solaris, and Windows NT, but is not invoked unless it is included in the queue manager initialization file. The component requires that DCE support is available.

Security enabling interface (SEI)

There are three parts to the SEI:

- Authorization service
- User identifier service
- Message channel agent exits

See also Chapter 3, “Introduction to MQSeries security” on page 21 for further information.

Authorization service

This service provides access control facilities to the queue manager when an application issues an MQI call (for example, MQOPEN) or a command (for example, DELETE QLOCAL) that requires an authorization check to be carried out.

This enables the queue manager to check that users, or programs, have the appropriate authority for the actions they are trying to perform on queue manager objects.

The authorization service provides the following functions:

- Check object authority
- Set object authority
- Set initial authority
- Delete object authority
- Get object authority
- Copy all object authority

You can install your own version of this service, which can either be self-contained, or might in turn interface to some other authorization service that is available on the platform. Your service is invoked through a programming interface, which is part of the SEI. It maintains (either itself or by using another underlying service) lists of authorizations, and upon request returns information to the queue manager about whether a particular principal has authority to perform a certain action on a specified object.

This service is provided on MQSeries for UNIX systems, MQSeries for OS/2 Warp, and MQSeries for Windows NT.

Object authority manager: The *object authority manager (OAM)* is an installable component that provides authorization services.

The component is provided as part of the MQSeries products on the following platforms:

- Digital OpenVMS
- Tandem NSK
- UNIX systems
- Windows NT

MQSeries for OS/2 Warp does not provide an authorization component, but is designed to accept any components (that provide authorization service functions) you might want to supply or obtain from independent software vendors.

User identifier service

On OS/2 Warp, it is not necessary for a user to log into the system, and therefore the queue manager cannot normally find a specific user identifier to associate with an application running on OS/2 Warp.

The user identifier service defines a programming interface, part of the SEI, which allows you to install your own service to supply a user identifier to the queue manager.

This service is provided only on MQSeries for OS/2 Warp.

This service is used by the queue manager to obtain a user ID. By default, the queue manager places the user ID in the message descriptor of messages when it puts them on queues, so that the application program that gets the messages can verify that they originated from authorized users or programs.

The queue manager can also make use of this user identifier for authorization checking.

The user identifier service provides just one function:

- Find user ID - obtain the predefined user ID

The user identifier service is not provided for client applications, for which another technique is available. See Chapter 7, "Setting up MQSeries client security" in the *MQSeries Clients* manual.

Environment user ID: The *environment user ID* installable component provides the user identifier service, by obtaining a user ID value from an environment variable. The value of this variable is set when the component is installed.

Message channel agent exits

A mechanism for transmitting messages from one queue manager to another is referred to as a message channel. At each end of a channel a program called a message channel agent (MCA) controls the transmission of messages along that channel.

Exit points are defined at various points in the operation of an MCA. You can define functions that will be invoked at these points. Exit points are of particular relevance to security, and are therefore part of the SEI. They are:

- Security exits

At each end, a security exit is invoked after communication has been established with the partner, but before message transfer starts. Each security exit has the opportunity to exchange security messages with the security exit at the partner, in order to satisfy itself of the partner's authenticity. If either is not satisfied, it can prevent any message transfer.

- Message exits

A message exit is invoked at the sending end just before a message is transferred, and at the receiving end just before it is stored. It has the opportunity to change any information in the message, including information in the message header such as the user identifier. This facility can be used to translate user identifiers on entering a new security domain or, for example, to set a blanket user identifier that has low authorization when receiving messages along a channel from an untrusted node. Message exits can also reject or reroute messages.

On AIX, HP-UX, OS/2 Warp, OS/400, Sun Solaris, and Windows NT, you can call more than one message exit.

- Send and receive exits

These are invoked just before any transmission is sent, and just after one is received. You can make use of this to provide encryption of sensitive data sent across open networks.

On AIX, HP-UX, OS/2 Warp, OS/400, Sun Solaris, and Windows NT, you can call more than one send or receive exit.

You can define different exit modules for different channels.

See Chapter 35, "Channel-exit programs" in the *MQSeries Intercommunication* manual for further information about channel exits.

Data conversion interface (DCI)

Messages sent between platforms that normally use different encodings (for example, where integer fields are byte-swapped) and coded character set identifiers (CCSIDs) require conversion. An application getting a message from a queue can request that the queue manager converts the message data into the encoding and CCSID of its choice, which will normally be the standard ones in use on the platform on which it is running.

The message header contains information about the encoding and CCSID of the message data. It also contains a format name, which identifies the shape of the data. You can install exits, which have the same names as format names, to perform data conversions on the corresponding messages. These exits interface to the queue manager through a programming interface, called the DCI.

To help you provide these exits, MQSeries provides a utility that accepts a C language structure definition and generates C source code that can be built to provide an exit.

Built-in conversion is provided for MQSeries-defined standard formats.

The DCI is implemented only on MQSeries for OS/390, MQSeries for OS/2 Warp, MQSeries for Windows NT, MQSeries on UNIX systems, and MQSeries for AS/400. When transmitting messages from a platform that does support it to one that does not, you can ask for this function to be carried out on all messages sent along a particular channel. This means that when the messages arrive at their destination, they are already in the standard encoding and CCSID for that platform.

See Chapter 11, “Writing data-conversion exits” in the *MQSeries Application Programming Guide* for information about data-conversion exit programs.

Part 2. Planning for MQSeries for AS/400

Chapter 9. Introduction to MQSeries for AS/400	65
Planning for MQSeries	65
Preparing your applications for MQSeries	66
Planning to use MQSeries in a network	66
Planning recovery services with MQSeries	67
Planning data security with MQSeries	67
Administration of MQSeries	67
Support for R/3 with MQSeries	67
Concurrent use-based pricing and MQSeries	67
Installing and setting up MQSeries	68
Installing MQSeries	68
Setting up MQSeries	68
 Chapter 10. Backup and recovery planning for MQSeries for AS/400	69
Journal control with MQSeries	69
 Chapter 11. Security planning for MQSeries for AS/400	71
Naming differences between OS/400 and MQSeries for AS/400	71
Security planning and MQSeries	71
Security exits with MQSeries	72
 Chapter 12. Administration of MQSeries for AS/400	73
Managing objects with MQSeries	73
Commands on MQSeries	73
Managing communications with MQSeries	74
Remote administration with MQSeries	74
Managing remote systems from MQSeries	74
Managing MQSeries from remote systems	75
Using the MQSeries administration utility	75
 Chapter 13. Storage planning for MQSeries for AS/400	77
Product storage for MQSeries	77
Journal storage for MQSeries	77
Storage for other data sets used by MQSeries	78
Message queues for MQSeries	78
Performance information for MQSeries	78

Chapter 9. Introduction to MQSeries for AS/400

MQSeries for AS/400 runs on an AS/400 capable of running OS/400 to provide messaging and queuing applications support.

This chapter includes basic information on:

- “Planning for MQSeries”
- “Support for R/3 with MQSeries” on page 67
- “Concurrent use-based pricing and MQSeries” on page 67
- “Installing and setting up MQSeries” on page 68

For more information on the hardware and software environment needed by the MQSeries for AS/400 product, see “MQSeries for AS/400” on page 235.

Planning for MQSeries

This chapter helps you to plan for the introduction of MQSeries for AS/400 into your enterprise and introduces the items you must consider when doing this planning.

This chapter does not provide detailed information to enable you to perform the installation of MQSeries for AS/400. That information is provided in the *MQSeries for AS/400 Administration Guide*.

There are several stages in planning for the use of MQSeries for AS/400 that you must go through. They are:

1. Preparing your applications for the use of MQSeries for AS/400
2. Planning to include MQSeries for AS/400 in a network
3. Preparing to install MQSeries for AS/400
4. Planning to set up MQSeries for AS/400

A prime requirement for a message delivery system is that it must be reliable. Many functions are built into MQSeries for AS/400 to ensure that:

- Messages are not lost despite system failures
- Messages are not delivered more than once
- Messages are not accessed or delivered to unauthorized persons or applications

MQSeries for AS/400 uses OS/400 journaling and other facilities to support these functions.

You must also plan for the operation and administration of MQSeries for AS/400 in your enterprise and consider the implementation of the MQSeries for AS/400 security facilities in addition to those of OS/400. Brief outlines of these planning operations are included in this chapter.

Preparing your applications for MQSeries

MQSeries for AS/400 brings the Message Queue Interface (MQI) to your applications. This interface allows you to modify existing applications and to write new applications. The MQI removes much of the need to understand the network and communication systems that you use. Thus you can expect to generate applications more speedily than before. However, you must plan to take advantage of the MQI by planning its use in your applications and by understanding the ways in which it assists you.

You can find more information on how to use the MQI in your applications by referring to the *MQSeries Application Programming Guide*.

Interfacing with CICS

With the MQSeries for AS/400 products you can create application programs for the CICS for AS/400 transaction environment. These applications can use the MQI to communicate with CICS or non-CICS programs in any of the environments supported by the MQSeries products.

Using C++

You can use the OS/2 environment to write C++ programs for AS/400, using Client Access/400 to provide links to an AS/400 host, and VisualAge® C++ for AS/400, which is a cross-compiler add-on for VisualAge C++ for OS/2. (Client Access/400 is an OS/2 program; it is not related to the MQSeries concept of clients.)

An OS/2 programmer can use Client Access/400 to mount an OS/400 file system. MQSeries for AS/400 includes an image for such a file system (IFS), containing a number of items specifically for OS/2 cross-compiler usage.

An OS/2 installation program is provided with MQSeries for AS/400 V4R2M1 on the IFS. This installs an OS/2 toolkit for users of VisualAge C++ for AS/400, including C and C++ header files, C++ sample program source, and C++ documentation. See “Compiling C++ sample programs for AS/400, using OS/2” in the *MQSeries Using C++* manual for more information.

Planning to use MQSeries in a network

MQSeries for AS/400 uses the distributed queuing facility to exchange messages between MQSeries platforms using the SNA LU 6.2 and TCP transmission protocols.

You must consider how you will attach MQSeries for AS/400 to a network, and how you will define the channels that are used to exchange messages.

According to the way that you have set your systems up, security checks can be performed at various times. MQSeries for AS/400 does not provide communications link authorization or data encryption on these links. Instead, various exits are provided that can be used by your applications to provide these facilities.

“MQSeries interoperability summary” on page 226 shows some of the links that are possible to other MQSeries products, and the transmission protocols that are used on these links. For further information about distributed queuing, refer to Part 5, “DQM in MQSeries for AS/400” in the *MQSeries Intercommunication* manual.

Planning recovery services with MQSeries

MQSeries for AS/400 makes use of the OS/400 journaling service to allow backup and recovery of the messaging system. Chapter 10, “Backup and recovery planning for MQSeries for AS/400” on page 69 introduces you to the recovery facilities and to the items you must consider in order to include MQSeries for AS/400 in your backup and recovery plans.

Planning data security with MQSeries

MQSeries for AS/400 makes use of the existing OS/400 security management facilities. This book indicates the particular way that MQSeries for AS/400 uses the standard OS/400 security.

Administration of MQSeries

A summary of the administration facilities provided by the MQSeries for AS/400 products is given in Chapter 12, “Administration of MQSeries for AS/400” on page 73. Full details of these facilities can be found in the *MQSeries for AS/400 Administration Guide*.

Support for R/3 with MQSeries

The MQSeries link for R/3 for AS/400 product provides an interface that enables you to integrate your R/3 application with applications running in other environments (including those on R/3 and R/2 environments).

The R/3 link works with the Application Link Enabling (ALE) layer of the R/3 system to transmit Intermediate Documents (IDocs) into and out of your R/3 system, using MQSeries messages and queues to carry the information. It extends the scope of your business by allowing you to link your R/3 applications to any other application that you can access through MQSeries, even when those applications require different data formats.

For more information, see the *MQSeries link for R/3 User's Guide*.

Concurrent use-based pricing and MQSeries

MQSeries for AS/400 counts concurrent users. A user is defined as a concurrent MQSeries connect. An MQSeries connect is established within an OS/400 job by an application program or command (including the Systems Administration Application and IBM-supplied commands) instigating an **MQCONN** call. It is terminated when an **MQDISC** call is instigated. (These calls can be issued explicitly or alternatively they can be implied by the use of the **MQOPEN** and **MQCLOSE** calls.) MQSeries does not charge for connections performed by the product itself, for example, the Command Server.

Each OS/400 job simultaneously connected to the active queue manager (server) is counted as one concurrent user. Only one connect can be established per job at any given time.

The number of users licensed for concurrent use is normally determined by the maximum who will be active at any one time. OS/400 provides monitoring and reporting for use-based programs. Customers will be advised when they approach the authorized user limit (90%). One use is included in the base MQSeries charge.

You can use the license information command (WRKLICINF) to manage the use of the MQSeries product.

Clients are not charged for per se, but their use implies a concurrent use at the server.

Installing and setting up MQSeries

MQSeries for AS/400 is installed by using the OS/400 GO LICPGM command, issued from the command line. When you issue this command, you are presented with a menu from which you can choose to install MQSeries for AS/400.

To prepare for the actual installation, you need to plan how much DASD you require in your OS/400 system to accommodate MQSeries for AS/400.

Assistance is given in Chapter 13, “Storage planning for MQSeries for AS/400” on page 77 to help you plan the amount of DASD required by MQSeries for AS/400.

Installing MQSeries

For MQSeries for AS/400, you must follow the instructions in the *MQSeries for AS/400 Administration Guide*.

The installation verification procedure is performed by creating and starting a queue manager, and creating the undelivered-message (dead-letter) queue.

Setting up MQSeries

MQSeries for AS/400 requires some setting up after installation in order to meet the individual and special requirements of your system, and to use your system resources in the most effective way. Below are the items you must consider:

- Define queues
 - Consider your naming conventions for queues
- Define trigger processes
- Define remote links
 - Define associated transmission queues
 - Consider your naming conventions for remote queues
 - Consider your naming conventions for channels

The setup procedures are described in the *MQSeries for AS/400 Administration Guide*.

Chapter 10. Backup and recovery planning for MQSeries for AS/400

MQSeries for AS/400 uses the journaling and recovery facilities provided by OS/400. You should be familiar with these facilities and refer to the *AS/400 Backup and Recovery* manual.

MQSeries for AS/400 has two unique journals that are created when MQSeries is created. MQSeries data events are recorded in these journals under the normal AS/400 controls. The events that are recorded are those that are required to recover MQSeries in case of failure. For message queues, all persistent messages are recorded in the journals; nonpersistent messages are not. This means that, in the event of a problem causing loss of messages that exist on a queue, the persistent contents can be recovered by use of the journals. The methods for recovery of such data or messages are discussed in the *MQSeries for AS/400 Administration Guide*.

You need to consider how the message data routed through MQSeries is to be journaled, and how you will extend your existing recovery plans to include MQSeries related data.

Journal control with MQSeries

When data in a journal receiver reaches a threshold value, a new one is automatically created, attached, and brought into use by MQSeries. The old journal receiver is not deleted by MQSeries; this is a task that must be completed by the system administrator. MQSeries will issue a message to the administrator containing some key dates that are associated with the journal receiver that has been replaced by the new one. It is up to your system administrator to decide what action must be taken to dispose of the old journal receiver using the dates supplied in the message. The action might be to move the old journal receiver to long term storage, or simply to delete it. However, deletion of journal receivers must be carefully considered as the records might still be needed for restart. The receivers might contain information regarding long-lived persistent messages. The choice is dependent on your strategy for data security and recovery.

Figure 10 on page 70 illustrates the concepts of journaling with MQSeries for AS/400 and shows how the message sent to the administrator contains date information pointers to indicate the journal receivers that should be saved to off-line media, those saved journal receivers that can be deleted, and those online journal receivers that can be freed. System backups have not been considered in the above description of journaling for MQSeries. You should continue to take system backups as required by your standard system operating procedures.

For more information on creating a system backup plan, refer to the *AS/400 Backup and Recovery* manual.




Figure 10. Journaling and date messages

Chapter 11. Security planning for MQSeries for AS/400

MQSeries for AS/400 uses OS/400 system security when accessing system objects. However, as an MQSeries product, the security accesses and controls are slightly different from other OS/400 operations.

You should be familiar with the security information contained in the *AS/400 Security - Reference* manual.

This chapter includes basic information about:

- “Naming differences between OS/400 and MQSeries for AS/400”
- “Security planning and MQSeries”
- “Security exits with MQSeries” on page 72

Naming differences between OS/400 and MQSeries for AS/400

MQSeries for AS/400 objects have 48-character names; OS/400 objects have 10-character names. MQSeries for AS/400 creates, owns, and maintains, a mapping between the 48-character MQSeries for AS/400 names and the 10-character names of the OS/400 objects that represent the MQSeries for AS/400 objects. If the MQSeries for AS/400 name is a valid OS/400 name, the same name is used in the mapping.

Security planning and MQSeries

The MQSeries for AS/400 objects that you must plan security authorities for are the queue manager object itself, the catalog object, and the administration object. You must also consider the security of your queues and processes.

The queue manager object contains the queue manager attributes, the catalog object contains the mapping information, and the administration object is used to hold the authorities to pass on or set message context.

MQSeries for AS/400 provides commands to grant, revoke, and query the object authority for MQSeries objects. This is because the MQSeries 48-character name is used, not the name of an OS/400 object. The authorities to MQSeries objects are those of the OS/400 application accessing the objects.

The mapping from MQSeries object authority to the system access authority occurs when an application is checked for the proper authority. For example, the authority on a queue is checked when an application issues an **MQOPEN** command through the MQI; it is not checked on each **MQGET** or **MQPUT**.

You need to plan how your users will be granted authority to the queue manager objects. You also need to plan authorizations to the programs and commands supplied with MQSeries. Authorities can be granted either individually, as a group, or by authorization lists. Granting authority follows normal OS/400 practice and you should refer to the *AS/400 Security - Reference* manual.

Note: The authorizations set by the MQSeries commands can be displayed using the DSPMQMAUT MQSeries command. You can also use the normal OS/400 commands, although it will not be obvious which MQSeries objects they apply to.

The authorizations can be copied from one user to another using the GRTMQMAUT MQSeries command, or by using the OS/400 grant object authority command.

For further details of MQSeries security handling, see the *MQSeries for AS/400 Administration Guide*.

Security exits with MQSeries

The message channels that are used for distributed queuing have exit facilities that can be used to invoke programs supplied by you. Examples of the types of function for which these exit facilities are intended include:

- Verification that the two partners at the ends of the channel are genuine, and have the appropriate security authorizations to take part in the exchange
- Encryption and decryption of messages

You need to consider whether you should provide exit programs to support your security plan.

For more information about security exits, refer to the Chapter 35, “Channel-exit programs” in the *MQSeries Intercommunication* manual.

Chapter 12. Administration of MQSeries for AS/400

This chapter is a summary of the administration facilities provided by the MQSeries for AS/400 products. The chapter has the following sections:

- “Managing objects with MQSeries”
- “Remote administration with MQSeries” on page 74
- “Using the MQSeries administration utility” on page 75

Details of the commands, command interfaces, and utilities that are provided by MQSeries for AS/400 are given in the *MQSeries for AS/400 Administration Guide*.

Managing objects with MQSeries

It is the administrator's job to monitor MQSeries for AS/400 and make any changes that might be necessary. To do this, the administrator needs to know where each MQSeries object resides, what its characteristics are, and who has access to it.

The administrator can manage and monitor the resources either by use of command line entries, or by using the administration utility supplied with the product. Alternatively, if you have sets of commands that you issue regularly, you can write a CL program. Details of how to write these administration programs are contained in the *MQSeries for AS/400 Administration Guide*.

MQSeries for AS/400 can access security checks to ensure that the user is authorized to issue particular commands for particular resources.

Commands on MQSeries

MQSeries for AS/400 supports the following administration facilities:

- **CL Commands**

MQSeries for AS/400 provides Control Language commands (CL commands). These can be issued either at the command line, or by writing a CL program.

Examples of CL tasks include:

- Authorize systems administrators
- Start and stop a queue manager
- Define, change, and display a queue
- Define, change, and display a process
- Define, test, and delete a channel

CL commands are designed exclusively for OS/400, and CL responses are designed to be human-readable. The commands perform similar functions to PCF commands, but the format is designed to match the standard OS/400 format, whereas PCF commands are platform independent, with both the command and response formats being intended for program use.

- **MQSeries commands (MQSC)**

With MQSeries for AS/400, you can build commands by entering the MQSC commands into a member of a specified library and running the STRMQMMQSC command. For information about how to do this, see Appendix E, “How to issue MQSC commands on OS/400” in the *MQSeries Command Reference* manual.

- **PCF commands**

Any local or remote application program can generate PCF commands in messages and put them to the command queue, `SYSTEM.ADMIN.COMMAND.QUEUE`, to be processed by the MQSeries for AS/400 command server.

More information on how to use all these facilities is given in the *MQSeries for AS/400 Administration Guide*.

MQSeries for AS/400 can verify that the user is authorized to issue particular commands for particular resources.

Changes made to the resource definitions of a queue manager using the commands (directly or indirectly) are preserved across restarts of the MQSeries for AS/400 system.

Managing communications with MQSeries

Part of the administrator's role is to ensure that the required communications links are activated, and to monitor the status of these links as required by your enterprise. You can find information describing these tasks in Chapter 29, "Monitoring and controlling channels in MQSeries for AS/400" in the *MQSeries Intercommunication* manual.

Remote administration with MQSeries

There are two aspects to the MQSeries remote administration facilities:

- MQSeries for AS/400 can be used to manage remote systems.
- Other remote products can be used to manage MQSeries for AS/400.

Managing remote systems from MQSeries

Facilities are provided by MQSeries for AS/400 to allow an administrator to manage the following systems remotely:

- MQSeries for AS/400
- MQSeries for Digital OpenVMS
- MQSeries for OS/2 Warp
- MQSeries for Tandem NSK
- MQSeries on UNIX systems
- MQSeries for Windows NT

Because of the differences in the MQSeries products, it is not always possible to manage remotely the same set of MQSeries objects or attributes that you can manage locally.

If you wish to manage any other MQSeries product (for example, MQSeries for OS/390) you can write an application program to send the appropriate commands to the command queue at the remote queue manager. However, some products do not have a command queue, so they cannot be administered from a local or remote application program.

Managing MQSeries from remote systems

MQSeries for AS/400 can be managed from a remote MQSeries system, by an administrator using the facilities provided by the following products:

- MQSeries for AS/400
- MQSeries for Digital OpenVMS
- MQSeries for OS/2 Warp
- MQSeries for Tandem NSK
- MQSeries on UNIX systems
- MQSeries for Windows NT

Note: You can manage MQSeries for AS/400 from MQSeries for OS/390 by writing an application program to send the appropriate PCF commands to the command queue.

Using the MQSeries administration utility

Much of the functionality of the CL commands is available in a user-friendly way from the MQSeries for AS/400 administration utility, described in the *MQSeries for AS/400 Administration Guide*.

The utility can be used for the administration of local MQSeries for AS/400 products, and for remote administration of a number of other MQSeries products, as listed in “Remote administration with MQSeries” on page 74.

The MQSeries administration utility, when started, supplies a set of panels to help you perform various administrative tasks. These panels help you to:

- Start and stop the local queue manager
- Create, copy, and delete local and remote queue manager objects
- Display and change the attributes of a queue manager (local or remote), and its objects
- Grant and revoke security access to local queue manager objects
- View the contents of a queue and individual messages on a local queue manager

You can find information about the administration utility in the *MQSeries for AS/400 Administration Guide*.

Chapter 13. Storage planning for MQSeries for AS/400

This chapter tells you how to plan the type and amount of storage you require when you include MQSeries for AS/400 in your system. It contains information about:

- “Product storage for MQSeries”
- “Journal storage for MQSeries”
- “Storage for other data sets used by MQSeries” on page 78
- “Performance information for MQSeries” on page 78

Product storage for MQSeries

MQSeries for AS/400 requires approximately 60 MB of main storage in the QMQM library.

This size includes the product programs, message files, panels and prompts, commands, and ancillaries. The size varies slightly according to any options that you select.

See the appropriate *MQSeries for AS/400 Administration Guide* for details on the options that you can select.

Journal storage for MQSeries

Significant events and data changes are journaled by OS/400. Such data is sent by MQSeries for AS/400 to unique journals. These journals direct the data to a series of predefined journal receivers. The threshold values of these receivers are set up by MQSeries for AS/400 to a default size of 16 MB.

When data in a journal receiver reaches its threshold value, a new one is automatically created, attached, and brought into use by MQSeries for AS/400. A message is sent to the system administrator containing key dates associated with the journal receivers. Action must be taken by the administrator to dispose of the old journal receiver according to the dates supplied in the message. See Chapter 10, “Backup and recovery planning for MQSeries for AS/400” on page 69 for more information about journaling.

You need to plan for some permanent storage to which journal receivers can be offloaded when they are no longer required to be maintained in main storage. The journals can be offloaded to diskettes, DASD, tape, or other media supported in your enterprise.

Storage for other data sets used by MQSeries

The total amount of storage you should reserve for MQSeries for AS/400 depends mainly on the amount needed to store messages; in the majority of cases, the amount needed to store the other MQSeries objects that are required, such as process objects, and the queue manager object, is small compared to that required for messages.

Therefore, you can get an approximate figure for the amount of storage required in the data sets, by calculating the amount required for both persistent and nonpersistent messages, using the algorithms described in the next section, and adding the two amounts together.

Message queues for MQSeries

All messages are stored in the QMQMDATA library, with nonpersistent and persistent messages being stored within different storage spaces. The amount of storage you should reserve is dependent on the number of messages you expect your applications to be handling at any one time, and the expected size of these messages.

Each message consist of two portions: a message descriptor, and message data.

The actual size of a message descriptor is 456 bytes. If you are using distribution lists, or grouped or segmented messages, the size of the header will increase for the transmission queue. However, because data storage is obtained by the queue manager in 1024 byte (1 KB) blocks, it is necessary to allow for one block of storage for the descriptor when calculating the amount of storage for messages.

The amount of storage required for the data portion of a message is the size of your message data, rounded up to the next 1 KB block boundary.

So, the amount of storage, in 1 KB blocks, that you should reserve for persistent messages is:

$$\text{Number of 1 KB blocks required} = n * (1 + D)$$

where n = number of messages

and D = message data size / 1024
(D is rounded up to the next higher integer)

The amount of storage for nonpersistent messages is computed using the same algorithm.

The maximum size of a single queue on MQSeries for AS/400 is 320 MB.

Performance information for MQSeries

Information about MQSeries performance is available on the Internet at:

<http://www.software.ibm.com/ts/mqseries/txppacs/txpml.html>

Part 3. Planning for MQSeries on Digital OpenVMS

Chapter 14. Introduction to MQSeries on Digital OpenVMS	81
Planning for MQSeries	81
Preparing your applications for use with MQSeries	82
Planning to use MQSeries in a network	82
Installing MQSeries	82
Setting up MQSeries	82
Planning recovery services with MQSeries	83
Planning data security on MQSeries	83
Administration with MQSeries	83
Migration from MQSeries Version 1	84
 Chapter 15. Backup and recovery planning for MQSeries for Digital OpenVMS	85
Logging with MQSeries	85
Types of logging for MQSeries	85
Selecting a logging method with MQSeries	86
Recovering from problems with MQSeries	87
 Chapter 16. Security planning for MQSeries for Digital OpenVMS	89
Controlling access to resources for MQSeries	89
Managing access through user groups with MQSeries	89
Resources you can protect with MQSeries	90
Using the security commands MQSeries	90
Security exits with MQSeries	91
 Chapter 17. Administration of MQSeries for Digital OpenVMS	93
Managing objects with MQSeries	93
Commands on MQSeries	93
Managing communications with MQSeries	94
Remote administration with MQSeries	94
Managing remote systems from MQSeries	94
Managing MQSeries from remote systems	94
 Chapter 18. Storage planning for MQSeries for Digital OpenVMS	95
RAM considerations for MQSeries	95
Disk space considerations for MQSeries	95
Product modules for MQSeries	95
Paging space for MQSeries	95
Message queues for MQSeries	96
Log files for MQSeries	96
Sample configuration for MQSeries	97
Capacity planning figures for MQSeries	97

Chapter 14. Introduction to MQSeries on Digital OpenVMS

There are two MQSeries products for Digital OpenVMS; one for AXP and one for VAX. The products comprise two parts, the *server* and the *clients*. The server runs on a machine that is capable of running an MQSeries queue manager; the clients provided with the product are for Digital OpenVMS, DOS, OS/2 Warp, and Windows 3.1. (The Windows 3.1 client can operate under Windows 3.1, Windows 95 or within the WIN-OS/2® environment under OS/2 Warp.)

MQSeries provides the MQI programming interface for use by application programs that are running on the server or the client processor. More detail on MQSeries clients and servers is given in Chapter 7, "Introduction to MQSeries clients and servers" on page 49.

For information on the hardware and software environments, see "MQSeries for Digital OpenVMS" on page 237.

Planning for MQSeries

This chapter helps you to plan for the introduction of MQSeries for Digital OpenVMS into your enterprise, and introduces the items that you need to consider when doing this planning.

There are several stages in planning for the use of MQSeries for Digital OpenVMS that you must go through. They are:

1. Preparing your applications for the use of MQSeries for Digital OpenVMS
2. Planning to include MQSeries for Digital OpenVMS in a network
3. Preparing to install MQSeries for Digital OpenVMS
4. Planning to set up MQSeries for Digital OpenVMS

A prime requirement for a message delivery system is that it must be reliable. Many functions are built into MQSeries for Digital OpenVMS to ensure that:

- Messages are not lost despite system failures
- Messages are not delivered more than once
- Messages are not accessed by, or delivered to, unauthorized persons or applications

MQSeries for Digital OpenVMS uses logging and other facilities to support these functions.

You must also plan for the operation and administration of MQSeries for Digital OpenVMS in your enterprise, and consider the implementation of an appropriate set of security facilities. Brief outlines of these planning operations are included in this chapter.

Preparing your applications for use with MQSeries

MQSeries for Digital OpenVMS brings the Message Queue Interface (MQI) to your applications. This interface allows you to modify existing applications and to write new applications. The MQI removes much of the need to understand the network and communication systems that you use. Thus you can expect to generate applications more speedily than before. However, you must prepare to take advantage of the MQI by planning its use in your applications and by understanding the ways in which it assists you.

You can find more information on how to use the MQI in your applications by referring to the *MQSeries Application Programming Guide*.

Planning to use MQSeries in a network

MQSeries for Digital OpenVMS uses the distributed queue management (DQM) facility to exchange messages between MQSeries platforms, using either the DECnet, SNA LU 6.2 or TCP transmission protocols.

You must consider how you will attach MQSeries for Digital OpenVMS to a network, and how you will define the message channels that will be used to exchange messages.

According to the way that you have set your systems up, security checks can be performed at various times. Various exits are provided that can be used by your applications to provide these facilities.

“MQSeries interoperability summary” on page 226 shows the links that are possible to other MQSeries products, and the transmission protocols that can be used.

For further information about distributed queue management, refer to the *MQSeries Intercommunication* manual.

Installing MQSeries

MQSeries for Digital OpenVMS is installed with the OpenVMS VMSINSTALL utility. For information about installing MQSeries, see the *MQSeries for Digital OpenVMS System Management Guide*.

To prepare for the actual installation, you need to plan how much disk space will be required in your Digital OpenVMS system to accommodate MQSeries. Assistance is given in Chapter 18, “Storage planning for MQSeries for Digital OpenVMS” on page 95 to help you plan the amount of space required.

Setting up MQSeries

After installation, MQSeries for Digital OpenVMS needs to be set up, and customized for your own use. This ensures that the appropriate Digital OpenVMS facilities are made available to MQSeries, and that your MQSeries system is correctly initialized and ready to work with your applications.

MQSeries for Digital OpenVMS uses configuration files to hold the product configuration information used for logging, communications protocols and installable components. After installing the product, you can edit these files to tailor the operation of the product to meet the requirements of your installation.

In addition, you need to do the following:

- Define queues
 - Consider your naming conventions for queues
- Define trigger processes
- Define remote links
 - Define associated transmission queues
 - Consider your naming conventions for remote queues
 - Consider your naming conventions for channels

Note: The characters within the names given to all MQSeries objects are case sensitive. Therefore, be very careful when defining the names of objects, to select the appropriate uppercase or lowercase characters.

You can find more information on the setting up and customizing processes for MQSeries for Digital OpenVMS in the *MQSeries for Digital OpenVMS System Management Guide*.

Planning recovery services with MQSeries

MQSeries for Digital OpenVMS provides logging services to allow backup and recovery of the messaging system. Chapter 15, “Backup and recovery planning for MQSeries for Digital OpenVMS” on page 85 introduces you to these facilities, and to the items that you need to consider in order to include MQSeries for Digital OpenVMS in your backup and recovery plans.

You can find more information on the backup and recovery facilities provided by MQSeries for Digital OpenVMS in the *MQSeries for Digital OpenVMS System Management Guide*.

Planning data security on MQSeries

MQSeries for Digital OpenVMS uses the facilities of the MQSeries *object authority manager (OAM)* installable component to control access to the various different types of queue manager resource (queues, process definitions, channels, and queue managers).

You can find more general information on authorization installable components in Chapter 8, “Introduction to the MQSeries Framework” on page 55.

Chapter 16, “Security planning for MQSeries for Digital OpenVMS” on page 89 introduces you to the security facilities provided by MQSeries for Digital OpenVMS and to some of the items you need to consider when planning for security.

You can find more information on the security facilities provided by MQSeries for Digital OpenVMS in the *MQSeries for Digital OpenVMS System Management Guide*.

Administration with MQSeries

A summary of the administration facilities provided is given in Chapter 17, “Administration of MQSeries for Digital OpenVMS” on page 93. Full details of these facilities can be found in the *MQSeries for Digital OpenVMS System Management Guide*.

See also “MQSeries product administration facilities” on page 36.

Migration from MQSeries Version 1

To use MQSeries application programs that were written for MQSeries Version 1 with MQSeries for Digital OpenVMS, you need to do the following:

1. Redefine all message queues.
2. Redefine all message channels.
3. Recompile the application programs, using the MQSeries Version 2 header files.

This might be a suitable time to consider whether you need to re-design any parts of your application, to take advantage of the additional function provided by MQSeries for Digital OpenVMS.

One difference between MQSeries for Digital OpenVMS Version 2.2 or later, and the earlier products is that MQSeries for Digital OpenVMS does its own queue storage management. It is not necessary to run a utility program to recover the space that was occupied by messages that have been removed from queues by MQGET calls; this is done automatically by MQSeries.

Chapter 15. Backup and recovery planning for MQSeries for Digital OpenVMS

This chapter describes the background concepts of recovery and restart. It contains the following sections:

- “Logging with MQSeries”
- “Recovering from problems with MQSeries” on page 87

More details of the logging and recovery facilities of MQSeries for Digital OpenVMS are given in the *MQSeries for Digital OpenVMS System Management Guide*.

Logging with MQSeries

The basic premise of a messaging system is that messages entered into the system are assured of delivery to the destination. One of the ways of ensuring that messages are not lost is to maintain a record of the activities of the queue manager that handles the receipt, transmission, and delivery of messages.

MQSeries for Digital OpenVMS does this by recording all the significant changes to the data controlled or managed by the queue manager in a log. This process is called logging. The data changes that are logged include the puts and gets of persistent messages to and from queues, changes to queue attributes, and channel activity.

The purpose of logging is to create and maintain a log that:

- Keeps records of queue manager changes
- Keeps records of queue updates for use by the restart process
- Is a source for restoration of data should there be a hardware or software failure

Each MQSeries log consists of a log control file, together with one or more log files for the storage of data.

The log control file is, as its name implies, used to control and monitor the use of the log files. It contains information relating to the size, location, next available file, and other data related particularly to the log files themselves. All the log files within one log are the same size; there is a default value for this size, but you can override this value when you set up the log.

Types of logging for MQSeries

MQSeries for Digital OpenVMS has two approaches to maintaining records of queue manager activities:

- Circular logging
- Linear logging

Each type of logging stores the recorded data in a set of files. The differences between the two types of logging are the contents, and the way that the files are linked together.

With circular logging, the set of log files are effectively linked together so as to form a ring. When data is collected, it is written sequentially into the files, in such a way as to reuse the log files in the ring. You can use circular logging for:

- Crash recovery - that is, after a system failure of some kind has stopped the queue manager unexpectedly
- Restart recovery - after a planned closedown of the system

With linear logging, the log is maintained as a continuous sequence of files. When data is collected, it is written sequentially into the log files; the space in the files is not reused, so that you can always retrieve any record from the time that the queue manager was created.

Because disk space is finite, you might have to plan for some form of archiving. Also, if you are handling a high volume of persistent messages, all your log files will eventually be filled. This will result in operator messages being written to an error log file; some action will need to be taken by the system administrator to make more log space available, or to reuse the existing space. You can use linear logging for:

- Crash recovery
- Restart recovery
- Media recovery - to recreate lost or damaged data after a media failure by replaying the contents of the log

Selecting a logging method with MQSeries

You must base your selection of log type on your requirements for recovery.

Both types of logging can cope with unexpected power outages in the absence of hardware failure. If you accept that only crash or restart recovery is required, circular logging might be adequate. If media recovery is important to you, select linear logging.

With each type of logging, you need to decide on the number of files to use in the log, and their size. The total amount of space needed depends on the amount of data to be recorded, which depends on various parameters, including:

- The size of messages
- The number of puts and gets from queues
- The number of messages being transmitted by the message channel agents

Recovering from problems with MQSeries

MQSeries can recover from communications failures and power loss incidents. In addition, it is sometimes possible to recover from other types of problem with the MQSeries data, such as inadvertent deletion of a file.

In the case of a communications failure, messages remain on the queues until they are removed by a receiving application. If the message is being transmitted, it remains on the transmission queue until it can be successfully transmitted. To recover from a communications failure, it is normally sufficient simply to restart the channels using the link that failed.

On a restart after your system has lost power, the queue manager restores all the persistent messages that were on the queues to the state that existed just before the power failure, so that no persistent messages are lost; nonpersistent messages are discarded.

There are ways in which an MQSeries object can become unusable, for example due to inadvertent damage. In such situations, you will have to take steps to recover either your complete system or some part of it. The action required depends on when the damage is detected, whether the log method selected supports media recovery, and which object or objects are damaged.

Chapter 16. Security planning for MQSeries for Digital OpenVMS

This chapter describes the access control security features in MQSeries for Digital OpenVMS. It contains these sections:

- “Controlling access to resources for MQSeries”
- “Resources you can protect with MQSeries” on page 90
- “Using the security commands MQSeries” on page 90
- “Security exits with MQSeries” on page 91

Full details of MQSeries for Digital OpenVMS security handling are given in the *MQSeries for Digital OpenVMS System Management Guide*.

Controlling access to resources for MQSeries

With MQSeries for Digital OpenVMS, access to queue manager resources is controlled through the *object authority manager (OAM)*, which is the default authorization installable component. Because the OAM is an installable component, you can implement your own security controls in place of, or in addition to, those supplied by the OAM. (For more information on installable services and installable components, see Chapter 8, “Introduction to the MQSeries Framework” on page 55.)

Users can access queue manager objects (queues, process definitions, channels, and queue managers) only if they have the required authority. The OAM manages a user’s authorization to manipulate MQSeries objects, and provides a command interface through which you can grant or revoke access authority to an object for a specific group of users.

Managing access through user groups with MQSeries

In discussing security in a Digital OpenVMS environment, we use the term *principal* rather than user ID. The reason for this is that authorities granted to a user ID can also be granted to other entities, for example, an application program that issues MQI calls, or an administration program that issues PCF commands. In these cases, the principal associated with a program is not necessarily the user ID that was used when the program was started.

Managing access permissions to MQSeries resources is based on Digital OpenVMS *rights identifiers*, that is, identifiers held by principals. A principal can hold one or more OpenVMS rights identifiers. A group is defined as the set of all principals that have been granted a specific rights identifier.

The OAM does not maintain authorizations at the level of individual principals. The mapping of principals to identifier names is carried out within the OAM, and operations are carried out at the rights identifier level.

The authorizations that a principal has are the union of the authorizations of all the rights identifiers that it holds, that is, its process rights. Whenever a principal requests access to a resource, the OAM computes this union, and then checks the authorization against it.

Resources you can protect with MQSeries

Through MQSeries for Digital OpenVMS you can control:

- Access to MQSeries objects through the MQI. When an application program attempts to access an object, the OAM checks if the user ID making the request has the authorization (through the identifier held) for the operation requested.

In particular, this means that queues, and the messages on queues, can be protected from unauthorized access.
- Permission to use MQSC commands. Only principals that hold rights identifier **mqm** can execute queue manager administration commands, for example, to create a queue.
- Permission to use control commands. Only principals that hold rights identifier **mqm** can execute control commands, for example, creating a queue manager, starting a command server, or using runmqsc.
- Permission to use PCF commands.

Different users can be granted different kinds of access authority to the same object. For example, for a specific queue, users holding one identifier might be allowed to perform both put and get operations; users with another identifier might only be allowed to browse the queue (**MQGET** with browse option). Similarly, users with identifiers might have get and put authority to a queue, but might not be allowed to alter or delete the queue.

Using rights identifiers for authorizations with MQSeries

Using identifiers for authorization, rather than individual principals, reduces the amount of administration required. Typically, a particular kind of access is required by more than one principal. For example, you might define a group consisting of end users who want to run a particular application. New users can be given access simply by granting the appropriate identifier to their OpenVMS user ID.

Try to keep the number of groups as small as possible. Dividing principals into one group for application users, and one for administrators, is a good place to start.

Using the security commands MQSeries

The OAM provides a command interface for granting and revoking authority. Before you can use these commands, you must be suitably authorized - your user ID must hold the OpenVMS rights identifier **mqm**. This identifier should have been set up when you installed the product.

If your user ID holds identifier **mqm**, you have a 'super user' authority to the queue manager. This means that you are authorized to issue any MQI request or command from your user ID.

The OAM provides two commands that you can invoke from your OpenVMS DCL to manage the authorizations of users. These are:

- **setmqaut** (set or reset authority)
- **dspmqaut** (display authority)

Details of these commands can be found in the *MQSeries for Digital OpenVMS System Management Guide*.

Security exits with MQSeries

The message channels that are used for distributed queuing, and the MQI channels that are used between clients and servers, both have security exit facilities that can invoke programs that you have supplied.

For more information on these security exit programs, see Chapter 35, “Channel-exit programs” in the *MQSeries Intercommunication* manual.

Chapter 17. Administration of MQSeries for Digital OpenVMS

This chapter is a summary of the administration facilities provided by MQSeries for Digital OpenVMS. It has the following sections:

- “Managing objects with MQSeries”
- “Remote administration with MQSeries” on page 94

Details of the commands, command interfaces, and utilities that are provided by MQSeries for Digital OpenVMS are given in the *MQSeries for Digital OpenVMS System Management Guide*. You need to arrange for users who need to be able to use these administration facilities to have the necessary authorizations, using the procedures given in the *System Management Guide*.

Managing objects with MQSeries

It is the administrator's job to monitor MQSeries for Digital OpenVMS and make any changes that might be necessary. To do this, the administrator needs to know where each MQSeries object resides, what its characteristics are, and who has access to it.

The administrator can manage and monitor the resources using MQSeries commands (MQSC), or, if there are sets of commands that are issued regularly, by writing an application program that places them on the command queue.

MQSeries can use the security features provided by the OAM, or by a security component that you have installed, to ensure that the user is authorized to issue particular commands for particular resources.

Commands on MQSeries

MQSeries for Digital OpenVMS supports the following administration commands and facilities:

- You can enter control commands on the command line.
- You can use the **runmqsc** control command to cause MQSC commands from standard input to be executed.
- Any local or remote MQSeries application program can generate PCF commands in messages and put them to the command queue SYSTEM.ADMIN.COMMAND.QUEUE, to be processed by the MQSeries for Digital OpenVMS command server.

More information on how to use all these facilities is given in the *MQSeries for Digital OpenVMS System Management Guide*.

Changes made to the resource definitions of a queue manager using the commands (directly or indirectly) are preserved across restarts of MQSeries for Digital OpenVMS.

Managing communications with MQSeries

Part of the administrator's role is to ensure that the required communications links are activated, and to monitor the status of these links as required by your enterprise. You can find information describing these tasks in Chapter 8, "Monitoring and controlling channels on distributed platforms" in the *MQSeries Intercommunication* manual.

Remote administration with MQSeries

There are two aspects to the MQSeries remote administration facilities:

- MQSeries for Digital OpenVMS can be used to manage remote systems.
- Other remote products can be used to manage MQSeries for Digital OpenVMS.

Managing remote systems from MQSeries

Facilities are provided by MQSeries for Digital OpenVMS to allow an administrator to manage the following remote systems:

- MQSeries for AS/400
- MQSeries for Digital OpenVMS
- MQSeries for OS/2 Warp
- MQSeries for OS/390
- MQSeries for Tandem NSK
- MQSeries on UNIX systems
- MQSeries for Windows NT

Because of the differences in the MQSeries products, it is not always possible to manage remotely the same set of MQSeries objects or attributes that you can manage locally.

If you want to manage any other MQSeries product, you can write an application program to send the appropriate commands to the command queue for that product. However, some MQSeries products do not have a command queue, so they cannot accept commands from local or remote application programs.

Managing MQSeries from remote systems

MQSeries for Digital OpenVMS can be managed from a remote MQSeries system, by an administrator using the facilities provided by the following products:

- MQSeries for AS/400
- MQSeries for Digital OpenVMS
- MQSeries for OS/390
- MQSeries for OS/2 Warp
- MQSeries for Tandem NSK
- MQSeries on UNIX systems
- MQSeries for Windows NT

Note: You can manage MQSeries for Digital OpenVMS from MQSeries for OS/390 by writing an application program to send the appropriate PCF commands to the command queue.

Chapter 18. Storage planning for MQSeries for Digital OpenVMS

This chapter tells you how to plan the type and amount of storage you require when you include MQSeries for Digital OpenVMS in your network. It has the following sections:

- “RAM considerations for MQSeries”
- “Disk space considerations for MQSeries”
- “Sample configuration for MQSeries” on page 97
- “Capacity planning figures for MQSeries” on page 97

RAM considerations for MQSeries

The processor memory (RAM) is used by MQSeries for Digital OpenVMS in the execution of the product modules, and as a paging area for the messages that are being processed. Parts of the paging area are written to, and read from, disk as necessary.

The minimum amount of RAM required to run the MQSeries for Digital OpenVMS server is 16 MB on VAX and 32 MB on AXP, if more RAM is available, the performance of the message processing improves.

The amount of RAM required on each client system for an MQSeries client is small compared to that required for the operating system on each of the platforms.

Disk space considerations for MQSeries

Disk space is used by MQSeries for Digital OpenVMS for the following:

- Product modules - client and server executable modules and the toolkit
- Paging space - server only
- Message queues - server only
- Logs - server only

Product modules for MQSeries

The disk space that you require for the product modules depends on the options that you decide to install: the options are described in the *MQSeries for Digital OpenVMS System Management Guide*.

Space might be required for client and server executable program modules and the toolkit. If all options are selected, 16 MB are required on VAX and 18 MB on AXP.

Paging space for MQSeries

The messages that the server is processing are stored in memory, and are paged to disk.

The algorithm used to calculate the size of the paging space required to support a particular application is complex, and is not given in this manual. Instead, you should refer to “Sample configuration for MQSeries” on page 97, which gives the paging space used on the typical minimum configuration.

Message queues for MQSeries

In order to estimate the total amount of storage that you will need for queues, you need to know:

- The number of queues that you have.
- The maximum number of messages there will be on each of the queues at any one time.
- The average size of message on each of the queues. The amount of storage required for one message varies. It is based on the size of the message data plus the size of the message header (456 bytes), rounded up the nearest 512-byte block. If you are using distribution lists, or grouped or segmented messages, the size of the header will increase for the transmission queue.

Given these values, you can calculate the total amount of space required for queues. However, this value is likely to be an approximate value only, and it is advisable to add a contingency value, to avoid the situation where there is no space left for messages on the queues when your application is running.

The maximum size of a single queue on MQSeries for Digital OpenVMS is 320 MB.

Log files for MQSeries

Significant events and data changes can be logged in circular or sequential logs. In particular, the logs are used for recording persistent messages.

All the log files in a log are of the same size. By default, this size is 4 MB, but this value can be changed by the system administrator when the log is defined.

For a circular log, the system administrator needs to specify how many files should be included in the log. For a sequential log, the number of files will increase over time, until the system administrator archives some of the files, and disposes of them. You need to plan for the permanent storage (diskettes, tape, or other media supported in your enterprise) that is to be used for these archived files.

Sample configuration for MQSeries

This section gives the amounts of storage required for a sample configuration consisting of a single server on the Digital OpenVMS processor with:

- The disk on the server holding the server and client product modules and the toolkit
- System default objects
- 20 local queues, each with 50 messages of 1 KB total length; half of the messages are persistent messages
- A single client
- No message channels for distributed queuing

The storage requirements for the server in this configuration are:

- RAM: 16 MB for VAX, 32 MB for AXP
- Disk space for MQSeries for Digital OpenVMS:
 - Product modules: 16 MB for VAX, 18 MB for AXP
 - Paging space: 64 MB
 - Message queues: 1.5 MB
 - Logs: 12 MB (circular log)

The storage requirements for the clients in this configuration are small compared to the storage required for the operating system on the platforms.

Capacity planning figures for MQSeries

The following table shows the notional limits of the number of operations that can be performed on each MQSeries-connected workstation. It is recommended that, for adequate performance, you do not exceed these limits.

The numbers quoted were measured on an Alpha Server 1000 4/266 server that had 128 MB of installed memory.

<i>Table 14. MQSeries for Digital OpenVMS, capacity planning</i>	
Resource	Maximum number
Queue managers (heavily used)	4
Connections (including channels)	112
Open queues	1024
Active channels	112
Clients	112
Note: The number of connections, active channels, and clients can be doubled if you use the MQSeries fastpath bindings.	

Part 4. Planning for MQSeries for OS/2 Warp

Chapter 19. Introduction to MQSeries for OS/2 Warp	101
Planning for MQSeries	101
Preparing your applications for the use of MQSeries	101
Planning to use MQSeries in a network	102
Installing MQSeries for OS/2 Warp	102
Setting up MQSeries	102
Planning recovery services for MQSeries	103
Planning data security for MQSeries	103
Administration of MQSeries	103
Migration from previous versions of MQSeries	104
Euro symbol support	104
 Chapter 20. Backup and recovery planning for MQSeries for OS/2 Warp	105
Logging with MQSeries	105
Types of logging with MQSeries	106
Selecting a logging method with MQSeries	106
Resource management with MQSeries	107
MQSeries as a resource manager	107
MQSeries as a transaction manager	107
Recovering from problems with MQSeries	108
 Chapter 21. Security planning for MQSeries for OS/2 Warp	109
Setting user IDs with MQSeries	109
Security exits for MQSeries	109
 Chapter 22. Administration of MQSeries for OS/2 Warp	111
Managing objects with MQSeries	111
Commands with MQSeries	111
Managing communications with MQSeries	111
Remote administration with MQSeries	112
Managing remote systems from MQSeries	112
Managing MQSeries from remote systems	112
 Chapter 23. Storage planning for MQSeries for OS/2 Warp	113
RAM considerations for MQSeries	113
Disk space considerations for MQSeries	113
Product modules for MQSeries	113
Message queues for MQSeries	114
Log files for MQSeries	114
Capacity planning and performance figures for MQSeries	114

Chapter 19. Introduction to MQSeries for OS/2 Warp

The MQSeries for OS/2 Warp product is in two parts, the *server* and the *client*. The server runs on a machine that is capable of running OS/2 Warp; the clients provided with the product are for AIX, DOS, HP-UX, OS/2 Warp, Sun Solaris, Windows NT, Windows 3.1, Windows 95, and Windows 98.

MQSeries provides the MQI programming interface for use by application programs that are running on the server or the client processor. More detail on clients and servers is given in Chapter 7, "Introduction to MQSeries clients and servers" on page 49.

This chapter includes basic information about:

- "Planning for MQSeries"
- "Migration from previous versions of MQSeries" on page 104

For more information on the hardware and software environments needed by MQSeries, see "MQSeries for OS/2 Warp" on page 241.

Planning for MQSeries

This chapter helps you to plan for the introduction of MQSeries into your enterprise, and introduces the items that you need to consider when doing this planning.

There are several stages in planning for the use of MQSeries that you must go through. They are:

1. Preparing your applications for the use of MQSeries
2. Planning to include MQSeries in a network
3. Preparing to install MQSeries
4. Planning to set up MQSeries

A prime requirement for a message delivery system is that it must be reliable. Many functions are built into MQSeries to ensure that messages are not lost despite system failures, and are not delivered more than once. MQSeries uses logging and other facilities to support these functions.

You must also plan for the operation and administration of MQSeries in your enterprise and consider the implementation of an appropriate set of security facilities. Brief outlines of these planning operations are included in this chapter.

Preparing your applications for the use of MQSeries

MQSeries brings the Message Queue Interface (MQI) to your applications. This interface allows you to modify existing applications and to write new applications. The MQI removes much of the need to understand the network and communication systems that you use. Thus you can expect to generate applications more speedily than before. However, you must plan to take advantage of the MQI by planning its use in your applications and by understanding the ways in which it assists you.

You can find more information on how to use the MQI in your applications by referring to the *MQSeries Application Programming Guide*.

Interfacing with CICS with MQSeries

With MQSeries you can create application programs for the CICS for OS/2 or CICS for Windows NT transaction environment. These applications can use the MQI to communicate with CICS or non-CICS programs in any of the environments supported by the MQSeries products.

Planning to use MQSeries in a network

MQSeries uses the distributed queuing facility to exchange messages between MQSeries platforms, using either the SNA LU 6.2, TCP, SPX, or NetBIOS transmission protocols.

You must consider how you will attach MQSeries to a network, and how you will define the channels that will be used to exchange messages. You can simplify your definitions for distributed queuing by using MQSeries clusters.

According to the way that you have set your systems up, security checks can be performed at various times. You can provide your own security services, using the exit facilities provided by MQSeries. MQSeries also provides exits relating to DCE security.

“MQSeries interoperability summary” on page 226 shows the links that are possible to other MQSeries products, and the transmission protocols that can be used.

For further information about distributed queuing, refer to the *MQSeries Intercommunication* and the *MQSeries Queue Manager Clusters* manuals.

Installing MQSeries for OS/2 Warp

MQSeries for OS/2 Warp is installed by using Software Installer/2 (SI/2), an IBM product. Although this is a separate licensed program, an SI/2 module is provided with your copy of MQSeries for OS/2 Warp that requires no additional license to be purchased. The supplied version of SI/2 is restricted in such a way that it can only be used for the installation of MQSeries for OS/2 Warp.

To prepare for the actual installation, you need to plan how much disk space you require in your OS/2 Warp system to accommodate MQSeries for OS/2 Warp. Assistance is given in Chapter 23, “Storage planning for MQSeries for OS/2 Warp” on page 113 to help you plan the amount of space required.

When you have installed MQSeries, you can run the supplied installation verification test. You can find more information to help you with the installation of MQSeries for OS/2 Warp in “Chapter 3. Installing MQSeries for OS/2 Warp” in the *MQSeries for OS/2 Warp V5.1 Quick Beginnings* manual.

Setting up MQSeries

After installation, MQSeries needs to be set up, and customized for your own use. This ensures that the appropriate operating system facilities are made available to MQSeries, and that your MQSeries system is correctly initialized and ready to work with your applications.

MQSeries uses configuration files to hold the product configuration information used for logging, communications protocols and installable components. After installing the product, you can edit these files to tailor the operation of the product to meet the requirements of your installation.

In addition, you need to do the following:

- Define queues
 - Consider your naming conventions for queues
- Define trigger processes
- Define remote links
 - Define associated transmission queues
 - Consider your naming conventions for remote queues
 - Consider your naming conventions for channels

Note: The characters within the names given to all MQSeries objects are case sensitive. Therefore, be very careful when defining the names of objects, to select the appropriate uppercase or lowercase characters.

You can find more information on the setting up and customizing processes for MQSeries in Chapter 6, “Managing queue managers using control commands” in the *MQSeries System Administration* manual.

Planning recovery services for MQSeries

MQSeries provides logging services to allow backup and recovery of the messaging system. Chapter 20, “Backup and recovery planning for MQSeries for OS/2 Warp” on page 105 introduces you to these facilities, and to the items that you need to consider in order to include MQSeries in your backup and recovery plans.

You can find more information on the backup and recovery facilities provided by MQSeries in Chapter 15, “Recovery and restart” in the *MQSeries System Administration* manual.

Planning data security for MQSeries

MQSeries provides a number of security facilities for use by your applications. An introduction to these facilities is given in Chapter 21, “Security planning for MQSeries for OS/2 Warp” on page 109.

Administration of MQSeries

A summary of the administration facilities provided by MQSeries are given in Chapter 2, “An introduction to MQSeries administration” in the *MQSeries System Administration* manual.

Migration from previous versions of MQSeries

When you have migrated from MQSeries Version 2 to MQSeries Version 5 you will **not** be able to revert to Version 2. You should back up your system before installing the new version. This will enable you to back off the upgrade if necessary. If you do this however, you will not be able to recover the work performed by MQSeries Version 5.

With MQSeries Version 5, the system default objects are created automatically when you use the `crtmqm` command to create a queue manager. The sample MQSC definition file, `AMQSCOMA.TST`, is no longer provided. If you have used `AMQSCOMA.TST` to customize your settings for MQSeries Version 2, and you want to use the same settings with Version 5, save your version of the file before you install MQSeries Version 5. You can then use this file to create the Version 2 default objects. Alternatively, you can generate a new MQSC definition file if required.

A list of the system default objects for MQSeries Version 5 is provided in “System default objects” in the *MQSeries System Administration* manual.

Euro symbol support

Support for the new euro currency symbol has been added to MQSeries. If you need to modify your applications to use this symbol, ensure that they use one of the coded character sets that include it. These are described in Appendix F, “Code page conversion tables” in the *MQSeries Application Programming Reference* manual. If you need to change the coded character set used by your queue manager, use the `CCSID` attribute of the `ALTER QMGR` command (or the equivalent `PCF` command).

Chapter 20. Backup and recovery planning for MQSeries for OS/2 Warp

This chapter describes the background concepts of recovery and restart. It contains the following sections:

- “Logging with MQSeries”
- “Resource management with MQSeries” on page 107
- “Recovering from problems with MQSeries” on page 108

More details of the logging and recovery facilities are given in Chapter 15, “Recovery and restart” in the *MQSeries System Administration* manual.

Logging with MQSeries

The basic premise of a messaging system is that messages entered into the system are assured of delivery to the destination. One of the ways of ensuring that messages are not lost, is to maintain a record of the activities of the queue manager that handles the receipt, transmission, and delivery of messages.

MQSeries does this by recording all the significant changes to the data controlled or managed by the queue manager in a log. This process is called *logging*. The data changes that are logged include the puts and gets of persistent messages to and from queues, changes to queue attributes, and channel activities.

The purpose of logging is to create and maintain a log that:

- Keeps records of queue manager changes
- Keeps records of queue updates for use by the restart process
- Is a source for restoration of data should there be a hardware or software failure

Each MQSeries log consists of a log control file, together with one or more log files for the storage of data.

The log control file is, as its name implies, used to control and monitor the use of the log files. It contains information relating to the size, location, next available file, and other data related particularly to the log files themselves. All the log files within one log are the same size; there is a default value for this size, but you can override this value when you set up the log.

MQSeries provides a log dump facility (DMPMQLOG). This enables you to format and display the contents of the log when doing problem determination.

Types of logging with MQSeries

In MQSeries, there are two approaches to maintaining records of queue manager activities:

- Circular logging
- Linear logging

Each type of logging stores the recorded data in a set of files. The differences between the two types of logging are the contents, and the way that the files are linked together.

With circular logging, the set of log files are effectively linked together so as to form a ring. When data is collected, it is written sequentially into the files in such a way as to reuse the log files in the ring. You can use circular logging for:

- Crash recovery - that is, after a system failure of some kind has stopped the queue manager unexpectedly
- Restart recovery - after a planned close down of the system

With linear logging, the log is maintained as a continuous sequence of files. When data is collected, it is written sequentially into the log files; the space in the files is not reused, so that you can always retrieve any record from the time that the queue manager was created.

Because disk space is finite, you might have to plan for some form of archiving. Also, if you are handling a high volume of persistent messages, all your log files will eventually be filled. This will result in operator messages being written to an error log file, and some action will need to be taken by the system administrator to make more log space available, or to reuse the existing space. You can use linear logging for:

- Crash recovery
- Restart recovery
- Media recovery - to recreate lost or damaged data after a media failure by replaying the contents of the log

Selecting a logging method with MQSeries

You must base your selection of log type on your requirements for recovery.

Both types of logging can cope with unexpected power outages in the absence of hardware failure. If you accept that only crash or restart recovery is required, circular logging might be adequate. If media recovery is important to you, select linear logging.

With each type of logging, you will need to decide on the number of files to use in the log, and their size. The total amount of space needed will depend on the amount of data to be recorded, which depends on various parameters, including:

- The size of messages
- The number of gets and puts to queues
- The number of messages being transmitted by the message channel agents

Resource management with MQSeries

MQSeries supports the coordination of transactions by an external transaction manager that uses the X/Open XA interface. MQSeries can also act as a transaction manager, coordinating updates made by external resource managers.

MQSeries as a resource manager

MQSeries supports the coordination of transactions by an external transaction manager that uses the X/Open XA interface.

In an XA configuration, the MQSeries queue manager acts as an XA resource manager, managing message queues. The XA transaction manager coordinates the operations of the queue manager, and any other resource managers, to synchronize the commit or backout of transactions. This ensures that updates to MQSeries message queues are coordinated with the updates to all the other types of resource being managed.

CICS for OS/2 Warp does not operate as an XA transaction manager, so the XA resource management capabilities of MQSeries for OS/2 Warp cannot be used. However, CICS does provide a single-phase commit process (as opposed to the two-phase XA coordination), which MQSeries takes part in.

This support is available only on the MQSeries server, and is not available to client applications. See the information on CICS transactions in “Using CICS” in the *MQSeries System Administration* manual for more details.

MQSeries as a transaction manager

MQSeries can act as a transaction manager and coordinate updates made by external resource managers within MQSeries units of work. These external resource managers must comply to the X/Open XA interface. MQSeries can act as a transaction manager for DB2.

Recovering from problems with MQSeries

MQSeries will recover from both communications failures and power loss incidents. In addition, it is sometimes possible to recover from other types of problem with the MQSeries data, such as inadvertent deletion of a file.

In the case of a communications failure, messages simply remain on queues until they are removed from the queues by a receiving application. If the message is being transmitted, it remains on the transmission queue until it can be successfully transmitted. To recover from a communications failure, it will normally be sufficient simply to restart the channels using the link that failed.

On a restart after your system has lost power, the queue manager will restore all the persistent messages on the queues to the state that existed just before the power failure, so that no persistent messages are lost; nonpersistent messages are discarded.

There are ways in which an MQSeries object can become unusable, for example due to inadvertent damage. In such situations, you will have to take steps to recover either your complete system or some part of it. The action required depends on when the damage is detected, whether the log method selected supports media recovery, and which object or objects are damaged.

Chapter 21. Security planning for MQSeries for OS/2 Warp

In general, each MQSeries product provides security facilities by building on those provided by the platform for which the product was designed.

This chapter describes the security facilities provided by MQSeries. The chapter contains these sections:

- “Setting user IDs with MQSeries”
- “Security exits for MQSeries”

Setting user IDs with MQSeries

MQSeries for OS/2 Warp provides the *User ID* installable component. This can be used to generate a user ID value, which the queue manager places in the message context portion of the message descriptor of all messages that are generated by application programs running on the MQSeries for OS/2 Warp client or server.

This user ID can be used by the programs that receive the messages, to verify that the messages have come from an authorized user.

Details of the User ID installable component can be found in Chapter 14, “User identifier service” in the *MQSeries Programmable System Management* manual.

Security exits for MQSeries

The message channels that are used for distributed queuing, and the MQI channels that are used between clients and servers, both have security exit facilities that can invoke programs you have supplied.

For more information on these security exit programs, see Chapter 35, “Channel-exit programs” in the *MQSeries Intercommunication* manual.

Chapter 22. Administration of MQSeries for OS/2 Warp

This chapter is a summary of the administration facilities provided by MQSeries. It has the following sections:

- “Managing objects with MQSeries”
- “Remote administration with MQSeries” on page 112

Details of the commands, command interfaces, and utilities that are provided by MQSeries are given in the *MQSeries System Administration* manual.

Managing objects with MQSeries

It is the administrator's job to monitor MQSeries and make any changes that might be necessary. To do this, the administrator needs to know where each MQSeries object resides, what its characteristics are, and who has access to it.

The administrator can manage and monitor the resources using MQSeries commands (MQSC), or, if there are sets of commands that are issued regularly, by writing an application program that places them on the command queue.

Commands with MQSeries

MQSeries supports the following administration commands and facilities:

- MQSeries provides control commands that you can enter through the OS/2 Warp command line.
- You can use the **runmqsc** control command to cause MQSC commands from standard input to be executed.
- Any local or remote MQSeries application program can generate PCF commands in messages, and put them to the command queue, SYSTEM.ADMIN.COMMAND.QUEUE, to be processed by the MQSeries command server.

More information on how to use all these facilities is given in Chapter 2, “An introduction to MQSeries administration” in the *MQSeries System Administration* manual.

Changes made to the resource definitions of a queue manager using the commands (directly or indirectly) are preserved across restarts of the MQSeries system.

Managing communications with MQSeries

Part of the administrator's role is to ensure that the required communications links are activated, and to monitor the status of these links as required by your enterprise. You can find information describing these tasks in Part 3, “DQM in MQSeries for OS/2 Warp, Windows NT, Digital OpenVMS, Tandem NSK, and UNIX systems” in the *MQSeries Intercommunication* manual.

Remote administration with MQSeries

There are two aspects to the MQSeries remote administration facilities:

- MQSeries for OS/2 Warp can be used to manage remote systems.
- Other remote products can be used to manage an MQSeries for OS/2 Warp system.

Managing remote systems from MQSeries

Facilities are provided by MQSeries to allow an administrator to manage the following remote systems:

- MQSeries for AS/400
- MQSeries for Digital OpenVMS
- MQSeries for OS/390
- MQSeries for OS/2 Warp
- MQSeries for Tandem NSK
- MQSeries on UNIX systems
- MQSeries for Windows NT

Because of the differences between the MQSeries products, it is not always possible to manage remotely the same set of MQSeries objects or attributes that you can manage locally.

If you wish to manage any other MQSeries product, you can write an application program to send the appropriate commands to the command queue for that product. However, some MQSeries products do not have a command queue, so they cannot accept commands from local or remote application programs.

Managing MQSeries from remote systems

MQSeries for OS/2 Warp can be managed from a remote MQSeries system, by an administrator using the facilities provided by the following products:

- MQSeries for AS/400
- MQSeries for Digital OpenVMS
- MQSeries for OS/390
- MQSeries for OS/2 Warp
- MQSeries for Tandem NSK
- MQSeries on UNIX systems
- MQSeries for Windows NT

Note: You can manage MQSeries for OS/2 Warp from MQSeries for OS/390 by writing an application program to send the appropriate PCF commands to the command queue.

Chapter 23. Storage planning for MQSeries for OS/2 Warp

This chapter tells you how to plan the type and amount of storage you require when you include MQSeries in your system. It has the following sections:

- “RAM considerations for MQSeries”
- “Disk space considerations for MQSeries”
- “Capacity planning and performance figures for MQSeries” on page 114

RAM considerations for MQSeries

The processor memory (RAM) is used by MQSeries in the execution of the product modules, and as a paging area for the messages that are being processed. Parts of the paging area are written to, and read from, disk as necessary.

The minimum amount of RAM required to run the MQSeries server on OS/2 is 24 MB; if more RAM is available, the performance of the message processing improves. Allow 0.5 MB for each MQSeries client connected.

The amount of RAM required on each client system for an MQSeries client is small compared to that required for the operating system on each of the platforms.

Disk space considerations for MQSeries

Disk space is used by MQSeries for the following:

- Product modules - client and server executable modules, the toolkit, and the online documentation
- Paging space - server only
- Message queues - server only
- Logs - server only

Product modules for MQSeries

The disk space that you require for the product modules depends on the options that you decide to install: the options are described in “Chapter 2. Planning to Install MQSeries for OS/2 Warp” in the *MQSeries for OS/2 Warp V5.1 Quick Beginnings* manual.

Space might be required for client and server executable program modules, the toolkit, and the online documentation. If all options are selected, 66.5 MB is required.

The product modules can be stored on a LAN server, as an alternative to them being stored on a disk attached to the MQSeries client or server. MQSeries loads the modules from the LAN server when required.

Message queues for MQSeries

In order to estimate the total amount of storage that you will need for queues, you need to know:

- The number of queues that you have.
- The maximum number of messages there will be on each of the queues at any one time.
- The average size of message on each of the queues. The amount of storage required for one message varies. It is based on the size of the message data plus the size of the message header (456 bytes), rounded up the nearest 512-byte block. If you are using distribution lists, or grouped or segmented messages, the size of the header increases for the transmission queue.

Given these values, you can calculate the total amount of space required for queues. However, this value is likely to be an approximate value only, and it is advisable to add a contingency value, to avoid the situation where there is no space left for messages on the queues when your application is running.

The maximum size for a single queue on MQSeries for OS/2 Warp is 2 GB.

Log files for MQSeries

Significant events and data changes can be logged in circular or sequential logs. In particular, the logs are used for recording persistent messages.

All the log files in a log are of the same size. By default, this size is 4 MB, but this value can be changed by the system administrator when the log is defined.

For a circular log, the system administrator needs to specify how many files should be included in the log. For a sequential log, the number of files will increase over time, until the system administrator archives some of the files, and disposes of them. You need to plan for the permanent storage (diskettes, tape, or other media supported in your enterprise) that is to be used for these archived files.

Capacity planning and performance figures for MQSeries

Information about MQSeries performance and capacity planning is available on the Internet at:

<http://www.software.ibm.com/ts/mqseries/txppacs/txpml.html>

Part 5. Planning for MQSeries for OS/390

Chapter 24. Introduction to MQSeries for OS/390	117
Planning for MQSeries	117
Preparing your applications for the use of MQSeries	118
Planning to use MQSeries in a network	119
Using the OS/390 Workload Manager with MQSeries	120
Planning recovery services with MQSeries	120
Planning data security with MQSeries	120
Administration with MQSeries	120
Installing and customizing MQSeries	121
Installing MQSeries	121
Customizing MQSeries	121
Verifying your installation of MQSeries	122
Migrating from MQSeries for MVS/ESA	122
 Chapter 25. Data sets used by MQSeries for OS/390	123
Page sets for MQSeries	123
Buffer pools and buffers for MQSeries	123
Storage classes for MQSeries	123
Log data sets for MQSeries	124
Bootstrap data set for MQSeries	125
Archive log data sets and BSDS copies for MQSeries	125
What a log contains for MQSeries	125
Checkpoint records for MQSeries	126
 Chapter 26. Backup and recovery planning for MQSeries for OS/390	127
Planning your logging environment with MQSeries	127
Planning your archive storage with MQSeries	127
Other recovery considerations with MQSeries	128
CICS recovery	128
IMS recovery	128
RRS recovery	128
Backup and recovery with DFHSM	128
Using Extended Recovery Facility (XRF)	129
Using the OS/390 Automatic Restart Manager (ARM)	129
Preparing for disaster recovery	130
General tips for backup and recovery with MQSeries	130
Periodically taking backup copies	130
Using dual logging for your log data sets	131
Keeping archive logs you might need	131
Retaining the DD name or page set association	131
 Chapter 27. Security planning for MQSeries for OS/390	133
MQSeries security overview	134
Subsystem security with MQSeries	134
Security classes used by MQSeries	135
Security exits with MQSeries	135
Things to consider when setting up security	135
 Chapter 28. Administration of MQSeries for OS/390	137
Managing objects with MQSeries	137

Commands on MQSeries	137
Managing communications with MQSeries	138
Remote administration with MQSeries	138
Managing remote systems from MQSeries	138
Managing MQSeries from remote systems	138
Managing accounting information with MQSeries	139
Using the MQSeries utilities	139
The CSQUTIL utility	139
The data conversion exit utility	140
The change log inventory utility	140
The print log map utility	140
The log print utility	140
Chapter 29. Storage planning for MQSeries for OS/390	141
MQSeries address space storage	141
Private region storage usage	142
Logs and archive storage for MQSeries	142
Storage for page data sets and messages	143
Storage for bootstrap data sets (BSDS)	143
Planning your library storage for MQSeries	143
Further information for MQSeries	143
Chapter 30. Performance of MQSeries for OS/390	145
Impact of logging for MQSeries	145
Impact of dual logging on MQSeries	146
Fast write for logging on MQSeries	147
Causes of I/O to log for MQSeries	148
Checkpointing on MQSeries	148
MQSeries page set I/O on MQSeries	148
Buffer pools, page sets, storage classes, and queues for MQSeries	149
Monitoring performance for MQSeries	150
Where to find more information	150
Chapter 31. Measured usage license charges with MQSeries for OS/390	151

Chapter 24. Introduction to MQSeries for OS/390

MQSeries for OS/390 runs on a System/390 that is capable of running OS/390, to provide messaging and queuing support for the following types of application:

- CICS
- IMS
- TSO and batch

This chapter provides basic information about:

- “Planning for MQSeries”
- “Installing and customizing MQSeries” on page 121
- “Migrating from MQSeries for MVS/ESA” on page 122

Chapter 29, “Storage planning for MQSeries for OS/390” on page 141 gives information on the storage requirements for MQSeries for OS/390. For more information on the hardware and software requirements for MQSeries for OS/390, see “MQSeries for OS/390” on page 243.

Planning for MQSeries

This chapter helps you to plan for the introduction of MQSeries for OS/390 into your enterprise. Chapter 1, “Introduction to IBM MQSeries” on page 3 introduces you to the concepts you must consider.

This chapter does not provide you with detailed information to enable you to perform the installation of MQSeries for OS/390. That information is provided in the *MQSeries for OS/390 Program Directory*. Equally, you are directed to other publications for detailed information on particular topics.

There are several stages in planning for the use of MQSeries for OS/390 that you must go through. They are:

1. Preparing your applications for the use of MQSeries for OS/390
2. Planning to include MQSeries for OS/390 in a network
3. Preparing to install MQSeries for OS/390
4. Planning to customize MQSeries for OS/390

A prime requirement for a message delivery system is that it must be reliable. Many functions are built into MQSeries for OS/390 to ensure that:

- Messages are not lost despite system failures
- Messages are not delivered more than once
- Messages are not accessed by, or delivered to, unauthorized persons or applications

The features provided by MQSeries for OS/390 to support this, and which you must plan for, include:

- Logging (including options for dual logging and archiving)
- Automatic recovery from transaction, system, and storage media failures (for which suitable backups are needed)
- Restart from backup files
- Access to security management facilities

You must also plan for the administration of MQSeries for OS/390 in your operation, make decisions regarding the performance aspects of the product, and consider, if necessary, possible migration of both your system and applications from other products. Brief outlines of these planning operations are included in this chapter.

Preparing your applications for the use of MQSeries

MQSeries for OS/390 brings the Message Queue Interface (MQI) to your applications. This interface allows you to modify existing applications and to write new applications. The MQI removes much of the need to understand any network or communication systems that you use. Thus you can expect to complete applications more speedily than before. However, you must plan to take advantage of the MQI by planning its use in your applications and by understanding the ways in which it assists you.

You can find more information on how to use MQSeries for OS/390 in your applications by referring to the *MQSeries Application Programming Guide*.

Interfacing with CICS, IMS, or Batch

With MQSeries for OS/390 you can create applications in these environments:

- A CICS transaction environment
- An IMS transaction environment
- An OS/390 Batch and Time Sharing Option (TSO) environment, optionally using RRS

Applications (or transactions) connect to MQSeries by means of an *adapter*. There are adapters for each of these environments included in MQSeries for OS/390.

The MQSeries-IMS bridge

The MQSeries-IMS bridge is a component of MQSeries for OS/390 that allows direct access from MQSeries applications to applications on your IMS system. It enables implicit MQSeries API support. This means that you can re-engineer legacy applications that were controlled by 3270-connected terminals to be controlled by MQSeries messages, without having to rewrite, recompile, or relink them.

The bridge is an IMS *Open Transaction Manager Access* (OTMA) client.

The MQSeries-CICS bridge

The MQSeries-CICS bridge enables an application, not running in a CICS environment, to run a *program* or *transaction* on CICS and get a response back. This non-CICS application can be run from any environment that has access to an MQSeries network that encompasses MQSeries for OS/390.

A *program* is a CICS program that can be invoked using the EXEC CICS LINK command. It must conform to the DPL subset of the CICS API, that is, it must not use CICS terminal or syncpoint facilities. A *transaction* is a CICS transaction designed to run on a 3270 terminal. This transaction can use BMS or TC commands. It can be conversational or part of a pseudoconversation. It is permitted to issue syncpoints.

Planning to use MQSeries in a network

MQSeries for OS/390 uses the distributed queue management (DQM) facility to exchange messages between MQSeries platforms.

With MQSeries for OS/390, access to remote queues can be with:

- SNA LU 6.2
- TCP
- CICS (using ISC)

Which of these alternative methods of connection is best for your installation depends on a number of factors, including:

- Whether you require CICS for use by your applications
- What other MQSeries products you wish to connect to, and the methods of connection that they support
- If there are alternatives possible, whether you require the best possible performance

You need to decide which of these protocols you are going to use before you install MQSeries for OS/390. “MQSeries interoperability summary” on page 226 shows the connections that are possible with networks containing MQSeries products.

Having decided on which form of connection to use, you need to define the channels that are to be used in the exchange of messages. You can simplify your definitions for distributed queuing by using MQSeries clusters (not available if you are using CICS ISC for distributed queuing).

For further information about distributed queuing, refer to the *MQSeries Intercommunication* and the *MQSeries Queue Manager Clusters* manuals. Refer to the *CICS Intercommunication Guide* for details on managing remote CICS links.

Using the OS/390 Workload Manager with MQSeries

If you want to use the queuing services of the OS/390 workload manager (WLM) with MQSeries, you need to use MQSeries *Workflow*. Use the WLM to define different classes of service for your MQSeries messages. When you have done this, if you put messages on a special queue called a *WLM-managed queue*, Workflow will pass information taken from the message descriptor and the work information header to the WLM, and so determine which class of service to use for the message.

For a general explanation of the basic concepts of MQSeries Workflow, see the *MQSeries Workflow: Concepts and Architecture* manual (GH12-6285), and for information about planning to use it on OS/390, see the *MQSeries Workflow for OS/390: Customization and Administration* manual (SC33-7030). For information about the Workload Manager, see the *MVS Planning: Workload Management* manual (GC28-1761).

Planning recovery services with MQSeries

Chapter 26, “Backup and recovery planning for MQSeries for OS/390” on page 127 introduces the concepts of recovery management in MQSeries for OS/390 subsystems. This chapter leads you into the planning you must do to ensure that your data can be recovered in cases of network or system failures.

Planning data security with MQSeries

MQSeries for OS/390 does not provide any security facilities of its own, but uses those provided by existing security management facilities. This book explores the possible options you must select from to protect your data and users from unauthorized access.

Administration with MQSeries

A summary of the administration facilities provided by the MQSeries for OS/390 products is given in Chapter 28, “Administration of MQSeries for OS/390” on page 137. Full details of these facilities can be found in the *MQSeries Command Reference*, and in the *MQSeries for OS/390 System Management Guide*.

Installing and customizing MQSeries

MQSeries for OS/390 uses the standard OS/390 installation procedure. This section reminds you of that procedure and also introduces some of the work that must be planned in order to customize MQSeries for OS/390 to your enterprise's particular needs.

Before you install MQSeries for OS/390, you must decide the following:

- Which communications protocol you are going to use
- Whether you are going to install one of the following optional national language features:
 - Japanese
 - Simplified Chinese
 - U.S. English (uppercase)
- Whether you are going to install the optional Client Attachment feature

You also need to plan how much storage you require in your OS/390 system to accommodate MQSeries for OS/390. Assistance is given in Chapter 29, "Storage planning for MQSeries for OS/390" on page 141 to help you plan the amount of storage required for MQSeries for OS/390. The chapter also gives an indication of the amount of storage you should plan to use, for example, for logs, page data sets, and objects.

Installing MQSeries

MQSeries for OS/390 is supplied with a Program Directory that contains specific instructions for installing the program on an OS/390 system. You must follow the instructions in the *MQSeries for OS/390 Program Directory*. They include not only details of the installation process, but also information about the prerequisite products and their service or maintenance levels.

SMP/E, used for installation on the OS/390 platform, validates the service levels and prerequisite and corequisite products, and maintains the SMP/E history records to record the installation of MQSeries for OS/390. It loads the MQSeries for OS/390 libraries and checks that the loads have been successful. You then have to customize the product to your own requirements.

Customizing MQSeries

MQSeries requires some customization after installation in order to meet the individual and special requirements of your system, and to use your system resources in the most effective way. Customization is described in detail in the *MQSeries for OS/390 System Management Guide*. However, below are the items you must consider when planning to customize your system.

You need to:

- Choose which language you want to use
- Choose the distributed queuing facility
- Define the MQSeries subsystem to OS/390
- Update the OS/390 link list
- APF authorize the MQSeries load libraries
- Update the OS/390 program properties table
- Create procedures for the MQSeries subsystem

- Create the channel initiator procedures
- Implement your ESM security controls
- Customize the initialization input data sets
- Create the bootstrap and log data sets
- Define your page sets
- Tailor your system parameter modules
- Tailor the channel initiator parameter module
- Set up the Batch/TSO and RRS adapters
- Set up the operations and control panels
- Set up the CICS and IMS adapters
- Suppress information messages
- Set up the CICS and IMS bridges

Verifying your installation of MQSeries

After the installation and customization has been completed, you can use an installation verification program (IVP) supplied with the product to verify that the installation has been completed successfully. The IVP supplied is an assembler language program and should be run after MQSeries for OS/390 has been customized to suit your enterprise's needs. Details of the IVP and customization are given in the *MQSeries for OS/390 System Management Guide*.

Migrating from MQSeries for MVS/ESA

If you are migrating from MQSeries for MVS/ESA you do not have to perform most of the customization tasks listed in “Customizing MQSeries” on page 121. Information about what you need to do when migrating from a previous version is given in the *MQSeries for OS/390 System Management Guide*.

When you have migrated to MQSeries for OS/390 Version 2.1, you will **not** be able to revert to previous versions of MQSeries for MVS/ESA.

Chapter 25. Data sets used by MQSeries for OS/390

This chapter provides a general introduction to the specialized data sets used by MQSeries for OS/390. MQSeries for OS/390 uses data sets called *page sets* for storing messages. It maintains *logs* of data changes and significant events as they occur to provide backup and recovery facilities. The logs contain information about queues and messages. The *bootstrap data set (BSDS)* stores information about the data sets that contain the logs.

This chapter contains basic information about:

- “Page sets for MQSeries”
- “Log data sets for MQSeries” on page 124
- “Bootstrap data set for MQSeries” on page 125
- “What a log contains for MQSeries” on page 125
- “Checkpoint records for MQSeries” on page 126

Page sets for MQSeries

A page set is a linear VSAM data set that has been formatted for use by MQSeries for OS/390. Page sets are used primarily to store messages and object definitions. Each page set is identified by a page set ID (PSID), an integer in the range 00 through 99. In particular, MQSeries for OS/390 uses page set 00 to store queue definitions and other important information relevant to the queue manager.

Management of page sets is done through the use of buffer pools and storage classes.

Buffer pools and buffers for MQSeries

For efficiency, MQSeries for OS/390 implements a form of caching whereby messages are stored temporarily in buffers before being stored in page sets in DASD.

The buffers are organized into buffer pools. You can define up to four buffer pools for each MQSeries subsystem. Each buffer is 4 KB long. The maximum number of buffers is determined by the amount of storage available in the MQSeries address space. You are recommended to use four buffer pools.

Storage classes for MQSeries

A storage class maps one or more queues to a page set. When you define a queue you can also specify its storage class. More than one queue can use the same storage class, and you can define as many storage classes as you wish.

Log data sets for MQSeries

MQSeries for OS/390 records all *persistent* messages in the *active log* as they are put onto queues by applications. The active log resides on DASD. Entries to it are placed into a log buffer in main storage. The log buffer is written to main storage when a persistent message is placed in it or when it reaches a threshold value set at customization time. The log contains the information needed to recover messages, queues, and the queue manager; it does not contain information on statistics, tracing, or performance evaluation. (The *MQSeries for OS/390 System Management Guide* shows how to specify destinations for trace, statistic, and performance data.) The active log contains information from all the queues being used with MQSeries for OS/390.

When the active log is full, MQSeries for OS/390 switches to the next available log data set and, if archiving has been switched on during customization, copies the contents of this log to an *archive log*. The archive log can be a data set on a direct access storage device (DASD) or on magnetic tape. If there is a problem, MQSeries for OS/390 uses these log entries to restore the message queues.

The archive log consists of up to 1000 sequential data sets. Each data set can be cataloged using the Integrated Catalog Facility (ICF).

MQSeries for OS/390 allows you to have either *single logging* or *dual logging*. Dual logging is used to minimize the likelihood of problems during restart. When dual logging is in use, MQSeries for OS/390 records the same information into two data sets.

Single logging gives you between 2 and 53 active log data sets. Dual logging gives you between 4 and 106 active log data sets. If possible, when using dual logging, the log data sets should be on separate volumes. This reduces the risk of them both being lost if the volume is corrupted or destroyed. Each active log data set is a single-volume, single-extent VSAM entry-sequenced data set (ESDS).

There is no relationship between the number of queues and the number of log data sets that you have. Instead, the number of data sets required is dependent on the amount of message traffic that you plan for. An algorithm is given in “Logs and archive storage for MQSeries” on page 142 to help you to calculate the amount of storage you should reserve for your logs.

For a complete description of logs, their contents, customization, and archiving, see the *MQSeries for OS/390 System Management Guide*.

Bootstrap data set for MQSeries

The *bootstrap data set* (BSDS) is a VSAM key-sequenced data set (KSDS) that holds information needed by MQSeries for OS/390. It contains:

- An inventory of all active and archived log data sets known to MQSeries for OS/390. This inventory is used by MQSeries for OS/390 to:
 - Track the active and archived log data sets
 - Locate log records so that it can satisfy log read requests during normal processing
 - Locate log records so that it can handle restart processing

MQSeries for OS/390 stores information in the inventory each time an archive log data set is defined or an active log data set is reused. For active logs, the inventory shows which are full and which are available for reuse. The inventory holds the relative byte address (RBA) of each log data set. There can be more than one RBA if the log data set spans more than one volume.

- A *wrap-around* inventory of all recent MQSeries for OS/390 activity. This is needed if MQSeries for OS/390 has to be restarted.

The active logs are first registered in the BSDS when MQSeries for OS/390 is initiated. They cannot be replaced, nor can new ones be added, without terminating and restarting MQSeries. The BSDS is required if the subsystem has an error and has to be restarted. To minimize the likelihood of problems during a restart, MQSeries can be configured with dual BSDSs, each recording the same information. This is known as running in “dual mode”. As for dual active log data sets, copies should, if possible, be on separate volumes. This reduces the risk of them both being lost if the volume is corrupted or destroyed.

Archive log data sets and BSDS copies for MQSeries

A copy of the BSDS is placed in each new archive data set. If the archive log is on tape, the BSDS copy is the first file on the first output volume. If the archive log is on DASD, the BSDS copy is a separate file on the same volume.

What a log contains for MQSeries

An active log can contain up to 2^{48} bytes. Each byte in the active log can be addressed by its offset from the beginning of the log, and that offset is known as its *relative byte address* (RBA).

The log is made up of *log records*, each of which is a set of log data treated as a single unit. A log record is identified by the RBA of the first byte of its header; that RBA is called the *relative byte address of the record*. The RBA is like a time stamp because it uniquely identifies a record that starts at a particular point in the log.

Each log record has a header that gives its type, the MQSeries component that caused the record to be made, and, for unit of recovery records, the unit of recovery identifier.

Most of the log records describe changes to MQSeries queues. All such changes are made within units of recovery.

Checkpoint records for MQSeries

To reduce restart time, MQSeries for OS/390 takes periodic checkpoints during normal operation:

- When a predefined, customized number of log records has been written
- At the end of a successful restart
- At normal termination

At a checkpoint, MQSeries logs its current status and registers the RBA of the checkpoint in the bootstrap data set (BSDS). At restart, MQSeries uses the information in the checkpoint records to reconstruct the state it was in when it terminated.

Many log records can be written for a single checkpoint.

Chapter 26. Backup and recovery planning for MQSeries for OS/390

Developing backup and recovery procedures at your site is vital to avoid costly and time-consuming losses of data. MQSeries for OS/390 provides the means for recovering both queues and messages to their current state after a system failure. You should develop procedures for backing up page sets and creating a point of consistency.

This chapter describes what you should consider to minimize problems following any system failure. It contains information about:

- “Planning your logging environment with MQSeries”
- “Planning your archive storage with MQSeries”
- “Other recovery considerations with MQSeries” on page 128
- “General tips for backup and recovery with MQSeries” on page 130

Planning your logging environment with MQSeries

The MQSeries for OS/390 logging environment is established during customization to specify options, such as whether to have single or dual active logs, what media to use for the archive log volumes, and how many log buffers to have.

In a production subsystem, it is important to establish dual archiving and dual logging to minimize the risk of losing your data (for example, because of DASD failures).

Planning your archive storage with MQSeries

This section describes the different ways of maintaining your archive log data sets.

Archive log data sets can be placed on standard-label tapes, or DASD, and can be managed by Data Facility Hierarchical Storage Manager (DFHSM).

Archive log data sets are dynamically allocated, with names chosen by MQSeries for OS/390. The data set name prefix, block size, unit name, and DASD sizes needed for such allocations are specified when MQSeries for OS/390 is customized. You can also choose, at customization time, to have MQSeries for OS/390 add a date and time to the archive log data set name. You can change this information by customizing MQSeries for OS/390 again.

If you specify dual archive logs at installation time, each log *control interval* (CI) retrieved from the active log is written to two archive log data sets. The log records that are contained on the pair of archive log data sets are identical, but the end-of-volume points are not synchronized for multivolume data sets.

Other recovery considerations with MQSeries

In addition to the logging and archiving facilities provided by MQSeries for OS/390, you should also consider other space management and recovery facilities that are provided in your enterprise. The following sections provide a reminder of some of these facilities.

CICS recovery

CICS recognizes MQSeries for OS/390 as a non-CICS resource (or external resource manager), and includes MQSeries for OS/390 as an agent in any syncpoint coordination requests using the CICS resource manager interface (RMI). For more information about CICS recovery, see the *CICS Recovery and Restart Guide*. For information about the CICS resource manager interface, see the *CICS Customization Guide*.

IMS recovery

IMS/ESA recognizes MQSeries for OS/390 as an external subsystem and as a participant in syncpoint coordination. IMS recovery for external subsystem resources is described in the *IMS/ESA Customization Guide*.

RRS recovery

MQSeries can participate in units of recovery managed by OS/390 Recoverable Resource Manager Services (RRS). This means that MQSeries batch applications can participate in two-phase commit processing with other products that support RRS (for example, DB2). For more information, see “Transaction management and recoverable resource manager services” in the *MQSeries Application Programming Guide*.

Backup and recovery with DFHSM

The data facility hierarchical storage manager (DFHSM) does automatic space and data availability management among storage devices in your system. If you use it, you need to know that it moves data to and from MQSeries for OS/390 storage automatically.

DFHSM manages your DASD space efficiently by moving data sets that have not been used recently to less expensive storage. It also makes your data available for recovery by automatically copying new or changed data sets to tape, or DASD, backup volumes. It can delete data sets, or move them to another device. Its operations occur daily, at a specified time, and allow for keeping a data set for a predetermined period before deleting or moving it.

All DFHSM operations can also be performed manually. The *Data Facility Hierarchical Storage Manager User's Guide* explains how to use the DFHSM commands.

If you use DFHSM with MQSeries for OS/390, be aware that DFHSM:

- Uses cataloged data sets
- Operates on page sets and logs

Using Extended Recovery Facility (XRF)

MQSeries for OS/390 can be used in an Extended Recovery Facility (XRF) environment. All MQSeries for OS/390-owned data sets (executable code, BSDSs, logs, and page sets) must be on DASD shared between the active and alternate XRF processors. If you use XRF for recovery, you must stop MQSeries for OS/390 on the active processor and start it on the alternate. For CICS, this can be done using the command list table (CLT) provided by CICS, or manually by the system operator. For IMS, this is a manual operation and must be done after the coordinating IMS system has completed the processor switch.

MQSeries for OS/390 utilities must be completed or terminated before MQSeries for OS/390 can be switched to the alternate processor. Consider the effect of this potential interruption carefully when planning your XRF recovery plans.

Take care to prevent MQSeries for OS/390 starting on the alternate processor before the MQSeries for OS/390 system on the active processor terminates. A premature start can cause severe integrity problems in data, the catalog, and the log. Using global resource serialization (GRS) helps avoid the integrity problems by preventing simultaneous use of MQSeries for OS/390 on the two systems. The BSDS must be included as a protected resource, and the active and alternate XRF processors must be included in the GRS ring.

Using the OS/390 Automatic Restart Manager (ARM)

MQSeries for OS/390 can be used in conjunction with the OS/390 automatic restart manager (ARM). If a queue manager or a channel initiator has failed, ARM will restart it on the same OS/390 image. If OS/390 fails, a whole group of related subsystems and applications will also fail. ARM can restart all the failed systems automatically, in a predefined order, on another OS/390 image within the sysplex. This is called a cross-system restart.

You can use ARM to restart an MQSeries subsystem that uses LU 6.2 communication protocols on a different OS/390 image within the sysplex in the event of OS/390 failure. (You cannot do this if you use TCP communication protocols.)

To enable automatic restart:

- You must set up an ARM coupling data set.
- You must define the automatic restart actions that you want OS/390 to perform in an *ARM policy*.
- The ARM policy must be started.
- The subsystem must register with ARM at startup.

If you want to restart queue managers in different OS/390 images automatically, every queue manager must be defined in each OS/390 image on which that queue manager might be restarted, with a sysplex-wide unique 4-character subsystem name.

Using MQSeries with ARM is described in the *MQSeries for OS/390 System Management Guide*.

Preparing for disaster recovery

In the case of a total loss of an MQSeries for OS/390 computing center, you can recover on another MQSeries for OS/390 system at a recovery site. To be able to do this, you must regularly back up the data sets and logs and provide the means to transfer them to the recovery site if necessary.

General tips for backup and recovery with MQSeries

The MQSeries for OS/390 restart process recovers your data to a consistent state by applying log information to the page sets. If your page sets are damaged or unavailable, you can resolve the problem using your backup copies of your page sets (provided that all the logs are available). If your log data sets are damaged or unavailable, it might not be possible to recover completely. It is recommended that you do the following:

- Periodically take backup copies
- Use dual logging for your active log, archive log, and bootstrap data sets
- Keep archive logs you might need
- Retain the DD name or page set association

These are described in more detail below.

Periodically taking backup copies

A *point of consistency* is the term used to describe a set of backup copies of MQSeries for OS/390 page sets and the corresponding log data sets required to recover these page sets. These backup copies provide a potential restart point in the event of page set loss (for example, page set I/O error). If MQSeries for OS/390 were to be restarted using these backup copies, the data in MQSeries for OS/390 would be consistent up to the point that these copies were taken. Providing that all logs are available from this point, MQSeries for OS/390 can be recovered to the point of failure. See the *MQSeries for OS/390 System Management Guide* for more information about points of consistency.

The more recent your backup copies the quicker MQSeries for OS/390 can recover the data in the page sets. The recovery of the page sets is dependent on all the necessary log data sets being available.

In planning for recovery, you need to determine how often to take backup copies and how many complete backup cycles to keep. These values tell you how long you must keep your log data sets and backup copies of page sets for MQSeries for OS/390 recovery.

In deciding how often to take backup copies, consider the time needed to recover a page set. It is determined by:

- The amount of log to traverse
- The time it takes an operator to mount and remove archive tape volumes
- The time it takes to read the part of the log needed for recovery
- The time needed to reprocess changed pages

In general, the more often you make backup copies, the less time recovery takes; but, of course, the more time is spent making copies.

You should keep at least two copies of each cycle of page set backup. This reduces the risk involved if one backup copy is lost or damaged.

Using dual logging for your log data sets

This increases the chances of recovering from all problems. However, it also increases the processing overhead and will affect the performance of your system. You need to consider the gains and losses caused by dual logging.

If you use dual logging, keep the dual logs separate.

Keeping archive logs you might need

MQSeries for OS/390 can use archive logs during restart. You must keep sufficient archive logs so that the system can be fully restored. MQSeries for OS/390 might need to use an archive log to recover a page set from a restored backup copy. If you have discarded that archive log, MQSeries for OS/390 will not be able to restore the page set to its current state and you will have to resolve the problem manually. See the *MQSeries for OS/390 System Management Guide* for details of how recovery is effected using the archive log.

Retaining the DD name or page set association

MQSeries for OS/390 associates page set number 00 with DD name CSQP0000, page set number 01 with DD name CSQP0001, and so on up to CSQP0099. MQSeries for OS/390 writes recovery log records for a page set based on the DD name the page set is associated with. For this reason, you must not move or rename page sets that have already been associated with a page data set ID (PSID) DD name; otherwise, MQSeries for OS/390 tries to recover the page sets with the wrong log data.

Chapter 27. Security planning for MQSeries for OS/390

Because MQSeries for OS/390 handles information passing between subsystems, it needs the safeguard of a security system to ensure that the resources it owns and manages are protected and secure from unauthorized access. It needs to ensure that the following are not accessed or changed by any unauthorized person or process:

- Connections to the MQSeries for OS/390 subsystem
- Resources such as queues, processes, and namelists
- MQSeries links to remote queue managers
- MQSeries system control commands
- MQSeries messages
- Context information in messages

To provide the necessary security, MQSeries for OS/390 uses the OS/390 System Authorization Facility (SAF) to route authorization requests to an external security manager (ESM), such as the Resource Access Control Facility (RACF). MQSeries does no verification of its own.

This book assumes that you are using RACF as your ESM. If you are using a different ESM, you might need to modify the techniques mentioned in this book.

The decision to allow access to an object is made by the ESM. MQSeries follows the decision made by the ESM. If the ESM cannot make a decision, MQSeries does not allow access to the object.

If you are planning a distributed system, you must agree on the levels of security checking that are provided and used by the various administrative domains that exist across these distributed systems. Such agreement must also cover network security aspects and access by clients.

This chapter includes basic information about:

- “MQSeries security overview” on page 134
- “Security exits with MQSeries” on page 135
- “Things to consider when setting up security” on page 135

For further information about security facilities in MQSeries for OS/390, refer to the *MQSeries for OS/390 System Management Guide*.

MQSeries security overview

MQSeries for OS/390 provides you with a range of choices when specifying your security requirements. The choice ranges from no security checking to full checking.

Subsystem security with MQSeries

Subsystem security allows you to control whether any security checking is done on the whole subsystem. You can set security checking according to how secure you decide your users are in a particular subsystem. For example, you might apply full security checking on your production system, but have no checking on your test system.

If you decide you want subsystem security, you also need to consider the following:

- Connection security

Do you want to control who and what connects to your MQSeries for OS/390 subsystem?

- API resource security

Resources can be security checked when a user issues **MQOPEN** or **MQPUT1** calls to the API. The security checking of the API resources is subdivided into the following:

- Queue security

Queue security allows you to control who is allowed to open a queue and how they are allowed to access it.

- Process security

Process security allows you to control who is allowed to open a process.

- Namelist security

Namelist security allows you to control who is allowed to open a namelist.

- Alternate user security

Alternate user security is used to control whether a particular user can use another user ID's authority to open an object on that user ID's behalf.

- Context security

Context information consists of two parts, an identity section and an origin section. The identity section specifies who the message came from; the origin section specifies where the message came from and when it was put to the queue.

Context security allows you to control who is allowed to use the context-related options.

- Command security

Command security allows you to control who is allowed to issue an MQSeries for OS/390 command.

- Command resource security

Command resource security allows you to control the resources a command can access. Command resource security is independent of API security. For

example, user A might be allowed to define a local queue but might not be allowed to get messages from that queue.

- Reslevel security

Reslevel security is not a type of security but an option that allows you to control the number of user IDs checked for MQSeries for OS/390 API resource security checking (where applicable).

Security classes used by MQSeries

MQSeries for OS/390 uses its own special RACF classes to hold its security information. These special classes are described in the *MQSeries for OS/390 System Management Guide*.

Security exits with MQSeries

The message channels that are used for distributed queuing and the MQI channels that are used between clients and servers, have security exit facilities that can invoke programs supplied by you. Examples of the types of function for which these exit facilities are intended include:

- Verification that the partners at the ends of the channel are genuine, and have the appropriate security authorizations to take part in the exchange
- Encryption and decryption of messages

For more information about security exits, refer to Chapter 35, “Channel-exit programs” in the *MQSeries Intercommunication* manual.

Things to consider when setting up security

In order to help you set up your security you need to consider the following:

- Decide what levels of security you require (from above list).
- Decide what types of resources are going to be used and, preferably, set up a naming convention for them (for example, queues and their names).
- Decide who will be using the system and the resources you have. Consider which users and user IDs will use which resources and so on.
- Decide how they are going to be using the system and what access levels each user requires for each resource they use.
- Decide any grouping of users and resources that might be required.
- Decide which users will be accessing or connecting to MQSeries for OS/390 and how they will be doing so; for example, batch, CICS, IMS, and so on.
- Decide on how to manage network security, for example to ensure that all incoming messages are from authorized applications or users and that all outgoing messages are from authentic users and are secure.

For details on how the steps can be carried out to satisfy your security requirements, refer to the *MQSeries for OS/390 System Management Guide*.

Chapter 28. Administration of MQSeries for OS/390

This chapter is a summary of the administration facilities provided by MQSeries for OS/390. It has the following sections:

- “Managing objects with MQSeries”
- “Remote administration with MQSeries” on page 138
- “Managing accounting information with MQSeries” on page 139
- “Using the MQSeries utilities” on page 139

Details of the administration facilities provided by MQSeries for OS/390 are given in the *MQSeries Command Reference*, and in the *MQSeries for OS/390 System Management Guide*.

Managing objects with MQSeries

It is the administrator's job to monitor MQSeries for OS/390 and make any changes that might be necessary. To do this, the administrator needs to know where each MQSeries object resides, what its characteristics are, and who has access to it. The administrator can manage and monitor the resources by use of the commands, the operations and control panels, or the utility programs supplied with MQSeries for OS/390.

If there are sets of commands that are issued regularly on your system, you can run a supplied utility program, or write a program that constructs commands and places them on the command queue. Details of how to write these administration programs are contained in the *MQSeries for OS/390 System Management Guide*.

Commands on MQSeries

MQSeries for OS/390 supports MQSC commands, which can be issued from the following sources:

- The OS/390 console.
- The initialization input data set, CSQINP1, to be processed before the restart phase of MQSeries for OS/390 initialization.
- The initialization input data set, CSQINP2, to be processed after the restart phase of MQSeries for OS/390 initialization.
- The initialization input data set, CSQINPX, to be processed whenever the channel initiator is started.
- The supplied batch utility, CSQUTIL, processing a list of commands in a sequential data set.
- A suitably authorized application, by sending a command as a message to the command queue. This can be either:
 - A batch region program
 - A CICS application
 - An IMS application
 - A TSO application
 - An application program or utility on another MQSeries system

Much of the functionality of these commands is available in a user-friendly way from the MQSeries for OS/390 operations and controls panels. Information on using commands, and on using the operations and controls panels is given in the *MQSeries for OS/390 System Management Guide*.

MQSeries for OS/390 can perform security checks to ensure that the user is authorized to issue particular commands for particular resources.

Changes made to the resource definitions of a queue manager using the commands (directly or indirectly) are preserved across restarts of the MQSeries subsystem.

MQSeries for OS/390 does not support the PCF commands.

Managing communications with MQSeries

Part of the administrator's role is to ensure that the required communications links are activated, and to monitor the status of these links as required by your enterprise. You can find information describing these tasks in Chapter 22, "Monitoring and controlling channels on OS/390" in the *MQSeries Intercommunication* manual.

Remote administration with MQSeries

There are two aspects to the MQSeries remote administration facilities:

- MQSeries for OS/390 can be used to manage remote systems.
- Other remote products can be used to manage an MQSeries for OS/390 system.

Managing remote systems from MQSeries

Your administrator can manage remote MQSeries for OS/390 systems using facilities provided by MQSeries for OS/390.

Because of the differences between the MQSeries products, it is not always possible to manage remotely the same set of objects or attributes that you can manage locally.

If you wish to manage any other MQSeries product, you can write an application program to send the appropriate commands to the queue manager command queue. However, some MQSeries products do not have a command queue, and they cannot accept commands from local or remote application programs.

Managing MQSeries from remote systems

MQSeries for OS/390 can be managed from a remote MQSeries system, by an administrator using the facilities provided by the following products:

- MQSeries for Digital OpenVMS
- MQSeries for OS/390
- MQSeries for OS/2 Warp
- MQSeries for Tandem NSK
- MQSeries on UNIX systems
- MQSeries for Windows NT

Managing accounting information with MQSeries

MQSeries for OS/390 provides an accounting trace to enable you to collect information that you can use to charge your customers for their use of your MQSeries for OS/390 subsystem. This facility is described in the *MQSeries for OS/390 System Management Guide*.

Using the MQSeries utilities

MQSeries for OS/390 supplies a set of utility programs to help you perform various administrative tasks. These utilities:

- Perform backup, restoration, and reorganization tasks
- Issue commands and process object definitions
- Generate data-conversion exits
- Modify the bootstrap data set
- List information about the logs
- Print the logs

For more information about all these utilities, see the *MQSeries for OS/390 System Management Guide*.

The CSQUTIL utility

The CSQUTIL utility program is provided with MQSeries for OS/390 to help you perform backup, restoration, and reorganization tasks, and to issue commands and process object definitions. Through this utility program, you can invoke the following functions:

COMMAND	To issue any of the MQSC commands described in the <i>MQSeries Command Reference</i> manual, to record object definitions, and to make client-channel definition files.
COPY	To read the contents of a named MQSeries for OS/390 message queue or the contents of all the queues of a named page set, and put them into a sequential file and retain the original queue.
COPYPAGE	To copy whole page sets to larger page data sets.
EMPTY	To delete the contents of a named MQSeries for OS/390 message queue or the contents of all the queues of a named page set, retaining the definitions of the queues.
FORMAT	To format MQSeries for OS/390 page sets.
LOAD	To restore the contents of a named MQSeries for OS/390 message queue or the contents of all the queues of a named page set from a sequential file created by the COPY function.
RESETPAGE	To copy whole page sets to other page set data sets and reset the log information in the copy.
SCOPY	To copy the contents of a queue to a data set while the queue manager is offline.
SDEFS	To produce a set of define commands for objects while the queue manager is offline.

The data conversion exit utility

The MQSeries for OS/390 data conversion exit utility (CSQUCVX) runs as a stand-alone utility to create data conversion exit routines.

The change log inventory utility

The MQSeries for OS/390 change log inventory utility program (CSQJU003) runs as a stand-alone utility to change the bootstrap data set (BSDS). The utility can be used to:

- Add or delete active or archive log data sets
- Supply passwords for archive logs

The print log map utility

The MQSeries for OS/390 print log map utility program (CSQJU004) runs as a stand-alone utility to list the following information:

- Log data set name and log RBA association for both copies of all active and archive log data sets. Note that if dual logging is not active, there is only one copy of the data sets.
- Active log data sets available for new log data.
- Contents of the queue of checkpoint records in the bootstrap data set (BSDS).
- Contents of the archive log command history record.
- System and utility time stamps.

The log print utility

The log print utility program (CSQ1LOGP) is run as a stand-alone utility. You can run the utility specifying:

- A bootstrap data set (BSDS)
- Active logs (with no BSDS)
- Archive logs (with no BSDS)

Chapter 29. Storage planning for MQSeries for OS/390

This chapter tells you how to plan the type and amount of storage you require when you include MQSeries for OS/390 in your system. It contains information about:

- “MQSeries address space storage”
- “Logs and archive storage for MQSeries” on page 142
- “Storage for page data sets and messages” on page 143
- “Storage for bootstrap data sets (BSDS)” on page 143
- “Planning your library storage for MQSeries” on page 143
- “Further information for MQSeries” on page 143

MQSeries for OS/390 is an OS/390 subsystem running in its own address space. The virtual storage usage therefore falls into two categories: the storage used by the subsystem address space itself and the additional storage used by applications requesting MQSeries for OS/390 services.

MQSeries address space storage

Each MQSeries for OS/390 subsystem (including the channel initiator) has the following storage requirements:

CSA	4 KB
ECSA	5 MB

In addition, each concurrent MQSeries task requires about 1500 bytes of ECSA. When a task ends, this storage can be reused by other MQSeries tasks. MQSeries does not release the storage until the queue manager is shut down, so the maximum amount of ECSA required can be calculated by multiplying the maximum number of concurrent tasks by 1500 bytes.

Concurrent tasks consist of the following:

- The number of Batch, TSO or IMS regions that have connected to MQSeries, but not disconnected
- The number of CICS transactions that have issued an MQSeries request, but have not terminated

The trace table also resides in the ECSA; you should use the TRACTBL parameter of the CSQ6SYSP macro to determine the size of the resident trace table. This macro is described in the *MQSeries for OS/390 System Management Guide* manual.

Private region storage usage

Every channel uses the following private region virtual storage below the 16 MB line in the channel initiator address space:

- 1200 bytes if LE/370 APAR PQ03507 has been applied
- None if LE/370 APAR PQ06157 has also been applied
- 8 KB otherwise

Every channel uses approximately 160 KB of extended private region in the channel initiator address space. Storage is increased if messages larger than 32 KB are transmitted.

This increased storage is freed when:

- A sending or client channel requires less than half the current buffer size for 10 consecutive sends
- A heartbeat is sent or received

The storage is freed for re-use within the LE environment, but is not seen as free by the OS/390 virtual storage manager.

This means that the upper limit for the number of channels is dependent on message size and arrival patterns as well as individual user system limitations on extended private region size. The limit is likely to be approximately 9000 channels on many systems.

Logs and archive storage for MQSeries

Active log data sets record significant events and data changes. They are periodically off-loaded to the archive log. Consequently, the space requirements for your active log data sets depend on the volume of messages that your MQSeries for OS/390 handles and how often the active logs are off-loaded to your archive data sets. MQSeries for OS/390 provides optional support for dual logging; if you use this your log storage requirement will be doubled.

If you decide to place the archive data sets on direct access storage devices (DASD), you need to reserve enough space on the devices. Space should also be reserved for the bootstrap data sets (BSDS). The functions of these data sets are described in Chapter 25, "Data sets used by MQSeries for OS/390" on page 123. The above are all separate data sets and should, preferably, be allocated space on different volumes and strings to minimize DASD contention and problems caused by any defects on the physical devices.

As each change to the system is logged, the size of storage required can be estimated from the size and expected throughput of messages. You must add to this a small overhead for the header information in the data sets.

To arrive at the size of the log extents, an algorithm can be developed which depends on various factors including the message rate, the message size in bytes, and how often you want to switch the log.

Below is shown an approximate calculation for the number of records to specify in the cluster for the log data set.

Number of records = (a * log switch interval required in seconds) / 4096

where a = (Number of puts/sec * Average message size)+440
 + (Number of gets/sec * 72)
 + (Number of units of recovery started * 100)
 + (Number of syncpoints per second * 196)

Storage for page data sets and messages

The amount of storage needed for page data sets depends on the sizes of the messages that your applications will exchange, on the numbers of these messages, and on the rate at which they are created or exchanged. You can calculate the amount of storage needed for page data sets using the algorithm given in the *MQSeries for OS/390 System Management Guide*.

Storage for bootstrap data sets (BSDS)

Each BSDS requires 500 KB. You must have one BSDS but, optionally, can choose to have dual BSDSs. Further information about choosing single or dual BSDSs is given in Chapter 25, "Data sets used by MQSeries for OS/390" on page 123.

Planning your library storage for MQSeries

You need to allocate storage for the product libraries. The exact figures depend on your configuration, but an estimate of the space required by the distribution libraries is 35 MB. The target libraries also require about 35 MB. Additionally, you require space for the SMP/E libraries.

You should refer to the program directory supplied with MQSeries for OS/390 for information about the required libraries and their sizes.

Further information for MQSeries

This chapter has shown some of the main considerations when planning the storage required for MQSeries for OS/390. For more information about the library sizes, refer to the *MQSeries for OS/390 Program Directory*. For more information about storage variables to be defined during customization, refer to the *MQSeries for OS/390 System Management Guide*.

Chapter 30. Performance of MQSeries for OS/390

This chapter introduces the performance considerations that you must review when planning to include MQSeries for OS/390 in your system. These items include:

- “Impact of logging for MQSeries”
- “Causes of I/O to log for MQSeries” on page 148
- “Buffer pools, page sets, storage classes, and queues for MQSeries” on page 149
- “Monitoring performance for MQSeries” on page 150
- “Where to find more information” on page 150

Impact of logging for MQSeries

The performance of MQSeries for OS/390 is sensitive to logging activities. MQSeries for OS/390 provides and maintains data integrity by the use of logs to record messaging events. If no logging were to take place, the performance of the system would depend primarily on processor availability.

MQSeries logs and page data sets are used in the same way as is typical for database systems. That is, messages are written to the log data set and held in virtual storage buffer pools backed by page data sets that are updated asynchronously.

Logs generally have a greater effect on the performance of MQSeries than they do on the performance of a database system. This is because typical database systems have a high read-only to update ratio, whereas in MQSeries, most **MQPUT** and **MQGET** operations are the equivalent of the addition and deletion of database rows respectively (an update operation). This means that MQSeries logs are typically written to more frequently than the logs for a database system. However, nonpersistent (nonrecoverable) messages are not written to the log data set.

Significant logging takes place mainly when using persistent messages, and particularly when persistent messages are being moved between queue managers. Hence, performance is affected by the number, and size, of persistent messages in the system, and also by the frequency of syncpointing and DASD performance for the log data sets.

Figure 11 on page 146 shows the response overhead added by logging for various message sizes in a typical CICS region. You will see that the response time increases by about 15%.

To achieve the best performance:

- Put active logs on the fastest DASD (for example, use DASD fast write).
- Ensure that when an active log is in use it is the only data set on that volume.




Figure 11. Impact of logging on response time

Impact of dual logging on MQSeries

MQSeries for OS/390 offers the capability of having dual logs. These logs should be placed on separate volumes. This ensures the log writes are not competing for disk accesses on the same volume and are therefore faster, as well as giving more protection against unexpected corruption of data on a volume.

Figure 12 on page 147 shows the overhead in terms of transaction response times in a CICS region with and without dual logging. Each transaction in Figure 12 on page 147 consists, on average, of five put or get messages, and covers a range of about 300 to 500 log events per second.

Note: The fast write facility is turned on in this example. For an explanation see “Fast write for logging on MQSeries” on page 147.

Ideally, data sets containing one copy of the log should be located on DASD accessed through a separate control unit and separate channel path from data sets containing the other copy.




Figure 12. Impact of dual logging on response time

Fast write for logging on MQSeries

Fast write is a facility provided on some DASD controllers. It is a cache that is used to buffer write operations to DASD. Data can be written into the cache at channel speeds and is not held up by seek, rotational, and other delays in the DASD hardware.

Throughput gains can be made by directing the logs to a fast write facility if it is available. The facility significantly reduces I/O response times, as shown in Figure 13 on page 148. The figure shows that if fast write is in use, a high throughput can be sustained beyond the point where, without fast write caching, the I/O time to complete would cause degradation in the transaction response time.




Figure 13. Impact of using 3990 fast write on response time

Causes of I/O to log for MQSeries

The active log buffer is written to DASD when a syncpoint is taken or when the threshold value set for flushing the buffer to DASD is reached. The log buffer is also written to DASD when a persistent message is placed on a queue and that message is not operating within a syncpoint.

Checkpointing on MQSeries

The purpose of a checkpoint is to harden committed messages to DASD periodically, and reduce the elapsed time required to recover messages in the event of recovery restart. The number of writes to the log buffer before a checkpoint is taken is defined when the system is customized. A checkpoint is also taken at each log switch.

At each checkpoint, all buffer pool pages that have changes not yet written to a page set, and older than the previous checkpoint, are written. Consequently, a higher number of log writes specified between checkpoints tends to decrease the amount of page set I/O, but increase the elapsed time for any recovery restart.

MQSeries page set I/O on MQSeries

Page set I/O is another activity that impacts performance. Hence, the more it can be avoided, the better the performance. You should specify enough buffer pool pages to contain the expected workload, so reducing excessive I/O. If the number you specify is insufficient, the I/O rate of the OS/390 system will increase.

At initialization you need to define the number of data buffers that are to be made available for use by queues. You can define between one and four buffer pools. Each buffer pool can hold between 100 and 125 000 buffers. You must define how many buffers you will need. Each buffer pool is also defined to a particular page data set ID (PSID).

You must also decide where the page data sets will be placed. When you have defined more than one PSID, it is best to locate the data sets on different physical volumes.

Buffer pools, page sets, storage classes, and queues for MQSeries

- Buffer pools are areas of MQSeries for OS/390 virtual storage reserved to satisfy the buffering requirements for one or more queues.
- Page sets are VSAM linear datasets and are each associated with a buffer pool.
- Storage classes are used to provide a mapping between queues and page sets.
- A queue is associated with a page set, which is a VSAM data set that is used when MQSeries for OS/390 moves data (for example, queues and messages) from buffers in main storage to permanent backing storage (DASD).

This gives a hierarchy which provides the following mappings:

- A queue (via its storage class) is associated with a single page set; many queues can map to the same page set.
- A page set is associated with a single buffer pool; many page sets can map to the same buffer pool.

In general, it is best to allocate as much storage as possible for the buffer pools. The larger the pool, the more likely that a message put to a queue will stay in storage long enough for it to be retrieved, thus saving I/O operations to the backing page set.

You should try to separate short-lived messages from messages that exist for a long time (for example half an hour). This means using different queues for the different messages, allocating the queues to different page sets, and allocating the different page sets to different buffer pools.

For short-lived messages you should allocate a large buffer pool. Long lived messages are written to the page set when the buffer pool fills up, or the messages have existed over two checkpoints. They are written to disk to reduce the startup time if the queue manager ends abnormally. Having a large buffer pool causes a lot of activity at a checkpoint, when the queue manager writes out the 'old' messages. Having a small buffer pool causes the data to be written to the page set at a steady rate, and reduces the impact at a checkpoint.

Refer to the *MQSeries for OS/390 System Management Guide* for more information about tuning your system.

Monitoring performance for MQSeries

A number of tools to monitor the performance of an MQSeries for OS/390 subsystem are provided. These include:

- Trace
- Display commands
- CICS adapter statistics

Further tools are provided by OS/390:

- System Management Facility (SMF)
- Generalized Trace Facility (GTF)

You can also use other IBM licensed programs:

- Service Level Reporter (SLR)
- Resource Management Facility (RMF™)
- CICS Monitoring facility

The use of these tools to monitor MQSeries for OS/390 performance is described in the *MQSeries for OS/390 System Management Guide*.

In addition to using these tools, with MQSeries for OS/390 you can write your own application programs, to use the event messages generated by the instrumentation events facility to produce performance reports.

More information on using instrumentation events is given in Part 1, “Event monitoring” in the *MQSeries Programmable System Management* manual.

Where to find more information

Information about MQSeries performance is available on the Internet at:

<http://www.software.ibm.com/mqseries/txppacs/txpm1.html>

Chapter 31. Measured usage license charges with MQSeries for OS/390

Measured Usage License Charges (MULC) is a particular way of charging you for an IBM product that runs on an OS/390 system, based on how much use you make of the product. To determine the product usage, the OS/390 system records the amount of processor time that is used by the product when it executes.

OS/390 can measure how much processing time is spent in doing work on behalf of the MQSeries queue manager which is handling MQI calls, executing MQSeries commands, or performing some other action to support the messaging and queuing functions used by your application programs. The amount of processing time is recorded in a file at hourly intervals, and the hourly records are totalled at the end of a month. In this way, the total amount of time that has been used by the MQSeries for OS/390 product on your behalf is computed, and used to determine how much you should pay for your use of the MQSeries for OS/390 product that month.

MULC is implemented as follows:

- When MQSeries for OS/390 is installed, it identifies itself to OS/390, and requests that the *System Management Facilities (SMF)* mechanism within OS/390 is to automatically measure how much processor time is used by the MQSeries for OS/390 product.
- When enabled, the OS/390 usage measurement facility collects usage figures for each hour of the day, and generates usage records that are added to a report file on disk.
- At the end of one full month, these usage records are collected by a program, which generates a report of product usage for the month. This report is used to determine the charge for the MQSeries for OS/390 product.

More details on MULC can be found in *MVS/ESA Support for Measured License Charges*, GC28-1098.

Part 6. Planning for MQSeries for Tandem NSK

Chapter 32. Introduction to MQSeries on Tandem NSK	155
Planning for MQSeries	155
Preparing your applications for use with MQSeries	155
Planning to use MQSeries in a network	156
Installing MQSeries	156
Setting up MQSeries	156
Planning recovery services with MQSeries	157
Planning data security on MQSeries	157
Administration with MQSeries	157
Migration from MQSeries for Tandem NSK Version 1.5.1	158
Migrating applications with MQSeries	158
 Chapter 33. Backup and recovery planning for MQSeries for Tandem NSK	 159
Recovery facilities with MQSeries	159
Recovering from problems with MQSeries	159
Backing up and restoring with MQSeries	159
 Chapter 34. Security planning for MQSeries for Tandem NSK	 161
Controlling access to resources with MQSeries	161
Managing access through user groups with MQSeries	162
Resources you can protect with MQSeries	162
Using the Object Authority Manager (OAM) commands with MQSeries	163
Security exits with MQSeries	163
 Chapter 35. Administration of MQSeries for Tandem NSK	 165
Managing objects with MQSeries	165
Commands on MQSeries	165
Managing communications with MQSeries	166
Remote administration with MQSeries	166
Managing remote systems from MQSeries	166
Managing MQSeries from remote systems	166

Chapter 32. Introduction to MQSeries on Tandem NSK

MQSeries for Tandem NSK runs on a machine that is capable of running the Tandem NSK operating system. MQSeries provides the MQI programming interface for use by application programs that are running on Tandem NSK.

For information on the hardware and software environments, see “MQSeries for Tandem NSK” on page 249.

Planning for MQSeries

This chapter helps you to plan for the introduction of MQSeries for Tandem NSK into your enterprise, and introduces the items that you need to consider when doing this planning.

There are several stages in planning for the use of MQSeries for Tandem NSK that you must go through. They are:

1. Preparing your applications for the use of MQSeries for Tandem NSK
2. Planning to include MQSeries for Tandem NSK in a network
3. Preparing to install MQSeries for Tandem NSK
4. Planning to set up MQSeries for Tandem NSK

A prime requirement for a message delivery system is that it must be reliable. Functions are built into MQSeries for Tandem NSK to ensure that:

- Messages are not lost despite system failures
- Messages are not delivered more than once
- Messages are not accessed by, or delivered to, unauthorized persons or applications

MQSeries uses Tandem NSK facilities to support these functions.

You must also plan for the operation and administration of MQSeries for Tandem NSK in your enterprise, and consider the implementation of an appropriate set of security facilities. Brief outlines of these planning operations are included in this chapter.

Preparing your applications for use with MQSeries

MQSeries for Tandem NSK brings the Message Queue Interface (MQI) to your applications. This interface allows you to modify existing applications and to write new applications. The MQI removes much of the need to understand the network and communication systems that you use. Thus you can expect to generate applications more speedily than before. However, you must prepare to take advantage of the MQI by planning its use in your applications and by understanding the ways in which it assists you.

You can find more information on how to use the MQI in your applications by referring to the *MQSeries Application Programming Guide*.

Planning to use MQSeries in a network

MQSeries for Tandem NSK uses distributed queuing to exchange messages between MQSeries platforms, using either the SNA LU 6.2, or TCP transmission protocols.

You must consider how you will attach MQSeries for Tandem NSK to a network, and how you will define the message channels that will be used to exchange messages.

According to the way that you have set your systems up, security checks can be performed at various times. Various exits are provided that can be used by your applications to provide these facilities.

“MQSeries interoperability summary” on page 226 shows the links that are possible to other MQSeries products, and the transmission protocols that can be used.

For further information about distributed queuing, refer to the *MQSeries Intercommunication* manual.

Installing MQSeries

MQSeries for Tandem NSK is installed with the **instmqm** control command. For information about installing MQSeries, see the *MQSeries for Tandem NonStop Kernel System Management Guide*.

Setting up MQSeries

After installation, MQSeries for Tandem NSK needs to be set up, and customized for your own use. This ensures that the appropriate Tandem NSK facilities are made available to MQSeries, and that your MQSeries system is correctly initialized and ready to work with your applications.

You need to do the following:

- Define queues
 - Consider your naming conventions for queues
- Define trigger processes
- Define remote links
 - Define associated transmission queues
 - Consider your naming conventions for remote queues
 - Consider your naming conventions for channels

Note: The characters within the names given to all MQSeries objects are case sensitive. Therefore, be very careful when defining the names of objects, to select the appropriate uppercase or lowercase characters.

You can find more information on the setting up and customizing processes for MQSeries for Tandem NSK in the *MQSeries for Tandem NonStop Kernel System Management Guide*.

Planning recovery services with MQSeries

MQSeries for Tandem NSK provides facilities to allow backup and recovery of the messaging system. Chapter 33, “Backup and recovery planning for MQSeries for Tandem NSK” on page 159 introduces you to these facilities, and to the items that you need to consider in order to include MQSeries for Tandem NSK in your backup and recovery plans.

You can find more information on the backup and recovery facilities provided by MQSeries for Tandem NSK in the *MQSeries for Tandem NonStop Kernel System Management Guide*.

Planning data security on MQSeries

MQSeries for Tandem NSK uses the facilities of the MQSeries *object authority manager (OAM)* installable component to control access to the various different types of queue manager resource (queues, process definitions, channels, and queue managers).

You can find more general information on authorization installable components in Chapter 8, “Introduction to the MQSeries Framework” on page 55.

Chapter 34, “Security planning for MQSeries for Tandem NSK” on page 161 introduces you to the security facilities provided by MQSeries for Tandem NSK and to some of the items you need to consider when planning for security.

You can find more information on the security facilities provided by MQSeries for Tandem NSK in the *MQSeries for Tandem NonStop Kernel System Management Guide*.

Administration with MQSeries

Information about administering MQSeries is given in “MQSeries product administration facilities” on page 36.

A summary of the administration facilities provided for Tandem NSK is given in Chapter 35, “Administration of MQSeries for Tandem NSK” on page 165. Full details of these facilities can be found in the *MQSeries for Tandem NonStop Kernel System Management Guide*.

Migration from MQSeries for Tandem NSK Version 1.5.1

If you are a user of MQSeries for Tandem NSK Version 1.5.1, you can convert your existing MQSeries configuration files and messages to work with MQSeries for Tandem NSK Version 2.2 using the following two conversion utilities:

- | | |
|----------------|---|
| CNV1520 | Converts MQSeries for Tandem NSK Version 1.5.1 queue and channel definitions into MQSC scripts. |
| CNVMSGs | Transfers messages from MQSeries for Tandem NSK Version 1.5.1 message queues to Version 2.2 message queues after the queue definitions have been established using CNV1520. |

Both utilities reside in the ZMQSEXE subvolume.

Migrating applications with MQSeries

To migrate your MQSeries for Tandem NSK Version 1.5.1 applications you must recompile and rebind them with Version 2.2 header files and libraries. Stubs have been provided for MQI calls that are not present or required in MQSeries for Tandem NSK Version 2.2, so code changes relating to MQSeries (other than including the correct header files) are not required. However, MQSeries for Tandem NSK Version 2.2 requires that you compile C programs with the WIDE model. MQSeries for Tandem NSK Version 1.5.1 required LARGE; if your programs contain code that relies on LARGE data representations, the code might have to be changed before it functions correctly under the WIDE model.

Chapter 33. Backup and recovery planning for MQSeries for Tandem NSK

This chapter describes the background concepts of recovery and restart. More information about the recovery facilities of MQSeries for Tandem NSK is given in the *MQSeries for Tandem NonStop Kernel System Management Guide*.

Recovery facilities with MQSeries

MQSeries for Tandem NSK ensures that messages are not lost by using the Tandem NonStop Transaction Manager (TM/MP). TM/MP provides transaction protection, queue-file consistency, and queue-file recovery.

The TM/MP subsystem manages the complex operations for current transactions and database consistency, both user operations and MQSeries operations, making these operations transparent to both users and application programs.

A recovery restores the queue manager to the state it was in when the queue manager stopped. Any transactions that are in process are rolled back, removing from the queues any messages that were not committed at the time the queue manager stopped. Recovery restores all persistent messages; nonpersistent messages are lost during the process.

Recovering from problems with MQSeries

If you properly configure MQSeries and your NSK system software and hardware, the failure of any single hardware or software component does not result in the loss of any data or system functions. MQSeries can recover from a single point of failure while maintaining data integrity.

For more information about recovery from failures, see the *MQSeries for Tandem NonStop Kernel System Management Guide*.

Backing up and restoring with MQSeries

Periodically, you might want to make a backup of your queue manager data to provide protection against possible corruption due to hardware failures. See the *MQSeries for Tandem NonStop Kernel System Management Guide* for information about backing up and restoring MQSeries for Tandem NSK.

Chapter 34. Security planning for MQSeries for Tandem NSK

Because MQSeries queue managers handle the transfer of information that is potentially valuable, you need the safeguard of an authority system. This step ensures that the resources that a queue manager owns and manages are protected from unauthorized access, which could lead to the loss or disclosure of the information. In a secure system, it is essential that none of the following are accessed or changed by any unauthorized user or application:

- Connections to a queue manager
- Access to MQSeries objects such as queues, channels, and processes
- Commands for queue manager administration, including MQSC and PCF commands
- Access to MQSeries messages
- Context information associated with messages

You should develop your own policy with respect to which users have access to which resources.

This chapter describes the access control security features in MQSeries for Tandem NSK. It contains these sections:

- “Controlling access to resources with MQSeries”
- “Resources you can protect with MQSeries” on page 162
- “Using the Object Authority Manager (OAM) commands with MQSeries” on page 163
- “Security exits with MQSeries” on page 163

Full details of MQSeries for Tandem NSK security handling are given in the *MQSeries for Tandem NonStop Kernel System Management Guide*.

Controlling access to resources with MQSeries

By default, access to queue manager resources is controlled through an authorization service installable component. The authorization service component supplied with MQSeries for Tandem NSK is called the OAM and is automatically installed and enabled for each queue manager you create, unless you specify otherwise.

The OAM is an *installable component* of the authorization service. Because the OAM is an installable component, you can implement your own security controls in place of, or in addition to, those supplied by the OAM. (For more information on installable services and installable components, see Chapter 8, “Introduction to the MQSeries Framework” on page 55.)

The OAM manages users’ authorizations to manipulate MQSeries objects, including queues, process definitions, and channels. It also provides a command interface through which you can grant or revoke access authority to an object for a specific group of users. The decision to allow access to a resource is made by the OAM,

and the queue manager follows that decision. If the OAM cannot make a decision, the queue manager prevents access to that resource.

The OAM uses the user and group IDs and security features of the Tandem NSK operating system. Users can access queue manager objects only if they have the required authority.

Managing access through user groups with MQSeries

Managing access permissions to MQSeries resources is based on NSK *groups*. The OAM maintains authorizations at the group level.

Using groups, rather than individual users, for authorization reduces the amount of administration required. Typically, a particular kind of access is required by more than one user. For example, you might define a group consisting of end users who want to run a particular application. New users can be given access by adding the appropriate group to their NSK user ID. Unless MQSeries is installed on a system using SAFEGUARD to create data sharing groups, each user ID can be associated with a single, primary group only.

You should keep the number of groups as small as possible. For example, you can divide users into one group for application users and one for administrators.

Resources you can protect with MQSeries

Through OAM you can control:

- Access to MQSeries objects through the MQI. When an application program attempts to access an object, the OAM checks if the user ID making the request has the authorization (through its user group) for the operation requested.

In particular, this means that queues, and the messages on queues, can be protected from unauthorized access.
- Permission to use MQSC commands; only members of user group MQM, or those authorized via **setmqaut**, can execute queue manager administration commands, for example, to create a queue.
- Permission to use control commands; only members of user group MQM can execute control commands, for example, creating a queue manager or starting a command server.
- Permission to use PCF commands.

Different groups of users can be granted different kinds of access authority to the same object. For example, for a specific queue, one group might be allowed to perform both put and get operations; another group can only be allowed to browse the queue (MQGET with browse option). Similarly, some groups might have get and put authority to a queue, but are not allowed to alter or delete the queue.

Using the Object Authority Manager (OAM) commands with MQSeries

The OAM provides a command interface for granting and revoking authority. Before you can use these commands, you must be authorized – your user ID must belong to the NSK MQM group. This group should have been set up before you installed the product.

If your user ID is a member of group MQM, you have a ‘super user’ authority to the queue manager. You are now authorized to issue any MQI request or control command from your user ID.

The OAM provides two commands that you can invoke from TACL to manage the authorizations of users. These are:

- **setmqaut** (set or reset authority)
- **dspmqaut** (display authority)

Details of these commands can be found in the *MQSeries for Tandem NonStop Kernel System Management Guide*.

Security exits with MQSeries

The message channels that are used for distributed queuing, and the MQI channels that are used between clients and servers, both have security exit facilities that can invoke programs that you have supplied.

For more information on these security exit programs, see Chapter 35, “Channel-exit programs” in the *MQSeries Intercommunication* manual.

Chapter 35. Administration of MQSeries for Tandem NSK

This chapter is a summary of the administration facilities provided by MQSeries for Tandem NSK. It has the following sections:

- “Managing objects with MQSeries”
- “Remote administration with MQSeries” on page 166

Details of the commands, command interfaces, and utilities that are provided by MQSeries for Tandem NSK are given in the *MQSeries for Tandem NonStop Kernel System Management Guide*. You need to arrange for users who need to be able to use these administration facilities to have the necessary authorizations, using the procedures given in the *System Management Guide*.

Managing objects with MQSeries

It is the administrator's job to monitor MQSeries for Tandem NSK and make any changes that might be necessary. To do this, the administrator needs to know where each MQSeries object resides, what its characteristics are, and who has access to it.

The administrator can manage and monitor the resources using MQSeries commands (MQSC), or, if there are sets of commands that are issued regularly, by writing an application program that places them on the command queue.

MQSeries can use the security features provided by the OAM, or by a security component that you have installed, to ensure that the user is authorized to issue particular commands for particular resources.

Commands on MQSeries

MQSeries for Tandem NSK supports the following administration commands and facilities:

- You can enter control commands on the command line.
- You can use the **runmqsc** control command to cause MQSC commands from standard input to be executed.
- Any local or remote MQSeries application program can generate PCF commands in messages and put them to the command queue SYSTEM.ADMIN.COMMAND.QUEUE, to be processed by the MQSeries for Tandem NSK command server.

In addition:

- Some TS/MP (Pathway) commands are used for administration.
- The MQM (Message Queue Management) facility supports some administration tasks.

More information on how to use all these facilities is given in the *MQSeries for Tandem NonStop Kernel System Management Guide*.

Changes made to the resource definitions of a queue manager using the commands (directly or indirectly) are preserved across restarts of MQSeries for Tandem NSK.

Managing communications with MQSeries

Part of the administrator's role is to ensure that the required communications links are activated, and to monitor the status of these links as required by your enterprise. You can find information describing these tasks in Part 3, "DQM in MQSeries for OS/2 Warp, Windows NT, Digital OpenVMS, Tandem NSK, and UNIX systems" in the *MQSeries Intercommunication* manual.

Remote administration with MQSeries

There are two aspects to the MQSeries remote administration facilities:

- MQSeries for Tandem NSK can be used to manage remote systems.
- Other remote products can be used to manage MQSeries for Tandem NSK.

Managing remote systems from MQSeries

Facilities are provided by MQSeries for Tandem NSK to allow an administrator to manage the following remote systems:

- MQSeries for AS/400
- MQSeries for Digital OpenVMS
- MQSeries for OS/2 Warp
- MQSeries for OS/390
- MQSeries for Tandem NSK
- MQSeries on UNIX systems
- MQSeries for Windows NT

Because of the differences in the MQSeries products, it is not always possible to manage remotely the same set of MQSeries objects or attributes that you can manage locally.

If you want to manage any other MQSeries product, you can write an application program to send the appropriate commands to the command queue for that product. However, some MQSeries products do not have a command queue, so they cannot accept commands from local or remote application programs.

Managing MQSeries from remote systems

MQSeries for Tandem NSK can be managed from a remote MQSeries system, by an administrator using the facilities provided by the following products:

- MQSeries for AS/400
- MQSeries for Digital OpenVMS
- MQSeries for OS/390
- MQSeries for OS/2 Warp
- MQSeries for Tandem NSK
- MQSeries on UNIX systems
- MQSeries for Windows NT

Note: You can manage MQSeries for Tandem NSK from MQSeries for OS/390 by writing an application program to send the appropriate PCF commands to the command queue.

Part 7. Planning for MQSeries on UNIX systems

Chapter 36. Introduction to MQSeries on UNIX systems	169
Planning for MQSeries	170
Preparing your applications for use with MQSeries	170
Planning to use MQSeries in a network	171
Installing MQSeries	171
Setting up MQSeries	172
Planning recovery services with MQSeries	172
Planning data security on MQSeries	172
Administration with MQSeries	173
Support for R/3 with MQSeries	173
Migration from MQSeries Version 1	173
Migration from MQSeries Version 2	174
Euro symbol support	174
 Chapter 37. Backup and recovery planning for MQSeries on UNIX systems	 175
Logging with MQSeries	175
Types of logging with MQSeries	176
Selecting a logging method with MQSeries	176
Resource management with MQSeries	177
MQSeries as a resource manager	177
MQSeries as a transaction manager	177
Recovering from problems with MQSeries	178
High availability with MQSeries	178
 Chapter 38. Security planning for MQSeries on UNIX systems	 179
Controlling access to resources with MQSeries	179
Managing access through user groups with MQSeries	179
Resources you can protect with MQSeries	180
Using the security commands with MQSeries	180
Security exits with MQSeries	181
 Chapter 39. Administration of MQSeries on UNIX systems	 183
Managing objects with MQSeries	183
Commands on MQSeries	183
Managing communications with MQSeries	184
Remote administration with MQSeries	184
Managing remote systems from MQSeries	184
Managing MQSeries from remote systems	184
 Chapter 40. Storage planning for MQSeries on UNIX systems	 185
RAM considerations for MQSeries	185
Disk space considerations for MQSeries	185
Product modules for MQSeries	185
Message queues for MQSeries	186
Log files for MQSeries	186
Capacity planning and performance figures for MQSeries	186

Chapter 36. Introduction to MQSeries on UNIX systems

MQSeries on UNIX systems

MQSeries on UNIX systems is the general term used in this book for UNIX operating systems that support MQSeries Level 2 products (for example: AIX, Sun Solaris, and HP-UX).

MQSeries products that run on UNIX operating systems comprise two parts, the *server* and the *clients*. The server runs on a machine that is capable of running an MQSeries queue manager on a UNIX system; the clients provided with the product are for OS/2 Warp, Windows 3.1, DOS, Windows 95, and your UNIX platform. On AIX, HP-UX, and Sun Solaris, clients are also provided for AIX, HP-UX, Sun Solaris, and Windows NT.

A variety of terminals (such as X-stations, non-programmable terminals, and portables) can access the server code. There is no MQSeries code on such terminals.

For more information on the hardware and software environments, see:

- “MQSeries for AIX” on page 232.
- “MQSeries for AT&T GIS UNIX” on page 236.
- “MQSeries for HP-UX” on page 239.
- “MQSeries for SINIX and DC/OSx” on page 245.
- “MQSeries for Sun Solaris” on page 247.

In this section, you are sometimes referred to other books for more information; the appropriate books are:

Table 15. MQSeries on UNIX systems: system administration manuals

UNIX platform	See these manuals
AIX	<i>MQSeries for AIX V5.1 Quick Beginnings, MQSeries System Administration</i>
AT&T GIS UNIX	<i>MQSeries for AT&T GIS UNIX System Management Guide</i>
HP-UX	<i>MQSeries for HP-UX V5.1 Quick Beginnings, MQSeries System Administration</i>
SINIX and DC/OSx	<i>MQSeries for SINIX and DC/OSx System Management Guide</i>
Sun Solaris	<i>MQSeries for Sun Solaris V5.1 Quick Beginnings, MQSeries System Administration</i>

Planning for MQSeries

This chapter helps you to plan for the introduction of MQSeries on UNIX systems into your enterprise, and introduces the items that you need to consider when doing this planning.

There are several stages in planning for the use of MQSeries on UNIX systems that you must go through. They are:

1. Preparing your applications for the use of MQSeries on UNIX systems
2. Planning to include MQSeries on UNIX systems in a network
3. Preparing to install MQSeries on UNIX systems
4. Planning to set up MQSeries on UNIX systems

A prime requirement for a message delivery system is that it must be reliable. Many functions are built into MQSeries on UNIX systems to ensure that:

- Messages are not lost despite system failures
- Messages are not delivered more than once
- Messages are not accessed by, or delivered to, unauthorized persons or applications

MQSeries on UNIX systems uses logging and other facilities to support these functions.

You must also plan for the operation and administration of MQSeries on UNIX systems in your enterprise, and consider the implementation of an appropriate set of security facilities. Brief outlines of these planning operations are included in this chapter.

Preparing your applications for use with MQSeries

MQSeries on UNIX systems brings the Message Queue Interface (MQI) to your applications. This interface allows you to modify existing applications and to write new applications. The MQI removes much of the need to understand the network and communication systems that you use. Thus you can expect to generate applications more speedily than before. However, you must prepare to take advantage of the MQI by planning its use in your applications and by understanding the ways in which it assists you.

You can find more information on how to use the MQI in your applications by referring to the *MQSeries Application Programming Guide*.

MQSeries for AT&T GIS UNIX and DC/OSx do not support threads. MQSeries for AIX, HP-UX, SINIX, and Sun Solaris support multithreaded applications, but there are limitations that are documented in "Threading" in the *MQSeries Application Programming Guide* manual. If the platform that you intend to use is not specifically mentioned, check with your IBM support center whether multithreaded applications are supported.

Interfacing with CICS with MQSeries

With MQSeries products on UNIX systems, you can create application programs for the appropriate CICS transaction environment. These applications can use the MQI to communicate with CICS or non-CICS programs in any of the environments supported by the MQSeries products.

Planning to use MQSeries in a network

MQSeries on UNIX systems uses the distributed queue management (DQM) facility to exchange messages between MQSeries platforms, using either the SNA LU 6.2 or TCP transmission protocols. The UDP (User Datagram Protocol) can also be used on AIX.

You must consider how you will attach MQSeries on UNIX systems to a network, and how you will define the message channels that will be used to exchange messages. You can simplify your definitions for distributed queuing on AIX, HP-UX, and Sun Solaris by using MQSeries clusters.

According to the way that you have set your systems up, security checks can be performed at various times. MQSeries products on UNIX systems do not provide communications link authorization or data encryption on these links. Instead, various exits are provided that can be used by your applications to provide these facilities. On AIX, HP-UX, and Sun Solaris, MQSeries also provides exits relating to DCE security.

“MQSeries interoperability summary” on page 226 shows the links that are possible to other MQSeries products, and the transmission protocols that can be used.

For further information about distributed queue management, refer to the *MQSeries Intercommunication* and the *MQSeries Queue Manager Clusters* manuals.

Installing MQSeries

Before you can install one of the MQSeries products on a UNIX system, you must create both a group and user with the name **mqm** that will own the directories and files that contain the various resources associated with the product. These are created for you when you install MQSeries on AIX, provided you are not using NIS (if they do not already exist).

To prepare for the actual installation, you need to plan how much disk space will be required in your UNIX system to accommodate MQSeries. Assistance is given in Chapter 40, “Storage planning for MQSeries on UNIX systems” on page 185 to help you plan the amount of space required.

You can find more information to help you with the installation of MQSeries on a UNIX system in the appropriate manual (see Table 15 on page 169).

When you have installed MQSeries on AIX, HP-UX, or Sun Solaris, you can run the supplied installation verification test. This is described in:

- “Chapter 3. Installing the MQSeries for AIX Server” in the *MQSeries for AIX V5.1 Quick Beginnings* manual
- “Chapter 3. Installing the MQSeries for HP-UX Server” in the *MQSeries for HP-UX V5.1 Quick Beginnings* manual

- “Chapter 3. Installing the MQSeries for Sun Solaris Server” in the *MQSeries for Sun Solaris V5.1 Quick Beginnings* manual

Setting up MQSeries

After installation, MQSeries needs to be set up, and customized for your own use. This ensures that the appropriate UNIX system facilities are made available to MQSeries, and that your MQSeries system is correctly initialized and ready to work with your applications.

MQSeries uses configuration files to hold the product configuration information used for logging, communications protocols and installable components. After installing the product, you can edit these files to tailor the operation of the product to meet the requirements of your installation.

In addition, you need to do the following:

- Define queues
 - Consider your naming conventions for queues
- Define trigger processes
- Define remote links
 - Define associated transmission queues
 - Consider your naming conventions for remote queues
 - Consider your naming conventions for channels

Note: The characters within the names given to all MQSeries objects are case sensitive. Therefore, be very careful when defining the names of objects, to select the appropriate uppercase or lowercase characters.

You can find more information about the setting up and customizing processes for MQSeries on UNIX systems in the appropriate manual (see Table 15 on page 169).

Planning recovery services with MQSeries

MQSeries provides logging services to allow backup and recovery of the messaging system. Chapter 37, “Backup and recovery planning for MQSeries on UNIX systems” on page 175 introduces you to these facilities, and to the items that you need to consider in order to include MQSeries on UNIX systems in your backup and recovery plans.

You can find more information on the backup and recovery facilities provided by MQSeries in the appropriate manual (see Table 15 on page 169).

Planning data security on MQSeries

MQSeries uses the facilities of the MQSeries *object authority manager (OAM)* installable component to control access to the various different types of queue manager resource (queues, process definitions, channels, and queue managers).

You can find more general information on authorization installable components in Chapter 8, “Introduction to the MQSeries Framework” on page 55.

Chapter 38, “Security planning for MQSeries on UNIX systems” on page 179 introduces you to the security facilities provided by MQSeries and to some of the items you need to consider when planning for security.

You can find more information on the security facilities provided by MQSeries on UNIX systems in the appropriate manual (see Table 15 on page 169).

Administration with MQSeries

A summary of the administration facilities provided is given in Chapter 39, “Administration of MQSeries on UNIX systems” on page 183. Full details of these facilities can be found in the appropriate manual (see Table 15 on page 169).

Support for R/3 with MQSeries

The following products:

- MQSeries link for R/3 for AIX
- MQSeries link for R/3 for HP-UX
- MQSeries link for R/3 for Sun Solaris

provide an interface that enables you to integrate your R/3 application with applications running in other environments (including those on R/3 and R/2 environments).

The R/3 link works with the Application Link Enabling (ALE) layer of the R/3 system to transmit Intermediate Documents (IDocs) into and out of your R/3 system, using MQSeries messages and queues to carry the information. It extends the scope of your business by allowing you to link your R/3 applications to any other application that you can access through MQSeries, even when those applications require different data formats.

For more information, see the *MQSeries link for R/3 User's Guide*.

Migration from MQSeries Version 1

To use MQSeries application programs that were written for version 1 of MQSeries with version 2 of MQSeries, you need to do the following:

1. Redefine all message queues.
2. Redefine all message channels.
3. Recompile the application programs, using the MQSeries version 2 header files.

This might be a suitable time to consider whether you need to re-design any parts of your application, to take advantage of the additional function provided by version 2 of MQSeries.

One difference between version 2 of MQSeries on UNIX systems and the earlier products is that version 2 does its own queue storage management. It is not necessary to run a utility program to recover the space that was occupied by messages that have been removed from queues by **MQGET** calls; this is done automatically by MQSeries.

Migration from MQSeries Version 2

When you have migrated from MQSeries Version 2 to MQSeries Version 5 you will **not** be able to revert to Version 2. You should back up your system before installing the new version. This will enable you to back off the upgrade if necessary. If you do this however, you will not be able to recover the work performed by MQSeries Version 5.

With MQSeries Version 5, the system default objects are created automatically when you use the `crtmqm` command to create a queue manager. The sample MQSC definition file, `AMQSCOMA.TST`, is no longer provided. If you have used `AMQSCOMA.TST` to customize your settings for MQSeries Version 2, and you want to use the same settings with Version 5, save your version of the file before you install MQSeries Version 5. You can then use this file to create the Version 2 default objects. Alternatively, you can generate a new MQSC definition file if required.

A list of the system default objects for MQSeries Version 5 is provided in “System default objects” in the *MQSeries System Administration* manual.

Euro symbol support

Support for the new euro currency symbol has been added to MQSeries for AIX, HP-UX, and Sun Solaris. If you need to modify your applications to use this symbol, ensure that they use one of the coded character sets that include it. These are described in Appendix F, “Code page conversion tables” in the *MQSeries Application Programming Reference* manual. If you need to change the coded character set used by your queue manager, use the `CCSID` attribute of the `ALTER QMGR` command (or the equivalent `PCF` command).

Chapter 37. Backup and recovery planning for MQSeries on UNIX systems

This chapter describes the background concepts of recovery and restart. It contains the following sections:

- “Logging with MQSeries”
- “Resource management with MQSeries” on page 177
- “Recovering from problems with MQSeries” on page 178
- “High availability with MQSeries” on page 178

More details of the logging and recovery facilities of MQSeries on UNIX systems are given in the appropriate manual (see Table 15 on page 169).

Logging with MQSeries

The basic premise of a messaging system is that messages entered into the system are assured of delivery to the destination. One of the ways of ensuring that messages are not lost is to maintain a record of the activities of the queue manager that handles the receipt, transmission, and delivery of messages.

MQSeries on UNIX systems does this by recording all the significant changes to the data controlled or managed by the queue manager in a log. This process is called logging. The data changes that are logged include the puts and gets of persistent messages to and from queues, changes to queue attributes, and channel activity.

The purpose of logging is to create and maintain a log that:

- Keeps records of queue manager changes
- Keeps records of queue updates for use by the restart process
- Is a source for restoration of data should there be a hardware or software failure

Each MQSeries log consists of a log control file, together with one or more log files for the storage of data.

The log control file is, as its name implies, used to control and monitor the use of the log files. It contains information relating to the size, location, next available file, and other data related particularly to the log files themselves. All the log files within one log are the same size; there is a default value for this size, but you can override this value when you set up the log.

On some UNIX platforms, MQSeries provides a log dump facility (DMPMQLOG). This enables you to format and display the contents of the log when doing problem determination.

Types of logging with MQSeries

MQSeries on UNIX systems has two approaches to maintaining records of queue manager activities:

- Circular logging
- Linear logging

Each type of logging stores the recorded data in a set of files. The differences between the two types of logging are the contents, and the way that the files are linked together.

With circular logging, the set of log files are effectively linked together so as to form a ring. When data is collected, it is written sequentially into the files, in such a way as to reuse the log files in the ring. You can use circular logging for:

- Crash recovery - that is, after a system failure of some kind has stopped the queue manager unexpectedly
- Restart recovery - after a planned closedown of the system

With linear logging, the log is maintained as a continuous sequence of files. When data is collected, it is written sequentially into the log files; the space in the files is not reused, so that you can always retrieve any record from the time that the queue manager was created.

Because disk space is finite, you might have to plan for some form of archiving. Also, if you are handling a high volume of persistent messages, all your log files will eventually be filled. This will result in operator messages being written to an error log file; some action will need to be taken by the system administrator to make more log space available, or to reuse the existing space. You can use linear logging for:

- Crash recovery
- Restart recovery
- Media recovery - to recreate lost or damaged data after a media failure by replaying the contents of the log

Selecting a logging method with MQSeries

You must base your selection of log type on your requirements for recovery.

Both types of logging can cope with unexpected power outages in the absence of hardware failure. If you accept that only crash or restart recovery is required, circular logging might be adequate. If media recovery is important to you, select linear logging.

With each type of logging, you need to decide on the number of files to use in the log, and their size. The total amount of space needed depends on the amount of data to be recorded, which depends on various parameters, including:

- The size of messages
- The number of puts and gets from queues
- The number of messages being transmitted by the message channel agents

Resource management with MQSeries

MQSeries on UNIX systems supports the coordination of transactions by an external transaction manager that uses the X/Open XA interface. On some UNIX platforms, MQSeries can also act as a syncpoint coordinator, coordinating updates made by external resource managers.

MQSeries as a resource manager

In an XA configuration, the MQSeries queue manager acts as an XA resource manager, managing message queues. The XA transaction manager coordinates the operations of the queue manager, and any other XA-compliant resource managers, to synchronize the commit or backout of transactions. This ensures that updates to MQSeries message queues are coordinated with the updates to all the other types of resource being managed.

With MQSeries on UNIX systems, the XA transaction manager can be as follows:

CICS/TXSeries AIX, HP-UX, SINIX, and Sun Solaris

Encina HP-UX and SINIX

Tuxedo AIX, AT&T GIS UNIX², HP-UX, SINIX and DC/OSx, and Sun Solaris

The MQSeries resources are committed or backed out as directed by CICS, ENCINA, or TUXEDO. This support is available only on the MQSeries on UNIX systems server, and is not available to client applications.

MQSeries as a transaction manager

On some UNIX platforms, MQSeries can act as a transaction manager and coordinate updates made by external resource managers within MQSeries units of work. These external resource managers must comply to the X/Open XA interface.

MQSeries for AIX, MQSeries for HP-UX, and MQSeries for Sun Solaris can act as transaction managers for the following XA-compliant database managers:

- DB2
- Oracle
- Sybase (AIX and Sun Solaris only)

² This platform has become NCR UNIX SVR4 MP-RAS, R3.0

Recovering from problems with MQSeries

MQSeries can recover from communications failures and power loss incidents. In addition, it is sometimes possible to recover from other types of problem with the MQSeries data, such as inadvertent deletion of a file.

In the case of a communications failure, messages remain on the queues until they are removed by a receiving application. If the message is being transmitted, it remains on the transmission queue until it can be successfully transmitted. To recover from a communications failure, it is normally sufficient simply to restart the channels using the link that failed.

On a restart after your system has lost power, the queue manager restores all the persistent messages that were on the queues to the state that existed just before the power failure, so that no persistent messages are lost; nonpersistent messages are discarded.

There are ways in which an MQSeries object can become unusable, for example due to inadvertent damage. In such situations, you will have to take steps to recover either your complete system or some part of it. The action required depends on when the damage is detected, whether the log method selected supports media recovery, and which object or objects are damaged.

High availability with MQSeries

For those situations where high availability is a requirement, you might wish to consider using MQSeries for AIX with the AIX High Availability Cluster Multi-Processing/6000 (HACMP/6000™) product.

HACMP/6000 offers an efficient way to recover from failures at the AIX server that is running your application programs. The product allows for servers to be configured to provide, for example, automatic transfer to a standby processor if the primary one fails.

Also on AIX, you can use *disk mirroring* to improve the availability of your application data on disk.

Chapter 38. Security planning for MQSeries on UNIX systems

This chapter describes the access control security features in MQSeries on UNIX systems. It contains these sections:

- “Controlling access to resources with MQSeries”
- “Resources you can protect with MQSeries” on page 180
- “Using the security commands with MQSeries” on page 180
- “Security exits with MQSeries” on page 181

Full details of MQSeries on UNIX systems security handling are given in Chapter 10, “Protecting MQSeries objects” in the *MQSeries System Administration* manual.

Controlling access to resources with MQSeries

With MQSeries on UNIX systems, access to queue manager resources is controlled through the *object authority manager (OAM)*, which is the default authorization installable component. Because the OAM is an installable component, you can implement your own security controls in place of, or in addition to, those supplied by the OAM. For more information on installable services and installable components, see Chapter 8, “Introduction to the MQSeries Framework” on page 55.

Users can access queue manager objects (queues, process definitions, channels, namelists, and queue managers) only if they have the required authority. The OAM manages a user’s authorization to manipulate MQSeries objects, and provides a command interface through which you can grant or revoke access authority to an object for a specific group of users.

Managing access through user groups with MQSeries

In discussing security in a UNIX environment, we use the term *principal* rather than user ID. The reason for this is that authorities granted to a user ID can also be granted to other entities, for example, an application program that issues MQI calls, or an administration program that issues PCF commands. In these cases, the principal associated with a program is not necessarily the user ID that was used when the program was started.

Managing access permissions to MQSeries resources is based on *user groups*, that is, groups of principals. The OAM does not maintain authorizations at the level of individual principals. The mapping of principals to group names is carried out within the OAM, and operations are carried out at the group level.

The authorizations that a principal has are the union of the authorizations of all the groups of which it is a member, that is, its *group set*. Whenever a principal requests access to a resource, the OAM computes this union, and then checks the authorization against it.

Resources you can protect with MQSeries

Through MQSeries on UNIX systems you can control:

- **Access to queue manager objects through the MQI**

When an application program attempts to access an object, the OAM checks to see if the principal making the request has the authorization (through its user group) for the operation requested. In this way, the queues, and the messages on queues, can be protected from unauthorized access.

- **Permission to use MQSeries commands**

Only members of authorized user groups can execute queue manager administration commands.

When a member of a user group attempts to execute a command, the OAM checks to see if the principal making the request has the authorization (through its user group) to use the command. These access control checks are performed irrespective of whether the commands are issued through the **runmqsc** (run MQSC commands) command, or through an application that uses PCFs.

Different groups of users can be granted different kinds of access authority to the same object. For example, one group might be allowed to read (**MQGET**) messages from a queue, but not to write (**MQPUT**) messages to that queue. Other groups might be given authority to put messages to and get messages from the same queue. Similarly, some groups might have get and put authority but not be allowed to create or delete queues.

Using groups for authorizations with MQSeries

Using groups for authorization, rather than individual principals, reduces the amount of administration required. Normally, a particular kind of access is required by more than one principal. For example, you might define a group consisting of end users who want to run a particular application. New users can be given access simply by adding their user ID to the appropriate group.

Try to keep the number of groups as small as possible. Dividing principals into one group for application users, and one for administrators, is a good place to start.

Using the security commands with MQSeries

The OAM provides two commands that you can use to manage the authorizations of users. These are:

- **setmqaut** - set or reset authority
- **dspmqaut** - view authority

When you start a queue manager, it uses a group ID of **mqm**, and a user ID of **mqm**. These must be defined before you can start a queue manager. After this, any principal belonging to the group **mqm** can issue **setmqaut** commands to change authorizations to resources.

Details of these commands can be found in Chapter 17, "MQSeries control commands" in the *MQSeries System Administration* manual.

Security exits with MQSeries

The message channels that are used for distributed queuing, and the MQI channels that are used between clients and servers, both have security exit facilities that can invoke programs that you have supplied.

For more information on these security exit programs, see Chapter 35, “Channel-exit programs” in the *MQSeries Intercommunication* manual.

Chapter 39. Administration of MQSeries on UNIX systems

This chapter is a summary of the administration facilities provided by MQSeries on UNIX systems. It has the following sections:

- “Managing objects with MQSeries”
- “Remote administration with MQSeries” on page 184

Details of the commands, command interfaces, and utilities that are provided by MQSeries on UNIX systems are given in the appropriate manual (see Table 15 on page 169).

You need to arrange for users who need to be able to use these administration facilities to have the necessary authorizations, using the procedures given in the appropriate manual (see Table 15 on page 169).

Managing objects with MQSeries

It is the administrator's job to monitor MQSeries on UNIX systems and make any changes that might be necessary. To do this, the administrator needs to know where each MQSeries object resides, what its characteristics are, and who has access to it.

The administrator can manage and monitor the resources using MQSeries commands (MQSC), or, if there are sets of commands that are issued regularly, by writing an application program that places them on the command queue.

MQSeries can use the security features provided by the OAM, or by a security component that you have installed, to ensure that the user is authorized to issue particular commands for particular resources.

Commands on MQSeries

MQSeries supports the following administration commands and facilities:

- You can enter control commands on the command line.
- You can use the **runmqsc** control command to cause MQSC commands from standard input to be executed.
- Any local or remote MQSeries application program can generate PCF commands in messages and put them to the command queue `SYSTEM.ADMIN.COMMAND.QUEUE`, to be processed by the command server.

More information on how to use all these facilities is given in the appropriate manual (see Table 15 on page 169).

Changes made to the resource definitions of a queue manager using the commands (directly or indirectly) are preserved across restarts of MQSeries.

Managing communications with MQSeries

Part of the administrator's role is to ensure that the required communications links are activated, and to monitor the status of these links as required by your enterprise. You can find information describing these tasks in Part 3, "DQM in MQSeries for OS/2 Warp, Windows NT, Digital OpenVMS, Tandem NSK, and UNIX systems" in the *MQSeries Intercommunication* manual.

Remote administration with MQSeries

There are two aspects to the MQSeries remote administration facilities:

- The local MQSeries system can be used to manage remote systems.
- Other remote products can be used to manage the local MQSeries system.

Managing remote systems from MQSeries

Facilities are provided by MQSeries to allow an administrator to manage the following remote systems:

- MQSeries for AS/400
- MQSeries for Digital OpenVMS
- MQSeries for OS/390
- MQSeries for OS/2 Warp
- MQSeries for Tandem NSK
- MQSeries on UNIX systems
- MQSeries for Windows NT

Because of the differences in the MQSeries products, it is not always possible to manage remotely the same set of MQSeries objects or attributes that you can manage locally.

If you want to manage any other MQSeries product, you can write an application program to send the appropriate commands to the command queue for that product. However, some MQSeries products do not have a command queue, so they cannot accept commands from local or remote application programs.

Managing MQSeries from remote systems

The local MQSeries system can be managed from a remote MQSeries system, by an administrator using the facilities provided by the following products:

- MQSeries for AS/400
- MQSeries for Digital OpenVMS
- MQSeries for OS/390
- MQSeries for OS/2 Warp
- MQSeries for Tandem NSK
- MQSeries on UNIX systems
- MQSeries for Windows NT

Note: You can manage MQSeries on UNIX systems from MQSeries for OS/390 by writing an application program to send the appropriate PCF commands to the command queue.

Chapter 40. Storage planning for MQSeries on UNIX systems

This chapter tells you how to plan the type and amount of storage you require when you include MQSeries on UNIX systems in your network. It has the following sections:

- “RAM considerations for MQSeries”
- “Disk space considerations for MQSeries”
- “Capacity planning and performance figures for MQSeries” on page 186

RAM considerations for MQSeries

The processor memory (RAM) is used by MQSeries on UNIX systems in the execution of the product modules, and as a paging area for the messages that are being processed. Parts of the paging area are written to, and read from, disk as necessary.

The minimum amount of RAM required to run the MQSeries on UNIX systems server is 24 MB; if more RAM is available, the performance of the message processing improves.

The amount of RAM required on each client system for an MQSeries client is small compared to that required for the operating system on each of the platforms.

Disk space considerations for MQSeries

Disk space is used by MQSeries on UNIX systems for the following:

- Product modules - client and server executable modules, the toolkit, and the online documentation
- Paging space - server only
- Message queues - server only
- Logs - server only

Product modules for MQSeries

The disk space that you require for the product modules depends on the options that you decide to install: the options are described in the appropriate manual (see Table 15 on page 169).

Space might be required for client and server executable program modules and the toolkit. If all options are selected, 20 MB is required. You will need approximately 15 MB more than this if you install the online documentation.

The product modules can be stored on a LAN server, as an alternative to them being stored on a disk attached to the client or server. MQSeries loads the modules from the LAN server when required.

Message queues for MQSeries

In order to estimate the total amount of storage that you will need for queues, you need to know:

- The number of queues that you have.
- The maximum number of messages there will be on each of the queues at any one time.
- The average size of message on each of the queues. The amount of storage required for one message varies. It is based on the size of the message data plus the size of the message header (456 bytes), rounded up the nearest 512-byte block. If you are using distribution lists, or grouped or segmented messages, the size of the header will increase for the transmission queue.

Given these values, you can calculate the total amount of space required for queues. However, this value is likely to be an approximate value only, and it is advisable to add a contingency value, to avoid the situation where there is no space left for messages on the queues when your application is running.

The maximum size of a single queue on MQSeries for AIX, HP-UX, and Sun Solaris is 2 GB; on other UNIX platforms it is 320 MB.

Log files for MQSeries

Significant events and data changes can be logged in circular or sequential logs. In particular, the logs are used for recording persistent messages.

All the log files in a log are of the same size. By default, this size is 4 MB, but this value can be changed by the system administrator when the log is defined.

For a circular log, the system administrator needs to specify how many files should be included in the log. For a sequential log, the number of files will increase over time, until the system administrator archives some of the files, and disposes of them. You need to plan for the permanent storage (diskettes, tape, or other media supported in your enterprise) that is to be used for these archived files.

Capacity planning and performance figures for MQSeries

Information about MQSeries performance and capacity planning is available on the Internet at:

<http://www.software.ibm.com/mqseries/txppacs/txpm1.html>

For AT&T GIS UNIX and SINIX and DC/OSx, use the information about MQSeries for AIX as a starting point.

Part 8. Planning for MQSeries for VSE/ESA

Chapter 41. Introduction to MQSeries on VSE/ESA	189
Planning for MQSeries	189
Preparing your applications for use with MQSeries	189
Planning to use MQSeries in a network	189
Installing MQSeries	190
Setting up MQSeries	190
Backup and recovery planning for MQSeries for VSE/ESA	190
Security planning for MQSeries for VSE/ESA	191
Administration of MQSeries for VSE/ESA	191
Migration from MQSeries Version 1.4	191

Chapter 41. Introduction to MQSeries on VSE/ESA

MQSeries for VSE/ESA runs on any machine that is capable of running the VSE/ESA operating system. It runs as a CICS task, so various features of the product are controlled by CICS itself.

MQSeries provides the MQI programming interface for use by application programs that are running on VSE/ESA.

For information on the hardware and software environments, see “MQSeries for VSE/ESA” on page 254.

Planning for MQSeries

This chapter helps you to plan for the introduction of MQSeries for VSE/ESA into your enterprise, and introduces the items that you need to consider when doing this planning.

There are several stages in planning for the use of MQSeries for VSE/ESA that you must go through. They are:

1. Preparing your applications for the use of MQSeries for VSE/ESA
2. Planning to include MQSeries for VSE/ESA in a network
3. Preparing to install MQSeries for VSE/ESA
4. Planning to set up MQSeries for VSE/ESA

You must also plan for the operation and administration of MQSeries for VSE/ESA in your enterprise, and consider the implementation of an appropriate set of security facilities. Brief outlines of these operations are included in this chapter.

Preparing your applications for use with MQSeries

MQSeries for VSE/ESA brings the Message Queue Interface (MQI) to your applications. This interface allows you to modify existing applications and to write new applications. The MQI removes much of the need to understand the network and communication systems that you use. Thus you can expect to generate applications more speedily than before. However, you must prepare to take advantage of the MQI by planning its use in your applications and by understanding the ways in which it assists you.

You can find more information on how to use the MQI in your applications by referring to the *MQSeries Application Programming Guide*.

Planning to use MQSeries in a network

MQSeries for VSE/ESA uses the distributed queue management (DQM) facility to exchange messages between MQSeries platforms, using either the SNA LU 6.2 or TCP transmission protocols.

You must consider how you will attach MQSeries for VSE/ESA to a network, and how you will define the message channels that will be used to exchange messages. “MQSeries interoperability summary” on page 226 shows the links that are possible to other MQSeries products, and the transmission protocols that can be used.

For further information about distributed queue management, refer to the *MQSeries Intercommunication* manual.

Installing MQSeries

MQSeries for VSE/ESA is installed using standard VSE/ESA installation techniques. For information about installing MQSeries, see the *MQSeries for VSE/ESA System Management Guide*.

To prepare for installation, you need to plan how much disk space will be required in your VSE/ESA system to accommodate MQSeries. The disk space requirements for MQSeries for VSE/ESA are:

- 3380** 3 cylinders
- 3390** 2 cylinders
- FBA** 4500 blocks

Setting up MQSeries

After installation, MQSeries for VSE/ESA needs to be set up, and customized for your own use. This ensures that the appropriate VSE/ESA facilities are made available to MQSeries, and that your MQSeries system is correctly initialized and ready to work with your applications.

You need to do the following:

- Allocate and initialize the required MQSeries files
 - Create the setup file
 - Create the MQSeries configuration file
 - Create cluster definitions for MQSeries queues
- Prepare CICS for MQSeries
 - Define CICS resources into the CICS CSD
 - Define entry definitions for the CICS Destination Control Table
 - Define entry definitions for the CICS File Control Table
- Define remote links
 - Define associated transmission queues
 - Consider your naming conventions for remote queues
 - Consider your naming conventions for channels

You can find more information on the setting up and customizing processes for MQSeries for VSE/ESA in the *MQSeries for VSE/ESA System Management Guide*.

Backup and recovery planning for MQSeries for VSE/ESA

MQSeries uses its own recovery and restart logic in conjunction with CICS file management. You must define all the MQSeries VSAM clusters in the DFHFCT with the LOG parameter set to YES. In addition, you must ensure that the CICS logging facility is activated with JCT=xx or YES in your DFHSIT.

If you do not do this, you might lose messages, or MQSeries might not be able to use message sequence numbers correctly.

You can find more information on the recovery facilities provided by MQSeries for VSE/ESA in the *MQSeries for VSE/ESA System Management Guide*.

Security planning for MQSeries for VSE/ESA

MQSeries for VSE/ESA uses CICS to provide its security features.

Administration of MQSeries for VSE/ESA

There are two ways of administering an MQSeries for VSE/ESA system:

- You can use the CICS transaction MQMT.
MQMT allows you to configure, operate, and monitor an MQSeries for VSE/ESA system. MQMT also supports the browsing of message queues.
- You can use the MQSeries Command Line interface (MQCL)
MQCL supports the management of queues and channels.

Full details of these facilities can be found in the *MQSeries for VSE/ESA System Management Guide*.

Migration from MQSeries Version 1.4

To use MQSeries application programs that were written for MQSeries Version 1.4 with MQSeries for VSE/ESA, you need to do the following:

1. Redefine all message queues.
2. Redefine all message channels.
3. Recompile the application programs, using the MQSeries Version 2 header files.

This might be a suitable time to consider whether you need to re-design any parts of your application, to take advantage of the additional function provided by MQSeries for VSE/ESA.

One difference between MQSeries for VSE/ESA Version 2.1 or later, and the earlier products is that MQSeries for VSE/ESA does its own queue storage management. It is not necessary to run a utility program to recover the space that was occupied by messages that have been removed from queues by MQGET calls; this is done automatically by MQSeries.

Part 9. Planning for MQSeries on Windows NT

Chapter 42. Introduction to MQSeries for Windows NT	195
Planning for MQSeries	195
Preparing your applications for the use of MQSeries	196
Planning to use MQSeries in a network	196
Installing MQSeries	197
Setting up MQSeries	197
Planning recovery services for MQSeries	197
Planning data security for MQSeries	198
Administration of MQSeries	198
Support for R/3 with MQSeries	198
Migration from previous versions of MQSeries	198
Euro symbol support	199
 Chapter 43. Backup and recovery planning for MQSeries for Windows NT	 201
Logging with MQSeries	201
Types of logging with MQSeries	202
Selecting a logging method with MQSeries	202
Resource management with MQSeries	203
MQSeries as a resource manager	203
MQSeries as a transaction manager	203
Recovering from problems with MQSeries	204
 Chapter 44. Security planning for MQSeries for Windows NT	 205
User ID support with MQSeries	205
Security exits with MQSeries	206
MQAdmin user ID	206
 Chapter 45. Administration of MQSeries for Windows NT	 207
Managing objects with MQSeries	207
Microsoft Management Console snap-in applications	207
Web administration	208
Active Directory Service Interfaces	208
Commands with MQSeries	208
Managing communications with MQSeries	208
Remote administration with MQSeries	209
Managing remote systems from MQSeries	209
Managing MQSeries from remote systems	209
 Chapter 46. Storage planning for MQSeries for Windows NT	 211
RAM considerations for MQSeries	211
Disk space considerations for MQSeries	211
Product modules for MQSeries	211
Message queues for MQSeries	212
Log files for MQSeries	212
Capacity planning and performance figures for MQSeries	212

Chapter 42. Introduction to MQSeries for Windows NT

Several MQSeries products run on Microsoft Windows NT. These products are:

- MQSeries for Windows NT Version 5.1, which runs on Windows NT Version 4.0.
- MQSeries for Windows Version 2.1, which runs on Windows NT Version 4.0 (and Windows 95 and Windows 98). This 'lightweight' messaging and queuing product is described in Chapter 47, "Introduction to MQSeries for Windows" on page 215.
- MQSeries link for R/3 Version 1.2 for Windows NT, which runs on Windows NT Version 3.5.1 and Version 4.0; see "Support for R/3 with MQSeries" on page 198.

The following chapters provide information about MQSeries for Windows NT Version 5.1.

The MQSeries for Windows NT products are in two parts, the *server* and the *clients*. The server runs on a machine that is capable of running Windows NT; the clients provided with the product are for AIX, DOS, HP-UX, OS/2 Warp, Sun Solaris, Windows NT, Windows 3.1, Windows 95, and Windows 98.

MQSeries provides the MQI programming interface for use by application programs that are running on the server or the client processor. More detail on clients and servers is given in Chapter 7, "Introduction to MQSeries clients and servers" on page 49.

MQSeries for Windows NT Version 5.1 automatically installs the system upgrades so that you can use the Microsoft Management Console interface and Active Directory Service Interfaces provided in MQSeries for Windows NT Version 5.1. If you prefer, you can still use the MQSeries command-line interface to Windows NT.

The remaining sections of this chapter give basic information about:

- "Planning for MQSeries"
- "Support for R/3 with MQSeries" on page 198
- "Migration from previous versions of MQSeries" on page 198

For more information on the hardware and software environments needed by MQSeries, see "MQSeries for Windows NT" on page 259.

Planning for MQSeries

This chapter helps you to plan for the introduction of MQSeries into your enterprise, and introduces the items that you need to consider when doing this planning.

There are several stages in planning for the use of MQSeries that you must go through. They are:

1. Preparing your applications for the use of MQSeries
2. Planning to include MQSeries in a network
3. Preparing to install MQSeries
4. Planning to set up MQSeries

A prime requirement for a message delivery system is that it must be reliable. Many functions are built into MQSeries to ensure that messages are not lost despite system failures, and are not delivered more than once. MQSeries uses logging and other facilities to support these functions.

You must also plan for the operation and administration of MQSeries in your enterprise and consider the implementation of an appropriate set of security facilities. Brief outlines of these planning operations are included in this chapter.

Preparing your applications for the use of MQSeries

MQSeries brings the Message Queue Interface (MQI) to your applications. This interface allows you to modify existing applications and to write new applications. The MQI removes much of the need to understand the network and communication systems that you use. Thus you can expect to generate applications more speedily than before. However, you must plan to take advantage of the MQI by planning its use in your applications and by understanding the ways in which it assists you. You can find information on how to use the MQI in your applications in the *MQSeries Application Programming Guide*.

MQSeries applications can exploit Lightweight Directory Access Protocol (LDAP) directories. This is described in Chapter 30, "Using lightweight directory access protocol services with MQSeries for Windows NT" in the *MQSeries Application Programming Guide*.

Interfacing with CICS with MQSeries

With MQSeries you can create application programs for the CICS for Windows NT transaction environment. These applications can use the MQI to communicate with CICS or non-CICS programs in any of the environments supported by the MQSeries products.

Planning to use MQSeries in a network

MQSeries uses the distributed queuing facility to exchange messages between MQSeries platforms, using the TCP, SNA LU 6.2, SPX, or NetBIOS transmission protocols.

You must consider how you will attach MQSeries to a network, and how you will define the channels that will be used to exchange messages. You can simplify your definitions for distributed queuing by using MQSeries clusters.

According to the way that you have set your systems up, security checks can be performed at various times. You can provide your own security services, using the exit facilities provided by MQSeries. MQSeries also provides exits relating to DCE security.

"MQSeries interoperability summary" on page 226 shows the links that are possible to other MQSeries products, and the transmission protocols that can be used.

For further information about distributed queuing, refer to the *MQSeries Intercommunication* and the *MQSeries Queue Manager Clusters* manuals.

Installing MQSeries

Information on installing MQSeries for Windows NT is given in Chapter 4, “Installing MQSeries for Windows NT” in the *MQSeries for Windows NT V5.1 Quick Beginnings* manual.

When you have installed MQSeries, you can run the supplied PostCard application to check that the product has installed correctly.

Setting up MQSeries

After installation, MQSeries needs to be set up, and customized for your own use. This ensures that the appropriate operating system facilities are made available to MQSeries, and that your MQSeries system is correctly initialized and ready to work with your applications.

MQSeries for Windows NT uses the registry to hold the product configuration information used for logging, communications protocols, and installable components.

You then use the MQSeries Explorer user interface to define the queues, queue managers, and other objects that will be needed in your MQSeries network.

Notes:

1. The characters within the names given to all MQSeries objects are case sensitive. Be very careful when defining the names of objects to select the appropriate uppercase or lowercase characters.
2. You should consider your naming conventions for:
 - Queues
 - Remote queues
 - Channels

You can find more information on the setting up and customizing processes for MQSeries in Chapter 45, “Administration of MQSeries for Windows NT” on page 207.

Planning recovery services for MQSeries

MQSeries provides logging services to allow backup and recovery of the messaging system. Chapter 43, “Backup and recovery planning for MQSeries for Windows NT” on page 201 introduces you to these facilities, and to the items that you need to consider in order to include MQSeries in your backup and recovery plans.

You can find more information on the backup and recovery facilities provided by MQSeries in Chapter 15, “Recovery and restart” in the *MQSeries System Administration* manual.

Planning data security for MQSeries

MQSeries provides a number of security facilities for use by your applications. An introduction to these facilities is given in Chapter 44, “Security planning for MQSeries for Windows NT” on page 205.

You can find more information on the security facilities provided by MQSeries in Chapter 10, “Protecting MQSeries objects” in the *MQSeries System Administration* manual.

Administration of MQSeries

A summary of the administration facilities provided by MQSeries is given in Chapter 45, “Administration of MQSeries for Windows NT” on page 207.

Support for R/3 with MQSeries

The MQSeries link for R/3 for Windows NT product provides an interface that enables you to integrate your R/3 application with applications running in other environments (including those on R/3 and R/2 environments).

The R/3 link works with the Application Link Enabling (ALE) layer of the R/3 system to transmit Intermediate Documents (IDocs) into and out of your R/3 system, using MQSeries messages and queues to carry the information. It extends the scope of your business by allowing you to link your R/3 applications to any other application that you can access through MQSeries, even when those applications require different data formats.

For more information, see the *MQSeries link for R/3 User's Guide*.

Migration from previous versions of MQSeries

When you have migrated from MQSeries Version 2 to MQSeries Version 5 you will **not** be able to revert to Version 2. Similarly, if you have migrated from Version 5.0 to Version 5.1, you will not be able to revert to Version 5.0. You should back up your system before installing the new version. This will enable you to back off the upgrade if necessary. If you do this however, you will not be able to recover the work performed by the later version of MQSeries.

With MQSeries Version 5, the system default objects are created automatically when you use the **crtmqm** command to create a queue manager.

The sample MQSC definition file, AMQSCOMA.TST, is no longer provided. If you have used AMQSCOMA.TST to customize your settings for MQSeries Version 2, and you want to use the same settings with Version 5, save your version of the file before you install MQSeries Version 5. You can then use this file to create the Version 2 default objects. Alternatively, you can generate a new MQSC definition file if required.

A list of the system default objects for MQSeries Version 5 is provided in “System default objects” in the *MQSeries System Administration* manual.

With MQSeries Version 5.1, the installation process decides whether this is a new installation or an update from a previous level of MQSeries for Windows NT. If you

are moving from a earlier level, all the files you previously selected (for example, the toolkit) or created (for example, your queue managers) are maintained.

MQSeries for Windows NT Version 5.1 automatically migrates configuration information from your .INI files into the Windows NT registry. Configuration information is then updated when you define or change details through the user interface.

Euro symbol support

Support for the new euro currency symbol has been added to MQSeries. If you need to modify your applications to use this symbol, ensure that they use one of the coded character sets that include it. These are described in Appendix F, “Code page conversion tables” in the *MQSeries Application Programming Reference* manual. If you need to change the coded character set used by your queue manager, use the CCSID attribute of the ALTER QMGR command (or the equivalent PCF command).

Chapter 43. Backup and recovery planning for MQSeries for Windows NT

This chapter describes the background concepts of recovery and restart. It contains the following sections:

- “Logging with MQSeries”
- “Resource management with MQSeries” on page 203
- “Recovering from problems with MQSeries” on page 204

More details of the logging and recovery facilities are given in Chapter 15, “Recovery and restart” in the *MQSeries System Administration* manual.

Logging with MQSeries

The basic premise of a messaging system is that messages entered into the system are assured of delivery to the destination. One of the ways of ensuring that messages are not lost, is to maintain a record of the activities of the queue manager that handles the receipt, transmission, and delivery of messages.

MQSeries does this by recording all the significant changes to the data controlled or managed by the queue manager in a log. This process is called *logging*. The data changes that are logged include the puts and gets of persistent messages to and from queues, changes to queue attributes, and channel activities.

The purpose of logging is to create and maintain a log that:

- Keeps records of queue manager changes
- Keeps records of queue updates for use by the restart process
- Is a source for restoration of data should there be a hardware or software failure

Each MQSeries log consists of a log control file, together with one or more log files for the storage of data.

The log control file is, as its name implies, used to control and monitor the use of the log files. It contains information relating to the size, location, next available file, and other data related particularly to the log files themselves. All the log files within one log are the same size; there is a default value for this size, but you can override this value when you set up the log.

MQSeries provides a log dump facility (DMPMQLOG). This enables you to format and display the contents of the log when doing problem determination.

Types of logging with MQSeries

In MQSeries, there are two approaches to maintaining records of queue manager activities:

- Circular logging
- Linear logging

Each type of logging stores the recorded data in a set of files. The differences between the two types of logging are the contents, and the way that the files are linked together.

With circular logging, the set of log files are effectively linked together so as to form a ring. When data is collected, it is written sequentially into the files in such a way as to reuse the log files in the ring. You can use circular logging for:

- Crash recovery - that is, after a system failure of some kind has stopped the queue manager unexpectedly
- Restart recovery - after a planned close down of the system

With linear logging, the log is maintained as a continuous sequence of files. When data is collected, it is written sequentially into the log files; the space in the files is not reused, so that you can always retrieve any record from the time that the queue manager was created.

Because disk space is finite, you might have to plan for some form of archiving. Also, if you are handling a high volume of persistent messages, all your log files will eventually be filled. This will result in operator messages being written to an error log file, and some action will need to be taken by the system administrator to make more log space available, or to reuse the existing space. You can use linear logging for:

- Crash recovery
- Restart recovery
- Media recovery - to recreate lost or damaged data after a media failure by replaying the contents of the log

Selecting a logging method with MQSeries

You must base your selection of log type on your requirements for recovery.

Both types of logging can cope with unexpected power outages in the absence of hardware failure. If you accept that only crash or restart recovery is required, circular logging might be adequate. If media recovery is important to you, select linear logging.

With each type of logging, you will need to decide on the number of files to use in the log, and their size. The total amount of space needed will depend on the amount of data to be recorded, which depends on various parameters, including:

- The size of messages
- The number of gets and puts to queues
- The number of messages being transmitted by the message channel agents

Resource management with MQSeries

MQSeries supports the coordination of transactions by an external transaction manager that uses the X/Open XA interface. MQSeries can also act as a transaction manager, coordinating updates made by external resource managers.

MQSeries as a resource manager

MQSeries supports the coordination of transactions by an external transaction manager that uses the X/Open XA interface.

In an XA configuration, the MQSeries queue manager acts as an XA resource manager, managing message queues. The XA transaction manager coordinates the operations of the queue manager, and any other resource managers, to synchronize the commit or backout of transactions. This ensures that updates to MQSeries message queues are coordinated with the updates to all the other types of resource being managed.

TXSeries for Windows NT operates as an XA transaction manager, so the XA resource management capabilities of MQSeries for Windows NT can be used. MQSeries for Windows NT can also use BEA Tuxedo as a transaction manager.

This support is available only on the MQSeries server, and is not available to client applications. See the information on transactional support in Chapter 14, "Transactional support" in the *MQSeries System Administration* manual for more details.

MQSeries as a transaction manager

MQSeries can act as a transaction manager and coordinate updates made by external resource managers within MQSeries units of work. These external resource managers must comply to the X/Open XA interface. MQSeries can act as a transaction manager for DB2 or Sybase.

Recovering from problems with MQSeries

MQSeries will recover from both communications failures and power loss incidents. In addition, it is sometimes possible to recover from other types of problem with the MQSeries data, such as inadvertent deletion of a file.

In the case of a communications failure, messages simply remain on queues until they are removed from the queues by a receiving application. If the message is being transmitted, it remains on the transmission queue until it can be successfully transmitted. To recover from a communications failure, it will normally be sufficient simply to restart the channels using the link that failed.

On a restart after your system has lost power, the queue manager will restore all the persistent messages on the queues to the state that existed just before the power failure, so that no persistent messages are lost; nonpersistent messages are discarded.

There are ways in which an MQSeries object can become unusable, for example due to inadvertent damage. In such situations, you will have to take steps to recover either your complete system or some part of it. The action required depends on when the damage is detected, whether the log method selected supports media recovery, and which object or objects are damaged.

You can configure your queue manager to restart without user intervention when the system powers up. This can include the channel initiator, any listeners, the command server, and the trigger monitor.

Chapter 44. Security planning for MQSeries for Windows NT

In general, each MQSeries product provides security facilities by building on those provided by the platform for which the product was designed.

This chapter describes the following security facilities provided by MQSeries for Windows NT:

- “User ID support with MQSeries”
- “Security exits with MQSeries” on page 206
- “MQAdmin user ID” on page 206

User ID support with MQSeries

MQSeries for Windows NT handles the user ID of the logged-on user in two ways:

1. The user ID is stored in the message descriptor of messages when they are created.
2. The user ID is used when MQSeries performs authorization checks for access to MQSeries objects, such as queues.

The maximum length of user ID that is used in these ways by all MQSeries products is 12 characters.

On Windows NT, the user name can be longer than 12 characters. For example, the default user name for administration on Windows NT is *Administrator*.

MQSeries for Windows NT Version 5.1 supports user names that are longer than 12 characters, while at the same time maintaining compatibility with other products in the MQSeries family. The Windows NT security identifier (SID) is used to supplement the 12-character user ID. The SID contains information that identifies the full user account details on the Windows NT security account manager (SAM) database where the user is defined.

When a message is created on MQSeries for Windows NT, MQSeries stores the SID in the message descriptor. When MQSeries for Windows NT performs authorization checks, it uses the SID to query the full information from the SAM database.

Note: The SAM database in which the user is defined must be accessible for this query to succeed.

The Windows NT SID allows MQSeries to distinguish between two user names that are the same. For example, the user name *JohnSmith* can be defined on different Windows NT SAMs. A new option on the Windows NT authorization service controls whether the authority checks require both a user ID and a valid Windows NT SID to be available before granting access to MQSeries objects. For example, when this option is set, administration messages to the `SYSTEM.ADMIN.COMMAND.QUEUE` from other systems must supply a SID that is valid on the local system and that resolves to the user ID in the message context.

The changes in MQSeries for Windows NT Version 5.1 that allow the Windows NT SID to be used are as follows:

- The message queue interface (MQI):
 - Changes to the *AccountingToken* field in the Message Descriptor (MQMD)
 - A new version, MQOD_VERSION_3, of the Object Descriptor (MQOD) to provide the *AltSecurityIdentifier* field

See the *MQSeries Application Programming Guide* and the *MQSeries Application Programming Reference* manuals for more information.

- New fields in the Channel Definition (MQCD) structure to support longer user ID fields.

See the *MQSeries Intercommunication* manual for more information.

- The maximum length of the MCAUSER parameter in the DEFINE CHANNEL, ALTER CHANNEL, and DISPLAY CHANNEL MQSC commands is increased to 64 characters.

See the *MQSeries Command Reference* manual for more information.

- The maximum length of the *MCAUserIdentifier* parameter in the Create Channel, Change Channel, Copy Channel, and Inquire Channel PCF commands is increased to 64 characters.

See the *MQSeries Programmable System Management* manual for more information.

- The MQSeries Object Authority Manager (OAM), through its **setmqaut** and **dspmqaut** commands, allows a long user name and a domain qualifier.

See the *MQSeries System Administration* manual for more information.

Security exits with MQSeries

The message channels that are used for distributed queuing, and the MQI channels that are used between clients and servers, both have security exit facilities that can invoke programs you have supplied.

For more information on these security exit programs, see Chapter 35, “Channel-exit programs” in the *MQSeries Intercommunication* manual.

MQAdmin user ID

When MQSeries for Windows NT is installed, a user administrator account called MQAdmin is created for MQSeries on the local machine to run the MQSeries service. The password for this account is generated by MQSeries. If you want to change this password, you must change it in the following two places:

- The **User Manager** for the local machine
- The **Run as** property of the **IBM MQSeries Services** application in DCOMCNFG

This is described in “Security” in the *MQSeries System Administration* manual.

Chapter 45. Administration of MQSeries for Windows NT

This chapter is a summary of the administration facilities provided by MQSeries. It has the following sections:

- “Managing objects with MQSeries”
- “Remote administration with MQSeries” on page 209

Managing objects with MQSeries

It is the administrator's job to monitor MQSeries and make any changes that might be necessary. To do this, the administrator needs to know where each MQSeries object resides, what its characteristics are, and who has access to it.

The administrator can manage and monitor the resources by using:

- The MQSeries Explorer.
- The MQSeries Services snap-in.
- The MQSeries Web Administration application.
- The Active Directory Service Interfaces.
- The MQSeries control commands, MQSC commands, or (if there are sets of commands that are issued regularly) by writing an application program that places them on the command queue.

Microsoft Management Console snap-in applications

MQSeries for Windows NT provides two snap-in applications that run under the Microsoft management console (MMC). They provide a graphical user interface for administering the elements of your MQSeries network.

MQSeries Explorer

The MQSeries Explorer snap-in application allows you to define and control:

- Queue managers
- Clusters (networks of queue managers that can be on several MQSeries systems)
- Other objects (such as queues, channels, processes, client connections, and namelists)

The user interface provides extensive help information to guide you through the tasks involved.

MQSeries services snap-in

The MQSeries services snap-in application allows you to define and control services (for example, the MQSeries command server, channel initiators, listeners, and configuration information).

The user interface provides extensive help information to guide you through the tasks involved.

Web administration

MQSeries for Windows NT also provides a web-based application that allows you to administer your MQSeries network from a web browser running on Windows NT, Windows 95, or Windows 98. The application allows you to use MQSeries command (MQSC) facilities, either as individual commands or multiple commands in a script.

Its user interface provides extensive help information to guide you through the tasks involved.

Active Directory Service Interfaces

Support for the Microsoft Active Directory Service Interfaces (ADSI) is available through the IBM MQSeries namespace. ADSI support within MQSeries supports the modification of existing objects only, you cannot create new ones.

For more information about ADSI, see Chapter 6, "Using the Active Directory Service Interfaces (ADSI)" in the *MQSeries for Windows NT Using the Component Object Model Interface* manual.

Commands with MQSeries

MQSeries supports the following administration commands and facilities:

- MQSeries provides control commands that you can enter through the Windows NT command line.
- You can use the **runmqsc** control command to cause MQSC commands from standard input to be executed.
- Any local or remote MQSeries application program can generate PCF commands in messages, and put them to the command queue, SYSTEM.ADMIN.COMMAND.QUEUE, to be processed by the MQSeries command server.

More information on how to use all these facilities is given in Chapter 2, "An introduction to MQSeries administration" in the *MQSeries System Administration* manual.

Changes made to the resource definitions of a queue manager using the commands (directly or indirectly) are preserved across restarts of the MQSeries system.

Managing communications with MQSeries

Part of the administrator's role is to ensure that the required communications links are activated, and to monitor the status of these links as required by your enterprise. You can find information describing these tasks in Part 3, "DQM in MQSeries for OS/2 Warp, Windows NT, Digital OpenVMS, Tandem NSK, and UNIX systems" in the *MQSeries Intercommunication* manual.

Remote administration with MQSeries

There are two aspects to the MQSeries remote administration facilities:

- MQSeries for Windows NT can be used to manage remote systems.
- Other remote products can be used to manage a MQSeries for Windows NT system.

Managing remote systems from MQSeries

Facilities are provided by MQSeries to allow an administrator to manage the following remote systems:

- MQSeries for AS/400
- MQSeries for Digital OpenVMS
- MQSeries for OS/390
- MQSeries for OS/2 Warp
- MQSeries for Tandem NSK
- MQSeries on UNIX systems
- MQSeries for Windows NT

Because of the differences between the MQSeries products, it is not always possible to manage remotely the same set of MQSeries objects or attributes that you can manage locally.

If you want to manage any other MQSeries product, you can write an application program to send the appropriate commands to the command queue for that product. However, some MQSeries products do not have a command queue, so they cannot accept commands from local or remote application programs.

Managing MQSeries from remote systems

MQSeries for Windows NT can be managed from a remote MQSeries system, by an administrator using the facilities provided by the following products:

- MQSeries for AS/400
- MQSeries for Digital OpenVMS
- MQSeries for OS/390
- MQSeries for OS/2 Warp
- MQSeries for Tandem NSK
- MQSeries on UNIX systems
- MQSeries for Windows NT

Note: You can manage MQSeries for Windows NT from MQSeries for OS/390 by writing an application program to send the appropriate PCF commands to the command queue.

Chapter 46. Storage planning for MQSeries for Windows NT

This chapter tells you how to plan the type and amount of storage you require when you include MQSeries in your system. It has the following sections:

- “RAM considerations for MQSeries”
- “Disk space considerations for MQSeries”
- “Capacity planning and performance figures for MQSeries” on page 212

RAM considerations for MQSeries

The processor memory (RAM) is used by MQSeries in the execution of the product modules, and as a paging area for the messages that are being processed. Parts of the paging area are written to, and read from, disk as necessary.

The minimum amount of RAM required to run the MQSeries server on Windows NT is 24 MB; if more RAM is available, the performance of the message processing improves. Allow 0.5 MB for each MQSeries client connected.

The amount of RAM required on each client system for an MQSeries client is small compared to that required for the operating system on each of the platforms.

Disk space considerations for MQSeries

Disk space is used by MQSeries for the following:

- Product modules - client and server executable modules, the toolkit, and the online documentation
- Paging space - server only
- Message queues - server only
- Logs - server only

Product modules for MQSeries

The disk space that you require for the product modules depends on the options that you decide to install: the options are described in Chapter 3, “Planning to install MQSeries for Windows NT” in the *MQSeries for Windows NT V5.1 Quick Beginnings* manual.

Space might be required for client and server executable program modules, the toolkit, and the online documentation.

The product modules can be stored on a LAN server, as an alternative to them being stored on a disk attached to the MQSeries client or server. MQSeries loads the modules from the LAN server when required.

Message queues for MQSeries

In order to estimate the total amount of storage that you will need for queues, you need to know:

- The number of queues that you have.
- The maximum number of messages there will be on each of the queues at any one time.
- The average size of message on each of the queues. The amount of storage required for one message varies. It is based on the size of the message data plus the size of the message header (456 bytes), rounded up the nearest 512-byte block. If you are using distribution lists, or grouped or segmented messages, the size of the header increases for the transmission queue.

Given these values, you can calculate the total amount of space required for queues. However, this value is likely to be an approximate value only, and it is advisable to add a contingency value, to avoid the situation where there is no space left for messages on the queues when your application is running.

The maximum size of a single queue on MQSeries for Windows NT is 2 GB.

Log files for MQSeries

Significant events and data changes can be logged in circular or sequential logs. In particular, the logs are used for recording persistent messages.

All the log files in a log are of the same size. By default, this size is 4 MB, but this value can be changed by the system administrator when the log is defined.

For a circular log, the system administrator needs to specify how many files should be included in the log. For a sequential log, the number of files will increase over time, until the system administrator archives some of the files, and disposes of them. You need to plan for the permanent storage (diskettes, tape, or other media supported in your enterprise) that is to be used for these archived files.

Capacity planning and performance figures for MQSeries

Information about MQSeries performance and capacity planning is available on the Internet at:

<http://www.software.ibm.com/ts/mqseries/txppacs/txpm1.html>

Part 10. Planning for MQSeries for Windows

Chapter 47. Introduction to MQSeries for Windows	215
Where to use MQSeries for Windows	216
The features of MQSeries for Windows	218
Comparing queue managers, clients, and servers	219
How MQSeries for Windows differs from the other MQSeries products	219

Chapter 47. Introduction to MQSeries for Windows

MQSeries for Windows is a lightweight messaging and queuing product that provides MQSeries functions on workstations that run on the Microsoft Windows platform. It uses significantly fewer resources than other MQSeries products, so it is a good choice to use as a single-user queue manager running on a small or medium-sized personal computer.

- MQSeries for Windows Version 2.0 is a 16-bit product that runs on Microsoft Windows 3.1 and Windows 95.
- MQSeries for Windows Version 2.1 is a 32-bit product that runs on Windows 95, Windows 98, and Windows NT Version 4.0.

For information about these products, see:

- *MQSeries for Windows Version 2.0 User's Guide*
- *MQSeries for Windows Version 2.1 User's Guide*

Do not confuse MQSeries for Windows with MQSeries for Windows NT Version 5. This product is described in Chapter 42, "Introduction to MQSeries for Windows NT" on page 195.

MQSeries for Windows is particularly well suited to users of messaging applications who want to use a standard configuration. It uses definition files that automatically create and start the messaging components the users need, and it can automatically start components when the users start their workstations. These features reduce the need for users of applications to be aware of the messaging product and allow them to concentrate on the applications they want to use.

This chapter contains the following sections:

- "Where to use MQSeries for Windows" on page 216

This explains the intended use of MQSeries for Windows.

- "The features of MQSeries for Windows" on page 218

This introduces the features provided by MQSeries for Windows.

- "Comparing queue managers, clients, and servers" on page 219

This gives a comparison of supported features on MQSeries for Windows.

- "How MQSeries for Windows differs from the other MQSeries products" on page 219

This summarizes the differences between MQSeries for Windows and the other workstation products in the MQSeries family.

Where to use MQSeries for Windows

MQSeries for Windows is designed for use as a *leaf node* in a network of queue managers; that is, it is intended for use by a single user on a workstation that is connected to only one other computer in an MQSeries network of computers (see Figure 14 on page 217).

There are important differences between a leaf-node queue manager, an MQSeries client, and a server-node queue manager:

- A leaf-node queue manager is a lightweight product that connects to a network of one or more larger servers. It manages its own queues, so an application that runs on a leaf-node queue manager can continue to work, even if there is a failure in the messaging network or if the user decides to work in standalone (disconnected) mode (for example, away from their own office or in a branch office that does not currently have a connection to a server).

A leaf-node queue manager is **not** intended for use as an intermediate queue manager that passes messages from one queue manager to another or one that serves many users. For this reason it does not support MQSeries clients. It **is** intended for a single user working on their own workstation.

- An MQSeries client provides no queue manager functions and it has no queues. It is dependent on an MQSeries server (of the type that supports MQSeries clients). The server owns the queues that the client uses, so if the communication link between the client and the server is broken, the client cannot use those queues.
- A server-node queue manager is a product (such as MQSeries for Windows NT) that manages the queues and communication channels required to support the transfer of messages between queue managers. The computer on which the server-node queue manager runs is large enough to manage the volume of messages such a server might be required to process, and it might also support MQSeries clients. Such a queue manager is likely to be used by a network administrator.

MQSeries for Windows typically runs on workstations that are not powerful enough to act as a server. Like a server though, MQSeries for Windows manages its own queues and the channels to communicate with other queue managers. However, because it is intended to be a leaf node, MQSeries for Windows does not provide all the server functions available on other MQSeries queue managers; these include media recovery, two-phase commit, instrumentation events, and MQSeries client support. For a full list of the MQSeries features that MQSeries for Windows does not support, see “How MQSeries for Windows differs from the other MQSeries products” on page 219.

MQSeries for Windows is designed to run in the Windows environment, so it provides Windows programs that help to make the queue manager easier to use. These programs are not provided by other MQSeries products.




Figure 14. A network of server queue managers and three leaf-node queue managers. The leaf node queue managers run on Windows; they each connect to only one server. The server queue managers run on any other MQSeries platform; they can each have many connections.

The features of MQSeries for Windows

MQSeries for Windows provides existing MQSeries features, but on the Windows operating system:

- A small footprint queue manager that runs on Windows
- The MQSeries Message Queue Interface (MQI) for application development on Windows
- Application development support for the C and Visual Basic programming languages
- Communication between queue managers using TCP
- Standard MQSeries message types and formats
- *Persistent messages* (which survive restarts of the workstation) and nonpersistent messages
- Standard MQSC commands to create, alter, or delete MQSeries objects (but MQSeries for Windows does not support all the commands)
- Enablement for automatic installation
- Report generation, including confirm on arrival (COA), confirm on delivery (COD), and message expiry
- Remote administration using PCF commands and MQSeries events (Version 2.1 only)

In addition, MQSeries for Windows provides these features:

- To help users of applications to get started quickly and easily the first time they use the product, MQSeries for Windows uses definition files that automatically create and start the messaging components the users need.
- To help users of applications to get started when they start their workstations, MQSeries for Windows can automatically start its components.
- To help you to set up and work with your MQ components:
 - Version 2.0 of MQSeries for Windows provides utilities you can access from the MQSeries for Windows program group in the Windows Program Manager.
 - Version 2.1 of MQSeries for Windows provides an MQSeries Properties dialog box. You can open this from the Windows taskbar and Control Panel.

These facilities are supported by extensive online help.

- To make it easier to work with the message channels that you must use to send messages between queue managers, MQSeries for Windows provides channel groups. A channel group is a collection of channels that you start and stop at the same time.
- To make it easier to work with dial-up devices (such as modems) when you connect two queue managers:
 - Version 2.0 of MQSeries for Windows provides transport links which can help you to control the duration (and hence the cost) of such a connection.
 - Version 2.1 of MQSeries for Windows uses the dial-up networking connections provided by the operating system.

Comparing queue managers, clients, and servers

If you already use MQSeries clients, see Table 16 for a summary of the differences between an MQSeries for Windows queue manager, an MQSeries client, and an MQSeries server.

Table 16. Comparison of supported features on MQSeries for Windows

Feature	MQSeries for Windows	MQSeries client on Windows	MQSeries for OS/2 Warp
Independent operation	Yes	No	Yes
Queue manager	Yes	No	Yes
Queues	Yes	No	Yes
Message channels	Yes	No	Yes
Run MQSC commands	Utility (V2.0), interactive (V2.1), or command file	No	Command line or command file
Persistence of MQSeries objects	Yes	All objects are on the server	Yes
Logging and media recovery	No	All objects are on the server	Yes
Automatic installation	Yes	Yes	Yes
Automatic start up	Yes	No	No
Supports MQSeries clients	No	Not applicable	Yes

How MQSeries for Windows differs from the other MQSeries products

MQSeries for Windows is a leaf-node queue manager for the Microsoft Windows platform. It is designed to minimize system requirements so that workstations with relatively modest specifications can use commercial messaging. This section summarizes the differences between MQSeries for Windows and the other workstation products in the MQSeries family. The features are listed in alphabetic order.

Attributes of queues and queue managers

MQSeries for Windows does not support all the attributes of queues and queue managers (for example, it does not support those related to triggering). If you use an unsupported attribute in a command or an MQI call, MQSeries for Windows returns a value to show that the attribute is not supported.

Authority checking on the MQOPEN call

MQSeries for Windows does not support the SETMQAUT and DSPMQAUT commands.

Command Server

Version 2.0 of MQSeries for Windows does not support the MQSeries Command Server, so it does not support any MQSeries feature that

uses the command server (for example, PCF commands and remote administration).

Version 2.1 provides a command server.

Context passing

MQSeries for Windows does not copy context information from messages it receives from other queue managers. This is because MQSeries for Windows is intended to be a leaf node; it is not intended to be an intermediate node in a network of queue managers, where messages received from one queue manager are passed on to another.

Control commands

In other MQSeries products, you can issue control commands from the command line. MQSeries for Windows provides a user interface to enable you to perform the functions of some of these commands (for example, starting and stopping a queue manager). For a comparison with the MQSeries control commands, see the *MQSeries for Windows User's Guide*.

Data conversion

When an MQSeries for Windows queue manager receives data from a queue manager running on a different platform, it cannot convert the machine encoding, integer representation, or coded character set of the application data. Also, it cannot run data conversion exits. This means that any data conversion that is required must be performed by the other queue manager.

Dead-letter queues

MQSeries for Windows does not support dead-letter queues. A dead-letter queue is a queue to which a queue manager or application sends messages it cannot deliver to their correct destination. It is also known as an undelivered-message queue.

An MQSeries for Windows queue manager does not need a dead-letter queue because, being a leaf node, it is always on the edge of a network of queue managers. This means that it does not have to store messages for onward transmission to other queue managers.

Distributed Computing Environment (DCE) directories

MQSeries for Windows does not support DCE directories.

Distributed Computing Environment (DCE) security

MQSeries for Windows does not support exits relating to DCE security.

Events See *instrumentation events*.

Installable services

MQSeries for Windows does not support MQSeries installable services. These are additional functions provided in other MQSeries products as several independent components.

Instrumentation events

Instrumentation events are facilities you can use to monitor the operation of queue managers and channels in a network of MQSeries systems. Version 2.1 of MQSeries for Windows generates most of the MQSeries instrumentation events. Version 2.0 does not generate instrumentation events.

Media recovery and logging

MQSeries for Windows does not support the creation of a sequence of log records that contain an image of an object. Other MQSeries products allow you to create such records and re-create objects from this image.

Message Queue Interface (MQI)

MQSeries for Windows supports a subset of the MQI.

To understand those features of the MQI that MQSeries for Windows does not support, see the *MQSeries for Windows User's Guide*.

Message retry exit

MQSeries for Windows does not support a message retry exit.

An MQSeries for Windows queue manager does not need a message retry exit because, being a leaf node, it is always on the edge of a network of queue managers. This means that it does not have to store messages for onward transmission to other queue managers.

MQI channels

MQSeries for Windows does not support MQI channels. These are client connection and server connection channels. These are used with MQSeries clients only, so MQSeries for Windows does not support them.

MQSC commands

MQSeries for Windows supports a subset of the MQSC commands. To see which commands it supports, see the *MQSeries for Windows User's Guide*.

However, MQSeries for Windows provides facilities that allow you to type MQSC commands in a window (and test and reissue them) and run MQSC command files. This is described in the *MQSeries for Windows User's Guide*.

MQSeries client and server support

You cannot use an MQSeries for Windows queue manager as an MQSeries client, nor can you use it to support its own MQSeries clients.

Network support

MQSeries for Windows supports TCP only.

Object Authority Manager (OAM)

MQSeries for Windows does not provide a security manager. It does not support the SETMQAUT and DSPMQAUT commands.

Process definitions

Other MQSeries products use process definitions for setting up the automatic triggering of applications. MQSeries for Windows does not support triggering or process definitions.

Programmable Command Formats (PCFs)

Version 2.0 of MQSeries for Windows does not support PCFs.

Version 2.1 supports many of the PCF commands. To see which commands, see the *MQSeries for Windows User's Guide*.

Queue manager

MQSeries for Windows supports multiple queue manager definitions, but it allows only one queue manager to run at any time.

Queue manager quiescing

MQSeries for Windows does not support the quiescing of a queue manager. This is the ability to allow applications to finish processing before the queue manager is stopped, and to prevent any further applications starting.

Sample programs

MQSeries for Windows provides Windows versions of some of the MQSeries sample programs. The MQSeries for Windows samples are described in the *MQSeries for Windows User's Guide*.

Security manager

See *object authority manager*.

Signaling

Version 2.0 of MQSeries for Windows does not support signaling.

Version 2.1 supports signalling, so you can use the MQGMO_SET_SIGNAL option with the MQGET call on Windows applications.

Triggering

MQSeries for Windows does not support triggering, so it does not allow a queue manager to start an application automatically when predetermined conditions on a queue are satisfied. The following features of triggering are also not supported:

- Initiation queues
- Process definitions
- Trigger monitors

Two-phase commit

MQSeries for Windows does not support two-phase commit. This is a protocol for the coordination of changes to recoverable resources when more than one resource manager is used by a single transaction.

However, MQSeries for Windows does allow the queue manager to commit or back out units of work.

Part 11. The MQSeries family

Chapter 48. MQSeries product summaries	225
Lists of MQSeries products	225
MQSeries interoperability summary	226
MQSeries product functional comparison	228
 Chapter 49. MQSeries at a glance	 231
MQSeries for AIX	232
MQSeries for AS/400	235
MQSeries for AT&T GIS UNIX	236
MQSeries for Digital OpenVMS	237
MQSeries client for DOS	238
MQSeries for HP-UX	239
MQSeries for OS/2 Warp	241
MQSeries for OS/390	243
MQSeries for SINIX and DC/OSx	245
MQSeries for Sun Solaris	247
MQSeries for Tandem NSK	249
MQSeries for UnixWare	251
MQSeries client for VM/ESA	253
MQSeries for VSE/ESA	254
MQSeries for Windows Version 2.0	255
MQSeries for Windows Version 2.1	257
MQSeries for Windows NT	259
MQSeries client for Windows 3.1	262
MQSeries client for Windows 95 and Windows 98	263
MQSeries link for R/3	264

Chapter 48. MQSeries product summaries

This chapter gives summary information for all the products in the MQSeries family. It has the following sections:

- “Lists of MQSeries products”
- “MQSeries interoperability summary” on page 226
- “MQSeries product functional comparison” on page 228

Lists of MQSeries products

This book applies to the MQSeries products listed in the following tables. The products fall into two broad categories, Level 1 and Level 2, in respect of the function they support.

Some of the products were renamed in November 1994; for those products, the name by which the product used to be known is given, as well as the current product name.

Level 1 products

<i>Table 17. MQSeries products, Level 1</i>	
Product name	Previous name
MQSeries for UnixWare V1.4.1	ezBRIDGE Transact on UnixWare for MQSeries Release 3.0

Level 2 products

<i>Table 18. MQSeries products, Level 2</i>		
Product name	Server	Client
MQSeries for AIX V5.1	Yes	Yes
MQSeries for AS/400 V4R2M1	Yes	No
MQSeries for AT&T GIS UNIX V2.2	Yes	Yes
MQSeries for Digital OpenVMS V2.2	Yes	Yes
MQSeries for HP-UX V5.1	Yes	Yes
MQSeries for OS/2 Warp V5.1	Yes	Yes
MQSeries for OS/390 V2.1 (formerly MQSeries for MVS/ESA)	Yes	No
MQSeries for SINIX and DC/OSx V2.2	Yes	Yes
MQSeries for Sun Solaris V5.1	Yes	Yes
MQSeries for Tandem NonStop Kernel V2.2	Yes	No
MQSeries for VSE/ESA V2.1	Yes	No
MQSeries for Windows V2.0	No	No
MQSeries for Windows V2.1	No	No
MQSeries for Windows NT V5.1	Yes	Yes

MQSeries interoperability summary

The tables in this section show the transmission protocols that are supported by the channels in each of the MQSeries products. Tables are provided for the two types of channel that are supported by the MQSeries products:

- **Message channels** - used to link MQSeries queue managers
- **MQI channels** - used to link MQSeries clients and servers

The tables can be used to determine the alternative protocols that can be used to link any two products together, as follows:

1. Find the row in the table that contains the first MQSeries product of interest.
2. Find the row that contains the second MQSeries product of interest.
3. Look at each column position in each of these rows. Where there is a column that has a check symbol ✓ in both rows, then the transmission protocol associated with that column can be used to link the two products.

The “at a glance” sections in Chapter 49, “MQSeries at a glance” on page 231 give details of the prerequisite hardware and software necessary at the two ends of a link for a particular transmission protocol.

Message channels - transmission protocols supported

Table 19. Message channels, transmission protocols supported

MQSeries product	SNA LU 6.2	TCP	NetBIOS	DECnet	SPX	UDP
MQSeries for AS/400	✓	✓	—	—	—	—
MQSeries for AIX	✓	✓	—	—	—	✓
MQSeries for AT&T GIS UNIX	✓	✓	—	—	—	—
MQSeries for Digital OpenVMS	✓	✓	—	✓	—	—
MQSeries for HP-UX	✓	✓	—	—	—	—
MQSeries for OS/2 Warp	✓	✓	✓	—	✓	—
MQSeries for OS/390	✓	✓	—	—	—	—
MQSeries for SINIX and DC/OSx	✓	✓	—	—	—	—
MQSeries for Sun Solaris	✓	✓	—	—	—	—
MQSeries for Tandem NSK	✓	✓	—	—	—	—
MQSeries for UnixWare	✓	✓	—	—	—	—
MQSeries for VSE/ESA	✓	✓	—	—	—	—
MQSeries for Windows	—	✓	—	—	—	✓(1)
MQSeries for Windows NT	✓	✓	✓	—	✓	—
Note: (1) UDP is supported only on Version 2.0.						

MQI channels - transmission protocols supported

Table 20. MQI channels, transmission protocols supported by servers

MQSeries servers	SNA LU 6.2	TCP	NetBIOS	DECnet	SPX
Digital OpenVMS	—	✓	—	✓	—
OS/2 Warp	✓	✓	✓	—	✓
OS/390	✓	✓	—	—	—
OS/400	✓	✓	—	—	—
Tandem NSK	✓	✓	—	—	—
UNIX systems	✓	✓	—	—	—
VSE/ESA	✓	✓	—	—	—
Windows NT	✓	✓	✓	—	✓

Table 21. MQI channels, transmission protocols supported by clients

MQSeries clients	SNA LU 6.2	TCP	NetBIOS	DECnet	SPX
DOS	—	✓	✓	—	✓
Digital OpenVMS	✓(1)	✓	—	✓	—
OS/2 Warp	✓	✓	✓	—	✓
UNIX systems	✓	✓	—	—	—
VM/ESA	✓	✓	—	—	—
Windows NT	✓	✓	✓	—	✓
Windows 3.1	—	✓	✓	—	✓
Windows 95 and Windows 98	—	✓	✓	—	✓

Note: (1) On Digital OpenVMS, SNA LU 6.2 supports only PU 2.0. Therefore communication can be to PU 5.0 only on an OS/390 server. If you want to communicate with a server on a platform other than OS/390, you must use another protocol. See Table 2 in the *MQSeries Clients* manual for more information.

MQSeries product functional comparison

Table 22 is a summary of the MQI functions that are provided by the MQSeries products. Those functions that are marked with the symbol ✓ are supported by all products identified by the column heading, except where indicated by the notes following the table.

Table 22 (Page 1 of 2). MQSeries product functional comparison

Function	Digital OpenVMS (1)	OS/390	OS/400	Tandem NSK	UNIX systems, OS/2 Warp, Windows NT (1)	VSE/ESA	Windows V2.0 & V2.1	UnixWare (1)
MQCONN/MQDISC	✓	✓	✓	✓	✓	✓	✓	✓
Queue manager groups	✓ (2)	—	—	✓ (2)	✓ (2)	—	—	—
MQOPEN/MQCLOSE	✓	✓	✓	✓	✓	✓	✓	✓
Queue-manager aliases	✓	✓	✓	✓	✓	✓	✓	✓
Reply-to queue aliases	✓	✓	✓	✓	✓	✓	✓	✓
Default input open option	✓	✓	✓	✓	✓	—	✓	—
Model/dynamic queues	✓	✓	✓	✓	✓	—	✓	—
Namelists	—	✓	—	—	✓ (3)	—	—	—
Default transmission queue	✓	✓	✓	✓	✓	—	✓	—
Distribution lists	—	—	✓	—	✓ (3)	—	—	—
MQPUT	✓	✓	✓	✓	✓	✓	✓	✓
Max message length	4 MB	4 MB	4 MB	4 MB	100 MB(4)	4 MB	4 MB	64 000
Max queue size	320 MB	2 GB	320 MB	2 GB(5)	2 GB(6)	4 GB	—	—
Dead-letter queue	✓	✓	✓	✓	✓	✓	—	✓
Nonpersistent messages	✓	✓	✓	✓	✓	✓	✓	—
Triggering (first and every)	✓	✓	✓	✓	✓	—	—	—
Full triggering (depth, priority)	✓	✓	✓	✓	✓	—	—	—
Message priority	✓	✓	✓	✓	✓	✓	✓	—
Application-specified syncpoint	✓	✓	✓	✓	✓	✓	✓	—
Context	✓	✓	✓	✓	✓	✓ (7)	✓ (8)	— (7)
Exception reports	✓	✓	✓	✓	✓	—	✓	—
Exception reports with data	✓	✓	✓	✓	✓	—	✓	—
COA, COD reports	✓	✓	✓	✓	✓	✓	✓	—
Message expiry	✓	✓	✓	✓	✓	—	✓	—
Report options for up-level	✓	✓	—	✓	✓	—	✓	—
MQGET	✓	✓	✓	✓	✓	✓	✓	✓
Browse	✓	✓	✓	✓	✓	✓	✓	✓
Browse with lock	✓	—	✓	✓	✓	✓	—	✓ (9)
Browse under cursor	✓	—	✓	✓	✓	✓	✓	—
Shared input	✓	✓	✓	✓	✓	✓	✓	✓
Get with signal	—	✓	—	✓	—	—	✓ (10)	—
Get by MsgId/CorrelId	✓	✓	✓	✓	✓	✓	✓	—
Message backout count	✓	✓	✓	✓	✓	—	✓	—
Mark skip backout	—	✓	—	—	—	—	—	—
Message data conversion	✓	✓	✓	✓	✓	—	—	—

Table 22 (Page 2 of 2). MQSeries product functional comparison

Function	Digital OpenVMS (1)	OS/390	OS/400	Tandem NSK	UNIX systems, OS/2 Warp, Windows NT (1)	VSE/ESA	Windows V2.0 & V2.1	UnixWare (1)
MQINQ	✓	✓	✓	✓	✓	✓	✓	✓ (11)
Queue retention interval	✓	✓	✓	✓	✓	—	—	—
MQSET	✓	✓	✓	✓	✓	✓	✓	—
MQCMIT/MQBACK	✓	✓	—	✓	✓	—	✓	—
MQBEGIN	—	—	—	—	✓ (3)	—	—	—
MQSC commands	✓	✓	✓	✓	✓	—	✓	—
PCF commands	✓	—	✓	✓	✓	—	✓ (10)	—
API crossing exit	—	✓ (12)	—	—	—	—	—	—
Message channel exits	✓	✓	✓	✓	✓	—	✓	—
Events	✓	✓	✓	✓	✓	—	✓ (10)	—
Segmented messages	—	—	✓	—	✓ (3)	✓	—	—
Reference messages	—	—	✓	—	✓ (3)	—	—	—
Fast channels	—	✓	✓	—	✓ (3)	—	✓ (10)	—
Message retry exit	✓	—	✓	✓	✓	—	—	—
Channel heartbeats	—	✓ (13)	✓	—	✓ (3)	—	—	—
Channel auto-definition	—	✓(14)	✓	—	✓ (3)	—	—	—
Clusters	—	✓	—	—	✓ (3)	—	—	—

Notes:

1. Functions similar on clients and server.
2. From client applications only.
3. AIX, HP-UX, OS/2 Warp, Sun Solaris, and Windows NT only.
4. In the DOS environment, limitations might be imposed by memory availability. On MQSeries for AT&T GIS UNIX and SINIX and DC/OSx, the maximum message length is 4 MB.
5. The maximum queue size is the maximum size allowed by Tandem NSK. The size of a queue file is limited to 2 GB or the available disk space. The queue can be larger than this if the file is partitioned.
6. On MQSeries for AT&T GIS UNIX and SINIX and DC/OSx, the maximum queue size is 320 MB.
7. Context fields are conveyed without any checks.
8. Context passing is not supported.
9. Must do *Browse First and Lock*.
10. Version 2.1 only.
11. For queues only.
12. CICS only.
13. Not for MQI channels.
14. Cluster channels only.

Chapter 49. MQSeries at a glance

This chapter gives information about the requirements for each MQSeries platform.

Table 23. MQSeries products at a glance

For information about...	See page...
AIX	232
AS/400	235
AT&T GIS UNIX (1)	236
Digital OpenVMS	237
DOS client	238
HP-UX	239
OS/2 Warp	241
OS/390	243
SINIX and DC/OSx	245
Sun Solaris	247
Tandem NonStop Kernel	249
UnixWare	251
VM/ESA client	253
VSE/ESA	254
Windows (16-bit)	255
Windows (32-bit)	257
Windows NT	259
Windows 3.1 client	262
Windows 95 and Windows 98 client	263
MQSeries link for R/3	264
Note: (1) This platform has become NCR UNIX SVR4 MP-RAS, R3.0	

MQSeries, when used in accordance with its associated documentation, is capable of correctly processing, providing, and receiving date data within and between the twentieth and twenty-first centuries, provided that all products (for example, hardware, software, and firmware) used with this IBM Program properly exchange accurate date data with it.

Customers should contact third party owners or vendors regarding the readiness status of their products.

IBM reserves the right to update the information shown here. For the latest information regarding levels of supported software, refer to

<http://www.software.ibm.com/ts/mqseries/platforms>

and for the latest IBM statement regarding Year2000 readiness, refer to

<http://www.ibm.com/IBM/year2000/>

MQSeries for AIX

MQSeries for AIX, Version 5.1

Machine requirements

MQSeries for AIX runs on any IBM RS/6000™ that is capable of running the required level of AIX, and that has sufficient storage to meet the combined requirements of the programming prerequisites, MQSeries for AIX, the access methods, and the application programs:

- IBM RS/6000 POWERserver®
- IBM RS/6000 POWERstation
- IBM Scalable POWERparallel® systems
- Any other trademarked AIX systems, whether from IBM or other vendors, for example:
 - Bull DPX/20 (RISC)
 - Bull Escala (SMP)
 - Motorola
 - Zenith

An MQSeries client can run on any personal computer that is capable of running the client code and that has sufficient storage to meet the combined requirements of the programming prerequisites, the client code, access methods, and the application programs.

Software requirements

Software requirements are identical for server and client AIX environments unless otherwise stated.

Minimum supported levels are shown. Later levels, if any, are supported unless otherwise stated.

- AIX Version, 4.2 or Version 4.3.x.

Note: Use level 4.2.1 or later if user data conversion of Greek, Cyrillic, Eastern European, Turkish, Japanese, or Korean language text longer than 2000 bytes is required.

Clients

Client code for AIX, DOS, HP-UX, OS/2 Warp, Sun Solaris, Windows NT, Windows 3.1, Windows 95, and Windows 98 workstations is distributed with the server code.

The MQSeries client for Java is also distributed with the server code; see Chapter 11, “Building applications for MQSeries clients” in the *MQSeries Clients* manual for more information.

Connectivity

- IBM eNetwork™ Communications Server for AIX, Version 5.0
- TCP (as part of the base operating system)

Note: MQSeries for AIX Version 5.1 supports the User Datagram Protocol (UDP), a part of the Internet suite of protocols, as an alternative to TCP. You might decide to use UDP instead of TCP for your mobile radio network, where you

need to reduce the traffic, and therefore the cost, on a packet radio data network.

UDP is supplied as part of the operating system or TCP/IP suite you are using; you do not need to buy and install a separate UDP product.

Options

- Transaction processing managers (server only)
 - TXSeries for AIX, Version 4.2
 - BEA Tuxedo, Version 5.1, 6.1, or 6.4
- Databases (server only)
 - DB2 Universal Database™, Version 5.0
 - Oracle 7.3.2.1
 - Oracle 8.0.4
 - Sybase Adaptive Server, Version 11.5
 - Sybase Embedded SQL/C, Version 11.1
 - Sybase Open Client/C, Version 11.1.1
 - Sybase XA Server, Version 11.1.1 (SWR 7993)
- IBM Software Servers
 - Communications Server for AIX, Version 4.0
 - Database Server for AIX, Version 4.0
 - Directory Security Server for AIX, Version 4
 - Internet Connection Server for AIX, Version 4.1.1
 - Internet Connection Secure Server for AIX, Version 4.1
 - Transaction Server for AIX, Version 4.0
- IBM eNetwork LDAP Directory Version 1.1.1
- DCE
 - IBM Directory and Security Server for AIX, Version 4
 - MQSeries DCE names and security modules are provided as part of MQSeries for AIX

Web functions

Web functions require Java, Version 1.1.1

- Web browsers
 - Internet Gateway - HTML 3.2 or later compatible browser
 - Java Client - HTML 3.2 plus JDK 1.1.1 enabled browser
- Web Servers for the Internet Gateway
 - Lotus® Domino®
 - Lotus Domino Go Webserver, Version 4.6
 - IBM Internet Connection Server, Version 4.1
 - Netscape FastTrack Server, Version 2.0
 - Netscape Enterprise Server, Version 2.0
 - Apache Web Server, Version 1.1.1
 - Microsoft Internet Information Server, Version 2.0

Languages and compilers

- IBM C for AIX, Version 3.1.4
- IBM C Set++ for AIX, Version 3.1
- Micro Focus COBOL compiler for UNIX, Version 4.0
- IBM COBOL Set for AIX, Version 1.1
- IBM PL/I set for AIX, Version 1.1

Delivery

MQSeries for AIX is supplied on CD-ROM. Two CD-ROMs are supplied; one containing the MQSeries for AIX server and client, and the other containing the other MQSeries clients shipped with MQSeries for AIX.

Installation

MQSeries for AIX is installed using either **Installation assistant**, **smit**, or **installp**.

The installation can be performed in approximately 5 minutes. Customization of the product is then required, the duration of this process being dependent on the individual requirements of the enterprise.

“Chapter 3. Installing the MQSeries for AIX Server” in the *MQSeries for AIX V5.1 Quick Beginnings* manual contains specific instructions for installing MQSeries for AIX.

MQSeries for AS/400

IBM MQSeries for AS/400 Version 4 Release 2 Modification 1

Machine requirements

MQSeries for AS/400 V4R2M1 runs on any AS/400 processor capable of running the required level of OS/400 and which has enough processor storage to meet the combined requirements of the programming prerequisites, the access methods, and the application programs.

Software requirements

Minimum supported levels are shown. Later levels, if any, are supported unless otherwise stated.

- OS/400 Version 4 Release 2 Modification 1

MQSeries for AS/400 clients

MQSeries for AS/400 supports but does not ship or configure MQSeries clients.

Connectivity

Connectivity can be through SNA LU 6.2 or TCP.

Options

- External Transaction Processing Monitors
 - CICS for AS/400 V4R2M1

To use the MQI in application programs that operate under CICS you also require the program libraries for the programming language that you are using

Languages and compilers

- ILE C for AS/400, Version 4.2.1
- ILE COBOL for AS/400, Version 4.2.1
- ILE RPG for AS/400, Version 4.2.1
- IBM VisualAge for C++ for AS/400, Version 4.2.1

ILE run-time is part of OS/400.

Delivery

MQSeries for AS/400 Version 4.2.1 is supplied on tape, diskette, and CD-ROM.

Installation

MQSeries for AS/400 is installed using the AS/400 **GO LICPGM** command. For installation instructions, refer to the *MQSeries for AS/400 Administration Guide*.

MQSeries for AT&T GIS UNIX

IBM MQSeries for AT&T GIS UNIX Version 2 Release 2

Machine requirements

MQSeries for AT&T GIS UNIX runs on any AT&T GIS 34xx, 35xx, or 36xx system. A minimum of 20 MB of disk space is required.

Software requirements

Minimum supported levels are shown. Later levels, if any, are supported unless otherwise stated.

- AT&T GIS UNIX SVR4 MP-RAS³ Version 2.0.3.01, or later Version 2

MQSeries for AT&T GIS UNIX clients

Client code for AT&T GIS UNIX³, OS/2 Warp, DOS, and Windows 3.1 workstations is distributed with the server code.

Connectivity

The network protocols supported are SNA LU 6.2 and TCP.

- AT&T GIS SNA Services Version 2.06 or later Version 2 to match hardware system
- TCP as part of base operating system

Options

- Transaction Processing monitors (coordination via X/Open XA interface)
 - Novell Tuxedo, Version 4.2.2

Languages and compilers

- AT&T GIS High Performance C, Version 1.0b
- AT&T C++ language system for AT&T GIS UNIX

Delivery

MQSeries for AT&T GIS UNIX is supplied on CD-ROM or QIC tape.

Installation

MQSeries for AT&T GIS UNIX is installed using the **pkgadd** command.

The installation can be performed in approximately 5 minutes. Customization of the product is then required, the duration of this process being dependent on the individual requirements of the enterprise.

The *MQSeries for AT&T GIS UNIX System Management Guide* contains specific instructions for installing this product.

³ This platform has become NCR UNIX SVR4 MP-RAS, R3.0

MQSeries for Digital OpenVMS

- MQSeries for Digital OpenVMS AXP Version 2 Release 2
- MQSeries for Digital OpenVMS VAX Version 2 Release 2

Machine requirements

Any Digital VAX machine, with minimum system disk space of 16 MB for VAX or 18 MB for AXP, and minimum memory of 16 MB for VAX or 32 MB for AXP.

Software requirements

Software requirements are identical for server and client Digital OpenVMS environments unless otherwise stated. Minimum supported levels are shown. Later levels, if any, are supported unless otherwise stated.

- Digital OpenVMS VAX Version 6.2 or later Version 6, or Version 7.1

Clients

Client code for Digital OpenVMS, OS/2 Warp, DOS, and Windows 3.1 workstations is distributed with the server code. The Windows 3.1 client can operate under Windows 3.1, Windows 95, or within the WIN-OS/2 environment under OS/2 Warp.

Connectivity

Network protocols supported are DECnet, SNA LU 6.2, and TCP.

- DECnet Phase IV
- DECnet OSI, Version 6.3
- Digital SNA APPC LU6.2 Programming Interface, Version 2.2
- Digital DECnet SNA Gateway, Version 1.2A
- Cisco Multinet for OpenVMS, Version 3.5
- DEC TCP/IP Services for OpenVMS, Version 4.0
- Attachmate PathWay for OpenVMS, Version 2.5.1
- Process Software's TCPware for OpenVMS, Version 5.2-3

Options

Distributed Computing Environment for OpenVMS, Version 1.3B

Languages and compilers

- DEC C, Version 5.0
- DEC C++, Version 5.0 (VAX) or 5.2 (AXP)
- DEC COBOL, Version 5.0 (VAX) or 2.2 (AXP)

Delivery

MQSeries for Digital OpenVMS is supplied on CD-ROM for AXP and on CD-ROM and TK50 tape cartridge for VAX.

Installation

MQSeries for Digital OpenVMS is installed with the OpenVMS VMSINSTAL utility, and takes approximately 10 minutes to install from CD-ROM. Customization of the product is then required, the duration of this process being dependent on the individual requirements of the enterprise.

MQSeries client for DOS

This section summarizes the machine and software requirements for the MQSeries DOS client.

Client code for DOS workstations is distributed with the server code for all servers except OS/390, OS/400, Tandem NSK, and VSE/ESA.

Machine requirements

An MQSeries client can run under DOS on any personal computer that is capable of running the client code and which has sufficient storage to meet the combined requirements of the programming prerequisites, the client code, access methods, and the application programs.

Software requirements

Minimum supported software levels are shown. Later levels, if any, are supported unless otherwise stated.

- DOS 5.0

Connectivity

- Internet Connection Corporate kit for Windows 3.1 and Windows 95, Version 5.0
- Novell NetWare Client for DOS/Win, Version 1.2
- Novell NetWare Client for OS/2, Version 2.1 (allows clients access to SPX via programs that run in a DOS window under OS/2)
- Novell LAN Workplace, Version 5.1
- FTP TCP for DOS

Languages and compilers

The following compilers are supported:

- Microsoft C, Version 7.0
- Microsoft Visual C++, Version 1.5

MQSeries for HP-UX

IBM MQSeries for HP-UX, Version 5.1

Machine requirements

The MQSeries for HP-UX servers can run on any HP 9000 Family 700 or Family 800 or Stratus Continuum/400 machine. A minimum of 20 MB of disk space is required.

Software requirements

Minimum supported levels are shown.

- HP-UX, Version 10.20 or 11.0

Clients

Client code for AIX, DOS, HP-UX, OS/2 Warp, Sun Solaris, Windows NT, Windows 3.1, Windows 95, and Windows 98 workstations is distributed with the server code.

The MQSeries client for Java is also distributed with the server code; see Chapter 11, “Building applications for MQSeries clients” in the *MQSeries Clients* manual for more information.

Connectivity

The network protocols supported are SNA LU 6.2 and TCP.

- HP SNAplusII
- TCP as part of base operating system

Options

- Transaction processing monitors (server only)
 - TXSeries for HP-UX, Version 4.2
 - BEA Tuxedo, Version 5.1, 6.1, or 6.4
 - HP Encina/9000, Version 1.2 or 2.2
- Databases (server only)
 - DB2 Universal Database, Version 5.0
 - Oracle 7.3.2.3 (with patches 437448 and 441647)
 - Oracle 8.0.4
- IBM Software Servers
 - Internet Connection Server for HP-UX, Version 4.2.1
 - Internet Connection Secure Server for HP-UX, Version 4.2.1
- DCE
 - The HP DCE/9000 version appropriate for the level of the HP-UX operating system in use, providing that this is compatible with DCE Version 1.4.1
 - MQSeries DCE names and security modules are provided as part of MQSeries for HP-UX

Web functions

Web functions require Java, Version 1.1.1

- Web browsers
 - Internet Gateway - HTML 3.2 or later compatible browser
 - Java Client - HTML 3.2 plus JDK 1.1.1 enabled browser
- Web Servers for the Internet Gateway
 - Lotus Domino
 - Lotus Domino Go Webserver, Version 4.6
 - IBM Internet Connection Server, Version 4.1
 - Netscape FastTrack Server, Version 2.1
 - Netscape Enterprise Server, Version 2.0
 - Apache Web Server, Version 1.1.1
 - Microsoft Internet Information Server, Version 2.0

Languages and compilers

- Bundled C compiler
- HP-UX ANSI C compiler
- C Softbench, Version 5.0
- IBM C compiler, Version 3.6
- IBM C++ compiler, Version 3.6
- HP C++, Version 3.1 for HP-UX Version 10.x
- HP-UX ANSI C++ compiler for HP-UX Version 10 and Version 11
- Micro Focus COBOL compiler for UNIX, Version 4
- COBOL Softbench, Version 4.0
- HP DCE/9000 application development tools (with applicable patches)

Delivery

MQSeries for HP-UX is supplied on CD-ROM. Two CD-ROMs are supplied; one containing the MQSeries for HP-UX server and client, and the other containing the other MQSeries clients shipped with MQSeries for HP-UX.

Installation

MQSeries for HP-UX is installed using the **update** command.

The installation can be performed in approximately 5 minutes. Customization of the product is then required, the duration of this process being dependent on the individual requirements of the enterprise.

“Chapter 3. Installing the MQSeries for HP-UX Server” in the *MQSeries for HP-UX V5.1 Quick Beginnings* manual contains specific instructions for installing this product.

MQSeries for OS/2 Warp

MQSeries for OS/2 Warp, Version 5.1

Machine requirements

MQSeries for OS/2 Warp runs on any personal computer that is capable of running the required level of OS/2 Warp, and which has sufficient RAM and disk storage to meet the combined requirements of the programming prerequisites, MQSeries for OS/2 Warp, the access methods, and the application programs. The system unit must have a CD-ROM device.

An MQSeries client can run on any personal computer that is capable of running the client code and which has sufficient storage to meet the combined requirements of the programming prerequisites, the client code, access methods, and the application programs.

Software requirements

Software requirements are identical for server and client OS/2 Warp environments unless otherwise stated.

Minimum supported software levels are shown. Later levels, if any, are supported unless otherwise stated.

- OS/2 Warp, Version 4
- OS/2 Warp Server, Version 4.0
- OS/2 Warp Server Advanced SMP feature
- OS/2 Workspace-On-Demand
- OS/2 e-Business Server

Clients

Client code for AIX, DOS, HP-UX, OS/2 Warp, Sun Solaris, Windows NT, Windows 3.1, Windows 95, and Windows 98 workstations is distributed with the server code.

The MQSeries client for Java is also distributed with the server code; see Chapter 11, “Building applications for MQSeries clients” in the *MQSeries Clients* manual for more information.

Connectivity

- IBM eNetwork Communications Server for OS/2 Warp, Version 5.0
- Novell Net Ware Client for OS/2, Version 1.20
- TCP/IP for OS/2, Version 2.0, base kit plus NetBIOS kit
- intraNetWare Client for OS/2
- NetWare for OS/2, Version 4.11

Options

- Transaction processing monitors (server only)
 - CICS Transaction Server for OS/2, Version 4.1
- Databases (server only)
 - DB2 Universal Database, Version 5.0
- IBM Software Servers
 - Database Server for OS/2 Warp, Version 4.0

- Directory Security Server for OS/2 Warp, Version 4.0
- Internet Connection Server for OS/2 Warp, Version 4.2.1
- Internet Connection Secure Server for OS/2 Warp, Version 4.2.1
- Transaction Server for OS/2, Version 4.0
- DCE
 - IBM Directory and Security Server for OS/2 Warp, Version 4.0
 - MQSeries DCE names and security modules are provided as part of MQSeries for OS/2 Warp

Web functions

Web functions require Java, Version 1.1.1

- Web browsers
 - Internet Gateway - HTML 3.2 or later compatible browser
 - Java Client - HTML 3.2 plus JDK 1.1.1 enabled browser
- Web Servers for the Internet Gateway
 - Lotus Domino
 - Lotus Domino Go Webserver, Version 4.6
 - IBM Internet Connection Server, Version 4.1
 - Netscape FastTrack Server, Version 2.0
 - Netscape Enterprise Server, Version 2.0
 - Apache Web Server, Version 1.1.1
 - Microsoft Internet Information Server, Version 2.0

Languages and compilers

- IBM C compiler, Version 3.6
- IBM C++ compiler, Version 3.6
- Borland C++ Compiler, Version 2.0 (C bindings)
- IBM VisualAge for C++ for OS/2, Version 3.0
- Micro Focus COBOL, Version 4
- IBM VisualAge for COBOL for OS/2, Version 1.1
- IBM PL/I for OS/2, Version 1.2
- IBM VisualAge for PL/I for OS/2

Delivery

MQSeries for OS/2 Warp is supplied on CD-ROM. Two CD-ROMs are supplied; one containing the MQSeries for OS/2 Warp server and client, and the other containing the other MQSeries clients shipped with MQSeries for OS/2 Warp.

Installation

MQSeries for OS/2 Warp is installed using Software Installer/2. The installation can be performed in approximately 15 minutes. Customization of the product is then required, the duration of this process being dependent on the individual requirements of the enterprise.

“Chapter 3. Installing MQSeries for OS/2 Warp” in the *MQSeries for OS/2 Warp V5.1 Quick Beginnings* manual contains specific instructions for installing MQSeries for OS/2 Warp. It also gives information about using Configuration, Installation, and Distribution (CID), and NetView Distribution Manager/2 (DM/2) to install MQSeries for OS/2 Warp.

MQSeries for OS/390

IBM MQSeries for OS/390 Version 2 Release 1

Machine requirements

MQSeries for OS/390 runs on any IBM System/390 processor that is capable of running the required level of OS/390, and which has enough storage to meet the combined requirements of the programming prerequisites, MQSeries for OS/390, the access methods, and the application programs.

Software requirements

This section lists the software requirements for Version 2.1 of MQSeries for OS/390. We recommend that you use one of the packaged offerings of OS/390 from IBM (for example, ServerPac). This includes most of the products that you will need to run MQSeries on OS/390, and the integrated products have been verified by IBM.

The list of elements included in OS/390, and the recommended levels of nonexclusive elements are described in *OS/390 Planning For Installation* (GC28-1726).

MQSeries for OS/390 Version 2.1 requires OS/390 Version 2.4 or later, together with the products included in OS/390. These include:

- C/C++
- DFSMS™/dfp
- HLASM
- ISPF
- JES
- Language Environment® (previously known as LE/370)
- Security Server (previously known as RACF®)
- SMP/E
- TCP/IP
- TSO/E
- UNIX Services (previously known as OpenEdition®)
- VTAM®

The following list gives the minimum levels required for the optional products that are not included in OS/390. You might not need all of these products.

- CICS, Version 4.1
- COBOL, Version 2.1 or VS COBOL 2, Release 4
- HL/ASM, Version 1.2
- Internet Connection Secure Server, Version 2.2
- IMS, Version 5.1
- ISPF, Version 4.2.1
- PL/I for OS/390, Version 1.1, or OS PL/I, Version 2.3

Additional requirements for some features

Some of the features of MQSeries for OS/390 Version 2.1 have additional requirements. These are listed below:

TCP IUCV interface

This can be used only on OS/390, Version 2.4. For later versions of OS/390, use the OpenEdition Sockets interface to TCP.

MQSeries Workflow

- OS/390, Version 2.6
- MQSeries Workflow, Version 3.1

Non-IBM products

If you choose to use Interlink TCPAccess in place of IBM's TCP/IP, the recommended minimum level is Version 4.1.

Clients

For MQSeries for OS/390 to support clients you need to install the client/server support code that is provided by the Client Attachment Feature of MQSeries for OS/390. However, you can administer clients without this feature.

Delivery

MQSeries for OS/390 is supplied on either 6250 tape or 3480 cartridge. (It is also available on 4-mm DAT tape for PC/390.) One tape or cartridge contains the product code together with four language features – U.S. English (mixed case), U.S. English (uppercase), Japanese, and Simplified Chinese – and the optional CICS mover facility. The optional Client Attachment and Internet Gateway features are both supplied on separate tapes or cartridges.

Installation

MQSeries for OS/390 is installed with SMP/E using the receive-apply-accept approach. JCL is provided on the tape to assist with this process.

The installation can be performed in approximately two hours. Customization of the product is then required, the duration of this process being dependent on the individual requirements of the enterprise.

The *MQSeries for OS/390 Program Directory* contains specific instructions for installing MQSeries for OS/390.

MQSeries for SINIX and DC/OSx

IBM MQSeries for SINIX and DC/OSx V2.2

Machine requirements

SINIX: RM200, RM300, RM400, RM600 systems with minimum disk space of 30 MB. If DynaText books are installed, a minimum of 50 MB of system disk space is needed.

DC/OSx: MServer, Nile systems with minimum disk space of 30 MB.

Software requirements

Software requirements are identical for server and client environments unless otherwise stated.

Minimum supported levels are shown. Later levels, if any, are supported unless otherwise stated.

- SINIX operating system, for RM200, RM300, or RM400 – SINIX-N Version 5.42C10 or later
- SINIX operating system, for RM600 – SINIX-Y Version 5.42A40 or later
- DC/OSx operating system Version 1.1-cd079

MQSeries for SINIX and DC/OSx clients

Client code for SINIX and DC/OSx, OS/2 Warp, DOS, and Windows 3.1 workstations is distributed with the server code.

The Windows 3.1 client can operate under Windows 3.1, Windows 95 or within the WIN-OS/2 environment under OS/2 Warp.

Client software provides a remote interface to a LAN server. It can reside at the server or at a file server and be copied dynamically to the client for use, or it can reside on the client's disk space.

Client support does not result in distributed coordination of units of work.

Connectivity

The network protocols supported are SNA LU 6.2 and TCP.

- SINIX: SNA
 - TRANSIT-SERVER 3.4 (SNA Communication Server Version)
 - TRANSIT-CLIENT 3.4 (SNA Comm. Client / Local Functions)
 - TRANSIT-CPIC 3.4 (SNA LU 6.2 Communication and CPI-C)
- SINIX: OpenNet TCP/IP (shipped with base SINIX operating system)
- DC/OSx: TCP/IP Version 1.0
- DC/OSx: SNA requires LU 6.2 SW Version 1.3
 - To support the ISC-2 (Intelligent Synchronous Controller) serial line
 - Comm Services V 1.2 and ISC with SNA engine V 3.1

- To support the ILC-T (Intelligent LAN Controller, Token ring) interface
 - Comm Services V 1.2 and Token Ring Mac interface V 1.3
- To support the SNA on the ESCON® IBM Channel link
XVI/ESCON Driver 1.0

Options

- Transaction Processing monitors (coordination via X/Open XA interface)
 - SINIX: Encina (version 1.1A00)
 - SINIX: CICS for Siemens Nixdorf SINIX (version 2.1)
 - SINIX: Novell Tuxedo (Version 5.0)
 - DC/OSx: Novell Tuxedo (Version 5.0)
- DCE
 - SINIX: Version DCE-MI V1.03B00

Note: DCE cannot be invoked from installable services or from user exits on the SINIX platform. However, stand-alone DCE programs can invoke the MQI.

Languages and compilers

- SINIX: C compiler (C-DS, MIPS), Version 1.1
- DC/OSx: C4.0 compiler, Version 4.0.1
- SINIX: Micro Focus COBOL, Version 3.2
- DC/OSx: Micro Focus COBOL, Version 3.2

Delivery

- For SINIX, MQSeries is supplied on CD-ROM.
- For DC/OSx, MQSeries is supplied on QIC-320 cartridge tape.

Documentation browsing

On SINIX, to view the online documentation, DynaText is required. Either use SINIX/Windows version 2 or later, which provides a DynaText viewer, or use the SINIX online documentation package (separate product), which also provides a DynaText viewer.

Installation

MQSeries for SINIX is installed using the **sysadm** command.

MQSeries for DC/OSx is installed using the **pkgadd** command.

The base directory for installation is /opt/mqm.

MQSeries for Sun Solaris

IBM MQSeries for Sun Solaris, Version 5.1

Machine requirements

Only the Sun SPARC and Sun UltraSPARC hardware is supported. A minimum of 25 MB of system disk space is required.

Software requirements

Software requirements are identical for server and client on Solaris environments unless otherwise stated.

Minimum supported levels are shown. Later levels are supported unless otherwise stated.

- Sun Solaris, Version 2.6 (with patches 105210-13 and 105568-10) or Version 7.

Clients

Client code for AIX, DOS, HP-UX, OS/2 Warp, Sun Solaris, Windows NT, Windows 3.1, Windows 95, and Windows 98 workstations is distributed with the server code.

The MQSeries client for Java is also distributed with the server code; see Chapter 11, “Building applications for MQSeries clients” in the *MQSeries Clients* manual for more information.

Connectivity

The network protocols supported are SNA LU 6.2 and TCP.

- SunLink SNA Peer-to-Peer, Version 9.1
- If a token ring is to be used, SunLink Token Ring Interface /SBus, Version 3.0.2 (with patch 102463).
- TCP as part of the base operating system.

Options

- Transaction Processing monitors (server only)
 - TXSeries for Sun Solaris, Version 4.2
 - BEA Tuxedo, Version 5.1, 6.1, or 6.4
- Databases (server only)
 - DB2 Universal Database, Version 5.0
 - Oracle 7.3.2.3
 - Oracle 8.0.4
 - Sybase Adaptive Server, Version 11.5
 - Sybase Embedded SQL/C, Version 11.1
 - Sybase Open Client/C, Version 11.1.1
 - Sybase XA Server, Version 11.1.1 (EBF7589)
- IBM Software Servers
 - Internet Connection Server for Sun Solaris, Version 4.1
 - Internet Connection Secure Server for Sun Solaris, Version 4.1

- DCE
 - Transarc DCE, Version 1.1 and later compatible releases
 - MQSeries DCE names and security modules are provided as part of MQSeries for Sun Solaris

Web functions

Web functions require Java, Version 1.1.3 plus the native thread pack.

- Web browsers
 - Internet Gateway - HTML 3.2 or later compatible browser
 - Java Client - HTML 3.2 plus JDK 1.1.1 enabled browser
- Web Servers for the Internet Gateway
 - Lotus Domino
 - Lotus Domino Go Webserver, Version 4.6
 - IBM Internet Connection Server, Version 4.1
 - Netscape FastTrack Server, Version 2.0
 - Netscape Enterprise Server, Version 2.0
 - Apache Web Server, Version 1.1.1
 - Microsoft Internet Information Server, Version 2.0

Languages and compilers

- SunWorkShop C Compiler, Version 4.2
- SunWorkShop C++ Compiler, Version 4.2
- Micro Focus COBOL for UNIX, Version 4.0

Delivery

MQSeries for Sun Solaris is supplied on CD-ROM. Two CD-ROMs are supplied; one containing the MQSeries for Sun Solaris server and client, and the other containing the other MQSeries clients shipped with MQSeries for Sun Solaris.

Installation

MQSeries for Sun Solaris is installed using the **pkgadd** command or the **sysadm** command. "Chapter 3. Installing the MQSeries for Sun Solaris Server" in the *MQSeries for Sun Solaris V5.1 Quick Beginnings* manual contains specific instructions for installing this product.

MQSeries for Tandem NSK

IBM MQSeries for Tandem NSK Version 2 Release 2

Machine requirements

Minimum hardware requirements are:

- Any of the Tandem NSK range of machines supported by Tandem NSK D3x, D4x, or G0x
- Specific hardware in support of user-selected network transport protocols

You are also recommended to have one or more mirrored data disks with specified space requirements for TMF audit space and the MQSeries database.

Software requirements

Minimum software requirements are:

- Tandem NSK D3x, D4x, or G0x operating systems, including TM/MP (TMF), ENSCRIBE, and EMS
- TS/MP (PATHWAY) to match the operating system
- SCF for configuration, command, and control of TCP and SNA network transports

Transaction logging is maintained with the Tandem TM/MP (TMF) product.

Connectivity

For SNA connectivity, either:

- SNAX/APC and SNAX/XF or SNAX/APN to match the operating system
- Insession ICE to match the operating system

For TCP connectivity:

- TCP to match the operating system

Clients

MQSeries for Tandem NSK supports, but does not ship, MQSeries clients.

Languages and compilers

Supported languages for application development:

- TAL
- C
- COBOL-85

Delivery

MQSeries for Tandem NSK is supplied on a 3480 cartridge.

Installation

The *MQSeries for Tandem NonStop Kernel System Management Guide* contains specific instructions for installing this product.

MQSeries for UnixWare

IBM MQSeries for UnixWare Version 1 Release 4.1

Machine requirements

For the following configurations: combined file/communications server, communications server only, file server only, or client only:

- Any 386 DX PC or better
 - Minimum system memory: 16 MB
 - Minimum disk space:
 - Combined file/comms server: 2 MB + size of queues
 - File server: size of queues
 - Communications server: 2 MB
 - Client: normal disk space supplied with machine
- Any LAN adapter

For SNA connectivity (communications server):

- Any 486 PC or better (including an ISA bus)
 - Minimum system memory: 16 MB
 - Minimum disk space: 28.5 MB + size of queues (where appropriate)
- Apertus Technologies Inc ELC Adapter (ISA) with:
 - Express 2.04b or 2.1.1 (for UnixWare Application Server SDK 1.1 or later 1.x)
 - Express 2.1.2 (for UnixWare Personal Edition 2.01 or later 2.x or Application Server 2.01 or 2.1)

or

- Emulex Adapter (ISA) with:
 - Express 2.04b or 2.1.1 (for UnixWare Application Server SDK 1.1 or later 1.x)
 - Express 2.1.2 (for UnixWare Personal Edition 2.01 or later 2.x or Application Server 2.01 or 2.1)

or

- Madge Token Ring Adapter (ISA) with:
 - Madge Smart 16/4 AT PLUS card with Express 2.1.2 (for UnixWare Personal Edition 2.01 or later 2.x or Application Server 2.01 or 2.1)
 - One of the following for UnixWare Application Server SDK 1.1 or later 1.x:

Madge card	Express Version
Madge Smart 16/4 AT card	2.04b or 2.1.1
Madge Smart 16/4 AT PLUS card	2.1.2

Software requirements

Minimum supported levels are shown. Later levels, if any, are supported unless otherwise stated.

For the following configurations: combined file/communications server, communications server only, file server only, or client only:

- UnixWare Application Server SDK Version 1.1 or later Version 1, including TCP. (For bridge support across TCP, contact your Novell service representative.)
- UnixWare Personal Edition 2.01 or later 2.x or Application Server 2.01 or 2.1 including TCP.
- Appropriate LAN software (file server or client): for example, NFS to match TCP. Customers who plan to use NFS should contact their service representative to obtain all available patches.

Languages and compilers

Supported language for application development:

- C

Delivery

MQSeries for UnixWare is supplied on 3.5-inch diskettes.

Installation

MQSeries for UnixWare is installed using the **pkgadd** command.

The installation can be performed in approximately 10 minutes.

The *MQSeries for UnixWare User's Guide* contains specific instructions for installing this product.

MQSeries client for VM/ESA

This section summarizes the machine and software requirements for the MQSeries client for VM/ESA.

Machine requirements

An MQSeries client can run under VM/ESA on any of the following machines:

- S/390 Parallel Enterprise Server™ - Generation 3
- S/390 Multiprise® 2000
- ES/9000® Processors

Software requirements

The following are prerequisites for MQSeries applications running on a VM/ESA client.

Minimum supported software levels are shown. Later levels, if any, are supported unless otherwise stated.

- VM/ESA, Version 2.3
- LE/370, Release 1.6
- TCP/IP, Release 2.0, or VTAM LU 6.2

Languages and compilers

The following compilers are supported:

- IBM C for VM, Release 3.1
- IBM VS COBOL II
- IBM OS/PL/I, Release 2.3
- IBM VM/ESA REXX/VM
- IBM Assembler

Delivery

The MQSeries client for VM/ESA is shipped with the VM/ESA product. It is preloaded with the installation of CMS, and can be accessed on the MAINT 193 disk.

MQSeries for VSE/ESA

IBM MQSeries for VSE/ESA Version 2 Release 1

Machine requirements

- Any IBM System 370 or 390 machine
- Any communications hardware supporting TCP or SNA LU 6.2

Software requirements

Minimum supported levels are shown. Later levels, if any, are supported unless otherwise stated.

- VSE/ESA Version 2.3 or later 2.x

Clients

MQSeries for VSE/ESA can act as a server to an MQSeries client, but does not ship or configure clients.

Connectivity

- For SNA, VTAM for VSE/ESA, Version 4.2
- For TCP, TCP/IP for VSE/ESA, Version 1.3

Options

- CICS/VSE®, Version 2.3
- LE/VSE runtime library, Version 1.4

Languages and compilers

- IBM C for VSE/ESA, Version 1.1
- IBM COBOL for VSE/ESA, Version 1.1
- IBM PL/I for VSE/ESA, Version 1.1

Delivery

MQSeries for VSE/ESA is supplied on 3480 cartridge, 6250 tape, and 4mm DAT tape.

Installation

The MQSeries for VSE/ESA tape is in standard IBM MSHP format.

The *MQSeries for VSE/ESA System Management Guide* contains specific instructions for installing this product.

MQSeries for Windows Version 2.0

IBM MQSeries for Windows Version 2.0

Machine requirements

MQSeries for Windows version 2.0 is a 16-bit product, so it runs on computers that run Windows 3.1, and it runs in 16-bit compatibility mode on Windows 95.

Table 24 suggests two configurations: one for running applications and the other for developing applications.

Note: These recommendations are for guidance only. They do not take into account the effects of any other software that might be running on the system at the same time.

Table 24. Suggested hardware configurations for MQSeries for Windows Version 2.0

Configuration	Processor	RAM	Hard disk
For running applications	386 16 MHz	4–8 MB	3.9 MB available
For developing applications	486 66 MHz or better	8–16 MB	5 MB available
Note: The specification for developing applications does not include hardware requirements for other development tools (for example, compilers).			

Software requirements

This section describes the software you require before you can use MQSeries for Windows version 2.0. This depends on whether you want to run MQSeries applications on MQSeries for Windows, or develop your own applications for it.

For running MQSeries applications

For running applications on MQSeries for Windows Version 2.0, you need the following software (or later versions):

- MS-DOS or PC DOS Version 3.3
- Microsoft Windows 3.1, Windows 95, Windows for Workgroups 3.11, or Win-OS/2 on OS/2 Version 3.0 (Warp)

MQSeries for Windows Version 2.0 runs in 16-bit compatibility mode on Windows 95.

Connectivity

- TCP for the operating system you are using:
 - For Microsoft Windows 3.1, you need IBM TCP/IP for DOS Version 2.1.1 with CSD 2.1.1.4.
 - For Microsoft Windows 95, use the version of TCP supplied with Windows 95.
 - For Microsoft Windows for Workgroups 3.11, you need IBM TCP/IP for DOS Version 2.1.1 with CSD 2.1.1.4.
 - For Win-OS/2, you need IBM TCP/IP for OS/2 Version 2.

Note: MQSeries for Windows Version 2.0 supports the User Datagram Protocol (UDP), a part of the Internet suite of protocols, as an alternative to TCP. You might decide to use UDP instead of TCP for your mobile radio network, where you need to reduce the traffic, and therefore the cost, on a packet radio data network.

UDP is supplied as part of the operating system or TCP/IP suite you are using; you do not need to buy and install a separate UDP product.

Languages and compilers

To develop and test MQSeries applications that run on Windows, in addition to the software listed in “For running MQSeries applications” on page 255, you need only the compiler for the programming language you will use:

For 16-bit C

Microsoft Visual C++, Version 1.5

For 32-bit C

Microsoft Visual C++, Version 2.0

For 16-bit BASIC

Microsoft Visual Basic, Version 3.0
or Microsoft Visual Basic, Version 4.0

For 32-bit BASIC

Microsoft Visual Basic, Version 4.0

MQSeries for Windows Version 2.0 runs in 16-bit compatibility mode on Windows 95, but you can write 32-bit MQSeries for Windows applications.

Delivery

MQSeries for Windows Version 2.0 is supplied on diskettes. It is enabled for Configuration, Installation, and Distribution (CID) so you can put the installation files on a LAN server for easier access.

Installation

The *MQSeries for Windows User's Guide* contains specific instructions for installing this product.

MQSeries for Windows Version 2.1

IBM MQSeries for Windows Version 2.1

Machine requirements

MQSeries for Windows version 2.1 is a 32-bit product, so it runs on computers that run Windows 95, Windows 98, or Windows NT Version 4.0. Table 25 suggests two configurations: one for running applications and the other for developing applications.

Note: These recommendations are for guidance only. They do not take into account the effects of any other software that might be running on the system at the same time.

Table 25. Suggested hardware configurations for MQSeries for Windows Version 2.1

Configuration	Processor	RAM	Hard disk
For running applications	386DX or better	At least 4 MB	At least 3.5 MB available
For developing applications	486 66 MHz or better	At least 8 MB	At least 5 MB available
Note: The specification for developing applications does not include hardware requirements for other development tools (for example, compilers).			

Software requirements

This section describes the software you require before you can use MQSeries for Windows version 2.1. This depends on whether you want to run MQSeries applications on MQSeries for Windows, or develop your own applications for it.

For running MQSeries applications

For running applications on MQSeries for Windows Version 2.1, you need the following software (or later versions):

- Microsoft Windows 95, Windows 98, or Windows NT Version 4.0

Connectivity

- TCP for the operating system you are using.

Languages and compilers

To develop and test MQSeries applications that run on Windows, in addition to the software listed in “For running MQSeries applications,” you need only the compiler for the programming language you will use:

- Microsoft Visual C++, Version 4.0
- Borland C
- Microsoft Visual Basic, Version 4.0

Delivery

MQSeries for Windows Version 2.1 is supplied on CD-ROM or diskettes. It is enabled for remote (or silent) installation so you can put the installation files on a LAN server for easier access.

Installation

The *MQSeries for Windows User's Guide* contains specific instructions for installing this product.

MQSeries for Windows NT

IBM MQSeries for Windows NT, Version 5.1

Machine requirements

MQSeries for Windows NT can run on any Intel 486 (or above) processor-based IBM PC machine or compatible.

Software requirements

Minimum supported levels are shown. Later levels, if any, are supported unless otherwise stated.

- Microsoft Windows NT, Version 4.0 (with Service Pack 4 or later) and later compatible versions

Clients

Client code for AIX, DOS, HP-UX, OS/2 Warp, Sun Solaris, Windows NT, Windows 3.1, Windows 95, and Windows 98 workstations is distributed with the server code.

The MQSeries client for Java is also distributed with the server code; see Chapter 11, “Building applications for MQSeries clients” in the *MQSeries Clients* manual for more information.

Connectivity

The network protocols supported are SNA LU 6.2, TCP, NetBIOS, and SPX.

- SNA LU 6.2
 - Attachmate EXTRA! Personal Client, Version 6.1 and 6.2
 - IBM Communications Server for Windows NT, Version 5.0
 - IBM Personal Communications for Windows NT, Version 5.0
 - Microsoft SNA Server, Version 2.11 and Version 3
- For TCP use the TCP facilities within Windows NT
- For NetBIOS use the NetBIOS facilities within Windows NT
- For SPX use the SPX facilities within Windows NT
- For clients only:
 - FTP OnNet SDK for Windows

Options

- Transaction Processing monitors (server only)
 - TXSeries for Windows NT, Version 4.2
 - BEA TUXEDO, Version 5.1, 6.1, or 6.4
- Databases
 - DB2 Universal Database, Version 5.0
 - Sybase Adaptive Server, Version 11.5
 - Sybase Embedded SQL/C, Version 11.1
 - Sybase Open Client/C, Version 11.1.1 (with latest support level)
 - Sybase XA Server, Version 11.1.1 (with latest support level)

- IBM Software Servers
 - Communications Server for Windows NT, Version 5.0
 - Database Server for Windows NT, Version 4.0
 - Directory Security Server for Windows NT, Version 5.0
 - Internet Connection Server for Windows NT, Version 4.2.1
 - Internet Connection Secure Server for Windows NT, Version 4.2.1
 - Transaction Server for Windows NT, Version 4.0
- DCE
 - IBM Directory and Security Server for Windows NT, Version 5
 - MQSeries DCE security modules are provided as part of MQSeries for Windows NT
- Microsoft Management Console, Version 1.1
- Active Directory Service Interfaces, Version 2.0
- HTMLHelp, Version 1.1

Web functions

Web functions require Java, Version 1.1.1

- Web browsers
 - Internet Gateway - HTML 3.2 or later compatible browser
 - Java Client - HTML 3.2 plus JDK 1.1.1 enabled browser
- Web administration
 - Netscape Navigator, Version 4.04 with the Java AWT upgrade
 - Internet Explorer, Version 4.01 SP1
- Web Servers for the Internet Gateway
 - Lotus Domino
 - Lotus Domino Go Webserver, Version 4.6
 - IBM Internet Connection Server, Version 4.1
 - Netscape FastTrack Server, Version 2.0
 - Netscape Enterprise Server, Version 2.0
 - Apache Web Server, Version 1.1.1
 - Microsoft Internet Information Server, Version 2.0

Languages and compilers

- IBM C compiler, Version 3.6
- IBM C++ compiler, Version 3.6
- Microsoft Visual C++ for Windows 95 and NT, Version 5.0
- IBM VisualAge for C++ for Windows, Version 3.5
- IBM VisualAge C++ Professional, Version 4.0
- Micro Focus object COBOL for Windows NT, Version 3.3 or Version 4
- IBM VisualAge COBOL for Windows NT, Version 2.1
- IBM VisualAge COBOL Enterprise, Version 2.2
- IBM PL/I for Windows, Version 1.2
- IBM VisualAge for PL/I for Windows
- IBM VisualAge PL/I Enterprise, Version 2.1
- IBM VisualAge e-business for Windows, Version 1.0.1
- IBM VisualAge for Java Enterprise, Version 2.0
- IBM VisualAge for Java Professional, Version 2.0
- Visual Basic for Windows, Version 4.0 and 5.0

Delivery

MQSeries for Windows NT is supplied on CD-ROM. Two CD-ROMs are supplied; one containing the MQSeries for Windows NT server and client, and the other containing the other MQSeries clients shipped with MQSeries for Windows NT.

Installation

MQSeries for Windows NT is installed using the **setup** utility.

The installation can be performed in approximately 15 minutes. The actual time taken depends on several factors, including the following:

- The speed of the machine
- Which functions you are installing
- Where you are installing from

Customization of the product is then required, the duration of this process being dependent on the individual requirements of the enterprise.

Chapter 4, "Installing MQSeries for Windows NT" in the *MQSeries for Windows NT V5.1 Quick Beginnings* manual contains specific instructions for installing this product.

MQSeries client for Windows 3.1

This section summarizes the machine and software requirements for the Windows 3.1 client.

Client code for Windows 3.1 workstations is distributed with the server code for all servers except OS/390, OS/400, Tandem NSK, and VSE/ESA.

Machine requirements

An MQSeries client can run under Windows 3.1 on any personal computer that is capable of running the client code and which has sufficient storage to meet the combined requirements of the programming prerequisites, the client code, access methods, and the application programs.

Software requirements

Minimum supported software levels are shown. Later levels, if any, are supported unless otherwise stated.

- Microsoft Windows 3.1
- Microsoft Windows 95 in 16-bit mode
- WIN-OS2 environment within OS/2

Connectivity

- IBM TCP/IP for OS/2 base kit (part of the base operating system) and DOS/Windows access kit (allows clients access to TCP via programs that run under WIN-OS2)
- Novell NetWare Client for DOS/Win, Version 1.2
- Novell NetWare Client for OS/2, Version 2.1 (allows clients to access SPX via programs that run under WIN-OS2)
- Other TCPs:
 - PC-NSFPro
 - Sunsoft
 - OnNet SDK for Windows

Languages and compilers

The following compilers are supported:

- Microsoft C, Version 7.0
- Microsoft Visual C++, Version 1.5

MQSeries client for Windows 95 and Windows 98

This section summarizes the machine and software requirements for the MQSeries client for Windows 95 and Windows 98.

Client code for Windows 95 and Windows 98 workstations is distributed with the server code for all servers except OS/390, OS/400, Tandem NSK, and VSE/ESA.

Machine requirements

An MQSeries client can run under Windows 95 or Windows 98 on any personal computer that is capable of running the client code and which has sufficient storage to meet the combined requirements of the programming prerequisites, the client code, access methods, and the application programs.

Software requirements

Minimum supported software levels are shown. Later levels, if any, are supported unless otherwise stated.

- Windows 95
- Windows 98

Connectivity

TCP, SPX, and NetBIOS are all provided in the operating system.

Languages and compilers

The following compilers are supported:

- IBM VisualAge C++, Version 3.5
- Microsoft Visual C++, Version 4.0
- Micro Focus COBOL Workbench, Version 4.0

MQSeries link for R/3

This section tells you about the hardware and software you need to run MQSeries link for R/3.

Hardware requirements

To install and run this product, you need about 5 MB of available hard disk space. There are no additional hardware requirements except for those listed for MQSeries and R/3 on the platform you are using.

Software requirements

To run the R/3 link, you must have installed the following:

- At least one R/3 system, version 3.0E or later.
- At least one instance of MQSeries for the chosen platform.
- The relevant MQSeries link for R/3 product for the chosen platform.
- On Windows NT, the **librfc32.dll** file that is supplied with the SAPGUI component of R/3.

Restrictions

The amount of R/3 IDoc data that can be sent in a single message is limited by the maximum MQSeries message size. With MQSeries Version 5 the maximum message size is 100 MB and with earlier versions of MQSeries the maximum message size is 4 MB. Because the MQSeries link for R/3 header files are part of the space that is assigned to MQSeries messages, the actual space available for R/3 transaction data is less than the full 100 MB (or 4MB). R/3 transaction data can consist of one IDoc or batched IDocs.

SAP AG recommends a maximum of 2 MB for each IDoc.

Supported platforms

MQSeries link for R/3 is available for the following release levels of these platforms:

- AIX 4.1.4
- AS/400 4.2
- HP-UX 10.10
- Sun Solaris 2.5.1
- Windows NT 3.5.1 with service pack 5 installed

MQSeries platforms

Using R/3 link, you can connect your R/3 system to other platforms that run MQSeries.

Part 12. Appendix

Appendix. Notices

This information was developed for products and services offered in the United States. IBM may not offer the products, services, or features discussed in this information in other countries. Consult your local IBM representative for information on the products and services currently available in your area. Any reference to an IBM product, program, or service is not intended to state or imply that only that IBM product, program, or service may be used. Any functionally equivalent product, program, or service that does not infringe any IBM intellectual property right may be used instead. However, it is the user's responsibility to evaluate and verify the operation of any non-IBM product, program, or service.

IBM may have patents or pending patent applications covering subject matter described in this information. The furnishing of this information does not give you any license to these patents. You can send license inquiries, in writing, to:

| IBM Director of Licensing
| IBM Corporation
| North Castle Drive
| Armonk, NY 10504-1785
| U.S.A.

For license inquiries regarding double-byte (DBCS) information, contact the IBM Intellectual Property Department in your country or send inquiries, in writing, to:

IBM World Trade Asia Corporation
Licensing
2-31 Roppongi 3-chome, Minato-ku
Tokyo 106, Japan

The following paragraph does not apply to the United Kingdom or any other country where such provisions are inconsistent with local law:

INTERNATIONAL BUSINESS MACHINES CORPORATION PROVIDES THIS PUBLICATION "AS IS" WITHOUT WARRANTY OF ANY KIND, EITHER EXPRESS OR IMPLIED, INCLUDING, BUT NOT LIMITED TO, THE IMPLIED WARRANTIES OF NON-INFRINGEMENT, MERCHANTABILITY, OR FITNESS FOR A PARTICULAR PURPOSE. Some states do not allow disclaimer of express or implied warranties in certain transactions, therefore this statement may not apply to you.

This information could include technical inaccuracies or typographical errors. Changes are periodically made to the information herein; these changes will be incorporated in new editions of the information. IBM may make improvements and/or changes in the product(s) and/or the program(s) described in this information at any time without notice.

Any references in this information to non-IBM documentation or non-IBM Web sites are provided for convenience only and do not in any manner serve as an endorsement of those documents or Web sites. The materials for those documents or Web sites are not part of the materials for this IBM product and use of those documents or Web sites is at your own risk.

Licensees of this program who wish to have information about it for the purpose of enabling: (i) the exchange of information between independently created programs and other programs (including this one) and (ii) the mutual use of the information which has been exchanged, should contact:

IBM United Kingdom Laboratories,
Mail Point 151,
Hursley Park,
Winchester,
Hampshire,
England
SO21 2JN.

Such information may be available, subject to appropriate terms and conditions, including in some cases, payment of a fee.

The licensed program described in this information and all licensed material available for it are provided by IBM under terms of the IBM Customer Agreement, IBM International Programming License Agreement, or any equivalent agreement between us.

Trademarks

The following terms are trademarks of International Business Machines Corporation in the United States, or other countries, or both:

AIX	AS/400	BookManager
CICS	CICS/VSE	DB2
DB2 Universal Database	DFSMS	eNetwork
ESCON	ES/9000	HACMP/6000
IBM	IMS	IMS/ESA
Language Environment	MQSeries	Multiprise
MVS/ESA	NetView	Open Blueprint
OpenEdition	OS/2	OS/400
OS/390	POWERparallel	POWERserver
RACF	RMF	RS/6000
SupportPac	System/390	S/390 Parallel Enterprise Server
TXSeries	VisualAge	VM/ESA
VSE/ESA	VTAM	WIN-OS/2

Lotus, Lotus Notes, and Domino are trademarks of Lotus Development Corporation in the United States, or other countries, or both.

ENCINA is a trademark of Transarc Corporation in the United States, or other countries, or both.

Java and all Java-based trademarks and logos are trademarks or registered trademarks of Sun Microsystems, Inc. in the United States and/or other countries.

Microsoft, Windows, Windows NT, and the Windows logo are trademarks of Microsoft Corporation in the United States and/or other countries.

UNIX is a registered trademark in the United States and/or other countries licensed exclusively through X/Open Company Limited.

Other company, product, or service names, may be the trademarks or service marks of others.

Part 13. Glossary and Index

Glossary of terms and abbreviations

This glossary defines MQSeries terms and abbreviations used in this book. If you do not find the term you are looking for, see the Index or the *IBM Dictionary of Computing*, New York: McGraw-Hill, 1994.

This glossary includes terms and definitions from the *American National Dictionary for Information Systems*, ANSI X3.172-1990, copyright 1990 by the American National Standards Institute (ANSI). Copies may be purchased from the American National Standards Institute, 11 West 42 Street, New York, New York 10036. Definitions are identified by the symbol (A) after the definition.

A

active log. See *recovery log*.

adapter. An interface between MQSeries for OS/390 and TSO, IMS, CICS, or batch address spaces. An adapter is an attachment facility that enables applications to access MQSeries services.

address space. The area of virtual storage available for a particular job.

administrator commands. MQSeries commands used to manage MQSeries objects, such as queues, processes, and namelists.

alias queue object. An MQSeries object, the name of which is an alias for a base queue defined to the local queue manager. When an application or a queue manager uses an alias queue, the alias name is resolved and the requested operation is performed on the associated base queue.

alternate user security. A security feature in which the authority of one user ID can be used by another user ID; for example, to open an MQSeries object.

APAR. Authorized program analysis report.

application environment. The software facilities that are accessible by an application program. On the OS/390 platform, CICS and IMS are examples of application environments.

archive log. See *recovery log*.

| **ARM.** Automatic Restart Management

asynchronous messaging. A method of communication between programs in which programs place messages on message queues. With

asynchronous messaging, the sending program proceeds with its own processing without waiting for a reply to its message. Contrast with *synchronous messaging*.

attribute. One of a set of properties that defines the characteristics of an MQSeries object.

authorization service. In MQSeries on UNIX systems, MQSeries for OS/2 Warp, and MQSeries for Windows NT, a service that provides authority checking of commands and MQI calls for the user identifier associated with the command or call.

authorized program analysis report (APAR). A report of a problem caused by a suspected defect in a current, unaltered release of a program.

| **Automatic Restart Management (ARM).** An OS/390 recovery function that can improve the availability of specific batch jobs or started tasks, and therefore result in faster resumption of productive work.

B

backout. An operation that reverses all the changes made during the current unit of recovery or unit of work. After the operation is complete, a new unit of recovery or unit of work begins. Contrast with *commit*.

| **bag.** See *data bag*.

bootstrap data set (BSDS). A VSAM data set that contains:

- An inventory of all active and archived log data sets known to MQSeries for OS/390
- A wrap-around inventory of all recent MQSeries for OS/390 activity

The BSDS is required if the MQSeries for OS/390 subsystem has to be restarted.

browse. In message queuing, to use the MQGET call to copy a message without removing it from the queue. See also *get*.

browse cursor. In message queuing, an indicator used when browsing a queue to identify the message that is next in sequence.

BSDS. Bootstrap data set.

buffer pool. An area of main storage used for MQSeries for OS/390 queues, messages, and object definitions. See also *page set*.

C

CCSID. Coded character set identifier.

CDF. Channel definition file.

channel. See *message channel*.

channel definition file (CDF). In MQSeries, a file containing communication channel definitions that associate transmission queues with communication links.

channel event. An event indicating that a channel instance has become available or unavailable. Channel events are generated on the queue managers at both ends of the channel.

checkpoint. (1) A time when significant information is written on the log. Contrast with *syncpoint*. (2) In MQSeries on UNIX systems, the point in time when a data record described in the log is the same as the data record in the queue. Checkpoints are generated automatically and are used during the system restart process.

CI. Control interval.

circular logging. In MQSeries on UNIX systems, MQSeries for OS/2 Warp, and MQSeries for Windows NT, the process of keeping all restart data in a ring of log files. Logging fills the first file in the ring and then moves on to the next, until all the files are full. At this point, logging goes back to the first file in the ring and starts again, if the space has been freed or is no longer needed. Circular logging is used during restart recovery, using the log to roll back transactions that were in progress when the system stopped. Contrast with *linear logging*.

CL. Control Language.

client. A run-time component that provides access to queuing services on a server for local user applications. The queues used by the applications reside on the server. See also *MQSeries client*.

client application. An application, running on a workstation and linked to a client, that gives the application access to queuing services on a server.

| **cluster.** A network of queue managers that are
| logically associated in some way.

coded character set identifier (CCSID). The name of a coded set of characters and their code point assignments.

command. In MQSeries, an administration instruction that can be carried out by the queue manager.

command server. The MQSeries component that reads commands from the system-command input queue, verifies them, and passes valid commands to the command processor.

commit. An operation that applies all the changes made during the current unit of recovery or unit of work. After the operation is complete, a new unit of recovery or unit of work begins. Contrast with *backout*.

Common Run-Time Environment (CRE). A set of services that enable system and application programmers to write mixed-language programs. These shared, run-time services can be used by C, COBOL85, FORTRAN, Pascal, and TAL programs.

completion code. A return code indicating how an MQI call has ended.

connect. To provide a queue manager connection handle, which an application uses on subsequent MQI calls. The connection is made either by the MQCONN call, or automatically by the MQOPEN call.

context. Information about the origin of a message.

context security. In MQSeries, a method of allowing security to be handled such that messages are obliged to carry details of their origins in the message descriptor.

control command. In MQSeries on UNIX systems, MQSeries for OS/2 Warp, and MQSeries for Windows NT, a command that can be entered interactively from the operating system command line. Such a command requires only that the MQSeries product be installed; it does not require a special utility or program to run it.

control interval (CI). A fixed-length area of direct access storage in which VSAM stores records and creates distributed free spaces. The control interval is the unit of information that VSAM transmits to or from direct access storage.

Control Language (CL). In MQSeries for AS/400, a language that can be used to issue commands, either at the command line or by writing a CL program.

CRE. Common Run-Time Environment.

Cross Systems Coupling Facility (XCF). Provides the OS/390 coupling services that allow authorized programs in a multisystem environment to communicate with programs on the same or different OS/390 systems.

D

data bag. In the MQAI, a bag that allows you to handle properties (or parameters) of objects.

data conversion interface (DCI). The MQSeries interface to which customer- or vendor-written programs that convert application data between different machine encodings and CCSIDs must conform. A part of the MQSeries Framework.

DCE. Distributed Computing Environment.

DCI. Data conversion interface.

dead-letter queue (DLQ). A queue to which a queue manager or application sends messages that it cannot deliver to their correct destination.

dead-letter queue handler. An MQSeries-supplied utility that monitors a dead-letter queue (DLQ) and processes messages on the queue in accordance with a user-written rules table.

distributed application. In message queuing, a set of application programs that can each be connected to a different queue manager, but that collectively constitute a single application.

Distributed Computing Environment (DCE). Middleware that provides some basic services, making the development of distributed applications easier. DCE is defined by the Open Software Foundation (OSF).

distributed queue management (DQM). In message queuing, the setup and control of message channels to queue managers on other systems.

DLQ. Dead-letter queue.

DQM. Distributed queue management.

dual logging. A method of recording MQSeries for OS/390 activity, where each change is recorded on two data sets, so that if a restart is necessary and one data set is unreadable, the other can be used. Contrast with *single logging*.

dual mode. See *dual logging*.

dynamic queue. A local queue created when a program opens a model queue object. See also *permanent dynamic queue* and *temporary dynamic queue*.

E

environment. See *application environment*.

ESM. External security manager.

event. See *channel event*, *instrumentation event*, *performance event*, and *queue manager event*.

event data. In an event message, the part of the message data that contains information about the event (such as the queue manager name, and the application that gave rise to the event). See also *event header*.

event message. Contains information (such as the category of event, the name of the application that caused the event, and queue manager statistics) relating to the origin of an instrumentation event in a network of MQSeries systems.

event queue. The queue onto which the queue manager puts an event message after it detects an event. Each category of event (queue manager, performance, or channel event) has its own event queue.

external security manager (ESM). A security product that is invoked by the OS/390 System Authorization Facility. RACF is an example of an ESM.

F

FIFO. First-in-first-out.

first-in-first-out (FIFO). A queuing technique in which the next item to be retrieved is the item that has been in the queue for the longest time. (A)

Framework. In MQSeries, a collection of programming interfaces that allow customers or vendors to write programs that extend or replace certain functions provided in MQSeries products. The interfaces are:

- MQSeries data conversion interface (DCI)
- MQSeries message channel interface (MCI)
- MQSeries name service interface (NSI)
- MQSeries security enabling interface (SEI)
- MQSeries trigger monitor interface (TMI)

G

Generalized Trace Facility (GTF). An OS/390 service program that records significant system events, such as supervisor calls and start I/O operations, for the purpose of problem determination.

get. In message queuing, to use the MQGET call to remove a message from a queue. See also *browse*.

GTF. Generalized Trace Facility.

I

ICE. Intersystem Communications Environment is a family of Tandem-based software products that enables you to access a variety of applications on Tandem computers.

| **in-doubt unit of recovery.** In MQSeries, the status of
| a unit of recovery for which a syncpoint has been
| requested but not yet confirmed.

initialization input data sets. Data sets used by MQSeries for OS/390 when it starts up.

initiation queue. A local queue on which the queue manager puts trigger messages.

installable services. In MQSeries on UNIX systems, MQSeries for OS/2 Warp, and MQSeries for Windows NT, additional functionality provided as independent components. The installation of each component is optional: in-house or third-party components can be used instead. See also *authorization service*, *name service*, and *user identifier service*.

instrumentation event. A facility that can be used to monitor the operation of queue managers in a network of MQSeries systems. MQSeries provides instrumentation events for monitoring queue manager resource definitions, performance conditions, and channel conditions. Instrumentation events can be used by a user-written reporting mechanism in an administration application that displays the events to a system operator. They also allow applications acting as agents for other administration networks to monitor reports and create the appropriate alerts.

Interactive System Productivity Facility (ISPF). An IBM licensed program that serves as a full-screen editor and dialog manager. It is used for writing application programs, and provides a means of generating standard screen panels and interactive dialogues between the application programmer and terminal user.

| **Internet Protocol (IP).** A protocol used to route data
| from its source to its destination in an Internet
| environment. This is the base layer, on which other
| protocol layers, such as TCP and UDP are built.

| **IP.** Internet Protocol.

ISPF. Interactive System Productivity Facility.

L

linear logging. In MQSeries on UNIX systems, MQSeries for OS/2 Warp, and MQSeries for Windows NT, the process of keeping restart data in a sequence of files. New files are added to the sequence as necessary. The space in which the data is written is not reused until the queue manager is restarted. Contrast with *circular logging*.

listener. In MQSeries distributed queuing, a program that monitors for incoming network connections.

local definition. An MQSeries object belonging to a local queue manager.

local definition of a remote queue. An MQSeries object belonging to a local queue manager. This object defines the attributes of a queue that is owned by another queue manager. In addition, it is used for queue-manager aliasing and reply-to-queue aliasing.

local queue. A queue that belongs to the local queue manager. A local queue can contain a list of messages waiting to be processed. Contrast with *remote queue*.

local queue manager. The queue manager to which a program is connected and that provides message queuing services to the program. Queue managers to which a program is not connected are called *remote queue managers*, even if they are running on the same system as the program.

| **log.** In MQSeries, a file recording the work done by
| queue managers while they receive, transmit, and
| deliver messages, to enable them to recover in the
| event of failure.

log control file. In MQSeries on UNIX systems, MQSeries for OS/2 Warp, and MQSeries for Windows NT, the file containing information needed to monitor the use of log files (for example, their size and location, and the name of the next available file).

log file. In MQSeries on UNIX systems, MQSeries for OS/2 Warp, and MQSeries for Windows NT, a file in which all significant changes to the data controlled by a queue manager are recorded. If the primary log files become full, MQSeries allocates secondary log files.

logical unit of work (LUW). See *unit of work*.

LU 6.2. A type of logical unit (LU) that supports general communication between programs in a distributed processing environment.

M

MCA. Message channel agent.

MCI. Message channel interface.

message. (1) In message queuing applications, a communication sent between programs. See also *persistent message* and *nonpersistent message*. (2) In system programming, information intended for the terminal operator or system administrator.

message channel. In distributed message queuing, a mechanism for moving messages from one queue manager to another. A message channel comprises two message channel agents (a sender at one end and a receiver at the other end) and a communication link. Contrast with *MQI channel*.

message channel agent (MCA). A program that transmits prepared messages from a transmission queue to a communication link, or from a communication link to a destination queue. See also *message queue interface*.

message channel interface (MCI). The MQSeries interface to which customer- or vendor-written programs that transmit messages between an MQSeries queue manager and another messaging system must conform. A part of the MQSeries Framework.

message descriptor. Control information describing the message format and presentation that is carried as part of an MQSeries message. The format of the message descriptor is defined by the MQMD structure.

message priority. In MQSeries, an attribute of a message that can affect the order in which messages on a queue are retrieved, and whether a trigger event is generated.

message queue. Synonym for *queue*.

message queue interface (MQI). The programming interface provided by the MQSeries queue managers. This programming interface allows application programs to access message queuing services.

message queuing. A programming technique in which each program within an application communicates with the other programs by putting messages on queues.

messaging. See *synchronous messaging* and *asynchronous messaging*.

model queue object. A set of queue attributes that act as a template when a program creates a dynamic queue.

MQAI. MQSeries Administration Interface.

MQI. Message queue interface.

MQI channel. Connects an MQSeries client to a queue manager on a server system, and transfers only MQI calls and responses in a bidirectional manner. Contrast with *message channel*.

MQSC. MQSeries commands.

MQSeries. A family of IBM licensed programs that provides message queuing services.

MQSeries Administration Interface (MQAI). A programming interface to MQSeries.

MQSeries client. Part of an MQSeries product that can be installed on a system without installing the full queue manager. The MQSeries client accepts MQI calls from applications and communicates with a queue manager on a server system.

MQSeries commands (MQSC). Human readable commands, uniform across all platforms, that are used to manipulate MQSeries objects. Contrast with *programmable command format (PCF)*.

N

namelist. An MQSeries object that contains a list of names, for example, queue names.

name service. In MQSeries on UNIX systems, MQSeries for OS/2 Warp, and MQSeries for Windows NT, the facility that determines which queue manager owns a specified queue.

name service interface (NSI). The MQSeries interface to which customer- or vendor-written programs that resolve queue-name ownership must conform. A part of the MQSeries Framework.

NetBIOS. Network Basic Input/Output System. An operating system interface for application programs used on IBM personal computers that are attached to the IBM Token-Ring Network.

nonpersistent message. A message that does not survive a restart of the queue manager. Contrast with *persistent message*.

NSI. Name service interface.

O

OAM. Object authority manager.

object. In MQSeries, an object is a queue manager, a queue, a process definition, a channel, a namelist, or a storage class (OS/390 only).

object authority manager (OAM). In MQSeries on UNIX systems and MQSeries for Windows NT, the default authorization service for command and object management. The OAM can be replaced by, or run in combination with, a customer-supplied security service.

Open Transaction Manager Access (OTMA). A transaction-based, connectionless client/server protocol. It functions as an interface for host-based communications servers accessing IMS TM applications through the OS/390 Cross Systems Coupling Facility (XCF). OTMA is implemented in an OS/390 sysplex environment. Therefore, the domain of OTMA is restricted to the domain of XCF.

OTMA. Open Transaction Manager Access.

output log-buffer. In MQSeries for OS/390, a buffer that holds recovery log records before they are written to the archive log.

P

page set. A VSAM data set used when MQSeries for OS/390 moves data (for example, queues and messages) from buffers in main storage to permanent backing storage (DASD).

PCF. Programmable command format.

PCF command. See *programmable command format*.

performance event. A category of event indicating that a limit condition has occurred.

persistent message. A message that survives a restart of the queue manager. Contrast with *nonpersistent message*.

ping. In distributed queuing, a diagnostic aid that uses the exchange of a test message to confirm that a message channel or a TCP/IP connection is functioning.

platform. In MQSeries, the operating system under which a queue manager is running.

point of recovery. In MQSeries for OS/390, the term used to describe a set of backup copies of MQSeries

for OS/390 page sets and the corresponding log data sets required to recover these page sets. These backup copies provide a potential restart point in the event of page set loss (for example, page set I/O error).

principal. In MQSeries on UNIX systems, MQSeries for OS/2 Warp, and MQSeries for Windows NT, a term used for a user identifier. Used by the object authority manager for checking authorizations to system resources.

process definition object. An MQSeries object that contains the definition of an MQSeries application. For example, a queue manager uses the definition when it works with trigger messages.

programmable command format (PCF). A type of MQSeries message used by:

- User administration applications, to put PCF commands onto the system command input queue of a specified queue manager
- User administration applications, to get the results of a PCF command from a specified queue manager
- A queue manager, as a notification that an event has occurred

Contrast with *MQSC*.

program temporary fix (PTF). A solution or by-pass of a problem diagnosed by IBM field engineering as the result of a defect in a current, unaltered release of a program.

PTF. Program temporary fix.

Q

queue. An MQSeries object. Message queuing applications can put messages on, and get messages from, a queue. A queue is owned and maintained by a queue manager. Local queues can contain a list of messages waiting to be processed. Queues of other types cannot contain messages—they point to other queues, or can be used as models for dynamic queues.

queue manager. (1) A system program that provides queuing services to applications. It provides an application programming interface so that programs can access messages on the queues that the queue manager owns. See also *local queue manager* and *remote queue manager*. (2) An MQSeries object that defines the attributes of a particular queue manager.

queuing. See *message queuing*.

R

RBA. Relative byte address.

reason code. A return code that describes the reason for the failure or partial success of an MQI call.

recovery log. In MQSeries for OS/390, data sets containing information needed to recover messages, queues, and the MQSeries subsystem. MQSeries for OS/390 writes each record to a data set called the *active log*. When the active log is full, its contents are off-loaded to a DASD or tape data set called the *archive log*. Synonymous with *log*.

relative byte address (RBA). The displacement in bytes of a stored record or control interval from the beginning of the storage space allocated to the data set to which it belongs.

remote queue. A queue belonging to a remote queue manager. Programs can put messages on remote queues, but they cannot get messages from remote queues. Contrast with *local queue*.

remote queue manager. To a program, a queue manager that is not the one to which the program is connected.

remote queue object. See *local definition of a remote queue*.

remote queuing. In message queuing, the provision of services to enable applications to put messages on queues belonging to other queue managers.

reply message. A type of message used for replies to request messages.

request message. A type of message used to request a reply from another program.

RESLEVEL. In MQSeries for OS/390, an option that controls the number of CICS user IDs checked for API-resource security in MQSeries for OS/390.

resource. Any facility of the computing system or operating system required by a job or task. In MQSeries for OS/390, examples of resources are buffer pools, page sets, log data sets, queues, and messages.

resource manager. An application, program, or transaction that manages and controls access to shared resources such as memory buffers and data sets. MQSeries, CICS, and IMS are resource managers.

Resource Recovery Services (RRS). An OS/390 facility that provides 2-phase syncpoint support across participating resource managers.

return codes. The collective name for completion codes and reason codes.

rollback. Synonym for *back out*.

RRS. Resource Recovery Services.

S

SAF. System Authorization Facility.

security enabling interface (SEI). The MQSeries interface to which customer- or vendor-written programs that check authorization, supply a user identifier, or perform authentication must conform. A part of the MQSeries Framework.

SEI. Security enabling interface.

server. (1) In MQSeries, a queue manager that provides queue services to client applications running on a remote workstation. (2) The program that responds to requests for information in the particular two-program, information-flow model of client/server. See also *client*.

signaling. In MQSeries for OS/390 and MQSeries for Windows 2.1, a feature that allows the operating system to notify a program when an expected message arrives on a queue.

single logging. A method of recording MQSeries for OS/390 activity where each change is recorded on one data set only. Contrast with *dual logging*.

single-phase backout. A method in which an action in progress must not be allowed to finish, and all changes that are part of that action must be undone.

single-phase commit. A method in which a program can commit updates to a queue without coordinating those updates with updates the program has made to resources controlled by another resource manager. Contrast with *two-phase commit*.

SNA. Systems Network Architecture.

SPX. Sequenced Packet Exchange transmission protocol.

storage class. In MQSeries for OS/390, a storage class defines the page set that is to hold the messages for a particular queue. The storage class is specified when the queue is defined.

subsystem. In OS/390, a group of modules that provides function that is dependent on OS/390. For example, MQSeries for OS/390 is an OS/390 subsystem.

synchronous messaging. A method of communication between programs in which programs place messages on message queues. With synchronous messaging, the sending program waits for a reply to its message before resuming its own processing. Contrast with *asynchronous messaging*.

syncpoint. An intermediate or end point during processing of a transaction at which the transaction's protected resources are consistent. At a syncpoint, changes to the resources can safely be committed, or they can be backed out to the previous syncpoint.

System Authorization Facility (SAF). An OS/390 facility through which MQSeries for OS/390 communicates with an external security manager such as RACF.

system.command.input queue. A local queue on which application programs can put MQSeries commands. The commands are retrieved from the queue by the command server, which validates them and passes them to the command processor to be run.

system control commands. Commands used to manipulate platform-specific entities such as buffer pools, storage classes, and page sets.

Systems Network Architecture (SNA). The description of the logical structure, formats, protocols, and operational sequences for transmitting information units through, and controlling the configuration and operation of, networks.

T

TACL. Tandem Advanced Command Language.

| **TCP.** Transmission Control Protocol.

| **TCP/IP.** Transmission Control Protocol/Internet Protocol.

thread. In MQSeries, the lowest level of parallel execution available on an operating system platform.

time-independent messaging. See *asynchronous messaging*.

TMF. Transaction Management Facility.

TMI. Trigger monitor interface.

TM/MP. NonStop Transaction Manager/MP.

trace. In MQSeries, a facility for recording MQSeries activity. The destinations for trace entries can include GTF and the system management facility (SMF). See also *global trace* and *performance trace*.

| **Transmission Control Protocol (TCP).** Part of the TCP/IP protocol suite. A host-to-host protocol between hosts in packet-switched communications networks. TCP provides connection-oriented data stream delivery. Delivery is reliable and orderly.

| **Transmission Control Protocol/Internet Protocol (TCP/IP).** A suite of communication protocols that support peer-to-peer connectivity functions for both local and wide area networks.

transmission program. See *message channel agent*.

transmission queue. A local queue on which prepared messages destined for a remote queue manager are temporarily stored.

trigger event. An event (such as a message arriving on a queue) that causes a queue manager to create a trigger message on an initiation queue.

triggering. In MQSeries, a facility allowing a queue manager to start an application automatically when predetermined conditions on a queue are satisfied.

trigger message. A message containing information about the program that a trigger monitor is to start.

trigger monitor. A continuously-running application serving one or more initiation queues. When a trigger message arrives on an initiation queue, the trigger monitor retrieves the message. It uses the information in the trigger message to start a process that serves the queue on which a trigger event occurred.

trigger monitor interface (TMI). The MQSeries interface to which customer- or vendor-written trigger monitor programs must conform. A part of the MQSeries Framework.

two-phase commit. A protocol for the coordination of changes to recoverable resources when more than one resource manager is used by a single transaction. Contrast with *single-phase commit*.

U

| **UDP.** User Datagram Protocol.

UIS. User identifier service.

undelivered-message queue. See *dead-letter queue*.

unit of recovery. A recoverable sequence of operations within a single resource manager. Contrast with *unit of work*.

unit of work. A recoverable sequence of operations performed by an application between two points of consistency. A unit of work begins when a transaction

starts or after a user-requested syncpoint. It ends either at a user-requested syncpoint or at the end of a transaction. Contrast with *unit of recovery*.

| **User Datagram Protocol (UDP).** Part of the TCP/IP
| protocol suite. A packet-level protocol built directly on
| the Internet Protocol layer. UDP is a connectionless
| and less reliable alternative to TCP. It is used for
| application-to-application programs between TCP/IP
| host systems.

user identifier service (UIS). In MQSeries for OS/2 Warp, the facility that allows MQI applications to

associate a user ID, other than the default user ID, with MQSeries messages.

utility. In MQSeries, a supplied set of programs that provide the system operator or system administrator with facilities in addition to those provided by the MQSeries commands. Some utilities invoke more than one function.

X

XCF. Cross Systems Coupling Facility.

Index

Numerics

- 1-phase commit 29
- 2-phase commit 29
- 3990 channel adaptor (OS/390) 147
- 3990 fast write (OS/390) 147

A

- access permission
 - MQSeries for Digital OpenVMS 89
 - MQSeries for Tandem NSK 162
 - MQSeries on UNIX systems 179
- accounting data (OS/390) 139
- Active Directory Service Interfaces (ADSI) 208
- active log (OS/390) 124, 142
- add log data sets (OS/390) 140
- administration
 - application programs 36
 - facilities 36
 - interface 37
 - MQAI 37
 - MQSeries for AS/400 73
 - MQSeries for Digital OpenVMS 83, 93
 - MQSeries for OS/2 Warp 103, 111
 - MQSeries for OS/390 137
 - MQSeries for Tandem NSK 157, 165
 - MQSeries for VSE/ESA 191
 - MQSeries for Windows NT 198, 207
 - MQSeries on UNIX systems 173, 183
 - of MQSeries Version 1 products 37
 - utility (OS/400) 75
- ADSI (Active Directory Service Interfaces) 208
- AIX
 - at a glance 232
- alias 16
- alias queue 11, 17
- alternate user security (OS/390) 134
- API crossing exit, platform support 229
- application data 5
- application data conversion 17
- application-specified syncpoint, platform support 228
- applications
 - administration programs 36
 - data conversion 17
 - preparing for use with MQSeries for AS/400 66
 - preparing for use with MQSeries for Digital OpenVMS 82
 - preparing for use with MQSeries for OS/2 Warp 101
 - preparing for use with MQSeries for OS/390 118
 - preparing for use with MQSeries for Tandem NSK 155

- applications (*continued*)
 - preparing for use with MQSeries for VSE/ESA 189
 - preparing for use with MQSeries for Windows NT 196
 - preparing for use with MQSeries on UNIX systems 170
 - time-independent 4
- applications on MQSeries clients
 - non-version 5 53
 - version 5 53
- archive log (OS/390) 142
- archive log data sets (OS/390) 125, 127
- archive storage (OS/390) 142
- assured delivery 18
- AT&T GIS UNIX 236
- attributes of messages 6
- authentication procedures 22
- authorization
 - commands (Digital OpenVMS) 90
 - commands (Tandem NSK) 163
 - commands (UNIX) 180
 - groups (UNIX) 180
 - object authority manager 59
 - rights identifiers (Digital OpenVMS) 90
 - service 58
- availability (OS/390) 127

B

- back out 27, 28
- backing up logs, frequency (OS/390) 130
- backup (OS/390) 127
- backup, restore, and reorganize utility (OS/390) 139
- bibliography xiv
- BookManager xix
- bootstrap data set (BSDS) (OS/390)
 - copies 125
 - dual mode 125
 - introduction 125
 - storage 142, 143
- browse under cursor, platform support 228
- browse with lock, platform support 228
- browse, platform support 228
- BSDS (bootstrap data set) (OS/390)
 - copies 125
 - dual mode 125
 - introduction 125
 - storage 142
- buffer pools and buffers (OS/390) 123

C

- capacity planning
 - Digital OpenVMS 97
 - OS/2 Warp 114
 - OS/390 141
 - OS/400 77
 - UNIX systems 186
 - Windows NT 212
- CCSID (coded character set identifier)
 - changing
 - MQSeries for AIX 174
 - MQSeries for HP-UX 174
 - MQSeries for Sun Solaris 174
 - OS/2 Warp 104
 - Windows NT 199
 - distributed queuing 17
- change log inventory utility (OS/390) 140
- channel
 - commands 40
 - events 46
 - introduction 13
 - speed 16
- channel auto-definition, platform support 229
- channel heartbeats, platform support 229
- checkpoint records (OS/390) 126
- CICS
 - bridge 119
 - interface
 - MQSeries for AS/400 66
 - MQSeries for OS/2 Warp 102
 - MQSeries for OS/390 118
 - MQSeries for Windows NT 196
 - MQSeries on UNIX systems 171
 - product support 28
 - recovery (OS/390) 128
- CICS ISC, MQSeries for OS/390 119
- circular logging
 - MQSeries for Digital OpenVMS 85
 - MQSeries for OS/2 Warp 106
 - MQSeries for Windows NT 202
 - MQSeries on UNIX systems 176
- CL commands (OS/400) 73
- client
 - attachment feature (OS/390) 244
 - channels 14
 - communication with servers 50
 - data conversion 51
 - description 49
 - installation 51
 - introduction 14
 - MQSeries for Windows 216
 - national language considerations 51
 - other platforms 53
 - platform support 52
 - transmission protocols 227
- client definitions, migrating 53
- cluster
 - commands 41
 - illustration 19
 - introduction 19
 - platform support 229
 - repository 8
 - support queues 8
- COA & COD reports, platform support 228
- coded character set identifier (CCSID)
 - changing
 - MQSeries for AIX 174
 - MQSeries for HP-UX 174
 - MQSeries for Sun Solaris 174
 - OS/2 Warp 104
 - Windows NT 199
 - distributed queuing 17
- command
 - formats 34
 - introduction 33
 - messages 35
 - MQSC 34
 - PCF 34
 - queue 8, 35
 - resource security (OS/390) 134
 - security (Digital OpenVMS) 90
 - security (Tandem NSK) 163
 - security (UNIX) 180
 - server 35
 - summary 38
- commit
 - 1-phase 29
 - 2-phase 29
 - single phase 29
- commit point 27
- communication
 - between clients and servers 50
 - managing (Digital OpenVMS) 94
 - managing (OS/2 Warp) 111
 - managing (Tandem NSK) 166
 - managing (UNIX) 184
 - managing (Windows NT) 208
- communication between queue managers 15
- communication protocol 226
- communications link 16
- compilers supported
 - MQSeries for AIX 234
 - MQSeries for AS/400 235
 - MQSeries for AT&T GIS UNIX 236
 - MQSeries for HP-UX 240
 - MQSeries for OS/2 Warp 242
 - MQSeries for OS/390 243
 - MQSeries for SINIX and DC/OSx 246
 - MQSeries for Sun Solaris 248
 - MQSeries for Tandem NSK 249
 - MQSeries for UnixWare 252

- compilers supported (*continued*)
 - MQSeries for VSE/ESA 254
 - MQSeries for Windows NT 260
 - MQSeries for Windows Version 2.0 256
 - MQSeries for Windows Version 2.1 257
 - MQSeries on DOS clients 238
 - MQSeries on VM/ESA clients 253
 - MQSeries on Windows 3.1 Clients 262
 - MQSeries on Windows 95 Clients 263
 - MQSeries on Windows 98 Clients 263
- concurrent use-based pricing 67
- connection security (OS/390) 134
- consistency 29
- consistent data 27
- context security (OS/390) 134
- context, platform support 228
- continuous operation, recovery planning (OS/390) 127
- control language (OS/400) 73
- converting data from other MQSeries platforms 17
- CSA storage requirement (OS/390) 141
- CSQ1LOGP log print utility (OS/390) 140
- CSQJU003 change log inventory (OS/390) 140
- CSQJU004 print log map utility (OS/390) 140
- CSQUTIL (OS/390) 139
 - backup 139
 - process object definitions 139
 - reorganize 139
 - restore 139
- customization of MQSeries for OS/390 121

D

- data conversion 17
 - clients 51
 - exit utility (OS/390) 140
- data conversion interface (DCI) 60
- Data Facility Hierarchical Storage Manager (DFHSM) (OS/390) 128
- data management (OS/390) 128
- data recovery (OS/390) 128
- data security planning
 - MQSeries for Digital OpenVMS 83
 - MQSeries for OS/2 Warp 103
 - MQSeries for Tandem NSK 157
 - MQSeries for VSE/ESA 191
 - MQSeries for Windows NT 198
 - MQSeries on UNIX systems 172
- data sets (OS/390)
 - archive data set types 127
 - archive log, description 127
- DB2 30
- DC/OSx
 - See MQSeries for SINIX and DC/OSx
- DCE naming component 58
- DCI (data conversion interface) 60
- dead-letter queue
 - introduction 8
 - platform support 228
- DECnet, platform support 226
- default input open option, platform support 228
- default transmission queue, platform support 228
- delete log data sets (OS/390) 140
- deleting journal receivers (OS/400) 69
- delivery
 - MQSeries for AIX 234
 - MQSeries for AS/400 235
 - MQSeries for AT&T GIS UNIX 236
 - MQSeries for Digital OpenVMS 237
 - MQSeries for HP-UX 240
 - MQSeries for OS/2 Warp 242
 - MQSeries for OS/390 244
 - MQSeries for SINIX and DC/OSx 246
 - MQSeries for Sun Solaris 248
 - MQSeries for Tandem NSK 249
 - MQSeries for UnixWare 252
 - MQSeries for VSE/ESA 254
 - MQSeries for Windows NT 261
 - MQSeries for Windows Version 2.0 256
 - MQSeries for Windows Version 2.1 258
 - MQSeries on VM/ESA clients 253
- DFHSM (Data Facility Hierarchical Storage Manager) (OS/390) 128
- Digital OpenVMS
 - administration 93
 - backup and recovery 85
 - introduction 81
 - security 89
 - storage 95
- disabling events 47
- disaster recovery (OS/390) 130
- disk mirroring 178
- disk space requirements
 - MQSeries for Digital OpenVMS 95
 - MQSeries for OS/2 Warp 113
 - MQSeries for Windows NT 211
 - MQSeries on UNIX systems 185
- distributed queuing 15
 - clusters 19
 - error recovery 18
 - introduction 15
 - MQSeries for AS/400 66
 - MQSeries for Digital OpenVMS 82
 - MQSeries for OS/2 Warp 102
 - MQSeries for OS/390 119
 - MQSeries for Tandem NSK 156
 - MQSeries for VSE/ESA 189
 - MQSeries for Windows NT 196
 - MQSeries on UNIX systems 171
 - security 24
- distribution library storage (OS/390) 143

Index

- distribution list
 - introduction 12
 - platform support 228
- DOS client 238
- DQM
 - See distributed queuing
- dspmqaout command
 - MQSeries for Digital OpenVMS 90
 - MQSeries for Tandem NSK 163
 - MQSeries on UNIX systems 180
- dual BSDS (OS/390) 125, 143
- dual logging (OS/390)
 - archive log data sets 127
 - establishing 127
 - introduction 124
 - performance 146
- dual mode (OS/390) 125
- dynamic queue 11
- dynamic queues, platform support 228

E

- ECSA storage requirement (OS/390) 141
- enabling events 47
- Encina 28
- end-to-end security 25
- environment user ID 59
- error messages 18
- error recovery in distributed queuing 18
- euro symbol
 - MQSeries for OS/2 Warp 104
 - MQSeries for Windows NT 199
 - MQSeries on UNIX systems 174
- event
 - description 45
 - enabling and disabling 47
 - introduction 45
 - message format 48
 - message lost 47
 - notification 46
 - platform support 229
 - types of 46
- event queue 7
 - event notification 46
 - triggered 47
 - unavailable 47
- exception reports with data, platform support 228
- exception reports, platform support 228
- exits, security
 - MQSeries for Digital OpenVMS 91
 - MQSeries for OS/2 Warp 109
 - MQSeries for Tandem NSK 163
 - MQSeries for Windows NT 206
 - MQSeries on UNIX systems 181
- extended recovery facility (OS/390) 129

- external transaction manager
 - MQSeries for OS/2 Warp 107
 - MQSeries for Windows NT 203
 - MQSeries on UNIX systems 177

F

- family differences
 - MQSeries for Windows 219
- fast channel
 - introduction 16
 - platform support 229
- fast write (OS/390) 147
- features of MQSeries for Windows 218
- format of event messages 48
- framework 55
- frequency of backing up logs (OS/390) 130
- function comparison table 228
- functional levels xiii

G

- get by Msgld & Correlld, platform support 228
- get with signal, platform support 228
- glossary 273
- GO LICPGM (OS/400) 68

H

- HACMP (High Availability Cluster Multi-Processing) 178
- header information (OS/390) 142
- High Availability Cluster Multi-Processing (HACMP) 178
- HP-UX
 - See MQSeries for HP-UX
- HTML (Hypertext Markup Language) xix
- Hypertext Markup Language (HTML) xix

I

- I/O response times (OS/390) 147
- ICF (integrated catalog facility) (OS/390) 124
- identification procedures 22
- IMS
 - bridge 118
 - recovery 128
- initiation queue 7
- installation verification program (OS/390) 122
- installing
 - clients 51
 - MQSeries for AS/400 68
 - MQSeries for Digital OpenVMS 82
 - MQSeries for OS/2 Warp 102
 - MQSeries for OS/390 121
 - MQSeries for Tandem NSK 156
 - MQSeries for VSE/ESA 190

- installing (*continued*)
 - MQSeries on UNIX systems 171
- instrumentation event
 - description 45
 - enabling and disabling 47
 - introduction 45
 - product support for 45
 - types of 46
- integrated catalog facility (ICF) (OS/390) 124
- interface with CICS
 - MQSeries for AS/400 66
 - MQSeries for OS/2 Warp 102
 - MQSeries for Windows NT 196
 - MQSeries on UNIX systems 171
- interfacing with CICS, IMS, and batch 118
- Internet 53
- Internet, installing clients from 51
- interoperability summary 226
- introduction 34
- introduction to MQSeries 3
- invoking framework components 56
- IVP (OS/390) 122

J

- journal receiver (OS/400) 69, 77
- journal storage (OS/400) 77
- journaling (OS/400) 67, 69

L

- languages
 - See programming languages
- large messages 6
- LDAP (Lightweight Directory Access Protocol) 196
- leaf node, MQSeries for Windows 216
- level 1 products, list xiii
- level 2 products, list xiv
- library storage (OS/390) 143
- Lightweight Directory Access Protocol (LDAP) 196
- linear logging
 - MQSeries for Digital OpenVMS 85
 - MQSeries for OS/2 Warp 106
 - MQSeries for Windows NT 202
 - MQSeries on UNIX systems 176
- local queue manager 15
- local queue object 11
- log (OS/390)
 - archive log 124
 - data sets 124, 140
 - dual logging 124, 146
 - dual, establishing 127
 - establishing logging 127
 - extents 142
 - introduction 124
 - logging environment 127

- log (OS/390) (*continued*)
 - map print utility 140
 - performance 145
 - print log map utility 140
 - print log utility 140
 - single logging 124, 145
 - storage 142
- log file storage
 - MQSeries for OS/2 Warp 114
 - MQSeries for Windows NT 212
 - required for MQSeries for Digital OpenVMS 96
 - required for MQSeries on UNIX systems 186
- log print utility (OS/390) 140
- log records utility (OS/390)
 - extract log records 140
 - print log records 140
- logging
 - MQSeries for Digital OpenVMS 83, 85
 - MQSeries for OS/2 Warp 103, 105
 - MQSeries for Windows 219
 - MQSeries for Windows NT 197, 201
 - MQSeries on UNIX systems 172, 175
- LU 6.2
 - MQSeries for AS/400 66
 - MQSeries for Digital OpenVMS 82
 - MQSeries for OS/2 Warp 102
 - MQSeries for OS/390 119
 - MQSeries for Tandem NSK 156
 - MQSeries for VSE/ESA 189
 - MQSeries on UNIX systems 171
 - platform support 226

M

- machine requirements
 - client on DOS 238
 - client on VM/ESA 253
 - client on Windows 3.1 262
 - client on Windows 95 263
 - client on Windows 98 263
 - MQSeries for Digital OpenVMS 237
 - MQSeries link for R/3 264
- maintaining consistency after errors 29
- managing remote links
 - MQSeries for AS/400 66
 - MQSeries for Digital OpenVMS 82
 - MQSeries for OS/2 Warp 102
 - MQSeries for OS/390 119
 - MQSeries for Tandem NSK 156
 - MQSeries for Windows NT 196
 - MQSeries on UNIX systems 171
- mark skip backout, platform support 228
- maximum message length, platform support 228
- maximum message size 6
- maximum queue size, platform support 228

Index

- MCA (message channel agent)
 - exits 59
 - introduction 16
- MCI (message channel interface) 57
- measured usage license charges (MULC) 151
- media recovery and logging, MQSeries for
 - Windows 219
- message
 - attributes 6
 - channels 13
 - description 5
 - event, format of 48
 - large 6
 - maximum number (OS/390) 142
 - persistent 6
 - priority 6
 - reference 7
 - segmented 7
 - size of 6
- message backout count, platform support 228
- message channel 13
 - exits, platform support 229
 - transmission protocols 226
- message channel agent (MCA)
 - exits 59
 - introduction 16
- message channel interface (MCI) 57
- message data conversion, platform support 228
- message descriptor 5
- message expiry, platform support 228
- message priority, platform support 228
- message queue 7
- message queue interface (MQI)
 - introduction 3
 - list of calls 3
- message queuing 3
- message retry exit, platform support 229
- message storage (OS/390) 143
- message-driven processing 4
- Microsoft Option Pack 195
- migration
 - client definitions 53
 - euro symbol
 - MQSeries for AIX 174
 - MQSeries for HP-UX 174
 - MQSeries for Sun Solaris 174
 - OS/2 Warp 104
 - Windows NT 199
 - from MQSeries Version 1
 - Digital OpenVMS 84
 - Tandem NSK 158
 - UNIX systems 173
 - from MQSeries Version 1.4
 - VSE/ESA 191
 - from MQSeries version 2 53
 - clients 53
 - OS/2 Warp 104
- migration (*continued*)
 - from MQSeries version 2 (*continued*)
 - UNIX systems 174
 - Windows NT 198
 - OS/390 122
- MMC snap-in applications, Windows NT 207
- model queue object 11
- model queues, platform support 228
- monitoring performance (OS/390) 150
- monitoring queue managers 45
- MQADMIN user ID (Windows NT) 206
- MQAI (MQSeries administration interface) 37
- MQBACK, platform support 229
- MQBEGIN, platform support 229
- MQCLOSE, platform support 228
- MQCMIT, platform support 229
- MQCONN, platform support 228
- MQDISC, platform support 228
- MQGET, platform support 228
- MQI (message queue interface)
 - introduction 3
 - list of calls 3
- MQI channel
 - description 50
 - introduction 14
 - transmission protocol 227
- MQINQ, platform support 229
- MQOPEN, platform support 228
- MQPUT, platform support 228
- MQSC commands
 - MQSeries for AS/400 73
 - MQSeries for Digital OpenVMS 93
 - MQSeries for OS/2 Warp 111
 - MQSeries for OS/390 137
 - MQSeries for Tandem NSK 165
 - MQSeries for Windows 219
 - MQSeries for Windows NT 208
 - MQSeries on UNIX systems 183
- MQSC commands, platform support 229
- MQSeries administration interface (MQAI) 37
- MQSeries and R/3
 - AS/400 67
 - UNIX systems 173
 - Windows NT 198
- MQSeries as a transaction manager 30
- MQSeries commands
 - Digital OpenVMS 93
 - introduction 33
 - MQSC 34
 - OS/2 Warp 111
 - OS/390 137
 - OS/400 73
 - PCF 34
 - summary of 38
 - Tandem NSK 165
 - UNIX systems 183

MQSeries commands (*continued*)

Windows NT 208

MQSeries Explorer (Windows NT) 207

MQSeries for AIX

See also MQSeries on UNIX systems

administration interface 37

compilers supported 234

distribution 234

euro symbol 174

installation 234

link for R/3 173

machine requirements 232

maximum queue size 228

software requirements 232

web functions 233

MQSeries for AS/400

administration 73

backup and recovery 69

CICS interface 66

compilers supported 235

concurrent use-based pricing 67

distribution 235

installation 235

introduction 65

machine requirements 235

maximum queue size 228

security 71

software requirements 235

storage 77

using C++ 66

MQSeries for AT&T GIS UNIX

See also MQSeries on UNIX systems

compilers supported 236

distribution 236

installation 236

machine requirements 236

maximum queue size 228

software requirements 236

MQSeries for Digital OpenVMS

administration 93

backup and recovery 85

connectivity 237

delivery 237

installation 237

introduction 81

machine requirements 237

maximum queue size 228

security 89

software requirements 237

storage 95

MQSeries for HP-UX

See also MQSeries on UNIX systems

administration interface 37

compilers supported 240

distribution 240

euro symbol 174

MQSeries for HP-UX (*continued*)

installation 240

link for R/3 173

machine requirements 239

maximum queue size 228

software requirements 239

web functions 240

MQSeries for MVS/ESA

See MQSeries for OS/390

MQSeries for OS/2 Warp

administration 111

administration interface 37

backup and recovery 105

CICS interface 102

compilers supported 242

distribution 242

euro symbol 104

installation 242

introduction 101

machine requirements 241

maximum queue size 228

security 109

software requirements 241

storage 113

web functions 242

MQSeries for OS/390

administration 137

backup and recovery 127

compilers supported 243

customization 121

data sets 123

distribution 244

installation 244

interfacing with CICS, IMS, and batch 118

introduction 117

machine requirements 243

maximum queue size 228

migrating from previous versions 122

OS/390 Automatic Restart Manager (ARM) 129

performance 145

preparing for use of 118

security 133

software requirements 243

storage 141

usage charges 151

using the Workload Manager 120

verifying installation 122

MQSeries for SINIX and DC/OSx

See also MQSeries on UNIX systems

compilers supported 246

distribution 246

installation 246

machine requirements 245

maximum queue size 228

software requirements 245

Index

- MQSeries for Sun Solaris
 - See also* MQSeries on UNIX systems
 - administration interface 37
 - compilers supported 248
 - distribution 248
 - euro symbol 174
 - installation 248
 - link for R/3 173
 - machine requirements 247
 - maximum queue size 228
 - software requirements 247
 - web functions 248
- MQSeries for Tandem NSK
 - administration 165
 - backup and recovery 159
 - compilers supported 249
 - distribution 249
 - installation 250
 - introduction 155
 - machine requirements 249
 - maximum queue size 228
 - security 161
 - software requirements 249
- MQSeries for UnixWare
 - compilers supported 252
 - distribution 252
 - installation 252
 - machine requirements 251
 - software requirements 251
- MQSeries for VSE/ESA
 - compilers supported 254
 - distribution 254
 - installation 254
 - introduction 189
 - machine requirements 254
 - software requirements 254
- MQSeries for Windows
 - comparing queue managers, clients, and servers 219
 - family differences 219
 - features 218
 - introduction 215
 - media recovery and logging 219
 - MQSC commands 219
- MQSeries for Windows NT
 - Active Directory Service Interfaces (ADSI) 208
 - administration 207
 - administration interface 37
 - backup and recovery 201
 - compilers supported 260
 - distribution 261
 - euro symbol 199
 - installation 261
 - interface with CICS 196
 - introduction 195
 - machine requirements 259
- MQSeries for Windows NT (*continued*)
 - maximum queue size 228
 - MMC snap-in applications 207
 - MQSeries Explorer 207
 - security 205
 - services snap-in application 207
 - software requirements 259
 - storage 211
 - web administration 208
 - web functions 260
- MQSeries for Windows Version 2.0
 - See also* MQSeries for Windows
 - compilers supported 256
 - delivery 256
 - installation 256
 - machine requirements 255
 - software requirements 255
- MQSeries for Windows Version 2.1
 - See also* MQSeries for Windows
 - compilers supported 257
 - delivery 258
 - installation 258
 - machine requirements 257
 - software requirements 257
- MQSeries framework
 - illustration 56
 - introduction 55
- MQSeries link for R/3
 - machine requirements 264
 - platforms 264
 - software requirements 264
- MQSeries objects 9
- MQSeries on DOS clients, compilers supported 238
- MQSeries on UNIX systems
 - administration 183
 - backup and recovery 175
 - euro symbol 174
 - introduction 169
 - security 179
 - storage 185
- MQSeries on VM/ESA clients
 - compilers supported 253
 - delivery 253
- MQSeries on Windows 3.1 clients, compilers supported 262
- MQSeries on Windows 95 clients, compilers supported 263
- MQSeries on Windows 98 clients, compilers supported 263
- MQSeries product lists 225
- MQSeries product summaries 225
- MQSeries publications xiv
- MQSeries server, platform support 52
- MQSeries Workflow for OS/390 120
- MQSeries-IMS bridge 118

MQSET, platform support 229
 MULC (measured usage license charges) 151
 multi-threaded applications, support on UNIX
 systems 170
 MVS/ESA
 See OS/390

N

name service interface (NSI) 57
 namelist
 commands 40
 introduction 12
 platform support 228
 security (OS/390) 134
 NCR UNIX SVR4 MP-RAS, R3.0 236
 NetBIOS, platform support 226
 network
 protocols supported 226
 security (OS/390) 133
 using MQSeries in 15
 non-version 5 clients 53
 nonpersistent message speed 16
 nonpersistent messages, platform support 228
 NSI (name service interface) 57

O

OAM (object authority manager) 23, 59
 object authority manager (OAM) 23, 59
 objects
 distribution lists 12
 managing (Digital OpenVMS) 93
 managing (OS/2 Warp) 111
 managing (Tandem NSK) 165
 managing (UNIX) 183
 managing (Windows NT) 207
 namelist 12
 process definition 13
 queue manager 9
 rules for naming 9
 one-phase commit 29
 Open Blueprint 21
 operations and control panels (OS/390) 138
 Oracle 30
 OS/2 Warp
 administration 111
 backup and recovery 105
 CICS interface 102
 euro symbol 104
 introduction 101
 MQSeries performance information 114
 security 109
 storage 113
 OS/390
 administration 137

OS/390 (*continued*)
 Automatic Restart Manager (ARM) 129
 backup and recovery 127
 data sets 123
 introduction 117
 MQSeries performance information 150
 performance 145
 security 133
 storage 141
 usage charges 151
 using the Workload Manager 120
 OS/400
 administration 73
 backup and recovery 69
 introduction 65
 Link for R/3 67
 MQSeries performance information 78
 security 71
 storage 77
 using C++ 66
 OS/400 administration utility 75
 OS/400 control language 73
 overview of MQSeries security 21

P

page data set storage (OS/390) 143
 page set (OS/390)
 backup and recovery 130
 description 123
 I/O 148
 monitoring 150
 paging (OS/390) 148
 PCF (programmable command format)
 introduction 34
 platform support 229
 PDF (Portable Document Format) xix
 performance
 dual logging 146
 events 46
 OS/2 Warp 114
 OS/390 150
 checkpointing 145
 dual logging 145
 single logging 145
 syncpointing 145
 OS/400 78
 UNIX systems 186
 Windows NT 212
 persistent messages
 active log (OS/390) 124
 introduction 6
 journaling (OS/400) 69
 performance (OS/390) 145
 platform support
 client 52

Index

platform support (*continued*)

- MQSeries link for R/3 264
- server 52

point of consistency 27

point-to-point security 24

Portable Document Format (PDF) xix

PostScript format xx

principal

- MQSeries for Digital OpenVMS 89

- MQSeries on UNIX systems 179

print log map utility (OS/390) 140

priority, messages 6

process definition

- commands 39

- object 13

process security (OS/390) 134

product summaries 225

programmable command format (PCF)

- introduction 34

- platform support 229

programming languages

- MQSeries for AIX 234

- MQSeries for AS/400 235

- MQSeries for AT&T GIS UNIX 236

- MQSeries for HP-UX 240

- MQSeries for OS/2 Warp 242

- MQSeries for OS/390 243

- MQSeries for SINIX and DC/OSx 246

- MQSeries for Sun Solaris 248

- MQSeries for Tandem NSK 249

- MQSeries for UnixWare 252

- MQSeries for VSE/ESA 254

- MQSeries for Windows NT 260

- MQSeries for Windows Version 2.0 256

- MQSeries for Windows Version 2.1 257

- MQSeries on DOS clients 238

- MQSeries on VM/ESA clients 253

- MQSeries on Windows 3.1 clients 262

- MQSeries on Windows 95 clients 263

- MQSeries on Windows 98 clients 263

programs for administration 36

protecting resources

- MQSeries for Digital OpenVMS 90

- MQSeries for Tandem NSK 162

- MQSeries on UNIX systems 180

publications, MQSeries xiv

Q

queue

- alias 11

- assured delivery 18

- attributes 11

- cluster support 8

- command 35

- command input 8

queue (*continued*)

- commands 39

- dead-letter 8

- defining 11

- description 5

- event 7

 - event notification 46

 - triggered 47

 - unavailable 47

- initiation 7

- local 11

- maximum size 228

- message 7

- naming conventions 12

- remote 11

- reply-to 8

- retention interval, platform support 229

- security (OS/390) 134

- setting up distributed 16

- system default 9

- template for dynamic queues 11

- transmission 8

- undelivered message 8

queue manager

- access control 58

- commands 38

- communication 15

- description 5, 10

- events 46

- illustration 10

- monitoring 45

- objects 9

queue manager groups, platform support 228

queue-manager aliases, platform support 228

R

R/3 and MQSeries

- AS/400 67

- UNIX systems 173

- Windows NT 198

RAM requirements

- MQSeries for Digital OpenVMS 95

- MQSeries for OS/2 Warp 113

- MQSeries for Windows NT 211

- MQSeries on UNIX systems 185

RBA (relative byte address) (OS/390) 125

recovering from problems

- distributed queuing 18

- MQSeries for Digital OpenVMS 87

- MQSeries for OS/2 Warp 108

- MQSeries for Windows NT 204

- MQSeries on UNIX systems 178

recovery

- concepts 27

- data integrity and resource protection 4

- recovery (*continued*)
 - OS/2 Warp 103
 - OS/400 69
 - planning
 - Digital OpenVMS 83, 85
 - OS/2 Warp 105
 - OS/390 127
 - Tandem NSK 157, 159
 - UNIX systems 172, 175
 - VSE/ESA 190
 - Windows NT 201
 - units of 27
 - Windows NT 197
 - redbooks 20
 - reference messages
 - introduction 7
 - platform support 229
 - relative byte address (RBA) (OS/390) 125
 - remote administration
 - Digital OpenVMS 94
 - OS/2 Warp 112
 - OS/390 138
 - OS/400 74
 - Tandem NSK 166
 - UNIX systems 184
 - Windows NT 209
 - remote link security
 - MQSeries for AS/400 66
 - MQSeries for Digital OpenVMS 82
 - MQSeries for OS/2 Warp 102
 - MQSeries for Tandem NSK 156
 - MQSeries for Windows NT 196
 - MQSeries on UNIX systems 171
 - remote queue manager 15
 - remote queue object 11
 - remote queuing, setting up 16
 - reply-to queue 8
 - reply-to queue aliases, platform support 228
 - report options for up-level, platform support 228
 - repository, cluster support 8
 - required software
 - MQSeries for AIX 232
 - MQSeries for AS/400 235
 - MQSeries for AT&T GIS UNIX 236
 - MQSeries for HP-UX 239
 - MQSeries for OS/2 Warp 241
 - MQSeries for OS/390 243
 - MQSeries for Sun Solaris 247
 - MQSeries for Tandem NSK 249
 - MQSeries for UnixWare 252
 - MQSeries for VSE/ESA 254
 - MQSeries for Windows NT 259
 - reslevel security (OS/390) 135
 - resource access, controlling
 - MQSeries for Digital OpenVMS 89
 - MQSeries for Tandem NSK 161
 - resource access, controlling (*continued*)
 - MQSeries on UNIX systems 179
 - resource management
 - with MQSeries for OS/2 Warp 107
 - with MQSeries on UNIX systems 177
 - with Windows NT 203
 - resource protection
 - MQSeries for Digital OpenVMS 90
 - MQSeries for Tandem NSK 162
 - MQSeries on UNIX systems 180
 - resource recovery services (RRS) 28
 - restart 27
 - MQSeries for AS/400 69
 - MQSeries for Digital OpenVMS 85
 - MQSeries for OS/2 Warp 105
 - MQSeries for Tandem NSK 159
 - MQSeries for Windows NT 201
 - MQSeries on UNIX systems 175
 - rights identifiers (Digital OpenVMS) 89
 - RRS (resource recovery services) 28
 - RSTLICPGM (OS/400) 68
- ## S
- SAF 124
 - SAM (security account manager), Windows NT 205
 - security
 - commands 41, 42
 - distributed queuing 24
 - facilities 21
 - MQSeries for AS/400 71
 - MQSeries for Digital OpenVMS 89
 - MQSeries for OS/2 Warp 109
 - MQSeries for OS/390 133
 - MQSeries for Tandem NSK 161
 - MQSeries for Windows NT 205
 - MQSeries on UNIX systems 179
 - overview 21
 - remote links
 - MQSeries for AS/400 66
 - MQSeries for Digital OpenVMS 82
 - MQSeries for OS/2 Warp 102
 - MQSeries for Tandem NSK 156
 - MQSeries for Windows NT 196
 - MQSeries on UNIX systems 171
 - user exits 24
 - security authorization facility (OS/390) 124
 - security enabling interface (SEI) 58
 - security exits
 - MQSeries for AS/400 72
 - MQSeries for Digital OpenVMS 91
 - MQSeries for OS/2 Warp 109
 - MQSeries for OS/390 135
 - MQSeries for Tandem NSK 163
 - MQSeries for Windows NT 206
 - MQSeries on UNIX systems 181

Index

- security identifier (SID), Windows NT 205
- segmented messages
 - introduction 7
 - platform support 229
- SEI (security enabling interface) 58
- Sequenced Packet Exchange (SPX)
 - MQSeries for OS/2 Warp 102
 - platform support 226
- server
 - communication with clients 50
 - introduction 14
 - platform support 52
 - transmission protocols 227
- services
 - naming 57
 - user identifier 59
- services snap-in application (Windows NT) 207
- setmqaut command
 - MQSeries for Digital OpenVMS 90
 - MQSeries for Tandem NSK 163
 - MQSeries on UNIX systems 180
- setting up
 - alias name 16
 - how queue managers communicate 15
 - intermediate links 20
 - MQSeries for AS/400 68
 - MQSeries for Digital OpenVMS 82
 - MQSeries for OS/2 Warp 102
 - MQSeries for Tandem NSK 156
 - MQSeries for VSE/ESA 190
 - MQSeries for Windows NT 197
 - MQSeries on UNIX systems 172
 - remote queuing 16
- shared input, platform support 228
- SID (security identifier), Windows NT 205
- simple transfer 15
- single-phase commit 29
- SINIX
 - See MQSeries for SINIX and DC/OSx
- SMP/E for OS/390 installation 121
- SMP/E library storage (OS/390) 143
- SNA
 - MQSeries for AS/400 66
 - MQSeries for Digital OpenVMS 82
 - MQSeries for OS/2 Warp 102
 - MQSeries for OS/390 119
 - MQSeries for Tandem NSK 156
 - MQSeries for VSE/ESA 189
 - MQSeries on UNIX systems 171
 - platform support 226
- softcopy books xix
- Software Installer/2 102
- software required
 - client on DOS 238
 - client on VM/ESA 253
 - client on Windows 3.1 262
- software required (*continued*)
 - client on Windows 95 263
 - client on Windows 98 263
 - MQSeries for AIX 232
 - MQSeries for AS/400 235
 - MQSeries for AT&T GIS UNIX 236
 - MQSeries for Digital OpenVMS 237
 - MQSeries for HP-UX, Version 2 239
 - MQSeries for OS/2 Warp 241
 - MQSeries for OS/390 243
 - MQSeries for Sun Solaris 247
 - MQSeries for Tandem NSK 249
 - MQSeries for UnixWare 252
 - MQSeries for VSE/ESA 254
 - MQSeries for Windows NT 259
 - MQSeries link for R/3 264
- space management (OS/390) 128
- SPX (Sequenced Packet Exchange)
 - MQSeries for OS/2 Warp 102
 - platform support 226
- staged transfer 15
- storage (OS/390)
 - archive 142
 - bootstrap data set 143
 - BSDS 143
 - CSA requirement 141
 - distribution libraries 143
 - dual BSDS 143
 - library 143
 - log 142
 - messages 143
 - page data sets 143
 - planning 141
 - SMP/E libraries 143
 - target libraries 143
- storage class 14, 123
- storage planning
 - MQSeries for AS/400 77
 - MQSeries for Digital OpenVMS 95
 - MQSeries for OS/2 Warp 113
 - MQSeries for OS/390 141
 - MQSeries for VSE/ESA 190
 - MQSeries for Windows NT 211
 - MQSeries on UNIX systems 185
- subsystem security (OS/390) 134
- summary of commands 38
- SupportPacs 51
- Sybase 30
- syncpoint 27
 - See *also* point of consistency
- syncpoint coordinator, MQSeries as
 - OS/2 Warp 107
 - UNIX systems 177
 - Windows NT 203
- system default queue 9

SYSTEM.ADMIN.COMMAND.QUEUE 35
 SYSTEM.COMMAND.INPUT.QUEUE 35

T

Tandem NSK
 administration 165
 at a glance 249
 backup and recovery 159
 introduction 155
 security 161
 target library storage (OS/390) 143
 TCP
 MQSeries for AS/400 66
 MQSeries for Digital OpenVMS 82
 MQSeries for OS/2 Warp 102
 MQSeries for OS/390 119
 MQSeries for Tandem NSK 156
 MQSeries for VSE/ESA 189
 MQSeries on UNIX systems 171
 platform support 226
 template for dynamic queues 11
 terminology used in this book 273
 threads, support on UNIX systems 170
 time-independent applications 4
 TMI (trigger monitor interface) 56
 transaction manager, MQSeries as
 introduction 30
 OS/2 Warp 107
 UNIX systems 177
 Windows NT 203
 Transaction Processing SupportPacs 51
 Transaction Server 28
 transferring messages between queue managers 15
 transmission protocol 226
 transmission queue 8, 16
 trigger
 event 7
 message 7
 monitor 7, 13
 trigger monitor interface (TMI) 56
 triggered event queue 47
 triggering 6
 (depth, priority), platform support 228
 (first and every), platform support 228
 Tuxedo 28
 two-phase commit 29
 TXSeries 28
 types of logging
 with MQSeries for Digital OpenVMS 85
 with MQSeries for OS/2 Warp 106
 with MQSeries for Windows NT 202
 with MQSeries on UNIX systems 176

U

UDP (User Datagram Protocol)
 AIX 232
 platform support 226
 Windows 255
 undelivered message queue
 See dead-letter queue
 unit of recovery 27
 unit of work 27
 UNIX systems
 administration 183
 backup and recovery 175
 introduction 169
 MQSeries performance information 186
 multi-threaded applications 170
 security 179
 storage 185
 UnixWare 251
 URL on Internet 53
 usage charges (OS/390) 151
 User Datagram Protocol (UDP)
 AIX 232
 platform support 226
 Windows 255
 user exits, security 24
 user group
 MQSeries for Digital OpenVMS 89
 MQSeries for Tandem NSK 162
 MQSeries on UNIX systems 179
 user ID support, Windows NT 205
 user identifier service 59
 utilities (OS/390)
 backup 139
 change log utility 140
 CSQ1LOGP 140
 CSQJU004 140
 CSQUTIL 139
 data conversion exit 140
 log print 140
 print log map 140
 process object definitions 139
 reorganize 139
 restore 139

V

version 5 clients 53
 VM/ESA client 253
 VSE/ESA 254
 introduction 189

W

web administration, from Windows NT 208

Index

Web functions

- MQSeries for AIX 233
- MQSeries for HP-UX 240
- MQSeries for OS/2 Warp 242
- MQSeries for Sun Solaris 248
- MQSeries for Windows NT 260

Windows

- administration 215
- comparing queue managers, clients, and servers 219
- features 218

Windows 3.1 client at a glance 262

Windows 95 client at a glance 263

Windows 98 client at a glance 263

Windows Help xx

Windows NT

- Active Directory Service Interfaces (ADSI) 208
- administration 207
- backup and recovery 201
- euro symbol 199
- introduction 195
- link for R/3 198
- MMC snap-in applications 207
- MQSeries Explorer 207
- MQSeries performance information 212
- security 205
- security account manager (SAM) 205
- security for user IDs 205
- security identifier (SID) 205
- services snap-in application 207
- storage 211
- user ID support 205
- web administration 208

WLM (Workload Manager) 120

Workflow 120

Workload Manager (WLM) 120

workload, distributing between queue managers 20

X

X/Open XA interface

- MQSeries for OS/2 Warp 107
- MQSeries for Windows NT 203
- MQSeries on UNIX systems 177

XRF (extended recovery facility) (OS/390) 129

Sending your comments to IBM

MQSeries®

Planning Guide

GC33-1349-07

If you especially like or dislike anything about this book, please use one of the methods listed below to send your comments to IBM.

Feel free to comment on what you regard as specific errors or omissions, and on the accuracy, organization, subject matter, or completeness of this book. Please limit your comments to the information in this book and the way in which the information is presented.

To request additional publications, or to ask questions or make comments about the functions of IBM products or systems, you should talk to your IBM representative or to your IBM authorized remarketer.

When you send comments to IBM, you grant IBM a nonexclusive right to use or distribute your comments in any way it believes appropriate, without incurring any obligation to you.

You can send your comments to IBM in any of the following ways:

- By mail, use the Readers' Comment Form
- By fax:
 - From outside the U.K., after your international access code use 44 1962 870229
 - From within the U.K., use 01962 870229
- Electronically, use the appropriate network ID:
 - IBM Mail Exchange: GBIBM2Q9 at IBMAIL
 - IBMLink: HURSLEY(IDRCF)
 - Internet: idrcf@hursley.ibm.com

Whichever you use, ensure that you include:

- The publication number and title
- The page number or topic to which your comment applies
- Your name and address/telephone number/fax number/network ID.

Readers' Comments

MQSeries®

Planning Guide

GC33-1349-07

Use this form to tell us what you think about this manual. If you have found errors in it, or if you want to express your opinion about it (such as organization, subject matter, appearance) or make suggestions for improvement, this is the form to use.

To request additional publications, or to ask questions or make comments about the functions of IBM products or systems, you should talk to your IBM representative or to your IBM authorized remarketer. This form is provided for comments about the information in this manual and the way it is presented.

When you send comments to IBM, you grant IBM a nonexclusive right to use or distribute your comments in any way it believes appropriate without incurring any obligation to you.

Be sure to print your name and address below if you would like a reply.

Name

Address

Company or Organization

Telephone

Email

You can send your comments POST FREE on this form from any one of these countries:


Australia	Finland	Iceland	Netherlands	Singapore	United States
Belgium	France	Israel	New Zealand	Spain	of America
Bermuda	Germany	Italy	Norway	Sweden	
Cyprus	Greece	Luxembourg	Portugal	Switzerland	
Denmark	Hong Kong	Monaco	Republic of Ireland	United Arab Emirates	

If your country is not listed here, your local IBM representative will be pleased to forward your comments to us. Or you can pay the postage and send the form direct to IBM (this includes mailing in the U.K.).

2 Fold along this line

By air mail
Par avion

IBRS/CCR NUMBER: PHQ - D/1348/SO



REPONSE PAYEE
GRANDE-BRETAGNE

IBM United Kingdom Laboratories
Information Development Department (MP095)
Hursley Park,
WINCHESTER, Hants
SO21 2ZZ United Kingdom

3 Fold along this line

From: Name _____
Company or Organization _____
Address _____

EMAIL _____
Telephone _____

4 Fasten here with adhesive tape



1 Cut along this line

1 Cut along this line



Printed in the United States of America
on recycled paper containing 10%
recovered post-consumer fiber.

GC33-1349-07

