

Operating **S**ystem **E**nvironment **M**anager

For z/OS

Messages

Version 6.1

SC31-6902-01

Limits of Liability and Disclaimer of Warranty

Trident Services and E.S.A. Software makes no warranty of any kind, expressed or implied, with regard to the programs or documentation. Trident Services and E.S.A. Software shall not be liable in any event for incidental or consequent damages in connection with or arising out of the furnishing, performance, or use of these programs.

Information in this manual is subject to change without notice and does not represent a commitment on the part of the vendor. The software described in this manual is furnished under a license agreement, and may be used or copied only in accordance with the terms of that agreement.

Copyright Notice

IBM Operating System Environment Manager (OSEM) for z/OS. Licensed materials - Property of IBM.
5799-HAX

(c) Copyright IBM Corp 2007. All rights reserved.

(c) Copyright E.S.A. Software 1990-2007. All rights reserved.

No parts of this publication may be copied or distributed, transmitted, transcribed, stored in a retrieval system, translated into any human or computer language, or disclosed to third parties without the express written permission of IBM Corp or E.S.A. Software.

The following are trademarks of IBM Corp:

DFHSM
DFSMS
IBM
OS/390
RACF
z/OS

The following are trademarks of Computer Associates International:

CA-ACF2
CA-TOPSECRET
CA-1
EZ-Proclib

Second Edition (February 2006)

Revised October 20th, 2008

This edition applies to Operating System Environment Manager for z/OS (OSEM for z/OS) Version 6 Release 1 Modification 0 (Program Number 5799-HAX).

Table of Contents

OS/EM System Codes and Messages	MSG-1
System Codes	MSG-1
Format	MSG-1
User Completion Code	MSG-1
Asv-0000	MSG-1
Asv-0004	MSG-1
Asv-0008	MSG-1
Asv-0012	MSG-2
Asv-0016	MSG-2
Asv-0020	MSG-2
Asv-0024	MSG-2
Asv-0028	MSG-3
Asv-0032	MSG-3
AFF-0036	MSG-3
JESYSMSG (Allocation) Messages	MSG-4
Message Format	MSG-4
JESYSMSG Message Text	MSG-4
JESMSG (SYSLOG) and TSO Messages	MSG-5
Message Format	MSG-5
Error Message Module Identifier	MSG-5
Message Text	MSG-7
FEMxxx000	MSG-7
FEMIP001	MSG-7
FEMIP002	MSG-7
FEMALC003	MSG-7
FEMIP003	MSG-8
FEMCTL004	MSG-8
FEMHSP004	MSG-8
FEMIAT004	MSG-9
FEMINT004	MSG-9
FEMIP004	MSG-9
FEMLIB004	MSG-9
FEMTPS004	MSG-10
FEMIP006	MSG-10
FEMSVU006	MSG-10
FEMIP007	MSG-11
FEMIP008	MSG-11
FEMIP009	MSG-11
FEMIP010	MSG-12
FEMIP012	MSG-12
FEMHSP013	MSG-12
FEMLOD013	MSG-13
FEMS19013	MSG-13
FEMS22013	MSG-14
FEMLOD014	MSG-15
FEMLOD015	MSG-15
FEMIP016	MSG-15

FEMHSP017	MSG-16
FEMLOD017	MSG-16
FEMS19017	MSG-16
FEMS22017	MSG-17
FEMLOD018	MSG-17
FEM IPL019	MSG-17
FEM IPL020	MSG-18
FEM AIF021	MSG-18
FEM DIF021	MSG-18
FEM FIF021	MSG-19
FEM HIF021	MSG-19
FEM IIF021	MSG-19
FEM J2I021	MSG-20
FEM J3I021	MSG-20
FEM RIF021	MSG-20
FEM SIF021	MSG-21
FEM TIF021	MSG-21
FEM X00021	MSG-22
FEM CTL022	MSG-22
FEM DC1022	MSG-22
FEM IPL022	MSG-23
FEM LIB022	MSG-23
FEM THI022	MSG-23
FEM TPS022	MSG-24
FEM USI022	MSG-24
FEM J2M023	MSG-24
FEM J2S023	MSG-25
FEM X05023	MSG-25
FEM 2P4023	MSG-26
FEM ACN024	MSG-26
FEM ASY024	MSG-26
FEM COM024	MSG-27
FEM DCN024	MSG-27
FEM EXR024	MSG-28
FEM FCN024	MSG-28
FEM FTN024	MSG-28
FEM HCN024	MSG-29
FEM ICN024	MSG-29
FEM J2M024	MSG-30
FEM J2R024	MSG-30
FEM J2S024	MSG-30
FEM J3E024	MSG-31
FEM J3S024	MSG-31
FEM LOK024	MSG-32
FEM RCN024	MSG-32
FEM SCN024	MSG-32
FEM TCN024	MSG-33
FEM UJI024	MSG-33
FEM USI024	MSG-34
FEM VCN024	MSG-34
FEM X05024	MSG-34
FEM 2P4024	MSG-35
FEM 2P4024	MSG-35
FEM ACN025	MSG-36
FEM DCN025	MSG-36
FEM FRA025	MSG-36
FEM HCN025	MSG-37
FEM ICN025	MSG-37
FEM J3E025	MSG-37

FEMRCN025	MSG-38
FEMSCN025	MSG-38
FEMTCN025	MSG-39
FEMACN026	MSG-39
FEMDCN026	MSG-39
FEMFCN026	MSG-40
FEMHCN026	MSG-40
FEMICN026	MSG-40
FEMJ3E026	MSG-41
FEMRCN026	MSG-41
FEMSCN026	MSG-42
FEMTCN026	MSG-42
FEMCMD027	MSG-42
FEMDC1027	MSG-43
FEMIPLO27	MSG-43
FEMTPS027	MSG-43
FEMO2F027	MSG-44
FEMLOK029	MSG-44
FEMACN030	MSG-45
FEMALC030	MSG-45
FEMASY030	MSG-45
FEMDAD030	MSG-46
FEMDCN030	MSG-46
FEMFRA030	MSG-46
FEMF10030	MSG-47
FEMHCN030	MSG-47
FEMHSM030	MSG-47
FEMHSP030	MSG-48
FEMIAT030	MSG-48
FEMICN030	MSG-48
FEMISP030	MSG-49
FEMJS2030	MSG-49
FEMJS3030	MSG-49
FEMJ2I030	MSG-50
FEMJ2M030	MSG-50
FEMJ2S030	MSG-50
FEMJ3E030	MSG-51
FEMJ3I030	MSG-51
FEMJ3S030	MSG-51
FEMMIS030	MSG-52
FEMRAC030	MSG-52
FEMRCN030	MSG-52
FEMRC2030	MSG-53
FEMRD1030	MSG-53
FEMREL030	MSG-53
FEMSAF030	MSG-54
FEMSCH030	MSG-54
FEMSCN030	MSG-54
FEMSMF030	MSG-55
FEMTCN030	MSG-55
FEMTSO030	MSG-55
FEMUJI030	MSG-56
FEMUSI030	MSG-56
FEMUSO030	MSG-56
FEMUTL030	MSG-57
FEMVCN030	MSG-57
FEMX00030	MSG-57
FEMX06030	MSG-58
FEMX09030	MSG-58

FEMX49030	MSG-58
FEM2P4030	MSG-59
FEMDCN031	MSG-59
FEMABN032	MSG-59
FEMLIM033	MSG-59
FEMLIM034	MSG-60
FEMNUL035	MSG-60
FEMUJI036	MSG-60
FEMWTO037	MSG-61
FEMDB4038	MSG-61
FEMW21038	MSG-61
FEMW21039	MSG-62
FEMCTL040	MSG-62
FEMHSP040	MSG-62
FEMIAT040	MSG-63
FEMINT040	MSG-63
FEMLIB040	MSG-63
FEMTPS040	MSG-63
FEMCTL041	MSG-64
FEMCTL042	MSG-64
FEMCTL043	MSG-64
FEMCTL044	MSG-65
FEMLIB044	MSG-65
FEMCTL045	MSG-65
FEMLIB045	MSG-65
FEMCTL046	MSG-66
FEMREL046	MSG-66
FEMATH047	MSG-66
FEMALC048	MSG-66
FEMCOD048	MSG-67
FEMDAD048	MSG-67
FEMDAP048	MSG-67
FEMDMP048	MSG-68
FEMHSM048	MSG-68
FEMISP048	MSG-68
FEMJ2#048	MSG-68
FEMJS3048	MSG-69
FEMLIB048	MSG-69
FEMMIS048	MSG-69
FEMQRY048	MSG-70
FEMRAC048	MSG-70
FEMREL048	MSG-70
FEMSAF048	MSG-70
FEMSMF048	MSG-71
FEMSTM048	MSG-71
FEMSVU048	MSG-71
FEMTSO048	MSG-72
FEMCOD049	MSG-72
FEMCOD050	MSG-72
FEMCOD051	MSG-72
FEMDAP052	MSG-73
FEMHSP053	MSG-73
FEMIAT053	MSG-73
FEMHSP054	MSG-74
FEMIAT054	MSG-74
FEMHSP055	MSG-74
FEMIAT055	MSG-75
FEM2D0055	MSG-75
FEM2H0055	MSG-75

FEM2H4055	MSG-76
FEM2L0055	MSG-76
FEM2L4055	MSG-76
FEM2M0055	MSG-76
FEM2M4055	MSG-77
FEMX24055	MSG-77
FEM IPL056	MSG-77
FEMALC057	MSG-78
FEMDAD057	MSG-78
FEMHSM057	MSG-78
FEMISP057	MSG-78
FEMJS2057	MSG-79
FEMJS3057	MSG-79
FEMMIS057	MSG-79
FEMRAC057	MSG-80
FEMREL057	MSG-80
FEMSAF057	MSG-80
FEMSMF057	MSG-81
FEMTPS057	MSG-81
FEMTSO057	MSG-81
FEMALC058	MSG-82
FEMDAD058	MSG-82
FEMHSM058	MSG-82
FEMISP058	MSG-82
FEMJS2058	MSG-83
FEMJS3058	MSG-83
FEMMIS058	MSG-83
FEMRAC058	MSG-83
FEMSAF058	MSG-84
FEMSMF058	MSG-84
FEMTSO058	MSG-84
FEMINT059	MSG-84
FEMTPS059	MSG-85
FEMINT060	MSG-85
FEMINT061	MSG-85
FEMINT062	MSG-85
FEMINT063	MSG-86
FEMINT064	MSG-86
FEMINT065	MSG-86
FEMALC066	MSG-87
FEMB14066	MSG-87
FEMINT066	MSG-87
FEM IPL066	MSG-88
FEMJS2066	MSG-88
FEMLIB066	MSG-89
FEMLOD066	MSG-89
FEMTPS066	MSG-89
FEMW21066	MSG-90
FEM2M0066	MSG-90
FEM2M1066	MSG-90
FEMVCN067	MSG-91
FEMVCN069	MSG-91
FEMACN070	MSG-92
FEMALC070	MSG-92
FEMASY070	MSG-92
FEMCMD070	MSG-93
FEMCOM070	MSG-93
FEMDCN070	MSG-94
FEMDC1070	MSG-94

FEMEXR070	MSG-94
FEMFRA070	MSG-95
FEMFTN070	MSG-95
FEMHCN070	MSG-96
FEMHSP070	MSG-96
FEMIAT070	MSG-96
FEMICN070	MSG-97
FEM IPL070	MSG-97
FEMJS2070	MSG-98
FEMJ2M070	MSG-98
FEMJ2R070	MSG-98
FEMJ2S070	MSG-99
FEMJ3E070	MSG-99
FEMJ3S070	MSG-100
FEMLOK070	MSG-100
FEMRCN070	MSG-100
FEMSCN070	MSG-101
FEMTCN070	MSG-101
FEMTPS070	MSG-102
FEMUJI070	MSG-102
FEMUSI070	MSG-102
FEMVCN070	MSG-103
FEMX05070	MSG-103
FEM02F070	MSG-104
FEM1PL070	MSG-104
FEM2H5070	MSG-104
FEM2P4070	MSG-105
FEMACN071	MSG-105
FEMALC071	MSG-106
FEMASY071	MSG-106
FEMCMD071	MSG-106
FEMCOM071	MSG-107
FEMDCN071	MSG-107
FEMDC1071	MSG-107
FEMEXR071	MSG-108
FEMFRA071	MSG-108
FEMFTN071	MSG-109
FEMHCN071	MSG-109
FEMHSP071	MSG-109
FEMIAT071	MSG-110
FEMICN071	MSG-110
FEM IPL071	MSG-110
FEMJS2071	MSG-111
FEMJ2M071	MSG-111
FEMJ2R071	MSG-112
FEMJ2S071	MSG-112
FEMJ3E071	MSG-112
FEMJ3S071	MSG-113
FEMLOK071	MSG-113
FEMRCN071	MSG-113
FEMSCN071	MSG-114
FEMTCN071	MSG-114
FEMTPS071	MSG-115
FEMUJI071	MSG-115
FEMUSI071	MSG-115
FEMVCN071	MSG-116
FEMX05071	MSG-116
FEM02F071	MSG-116
FEM1PL071	MSG-117

FEM2H5071	MSG-117
FEM2P4071	MSG-118
FEMACN072	MSG-118
FEMALC072	MSG-118
FEMASY072	MSG-119
FEMCMD072	MSG-119
FEMCOM072	MSG-119
FEMDCN072	MSG-120
FEMDC1072	MSG-120
FEMEXR072	MSG-120
FEMFTN072	MSG-121
FEMHCN072	MSG-121
FEMHSP072	MSG-121
FEMIAT072	MSG-122
FEMICN072	MSG-122
FEMIPL072	MSG-122
FEMJS2072	MSG-123
FEMJ2M072	MSG-123
FEMJ2R072	MSG-123
FEMJ2S072	MSG-124
FEMJ3E072	MSG-124
FEMJ3S072	MSG-125
FEMLOK072	MSG-125
FEMRCN072	MSG-125
FEMSCN072	MSG-126
FEMTCN072	MSG-126
FEMTPS072	MSG-126
FEMUJI072	MSG-127
FEMUSI072	MSG-127
FEMVCN072	MSG-127
FEMX05072	MSG-128
FEM02F072	MSG-128
FEM1PL072	MSG-128
FEM2H5072	MSG-129
FEM2P4072	MSG-129
FEMACN073	MSG-129
FEMALC073	MSG-130
FEMASY073	MSG-130
FEMCMD073	MSG-130
FEMCOM073	MSG-131
FEMDCN073	MSG-131
FEMDC1073	MSG-132
FEMEXR073	MSG-132
FEMFRA073	MSG-132
FEMFTN073	MSG-133
FEMHCN073	MSG-133
FEMHSP073	MSG-133
FEMIAT073	MSG-134
FEMICN073	MSG-134
FEMIPL073	MSG-134
FEMJS2073	MSG-135
FEMJ2M073	MSG-135
FEMJ2R073	MSG-135
FEMJ2S073	MSG-136
FEMJ3E073	MSG-136
FEMJ3S073	MSG-136
FEMLOK073	MSG-137
FEMRCN073	MSG-137
FEMSCN073	MSG-137

FEMTCN073	MSG-138
FEMTPS073	MSG-138
FEMUJI073	MSG-138
FEMUSI073	MSG-139
FEMVCN073	MSG-139
FEMX05073	MSG-139
FEM02F073	MSG-140
FEM1PL073	MSG-140
FEM2H5073	MSG-140
FEM2P4073	MSG-141
FEMACN074	MSG-141
FEMALC074	MSG-141
FEMASY074	MSG-142
FEMCMD074	MSG-142
FEMCOM074	MSG-142
FEMDCN074	MSG-143
FEMDC1074	MSG-143
FEMEXR074	MSG-143
FEMFRA074	MSG-144
FEMFTN074	MSG-144
FEMHCN074	MSG-144
FEMHSP074	MSG-145
FEMIAT074	MSG-145
FEMICN074	MSG-145
FEMIPL074	MSG-146
FEMJS2074	MSG-146
FEMJ2M074	MSG-146
FEMJ2R074	MSG-147
FEMJ2S074	MSG-147
FEMJ3E074	MSG-147
FEMJ3S074	MSG-148
FEMLOK074	MSG-148
FEMRCN074	MSG-148
FEMSCN074	MSG-149
FEMTCN074	MSG-149
FEMTPS074	MSG-149
FEMUJI074	MSG-150
FEMUSI074	MSG-150
FEMVCN074	MSG-150
FEMX05074	MSG-151
FEM02F074	MSG-151
FEM1PL074	MSG-151
FEM2H5074	MSG-152
FEM2P4074	MSG-152
FEMACN075	MSG-152
FEMALC075	MSG-153
FEMASY075	MSG-153
FEMCMD075	MSG-153
FEMCOM075	MSG-154
FEMDCN075	MSG-154
FEMDC1075	MSG-154
FEMEXR075	MSG-155
FEMFRA075	MSG-155
FEMFTN075	MSG-155
FEMHCN075	MSG-156
FEMHSP075	MSG-156
FEMIAT075	MSG-156
FEMICN075	MSG-157
FEMIPL075	MSG-157

FEMJS2075	MSG-157
FEMJ2M075	MSG-158
FEMJ2R075	MSG-158
FEMJ2S075	MSG-158
FEMJ3E075	MSG-159
FEMJ3S075	MSG-159
FEMLOK075	MSG-159
FEMRCN075	MSG-160
FEMSCN075	MSG-160
FEMTCN075	MSG-160
FEMTPS075	MSG-161
FEMUJI075	MSG-161
FEMUSI075	MSG-161
FEMVCN075	MSG-162
FEMX05075	MSG-162
FEM02F075	MSG-162
FEM1PL075	MSG-163
FEM2H5075	MSG-163
FEM2P4075	MSG-163
FEMACN076	MSG-164
FEMALC076	MSG-164
FEMASY076	MSG-164
FEMCMD076	MSG-165
FEMCOM076	MSG-165
FEMDCN076	MSG-165
FEMDC1076	MSG-166
FEMEXR076	MSG-166
FEMFRA076	MSG-166
FEMFTN076	MSG-167
FEMHCN076	MSG-167
FEMHSP076	MSG-167
FEMIAT076	MSG-168
FEMICN076	MSG-168
FEMIPL076	MSG-168
FEMJS2076	MSG-169
FEMJ2M076	MSG-169
FEMJ2R076	MSG-169
FEMJ2S076	MSG-170
FEMJ3E076	MSG-170
FEMJ3S076	MSG-170
FEMLOK076	MSG-171
FEMRCN076	MSG-171
FEMSCN076	MSG-171
FEMTCN076	MSG-172
FEMTPS076	MSG-172
FEMUJI076	MSG-172
FEMUSI076	MSG-173
FEMVCN076	MSG-173
FEMX05076	MSG-173
FEM02F076	MSG-174
FEM1PL076	MSG-174
FEM2H5076	MSG-174
FEM2P4076	MSG-175
FEMLOD077	MSG-175
FEMDEL078	MSG-175
FEMLOD079	MSG-176
FEMLOD080	MSG-176
FEMLOD081	MSG-176
FEMCAL082	MSG-177

FEMHSP082	MSG-177
FEMJ2J082	MSG-177
FEMLOD082	MSG-178
FEMREL082	MSG-178
FEMX00082	MSG-178
FEM2TP082	MSG-179
FEMHSP083	MSG-179
FEMIAT083	MSG-179
FEMX24083	MSG-180
FEMREL084	MSG-180
FEMREL085	MSG-180
FEMJS2086	MSG-181
FEMALC087	MSG-181
FEMIPLO87	MSG-181
FEMJS2087	MSG-182
FEMLIB087	MSG-182
FEMQRY087	MSG-182
FEMTPS087	MSG-183
FEM2M0087	MSG-183
FEMJS2088	MSG-183
FEMJ2M089	MSG-183
FEMJ2S089	MSG-184
FEMJ2R090	MSG-184
FEMJ2M091	MSG-185
FEMJ2S091	MSG-185
FEM02F091	MSG-185
FEMJ2M092	MSG-186
FEMJ2S092	MSG-186
FEMACN093	MSG-186
FEMALC093	MSG-187
FEMASY093	MSG-187
FEMCMD093	MSG-187
FEMCOM093	MSG-188
FEMDCN093	MSG-188
FEMDC1093	MSG-188
FEMEXR093	MSG-189
FEMFRA093	MSG-189
FEMFTN093	MSG-190
FEMHCN093	MSG-190
FEMIAT093	MSG-190
FEMICN093	MSG-191
FEMIPLO93	MSG-191
FEMJS2093	MSG-191
FEMJ2M093	MSG-192
FEMJ2R093	MSG-192
FEMJ2S093	MSG-192
FEMJ3E093	MSG-193
FEMJ3S093	MSG-193
FEMLOK093	MSG-194
FEMRCN093	MSG-194
FEMSCN093	MSG-194
FEMTCN093	MSG-195
FEMTHI093	MSG-195
FEMTPS093	MSG-195
FEMUJI093	MSG-196
FEMUSI093	MSG-196
FEMVCN093	MSG-196
FEMX05093	MSG-197
FEM1PLO93	MSG-197

FEM02F093	MSG-198
FEM2H5093	MSG-198
FEMDAP094	MSG-198
FEMACT096	MSG-199
FEMACT097	MSG-199
FEMACT098	MSG-199
FEMACT099	MSG-200
FEMX06100	MSG-200
FEMACN101	MSG-200
FEMDCN101	MSG-201
FEMFRA101	MSG-201
FEMHCN101	MSG-202
FEMICN101	MSG-202
FEMRCN101	MSG-202
FEMSCN101	MSG-203
FEMTCN101	MSG-203
FEMJ3E102	MSG-203
FEM02F103	MSG-204
FEMREL104	MSG-204
FEMDB4105	MSG-204
FEMF10106	MSG-205
FEMF10107	MSG-205
FEMF10108	MSG-205
FEMX02109	MSG-206
FEMF10110	MSG-206
FEMF10111	MSG-206
FEMF10112	MSG-207
FEMJ3S113	MSG-207
FEMUTL114	MSG-207
FEMUTL115	MSG-208
FEMUTL116	MSG-208
FEMUTL117	MSG-208
FEMUTL118	MSG-209
FEMUTL119	MSG-209
FEMUTL120	MSG-209
FEMACT121	MSG-209
FEMUJI122	MSG-210
FEMPRE123	MSG-210
FEMPRE124	MSG-210
FEMPRE125	MSG-211
FEMPRE126	MSG-211
FEMPRE127	MSG-211
FEMPRE128	MSG-212
FEMPRE129	MSG-212
FEMPRE130	MSG-212
FEMPRE131	MSG-213
FEMPRE132	MSG-213
FEMPRE133	MSG-213
FEMPRE134	MSG-214
FEMPRE135	MSG-214
FEMPRE136	MSG-214
FEMPRE137	MSG-215
FEMPRE138	MSG-215
FEMALC139	MSG-215
FEMCOD139	MSG-216
FEMDAD139	MSG-216
FEMDAP139	MSG-216
FEMHSM139	MSG-217
FEMISP139	MSG-217

FEMJS2139	MSG-217
FEMJS3139	MSG-218
FEMMIS139	MSG-218
FEMRAC139	MSG-219
FEMSAF139	MSG-219
FEMSMF139	MSG-219
FEMTSO139	MSG-220
FEMCMD140	MSG-220
FEMCMD141	MSG-220
FEMALC143	MSG-221
FEMRD1144	MSG-221
FEMRD1145	MSG-221
FEMX02146	MSG-222
FEMX04146	MSG-222
FEMX05146	MSG-222
FEMX06146	MSG-223
FEMX24146	MSG-223
FEMX32146	MSG-223
FEMX44146	MSG-223
FEM2G3146	MSG-224
FEM2H0146	MSG-224
FEM2L0146	MSG-224
FEM2MM146	MSG-225
FEM2M3146	MSG-225
FEM IPL147	MSG-225
FEMX06148	MSG-225
FEMUSO149	MSG-226
FEM IPL150	MSG-226
FEM IPL151	MSG-226
FEMUSO152	MSG-227
FEMX32153	MSG-227
FEMREL154	MSG-227
FEMREL155	MSG-228
FEMSVU156	MSG-228
FEMALC157	MSG-228
FEMINT158	MSG-228
FEM2P1159	MSG-229
FEM2P2159	MSG-229
FEMALC160	MSG-229
FEMDMP160	MSG-229
FEMHSP160	MSG-230
FEMLIB160	MSG-230
FEMREL160	MSG-230
FEMTPS160	MSG-231
FEMW21160	MSG-231
FEMX32160	MSG-231
FEM2G2160	MSG-232
FEM2G3160	MSG-232
FEM2G4160	MSG-232
FEM2P1160	MSG-233
FEM2P3160	MSG-233
FEM2S0160	MSG-233
FEM IPL161	MSG-234
FEM IPL163	MSG-234
FEM IPL165	MSG-234
FEMJ3E166	MSG-234
FEMALC167	MSG-235
FEMJS2167	MSG-235
FEMTPS167	MSG-236

FEM2S0167	MSG-236
FEMJS2168	MSG-236
FEMX00169	MSG-237
FEMHSP170	MSG-237
FEMJS2170	MSG-237
FEMREL170	MSG-237
FEMLOD171	MSG-238
FEMREL171	MSG-238
FEMTPS172	MSG-238
FEMALC173	MSG-239
FEMALC174	MSG-239
FEMALC175	MSG-239
FEMTPS176	MSG-240
FEMTPS177	MSG-240
FEMALC178	MSG-240
FEMALC179	MSG-240
FEMTPS179	MSG-241
FEMTPS180	MSG-241
FEMTPS181	MSG-241
FEMTPS182	MSG-242
FEMALC183	MSG-242
FEMTPS183	MSG-242
FEMTPS184	MSG-242
FEMCMD185	MSG-243
FEMTPS186	MSG-243
FEMTPS187	MSG-243
FEMCMD188	MSG-244
FEMCMD189	MSG-244
FEMALC190	MSG-244
FEM IPL191	MSG-245
FEM LIB191	MSG-245
FEMW21191	MSG-245
FEMW21192	MSG-245
FEMUTL193	MSG-246
FEMS19194	MSG-246
FEMS22194	MSG-246
FEMREL196	MSG-246
FEMJS2197	MSG-247
FEMREL197	MSG-247
FEMLOD198	MSG-247
FEMUXW199	MSG-247
FEMUXW200	MSG-248
FEMUXA201	MSG-248
FEMLOD202	MSG-248
FEM IPL203	MSG-248
FEMREL204	MSG-249
FEMREL205	MSG-249
FEMACN206	MSG-249
FEMALC206	MSG-250
FEMASY206	MSG-250
FEMCMD206	MSG-250
FEMCOM206	MSG-251
FEMDCN206	MSG-251
FEMDC1206	MSG-252
FEMEXR206	MSG-252
FEMFRA206	MSG-252
FEMFTN206	MSG-253
FEMHCN206	MSG-253
FEMHSP206	MSG-253

FEMIAT206	MSG-254
FEMICN206	MSG-254
FEM IPL206	MSG-254
FEMJS2206	MSG-255
FEMJ2M206	MSG-255
FEMJ2R206	MSG-255
FEMJ2S206	MSG-256
FEMJ3E206	MSG-256
FEMJ3S206	MSG-256
FEMLOK206	MSG-257
FEMRCN206	MSG-257
FEMSCN206	MSG-257
FEMTCN206	MSG-258
FEMTPS206	MSG-258
FEMUJI206	MSG-258
FEMUSI206	MSG-259
FEMVCN206	MSG-259
FEMX05206	MSG-259
FEM02F206	MSG-260
FEM1PL206	MSG-260
FEM2H5206	MSG-260
FEM2P4206	MSG-261
FEMACN207	MSG-261
FEMALC207	MSG-261
FEMASY207	MSG-262
FEMCMD207	MSG-262
FEMCOM207	MSG-262
FEMDCN207	MSG-263
FEMDC1207	MSG-263
FEMEXR207	MSG-263
FEMFRA207	MSG-264
FEMFTN207	MSG-264
FEMHCN207	MSG-264
FEMHSP207	MSG-265
FEMIAT207	MSG-265
FEMICN207	MSG-265
FEM IPL207	MSG-266
FEMJS2207	MSG-266
FEMJ2M207	MSG-266
FEMJ2R207	MSG-267
FEMJ2S207	MSG-267
FEMJ3E207	MSG-267
FEMJ3S207	MSG-268
FEMLOK207	MSG-268
FEMRCN207	MSG-268
FEMSCN207	MSG-269
FEMTCN207	MSG-269
FEMTPS207	MSG-269
FEMUJI207	MSG-270
FEMUSI207	MSG-270
FEMVCN207	MSG-270
FEMX05207	MSG-271
FEM02F207	MSG-271
FEM1PL207	MSG-271
FEM2H5207	MSG-272
FEM2P4207	MSG-272
FEMACN208	MSG-272
FEMALC208	MSG-273
FEMASY208	MSG-273

FEMCMD208	MSG-273
FEMCOM208	MSG-274
FEMDCN208	MSG-274
FEMDC1208	MSG-274
FEMEXR208	MSG-275
FEMFRA208	MSG-275
FEMFTN208	MSG-275
FEMHCN208	MSG-276
FEMHSP208	MSG-276
FEMIAT208	MSG-276
FEMICN208	MSG-277
FEM IPL208	MSG-277
FEMJS2208	MSG-277
FEMJ2M208	MSG-278
FEMJ2R208	MSG-278
FEMJ2S208	MSG-278
FEMJ3E208	MSG-279
FEMJ3S208	MSG-279
FEMLOK208	MSG-279
FEMRCN208	MSG-280
FEMSCN208	MSG-280
FEMTCN208	MSG-280
FEMTPS208	MSG-281
FEMUJI208	MSG-281
FEMUSI208	MSG-281
FEMVCN208	MSG-282
FEMX05208	MSG-282
FEM02F208	MSG-282
FEM1PL208	MSG-283
FEM2H5208	MSG-283
FEM2P4208	MSG-283
FEMACN209	MSG-284
FEMALC209	MSG-284
FEMASY209	MSG-284
FEMCMD209	MSG-285
FEMCOM209	MSG-285
FEMDCN209	MSG-285
FEMDC1209	MSG-286
FEMEXR209	MSG-286
FEMFRA209	MSG-286
FEMFTN209	MSG-287
FEMHCN209	MSG-287
FEMHSP209	MSG-287
FEMIAT209	MSG-288
FEMICN209	MSG-288
FEM IPL209	MSG-288
FEMJS2209	MSG-289
FEMJ2M209	MSG-289
FEMJ2R209	MSG-289
FEMJ2S209	MSG-290
FEMJ3E209	MSG-290
FEMJ3S209	MSG-290
FEMLOK209	MSG-291
FEMRCN209	MSG-291
FEMSCN209	MSG-291
FEMTCN209	MSG-292
FEMTPS209	MSG-292
FEMUJI209	MSG-292
FEMUSI209	MSG-293

FEMVCN209	MSG-293
FEMX05209	MSG-293
FEM02F209	MSG-294
FEM1PL209	MSG-294
FEM2H5209	MSG-294
FEM2P4209	MSG-295
FEMACN210	MSG-295
FEMALC210	MSG-295
FEMASY210	MSG-296
FEMCMD210	MSG-296
FEMCOM210	MSG-296
FEMDCN210	MSG-297
FEMDC1210	MSG-297
FEMEXR210	MSG-297
FEMFRA210	MSG-298
FEMFTN210	MSG-298
FEMHCN210	MSG-298
FEMHSP210	MSG-299
FEMIAT210	MSG-299
FEMICN210	MSG-299
FEM IPL210	MSG-300
FEMJS2210	MSG-300
FEMJ2M210	MSG-300
FEMJ2R210	MSG-301
FEMJ2S210	MSG-301
FEMJ3E210	MSG-301
FEMJ3S210	MSG-302
FEMLOK210	MSG-302
FEMRCN210	MSG-302
FEMSCN210	MSG-303
FEMTCN210	MSG-303
FEMTPS210	MSG-303
FEMUJI210	MSG-304
FEMUSI210	MSG-304
FEMVCN210	MSG-304
FEMX05210	MSG-305
FEM02F210	MSG-305
FEM1PL210	MSG-305
FEM2H5210	MSG-306
FEM2P4210	MSG-306
FEMACN211	MSG-306
FEMALC211	MSG-307
FEMASY211	MSG-307
FEMCMD211	MSG-307
FEMCOM211	MSG-308
FEMDCN211	MSG-308
FEMDC1211	MSG-308
FEMEXR211	MSG-309
FEMFRA211	MSG-309
FEMFTN211	MSG-309
FEMHCN211	MSG-310
FEMHSP211	MSG-310
FEMIAT211	MSG-310
FEMICN211	MSG-311
FEM IPL211	MSG-311
FEMJS2211	MSG-311
FEMJ2M211	MSG-312
FEMJ2R211	MSG-312
FEMJ2S211	MSG-312

FEMJ3E211	MSG-313
FEMJ3S211	MSG-313
FEMLOK211	MSG-313
FEMRCN211	MSG-314
FEMSCN211	MSG-314
FEMTCN211	MSG-314
FEMTPS211	MSG-315
FEMUJI211	MSG-315
FEMUSI211	MSG-315
FEMVCN211	MSG-316
FEMX05211	MSG-316
FEM02F211	MSG-316
FEM1PL211	MSG-317
FEM2H5211	MSG-317
FEM2P4211	MSG-317
FEMACN212	MSG-318
FEMALC212	MSG-318
FEMASY212	MSG-318
FEMCMD212	MSG-319
FEMCOM212	MSG-319
FEMDCN212	MSG-319
FEMDC1212	MSG-320
FEMEXR212	MSG-320
FEMFRA212	MSG-320
FEMFTN212	MSG-321
FEMHCN212	MSG-321
FEMHSP212	MSG-321
FEMIAT212	MSG-322
FEMICN212	MSG-322
FEMIPL212	MSG-322
FEMJS212	MSG-323
FEMJ2M212	MSG-323
FEMJ2R212	MSG-323
FEMJ2S212	MSG-324
FEMJ3E212	MSG-324
FEMJ3S212	MSG-324
FEMLOK212	MSG-325
FEMRCN212	MSG-325
FEMSCN212	MSG-325
FEMTCN212	MSG-326
FEMTPS212	MSG-326
FEMUJI212	MSG-326
FEMUSI212	MSG-327
FEMVCN212	MSG-327
FEMX05212	MSG-327
FEM02F212	MSG-328
FEM1PL212	MSG-328
FEM2H5212	MSG-328
FEM2P4212	MSG-329
FEMACN213	MSG-329
FEMALC213	MSG-329
FEMASY213	MSG-330
FEMCMD213	MSG-330
FEMCOM213	MSG-330
FEMDCN213	MSG-331
FEMDC1213	MSG-331
FEMEXR213	MSG-331
FEMFRA213	MSG-332
FEMFTN213	MSG-332

FEMHCN213	MSG-332
FEMHSP213	MSG-333
FEMIAT213	MSG-333
FEMICN213	MSG-333
FEM IPL213	MSG-334
FEMJS2213	MSG-334
FEMJ2M213	MSG-334
FEMJ2R213	MSG-335
FEMJ2S213	MSG-335
FEMJ3E213	MSG-335
FEMJ3S213	MSG-336
FEMLOK213	MSG-336
FEMRCN213	MSG-336
FEMSCN213	MSG-337
FEMTCN213	MSG-337
FEMTPS213	MSG-337
FEMUJI213	MSG-338
FEMUSI213	MSG-338
FEMVCN213	MSG-338
FEMX05213	MSG-339
FEM02F213	MSG-339
FEM1PL213	MSG-339
FEM2H5213	MSG-340
FEM2P4213	MSG-340
FEMACN214	MSG-340
FEMALC214	MSG-341
FEMASY214	MSG-341
FEMCMD214	MSG-341
FEMCOM214	MSG-342
FEMDCN214	MSG-342
FEMDC1214	MSG-342
FEMEXR214	MSG-343
FEMFRA214	MSG-343
FEMFTN214	MSG-343
FEMHCN214	MSG-344
FEMHSP214	MSG-344
FEMIAT214	MSG-344
FEMICN214	MSG-345
FEM IPL214	MSG-345
FEMJS2214	MSG-345
FEMJ2M214	MSG-346
FEMJ2R214	MSG-346
FEMJ2S214	MSG-346
FEMJ3E214	MSG-347
FEMJ3S214	MSG-347
FEMLOK214	MSG-347
FEMRCN214	MSG-348
FEMSCN214	MSG-348
FEMTCN214	MSG-348
FEMTPS214	MSG-349
FEMUJI214	MSG-349
FEMUSI214	MSG-349
FEMVCN214	MSG-350
FEMX05214	MSG-350
FEM02F214	MSG-350
FEM1PL214	MSG-351
FEM2H5214	MSG-351
FEM2P4214	MSG-351
FEMACN215	MSG-352

FEMALC215	MSG-352
FEMASY215	MSG-352
FEMCMD215	MSG-353
FEMCOM215	MSG-353
FEMDCN215	MSG-353
FEMDC1215	MSG-354
FEMEXR215	MSG-354
FEMFRA215	MSG-354
FEMFTN215	MSG-355
FEMHCN215	MSG-355
FEMHSP215	MSG-355
FEMIAT215	MSG-356
FEMICN215	MSG-356
FEM IPL215	MSG-356
FEMJS2215	MSG-357
FEMJ2M215	MSG-357
FEMJ2R215	MSG-357
FEMJ2S215	MSG-358
FEMJ3E215	MSG-358
FEMJ3S215	MSG-358
FEMLOK215	MSG-359
FEMRCN215	MSG-359
FEMSCN215	MSG-359
FEMTCN215	MSG-360
FEMTPS215	MSG-360
FEMUJI215	MSG-360
FEMUSI215	MSG-361
FEMVCN215	MSG-361
FEMX05215	MSG-361
FEM02F215	MSG-362
FEM1PL215	MSG-362
FEM2H5215	MSG-362
FEM2P4215	MSG-363
FEMACN216	MSG-363
FEMALC216	MSG-363
FEMASY216	MSG-364
FEMCMD216	MSG-364
FEMCOM216	MSG-364
FEMDCN216	MSG-365
FEMDC1216	MSG-365
FEMEXR216	MSG-365
FEMFRA216	MSG-366
FEMFTN216	MSG-366
FEMHCN216	MSG-366
FEMHSP216	MSG-367
FEMIAT216	MSG-367
FEMICN216	MSG-367
FEM IPL216	MSG-368
FEMJS2216	MSG-368
FEMJ2M216	MSG-368
FEMJ2R216	MSG-369
FEMJ2S216	MSG-369
FEMJ3E216	MSG-369
FEMJ3S216	MSG-370
FEMLOK216	MSG-370
FEMRCN216	MSG-370
FEMSCN216	MSG-371
FEMTCN216	MSG-371
FEMTPS216	MSG-371

FEMUJI216	MSG-372
FEMUSI216	MSG-372
FEMVCN216	MSG-372
FEMX05216	MSG-373
FEM02F216	MSG-373
FEM1PL216	MSG-373
FEM2H5216	MSG-374
FEM2P4216	MSG-374
FEMACN217	MSG-374
FEMALC217	MSG-375
FEMASY217	MSG-375
FEMCMD217	MSG-375
FEMCOM217	MSG-376
FEMDCN217	MSG-376
FEMDC1217	MSG-376
FEMEXR217	MSG-377
FEMFRA217	MSG-377
FEMFTN217	MSG-377
FEMHCN217	MSG-378
FEMHSP217	MSG-378
FEMIAT217	MSG-378
FEMICN217	MSG-379
FEM1PL217	MSG-379
FEMJS2217	MSG-379
FEMJ2M217	MSG-380
FEMJ2R217	MSG-380
FEMJ2S217	MSG-380
FEMJ3E217	MSG-381
FEMJ3S217	MSG-381
FEMLOK217	MSG-381
FEMRCN217	MSG-382
FEMSCN217	MSG-382
FEMTCN217	MSG-382
FEMTPS217	MSG-383
FEMUJI217	MSG-383
FEMUSI217	MSG-383
FEMVCN217	MSG-384
FEMX05217	MSG-384
FEM02F217	MSG-384
FEM1PL217	MSG-385
FEM2H5217	MSG-385
FEM2P4217	MSG-385
FEMACT218	MSG-386
FEMB14218	MSG-386
FEM1PL219	MSG-386
FEMX06219	MSG-386
FEMX44219	MSG-387
FEMACN220	MSG-387
FEMDCN220	MSG-387
FEMFRA220	MSG-388
FEMHCN220	MSG-388
FEMHSP220	MSG-388
FEMICN220	MSG-388
FEM1PL220	MSG-389
FEMLIB220	MSG-389
FEMRCN220	MSG-389
FEMSCN220	MSG-390
FEMTCN220	MSG-390
FEMX06222	MSG-390

FEMX09223	MSG-391
FEMX09224	MSG-391
FEMHSP225	MSG-391
FEMHSP226	MSG-391
FEMX24226	MSG-392
FEMX00227	MSG-392
FEM2TP227	MSG-392
FEMJS2228	MSG-392
FEMREL229	MSG-393
FEMX06230	MSG-393
FEMUSI232	MSG-393
FEMACT233	MSG-393
FEMB14233	MSG-394
FEMX06234	MSG-394
FEM2TP235	MSG-394
FEMREL236	MSG-394
FEMIPL237	MSG-395
FEMIPL238	MSG-395
FEMIPL239	MSG-395
FEMIPL240	MSG-396
FEMJS2241	MSG-396
FEM2D0242	MSG-396
FEM2H0242	MSG-397
FEM2L0242	MSG-397
FEM2M0242	MSG-397
FEM2D0243	MSG-397
FEM2H0243	MSG-398
FEM2H4243	MSG-398
FEM2L4243	MSG-398
FEM2M0243	MSG-398
FEM2M4243	MSG-399
FEM2G0244	MSG-399
FEM2G9244	MSG-399
FEM2D0245	MSG-399
FEM2H0245	MSG-400
FEM2H4245	MSG-400
FEM2L0245	MSG-400
FEM2L4245	MSG-401
FEM2M0245	MSG-401
FEM2M4245	MSG-401
FEMX24245	MSG-401
FEM2D1246	MSG-402
FEM2H1246	MSG-402
FEM2L1246	MSG-402
FEM2M1246	MSG-402
FEM2D1247	MSG-403
FEM2H1247	MSG-403
FEM2L1247	MSG-403
FEM2M1247	MSG-403
FEMACT248	MSG-404
FEMX32249	MSG-404
FEMX49249	MSG-404
FEM2DM249	MSG-405
FEM2DM250	MSG-405
FEM2D0250	MSG-405
FEM2HM250	MSG-405
FEM2H0250	MSG-406
FEM2LM250	MSG-406
FEM2L0250	MSG-406

FEM2MM250	MSG-407
FEM2M0250	MSG-407
FEM2HM251	MSG-407
FEMALC252	MSG-407
FEMDAD252	MSG-408
FEMHSM252	MSG-408
FEMISP252	MSG-408
FEMJS2252	MSG-409
FEMJS3252	MSG-409
FEMMIS252	MSG-409
FEMRAC252	MSG-409
FEMSAF252	MSG-410
FEMSMF252	MSG-410
FEMTSO252	MSG-410
FEM2H3253	MSG-411
FEM2D3254	MSG-411
FEMCMD255	MSG-411
FEM2D3256	MSG-411
FEM2TP258	MSG-412
FEMAOD259	MSG-412
FEM2D0260	MSG-412
FEM2H0260	MSG-413
FEM2L0260	MSG-413
FEM2M0260	MSG-413
FEMTEX261	MSG-414
FEMTEX262	MSG-414
FEMTEX263	MSG-414
FEM2LM264	MSG-414
FEMSTM265	MSG-415
FEM2S0266	MSG-415
FEMLOD267	MSG-415
FEMPW1268	MSG-416
FEMLIB269	MSG-416
FEMLIB270	MSG-416
FEMLIB271	MSG-417
FEMLIB272	MSG-417
FEMLIB272	MSG-417
FEMLIB274	MSG-418
FEMLIB275	MSG-418
FEMLIB276	MSG-418
FEMLIB277	MSG-419
FEMLIB278	MSG-419
FEMLIB279	MSG-419
FEMLIB280	MSG-420
FEMLIB281	MSG-420
FEMLIB282	MSG-420
FEMU29283	MSG-421
FEMSMF284	MSG-421
FEMU29284	MSG-421
FEMRAC285	MSG-421
FEMLIB286	MSG-422
FEMLOD287	MSG-422
FEMBB4288	MSG-422
FEMHSP289	MSG-423
FEMX24289	MSG-423
FEMHSP290	MSG-424
FEMHSP291	MSG-424
FEMX24291	MSG-424
FEMHSP292	MSG-425

FEMX24292	MSG-425
FEMHSP293	MSG-425
FEMX24293	MSG-426
FEMHSP294	MSG-426
FEMX24294	MSG-426
FEMHSP295	MSG-427
FEMX24295	MSG-427
FEMREL296	MSG-427
FEMHSP297	MSG-428
FEMLOD297	MSG-428
FEMHSP298	MSG-429
FEMLOD298	MSG-429
FEMHSP299	MSG-430
FEMLOD299	MSG-430
FEMHSP300	MSG-431
FEMLOD300	MSG-431
FEMHSP301	MSG-432
FEMLOD301	MSG-432
FEMHSP302	MSG-433
FEMLOD302	MSG-433
FEMJS2303	MSG-434
FEMLOD304	MSG-434
FEMHSP305	MSG-435
FEMHSP306	MSG-435
FEMLOD307	MSG-435
FEM2TP308	MSG-436
FEMHSP312	MSG-436
FEMHSP313	MSG-436
FEM2TP314	MSG-437
FEMDMP1001	MSG-437
FEMDMP1002	MSG-438
FEMDMP1003	MSG-438
FEMDMP1004	MSG-438
FEM285I	MSG-438

Appendix A. \$HASP Messages for Job Routing (\$HASP6xx & \$HASP9xx)	A-1
Index	Index-1
Reader's Comment Form	READER-1

OS/EM System Codes and Messages

System Codes

Format

Asv-cc

sv: The SVC number in Hex (FF if no JES3 support)

cc: The user completion code

User Completion Code

Asv-0000

Explanation: An invalid return code was received from a User exit from RACF, IEFU84, or IEFU85 when the OS/EM controller routine was in SRB mode.

Source: FEMU84CN, FEMFRACN

System Action: The OS/EM controller module abends and a SVC dump is taken.

Operator Response: Contact the System Programmer

System Programmer Response: Correct the User exit that created the invalid return code. Perform an LLA REFRESH, reload the User exit with OS/EM reload facilities. Contact OS/EM support for assistance in problem resolution.

Asv-0004

Explanation: OS/EM SVC services have been requested by the OS/EM sub-system and the SVC data area in CSA/ECSA is missing.

Source: FEMSVCIF

System Action: The OS/EM SVC interface module abends and a SVC dump is taken.

Operator Response: Contact the System Programmer

System Programmer Response: Control blocks in CSA/ECSA have been overlaid. Drain the MVS system and perform an IPL. Contact OS/EM support for assistance in problem resolution.

Asv-0008

Explanation: OS/EM SVC services have been requested by the OS/EM sub-system and the SVC controller address for FEMSVCCN in the SVC data area is zero.

Source: FEMSVCIF

System Action: The OS/EM SVC interface module abends and a SVC dump is taken.

Operator Response: Contact the System Programmer

System Programmer Response: The SVC data area has been overlaid. Drain the MVS system and perform an IPL. Contact OS/EM support for assistance in problem resolution.

Asv-0012

Explanation: OS/EM SVC services have been requested by the OS/EM sub-system and the SVC table address in the SVC data area is zero.

Source: FEMSVCCN

System Action: The OS/EM SVC controller module abends and a SVC dump is taken.

Operator Response: Contact the System Programmer

System Programmer Response: The SVC data area has been overlaid. Drain the MVS system and perform an IPL. Contact OS/EM support for assistance in problem resolution.

Asv-0016

Explanation: OS/EM SVC services have been requested by the OS/EM sub-system and the original SVC address for SVC26 NOT CATALOGED 2 support, or SVC42 ATTACH used during JES2 or JES3 initialization is zero.

Source: FEMSVCCN

System Action: The OS/EM SVC controller module abends and a SVC dump is taken.

Operator Response: Contact the System Programmer

System Programmer Response: The SVC data area has been overlaid. Drain the MVS system and perform an IPL. Contact OS/EM support for assistance in problem resolution.

Asv-0020

Explanation: OS/EM has requested SRBTIMER services from MVS and the request failed. OS/EM sets an SRBTIMER to insure that User exits running in SRB mode do not go into a CPU loop and lock up the processor. The interval is 5 CPU seconds.

Source: FEMU84CN, FEMFRACN

System Action: The OS/EM SVC controller module abends and a SVC dump is taken.

Operator Response: Contact the System Programmer

System Programmer Response: The MVS operating system has been overlaid. Drain the MVS system and perform an IPL. Contact OS/EM support for assistance in problem resolution.

Asv-0024

Explanation: OS/EM SVC services have been requested by the OS/EM sub-system and the SVC mask byte in the SVC data area is zero.

Source: FEMSVCCN

System Action: The OS/EM SVC controller module abends and a SVC dump is taken.

Operator Response: Contact the System Programmer

System Programmer Response: The SVC data area has been overlaid. Drain the MVS system and perform an IPL. Contact OS/EM support for assistance in problem resolution.

Asv-0028

Explanation: OS/EM lock services have been requested by the OS/EM sub-system and the lock number passed to lock services is invalid.

Source: FEMLOCK

System Action: The OS/EM lock module abends and a SVC dump is taken.

Operator Response: Contact the System Programmer

System Programmer Response: Storage in CSA/ECSA has been overlaid. Drain the MVS system and perform an IPL. Contact OS/EM support for assistance in problem resolution.

Asv-0032

Explanation: OS/EM query services have failed on the PUTLINE macro.

Source: FEMQUERY

System Action: The OS/EM query module abends and a SVC dump is taken.

Operator Response: None

System Programmer Response: Re-issue the OS/EM QUERY command. Contact OS/EM support for assistance in problem resolution.

AFF-0036

Explanation: The OS/EM sub-system Communication Vector Table (CVT) is missing, and subsequently OS/EM does not know what its SVC number is.

Source: FEMSVICIF

System Action: The OS/EM SVC interface module abends and a SVC dump is taken.

Operator Response: None

System Programmer Response: Storage in CSA/ECSA has been overlaid. Drain the MVS system and perform an IPL. Contact OS/EM support for assistance in problem resolution.

JESYSMSG (Allocation) Messages

Message Format

FEMnnns

FEM - Message Prefix

nnn - Message Number

s - Message severity

I - Informational

JESYSMSG Message Text

```
FEM285I dsn dsp
VOL SER NOS=ser,ser,ser,ser,ser
VOL SER NOS=ser,ser,ser
```

Explanation: OS/EM optional NOT CATALOGED 2 support performed the disposition requested for the dataset. The message lists five volume serial numbers per line until all the volumes are listed. A period follows the last volume serial number.

dsn: The dataset name

dsp: One of the following

DELETED - The dataset is deleted

NOT DELETED 6 - No volumes are mounted

NOT DELETED 8 - Some volumes are in error

UNCATALOGED - The dataset is Uncataloged

ser: The serial number of the volumes involved

Source: FEM0002F

System Action: Processing continues

Operator Response: None

System Programmer Response: None

User Response: None

JESMSGLG (SYSLOG) and TSO Messages

Message Format

FEMxxxxnnn

FEM - Message Prefix

xxx - Module Identifier

nnn - Message Number

Error Message Module Identifier

ID	Module
ABN	FEMABEND FEMJ2AB*
ACN	FEMALCCN
ACT	FEMACTRT
AIF	FEMALCIF
ALC	FEMALLOC FEMALLO0 FEMALLO1
AOD	FEMALLOD
ASY	FEMASYNC
ATH	FEMAUTH
BB4	FEMBB410
B14	FEMBR14
CAL	FEMECALL
CMD	FEMCMD
COD	FEMCODE
COM	FEMCOMM
CTL	FEMCNTL
DAD	FEMDASD
DAP	FEMPOOL
DB4	FEMDB401
DCN	FEMDADCN
DC1	FEMDCB1
DEL	FEMDEL
DIF	FEMDADIF
DMP	FEMDUMP
ENF	FEMENF
EOM	FEMEOM

ID	Module
EOT	FEMEOT
EXR	FEMEXRTN
FIF	FEMFRAIF
FRA	FEMFRACN
FTN	FEMFRRTN
F10	FEMEFF10
GTI	FEMGETWI
GTW	FEMGETWK
HCN	FEMHSMCN
HIF	FEMHSMIF
HSM	FEMHSM FEMHSM0 FEMHSM1 FEMHSM2 FEMHSM3
HSP	FEMHJ20
IAT	FEMINTK
ICN	FEMISPCN
IIF	FEMISPIF
INT	FEMINIT
IPL	FEMIPL
ISP	FEMISPF
I16	FEMEXT16
JRS	FEMJ2RES
JS#	FEMJES2

ID	Module
JS2	FEMJES2A FEMJES2B FEMJES2C FEMJES2D FEMJES2E FEMJES2F FEMJES2G FEMJES2H
JS3	FEMJES3
J2D	FEMJ2DEL
J2E	FEMJ2ESx
J2I	FEMJ2ITx
J2J	FEMJ2JCx
J2M	FEMJ2MCx
J2R	FEMJ2ERx
J2S	FEMJ2SCx
J3E	FEMJ3ECN
J3I	FEMJ3ITF
J3S	FEMJ3SVC
LD1	FEMFLD1
LIB	FEMLIB
LIM	FEMLIMIT
LOD	FEMLOAD
LOK	FEMLOCK
MIS	FEMMISC
NUL	FEMNUL*
OPC	FEMOPCMD
PGI	FEMPGINT
PRE	FEMPRE00
PW1	FEMPWX01

ID	Module
QRY	FEMQUERY
RAC	FEMRACF
RCN	FEMRACCN
RCU	FEMRACUP FEMSAFUP
RCV	FEMRCSTK
RC2	FEMRCX02
RD1	FEMRDX01
REL	FEMRELOD
RIF	FEMRACIF
RPE	FEMRPEXT
SAF	FEMSAF
SCH	FEMTSSCH
SCN	FEMSAFCN FEMSMFCN
SIF	FEMSAFIF FEMSMFIF
SMF	FEMSMF*
STM	FEMSYSTEM
SVU	FEMSVUCUD
S19	FEM0001I
S20	FEM00020
S22	FEM0002B
S31	FEM0003A
S34	FEMSV34
S35	FEM0003E
S42	FEM0004B
TCN	FEMTSOCN
TEX	FEMTEXTIT
THI	FEMTHRDI
THT	FEMTHRDT
TIF	FEMTSOIF
TPS	FEMTPSHR
TSO	FEMTSO
TSU	FEMTSOUP
UJI	FEMUJI
USI	FEMUSI
USO	FEMUSO
UTL	FEMUTL

ID	Module
UXA	FEMUXABN
UXW	FEMUXWTO
U29	FEMU29
U83	FEMU83
VCN	FEMSVCCN
WTO	FEMWTO*
WTX	FEMWTOX
W21	FEMW21SD
X00	FEMJ2X00 FEMXIT0*
X02	FEMJ2X02
X04	FEMJ2X04
X05	FEMJ2X05
X06	FEMJ2X06
X09	FEMJ2X09
X14	FEMJ2X14
X24	FEMJ2X24
X28	FEMJ2X28
X29	FEMJ2X29
X32	FEMJ2N32 FEMJ2X32
X44	FEMJ2X44
X49	FEMJ2X49
02F	FEM0002F
1PL	FEM1PL1
2DM	FEMJ2DJx FEMJ2DMx
2D0	FEMJ2D0x
2D1	FEMJ2D1x
2D2	FEMJ2D2x
2D3	FEMJ2D3x
2GM	FEMJ2GMx
2G0	FEMJ2G0x
2G2	FEMJ2G2x
2G3	FEMJ2G3x
2G4	FEMJ2G4x
2G9	FEMJ2G9x
2HM	FEMJ2HMx
2H0	FEMJ2H0x

ID	Module
2H1	FEMJ2H1x
2H3	FEMJ2H3x
2H3	FEMJ2L3x
2H4	FEMJ2H4x
2H5	FEMJ2H5x
2LM	FEMJ2LMx
2L0	FEMJ2L0x
2L1	FEMJ2L1x
2L4	FEMJ2L4x
2MM	FEMJ2MMx
2M0	FEMJ2M0x
2M1	FEMJ2M1x
2M2	FEMJ2M2x
2M3	FEMJ2M3x
2M4	FEMJ2M4x
2P1	FEMJ2P1x
2P2	FEMJ2P2x
2P3	FEMJ2P3x
2P4	FEMJ2P4x
2P5	FEMJ2P5x
2P6	FEMJ2P6x
2P7	FEMJ2P7x
2RS	FEMJ2RES
2S0	FEMJ2S0x
2TP	FEMJ2TPx

Message Text

FEMxxx000

(UNDEFINED MESSAGE NUMBER)

Explanation: A message has been requested from the FEMMSG program, but the message number being requested does not exist.

Source: Unknown

System Action: Processing continues.

Operator Response: None.

System Programmer Response: Contact OS/EM support for assistance in problem resolution.

FEM IPL001

OS/EM CVT SUCCESSFULLY CREATED

Explanation: During OS/EM Sub-system Initialization the OS/EM Communication Vector Table (CVT) has been created without errors.

Source: FEM IPL

System Action: The CVT has been created.

Operator Response: None.

System Programmer Response: None.

FEM IPL002

START COMMAND ISSUED FOR *jjjj*

Explanation: During OS/EM Sub-system Initialization the start command has been issued for the Batch TMP procedure to load OS/EM options.

***jjjj*:** Sub-system name as defined in IEFSSN00 member in SYS1.PARMLIB.

Source: FEM IPL

System Action: START command issued.

Operator Response: None.

System Programmer Response: None.

FEMALC003

START COMMAND FOR FEMTPSHR FAILED

Explanation: The MGCRC macro used to issue a start command for the FEMTPSHR started task received a non-zero return code.

Source: FEMALLO1

System Action: The START command was not issued.

Operator Response: Issue the following command:

S FEMTPSHR.FEMTPSHR, SUB=MSTR

If that command fails, notify the systems programmer.

System Programmer Response: Review the system log to determine the cause of the failure.

FEMIPL003

START COMMAND FOR OSEM FAILED

Explanation: During OS/EM subsystem initialization the start command was issued for the Batch TMP procedure to load OS/EM options but has failed.

Source: FEMIPL

System Action: The START command was not issued.

Operator Response: None.

System Programmer Response: Review the system log to determine the cause of the failure. Initialize the OS/EM subsystem by issuing the command:

S OSEM, SUB=MSTR

FEMCTL004

OS/EM CVT AT WRONG LEVEL

Explanation: During OS/EM Initialization it was determined that the OS/EM CVT has already been built, and is not at the Release level required by the program currently executing.

Source: FEMCNTL

System Action: FEMCNTL ends with a Return Code of 16 and stops initialization.

Operator Response: Contact Systems Programmer.

System Programmer Response: Check and verify that the OS/EM load library hasn't been restored or replaced since OS/EM was started during the last IPL. Contact OS/EM support for assistance in problem resolution.

FEMHSP004

OS/EM CVT AT WRONG LEVEL

Explanation: During OS/EM Initialization it was determined that the OS/EM CVT has already been built, and is not at the Release level required by the program currently executing.

Source: FEMHJ20

System Action: FEMHJ20 ends with a Return Code of 16 and stops initialization.

Operator Response: Contact Systems Programmer.

System Programmer Response: Check and verify that the OS/EM load library hasn't been restored or replaced since OS/EM was started during the last IPL. Contact OS/EM support for assistance in problem resolution.

FEMIAT004

OS/EM CVT AT WRONG LEVEL

Explanation: During OS/EM Initialization it was determined that the OS/EM CVT has already been built, and is not at the Release level required by the program currently executing.

Source: FEMINTK

System Action: FEMINTK ends with a Return Code of 16 and stops initialization.

Operator Response: Contact Systems Programmer.

System Programmer Response: Check and verify that the OS/EM load library hasn't been restored or replaced since OS/EM was started during the last IPL. Contact OS/EM support for assistance in problem resolution.

FEMINT004

OS/EM CVT AT WRONG LEVEL

Explanation: During OS/EM Initialization it was determined that the OS/EM CVT has already been built, and is not at the Release level required by the program currently executing.

Source: FEMINIT

System Action: FEMINIT ends with a Return Code of 16 and stops initialization.

Operator Response: Contact Systems Programmer.

System Programmer Response: Check and verify that the OS/EM load library hasn't been restored or replaced since OS/EM was started during the last IPL. Contact OS/EM support for assistance in problem resolution.

FEMIPL004

OS/EM CVT AT WRONG LEVEL

Explanation: During OS/EM Initialization it was determined that the OS/EM CVT has already been built, and is not at the Release level required by the program currently executing.

Source: FEMIPL

System Action: FEMIPL ends with a Return Code of 16 and stops initialization.

Operator Response: Contact Systems Programmer.

System Programmer Response: Check and verify that the OS/EM load library hasn't been restored or replaced since OS/EM was started during the last IPL. Contact OS/EM support for assistance in problem resolution.

FEMLIB004

OS/EM CVT AT WRONG LEVEL

Explanation: During OS/EM Initialization it was determined that the OS/EM CVT has already been built, and is not at the Release level required by the program currently executing.

Source: FEMLIB

System Action: FEMLIB ends with a Return Code of 16 and stops initialization.

Operator Response: Contact Systems Programmer.

System Programmer Response: Check and verify that the OS/EM load library hasn't been restored or replaced since OS/EM was started during the last IPL. Contact OS/EM support for assistance in problem resolution.

FEMTPS004

OS/EM CVT AT WRONG LEVEL

Explanation: During OS/EM Initialization it was determined that the OS/EM CVT has already been built, and is not at the Release level required by the program currently executing.

Source: FEMTPSHR

System Action: FEMTPSHR ends with a Return Code of 16 and stops initialization.

Operator Response: Contact Systems Programmer.

System Programmer Response: Check and verify that the OS/EM load library hasn't been restored or replaced since OS/EM was started during the last IPL. Contact OS/EM support for assistance in problem resolution.

FEMIPL006

SVC TABLE UPDATE FAILED FOR SVC nnn RC = rr

Explanation: During OS/EM Sub-system Initialization FEMIPL has failed when issuing the SVCUPDTE macro to install the OS/EM SVC. The SVC number was specified in the IEFSSN00 member in SYS1.PARMLIB for Sub-system Initialization of OS/EM or during OS/EM automatic selection of a SVC number.

nnn: SVC Number selected for OS/EM Sub-system Initialization as specified in IEFSSN00 in SYS1.PARMLIB or during OS/EM automatic selection of a SVC number.

rr: Return code from SVCUPDTE macro.

Source: FEMIPL

System Action: FEMIPL ends with a Return Code of 16 and stops the Sub-system Initialization of OS/EM.

Operator Response: Contact Systems Programmer.

System Programmer Response: Look up the Return code displayed in the message and determine what action should be taken. Contact OS/EM support for assistance in problem resolution.

FEMSVU006

SVC TABLE UPDATE FAILED FOR SVC nnn RC = rr

Explanation: During OS/EM Sub-system Initialization FEMIPL has failed when issuing the SVCUPDTE macro to install the OS/EM SVC. The SVC number was specified in the IEFSSN00 member in SYS1.PARMLIB for Sub-system Initialization of OS/EM or during OS/EM automatic selection of a SVC number.

nnn: SVC Number selected for OS/EM Sub-system Initialization as specified in IEFSSN00 in SYS1.PARMLIB or during OS/EM automatic selection of a SVC number.

rr: Return code from SVCUPDTE macro.

Source: FEMSVUCUD

System Action: FEM IPL ends with a Return Code of 16 and stops the Sub-system Initialization of OS/EM.

Operator Response: Contact Systems Programmer.

System Programmer Response: Look up the Return code displayed in the message and determine what action should be taken. Contact OS/EM support for assistance in problem resolution.

FEM IPL007

INTERFACE MODULE program PROCESSED SUCCESSFULLY

Explanation: During OS/EM Sub-system Initialization FEM IPL has successfully loaded the interface module program. For some interface modules, this message also indicates OS/EM has also processed the pre-existing modules (e.g. IEFUTL, etc..) and updated OS/EM CVT to access these modules as the first user EXIT.

program: OS/EM interface module name

Source: FEM IPL

System Action: FEM IPL continues with OS/EM Sub-system Initialization, informational only.

Operator Response: None.

System Programmer Response: None.

FEM IPL008

PARM=zzzzzzzz

Explanation: During OS/EM Sub-system Initialization FEM IPL detected that the parm field as specified in the IEFSSN00 member in SYS1.PARMLIB is invalid, or the operator has replied to message FEM IPL010 with an invalid OS/EM Sub-system parm.

zzzzzzzz: Parm field as specified in IEFSSN00 member in SYS1.PARMLIB for OS/EM Sub-system Initialization, or as entered by the operator in response to message FEM IPL010.

Source: FEM IPL

System Action: FEM IPL issues messages FEM IPL009 and FEM IPL010 prompts the operator to enter a valid parm to be passed to OS/EM Sub-system Initialization.

Operator Response: Contact the System Programmer and reply to FEM IPL010 as instructed by the System Programmer.

System Programmer Response: Correct the IEFSSN00 member in SYS1.PARMLIB and/or instruct the operator as to the correct reply to message FEM IPL010.

FEM IPL009

PARM FIELD IS INVALID; ERROR AT OR NEAR POSITION xxx

Explanation: During OS/EM Sub-system Initialization FEM IPL detected that the parm field as specified in the IEFSSN00 member in SYS1.PARMLIB is invalid, or the operator has replied to message FEM IPL010 with an invalid OS/EM Sub-system parm.

xxx: The column position where the error is located.

Source: FEM IPL

System Action: FEM IPL issues messages FEM IPL008 and FEM IPL010 prompts the operator to enter a valid parm to be passed to OS/EM Sub-system Initialization.

Operator Response: Contact the System Programmer and reply to FEM IPL010 as instructed by the System Programmer.

System Programmer Response: Correct the IEFSSN00 member in SYS1.PARMLIB and/or instruct the operator as to the correct reply to message FEM IPL010.

FEM IPL010

REENTER PARM VALUE

Explanation: During OS/EM Sub-system Initialization FEM IPL detected that the parm field as specified in the IEFSSN00 member in SYS1.PARMLIB is invalid, or the operator has replied to message FEM IPL010 with an invalid OS/EM Sub-system parm.

Source: FEM IPL

System Action: FEM IPL issues messages FEM IPL008, FEM IPL009 and prompts the operator to enter a valid parm to be passed to OS/EM Sub-system Initialization.

Operator Response: Contact the System Programmer and reply to FEM IPL010 as instructed by the System Programmer.

System Programmer Response: Correct the IEFSSN00 member in SYS1.PARMLIB and/or instruct the operator as to the correct reply to message FEM IPL010.

FEM IPL012

EXIT program PROCESSED

Explanation: During OS/EM Sub-system Initialization, FEM IPL has successfully built the CDE entry for exit point program that points to the OS/EM interface module.

program: Exit point name being processed.

Source: FEM IPL

System Action: FEM IPL continues initialization of the OS/EM Sub-system.

Operator Response: None.

System Programmer Response: None.

FEM HSP013

LOAD ABEND aaa-rc

Explanation: Either during OS/EM Sub-system Initialization or during execution of the FEMCNTL functions in either ISPF or the batch TMP that sets OS/EM options a module was not loaded for reason aaa-rc.

aaa-rc: MVS System Code or OS/EM Pseudo Code and return code.

Source: FEM HJ20

System Action: OS/EM function being executed continues, but the program identified in other message numbers FEMxxx017, FEMxxx021, FEMxxx030 etc. is not loaded.

Operator Response: Contact System Programmer.

System Programmer Response: Pseudo abend codes are provided by OS/EM they are:

- 000-2 Module not suitable (OVLY or SCTR)
- 000-4 Module not RENT
- 000-5 JES2 Offset Table not available
- 000-6 Entry not found in module
- 000-7 JES2 module is an invalid format
- 000-8 Module is wrong version
- 000-9 Module is wrong JES2 version
- 000-A Loadlib allocation failed
- 000-C Loadlib open failed
- 000-D JES2 offset adjustment failed
- 000-E Module is not suitable (JES2 module in LPA)
- 000-F Module is not suitable (disallowed BR14)

Also see MVS System Codes, correct failing program and or situation and resubmit the command.

FEMLOD013

LOAD ABEND aaa-rc

Explanation: Either during OS/EM Sub-system Initialization or during execution of the FEMCNTL functions in either ISPF or the batch TMP that sets OS/EM options a module was not loaded for reason aaa-rc.

aaa-rc: MVS System Code or OS/EM Pseudo Code and return code.

Source: FEMLOAD

System Action: OS/EM function being executed continues, but the program identified in other message numbers FEMxxx017, FEMxxx021, FEMxxx030 etc. is not loaded.

Operator Response: Contact System Programmer.

System Programmer Response: Pseudo abend codes are provided by OS/EM they are:

- 000-2 Module not suitable (OVLY or SCTR)
- 000-4 Module not RENT
- 000-5 JES2 Offset Table not available
- 000-6 Entry not found in module
- 000-7 JES2 module is an invalid format
- 000-8 Module is wrong version
- 000-9 Module is wrong JES2 version
- 000-A Loadlib allocation failed
- 000-C Loadlib open failed
- 000-D JES2 offset adjustment failed
- 000-E Module is not suitable (JES2 module in LPA)
- 000-F Module is not suitable (disallowed BR14)

Also see MVS System Codes, correct failing program and or situation and resubmit the command.

FEMS19013

LOAD ABEND aaa-rc

Explanation: Either during OS/EM Sub-system Initialization or during execution of the FEMCNTL functions in either ISPF or the batch TMP that sets OS/EM options a module was not loaded for reason aaa-rc.

aaa-rc: MVS System Code or OS/EM Pseudo Code and return code.

Source: FEM0001I

System Action: OS/EM function being executed continues, but the program identified in other message numbers FEMxxx017, FEMxxx021, FEMxxx030 etc. is not loaded.

Operator Response: Contact System Programmer.

System Programmer Response: Pseudo abend codes are provided by OS/EM they are:

- 000-2 Module not suitable (OVLY or SCTR)
- 000-4 Module not RENT
- 000-5 JES2 Offset Table not available
- 000-6 Entry not found in module
- 000-7 JES2 module is an invalid format
- 000-8 Module is wrong version
- 000-9 Module is wrong JES2 version
- 000-A Loadlib allocation failed
- 000-C Loadlib open failed
- 000-D JES2 offset adjustment failed
- 000-E Module is not suitable (JES2 module in LPA)
- 000-F Module is not suitable (disallowed BR14)

Also see MVS System Codes, correct failing program and or situation and resubmit the command.

FEMS22013

LOAD ABEND aaa-rc

Explanation: Either during OS/EM Sub-system Initialization or during execution of the FEMCNTL functions in either ISPF or the batch TMP that sets OS/EM options a module was not loaded for reason aaa-rc.

aaa-rc: MVS System Code or OS/EM Pseudo Code and return code.

Source: FEM0002B

System Action: OS/EM function being executed continues, but the program identified in other message numbers FEMxxx017, FEMxxx021, FEMxxx030 etc. is not loaded.

Operator Response: Contact System Programmer.

System Programmer Response: Pseudo abend codes are provided by OS/EM they are:

- 000-2 Module not suitable (OVLY or SCTR)
- 000-4 Module not RENT
- 000-5 JES2 Offset Table not available
- 000-6 Entry not found in module
- 000-7 JES2 module is an invalid format
- 000-8 Module is wrong version
- 000-9 Module is wrong JES2 version
- 000-A Loadlib allocation failed
- 000-C Loadlib open failed
- 000-D JES2 offset adjustment failed
- 000-E Module is not suitable (JES2 module in LPA)
- 000-F Module is not suitable (disallowed BR14)

Also see MVS System Codes, correct failing program and or situation and resubmit the command.

FEMLOD014

MODULE NOT SUITABLE (reason)

Explanation:

This message accompanies FEMLOD017. OS/EM has determined that the named load module should not be loaded for one of the following reasons:

- (OVLY, SCTR, NOT RENT) - the attributes of the load module is not compatible for the function that it is intended to perform (e.g. a certain user exit may be required to be re-entrant but the load module is not).
- (DISALLOWED BR14) - OS/EM has determined that the load module is a 'stub' module (i.e. simply returns straight back to the caller) and, as such, performs no useful function.

Source: FEMLOAD

System Action: None

Operator Response: None

System Programmer Response:

If the load module is in error, correct the linkage editor statements, relink the failing program, perform LLA refresh as appropriate and reload the module through the OS/EM ISPF dialog.

If the load module is a stub then this can be treated as an informational message. Stub modules can be removed from LPA / LNKLIST in order to prevent the message from being issued.

FEMLOD015

MODULE IS WRONG VERSION

Explanation: During the execution of loading either an OS/EM module, or a user defined exit point module, the module identified in a previous message was determined to be at different version than the version currently being executed.

Source: FEMLOAD

System Action: OS/EM function being executed continues, but the program identified in other message number FEMxxx017 is not loaded.

Operator Response: Contact System Programmer.

System Programmer Response: Check LINKLIST, STEPLIB, JOBLIB, and ISPLLIB concatenation to find bad version of module being loaded and re-issue the OS/EM command that failed.

FEMIPLO16

OS/EM REQUIRES OS/390 Release 2.7 or later

Explanation: During OS/EM Sub-system Initialization OS/EM determined that the operating system OS/EM is running on is not a supported operating system release.

Source: FEMIPLO

System Action: OS/EM Sub-system Initialization stops.

Operator Response: Contact System Programmer.

System Programmer Response: Check that an OS/390 or z/OS system is the target system for OS/EM Initialization. Contact OS/EM support for assistance in problem resolution.

FEMHSP017

MODULE program LOAD FAILED

Explanation: During the of loading either an OS/EM module, or a user defined exit point module, the module identified by program was not loaded.

program: The module name that OS/EM attempted to load.

Source: FEMHJ20

System Action: OS/EM function being executed continues, but the program identified is not loaded. Other messages will follow with information with information as to what caused the load to fail.

Operator Response: Contact System Programmer.

System Programmer Response: Refer to the messages following this one and take the action indicated by those messages.

FEMLOD017

MODULE program LOAD FAILED

Explanation: During the of loading either an OS/EM module, or a user defined exit point module, the module identified by program was not loaded.

program: The module name that OS/EM attempted to load.

Source: FEMLOAD

System Action: OS/EM function being executed continues, but the program identified is not loaded. Other messages will follow with information with information as to what caused the load to fail.

Operator Response: Contact System Programmer.

System Programmer Response: Refer to the messages following this one and take the action indicated by those messages.

FEMS19017

MODULE program LOAD FAILED

Explanation: During the of loading either an OS/EM module, or a user defined exit point module, the module identified by program was not loaded.

program: The module name that OS/EM attempted to load.

Source: FEM0001I

System Action: OS/EM function being executed continues, but the program identified is not loaded. Other messages will follow with information with information as to what caused the load to fail.

Operator Response: Contact System Programmer.

System Programmer Response: Refer to the messages following this one and take the action indicated by those messages.

FEMS22017

MODULE program LOAD FAILED

Explanation: During the of loading either an OS/EM module, or a user defined exit point module, the module identified by program was not loaded.

program: The module name that OS/EM attempted to load.

Source: FEM0002B

System Action: OS/EM function being executed continues, but the program identified is not loaded. Other messages will follow with information with information as to what caused the load to fail.

Operator Response: Contact System Programmer.

System Programmer Response: Refer to the messages following this one and take the action indicated by those messages.

FEMLOD018

{subsystem} MODULE program LOADED (loadaddr) {VERSION verinfo}

Explanation: During OS/EM Sub-system or optional exit module loading, module program has been loaded successfully.

subsystem: The subsystem that the module operates with (e.g. JES2)

program: Exit point name being processed.

loadaddr: The load address of the module.

verinfo: The version number and generation date & time of module. This applies only to OS/EM system modules.

Source: FEMLOAD

System Action: OS/EM continues.

Operator Response: None.

System Programmer Response: None.

FEMIPL019

program INTERCEPT FAILED. ctlfield= xxxxxxxx {yyyyyyyy}

Explanation: During OS/EM Sub-system Initialization OS/EM was unable to establish the intercept routine for program. The control blocks for intercept program were modified during OS/EM Sub-system Initialization, and OS/EM was unable to continue processing.

program The program name.

ctlfield: The name of system control block field being displayed.

xxxxxxx: The contents of the first fullword of the displayed control field.

yyyyyyyy: The contents of the second fullword of the displayed control field (if applicable).

Source: FEMIPL

System Action: OS/EM Sub-system Initialization ends with a Return code 16.

Operator Response: Contact System Programmer.

System Programmer Response: Re-IPL. Contact OS/EM support for assistance in problem resolution.

FEM IPL020

FEM IPL ENDED - RC = nn

Explanation: During OS/EM Sub-system Initialization, FEM IPL has ended with a return code of nn.

nn Return code set by FEM IPL.

00 OS/EM Sub-system Initialization was successful.

08 One or more OS/EM modules were not successfully loaded, see previous messages for reasons.

16 OS/EM Sub-system Initialization failed, see previous messages for reasons.

Source: FEM IPL

System Action: FEM IPL has ended. If the return code is 00 OS/EM starts the batch TMP (OSEM) to set OS/EM options.

Operator Response: If the return code is 08 or 16 contact the System Programmer.

System Programmer Response: If the return code is a 00 no action is required. If the return code is 08 one or more OS/EM modules may not have been loaded, there will be messages preceding FEM IPL020 detailing what has failed. If the return code is 16 OS/EM Sub-system Initialization has failed and there will be messages preceding FEM IPL020 detailing what has failed. Correct failing components as detailed by the preceding messages and Re-IPL. Contact OS/EM support for assistance in problem resolution.

FEM AIF021

subsystem CONTROLLER MODULE module NOT LOADED

Explanation: During OS/EM exit processing the controller module was not loaded and cannot be executed.

subsystem: The subsystem that the controller module relates to (e.g. JES2)

module: The name of the module that could not be loaded.

Source: FEMALCIF

System Action: The OS/EM function identified by this message is not being executed. OS/EM functions continue for all other functions.

Operator Response: Contact System Programmer.

System Programmer Response: Refer to the messages preceding FEM AIF021, and take the corrective action as indicated by those messages. RELOAD the controller module that has failed. Contact OS/EM support for assistance in problem resolution.

FEM DIF021

subsystem CONTROLLER MODULE module NOT LOADED

Explanation: During OS/EM exit processing the controller module was not loaded and cannot be executed.

subsystem: The subsystem that the controller module relates to (e.g. JES2)

module: The name of the module that could not be loaded.

Source: FEMALCIF

System Action: The OS/EM function identified by this message is not being executed. OS/EM functions continue for all other functions.

Operator Response: Contact System Programmer.

System Programmer Response: Refer to the messages preceding FEMDIF021, and take the corrective action as indicated by those messages. RELOAD the controller module that has failed. Contact OS/EM support for assistance in problem resolution.

FEMFIF021

subsystem CONTROLLER MODULE module NOT LOADED

Explanation: During OS/EM exit processing the controller module was not loaded and cannot be executed.

subsystem: The subsystem that the controller module relates to (e.g. JES2)

module: The name of the module that could not be loaded.

Source: FEMFRAIF

System Action: The OS/EM function identified by this message is not being executed. OS/EM functions continue for all other functions.

Operator Response: Contact System Programmer.

System Programmer Response: Refer to the messages preceding FEMFIF021, and take the corrective action as indicated by those messages. RELOAD the controller module that has failed. Contact OS/EM support for assistance in problem resolution.

FEMHIF021

subsystem CONTROLLER MODULE module NOT LOADED

Explanation: During OS/EM exit processing the controller module was not loaded and cannot be executed.

subsystem: The subsystem that the controller module relates to (e.g. JES2)

module: The name of the module that could not be loaded.

Source: FEMHSMIF

System Action: The OS/EM function identified by this message is not being executed. OS/EM functions continue for all other functions.

Operator Response: Contact System Programmer.

System Programmer Response: Refer to the messages preceding FEMHIF021, and take the corrective action as indicated by those messages. RELOAD the controller module that has failed. Contact OS/EM support for assistance in problem resolution.

FEMIIF021

subsystem CONTROLLER MODULE module NOT LOADED

Explanation: During OS/EM exit processing the controller module was not loaded and cannot be executed.

subsystem: The subsystem that the controller module relates to (e.g. JES2)

module: The name of the module that could not be loaded.

Source: FEMISPIF

System Action: The OS/EM function identified by this message is not being executed. OS/EM functions continue for all other functions.

Operator Response: Contact System Programmer.

System Programmer Response: Refer to the messages preceding FEMIIF021, and take the corrective action as indicated by those messages. RELOAD the controller module that has failed. Contact OS/EM support for assistance in problem resolution.

FEMJ2I021

subsystem CONTROLLER MODULE module NOT LOADED

Explanation: During OS/EM exit processing the controller module was not loaded and cannot be executed.

subsystem: The subsystem that the controller module relates to (e.g. JES2)

module: The name of the module that could not be loaded.

Source: FEMJ2ITx

System Action: The OS/EM function identified by this message is not being executed. OS/EM functions continue for all other functions.

Operator Response: Contact System Programmer.

System Programmer Response: Refer to the messages preceding FEMJ2I021, and take the corrective action as indicated by those messages. RELOAD the controller module that has failed. Contact OS/EM support for assistance in problem resolution.

FEMJ3I021

subsystem CONTROLLER MODULE module NOT LOADED

Explanation: During OS/EM exit processing the controller module was not loaded and cannot be executed.

subsystem: The subsystem that the controller module relates to (e.g. JES2)

module: The name of the module that could not be loaded.

Source: FEMJ3ITF

System Action: The OS/EM function identified by this message is not being executed. OS/EM functions continue for all other functions.

Operator Response: Contact System Programmer.

System Programmer Response: Refer to the messages preceding FEMJ3I021, and take the corrective action as indicated by those messages. RELOAD the controller module that has failed. Contact OS/EM support for assistance in problem resolution.

FEMRIF021

subsystem CONTROLLER MODULE module NOT LOADED

Explanation: During OS/EM exit processing the controller module was not loaded and cannot be executed.

subsystem: The subsystem that the controller module relates to (e.g. JES2)

module: The name of the module that could not be loaded.

Source: FEMRACIF

System Action: The OS/EM function identified by this message is not being executed. OS/EM functions continue for all other functions.

Operator Response: Contact System Programmer.

System Programmer Response: Refer to the messages preceding FEMRIF021, and take the corrective action as indicated by those messages. RELOAD the controller module that has failed. Contact OS/EM support for assistance in problem resolution.

FEMSIF021

subsystem CONTROLLER MODULE module NOT LOADED

Explanation: During OS/EM exit processing the controller module was not loaded and cannot be executed.

subsystem: The subsystem that the controller module relates to (e.g. JES2)

module: The name of the module that could not be loaded.

Source: FEMSAFIF,FEMSMFIF

System Action: The OS/EM function identified by this message is not being executed. OS/EM functions continue for all other functions.

Operator Response: Contact System Programmer.

System Programmer Response: Refer to the messages preceding FEMSIF021, and take the corrective action as indicated by those messages. RELOAD the controller module that has failed. Contact OS/EM support for assistance in problem resolution.

FEMTIF021

subsystem CONTROLLER MODULE module NOT LOADED

Explanation: During OS/EM exit processing the controller module was not loaded and cannot be executed.

subsystem: The subsystem that the controller module relates to (e.g. JES2)

module: The name of the module that could not be loaded.

Source: FEMTSOIF

System Action: The OS/EM function identified by this message is not being executed. OS/EM functions continue for all other functions.

Operator Response: Contact System Programmer.

System Programmer Response: Refer to the messages preceding FEMTIF021, and take the corrective action as indicated by those messages. RELOAD the controller module that has failed. Contact OS/EM support for assistance in problem resolution.

FEMX00021

subsystem CONTROLLER MODULE module NOT LOADED

Explanation: During OS/EM exit processing the controller module was not loaded and cannot be executed.

subsystem: The subsystem that the controller module relates to (e.g. JES2)

module: The name of the module that could not be loaded.

Source: FEMXIT0x

System Action: The OS/EM function identified by this message is not being executed. OS/EM functions continue for all other functions.

Operator Response: Contact System Programmer.

System Programmer Response: Refer to the messages preceding FEMX00021, and take the corrective action as indicated by those messages. RELOAD the controller module that has failed. Contact OS/EM support for assistance in problem resolution.

FEMCTL022

UNABLE TO ESTABLISH ESTAE IN MODULE FEMCNTL - RC = nn

Explanation: During the execution of module FEMCNTL, the module FEMCNTL was unable to establish an ESTAE environment.

nn: Return code from the ESATE macro.

Source: FEMCNTL

System Action: The OS/EM module takes a SVC dump, disables the module, and deletes the module from storage. All functions related to this module are disabled.

Operator Response: Contact System Programmer.

System Programmer Response: Take the corrective action as indicated in the IBM Supervisor Services ESTAE macro reference. RELOAD the controller module using OS/EM functions. Contact OS/EM support for assistance in problem resolution.

FEMDC1022

UNABLE TO ESTABLISH ESTAE IN MODULE FEMDCB1 - RC = nn

Explanation: During the execution of module FEMDCB1, the module FEMDCB1 was unable to establish an ESTAE environment.

nn: Return code from the ESATE macro.

Source: FEMDCB1

System Action: The OS/EM module takes a SVC dump, disables the module, and deletes the module from storage. All functions related to this module are disabled.

Operator Response: Contact System Programmer.

System Programmer Response: Take the corrective action as indicated in the IBM Supervisor Services ESTAE macro reference. RELOAD the controller module using OS/EM functions. Contact OS/EM support for assistance in problem resolution.

FEMIPLO22

UNABLE TO ESTABLISH ESTAE IN MODULE FEMIPPL - RC = nn

Explanation: During the execution of module FEMIPPL, the module FEMIPPL was unable to establish an ESTAE environment.

nn: Return code from the ESATE macro.

Source: FEMIPPL

System Action: The OS/EM module takes a SVC dump, disables the module, and deletes the module from storage. All functions related to this module are disabled.

Operator Response: Contact System Programmer.

System Programmer Response: Take the corrective action as indicated in the IBM Supervisor Services ESTAE macro reference. RELOAD the controller module using OS/EM functions. Contact Contact OS/EM support for assistance in problem resolution.

FEMLIB022

UNABLE TO ESTABLISH ESTAE IN MODULE FEMLIB - RC = nn

Explanation: During the execution of module FEMLIB, the module FEMLIB was unable to establish an ESTAE environment.

nn: Return code from the ESATE macro.

Source: FEMLIB

System Action: The OS/EM module takes a SVC dump, disables the module, and deletes the module from storage. All functions related to this module are disabled.

Operator Response: Contact System Programmer.

System Programmer Response: Take the corrective action as indicated in the IBM Supervisor Services ESTAE macro reference. RELOAD the controller module using OS/EM functions. Contact Contact OS/EM support for assistance in problem resolution.

FEMTHI022

UNABLE TO ESTABLISH ESTAE IN MODULE FEMTHRDI - RC = nn

Explanation: During the execution of module FEMTHRDI, the module FEMTHRDI was unable to establish an ESTAE environment.

nn: Return code from the ESATE macro.

Source: FEMTHRDI

System Action: The OS/EM module takes a SVC dump, disables the module, and deletes the module from storage. All functions related to this module are disabled.

Operator Response: Contact System Programmer.

System Programmer Response: Take the corrective action as indicated in the IBM Supervisor Services ESTAE macro reference. RELOAD the controller module using OS/EM functions. Contact Contact OS/EM support for assistance in problem resolution.

FEMTPS022

UNABLE TO ESTABLISH ESTAE IN MODULE FEMTPSHR - RC = nn

Explanation: During the execution of module FEMTPSHR, the module FEMTPSHR was unable to establish an ESTAE environment.

nn: Return code from the ESATE macro.

Source: FEMTPSHR

System Action: The OS/EM module takes a SVC dump, disables the module, and deletes the module from storage. All functions related to this module are disabled.

Operator Response: Contact System Programmer.

System Programmer Response: Take the corrective action as indicated in the IBM Supervisor Services ESTAE macro reference. RELOAD the controller module using OS/EM functions. Contact OS/EM support for assistance in problem resolution.

FEMUSI022

UNABLE TO ESTABLISH ESTAE IN MODULE FEMUSI - RC = nn

Explanation: During the execution of module FEMUSI, the module FEMUSI was unable to establish an ESTAE environment.

nn: Return code from the ESATE macro.

Source: FEMUSI

System Action: The OS/EM module takes a SVC dump, disables the module, and deletes the module from storage. All functions related to this module are disabled.

Operator Response: Contact System Programmer.

System Programmer Response: Take the corrective action as indicated in the IBM Supervisor Services ESTAE macro reference. RELOAD the controller module using OS/EM functions. Contact OS/EM support for assistance in problem resolution.

FEMJ2M023

ABEND IN subsystem modtype (modname : entry) AT OFFSET xxxxxxxx

Explanation: An ABEND has been detected for a JES2 module either through ESTAE or FRR recovery programming.

subsystem: The name of the JES2 subsystem

modtype: The type of user module that failed

modname: The name of the failing module

entry: The entry point name for the failing module

xxxxxxx: The location within the failing module where the ABEND occurred.

Source: FEMJ2MCx

System Action: OS/EM function being executed continues, OS/EM takes a SVC dump for the abending module, takes the abending module out of service, and deletes the abending module from CSA/ECSA. Other messages will follow including FEMxxx025, FEMxxx026, and FEMxxx029. The module will show in a NOT LOADED status if a QUERY is done after an ABEND.

Operator Response: Contact System Programmer.

System Programmer Response: Use IPCS to determine the cause for the ABEND, take the corrective action required, perform an LLA,REFRESH, and RELOAD the failing module using the OS/EM ISPF RELOAD facility.

FEMJ2S023

ABEND IN subsystem modtype (modname : entry) AT OFFSET xxxxxxxx

Explanation: An ABEND has been detected for a JES2 module either through ESTAE or FRR recovery programming.

subsystem: The name of the JES2 subsystem
modtype: The type of user module that failed
modname: The name of the failing module
entry: The entry point name for the failing module
xxxxxxx: The location within the failing module where the ABEND occurred.

Source: FEMJ2SCx

System Action: OS/EM function being executed continues, OS/EM takes a SVC dump for the abending module, takes the abending module out of service, and deletes the abending module from CSA/ECSA. Other messages will follow including FEMxxx025, FEMxxx026, and FEMxxx029. The module will show in a NOT LOADED status if a QUERY is done after an ABEND.

Operator Response: Contact System Programmer.

System Programmer Response: Use IPCS to determine the cause for the ABEND, take the corrective action required, perform an LLA,REFRESH, and RELOAD the failing module using the OS/EM ISPF RELOAD facility.

FEMX05023

ABEND IN subsystem modtype (modname : entry) AT OFFSET xxxxxxxx

Explanation: An ABEND has been detected for a JES2 module either through ESTAE or FRR recovery programming.

subsystem: The name of the JES2 subsystem
modtype: The type of user module that failed
modname: The name of the failing module
entry: The entry point name for the failing module
xxxxxxx: The location within the failing module where the ABEND occurred.

Source: FEMJ2X05

System Action: OS/EM function being executed continues, OS/EM takes a SVC dump for the abending module, takes the abending module out of service, and deletes the abending module from CSA/ECSA. Other messages will follow including FEMxxx025, FEMxxx026, and FEMxxx029. The module will show in a NOT LOADED status if a QUERY is done after an ABEND.

Operator Response: Contact System Programmer.

System Programmer Response: Use IPCS to determine the cause for the ABEND, take the corrective action required, perform an LLA,REFRESH, and RELOAD the failing module using the OS/EM ISPF RELOAD facility.

FEM2P4023

ABEND IN subsystem modtype (modname : entry) AT OFFSET xxxxxxxx

Explanation: An ABEND has been detected for a JES2 module either through ESTAE or FRR recovery programming.

subsystem: The name of the JES2 subsystem
modtype: The type of user module that failed
modname: The name of the failing module
entry: The entry point name for the failing module
xxxxxxx: The location within the failing module where the ABEND occurred.

Source: FEMJ2P4x

System Action: OS/EM function being executed continues, OS/EM takes a SVC dump for the abending module, takes the abending module out of service, and deletes the abending module from CSA/ECSA. Other messages will follow including FEMxxx025, FEMxxx026, and FEMxxx029. The module will show in a NOT LOADED status if a QUERY is done after an ABEND.

Operator Response: Contact System Programmer.

System Programmer Response: Use IPCS to determine the cause for the ABEND, take the corrective action required, perform an LLA,REFRESH, and RELOAD the failing module using the OS/EM ISPF RELOAD facility.

FEMACN024

ABEND IN modtype modname AT OFFSET xxxxxxxx

Explanation: An ABEND has been detected for the specified module.

modtype: The type of module that ABENDED
modtype: The name of module that had the ABENDED
xxxxxxx: The location within the module where the ABEND occurred.

Source: FEMALCCN

System Action: OS/EM function being executed stops, OS/EM takes a SVC dump for the abending module, takes the abending module out of service, and deletes the abending module from CSA/ECSA. Other messages will accompany this including FEMxxx024, FEMxxx025, and FEMxxx029. The module will show in a NOT LOADED status if a QUERY is done after an ABEND.

Operator Response: Contact System Programmer.

System Programmer Response: Use IPCS to determine the cause for the ABEND, take the corrective action required, perform an LLA,REFRESH, and RELOAD the failing module using the OS/EM ISPF RELOAD facility. Contact OS/EM support for assistance in problem resolution.

FEMASY024

ABEND IN modtype modname AT OFFSET xxxxxxxx

Explanation: An ABEND has been detected for the specified module.

modtype: The type of module that ABENDED
modtype: The name of module that had the ABENDED
xxxxxxx: The location within the module where the ABEND occurred.

Source: FEMASYNC

System Action: OS/EM function being executed stops, OS/EM takes a SVC dump for the abending module, takes the abending module out of service, and deletes the abending module from CSA/ECSA. Other messages will accompany this including FEMxxx024, FEMxxx025, and FEMxxx029. The module will show in a NOT LOADED status if a QUERY is done after an ABEND.

Operator Response: Contact System Programmer.

System Programmer Response: Use IPCS to determine the cause for the ABEND, take the corrective action required, perform an LLA,REFRESH, and RELOAD the failing module using the OS/EM ISPF RELOAD facility. Contact OS/EM support for assistance in problem resolution.

FEMCOM024

ABEND IN modtype modname AT OFFSET xxxxxxxx

Explanation: An ABEND has been detected for the specified module.

modtype: The type of module that ABENDED

modtype: The name of module that had the ABENDED

xxxxxxx: The location within the module where the ABEND occurred.

Source: FEMCOMM

System Action: OS/EM function being executed stops, OS/EM takes a SVC dump for the abending module, takes the abending module out of service, and deletes the abending module from CSA/ECSA. Other messages will accompany this including FEMxxx024, FEMxxx025, and FEMxxx029. The module will show in a NOT LOADED status if a QUERY is done after an ABEND.

Operator Response: Contact System Programmer.

System Programmer Response: Use IPCS to determine the cause for the ABEND, take the corrective action required, perform an LLA,REFRESH, and RELOAD the failing module using the OS/EM ISPF RELOAD facility. Contact OS/EM support for assistance in problem resolution.

FEMDCN024

ABEND IN modtype modname AT OFFSET xxxxxxxx

Explanation: An ABEND has been detected for the specified module.

modtype: The type of module that ABENDED

modtype: The name of module that had the ABENDED

xxxxxxx: The location within the module where the ABEND occurred.

Source: FEMDADCN

System Action: OS/EM function being executed stops, OS/EM takes a SVC dump for the abending module, takes the abending module out of service, and deletes the abending module from CSA/ECSA. Other messages will accompany this including FEMxxx024, FEMxxx025, and FEMxxx029. The module will show in a NOT LOADED status if a QUERY is done after an ABEND.

Operator Response: Contact System Programmer.

System Programmer Response: Use IPCS to determine the cause for the ABEND, take the corrective action required, perform an LLA,REFRESH, and RELOAD the failing module using the OS/EM ISPF RELOAD facility. Contact OS/EM support for assistance in problem resolution.

FEMEXR024

ABEND IN modtype modname AT OFFSET xxxxxxxx

Explanation: An ABEND has been detected for the specified module.

modtype: The type of module that ABENDED
modtype: The name of module that had the ABENDED
xxxxxxx: The location within the module where the ABEND occurred.

Source: FEMEXRTN

System Action: OS/EM function being executed stops, OS/EM takes a SVC dump for the abending module, takes the abending module out of service, and deletes the abending module from CSA/ECSA. Other messages will accompany this including FEMxxx024, FEMxxx025, and FEMxxx029. The module will show in a NOT LOADED status if a QUERY is done after an ABEND.

Operator Response: Contact System Programmer.

System Programmer Response: Use IPCS to determine the cause for the ABEND, take the corrective action required, perform an LLA,REFRESH, and RELOAD the failing module using the OS/EM ISPF RELOAD facility. Contact OS/EM support for assistance in problem resolution.

FEMFCN024

ABEND IN modtype modname AT OFFSET xxxxxxxx

Explanation: An ABEND has been detected for the specified module.

modtype: The type of module that ABENDED
modtype: The name of module that had the ABENDED
xxxxxxx: The location within the module where the ABEND occurred.

Source: FEMFRACN

System Action: OS/EM function being executed stops, OS/EM takes a SVC dump for the abending module, takes the abending module out of service, and deletes the abending module from CSA/ECSA. Other messages will accompany this including FEMxxx024, FEMxxx025, and FEMxxx029. The module will show in a NOT LOADED status if a QUERY is done after an ABEND.

Operator Response: Contact System Programmer.

System Programmer Response: Use IPCS to determine the cause for the ABEND, take the corrective action required, perform an LLA,REFRESH, and RELOAD the failing module using the OS/EM ISPF RELOAD facility. Contact OS/EM support for assistance in problem resolution.

FEMFTN024

ABEND IN modtype modname AT OFFSET xxxxxxxx

Explanation: An ABEND has been detected for the specified module.

modtype: The type of module that ABENDED
modtype: The name of module that had the ABENDED
xxxxxxx: The location within the module where the ABEND occurred.

Source: FEMFRTN

System Action: OS/EM function being executed stops, OS/EM takes a SVC dump for the abending module, takes the abending module out of service, and deletes the abending module from

CSA/ECSA. Other messages will accompany this including FEMxxx024, FEMxxx025, and FEMxxx029. The module will show in a NOT LOADED status if a QUERY is done after an ABEND.

Operator Response: Contact System Programmer.

System Programmer Response: Use IPCS to determine the cause for the ABEND, take the corrective action required, perform an LLA,REFRESH, and RELOAD the failing module using the OS/EM ISPF RELOAD facility. Contact OS/EM support for assistance in problem resolution.

FEMHCN024

ABEND IN modtype modname AT OFFSET xxxxxxxx

Explanation: An ABEND has been detected for the specified module.

modtype: The type of module that ABENDED
modtype: The name of module that had the ABENDED
xxxxxxx: The location within the module where the ABEND occurred.

Source: FEMHSMCN

System Action: OS/EM function being executed stops, OS/EM takes a SVC dump for the abending module, takes the abending module out of service, and deletes the abending module from CSA/ECSA. Other messages will accompany this including FEMxxx024, FEMxxx025, and FEMxxx029. The module will show in a NOT LOADED status if a QUERY is done after an ABEND.

Operator Response: Contact System Programmer.

System Programmer Response: Use IPCS to determine the cause for the ABEND, take the corrective action required, perform an LLA,REFRESH, and RELOAD the failing module using the OS/EM ISPF RELOAD facility. Contact OS/EM support for assistance in problem resolution.

FEMICN024

ABEND IN modtype modname AT OFFSET xxxxxxxx

Explanation: An ABEND has been detected for the specified module.

modtype: The type of module that ABENDED
modtype: The name of module that had the ABENDED
xxxxxxx: The location within the module where the ABEND occurred.

Source: FEMISPCN

System Action: OS/EM function being executed stops, OS/EM takes a SVC dump for the abending module, takes the abending module out of service, and deletes the abending module from CSA/ECSA. Other messages will accompany this including FEMxxx024, FEMxxx025, and FEMxxx029. The module will show in a NOT LOADED status if a QUERY is done after an ABEND.

Operator Response: Contact System Programmer.

System Programmer Response: Use IPCS to determine the cause for the ABEND, take the corrective action required, perform an LLA,REFRESH, and RELOAD the failing module using the OS/EM ISPF RELOAD facility. Contact OS/EM support for assistance in problem resolution.

FEMJ2M024

ABEND IN modtype modname AT OFFSET xxxxxxxx

Explanation: An ABEND has been detected for the specified module.

modtype: The type of module that ABENDED
modtype: The name of module that had the ABENDED
xxxxxxx: The location within the module where the ABEND occurred.

Source: FEMJ2MCx

System Action: OS/EM function being executed stops, OS/EM takes a SVC dump for the abending module, takes the abending module out of service, and deletes the abending module from CSA/ECSA. Other messages will accompany this including FEMxxx024, FEMxxx025, and FEMxxx029. The module will show in a NOT LOADED status if a QUERY is done after an ABEND.

Operator Response: Contact System Programmer.

System Programmer Response: Use IPCS to determine the cause for the ABEND, take the corrective action required, perform an LLA,REFRESH, and RELOAD the failing module using the OS/EM ISPF RELOAD facility. Contact OS/EM support for assistance in problem resolution.

FEMJ2R024

ABEND IN modtype modname AT OFFSET xxxxxxxx

Explanation: An ABEND has been detected for the specified module.

modtype: The type of module that ABENDED
modtype: The name of module that had the ABENDED
xxxxxxx: The location within the module where the ABEND occurred.

Source: FEMJ2ERx

System Action: OS/EM function being executed stops, OS/EM takes a SVC dump for the abending module, takes the abending module out of service, and deletes the abending module from CSA/ECSA. Other messages will accompany this including FEMxxx024, FEMxxx025, and FEMxxx029. The module will show in a NOT LOADED status if a QUERY is done after an ABEND.

Operator Response: Contact System Programmer.

System Programmer Response: Use IPCS to determine the cause for the ABEND, take the corrective action required, perform an LLA,REFRESH, and RELOAD the failing module using the OS/EM ISPF RELOAD facility. Contact OS/EM support for assistance in problem resolution.

FEMJ2S024

ABEND IN modtype modname AT OFFSET xxxxxxxx

Explanation: An ABEND has been detected for the specified module.

modtype: The type of module that ABENDED
modtype: The name of module that had the ABENDED
xxxxxxx: The location within the module where the ABEND occurred.

Source: FEMJ2SCx

System Action: OS/EM function being executed stops, OS/EM takes a SVC dump for the abending module, takes the abending module out of service, and deletes the abending module from

CSA/ECSA. Other messages will accompany this including FEMxxx024, FEMxxx025, and FEMxxx029. The module will show in a NOT LOADED status if a QUERY is done after an ABEND.

Operator Response: Contact System Programmer.

System Programmer Response: Use IPCS to determine the cause for the ABEND, take the corrective action required, perform an LLA,REFRESH, and RELOAD the failing module using the OS/EM ISPF RELOAD facility. Contact OS/EM support for assistance in problem resolution.

FEMJ3E024

ABEND IN modtype modname AT OFFSET xxxxxxxx

Explanation: An ABEND has been detected for the specified module.

modtype: The type of module that ABENDED
modtype: The name of module that had the ABENDED
xxxxxxx: The location within the module where the ABEND occurred.

Source: FEMJ3ECN

System Action: OS/EM function being executed stops, OS/EM takes a SVC dump for the abending module, takes the abending module out of service, and deletes the abending module from CSA/ECSA. Other messages will accompany this including FEMxxx024, FEMxxx025, and FEMxxx029. The module will show in a NOT LOADED status if a QUERY is done after an ABEND.

Operator Response: Contact System Programmer.

System Programmer Response: Use IPCS to determine the cause for the ABEND, take the corrective action required, perform an LLA,REFRESH, and RELOAD the failing module using the OS/EM ISPF RELOAD facility. Contact OS/EM support for assistance in problem resolution.

FEMJ3S024

ABEND IN modtype modname AT OFFSET xxxxxxxx

Explanation: An ABEND has been detected for the specified module.

modtype: The type of module that ABENDED
modtype: The name of module that had the ABENDED
xxxxxxx: The location within the module where the ABEND occurred.

Source: FEMJ3SVC

System Action: OS/EM function being executed stops, OS/EM takes a SVC dump for the abending module, takes the abending module out of service, and deletes the abending module from CSA/ECSA. Other messages will accompany this including FEMxxx024, FEMxxx025, and FEMxxx029. The module will show in a NOT LOADED status if a QUERY is done after an ABEND.

Operator Response: Contact System Programmer.

System Programmer Response: Use IPCS to determine the cause for the ABEND, take the corrective action required, perform an LLA,REFRESH, and RELOAD the failing module using the OS/EM ISPF RELOAD facility. Contact OS/EM support for assistance in problem resolution.

FEMLOK024

ABEND IN modtype modname AT OFFSET xxxxxxxx

Explanation: An ABEND has been detected for the specified module.

modtype: The type of module that ABENDED
modtype: The name of module that had the ABENDED
xxxxxxx: The location within the module where the ABEND occurred.

Source: FEMLOCK

System Action: OS/EM function being executed stops, OS/EM takes a SVC dump for the abending module, takes the abending module out of service, and deletes the abending module from CSA/ECSA. Other messages will accompany this including FEMxxx024, FEMxxx025, and FEMxxx029. The module will show in a NOT LOADED status if a QUERY is done after an ABEND.

Operator Response: Contact System Programmer.

System Programmer Response: Use IPCS to determine the cause for the ABEND, take the corrective action required, perform an LLA,REFRESH, and RELOAD the failing module using the OS/EM ISPF RELOAD facility. Contact OS/EM support for assistance in problem resolution.

FEMRCN024

ABEND IN modtype modname AT OFFSET xxxxxxxx

Explanation: An ABEND has been detected for the specified module.

modtype: The type of module that ABENDED
modtype: The name of module that had the ABENDED
xxxxxxx: The location within the module where the ABEND occurred.

Source: FEMRACCN

System Action: OS/EM function being executed stops, OS/EM takes a SVC dump for the abending module, takes the abending module out of service, and deletes the abending module from CSA/ECSA. Other messages will accompany this including FEMxxx024, FEMxxx025, and FEMxxx029. The module will show in a NOT LOADED status if a QUERY is done after an ABEND.

Operator Response: Contact System Programmer.

System Programmer Response: Use IPCS to determine the cause for the ABEND, take the corrective action required, perform an LLA,REFRESH, and RELOAD the failing module using the OS/EM ISPF RELOAD facility. Contact OS/EM support for assistance in problem resolution.

FEMSCN024

ABEND IN modtype modname AT OFFSET xxxxxxxx

Explanation: An ABEND has been detected for the specified module.

modtype: The type of module that ABENDED
modtype: The name of module that had the ABENDED
xxxxxxx: The location within the module where the ABEND occurred.

Source: FEMSAFCN,FEMSMFCN

System Action: OS/EM function being executed stops, OS/EM takes a SVC dump for the abending module, takes the abending module out of service, and deletes the abending module from

CSA/ECSA. Other messages will accompany this including FEMxxx024, FEMxxx025, and FEMxxx029. The module will show in a NOT LOADED status if a QUERY is done after an ABEND.

Operator Response: Contact System Programmer.

System Programmer Response: Use IPCS to determine the cause for the ABEND, take the corrective action required, perform an LLA,REFRESH, and RELOAD the failing module using the OS/EM ISPF RELOAD facility. Contact OS/EM support for assistance in problem resolution.

FEMTCN024

ABEND IN modtype modname AT OFFSET xxxxxxxx

Explanation: An ABEND has been detected for the specified module.

modtype: The type of module that ABENDED
modtype: The name of module that had the ABENDED
xxxxxxx: The location within the module where the ABEND occurred.

Source: FEMTSOCN

System Action: OS/EM function being executed stops, OS/EM takes a SVC dump for the abending module, takes the abending module out of service, and deletes the abending module from CSA/ECSA. Other messages will accompany this including FEMxxx024, FEMxxx025, and FEMxxx029. The module will show in a NOT LOADED status if a QUERY is done after an ABEND.

Operator Response: Contact System Programmer.

System Programmer Response: Use IPCS to determine the cause for the ABEND, take the corrective action required, perform an LLA,REFRESH, and RELOAD the failing module using the OS/EM ISPF RELOAD facility. Contact OS/EM support for assistance in problem resolution.

FEMUJI024

ABEND IN modtype modname AT OFFSET xxxxxxxx

Explanation: An ABEND has been detected for the specified module.

modtype: The type of module that ABENDED
modtype: The name of module that had the ABENDED
xxxxxxx: The location within the module where the ABEND occurred.

Source: FEMUJI

System Action: OS/EM function being executed stops, OS/EM takes a SVC dump for the abending module, takes the abending module out of service, and deletes the abending module from CSA/ECSA. Other messages will accompany this including FEMxxx024, FEMxxx025, and FEMxxx029. The module will show in a NOT LOADED status if a QUERY is done after an ABEND.

Operator Response: Contact System Programmer.

System Programmer Response: Use IPCS to determine the cause for the ABEND, take the corrective action required, perform an LLA,REFRESH, and RELOAD the failing module using the OS/EM ISPF RELOAD facility. Contact OS/EM support for assistance in problem resolution.

FEMUSI024

ABEND IN modtype modname AT OFFSET xxxxxxxx

Explanation: An ABEND has been detected for the specified module.

modtype: The type of module that ABENDED
modtype: The name of module that had the ABENDED
xxxxxxx: The location within the module where the ABEND occurred.

Source: FEMUSI

System Action: OS/EM function being executed stops, OS/EM takes a SVC dump for the abending module, takes the abending module out of service, and deletes the abending module from CSA/ECSA. Other messages will accompany this including FEMxxx024, FEMxxx025, and FEMxxx029. The module will show in a NOT LOADED status if a QUERY is done after an ABEND.

Operator Response: Contact System Programmer.

System Programmer Response: Use IPCS to determine the cause for the ABEND, take the corrective action required, perform an LLA,REFRESH, and RELOAD the failing module using the OS/EM ISPF RELOAD facility. Contact OS/EM support for assistance in problem resolution.

FEMVCN024

ABEND IN modtype modname AT OFFSET xxxxxxxx

Explanation: An ABEND has been detected for the specified module.

modtype: The type of module that ABENDED
modtype: The name of module that had the ABENDED
xxxxxxx: The location within the module where the ABEND occurred.

Source: FEMSVCCN

System Action: OS/EM function being executed stops, OS/EM takes a SVC dump for the abending module, takes the abending module out of service, and deletes the abending module from CSA/ECSA. Other messages will accompany this including FEMxxx024, FEMxxx025, and FEMxxx029. The module will show in a NOT LOADED status if a QUERY is done after an ABEND.

Operator Response: Contact System Programmer.

System Programmer Response: Use IPCS to determine the cause for the ABEND, take the corrective action required, perform an LLA,REFRESH, and RELOAD the failing module using the OS/EM ISPF RELOAD facility. Contact OS/EM support for assistance in problem resolution.

FEMX05024

ABEND IN modtype modname AT OFFSET xxxxxxxx

Explanation: An ABEND has been detected for the specified module.

modtype: The type of module that ABENDED
modtype: The name of module that had the ABENDED
xxxxxxx: The location within the module where the ABEND occurred.

Source: FEMJ2X05

System Action: OS/EM function being executed stops, OS/EM takes a SVC dump for the abending module, takes the abending module out of service, and deletes the abending module from

CSA/ECSA. Other messages will accompany this including FEMxxx024, FEMxxx025, and FEMxxx029. The module will show in a NOT LOADED status if a QUERY is done after an ABEND.

Operator Response: Contact System Programmer.

System Programmer Response: Use IPCS to determine the cause for the ABEND, take the corrective action required, perform an LLA,REFRESH, and RELOAD the failing module using the OS/EM ISPF RELOAD facility. Contact OS/EM support for assistance in problem resolution.

FEM2P4024

ABEND IN modtype modname AT OFFSET xxxxxxxx

Explanation: An ABEND has been detected for the specified module.

modtype: The type of module that ABENDED
modtype: The name of module that had the ABENDED
xxxxxxx: The location within the module where the ABEND occurred.

Source: FEMJ2P4x

System Action: OS/EM function being executed stops, OS/EM takes a SVC dump for the abending module, takes the abending module out of service, and deletes the abending module from CSA/ECSA. Other messages will accompany this including FEMxxx024, FEMxxx025, and FEMxxx029. The module will show in a NOT LOADED status if a QUERY is done after an ABEND.

Operator Response: Contact System Programmer.

System Programmer Response: Use IPCS to determine the cause for the ABEND, take the corrective action required, perform an LLA,REFRESH, and RELOAD the failing module using the OS/EM ISPF RELOAD facility. Contact OS/EM support for assistance in problem resolution.

FEM2P4024

ABEND IN modtype modname AT OFFSET xxxxxxxx

Explanation: An ABEND has been detected for the specified module.

modtype: The type of module that ABENDED
modtype: The name of module that had the ABENDED
xxxxxxx: The location within the module where the ABEND occurred.

Source: FEMJ2P4x

System Action: OS/EM function being executed stops, OS/EM takes a SVC dump for the abending module, takes the abending module out of service, and deletes the abending module from CSA/ECSA. Other messages will accompany this including FEMxxx024, FEMxxx025, and FEMxxx029. The module will show in a NOT LOADED status if a QUERY is done after an ABEND.

Operator Response: Contact System Programmer.

System Programmer Response: Use IPCS to determine the cause for the ABEND, take the corrective action required, perform an LLA,REFRESH, and RELOAD the failing module using the OS/EM ISPF RELOAD facility. Contact OS/EM support for assistance in problem resolution.

FEMACN025

EXIT POINT program DISABLED

Explanation: During execution of user exit program the exit module has become disabled due to a previous error. Usually this message is the result of an ABEND and message FEMxxx023 is issued.

program: The user exit being disabled.

Source: FEMALCCN

System Action: OS/EM function being executed continues, OS/EM takes a SVC dump for the abending module, takes the abending module out of service, and deletes the abending module from CSA/ECSA. Other messages will accompany this including FEMxxx023, FEMxxx026, and FEMxxx029. The module will show in a NOT LOADED status if a QUERY is done after an ABEND.

Operator Response: Contact System Programmer.

System Programmer Response: Use IPCS to determine the cause for the ABEND, take the corrective action required, perform an LLA,REFRESH, and RELOAD the failing module using the OS/EM ISPF RELOAD facility.

FEMDCN025

EXIT POINT program DISABLED

Explanation: During execution of user exit program the exit module has become disabled due to a previous error. Usually this message is the result of an ABEND and message FEMxxx023 is issued.

program: The user exit being disabled.

Source: FEMDADCN

System Action: OS/EM function being executed continues, OS/EM takes a SVC dump for the abending module, takes the abending module out of service, and deletes the abending module from CSA/ECSA. Other messages will accompany this including FEMxxx023, FEMxxx026, and FEMxxx029. The module will show in a NOT LOADED status if a QUERY is done after an ABEND.

Operator Response: Contact System Programmer.

System Programmer Response: Use IPCS to determine the cause for the ABEND, take the corrective action required, perform an LLA,REFRESH, and RELOAD the failing module using the OS/EM ISPF RELOAD facility.

FEMFRA025

EXIT POINT program DISABLED

Explanation: During execution of user exit program the exit module has become disabled due to a previous error. Usually this message is the result of an ABEND and message FEMxxx023 is issued.

program: The user exit being disabled.

Source: FEMFRACN

System Action: OS/EM function being executed continues, OS/EM takes a SVC dump for the abending module, takes the abending module out of service, and deletes the abending module from CSA/ECSA. Other messages will accompany this including FEMxxx023, FEMxxx026, and FEMxxx029. The module will show in a NOT LOADED status if a QUERY is done after an ABEND.

Operator Response: Contact System Programmer.

System Programmer Response: Use IPCS to determine the cause for the ABEND, take the corrective action required, perform an LLA,REFRESH, and RELOAD the failing module using the OS/EM ISPF RELOAD facility.

FEMHCN025

EXIT POINT program DISABLED

Explanation: During execution of user exit program the exit module has become disabled due to a previous error. Usually this message is the result of an ABEND and message FEMxxx023 is issued.

program: The user exit being disabled.

Source: FEMHSMCN

System Action: OS/EM function being executed continues, OS/EM takes a SVC dump for the abending module, takes the abending module out of service, and deletes the abending module from CSA/ECSA. Other messages will accompany this including FEMxxx023, FEMxxx026, and FEMxxx029. The module will show in a NOT LOADED status if a QUERY is done after an ABEND.

Operator Response: Contact System Programmer.

System Programmer Response: Use IPCS to determine the cause for the ABEND, take the corrective action required, perform an LLA,REFRESH, and RELOAD the failing module using the OS/EM ISPF RELOAD facility.

FEMICN025

EXIT POINT program DISABLED

Explanation: During execution of user exit program the exit module has become disabled due to a previous error. Usually this message is the result of an ABEND and message FEMxxx023 is issued.

program: The user exit being disabled.

Source: FEMISPCN

System Action: OS/EM function being executed continues, OS/EM takes a SVC dump for the abending module, takes the abending module out of service, and deletes the abending module from CSA/ECSA. Other messages will accompany this including FEMxxx023, FEMxxx026, and FEMxxx029. The module will show in a NOT LOADED status if a QUERY is done after an ABEND.

Operator Response: Contact System Programmer.

System Programmer Response: Use IPCS to determine the cause for the ABEND, take the corrective action required, perform an LLA,REFRESH, and RELOAD the failing module using the OS/EM ISPF RELOAD facility.

FEMJ3E025

EXIT POINT program DISABLED

Explanation: During execution of user exit program the exit module has become disabled due to a previous error. Usually this message is the result of an ABEND and message FEMxxx023 is issued.

program: The user exit being disabled.

Source: FEMJ3ECN

System Action: OS/EM function being executed continues, OS/EM takes a SVC dump for the abending module, takes the abending module out of service, and deletes the abending module from CSA/ECSA. Other messages will accompany this including FEMxxx023, FEMxxx026, and FEMxxx029. The module will show in a NOT LOADED status if a QUERY is done after an ABEND.

Operator Response: Contact System Programmer.

System Programmer Response: Use IPCS to determine the cause for the ABEND, take the corrective action required, perform an LLA,REFRESH, and RELOAD the failing module using the OS/EM ISPF RELOAD facility.

FEMRCN025

EXIT POINT program DISABLED

Explanation: During execution of user exit program the exit module has become disabled due to a previous error. Usually this message is the result of an ABEND and message FEMxxx023 is issued.

program: The user exit being disabled.

Source: FEMRACCN

System Action: OS/EM function being executed continues, OS/EM takes a SVC dump for the abending module, takes the abending module out of service, and deletes the abending module from CSA/ECSA. Other messages will accompany this including FEMxxx023, FEMxxx026, and FEMxxx029. The module will show in a NOT LOADED status if a QUERY is done after an ABEND.

Operator Response: Contact System Programmer.

System Programmer Response: Use IPCS to determine the cause for the ABEND, take the corrective action required, perform an LLA,REFRESH, and RELOAD the failing module using the OS/EM ISPF RELOAD facility.

FEMSCN025

EXIT POINT program DISABLED

Explanation: During execution of user exit program the exit module has become disabled due to a previous error. Usually this message is the result of an ABEND and message FEMxxx023 is issued.

program: The user exit being disabled.

Source: FEMSAFCN,FEMSMFCN

System Action: OS/EM function being executed continues, OS/EM takes a SVC dump for the abending module, takes the abending module out of service, and deletes the abending module from CSA/ECSA. Other messages will accompany this including FEMxxx023, FEMxxx026, and FEMxxx029. The module will show in a NOT LOADED status if a QUERY is done after an ABEND.

Operator Response: Contact System Programmer.

System Programmer Response: Use IPCS to determine the cause for the ABEND, take the corrective action required, perform an LLA,REFRESH, and RELOAD the failing module using the OS/EM ISPF RELOAD facility.

FEMTCN025

EXIT POINT program DISABLED

Explanation: During execution of user exit program the exit module has become disabled due to a previous error. Usually this message is the result of an ABEND and message FEMxxx023 is issued.

program: The user exit being disabled.

Source: FEMTSOCN

System Action: OS/EM function being executed continues, OS/EM takes a SVC dump for the abending module, takes the abending module out of service, and deletes the abending module from CSA/ECSA. Other messages will accompany this including FEMxxx023, FEMxxx026, and FEMxxx029. The module will show in a NOT LOADED status if a QUERY is done after an ABEND.

Operator Response: Contact System Programmer.

System Programmer Response: Use IPCS to determine the cause for the ABEND, take the corrective action required, perform an LLA,REFRESH, and RELOAD the failing module using the OS/EM ISPF RELOAD facility.

FEMACN026

EXIT program DEACTIVATED

Explanation: During execution of user exit program the exit module has been deactivated due to a previous error. Usually this message is the result of an ABEND and message FEMxxx023 is issued.

program: Exit module name.

Source: FEMALCCN

System Action: OS/EM function being executed continues, OS/EM takes a SVC dump for the abending module, takes the abending module out of service, and deletes the abending module from CSA/ECSA. Other messages will accompany this including FEMxxx024, FEMxxx025, and FEMxxx029. The module will show in a NOT LOADED status if a QUERY is done after an ABEND.

Operator Response: Contact System Programmer.

System Programmer Response: Use IPCS to determine the cause for the ABEND, take the corrective action required, perform an LLA,REFRESH, and RELOAD the failing module using the OS/EM ISPF RELOAD facility.

FEMDCN026

EXIT program DEACTIVATED

Explanation: During execution of user exit program the exit module has been deactivated due to a previous error. Usually this message is the result of an ABEND and message FEMxxx023 is issued.

program: Exit module name.

Source: FEMDADCN

System Action: OS/EM function being executed continues, OS/EM takes a SVC dump for the abending module, takes the abending module out of service, and deletes the abending module from CSA/ECSA. Other messages will accompany this including FEMxxx024, FEMxxx025, and FEMxxx029. The module will show in a NOT LOADED status if a QUERY is done after an ABEND.

Operator Response: Contact System Programmer.

System Programmer Response: Use IPCS to determine the cause for the ABEND, take the corrective action required, perform an LLA,REFRESH, and RELOAD the failing module using the OS/EM ISPF RELOAD facility.

FEMFCN026

EXIT program DEACTIVATED

Explanation: During execution of user exit program the exit module has been deactivated due to a previous error. Usually this message is the result of an ABEND and message FEMxxx023 is issued.

program: Exit module name.

Source: FEMFRACN

System Action: OS/EM function being executed continues, OS/EM takes a SVC dump for the abending module, takes the abending module out of service, and deletes the abending module from CSA/ECSA. Other messages will accompany this including FEMxxx024, FEMxxx025, and FEMxxx029. The module will show in a NOT LOADED status if a QUERY is done after an ABEND.

Operator Response: Contact System Programmer.

System Programmer Response: Use IPCS to determine the cause for the ABEND, take the corrective action required, perform an LLA,REFRESH, and RELOAD the failing module using the OS/EM ISPF RELOAD facility.

FEMHCN026

EXIT program DEACTIVATED

Explanation: During execution of user exit program the exit module has been deactivated due to a previous error. Usually this message is the result of an ABEND and message FEMxxx023 is issued.

program: Exit module name.

Source: FEMHSMCN

System Action: OS/EM function being executed continues, OS/EM takes a SVC dump for the abending module, takes the abending module out of service, and deletes the abending module from CSA/ECSA. Other messages will accompany this including FEMxxx024, FEMxxx025, and FEMxxx029. The module will show in a NOT LOADED status if a QUERY is done after an ABEND.

Operator Response: Contact System Programmer.

System Programmer Response: Use IPCS to determine the cause for the ABEND, take the corrective action required, perform an LLA,REFRESH, and RELOAD the failing module using the OS/EM ISPF RELOAD facility.

FEMICN026

EXIT program DEACTIVATED

Explanation: During execution of user exit program the exit module has been deactivated due to a previous error. Usually this message is the result of an ABEND and message FEMxxx023 is issued.

program: Exit module name.

Source: FEMISPCN

System Action: OS/EM function being executed continues, OS/EM takes a SVC dump for the abending module, takes the abending module out of service, and deletes the abending module from CSA/ECSA. Other messages will accompany this including FEMxxx024, FEMxxx025, and FEMxxx029. The module will show in a NOT LOADED status if a QUERY is done after an ABEND.

Operator Response: Contact System Programmer.

System Programmer Response: Use IPCS to determine the cause for the ABEND, take the corrective action required, perform an LLA,REFRESH, and RELOAD the failing module using the OS/EM ISPF RELOAD facility.

FEMJ3E026

EXIT program DEACTIVATED

Explanation: During execution of user exit program the exit module has been deactivated due to a previous error. Usually this message is the result of an ABEND and message FEMxxx023 is issued.

program: Exit module name.

Source: FEMJ3ECN

System Action: OS/EM function being executed continues, OS/EM takes a SVC dump for the abending module, takes the abending module out of service, and deletes the abending module from CSA/ECSA. Other messages will accompany this including FEMxxx024, FEMxxx025, and FEMxxx029. The module will show in a NOT LOADED status if a QUERY is done after an ABEND.

Operator Response: Contact System Programmer.

System Programmer Response: Use IPCS to determine the cause for the ABEND, take the corrective action required, perform an LLA,REFRESH, and RELOAD the failing module using the OS/EM ISPF RELOAD facility.

FEMRCN026

EXIT program DEACTIVATED

Explanation: During execution of user exit program the exit module has been deactivated due to a previous error. Usually this message is the result of an ABEND and message FEMxxx023 is issued.

program: Exit module name.

Source: FEMRACCN

System Action: OS/EM function being executed continues, OS/EM takes a SVC dump for the abending module, takes the abending module out of service, and deletes the abending module from CSA/ECSA. Other messages will accompany this including FEMxxx024, FEMxxx025, and FEMxxx029. The module will show in a NOT LOADED status if a QUERY is done after an ABEND.

Operator Response: Contact System Programmer.

System Programmer Response: Use IPCS to determine the cause for the ABEND, take the corrective action required, perform an LLA,REFRESH, and RELOAD the failing module using the OS/EM ISPF RELOAD facility.

FEMSCN026

EXIT program DEACTIVATED

Explanation: During execution of user exit program the exit module has been deactivated due to a previous error. Usually this message is the result of an ABEND and message FEMxxx023 is issued.

program: Exit module name.

Source: FEMSAFCN,FEMSMFCN

System Action: OS/EM function being executed continues, OS/EM takes a SVC dump for the abending module, takes the abending module out of service, and deletes the abending module from CSA/ECSA. Other messages will accompany this including FEMxxx024, FEMxxx025, and FEMxxx029. The module will show in a NOT LOADED status if a QUERY is done after an ABEND.

Operator Response: Contact System Programmer.

System Programmer Response: Use IPCS to determine the cause for the ABEND, take the corrective action required, perform an LLA,REFRESH, and RELOAD the failing module using the OS/EM ISPF RELOAD facility.

FEMTCN026

EXIT program DEACTIVATED

Explanation: During execution of user exit program the exit module has been deactivated due to a previous error. Usually this message is the result of an ABEND and message FEMxxx023 is issued.

program: Exit module name.

Source: FEMTSOCN

System Action: OS/EM function being executed continues, OS/EM takes a SVC dump for the abending module, takes the abending module out of service, and deletes the abending module from CSA/ECSA. Other messages will accompany this including FEMxxx024, FEMxxx025, and FEMxxx029. The module will show in a NOT LOADED status if a QUERY is done after an ABEND.

Operator Response: Contact System Programmer.

System Programmer Response: Use IPCS to determine the cause for the ABEND, take the corrective action required, perform an LLA,REFRESH, and RELOAD the failing module using the OS/EM ISPF RELOAD facility.

FEMCMD027

ABEND IN OS/EM function MODULE module

Explanation: An ABEND occurred in an OS/EM function.

function: The functional area affected by the failing module

module: The name of the failing module

Source: FEMCMD

System Action: OS/EM function being executed continues, OS/EM takes a SVC dump for the abending module, takes the abending module out of service, and deletes the abending module from CSA/ECSA. Other messages will accompany this including FEMxxx024, FEMxxx025, and FEMxxx029. The module will show in a NOT LOADED status if a QUERY is done after an ABEND.

Operator Response: Contact System Programmer.

System Programmer Response: Use IPCS to determine the cause for the ABEND, take the corrective action required, perform an LLA,REFRESH, and RELOAD the failing module using the OS/EM ISPF RELOAD facility. Contact OS/EM support for assistance in problem resolution.

FEMDC1027

ABEND IN OS/EM function MODULE module

Explanation: An ABEND occurred in an OS/EM function.

function: The functional area affected by the failing module

module: The name of the failing module

Source: FEMDCB1

System Action: OS/EM function being executed continues, OS/EM takes a SVC dump for the abending module, takes the abending module out of service, and deletes the abending module from CSA/ECSA. Other messages will accompany this including FEMxxx024, FEMxxx025, and FEMxxx029. The module will show in a NOT LOADED status if a QUERY is done after an ABEND.

Operator Response: Contact System Programmer.

System Programmer Response: Use IPCS to determine the cause for the ABEND, take the corrective action required, perform an LLA,REFRESH, and RELOAD the failing module using the OS/EM ISPF RELOAD facility. Contact OS/EM support for assistance in problem resolution.

FEMIPL027

ABEND IN OS/EM function MODULE module

Explanation: An ABEND occurred in an OS/EM function.

function: The functional area affected by the failing module

module: The name of the failing module

Source: FEMIPL

System Action: OS/EM function being executed continues, OS/EM takes a SVC dump for the abending module, takes the abending module out of service, and deletes the abending module from CSA/ECSA. Other messages will accompany this including FEMxxx024, FEMxxx025, and FEMxxx029. The module will show in a NOT LOADED status if a QUERY is done after an ABEND.

Operator Response: Contact System Programmer.

System Programmer Response: Use IPCS to determine the cause for the ABEND, take the corrective action required, perform an LLA,REFRESH, and RELOAD the failing module using the OS/EM ISPF RELOAD facility. Contact OS/EM support for assistance in problem resolution.

FEMTPS027

ABEND IN OS/EM function MODULE module

Explanation: An ABEND occurred in an OS/EM function.

function: The functional area affected by the failing module

module: The name of the failing module

Source: FEMTPSHR

System Action: OS/EM function being executed continues, OS/EM takes a SVC dump for the abending module, takes the abending module out of service, and deletes the abending module from CSA/ECSA. Other messages will accompany this including FEMxxx024, FEMxxx025, and FEMxxx029. The module will show in a NOT LOADED status if a QUERY is done after an ABEND.

Operator Response: Contact System Programmer.

System Programmer Response: Use IPCS to determine the cause for the ABEND, take the corrective action required, perform an LLA,REFRESH, and RELOAD the failing module using the OS/EM ISPF RELOAD facility. Contact OS/EM support for assistance in problem resolution.

FEM02F027

ABEND IN OS/EM function MODULE module

Explanation: An ABEND occurred in an OS/EM function.

function: The functional area affected by the failing module

module: The name of the failing module

Source: FEM0002F

System Action: OS/EM function being executed continues, OS/EM takes a SVC dump for the abending module, takes the abending module out of service, and deletes the abending module from CSA/ECSA. Other messages will accompany this including FEMxxx024, FEMxxx025, and FEMxxx029. The module will show in a NOT LOADED status if a QUERY is done after an ABEND.

Operator Response: Contact System Programmer.

System Programmer Response: Use IPCS to determine the cause for the ABEND, take the corrective action required, perform an LLA,REFRESH, and RELOAD the failing module using the OS/EM ISPF RELOAD facility. Contact OS/EM support for assistance in problem resolution.

FEMLOK029

MODULE program STORAGE RELEASED (xxxxxxx)

Explanation: The specified module has been deleted from CSA/ECSA due to a previous error. Usually this message is the result of an ABEND and message FEMxxx024 is issued.

program: The name of the deleted module

xxxxxxx: The address where the module previously resided

Source: FEMFEMLOCK

System Action: OS/EM function being executed continues, OS/EM takes a SVC dump for the abending module, takes the abending module out of service, and deletes the abending module from CSA/ECSA. Other messages will accompany this including FEMxxx024, FEMxxx025, and FEMxxx026. The module will show in a NOT LOADED status if a QUERY is done after an ABEND.

Operator Response: Contact System Programmer.

System Programmer Response: Use IPCS to determine the cause for the ABEND, take the corrective action required, perform an LLA,REFRESH, and RELOAD the failing module using the OS/EM ISPF RELOAD facility.

FEMACN030

function MODULE program NOT LOADED

Explanation: The OS/EM command processor FEMCNTL has requested a module to be loaded and it has failed during the load process. Another message usually accompanies this detailing the reason for failure.

function: The functional area of the failing module.

program: The name of the failing module.

Source: FEMALCCN

System Action: The FEMCNTL command being processed is ignored.

Operator Response: None.

System Programmer Response: Check previous messages for the cause of the load failure. Take the corrective action as required and re-issue the OS/EM command. Contact OS/EM support for assistance in problem resolution.

FEMALC030

function MODULE program NOT LOADED

Explanation: The OS/EM command processor FEMCNTL has requested a module to be loaded and it has failed during the load process. Another message usually accompanies this detailing the reason for failure.

function: The functional area of the failing module.

program: The name of the failing module.

Source: FEMALCCN

System Action: The FEMCNTL command being processed is ignored.

Operator Response: None.

System Programmer Response: Check previous messages for the cause of the load failure. Take the corrective action as required and re-issue the OS/EM command. Contact OS/EM support for assistance in problem resolution.

FEMASY030

function MODULE program NOT LOADED

Explanation: The OS/EM command processor FEMCNTL has requested a module to be loaded and it has failed during the load process. Another message usually accompanies this detailing the reason for failure.

function: The functional area of the failing module.

program: The name of the failing module.

Source: FEMALCCN

System Action: The FEMCNTL command being processed is ignored.

Operator Response: None.

System Programmer Response: Check previous messages for the cause of the load failure. Take the corrective action as required and re-issue the OS/EM command. Contact OS/EM support for assistance in problem resolution.

FEMDAD030

function MODULE program NOT LOADED

Explanation: The OS/EM command processor FEMCNTL has requested a module to be loaded and it has failed during the load process. Another message usually accompanies this detailing the reason for failure.

function: The functional area of the failing module.

program: The name of the failing module.

Source: FEMDASD

System Action: The FEMCNTL command being processed is ignored.

Operator Response: None.

System Programmer Response: Check previous messages for the cause of the load failure. Take the corrective action as required and re-issue the OS/EM command. Contact OS/EM support for assistance in problem resolution.

FEMDCN030

function MODULE program NOT LOADED

Explanation: The OS/EM command processor FEMCNTL has requested a module to be loaded and it has failed during the load process. Another message usually accompanies this detailing the reason for failure.

function: The functional area of the failing module.

program: The name of the failing module.

Source: FEMDADCN

System Action: The FEMCNTL command being processed is ignored.

Operator Response: None.

System Programmer Response: Check previous messages for the cause of the load failure. Take the corrective action as required and re-issue the OS/EM command. Contact OS/EM support for assistance in problem resolution.

FEMFRA030

function MODULE program NOT LOADED

Explanation: The OS/EM command processor FEMCNTL has requested a module to be loaded and it has failed during the load process. Another message usually accompanies this detailing the reason for failure.

function: The functional area of the failing module.

program: The name of the failing module.

Source: FEMFRACN

System Action: The FEMCNTL command being processed is ignored.

Operator Response: None.

System Programmer Response: Check previous messages for the cause of the load failure. Take the corrective action as required and re-issue the OS/EM command. Contact OS/EM support for assistance in problem resolution.

FEMF10030

function MODULE program NOT LOADED

Explanation: The OS/EM command processor FEMCNTL has requested a module to be loaded and it has failed during the load process. Another message usually accompanies this detailing the reason for failure.

function: The functional area of the failing module.

program: The name of the failing module.

Source: FEMEFF10

System Action: The FEMCNTL command being processed is ignored.

Operator Response: None.

System Programmer Response: Check previous messages for the cause of the load failure. Take the corrective action as required and re-issue the OS/EM command. Contact OS/EM support for assistance in problem resolution.

FEMHCN030

function MODULE program NOT LOADED

Explanation: The OS/EM command processor FEMCNTL has requested a module to be loaded and it has failed during the load process. Another message usually accompanies this detailing the reason for failure.

function: The functional area of the failing module.

program: The name of the failing module.

Source: FEMHSMCN

System Action: The FEMCNTL command being processed is ignored.

Operator Response: None.

System Programmer Response: Check previous messages for the cause of the load failure. Take the corrective action as required and re-issue the OS/EM command. Contact OS/EM support for assistance in problem resolution.

FEMHSM030

function MODULE program NOT LOADED

Explanation: The OS/EM command processor FEMCNTL has requested a module to be loaded and it has failed during the load process. Another message usually accompanies this detailing the reason for failure.

function: The functional area of the failing module.

program: The name of the failing module.

Source: FEMHSMx

System Action: The FEMCNTL command being processed is ignored.

Operator Response: None.

System Programmer Response: Check previous messages for the cause of the load failure. Take the corrective action as required and re-issue the OS/EM command. Contact OS/EM support for assistance in problem resolution.

FEMHSP030

function MODULE program NOT LOADED

Explanation: The OS/EM command processor FEMCNTL has requested a module to be loaded and it has failed during the load process. Another message usually accompanies this detailing the reason for failure.

function: The functional area of the failing module.

program: The name of the failing module.

Source: FEMHJ20

System Action: The FEMCNTL command being processed is ignored.

Operator Response: None.

System Programmer Response: Check previous messages for the cause of the load failure. Take the corrective action as required and re-issue the OS/EM command. Contact OS/EM support for assistance in problem resolution.

FEMIAT030

function MODULE program NOT LOADED

Explanation: The OS/EM command processor FEMCNTL has requested a module to be loaded and it has failed during the load process. Another message usually accompanies this detailing the reason for failure.

function: The functional area of the failing module.

program: The name of the failing module.

Source: FEMINTK

System Action: The FEMCNTL command being processed is ignored.

Operator Response: None.

System Programmer Response: Check previous messages for the cause of the load failure. Take the corrective action as required and re-issue the OS/EM command. Contact OS/EM support for assistance in problem resolution.

FEMICN030

function MODULE program NOT LOADED

Explanation: The OS/EM command processor FEMCNTL has requested a module to be loaded and it has failed during the load process. Another message usually accompanies this detailing the reason for failure.

function: The functional area of the failing module.

program: The name of the failing module.

Source: FEMISPCN

System Action: The FEMCNTL command being processed is ignored.

Operator Response: None.

System Programmer Response: Check previous messages for the cause of the load failure. Take the corrective action as required and re-issue the OS/EM command. Contact OS/EM support for assistance in problem resolution.

FEMISP030

function MODULE program NOT LOADED

Explanation: The OS/EM command processor FEMCNTL has requested a module to be loaded and it has failed during the load process. Another message usually accompanies this detailing the reason for failure.

function: The functional area of the failing module.

program: The name of the failing module.

Source: FEMISPF

System Action: The FEMCNTL command being processed is ignored.

Operator Response: None.

System Programmer Response: Check previous messages for the cause of the load failure. Take the corrective action as required and re-issue the OS/EM command. Contact OS/EM support for assistance in problem resolution.

FEMJS2030

function MODULE program NOT LOADED

Explanation: The OS/EM command processor FEMCNTL has requested a module to be loaded and it has failed during the load process. Another message usually accompanies this detailing the reason for failure.

function: The functional area of the failing module.

program: The name of the failing module.

Source: FEMJES2x

System Action: The FEMCNTL command being processed is ignored.

Operator Response: None.

System Programmer Response: Check previous messages for the cause of the load failure. Take the corrective action as required and re-issue the OS/EM command. Contact OS/EM support for assistance in problem resolution.

FEMJS3030

function MODULE program NOT LOADED

Explanation: The OS/EM command processor FEMCNTL has requested a module to be loaded and it has failed during the load process. Another message usually accompanies this detailing the reason for failure.

function: The functional area of the failing module.

program: The name of the failing module.

Source: FEMJES3

System Action: The FEMCNTL command being processed is ignored.

Operator Response: None.

System Programmer Response: Check previous messages for the cause of the load failure. Take the corrective action as required and re-issue the OS/EM command. Contact OS/EM support for assistance in problem resolution.

FEMJ2I030

function MODULE program NOT LOADED

Explanation: The OS/EM command processor FEMCNTL has requested a module to be loaded and it has failed during the load process. Another message usually accompanies this detailing the reason for failure.

function: The functional area of the failing module.

program: The name of the failing module.

Source: FEMJ2ITx

System Action: The FEMCNTL command being processed is ignored.

Operator Response: None.

System Programmer Response: Check previous messages for the cause of the load failure. Take the corrective action as required and re-issue the OS/EM command. Contact OS/EM support for assistance in problem resolution.

FEMJ2M030

function MODULE program NOT LOADED

Explanation: The OS/EM command processor FEMCNTL has requested a module to be loaded and it has failed during the load process. Another message usually accompanies this detailing the reason for failure.

function: The functional area of the failing module.

program: The name of the failing module.

Source: FEMJ2MCx

System Action: The FEMCNTL command being processed is ignored.

Operator Response: None.

System Programmer Response: Check previous messages for the cause of the load failure. Take the corrective action as required and re-issue the OS/EM command. Contact OS/EM support for assistance in problem resolution.

FEMJ2S030

function MODULE program NOT LOADED

Explanation: The OS/EM command processor FEMCNTL has requested a module to be loaded and it has failed during the load process. Another message usually accompanies this detailing the reason for failure.

function: The functional area of the failing module.

program: The name of the failing module.

Source: FEMJ2SCx

System Action: The FEMCNTL command being processed is ignored.

Operator Response: None.

System Programmer Response: Check previous messages for the cause of the load failure. Take the corrective action as required and re-issue the OS/EM command. Contact OS/EM support for assistance in problem resolution.

FEMJ3E030

function MODULE program NOT LOADED

Explanation: The OS/EM command processor FEMCNTL has requested a module to be loaded and it has failed during the load process. Another message usually accompanies this detailing the reason for failure.

function: The functional area of the failing module.

program: The name of the failing module.

Source: FEMJ3ECN

System Action: The FEMCNTL command being processed is ignored.

Operator Response: None.

System Programmer Response: Check previous messages for the cause of the load failure. Take the corrective action as required and re-issue the OS/EM command. Contact OS/EM support for assistance in problem resolution.

FEMJ3I030

function MODULE program NOT LOADED

Explanation: The OS/EM command processor FEMCNTL has requested a module to be loaded and it has failed during the load process. Another message usually accompanies this detailing the reason for failure.

function: The functional area of the failing module.

program: The name of the failing module.

Source: FEMJ3ITF

System Action: The FEMCNTL command being processed is ignored.

Operator Response: None.

System Programmer Response: Check previous messages for the cause of the load failure. Take the corrective action as required and re-issue the OS/EM command. Contact OS/EM support for assistance in problem resolution.

FEMJ3S030

function MODULE program NOT LOADED

Explanation: The OS/EM command processor FEMCNTL has requested a module to be loaded and it has failed during the load process. Another message usually accompanies this detailing the reason for failure.

function: The functional area of the failing module.

program: The name of the failing module.

Source: FEMJ3SVC

System Action: The FEMCNTL command being processed is ignored.

Operator Response: None.

System Programmer Response: Check previous messages for the cause of the load failure. Take the corrective action as required and re-issue the OS/EM command. Contact OS/EM support for assistance in problem resolution.

FEMMIS030

function MODULE program NOT LOADED

Explanation: The OS/EM command processor FEMCNTL has requested a module to be loaded and it has failed during the load process. Another message usually accompanies this detailing the reason for failure.

function: The functional area of the failing module.

program: The name of the failing module.

Source: FEMMISC

System Action: The FEMCNTL command being processed is ignored.

Operator Response: None.

System Programmer Response: Check previous messages for the cause of the load failure. Take the corrective action as required and re-issue the OS/EM command. Contact OS/EM support for assistance in problem resolution.

FEMRAC030

function MODULE program NOT LOADED

Explanation: The OS/EM command processor FEMCNTL has requested a module to be loaded and it has failed during the load process. Another message usually accompanies this detailing the reason for failure.

function: The functional area of the failing module.

program: The name of the failing module.

Source: FEMRACF

System Action: The FEMCNTL command being processed is ignored.

Operator Response: None.

System Programmer Response: Check previous messages for the cause of the load failure. Take the corrective action as required and re-issue the OS/EM command. Contact OS/EM support for assistance in problem resolution.

FEMRCN030

function MODULE program NOT LOADED

Explanation: The OS/EM command processor FEMCNTL has requested a module to be loaded and it has failed during the load process. Another message usually accompanies this detailing the reason for failure.

function: The functional area of the failing module.

program: The name of the failing module.

Source: FEMRACCN

System Action: The FEMCNTL command being processed is ignored.

Operator Response: None.

System Programmer Response: Check previous messages for the cause of the load failure. Take the corrective action as required and re-issue the OS/EM command. Contact OS/EM support for assistance in problem resolution.

FEMRC2030

function MODULE program NOT LOADED

Explanation: The OS/EM command processor FEMCNTL has requested a module to be loaded and it has failed during the load process. Another message usually accompanies this detailing the reason for failure.

function: The functional area of the failing module.

program: The name of the failing module.

Source: FEMRCX02

System Action: The FEMCNTL command being processed is ignored.

Operator Response: None.

System Programmer Response: Check previous messages for the cause of the load failure. Take the corrective action as required and re-issue the OS/EM command. Contact OS/EM support for assistance in problem resolution.

FEMRD1030

function MODULE program NOT LOADED

Explanation: The OS/EM command processor FEMCNTL has requested a module to be loaded and it has failed during the load process. Another message usually accompanies this detailing the reason for failure.

function: The functional area of the failing module.

program: The name of the failing module.

Source: FEMRDX01

System Action: The FEMCNTL command being processed is ignored.

Operator Response: None.

System Programmer Response: Check previous messages for the cause of the load failure. Take the corrective action as required and re-issue the OS/EM command. Contact OS/EM support for assistance in problem resolution.

FEMREL030

function MODULE program NOT LOADED

Explanation: The OS/EM command processor FEMCNTL has requested a module to be loaded and it has failed during the load process. Another message usually accompanies this detailing the reason for failure.

function: The functional area of the failing module.

program: The name of the failing module.

Source: FEMRELOD

System Action: The FEMCNTL command being processed is ignored.

Operator Response: None.

System Programmer Response: Check previous messages for the cause of the load failure. Take the corrective action as required and re-issue the OS/EM command. Contact OS/EM support for assistance in problem resolution.

FEMSAF030

function MODULE program NOT LOADED

Explanation: The OS/EM command processor FEMCNTL has requested a module to be loaded and it has failed during the load process. Another message usually accompanies this detailing the reason for failure.

function: The functional area of the failing module.

program: The name of the failing module.

Source: FEMSAF

System Action: The FEMCNTL command being processed is ignored.

Operator Response: None.

System Programmer Response: Check previous messages for the cause of the load failure. Take the corrective action as required and re-issue the OS/EM command. Contact OS/EM support for assistance in problem resolution.

FEMSCH030

function MODULE program NOT LOADED

Explanation: The OS/EM command processor FEMCNTL has requested a module to be loaded and it has failed during the load process. Another message usually accompanies this detailing the reason for failure.

function: The functional area of the failing module.

program: The name of the failing module.

Source: FEMTSSCH

System Action: The FEMCNTL command being processed is ignored.

Operator Response: None.

System Programmer Response: Check previous messages for the cause of the load failure. Take the corrective action as required and re-issue the OS/EM command. Contact OS/EM support for assistance in problem resolution.

FEMSCN030

function MODULE program NOT LOADED

Explanation: The OS/EM command processor FEMCNTL has requested a module to be loaded and it has failed during the load process. Another message usually accompanies this detailing the reason for failure.

function: The functional area of the failing module.

program: The name of the failing module.

Source: FEMSAFCN,FEMSMFCN

System Action: The FEMCNTL command being processed is ignored.

Operator Response: None.

System Programmer Response: Check previous messages for the cause of the load failure. Take the corrective action as required and re-issue the OS/EM command. Contact OS/EM support for assistance in problem resolution.

FEMSMF030

function MODULE program NOT LOADED

Explanation: The OS/EM command processor FEMCNTL has requested a module to be loaded and it has failed during the load process. Another message usually accompanies this detailing the reason for failure.

function: The functional area of the failing module.

program: The name of the failing module.

Source: FEMSMFx

System Action: The FEMCNTL command being processed is ignored.

Operator Response: None.

System Programmer Response: Check previous messages for the cause of the load failure. Take the corrective action as required and re-issue the OS/EM command. Contact OS/EM support for assistance in problem resolution.

FEMTCN030

function MODULE program NOT LOADED

Explanation: The OS/EM command processor FEMCNTL has requested a module to be loaded and it has failed during the load process. Another message usually accompanies this detailing the reason for failure.

function: The functional area of the failing module.

program: The name of the failing module.

Source: FEMTSOCN

System Action: The FEMCNTL command being processed is ignored.

Operator Response: None.

System Programmer Response: Check previous messages for the cause of the load failure. Take the corrective action as required and re-issue the OS/EM command. Contact OS/EM support for assistance in problem resolution.

FEMTSO030

function MODULE program NOT LOADED

Explanation: The OS/EM command processor FEMCNTL has requested a module to be loaded and it has failed during the load process. Another message usually accompanies this detailing the reason for failure.

function: The functional area of the failing module.

program: The name of the failing module.

Source: FEMTSO

System Action: The FEMCNTL command being processed is ignored.

Operator Response: None.

System Programmer Response: Check previous messages for the cause of the load failure. Take the corrective action as required and re-issue the OS/EM command. Contact OS/EM support for assistance in problem resolution.

FEMUJI030

function MODULE program NOT LOADED

Explanation: The OS/EM command processor FEMCNTL has requested a module to be loaded and it has failed during the load process. Another message usually accompanies this detailing the reason for failure.

function: The functional area of the failing module.

program: The name of the failing module.

Source: FEMUJI

System Action: The FEMCNTL command being processed is ignored.

Operator Response: None.

System Programmer Response: Check previous messages for the cause of the load failure. Take the corrective action as required and re-issue the OS/EM command. Contact OS/EM support for assistance in problem resolution.

FEMUSI030

function MODULE program NOT LOADED

Explanation: The OS/EM command processor FEMCNTL has requested a module to be loaded and it has failed during the load process. Another message usually accompanies this detailing the reason for failure.

function: The functional area of the failing module.

program: The name of the failing module.

Source: FEMUSI

System Action: The FEMCNTL command being processed is ignored.

Operator Response: None.

System Programmer Response: Check previous messages for the cause of the load failure. Take the corrective action as required and re-issue the OS/EM command. Contact OS/EM support for assistance in problem resolution.

FEMUSO030

function MODULE program NOT LOADED

Explanation: The OS/EM command processor FEMCNTL has requested a module to be loaded and it has failed during the load process. Another message usually accompanies this detailing the reason for failure.

function: The functional area of the failing module.

program: The name of the failing module.

Source: FEMUSO

System Action: The FEMCNTL command being processed is ignored.

Operator Response: None.

System Programmer Response: Check previous messages for the cause of the load failure. Take the corrective action as required and re-issue the OS/EM command. Contact OS/EM support for assistance in problem resolution.

FEMUTL030

function MODULE program NOT LOADED

Explanation: The OS/EM command processor FEMCNTL has requested a module to be loaded and it has failed during the load process. Another message usually accompanies this detailing the reason for failure.

function: The functional area of the failing module.

program: The name of the failing module.

Source: FEMUTL

System Action: The FEMCNTL command being processed is ignored.

Operator Response: None.

System Programmer Response: Check previous messages for the cause of the load failure. Take the corrective action as required and re-issue the OS/EM command. Contact OS/EM support for assistance in problem resolution.

FEMVCN030

function MODULE program NOT LOADED

Explanation: The OS/EM command processor FEMCNTL has requested a module to be loaded and it has failed during the load process. Another message usually accompanies this detailing the reason for failure.

function: The functional area of the failing module.

program: The name of the failing module.

Source: FEMSVCCN

System Action: The FEMCNTL command being processed is ignored.

Operator Response: None.

System Programmer Response: Check previous messages for the cause of the load failure. Take the corrective action as required and re-issue the OS/EM command. Contact OS/EM support for assistance in problem resolution.

FEMX00030

function MODULE program NOT LOADED

Explanation: The OS/EM command processor FEMCNTL has requested a module to be loaded and it has failed during the load process. Another message usually accompanies this detailing the reason for failure.

function: The functional area of the failing module.

program: The name of the failing module.

Source: FEMXIT0

System Action: The FEMCNTL command being processed is ignored.

Operator Response: None.

System Programmer Response: Check previous messages for the cause of the load failure. Take the corrective action as required and re-issue the OS/EM command. Contact OS/EM support for assistance in problem resolution.

FEMX06030

function MODULE program NOT LOADED

Explanation: The OS/EM command processor FEMCNTL has requested a module to be loaded and it has failed during the load process. Another message usually accompanies this detailing the reason for failure.

function: The functional area of the failing module.

program: The name of the failing module.

Source: FEMJ2X06

System Action: The FEMCNTL command being processed is ignored.

Operator Response: None.

System Programmer Response: Check previous messages for the cause of the load failure. Take the corrective action as required and re-issue the OS/EM command. Contact OS/EM support for assistance in problem resolution.

FEMX09030

function MODULE program NOT LOADED

Explanation: The OS/EM command processor FEMCNTL has requested a module to be loaded and it has failed during the load process. Another message usually accompanies this detailing the reason for failure.

function: The functional area of the failing module.

program: The name of the failing module.

Source: FEMJ2X09

System Action: The FEMCNTL command being processed is ignored.

Operator Response: None.

System Programmer Response: Check previous messages for the cause of the load failure. Take the corrective action as required and re-issue the OS/EM command. Contact OS/EM support for assistance in problem resolution.

FEMX49030

function MODULE program NOT LOADED

Explanation: The OS/EM command processor FEMCNTL has requested a module to be loaded and it has failed during the load process. Another message usually accompanies this detailing the reason for failure.

function: The functional area of the failing module.

program: The name of the failing module.

Source: FEMJ2X49

System Action: The FEMCNTL command being processed is ignored.

Operator Response: None.

System Programmer Response: Check previous messages for the cause of the load failure. Take the corrective action as required and re-issue the OS/EM command. Contact OS/EM support for assistance in problem resolution.

FEM2P4030

function MODULE program NOT LOADED

Explanation: The OS/EM command processor FEMCNTL has requested a module to be loaded and it has failed during the load process. Another message usually accompanies this detailing the reason for failure.

function: The functional area of the failing module.

program: The name of the failing module.

Source: FEMJ2P4x

System Action: The FEMCNTL command being processed is ignored.

Operator Response: None.

System Programmer Response: Check previous messages for the cause of the load failure. Take the corrective action as required and re-issue the OS/EM command. Contact OS/EM support for assistance in problem resolution.

FEMDCN031

***WARNING* OS/EM WILL EXPIRE IN nn DAYS**

Explanation: The authorization code for OS/EM functions will expire in nn days.

nn: The number of days until OS/EM functions stop working.

Source: FEMDADCN

System Action: The OS/EM functions continue working until the authorization code has expired.

Operator Response: Contact System Programmer.

System Programmer Response: Contact OS/EM support and request a new authorization code.

FEMABN032

OS/EM INTENTIONAL ABEND S0C3

Explanation: OS/EM has forced an abend S0C3.

Source: FEMABEND, FEMJ2ABx

System Action: This abend is issued by an installation verification test exit.

Operator Response: None.

System Programmer Response: None.

FEMLIM033

LIMIT DATA POINTER AT nnnnnnnn IS INVALID

Explanation: During processing of Jobname Limits for a function, the pointer for the limit data area does not point to the OS/EM optional limit data area for this function. The limit eye catcher is missing.

nnnnnnnn: Virtual storage address of limit table for this function.

Source: FEMLIMIT

System Action: The limit pointer is zeroed and limit processing for this function stops. Message FEMLIM034 is also issued.

Operator Response: Contact System Programmer.

System Programmer Response: Check to see if any catastrophic errors have occurred previously. Storage overlays are the usual cause of this error. Take the corrective action as indicated by any other previous errors. Contact OS/EM support for assistance in problem resolution.

FEMLIM034

LIMIT POINTER ZEROED

Explanation: During processing of Jobname Limits for a function, the pointer for the limit data area does not point to the OS/EM optional limit data area for this function. The limit eye catcher is missing.

Source: FEMLIMIT

System Action: The limit pointer is zeroed and limit processing for this function stops. Message FEMLIM033 is also issued

Operator Response: Contact System Programmer.

System Programmer Response: Check to see if any catastrophic errors have occurred previously. Storage overlays are the usual cause of this error. Take the corrective action as indicated by any other previous errors. Contact OS/EM support for assistance in problem resolution.

FEMNUL035

OS/EM NULL EXIT. RC = nn

Explanation: A null exit has been loaded using optional OS/EM functions and is setting a return code as defined by the FEMNULxx Exit requested.

nn: Return code from the null exit requested.

Source:

FEMNULL0 - Sets return code 00
FEMNULL4 - Sets return code 04
FEMNULL8 - Sets return code 08
FEMNUL12 - Sets return code 12
FEMNUL16 - Sets return code 16

System Action: The OS/EM function where the null exit has been requested continues according to return code checking requested by the Exit definition.

Operator Response: None.

System Programmer Response: None.

FEMUJI036

USER NOT AUTHORIZED TO RUN JOB IN CLASS x

Explanation: During Job initialization processing, OS/EM options have requested Jobclass access enforcement and the Jobclass that is specified on the JOB card is not a valid Jobclass for the USER submitting the JOB.

x: Jobclass the Job was submitted to.

Source: FEMUJI

System Action: The JOB is cancelled.

Operator Response: None.

System Programmer Response: None.

User Response: Change the Jobclass to one that the USER has access to.

FEMWTO037

OS/EM WTO n

Explanation: OS/EM provides some WTO modules for testing options.

Source: FEMWTO0, FEMWTO1, FEMWTO2, FEMWTO3, FEMWTO4, FEMWTO5, FEMWTOX

System Action: The WTO is issued and processing continues.

Operator Response: None.

System Programmer Response: None.

FEMDB4038

nn type TAPES ALLOCATED; ONLY yy ALLOWED

Explanation: During Job allocation processing, OS/EM options have requested tape access enforcement and the number of tapes requested nn exceeds the number allowed in this Job class.

nn: Number of tapes requested.

type: The type of tape unit that has exceeded the allocation quota.

yy: Number of tapes allowed in this Job Class.

Source: FEMDB401

System Action: The JOB is cancelled with a System S222 Abend, unless tape control is in warn mode; in that case message FEMxxx039 will also be issued.

Operator Response: None.

System Programmer Response: None.

User Response: Change the Jobclass to one that the allows the number of tapes required.

FEMW21038

nn type TAPES ALLOCATED; ONLY yy ALLOWED

Explanation: During Job allocation processing, OS/EM options have requested tape access enforcement and the number of tapes requested nn exceeds the number allowed in this Job class.

nn: Number of tapes requested.

type: The type of tape unit that has exceeded the allocation quota.

yy: Number of tapes allowed in this Job Class.

Source: FEMW21SD

System Action: The JOB is cancelled with a System S222 Abend, unless tape control is in warn mode; in that case message FEMxxx039 will also be issued.

Operator Response: None.

System Programmer Response: None.

User Response: Change the Jobclass to one that the allows the number of tapes required.

FEMW21039

***WARNING* JOB WOULD BE CANCELLED**

Explanation: During Job allocation processing, Manager options have requested tape access enforcement and the number of tapes requested nn exceeds the number allowed in this Job class. Tape control is in warn mode.

Source: FEMW21SD

System Action: The JOB is not cancelled, because tape control is warn mode, message FEMxxx038 will also be issued.

Operator Response: None.

System Programmer Response: None.

User Response: Change the Jobclass to one that the allows the number of tapes required.

FEMCTL040

OS/EM CVT NOT FOUND OR NOT INITIALIZED

Explanation: During OS/EM command processing or OS/EM initialization functions, the OS/EM CVT was not found.

Source: FEMCNTL

System Action: The OS/EM command being processed, or the OS/EM function is ignored, because OS/EM functions are not active.

Operator Response: None.

System Programmer Response: Insure that the OS/EM sub-system initialization was successful. Re-IPL the system. Contact OS/EM support for assistance in problem resolution.

FEMHSP040

OS/EM CVT NOT FOUND OR NOT INITIALIZED

Explanation: During OS/EM command processing or OS/EM initialization functions, the OS/EM CVT was not found.

Source: FEMHJ20

System Action: The OS/EM command being processed, or the OS/EM function is ignored, because OS/EM functions are not active.

Operator Response: None.

System Programmer Response: Insure that the OS/EM sub-system initialization was successful. Re-IPL the system. Contact OS/EM support for assistance in problem resolution.

FEMIAT040

OS/EM CVT NOT FOUND OR NOT INITIALIZED

Explanation: During OS/EM command processing or OS/EM initialization functions, the OS/EM CVT was not found.

Source: FEMINTK

System Action: The OS/EM command being processed, or the OS/EM function is ignored, because OS/EM functions are not active.

Operator Response: None.

System Programmer Response: Insure that the OS/EM sub-system initialization was successful. Re-IPL the system. Contact OS/EM support for assistance in problem resolution.

FEMINT040

OS/EM CVT NOT FOUND OR NOT INITIALIZED

Explanation: During OS/EM command processing or OS/EM initialization functions, the OS/EM CVT was not found.

Source: FEMINIT

System Action: The OS/EM command being processed, or the OS/EM function is ignored, because OS/EM functions are not active.

Operator Response: None.

System Programmer Response: Insure that the OS/EM sub-system initialization was successful. Re-IPL the system. Contact OS/EM support for assistance in problem resolution.

FEMLIB040

OS/EM CVT NOT FOUND OR NOT INITIALIZED

Explanation: During OS/EM command processing or OS/EM initialization functions, the OS/EM CVT was not found.

Source: FEMLIB

System Action: The OS/EM command being processed, or the OS/EM function is ignored, because OS/EM functions are not active.

Operator Response: None.

System Programmer Response: Insure that the OS/EM sub-system initialization was successful. Re-IPL the system. Contact OS/EM support for assistance in problem resolution.

FEMTPS040

OS/EM CVT NOT FOUND OR NOT INITIALIZED

Explanation: During OS/EM command processing or OS/EM initialization functions, the OS/EM CVT was not found.

Source: FEMTPSHR

System Action: The OS/EM command being processed, or the OS/EM function is ignored, because OS/EM functions are not active.

Operator Response: None.

System Programmer Response: Insure that the OS/EM sub-system initialization was successful. Re-IPL the system. Contact OS/EM support for assistance in problem resolution.

FEMCTL041

VERB HAS INVALID FORMAT

Explanation: The OS/EM command processor for OS/EM options processing has detected a verb with an invalid format.

Source: FEMCNTL

System Action: The FEMCNTL command being processed is ignored.

Operator Response: None.

System Programmer Response: Insure that the OS/EM FEMCNTL command verb format is correct. Check the command format in this manual for the function being performed. If using the ISPF interface, check the command format for the verb being used. Contact OS/EM support for assistance in problem resolution.

FEMCTL042

VERB IS NOT SUPPORTED

Explanation: The OS/EM command processor for options processing has detected an unsupported verb.

Source: FEMCNTL

System Action: The FEMCNTL command being processed is ignored.

Operator Response: None.

System Programmer Response: Insure that the OS/EM Sub-system command verb is correct. Check the command format in in this manual for the function being performed. If using the ISPF interface, check the verb being used. Contact OS/EM support for assistance in problem resolution.

FEMCTL043

VERB IS NOT UNIQUE

Explanation: The OS/EM command processor has detected a FEMCNTL subcommand that is so abbreviated it matches more than one subcommand for this FEMCNTL command execution.

Source: FEMCNTL

System Action: The FEMCNTL command being processed is ignored.

Operator Response: None.

System Programmer Response: Specify enough of the FEMCNTL subcommand verb to insure the command verb is unique. Check the command format in this manual for the function being performed. If using the ISPF interface, check the subcommand for the verb being used. Contact OS/EM support for assistance in problem resolution.

FEMCTL044

VALID AUTHORIZATION CODE NOT SUPPLIED

Explanation: The OS/EM command processor for OS/EM processing, has determined that a valid authorization code has not been supplied before an FEMCNTL subcommand.

Source: FEMCNTL

System Action: The FEMCNTL command being processed is ignored.

Operator Response: None.

System Programmer Response: Insure that the OS/EM Sub-system was provided with a valid authorization code. Contact OS/EM support for a valid Authorization Code.

FEMLIB044

VALID AUTHORIZATION CODE NOT SUPPLIED

Explanation: The OS/EM command processor for OS/EM processing, has determined that a valid authorization code has not been supplied before an FEMCNTL subcommand.

Source: FEMLIB

System Action: The FEMLIB command being processed is ignored.

Operator Response: None.

System Programmer Response: Insure that the OS/EM Sub-system was provided with a valid authorization code. Contact OS/EM support for a valid Authorization Code.

FEMCTL045

OS/EM HAS EXPIRED

Explanation: The OS/EM command processor for OS/EM processing, has determined that OS/EM has expired.

Source: FEMCNTL

System Action: The FEMCNTL command being processed is ignored.

Operator Response: None.

System Programmer Response: Insure that the OS/EM Sub-system was provided with a valid authorization code. Contact OS/EM support for a valid Authorization Code.

FEMLIB045

OS/EM HAS EXPIRED

Explanation: The OS/EM command processor for OS/EM processing, has determined that OS/EM has expired.

Source: FEMLIB

System Action: The FEMLIB command being processed is ignored.

Operator Response: None.

System Programmer Response: Insure that the OS/EM Sub-system was provided with a valid authorization code. Contact OS/EM support for a valid Authorization Code.

FEMCTL046

USER NOT AUTHORIZED FOR SUBCOMMAND

Explanation: The OS/EM command processor for OS/EM options processing, has determined that security checking for FEMCNTL has been requested, and the User requesting the subcommand is not authorized to use it.

Source: FEMCNTL

System Action: The FEMCNTL command being processed is ignored.

Operator Response: None.

System Programmer Response: If the User requesting the FEMCNTL subcommand requires access, provide access through the Security interface as documented in the OS/EM User Guide.

FEMREL046

USER NOT AUTHORIZED FOR SUBCOMMAND

Explanation: The OS/EM command processor for OS/EM options processing, has determined that security checking for FEMCNTL has been requested, and the User requesting the subcommand is not authorized to use it.

Source: FEMRELOD

System Action: The FEMCNTL command being processed is ignored.

Operator Response: None.

System Programmer Response: If the User requesting the FEMCNTL subcommand requires access, provide access through the Security interface as documented in the OS/EM User Guide.

FEMATH047

***WARNING* RESOURCE 'xxxx' NOT PROTECTED**

Explanation: The OS/EM command processor for OS/EM options processing, has determined that security checking for FEMCNTL functions has not been defined to the security manager in use.

xxxx: The OS/EM resource that is not defined to the security manager.

Source: FEMAUTH

System Action: The FEMCNTL command being processed continues.

Operator Response: None.

System Programmer Response: Implement the Security interface as provided in the OS/EM Installation Guide to insure non-authorized personnel do not have access to the FEMCNTL commands.

FEMALC048

UNEXPECTED PARSE FAILURE

Explanation: The OS/EM command processor uses TSO module IKJPARS for parsing FEMCNTL options. IKJPARS has returned an error during processing of the FEMCNTL command options.

Source: FEMALLOC

System Action: The FEMCNTL command being processed is ignored.

Operator Response: None.

System Programmer Response: The ISPF user interface should be used to generate FEMCNTL commands. If the command was generated by the ISPF interface, contact OS/EM support for assistance in problem resolution.

FEMCOD048

UNEXPECTED PARSE FAILURE

Explanation: The OS/EM command processor uses TSO module IKJPARS for parsing FEMCNTL options. IKJPARS has returned an error during processing of the FEMCNTL command options.

Source: FEMCODE

System Action: The FEMCNTL command being processed is ignored.

Operator Response: None.

System Programmer Response: The ISPF user interface should be used to generate FEMCNTL commands. If the command was generated by the ISPF interface, contact OS/EM support for assistance in problem resolution.

FEMDAD048

UNEXPECTED PARSE FAILURE

Explanation: The OS/EM command processor uses TSO module IKJPARS for parsing FEMCNTL options. IKJPARS has returned an error during processing of the FEMCNTL command options.

Source: FEMDASD

System Action: The FEMCNTL command being processed is ignored.

Operator Response: None.

System Programmer Response: The ISPF user interface should be used to generate FEMCNTL commands. If the command was generated by the ISPF interface, contact OS/EM support for assistance in problem resolution.

FEMDAP048

UNEXPECTED PARSE FAILURE

Explanation: The OS/EM command processor uses TSO module IKJPARS for parsing FEMCNTL options. IKJPARS has returned an error during processing of the FEMCNTL command options.

Source: FEMPOOL

System Action: The FEMCNTL command being processed is ignored.

Operator Response: None.

System Programmer Response: The ISPF user interface should be used to generate FEMCNTL commands. If the command was generated by the ISPF interface, contact OS/EM support for assistance in problem resolution.

FEMDMP048

UNEXPECTED PARSE FAILURE

Explanation: The OS/EM command processor uses TSO module IKJPARS for parsing FEMCNTL options. IKJPARS has returned an error during processing of the FEMCNTL command options.

Source: FEMDUMP

System Action: The FEMCNTL command being processed is ignored.

Operator Response: None.

System Programmer Response: The ISPF user interface should be used to generate FEMCNTL commands. If the command was generated by the ISPF interface, contact OS/EM support for assistance in problem resolution.

FEMHSM048

UNEXPECTED PARSE FAILURE

Explanation: The OS/EM command processor uses TSO module IKJPARS for parsing FEMCNTL options. IKJPARS has returned an error during processing of the FEMCNTL command options.

Source: FEMHSM

System Action: The FEMCNTL command being processed is ignored.

Operator Response: None.

System Programmer Response: The ISPF user interface should be used to generate FEMCNTL commands. If the command was generated by the ISPF interface, contact OS/EM support for assistance in problem resolution.

FEMISP048

UNEXPECTED PARSE FAILURE

Explanation: The OS/EM command processor uses TSO module IKJPARS for parsing FEMCNTL options. IKJPARS has returned an error during processing of the FEMCNTL command options.

Source: FEMISPF

System Action: The FEMCNTL command being processed is ignored.

Operator Response: None.

System Programmer Response: The ISPF user interface should be used to generate FEMCNTL commands. If the command was generated by the ISPF interface, contact OS/EM support for assistance in problem resolution.

FEMJ2#048

UNEXPECTED PARSE FAILURE

Explanation: The OS/EM command processor uses TSO module IKJPARS for parsing FEMCNTL options. IKJPARS has returned an error during processing of the FEMCNTL command options.

Source: FEMJES2

System Action: The FEMCNTL command being processed is ignored.

Operator Response: None.

System Programmer Response: The ISPF user interface should be used to generate FEMCNTL commands. If the command was generated by the ISPF interface, contact OS/EM support for assistance in problem resolution.

FEMJS3048

UNEXPECTED PARSE FAILURE

Explanation: The OS/EM command processor uses TSO module IKJPARS for parsing FEMCNTL options. IKJPARS has returned an error during processing of the FEMCNTL command options.

Source: FEMJES3

System Action: The FEMCNTL command being processed is ignored.

Operator Response: None.

System Programmer Response: The ISPF user interface should be used to generate FEMCNTL commands. If the command was generated by the ISPF interface, contact OS/EM support for assistance in problem resolution.

FEMLIB048

UNEXPECTED PARSE FAILURE

Explanation: The OS/EM command processor uses TSO module IKJPARS for parsing FEMCNTL options. IKJPARS has returned an error during processing of the FEMCNTL command options.

Source: FEMLIB

System Action: The FEMCNTL command being processed is ignored.

Operator Response: None.

System Programmer Response: The ISPF user interface should be used to generate FEMCNTL commands. If the command was generated by the ISPF interface, contact OS/EM support for assistance in problem resolution.

FEMMIS048

UNEXPECTED PARSE FAILURE

Explanation: The OS/EM command processor uses TSO module IKJPARS for parsing FEMCNTL options. IKJPARS has returned an error during processing of the FEMCNTL command options.

Source: FEMMISC

System Action: The FEMCNTL command being processed is ignored.

Operator Response: None.

System Programmer Response: The ISPF user interface should be used to generate FEMCNTL commands. If the command was generated by the ISPF interface, contact OS/EM support for assistance in problem resolution.

FEMQRY048

UNEXPECTED PARSE FAILURE

Explanation: The OS/EM command processor uses TSO module IKJPARS for parsing FEMCNTL options. IKJPARS has returned an error during processing of the FEMCNTL command options.

Source: FEMQUERY

System Action: The FEMCNTL command being processed is ignored.

Operator Response: None.

System Programmer Response: The ISPF user interface should be used to generate FEMCNTL commands. If the command was generated by the ISPF interface, contact OS/EM support for assistance in problem resolution.

FEMRAC048

UNEXPECTED PARSE FAILURE

Explanation: The OS/EM command processor uses TSO module IKJPARS for parsing FEMCNTL options. IKJPARS has returned an error during processing of the FEMCNTL command options.

Source: FEMRACF

System Action: The FEMCNTL command being processed is ignored.

Operator Response: None.

System Programmer Response: The ISPF user interface should be used to generate FEMCNTL commands. If the command was generated by the ISPF interface, contact OS/EM support for assistance in problem resolution.

FEMREL048

UNEXPECTED PARSE FAILURE

Explanation: The OS/EM command processor uses TSO module IKJPARS for parsing FEMCNTL options. IKJPARS has returned an error during processing of the FEMCNTL command options.

Source: FEMRELOD

System Action: The FEMCNTL command being processed is ignored.

Operator Response: None.

System Programmer Response: The ISPF user interface should be used to generate FEMCNTL commands. If the command was generated by the ISPF interface, contact OS/EM support for assistance in problem resolution.

FEMSAF048

UNEXPECTED PARSE FAILURE

Explanation: The OS/EM command processor uses TSO module IKJPARS for parsing FEMCNTL options. IKJPARS has returned an error during processing of the FEMCNTL command options.

Source: FEMFEMSAF

System Action: The FEMCNTL command being processed is ignored.

Operator Response: None.

System Programmer Response: The ISPF user interface should be used to generate FEMCNTL commands. If the command was generated by the ISPF interface, contact OS/EM support for assistance in problem resolution.

FEMSMF048

UNEXPECTED PARSE FAILURE

Explanation: The OS/EM command processor uses TSO module IKJPARS for parsing FEMCNTL options. IKJPARS has returned an error during processing of the FEMCNTL command options.

Source: FEMFEMSMF

System Action: The FEMCNTL command being processed is ignored.

Operator Response: None.

System Programmer Response: The ISPF user interface should be used to generate FEMCNTL commands. If the command was generated by the ISPF interface, contact OS/EM support for assistance in problem resolution.

FEMSTM048

UNEXPECTED PARSE FAILURE

Explanation: The OS/EM command processor uses TSO module IKJPARS for parsing FEMCNTL options. IKJPARS has returned an error during processing of the FEMCNTL command options.

Source: FEMSYSTEM

System Action: The FEMCNTL command being processed is ignored.

Operator Response: None.

System Programmer Response: The ISPF user interface should be used to generate FEMCNTL commands. If the command was generated by the ISPF interface, contact OS/EM support for assistance in problem resolution.

FEMSVU048

UNEXPECTED PARSE FAILURE

Explanation: The OS/EM command processor uses TSO module IKJPARS for parsing FEMCNTL options. IKJPARS has returned an error during processing of the FEMCNTL command options.

Source: FEMSVUCUD

System Action: The FEMCNTL command being processed is ignored.

Operator Response: None.

System Programmer Response: The ISPF user interface should be used to generate FEMCNTL commands. If the command was generated by the ISPF interface, contact OS/EM support for assistance in problem resolution.

FEMTSO048

UNEXPECTED PARSE FAILURE

Explanation: The OS/EM command processor uses TSO module IKJPARS for parsing FEMCNTL options. IKJPARS has returned an error during processing of the FEMCNTL command options.

Source: FEMTSO

System Action: The FEMCNTL command being processed is ignored.

Operator Response: None.

System Programmer Response: The ISPF user interface should be used to generate FEMCNTL commands. If the command was generated by the ISPF interface, contact OS/EM support for assistance in problem resolution.

FEMCOD049

type CODE ACCEPTED

Explanation: The OS/EM command processor has accepted and processed the type code that was specified.

type: AUTHORIZATION , OPTION

Source: FEMCODE

System Action: The type code is processed and enables the FEMCNTL command to process OS/EM optional functions. Also see message FEMCOD052.

Operator Response: None.

System Programmer Response: None.

FEMCOD050

OS/EM WILL EXPIRE yyyy.ddd

Explanation: The OS/EM command processor FEMCNTL will expire in year yyyy and julian day ddd.

yyyy.ddd: Year and julian day OS/EM will expire.

Source: FEMCODE

System Action: All OS/EM optional functions and features will be available until yyyy.dddd. Also see message FEMCOD049.

Operator Response: None.

System Programmer Response: None.

FEMCOD051

type CODE NOT VALID FOR THIS CPU

Explanation: The OS/EM command processor has determined that the type code specified is not valid for this CPU.

type: AUTHORIZATION , OPTION.

Source: FEMCODE

System Action: The type code is not processed and FEMCNTL command is disabled for processing OS/EM optional functions.

Operator Response: Notify the System Programmer.

System Programmer Response: Verify that the type code supplied by OS/EM support was the one entered. Contact OS/EM support for assistance in problem resolution.

FEMDAP052

TYPE dsngroup ALREADY SPECIFIED FOR (DIS)ALLOW - NOT ADDED TO (DIS)ALLOW LIST

Explanation: During processing of FEMCNTL Quick Pool DASD pooling definitions, the same dataset name group was specified as both an allow list and a disallow list.

dsngroup: The name of the dataset name group.

Source: FEMPOOL

System Action: The FEMCNTL Quick Pool DASD pooling definition is not added to the (DIS)Allow list.

Operator Response: None.

System Programmer Response: Remove the dataset name group from either the allow list or the disallow list and re-issue the command.

FEMHSP053

jjjj WAITING FOR OS/EM INITIALIZATION TO COMPLETE

Explanation: OS/EM Sub-system Initialization is in progress. The batch TMP which loads all the OS/EM options has started and prevents job jjjj from starting until the batch TMP has completed.

jjjj: The Sub-system waiting for OS/EM initialization to complete.

Source: FEMHJ20

System Action: The Job jjjj waits until the batch TMP has completed loading all OS/EM options. Message FEMxxx054 is also issued to allow the Job jjjj to start before OS/EM options are loaded but the functional capabilities of Job jjjj could be unpredictable until the batch TMP has loaded the OS/EM options. If the batch TMP Abends reply Y to continue initialization.

Operator Response: None.

System Programmer Response: None.

FEMIAT053

jjjj WAITING FOR OS/EM INITIALIZATION TO COMPLETE

Explanation: OS/EM Sub-system Initialization is in progress. The batch TMP which loads all the OS/EM options has started and prevents job jjjj from starting until the batch TMP has completed.

jjjj: The Sub-system waiting for OS/EM initialization to complete.

Source: FEMINTK

System Action: The Job jjjj waits until the batch TMP has completed loading all OS/EM options. Message FEMxxx054 is also issued to allow the Job jjjj to start before OS/EM options are loaded but the functional capabilities of Job jjjj could be unpredictable until the batch TMP has loaded the OS/EM options. If the batch TMP Abends reply Y to continue initialization.

Operator Response: None.

System Programmer Response: None.

FEMHSP054

REPLY Y TO BYPASS WAIT

Explanation: OS/EM Sub-system Initialization has completed. The batch TMP which loads all the OS/EM options has started and stops Job jjjj from starting until the batch TMP has completed.

Source: FEMHJ20

System Action: The Job as specified in FEMxxx053 waits until the batch TMP has completed loading all OS/EM options. Message FEMxxx054 is issued to allow the Job jjjj to start before OS/EM options are loaded but the functional capabilities of Job jjjj could be unpredictable until the batch TMP has loaded the OS/EM options.

Operator Response: Reply Y only if instructed by the System Programmer. If the batch TMP Abends, reply Y to continue initialization.

System Programmer Response: None.

FEMIAT054

REPLY Y TO BYPASS WAIT

Explanation: OS/EM Sub-system Initialization has completed. The batch TMP which loads all the OS/EM options has started and stops Job jjjj from starting until the batch TMP has completed.

Source: FEMINTK

System Action: The Job as specified in FEMxxx053 waits until the batch TMP has completed loading all OS/EM options. Message FEMxxx054 is issued to allow the Job jjjj to start before OS/EM options are loaded but the functional capabilities of Job jjjj could be unpredictable until the batch TMP has loaded the OS/EM options.

Operator Response: Reply Y only if instructed by the System Programmer. If the batch TMP Abends, reply Y to continue initialization.

System Programmer Response: None.

FEMHSP055

INVALID REPLY - REENTER

Explanation: The operator has replied to message FEMxxx054 and the reply was not a Y. Also see messages FEMxxx053 and FEMxxx054 for further information.

Source: FEMHJ20

System Action: The Job as specified in FEMxxx053 waits until the batch TMP has completed loading all OS/EM options. Message FEMxxx054 is issued to allow the Job jjjj to start before OS/EM options are loaded but the functional capabilities of Job jjjj could be unpredictable until the batch TMP has loaded the OS/EM options.

Operator Response: Reply with correct response (Y) wait for the batch TMP to complete.

System Programmer Response: None.

FEMIAT055

INVALID REPLY - REENTER

Explanation: The operator has replied to message FEMxxx054 and the reply was not a Y. Also see messages FEMxxx053 and FEMxxx054 for further information.

Source: FEMINTK

System Action: The Job as specified in FEMxxx053 waits until the batch TMP has completed loading all OS/EM options. Message FEMxxx054 is issued to allow the Job jjjj to start before OS/EM options are loaded but the functional capabilities of Job jjjj could be unpredictable until the batch TMP has loaded the OS/EM options.

Operator Response: Reply with correct response (Y) wait for the batch TMP to complete.

System Programmer Response: None.

FEM2D0055

INVALID REPLY - REENTER

Explanation: The operator has replied to message FEMxxx054 and the reply was not a Y. Also see messages FEMxxx053 and FEMxxx054 for further information.

Source: FEMJ2D0x

System Action: The Job as specified in FEMxxx053 waits until the batch TMP has completed loading all OS/EM options. Message FEMxxx054 is issued to allow the Job jjjj to start before OS/EM options are loaded but the functional capabilities of Job jjjj could be unpredictable until the batch TMP has loaded the OS/EM options.

Operator Response: Reply with correct response (Y) wait for the batch TMP to complete.

System Programmer Response: None.

FEM2H0055

INVALID REPLY - REENTER

Explanation: The operator has replied to message FEMxxx054 and the reply was not a Y. Also see messages FEMxxx053 and FEMxxx054 for further information.

Source: FEMJ2H0x

System Action: The Job as specified in FEMxxx053 waits until the batch TMP has completed loading all OS/EM options. Message FEMxxx054 is issued to allow the Job jjjj to start before OS/EM options are loaded but the functional capabilities of Job jjjj could be unpredictable until the batch TMP has loaded the OS/EM options.

Operator Response: Reply with correct response (Y) wait for the batch TMP to complete.

System Programmer Response: None.

FEM2H4055

INVALID REPLY - REENTER

Explanation: The operator has replied to message FEMxxx054 and the reply was not a Y. Also see messages FEMxxx053 and FEMxxx054 for further information.

Source: FEMJ2H4x

System Action: The Job as specified in FEMxxx053 waits until the batch TMP has completed loading all OS/EM options. Message FEMxxx054 is issued to allow the Job jjjj to start before OS/EM options are loaded but the functional capabilities of Job jjjj could be unpredictable until the batch TMP has loaded the OS/EM options.

Operator Response: Reply with correct response (Y) wait for the batch TMP to complete.

System Programmer Response: None.

FEM2L0055

INVALID REPLY - REENTER

Explanation: The operator has replied to message FEMxxx054 and the reply was not a Y. Also see messages FEMxxx053 and FEMxxx054 for further information.

Source: FEMJ2L0x

System Action: The Job as specified in FEMxxx053 waits until the batch TMP has completed loading all OS/EM options. Message FEMxxx054 is issued to allow the Job jjjj to start before OS/EM options are loaded but the functional capabilities of Job jjjj could be unpredictable until the batch TMP has loaded the OS/EM options.

Operator Response: Reply with correct response (Y) wait for the batch TMP to complete.

System Programmer Response: None.

FEM2L4055

INVALID REPLY - REENTER

Explanation: The operator has replied to message FEMxxx054 and the reply was not a Y. Also see messages FEMxxx053 and FEMxxx054 for further information.

Source: FEMJ2L4x

System Action: The Job as specified in FEMxxx053 waits until the batch TMP has completed loading all OS/EM options. Message FEMxxx054 is issued to allow the Job jjjj to start before OS/EM options are loaded but the functional capabilities of Job jjjj could be unpredictable until the batch TMP has loaded the OS/EM options.

Operator Response: Reply with correct response (Y) wait for the batch TMP to complete.

System Programmer Response: None.

FEM2M0055

INVALID REPLY - REENTER

Explanation: The operator has replied to message FEMxxx054 and the reply was not a Y. Also see messages FEMxxx053 and FEMxxx054 for further information.

Source: FEMJ2M0x

System Action: The Job as specified in FEMxxx053 waits until the batch TMP has completed loading all OS/EM options. Message FEMxxx054 is issued to allow the Job jjjj to start before OS/EM options are loaded but the functional capabilities of Job jjjj could be unpredictable until the batch TMP has loaded the OS/EM options.

Operator Response: Reply with correct response (Y) wait for the batch TMP to complete.

System Programmer Response: None.

FEM2M4055

INVALID REPLY - REENTER

Explanation: The operator has replied to message FEMxxx054 and the reply was not a Y. Also see messages FEMxxx053 and FEMxxx054 for further information.

Source: FEMJ2M4x

System Action: The Job as specified in FEMxxx053 waits until the batch TMP has completed loading all OS/EM options. Message FEMxxx054 is issued to allow the Job jjjj to start before OS/EM options are loaded but the functional capabilities of Job jjjj could be unpredictable until the batch TMP has loaded the OS/EM options.

Operator Response: Reply with correct response (Y) wait for the batch TMP to complete.

System Programmer Response: None.

FEMX24055

INVALID REPLY - REENTER

Explanation: The operator has replied to message FEMxxx054 and the reply was not a Y. Also see messages FEMxxx053 and FEMxxx054 for further information.

Source: FEMJ2X24

System Action: The Job as specified in FEMxxx053 waits until the batch TMP has completed loading all OS/EM options. Message FEMxxx054 is issued to allow the Job jjjj to start before OS/EM options are loaded but the functional capabilities of Job jjjj could be unpredictable until the batch TMP has loaded the OS/EM options.

Operator Response: Reply with correct response (Y) wait for the batch TMP to complete.

System Programmer Response: None.

FEMIPL056

FEMIPL STARTED

Explanation: OS/EM Sub-system Initialization has started.

Source: FEMIPL

System Action: OS/EM Sub-system Initialization starts.

Operator Response: None.

System Programmer Response: None.

FEMALC057

function DATA AREA MISSING

Explanation: During processing of OS/EM reload facilities, a OS/EM optional module was requested for reload but the function that the module supports has never been selected by OS/EM options.

function: The functional area that the module supports.

Source: FEMALLOC

System Action: Reload processing for the OS/EM module fails.

Operator Response: None.

System Programmer Response: Verify that the module requested for reload was in use prior to issuing the reload command. Contact OS/EM support for assistance in problem resolution.

FEMDAD057

function DATA AREA MISSING

Explanation: During processing of OS/EM reload facilities, a OS/EM optional module was requested for reload but the function that the module supports has never been selected by OS/EM options.

function: The functional area that the module supports.

Source: FEMDASD

System Action: Reload processing for the OS/EM module fails.

Operator Response: None.

System Programmer Response: Verify that the module requested for reload was in use prior to issuing the reload command. Contact OS/EM support for assistance in problem resolution.

FEMHSM057

function DATA AREA MISSING

Explanation: During processing of OS/EM reload facilities, a OS/EM optional module was requested for reload but the function that the module supports has never been selected by OS/EM options.

function: The functional area that the module supports.

Source: FEMHSM

System Action: Reload processing for the OS/EM module fails.

Operator Response: None.

System Programmer Response: Verify that the module requested for reload was in use prior to issuing the reload command. Contact OS/EM support for assistance in problem resolution.

FEMISP057

function DATA AREA MISSING

Explanation: During processing of OS/EM reload facilities, a OS/EM optional module was re-

requested for reload but the function that the module supports has never been selected by OS/EM options.

function: The functional area that the module supports.

Source: FEMISPF

System Action: Reload processing for the OS/EM module fails.

Operator Response: None.

System Programmer Response: Verify that the module requested for reload was in use prior to issuing the reload command. Contact OS/EM support for assistance in problem resolution.

FEMJS2057

function DATA AREA MISSING

Explanation: During processing of OS/EM reload facilities, a OS/EM optional module was requested for reload but the function that the module supports has never been selected by OS/EM options.

function: The functional area that the module supports.

Source: FEMJES2x

System Action: Reload processing for the OS/EM module fails.

Operator Response: None.

System Programmer Response: Verify that the module requested for reload was in use prior to issuing the reload command. Contact OS/EM support for assistance in problem resolution.

FEMJS3057

function DATA AREA MISSING

Explanation: During processing of OS/EM reload facilities, a OS/EM optional module was requested for reload but the function that the module supports has never been selected by OS/EM options.

function: The functional area that the module supports.

Source: FEMJES3

System Action: Reload processing for the OS/EM module fails.

Operator Response: None.

System Programmer Response: Verify that the module requested for reload was in use prior to issuing the reload command. Contact OS/EM support for assistance in problem resolution.

FEMMIS057

function DATA AREA MISSING

Explanation: During processing of OS/EM reload facilities, a OS/EM optional module was requested for reload but the function that the module supports has never been selected by OS/EM options.

function: The functional area that the module supports.

Source: FEMMISC

System Action: Reload processing for the OS/EM module fails.

Operator Response: None.

System Programmer Response: Verify that the module requested for reload was in use prior to issuing the reload command. Contact OS/EM support for assistance in problem resolution.

FEMRAC057

function DATA AREA MISSING

Explanation: During processing of OS/EM reload facilities, a OS/EM optional module was requested for reload but the function that the module supports has never been selected by OS/EM options.

function: The functional area that the module supports.

Source: FEMRACF

System Action: Reload processing for the OS/EM module fails.

Operator Response: None.

System Programmer Response: Verify that the module requested for reload was in use prior to issuing the reload command. Contact OS/EM support for assistance in problem resolution.

FEMREL057

function DATA AREA MISSING

Explanation: During processing of OS/EM reload facilities, a OS/EM optional module was requested for reload but the function that the module supports has never been selected by OS/EM options.

function: The functional area that the module supports.

Source: FEMRELOD

System Action: Reload processing for the OS/EM module fails.

Operator Response: None.

System Programmer Response: Verify that the module requested for reload was in use prior to issuing the reload command. Contact OS/EM support for assistance in problem resolution.

FEMSAF057

function DATA AREA MISSING

Explanation: During processing of OS/EM reload facilities, a OS/EM optional module was requested for reload but the function that the module supports has never been selected by OS/EM options.

function: The functional area that the module supports.

Source: FEMSAF

System Action: Reload processing for the OS/EM module fails.

Operator Response: None.

System Programmer Response: Verify that the module requested for reload was in use prior to issuing the reload command. Contact OS/EM support for assistance in problem resolution.

FEMSMF057

function DATA AREA MISSING

Explanation: During processing of OS/EM reload facilities, a OS/EM optional module was requested for reload but the function that the module supports has never been selected by OS/EM options.

function: The functional area that the module supports.

Source: FEMSMF

System Action: Reload processing for the OS/EM module fails.

Operator Response: None.

System Programmer Response: Verify that the module requested for reload was in use prior to issuing the reload command. Contact OS/EM support for assistance in problem resolution.

FEMTPS057

function DATA AREA MISSING

Explanation: During processing of OS/EM reload facilities, a OS/EM optional module was requested for reload but the function that the module supports has never been selected by OS/EM options.

function: The functional area that the module supports.

Source: FEMTPSHR

System Action: Reload processing for the OS/EM module fails.

Operator Response: None.

System Programmer Response: Verify that the module requested for reload was in use prior to issuing the reload command. Contact OS/EM support for assistance in problem resolution.

FEMTSO057

function DATA AREA MISSING

Explanation: During processing of OS/EM reload facilities, a OS/EM optional module was requested for reload but the function that the module supports has never been selected by OS/EM options.

function: The functional area that the module supports.

Source: FEMTSO

System Action: Reload processing for the OS/EM module fails.

Operator Response: None.

System Programmer Response: Verify that the module requested for reload was in use prior to issuing the reload command. Contact OS/EM support for assistance in problem resolution.

FEMALC058

UNABLE TO RESTORE SVC TABLE ENTRY

Explanation: During processing of macro SVCUPDTE, the SVC table entry was altered by an unknown source.

Source: FEMALLOC

System Action:

Operator Response: None.

System Programmer Response: Check the operator console for some type of catastrophic error. Contact OS/EM support for assistance in problem resolution.

FEMDAD058

UNABLE TO RESTORE SVC TABLE ENTRY

Explanation: During processing of macro SVCUPDTE, the SVC table entry was altered by an unknown source.

Source: FEMDASD

System Action:

Operator Response: None.

System Programmer Response: Check the operator console for some type of catastrophic error. Contact OS/EM support for assistance in problem resolution.

FEMHSM058

UNABLE TO RESTORE SVC TABLE ENTRY

Explanation: During processing of macro SVCUPDTE, the SVC table entry was altered by an unknown source.

Source: FEMHSM

System Action:

Operator Response: None.

System Programmer Response: Check the operator console for some type of catastrophic error. Contact OS/EM support for assistance in problem resolution.

FEMISP058

UNABLE TO RESTORE SVC TABLE ENTRY

Explanation: During processing of macro SVCUPDTE, the SVC table entry was altered by an unknown source.

Source: FEMISPF

System Action:

Operator Response: None.

System Programmer Response: Check the operator console for some type of catastrophic error. Contact OS/EM support for assistance in problem resolution.

FEMJS2058

UNABLE TO RESTORE SVC TABLE ENTRY

Explanation: During processing of macro SVCUPDTE, the SVC table entry was altered by an unknown source.

Source: FEMJES2x

System Action:

Operator Response: None.

System Programmer Response: Check the operator console for some type of catastrophic error. Contact OS/EM support for assistance in problem resolution.

FEMJS3058

UNABLE TO RESTORE SVC TABLE ENTRY

Explanation: During processing of macro SVCUPDTE, the SVC table entry was altered by an unknown source.

Source: FEMJES3

System Action:

Operator Response: None.

System Programmer Response: Check the operator console for some type of catastrophic error. Contact OS/EM support for assistance in problem resolution.

FEMMIS058

UNABLE TO RESTORE SVC TABLE ENTRY

Explanation: During processing of macro SVCUPDTE, the SVC table entry was altered by an unknown source.

Source: FEMMISC

System Action:

Operator Response: None.

System Programmer Response: Check the operator console for some type of catastrophic error. Contact OS/EM support for assistance in problem resolution.

FEMRAC058

UNABLE TO RESTORE SVC TABLE ENTRY

Explanation: During processing of macro SVCUPDTE, the SVC table entry was altered by an unknown source.

Source: FEMRACF

System Action:

Operator Response: None.

System Programmer Response: Check the operator console for some type of catastrophic error. Contact OS/EM support for assistance in problem resolution.

FEMSAF058

UNABLE TO RESTORE SVC TABLE ENTRY

Explanation: During processing of macro SVCUPDTE, the SVC table entry was altered by an unknown source.

Source: FEMSAF

System Action:

Operator Response: None.

System Programmer Response: Check the operator console for some type of catastrophic error. Contact OS/EM support for assistance in problem resolution.

FEMSMF058

UNABLE TO RESTORE SVC TABLE ENTRY

Explanation: During processing of macro SVCUPDTE, the SVC table entry was altered by an unknown source.

Source: FEMSMF

System Action:

Operator Response: None.

System Programmer Response: Check the operator console for some type of catastrophic error. Contact OS/EM support for assistance in problem resolution.

FEMTSO058

UNABLE TO RESTORE SVC TABLE ENTRY

Explanation: During processing of macro SVCUPDTE, the SVC table entry was altered by an unknown source.

Source: FEMTSO

System Action:

Operator Response: None.

System Programmer Response: Check the operator console for some type of catastrophic error. Contact OS/EM support for assistance in problem resolution.

FEMINT059

PROGRAM FEMINIT MUST RUN AS STARTED TASK

Explanation: The batch TMP that loads the OS/EM options must run as started task.

Source: FEMINIT

System Action: The batch TMP stops processing and no OS/EM options are loaded.

Operator Response: Contact the System Programmer.

System Programmer Response: Re-submit the batch TMP as started task.

FEMTPS059

PROGRAM FEMTPSHR MUST RUN AS STARTED TASK

Explanation: The FEMTPSHR program determined that it is not running as a started task.

Source: FEMTPSHR

System Action: FEMTPSHR stops.

Operator Response: None.

System Programmer Response: Review the installation instructions for OS/EM TAPESHR and make any changes necessary so that FEMTPSHR does run as a started task.

FEMINT060

INVALID ASCB ADDRESS FOR POST

Explanation: During the batch TMP that loads the OS/EM options program, the address space control block (ASCB) for the sub-system that OS/EM is attempting to hold up until the batch TMP has completed loading the OPTIONS is invalid.

Source: FEMINIT

System Action: The batch TMP stops processing and no OS/EM options are loaded.

Operator Response: Contact the System Programmer.

System Programmer Response: Re-IPL the system. Contact OS/EM support for assistance in problem resolution.

FEMINT061

SYSTSPRT DD DUMMY ALLOCATION FAILED

Explanation: During the batch TMP that loads the OS/EM options program, the DDNAME SYSTSPRT was missing, the batch TMP attempted to allocate the SYSTSPRT as a DUMMY DDNAME but failed.

Source: FEMINIT

System Action: The batch TMP stops processing and no OS/EM options are loaded.

Operator Response: Contact the System Programmer.

System Programmer Response: Correct the JCL for the batch TMP and include the SYSTSPRT DDNAME. Contact OS/EM support for assistance in problem resolution.

FEMINT062

SYSTSPRT ALLOCATED TO DUMMY

Explanation: During the batch TMP that loads the OS/EM options program, the DDNAME SYSTSPRT was missing, the batch TMP attempted to allocated the SYSTSPRT as a DUMMY DDNAME.

Source: FEMINIT

System Action: The batch TMP continues processing.

Operator Response: Contact the System Programmer.

System Programmer Response: Correct the JCL for the batch TMP and include the SYSTSPRT DDNAME. The SYSTSPRT DDNAME is used to collect the initialization messages that are written at IPL time.

FEMINT063

SYSDUMP NOT ALLOCATED - CONTINUING

Explanation: During the batch TMP that loads the OS/EM options program, the DDNAME SYSDUMP was missing.

Source: FEMINIT

System Action: The batch TMP continues processing.

Operator Response: Contact the System Programmer.

System Programmer Response: Correct the JCL for the batch TMP and include the SYSDUMP DDNAME. The SYSDUMP DDNAME is used to write the SVC dump if the batch TMP Abends.

FEMINT064

TMP IKJEFT01 ABENDED aaaa

Explanation: The batch TMP that loads the MVS OS/EM options program has abended with a System Abend aaaa.

aaaa: MVS System Abend code.

Source: FEMINIT

System Action: The batch TMP stops processing.

Operator Response: Contact the System Programmer.

System Programmer Response: Use IPCS to process the SVC dump from the SYSDUMP DDNAME in the batch TMP, take the corrective action required, perform an LLA,REFRESH, and start the batch TMP. Contact OS/EM support for assistance in problem resolution.

FEMINT065

program ATTACH FAILED. RC = rc

Explanation: The OS/EM module that attaches the TSO batch TMP has failed.

program: IKJEFT01
rc: ATTACH return code.

Source: FEMINIT

System Action: The batch TMP stops processing.

Operator Response: Contact the System Programmer.

System Programmer Response: Refer to ATTACH macro to determine meaning of the return code, take the corrective action required, perform an LLA,REFRESH, and start the batch TMP. Contact OS/EM support for assistance in problem resolution.

FEMALC066

dataset DYNAMIC (UN)ALLOCATION FAILED. RC = rc

Explanation: An OS/EM module has attempted to dynamically allocate or unallocate a dataset and has failed.

dataset: The DDNAME or Dataset Name that was being allocated or unallocated.
DDNAME for Batch TMP
Password Dataset
Communication Dataset for TAPESHR
rc: Dynamic Allocation (SVC99) return code.

Source:: FEMALLO1

System Action: The FEMALLO1 function being executed fails.

Operator Response: Contact the System Programmer.

System Programmer Response: Refer to SVC99 macro to determine the meaning of the return code, take the corrective action required, re-issue the command or restart the batch TMP. Contact OS/EM support for assistance in problem resolution.

FEMBI4066

dataset DYNAMIC (UN)ALLOCATION FAILED. RC = rc

Explanation: An OS/EM module has attempted to dynamically allocate or unallocate a dataset and has failed.

dataset: The DDNAME or Dataset Name that was being allocated or unallocated.
DDNAME for Batch TMP
Password Dataset
Communication Dataset for TAPESHR
rc: Dynamic Allocation (SVC99) return code.

Source:: FEMBR14

System Action: The FEMBR14 function being executed fails.

Operator Response: Contact the System Programmer.

System Programmer Response: Refer to SVC99 macro to determine the meaning of the return code, take the corrective action required, re-issue the command or restart the batch TMP. Contact OS/EM support for assistance in problem resolution.

FEMINT066

dataset DYNAMIC (UN)ALLOCATION FAILED. RC = rc

Explanation: An OS/EM module has attempted to dynamically allocate or unallocate a dataset and has failed.

dataset: The DDNAME or Dataset Name that was being allocated or unallocated.
DDNAME for Batch TMP
Password Dataset
Communication Dataset for TAPESHR

rc: Dynamic Allocation (SVC99) return code.

Source:: FEMINIT

System Action: The FEMINIT function being executed fails.

Operator Response: Contact the System Programmer.

System Programmer Response: Refer to SVC99 macro to determine the meaning of the return code, take the corrective action required, re-issue the command or restart the batch TMP. Contact OS/EM support for assistance in problem resolution.

FEMIPLO66

dataset DYNAMIC (UN)ALLOCATION FAILED. RC = rc

Explanation: An OS/EM module has attempted to dynamically allocate or unallocate a dataset and has failed.

dataset: The DDNAME or Dataset Name that was being allocated or unallocated.
DDNAME for Batch TMP
Password Dataset
Communication Dataset for TAPESHR

rc: Dynamic Allocation (SVC99) return code.

Source:: FEMIPL

System Action: The FEMIPL function being executed fails.

Operator Response: Contact the System Programmer.

System Programmer Response: Refer to SVC99 macro to determine the meaning of the return code, take the corrective action required, re-issue the command or restart the batch TMP. Contact OS/EM support for assistance in problem resolution.

FEMJS2066

dataset DYNAMIC (UN)ALLOCATION FAILED. RC = rc

Explanation: An OS/EM module has attempted to dynamically allocate or unallocate a dataset and has failed.

dataset: The DDNAME or Dataset Name that was being allocated or unallocated.
DDNAME for Batch TMP
Password Dataset
Communication Dataset for TAPESHR

rc: Dynamic Allocation (SVC99) return code.

Source:: FEMJES2B,FEMJES2G

System Action: The FEMJES2B,FEMJES2G function being executed fails.

Operator Response: Contact the System Programmer.

System Programmer Response: Refer to SVC99 macro to determine the meaning of the return code, take the corrective action required, re-issue the command or restart the batch TMP. Contact OS/EM support for assistance in problem resolution.

FEMLIB066

dataset DYNAMIC (UN)ALLOCATION FAILED. RC = rc

Explanation: An OS/EM module has attempted to dynamically allocate or unallocate a dataset and has failed.

dataset: The DDNAME or Dataset Name that was being allocated or unallocated.
DDNAME for Batch TMP
Password Dataset
Communication Dataset for TAPESHR
rc: Dynamic Allocation (SVC99) return code.

Source:: FEMLIB

System Action: The FEMLIB function being executed fails.

Operator Response: Contact the System Programmer.

System Programmer Response: Refer to SVC99 macro to determine the meaning of the return code, take the corrective action required, re-issue the command or restart the batch TMP. Contact OS/EM support for assistance in problem resolution.

FEMLOD066

dataset DYNAMIC (UN)ALLOCATION FAILED. RC = rc

Explanation: An OS/EM module has attempted to dynamically allocate or unallocate a dataset and has failed.

dataset: The DDNAME or Dataset Name that was being allocated or unallocated.
DDNAME for Batch TMP
Password Dataset
Communication Dataset for TAPESHR
rc: Dynamic Allocation (SVC99) return code.

Source:: FEMLOAD

System Action: The FEMLOAD function being executed fails.

Operator Response: Contact the System Programmer.

System Programmer Response: Refer to SVC99 macro to determine the meaning of the return code, take the corrective action required, re-issue the command or restart the batch TMP. Contact OS/EM support for assistance in problem resolution.

FEMTPS066

dataset DYNAMIC (UN)ALLOCATION FAILED. RC = rc

Explanation: An OS/EM module has attempted to dynamically allocate or unallocate a dataset and has failed.

dataset: The DDNAME or Dataset Name that was being allocated or unallocated.
DDNAME for Batch TMP
Password Dataset
Communication Dataset for TAPESHR
rc: Dynamic Allocation (SVC99) return code.

Source:: FEMTPSHR

System Action: The FEMTPSHR function being executed fails.

Operator Response: Contact the System Programmer.

System Programmer Response: Refer to SVC99 macro to determine the meaning of the return code, take the corrective action required, re-issue the command or restart the batch TMP. Contact OS/EM support for assistance in problem resolution.

FEMW21066

dataset DYNAMIC (UN)ALLOCATION FAILED. RC = rc

Explanation: An OS/EM module has attempted to dynamically allocate or unallocate a dataset and has failed.

dataset: The DDNAME or Dataset Name that was being allocated or unallocated.

DDNAME for Batch TMP

Password Dataset

Communication Dataset for TAPESHR

rc: Dynamic Allocation (SVC99) return code.

Source:: FEMW21SD

System Action: The FEMW21SD function being executed fails.

Operator Response: Contact the System Programmer.

System Programmer Response: Refer to SVC99 macro to determine the meaning of the return code, take the corrective action required, re-issue the command or restart the batch TMP. Contact OS/EM support for assistance in problem resolution.

FEM2M0066

dataset DYNAMIC (UN)ALLOCATION FAILED. RC = rc

Explanation: An OS/EM module has attempted to dynamically allocate or unallocate a dataset and has failed.

dataset: The DDNAME or Dataset Name that was being allocated or unallocated.

DDNAME for Batch TMP

Password Dataset

Communication Dataset for TAPESHR

rc: Dynamic Allocation (SVC99) return code.

Source:: FEMJ2M0x

System Action: The FEMJ2M0x function being executed fails.

Operator Response: Contact the System Programmer.

System Programmer Response: Refer to SVC99 macro to determine the meaning of the return code, take the corrective action required, re-issue the command or restart the batch TMP. Contact OS/EM support for assistance in problem resolution.

FEM2M1066

dataset DYNAMIC (UN)ALLOCATION FAILED. RC = rc

Explanation: An OS/EM module has attempted to dynamically allocate or unallocate a dataset and has failed.

dataset: The DDNAME or Dataset Name that was being allocated or unallocated.

DDNAME for Batch TMP

Password Dataset
Communication Dataset for TAPESHR
rc: Dynamic Allocation (SVC99) return code.

Source:: FEMJ2M1x

System Action: The FEMJ2M1x function being executed fails.

Operator Response: Contact the System Programmer.

System Programmer Response: Refer to SVC99 macro to determine the meaning of the return code, take the corrective action required, re-issue the command or restart the batch TMP. Contact OS/EM support for assistance in problem resolution.

FEMVCN067

OS/EM SVC MODULE program DEACTIVATED

Explanation: The OS/EM SVC module program has been disabled / deactivated.

program: OS/EM SVC intercept module:
FEM0002F - SVC 26 Not Cataloged 2 intercept
FEM0004B - SVC 42 Attach SVC for JES2 or JES3 initialization

Source: FEMSVCCN

System Action: The SVC module is deactivated and the OS/EM function is disabled. Additional messages FEMxxx068 and FEMVCN069 are issued and a SVC dump is taken. If the function is SVC 26 then all optional OS/EM functions related to NOT CATALOGED 2 processing will be inoperative. If the function is SVC 42 then JES2 or JES3 initialization will proceed without OS/EM options being initialized; this could provide some additional problems during JES2 or JES3 initialization.

Operator Response: None.

System Programmer Response: Use IPCS to determine the reason for the abend. Take the corrective action indicated. Reload the SVC intercept using OS/EM reload facilities. Contact OS/EM support for assistance in problem resolution.

FEMVCN069

OS/EM SVC nnn INTERCEPT INACTIVATED

Explanation: The OS/EM SVC nnn intercept has been inactivated / disabled.

nnn: SVC intercept number:
SVC 26 Not Cataloged 2 intercept
SVC 42 Attach SVC for JES2 or JES3 initialization

Source: FEMSVCCN

System Action: The SVC module is intercept is inactivated. Additional messages FEMVCN067 and FEMxxx068 are issued and a SVC dump is taken. If the function is SVC 26 then all optional OS/EM functions related to NOT CATALOGED 2 processing will be inoperative. If the function is SVC 42 then JES2 or JES3 initialization will proceed without OS/EM options being initialized, this could provide some additional problems during JES2 or JES3 initialization.

Operator Response: None.

System Programmer Response: Use IPCS to determine the reason for the abend. Take the corrective action indicated. Reload the SVC intercept using OS/EM reload facilities. Contact OS/EM support for assistance in problem resolution.

FEMACN070

ABEND Ssss/Uuuu, PSW AT ABEND: pppp pppp

Explanation: OS/EM has detected an MVS System ABEND during execution of an OS/EM optional function or a user exit.

Ssss: The MVS system code.

Usss: The MVS user reason code.

pppp pppp: The PSW.

Source: FEMALCCN

System Action: The OS/EM function being executed continues. OS/EM takes an SVC dump for the abending module, takes the abending module out of service, and deletes the abending module from CSA/ECSA. See messages FEMxxx023, FEMxxx026 and FEMxxx029.

Operator Response: Contact the System Programmer.

System Programmer Response: Use IPCS to determine the cause of the ABEND, take the corrective action required, perform a LLA,REFRESH and reload the failing module using the OS/EM ISPF RELOAD facility. If necessary, contact OS/EM Technical Support for assistance with problem resolution.

FEMALC070

ABEND Ssss/Uuuu, PSW AT ABEND: pppp pppp

Explanation: OS/EM has detected an MVS System ABEND during execution of an OS/EM optional function or a user exit.

Ssss: The MVS system code.

Usss: The MVS user reason code.

pppp pppp: The PSW.

Source: FEMALLO0,FEMALLO1

System Action: The OS/EM function being executed continues. OS/EM takes an SVC dump for the abending module, takes the abending module out of service, and deletes the abending module from CSA/ECSA. See messages FEMxxx023, FEMxxx026 and FEMxxx029.

Operator Response: Contact the System Programmer.

System Programmer Response: Use IPCS to determine the cause of the ABEND, take the corrective action required, perform a LLA,REFRESH and reload the failing module using the OS/EM ISPF RELOAD facility. If necessary, contact OS/EM Technical Support for assistance with problem resolution.

FEMASY070

ABEND Ssss/Uuuu, PSW AT ABEND: pppp pppp

Explanation: OS/EM has detected an MVS System ABEND during execution of an OS/EM optional function or a user exit.

Ssss: The MVS system code.

Usss: The MVS user reason code.

pppp pppp: The PSW.

Source: FEMASYNC

System Action: The OS/EM function being executed continues. OS/EM takes an SVC dump for the abending module, takes the abending module out of service, and deletes the abending module from CSA/ECSA. See messages FEMxxx023, FEMxxx026 and FEMxxx029.

Operator Response: Contact the System Programmer.

System Programmer Response: Use IPCS to determine the cause of the ABEND, take the corrective action required, perform a LLA,REFRESH and reload the failing module using the OS/EM ISPF RELOAD facility. If necessary, contact OS/EM Technical Support for assistance with problem resolution.

FEMCMD070

ABEND Ssss/Uuuu, PSW AT ABEND: pppp pppp

Explanation: OS/EM has detected an MVS System ABEND during execution of an OS/EM optional function or a user exit.

Ssss: The MVS system code.

Usss: The MVS user reason code.

pppp pppp: The PSW.

Source: FEMCMD

System Action: The OS/EM function being executed continues. OS/EM takes an SVC dump for the abending module, takes the abending module out of service, and deletes the abending module from CSA/ECSA. See messages FEMxxx023, FEMxxx026 and FEMxxx029.

Operator Response: Contact the System Programmer.

System Programmer Response: Use IPCS to determine the cause of the ABEND, take the corrective action required, perform a LLA,REFRESH and reload the failing module using the OS/EM ISPF RELOAD facility. If necessary, contact OS/EM Technical Support for assistance with problem resolution.

FEMCOM070

ABEND Ssss/Uuuu, PSW AT ABEND: pppp pppp

Explanation: OS/EM has detected an MVS System ABEND during execution of an OS/EM optional function or a user exit.

Ssss: The MVS system code.

Usss: The MVS user reason code.

pppp pppp: The PSW.

Source: FEMCOMM

System Action: The OS/EM function being executed continues. OS/EM takes an SVC dump for the abending module, takes the abending module out of service, and deletes the abending module from CSA/ECSA. See messages FEMxxx023, FEMxxx026 and FEMxxx029.

Operator Response: Contact the System Programmer.

System Programmer Response: Use IPCS to determine the cause of the ABEND, take the corrective action required, perform a LLA,REFRESH and reload the failing module using the OS/EM ISPF RELOAD facility. If necessary, contact OS/EM Technical Support for assistance with problem resolution.

FEMDCN070

ABEND Ssss/Uuuu, PSW AT ABEND: pppp pppp

Explanation: OS/EM has detected an MVS System ABEND during execution of an OS/EM optional function or a user exit.

Ssss: The MVS system code.

Usss: The MVS user reason code.

pppp pppp: The PSW.

Source: FEMDADCN

System Action: The OS/EM function being executed continues. OS/EM takes an SVC dump for the abending module, takes the abending module out of service, and deletes the abending module from CSA/ECSA. See messages FEMxxx023, FEMxxx026 and FEMxxx029.

Operator Response: Contact the System Programmer.

System Programmer Response: Use IPCS to determine the cause of the ABEND, take the corrective action required, perform a LLA,REFRESH and reload the failing module using the OS/EM ISPF RELOAD facility. If necessary, contact OS/EM Technical Support for assistance with problem resolution.

FEMDC1070

ABEND Ssss/Uuuu, PSW AT ABEND: pppp pppp

Explanation: OS/EM has detected an MVS System ABEND during execution of an OS/EM optional function or a user exit.

Ssss: The MVS system code.

Usss: The MVS user reason code.

pppp pppp: The PSW.

Source: FEMDCB1

System Action: The OS/EM function being executed continues. OS/EM takes an SVC dump for the abending module, takes the abending module out of service, and deletes the abending module from CSA/ECSA. See messages FEMxxx023, FEMxxx026 and FEMxxx029.

Operator Response: Contact the System Programmer.

System Programmer Response: Use IPCS to determine the cause of the ABEND, take the corrective action required, perform a LLA,REFRESH and reload the failing module using the OS/EM ISPF RELOAD facility. If necessary, contact OS/EM Technical Support for assistance with problem resolution.

FEMEXR070

ABEND Ssss/Uuuu, PSW AT ABEND: pppp pppp

Explanation: OS/EM has detected an MVS System ABEND during execution of an OS/EM optional function or a user exit.

Ssss: The MVS system code.

Usss: The MVS user reason code.

pppp pppp: The PSW.

Source: FEMEXRTN

System Action: The OS/EM function being executed continues. OS/EM takes an SVC dump for the abending module, takes the abending module out of service, and deletes the abending module from CSA/ECSA. See messages FEMxxx023, FEMxxx026 and FEMxxx029.

Operator Response: Contact the System Programmer.

System Programmer Response: Use IPCS to determine the cause of the ABEND, take the corrective action required, perform a LLA,REFRESH and reload the failing module using the OS/EM ISPF RELOAD facility. If necessary, contact OS/EM Technical Support for assistance with problem resolution.

FEMFRA070

ABEND Ssss/Uuuu, PSW AT ABEND: pppp pppp

Explanation: OS/EM has detected an MVS System ABEND during execution of an OS/EM optional function or a user exit.

Ssss: The MVS system code.

Usss: The MVS user reason code.

pppp pppp: The PSW.

Source: FEMFRACN

System Action: The OS/EM function being executed continues. OS/EM takes an SVC dump for the abending module, takes the abending module out of service, and deletes the abending module from CSA/ECSA. See messages FEMxxx023, FEMxxx026 and FEMxxx029.

Operator Response: Contact the System Programmer.

System Programmer Response: Use IPCS to determine the cause of the ABEND, take the corrective action required, perform a LLA,REFRESH and reload the failing module using the OS/EM ISPF RELOAD facility. If necessary, contact OS/EM Technical Support for assistance with problem resolution.

FEMFTN070

ABEND Ssss/Uuuu, PSW AT ABEND: pppp pppp

Explanation: OS/EM has detected an MVS System ABEND during execution of an OS/EM optional function or a user exit.

Ssss: The MVS system code.

Usss: The MVS user reason code.

pppp pppp: The PSW.

Source: FEMFRRTN

System Action: The OS/EM function being executed continues. OS/EM takes an SVC dump for the abending module, takes the abending module out of service, and deletes the abending module from CSA/ECSA. See messages FEMxxx023, FEMxxx026 and FEMxxx029.

Operator Response: Contact the System Programmer.

System Programmer Response: Use IPCS to determine the cause of the ABEND, take the corrective action required, perform a LLA,REFRESH and reload the failing module using the OS/EM ISPF RELOAD facility. If necessary, contact OS/EM Technical Support for assistance with problem resolution.

FEMHCN070

ABEND Ssss/Uuuu, PSW AT ABEND: pppp pppp

Explanation: OS/EM has detected an MVS System ABEND during execution of an OS/EM optional function or a user exit.

Ssss: The MVS system code.

Usss: The MVS user reason code.

pppp pppp: The PSW.

Source: FEMHSMCN

System Action: The OS/EM function being executed continues. OS/EM takes an SVC dump for the abending module, takes the abending module out of service, and deletes the abending module from CSA/ECSA. See messages FEMxxx023, FEMxxx026 and FEMxxx029.

Operator Response: Contact the System Programmer.

System Programmer Response: Use IPCS to determine the cause of the ABEND, take the corrective action required, perform a LLA,REFRESH and reload the failing module using the OS/EM ISPF RELOAD facility. If necessary, contact OS/EM Technical Support for assistance with problem resolution.

FEMHSP070

ABEND Ssss/Uuuu, PSW AT ABEND: pppp pppp

Explanation: OS/EM has detected an MVS System ABEND during execution of an OS/EM optional function or a user exit.

Ssss: The MVS system code.

Usss: The MVS user reason code.

pppp pppp: The PSW.

Source: FEMHJ20

System Action: The OS/EM function being executed continues. OS/EM takes an SVC dump for the abending module, takes the abending module out of service, and deletes the abending module from CSA/ECSA. See messages FEMxxx023, FEMxxx026 and FEMxxx029.

Operator Response: Contact the System Programmer.

System Programmer Response: Use IPCS to determine the cause of the ABEND, take the corrective action required, perform a LLA,REFRESH and reload the failing module using the OS/EM ISPF RELOAD facility. If necessary, contact OS/EM Technical Support for assistance with problem resolution.

FEMIAT070

ABEND Ssss/Uuuu, PSW AT ABEND: pppp pppp

Explanation: OS/EM has detected an MVS System ABEND during execution of an OS/EM optional function or a user exit.

Ssss: The MVS system code.

Usss: The MVS user reason code.

pppp pppp: The PSW.

Source: FEMINTK

System Action: The OS/EM function being executed continues. OS/EM takes an SVC dump for the abending module, takes the abending module out of service, and deletes the abending module from CSA/ECSA. See messages FEMxxx023, FEMxxx026 and FEMxxx029.

Operator Response: Contact the System Programmer.

System Programmer Response: Use IPCS to determine the cause of the ABEND, take the corrective action required, perform a LLA,REFRESH and reload the failing module using the OS/EM ISPF RELOAD facility. If necessary, contact OS/EM Technical Support for assistance with problem resolution.

FEMICN070

ABEND Ssss/Uuuu, PSW AT ABEND: pppp pppp

Explanation: OS/EM has detected an MVS System ABEND during execution of an OS/EM optional function or a user exit.

Ssss: The MVS system code.

Usss: The MVS user reason code.

pppp pppp: The PSW.

Source: FEMISPCN

System Action: The OS/EM function being executed continues. OS/EM takes an SVC dump for the abending module, takes the abending module out of service, and deletes the abending module from CSA/ECSA. See messages FEMxxx023, FEMxxx026 and FEMxxx029.

Operator Response: Contact the System Programmer.

System Programmer Response: Use IPCS to determine the cause of the ABEND, take the corrective action required, perform a LLA,REFRESH and reload the failing module using the OS/EM ISPF RELOAD facility. If necessary, contact OS/EM Technical Support for assistance with problem resolution.

FEMIPL070

ABEND Ssss/Uuuu, PSW AT ABEND: pppp pppp

Explanation: OS/EM has detected an MVS System ABEND during execution of an OS/EM optional function or a user exit.

Ssss: The MVS system code.

Usss: The MVS user reason code.

pppp pppp: The PSW.

Source: FEMIPL

System Action: The OS/EM function being executed continues. OS/EM takes an SVC dump for the abending module, takes the abending module out of service, and deletes the abending module from CSA/ECSA. See messages FEMxxx023, FEMxxx026 and FEMxxx029.

Operator Response: Contact the System Programmer.

System Programmer Response: Use IPCS to determine the cause of the ABEND, take the corrective action required, perform a LLA,REFRESH and reload the failing module using the OS/EM ISPF RELOAD facility. If necessary, contact OS/EM Technical Support for assistance with problem resolution.

FEMJS2070

ABEND Ssss/Uuuu, PSW AT ABEND: pppp pppp

Explanation: OS/EM has detected an MVS System ABEND during execution of an OS/EM optional function or a user exit.

Ssss: The MVS system code.

Usss: The MVS user reason code.

pppp pppp: The PSW.

Source: FEMJES2B,FEMJES2G

System Action: The OS/EM function being executed continues. OS/EM takes an SVC dump for the abending module, takes the abending module out of service, and deletes the abending module from CSA/ECSA. See messages FEMxxx023, FEMxxx026 and FEMxxx029.

Operator Response: Contact the System Programmer.

System Programmer Response: Use IPCS to determine the cause of the ABEND, take the corrective action required, perform a LLA,REFRESH and reload the failing module using the OS/EM ISPF RELOAD facility. If necessary, contact OS/EM Technical Support for assistance with problem resolution.

FEMJ2M070

ABEND Ssss/Uuuu, PSW AT ABEND: pppp pppp

Explanation: OS/EM has detected an MVS System ABEND during execution of an OS/EM optional function or a user exit.

Ssss: The MVS system code.

Usss: The MVS user reason code.

pppp pppp: The PSW.

Source: FEMJ2MCx

System Action: The OS/EM function being executed continues. OS/EM takes an SVC dump for the abending module, takes the abending module out of service, and deletes the abending module from CSA/ECSA. See messages FEMxxx023, FEMxxx026 and FEMxxx029.

Operator Response: Contact the System Programmer.

System Programmer Response: Use IPCS to determine the cause of the ABEND, take the corrective action required, perform a LLA,REFRESH and reload the failing module using the OS/EM ISPF RELOAD facility. If necessary, contact OS/EM Technical Support for assistance with problem resolution.

FEMJ2R070

ABEND Ssss/Uuuu, PSW AT ABEND: pppp pppp

Explanation: OS/EM has detected an MVS System ABEND during execution of an OS/EM optional function or a user exit.

Ssss: The MVS system code.

Usss: The MVS user reason code.

pppp pppp: The PSW.

Source: FEMJ2ERx

System Action: The OS/EM function being executed continues. OS/EM takes an SVC dump for the abending module, takes the abending module out of service, and deletes the abending module from CSA/ECSA. See messages FEMxxx023, FEMxxx026 and FEMxxx029.

Operator Response: Contact the System Programmer.

System Programmer Response: Use IPCS to determine the cause of the ABEND, take the corrective action required, perform a LLA,REFRESH and reload the failing module using the OS/EM ISPF RELOAD facility. If necessary, contact OS/EM Technical Support for assistance with problem resolution.

FEMJ2S070

ABEND Ssss/Uuuu, PSW AT ABEND: pppp pppp

Explanation: OS/EM has detected an MVS System ABEND during execution of an OS/EM optional function or a user exit.

Ssss: The MVS system code.

Usss: The MVS user reason code.

pppp pppp: The PSW.

Source: FEMJ2SCx

System Action: The OS/EM function being executed continues. OS/EM takes an SVC dump for the abending module, takes the abending module out of service, and deletes the abending module from CSA/ECSA. See messages FEMxxx023, FEMxxx026 and FEMxxx029.

Operator Response: Contact the System Programmer.

System Programmer Response: Use IPCS to determine the cause of the ABEND, take the corrective action required, perform a LLA,REFRESH and reload the failing module using the OS/EM ISPF RELOAD facility. If necessary, contact OS/EM Technical Support for assistance with problem resolution.

FEMJ3E070

ABEND Ssss/Uuuu, PSW AT ABEND: pppp pppp

Explanation: OS/EM has detected an MVS System ABEND during execution of an OS/EM optional function or a user exit.

Ssss: The MVS system code.

Usss: The MVS user reason code.

pppp pppp: The PSW.

Source: FEMJ3ECN

System Action: The OS/EM function being executed continues. OS/EM takes an SVC dump for the abending module, takes the abending module out of service, and deletes the abending module from CSA/ECSA. See messages FEMxxx023, FEMxxx026 and FEMxxx029.

Operator Response: Contact the System Programmer.

System Programmer Response: Use IPCS to determine the cause of the ABEND, take the corrective action required, perform a LLA,REFRESH and reload the failing module using the OS/EM ISPF RELOAD facility. If necessary, contact OS/EM Technical Support for assistance with problem resolution.

FEMJ3S070

ABEND Ssss/Uuuu, PSW AT ABEND: pppp pppp

Explanation: OS/EM has detected an MVS System ABEND during execution of an OS/EM optional function or a user exit.

Ssss: The MVS system code.

Usss: The MVS user reason code.

pppp pppp: The PSW.

Source: FEMJ3SVC

System Action: The OS/EM function being executed continues. OS/EM takes an SVC dump for the abending module, takes the abending module out of service, and deletes the abending module from CSA/ECSA. See messages FEMxxx023, FEMxxx026 and FEMxxx029.

Operator Response: Contact the System Programmer.

System Programmer Response: Use IPCS to determine the cause of the ABEND, take the corrective action required, perform a LLA,REFRESH and reload the failing module using the OS/EM ISPF RELOAD facility. If necessary, contact OS/EM Technical Support for assistance with problem resolution.

FEMLOK070

ABEND Ssss/Uuuu, PSW AT ABEND: pppp pppp

Explanation: OS/EM has detected an MVS System ABEND during execution of an OS/EM optional function or a user exit.

Ssss: The MVS system code.

Usss: The MVS user reason code.

pppp pppp: The PSW.

Source: FEMLOCK

System Action: The OS/EM function being executed continues. OS/EM takes an SVC dump for the abending module, takes the abending module out of service, and deletes the abending module from CSA/ECSA. See messages FEMxxx023, FEMxxx026 and FEMxxx029.

Operator Response: Contact the System Programmer.

System Programmer Response: Use IPCS to determine the cause of the ABEND, take the corrective action required, perform a LLA,REFRESH and reload the failing module using the OS/EM ISPF RELOAD facility. If necessary, contact OS/EM Technical Support for assistance with problem resolution.

FEMRCN070

ABEND Ssss/Uuuu, PSW AT ABEND: pppp pppp

Explanation: OS/EM has detected an MVS System ABEND during execution of an OS/EM optional function or a user exit.

Ssss: The MVS system code.

Usss: The MVS user reason code.

pppp pppp: The PSW.

Source: FEMRACCN

System Action: The OS/EM function being executed continues. OS/EM takes an SVC dump for the abending module, takes the abending module out of service, and deletes the abending module from CSA/ECSA. See messages FEMxxx023, FEMxxx026 and FEMxxx029.

Operator Response: Contact the System Programmer.

System Programmer Response: Use IPCS to determine the cause of the ABEND, take the corrective action required, perform a LLA,REFRESH and reload the failing module using the OS/EM ISPF RELOAD facility. If necessary, contact OS/EM Technical Support for assistance with problem resolution.

FEMSCN070

ABEND Ssss/Uuuu, PSW AT ABEND: pppp pppp

Explanation: OS/EM has detected an MVS System ABEND during execution of an OS/EM optional function or a user exit.

Ssss: The MVS system code.

Usss: The MVS user reason code.

pppp pppp: The PSW.

Source: FEMSAFCN,FEMSMFCN

System Action: The OS/EM function being executed continues. OS/EM takes an SVC dump for the abending module, takes the abending module out of service, and deletes the abending module from CSA/ECSA. See messages FEMxxx023, FEMxxx026 and FEMxxx029.

Operator Response: Contact the System Programmer.

System Programmer Response: Use IPCS to determine the cause of the ABEND, take the corrective action required, perform a LLA,REFRESH and reload the failing module using the OS/EM ISPF RELOAD facility. If necessary, contact OS/EM Technical Support for assistance with problem resolution.

FEMTCN070

ABEND Ssss/Uuuu, PSW AT ABEND: pppp pppp

Explanation: OS/EM has detected an MVS System ABEND during execution of an OS/EM optional function or a user exit.

Ssss: The MVS system code.

Usss: The MVS user reason code.

pppp pppp: The PSW.

Source: FEMTSOCN

System Action: The OS/EM function being executed continues. OS/EM takes an SVC dump for the abending module, takes the abending module out of service, and deletes the abending module from CSA/ECSA. See messages FEMxxx023, FEMxxx026 and FEMxxx029.

Operator Response: Contact the System Programmer.

System Programmer Response: Use IPCS to determine the cause of the ABEND, take the corrective action required, perform a LLA,REFRESH and reload the failing module using the OS/EM ISPF RELOAD facility. If necessary, contact OS/EM Technical Support for assistance with problem resolution.

FEMTPS070

ABEND Ssss/Uuuu, PSW AT ABEND: pppp pppp

Explanation: OS/EM has detected an MVS System ABEND during execution of an OS/EM optional function or a user exit.

Ssss: The MVS system code.

Usss: The MVS user reason code.

pppp pppp: The PSW.

Source: FEMTPSHR

System Action: The OS/EM function being executed continues. OS/EM takes an SVC dump for the abending module, takes the abending module out of service, and deletes the abending module from CSA/ECSA. See messages FEMxxx023, FEMxxx026 and FEMxxx029.

Operator Response: Contact the System Programmer.

System Programmer Response: Use IPCS to determine the cause of the ABEND, take the corrective action required, perform a LLA,REFRESH and reload the failing module using the OS/EM ISPF RELOAD facility. If necessary, contact OS/EM Technical Support for assistance with problem resolution.

FEMUJI070

ABEND Ssss/Uuuu, PSW AT ABEND: pppp pppp

Explanation: OS/EM has detected an MVS System ABEND during execution of an OS/EM optional function or a user exit.

Ssss: The MVS system code.

Usss: The MVS user reason code.

pppp pppp: The PSW.

Source: FEMUJI

System Action: The OS/EM function being executed continues. OS/EM takes an SVC dump for the abending module, takes the abending module out of service, and deletes the abending module from CSA/ECSA. See messages FEMxxx023, FEMxxx026 and FEMxxx029.

Operator Response: Contact the System Programmer.

System Programmer Response: Use IPCS to determine the cause of the ABEND, take the corrective action required, perform a LLA,REFRESH and reload the failing module using the OS/EM ISPF RELOAD facility. If necessary, contact OS/EM Technical Support for assistance with problem resolution.

FEMUSI070

ABEND Ssss/Uuuu, PSW AT ABEND: pppp pppp

Explanation: OS/EM has detected an MVS System ABEND during execution of an OS/EM optional function or a user exit.

Ssss: The MVS system code.

Usss: The MVS user reason code.

pppp pppp: The PSW.

Source: FEMUSI

System Action: The OS/EM function being executed continues. OS/EM takes an SVC dump for the abending module, takes the abending module out of service, and deletes the abending module from CSA/ECSA. See messages FEMxxx023, FEMxxx026 and FEMxxx029.

Operator Response: Contact the System Programmer.

System Programmer Response: Use IPCS to determine the cause of the ABEND, take the corrective action required, perform a LLA,REFRESH and reload the failing module using the OS/EM ISPF RELOAD facility. If necessary, contact OS/EM Technical Support for assistance with problem resolution.

FEMVCN070

ABEND Ssss/Uuuu, PSW AT ABEND: pppp pppp

Explanation: OS/EM has detected an MVS System ABEND during execution of an OS/EM optional function or a user exit.

Ssss: The MVS system code.

Usss: The MVS user reason code.

pppp pppp: The PSW.

Source: FEMSVCCN

System Action: The OS/EM function being executed continues. OS/EM takes an SVC dump for the abending module, takes the abending module out of service, and deletes the abending module from CSA/ECSA. See messages FEMxxx023, FEMxxx026 and FEMxxx029.

Operator Response: Contact the System Programmer.

System Programmer Response: Use IPCS to determine the cause of the ABEND, take the corrective action required, perform a LLA,REFRESH and reload the failing module using the OS/EM ISPF RELOAD facility. If necessary, contact OS/EM Technical Support for assistance with problem resolution.

FEMX05070

ABEND Ssss/Uuuu, PSW AT ABEND: pppp pppp

Explanation: OS/EM has detected an MVS System ABEND during execution of an OS/EM optional function or a user exit.

Ssss: The MVS system code.

Usss: The MVS user reason code.

pppp pppp: The PSW.

Source: FEMJ2X05

System Action: The OS/EM function being executed continues. OS/EM takes an SVC dump for the abending module, takes the abending module out of service, and deletes the abending module from CSA/ECSA. See messages FEMxxx023, FEMxxx026 and FEMxxx029.

Operator Response: Contact the System Programmer.

System Programmer Response: Use IPCS to determine the cause of the ABEND, take the corrective action required, perform a LLA,REFRESH and reload the failing module using the OS/EM ISPF RELOAD facility. If necessary, contact OS/EM Technical Support for assistance with problem resolution.

FEM02F070

ABEND Ssss/Uuuu, PSW AT ABEND: pppp pppp

Explanation: OS/EM has detected an MVS System ABEND during execution of an OS/EM optional function or a user exit.

Ssss: The MVS system code.

Usss: The MVS user reason code.

pppp pppp: The PSW.

Source: FEM0002F

System Action: The OS/EM function being executed continues. OS/EM takes an SVC dump for the abending module, takes the abending module out of service, and deletes the abending module from CSA/ECSA. See messages FEMxxx023, FEMxxx026 and FEMxxx029.

Operator Response: Contact the System Programmer.

System Programmer Response: Use IPCS to determine the cause of the ABEND, take the corrective action required, perform a LLA,REFRESH and reload the failing module using the OS/EM ISPF RELOAD facility. If necessary, contact OS/EM Technical Support for assistance with problem resolution.

FEM1PL070

ABEND Ssss/Uuuu, PSW AT ABEND: pppp pppp

Explanation: OS/EM has detected an MVS System ABEND during execution of an OS/EM optional function or a user exit.

Ssss: The MVS system code.

Usss: The MVS user reason code.

pppp pppp: The PSW.

Source: FEM1PL1

System Action: The OS/EM function being executed continues. OS/EM takes an SVC dump for the abending module, takes the abending module out of service, and deletes the abending module from CSA/ECSA. See messages FEMxxx023, FEMxxx026 and FEMxxx029.

Operator Response: Contact the System Programmer.

System Programmer Response: Use IPCS to determine the cause of the ABEND, take the corrective action required, perform a LLA,REFRESH and reload the failing module using the OS/EM ISPF RELOAD facility. If necessary, contact OS/EM Technical Support for assistance with problem resolution.

FEM2H5070

ABEND Ssss/Uuuu, PSW AT ABEND: pppp pppp

Explanation: OS/EM has detected an MVS System ABEND during execution of an OS/EM optional function or a user exit.

Ssss: The MVS system code.

Usss: The MVS user reason code.

pppp pppp: The PSW.

Source: FEMJ2H5x

System Action: The OS/EM function being executed continues. OS/EM takes an SVC dump for the abending module, takes the abending module out of service, and deletes the abending module from CSA/ECSA. See messages FEMxxx023, FEMxxx026 and FEMxxx029.

Operator Response: Contact the System Programmer.

System Programmer Response: Use IPCS to determine the cause of the ABEND, take the corrective action required, perform a LLA,REFRESH and reload the failing module using the OS/EM ISPF RELOAD facility. If necessary, contact OS/EM Technical Support for assistance with problem resolution.

FEM2P4070

ABEND Ssss/Uuuu, PSW AT ABEND: pppp pppp

Explanation: OS/EM has detected an MVS System ABEND during execution of an OS/EM optional function or a user exit.

Ssss: The MVS system code.

Usss: The MVS user reason code.

pppp pppp: The PSW.

Source: FEMJ2P4x

System Action: The OS/EM function being executed continues. OS/EM takes an SVC dump for the abending module, takes the abending module out of service, and deletes the abending module from CSA/ECSA. See messages FEMxxx023, FEMxxx026 and FEMxxx029.

Operator Response: Contact the System Programmer.

System Programmer Response: Use IPCS to determine the cause of the ABEND, take the corrective action required, perform a LLA,REFRESH and reload the failing module using the OS/EM ISPF RELOAD facility. If necessary, contact OS/EM Technical Support for assistance with problem resolution.

FEMACN071

DATA AT PSW AREA (aaaaaaaa): dddddddd

Explanation: OS/EM has detected an MVS System ABEND during execution of an OS/EM optional function or a user exit.

aaaaaaaa: The address pointed to by the PSW (if accessible).

dddddddd: The contents of storage.

Source: FEMALCCN

System Action: The OS/EM function being executed continues. OS/EM takes an SVC dump for the abending module, takes the abending module out of service, and deletes the abending module from CSA/ECSA. See messages FEMxxx023, FEMxxx026 and FEMxxx029.

Operator Response: Contact the System Programmer.

System Programmer Response: Use IPCS to determine the cause of the ABEND, take the corrective action required, perform a LLA,REFRESH and reload the failing module using the OS/EM ISPF RELOAD facility. If necessary, contact OS/EM Technical Support for assistance with problem resolution.

FEMALC071

DATA AT PSW AREA (aaaaaaaa): dddddddd

Explanation: OS/EM has detected an MVS System ABEND during execution of an OS/EM optional function or a user exit.

aaaaaaaa: The address pointed to by the PSW (if accessible).

dddddddd: The contents of storage.

Source: FEMALLOC

System Action: The OS/EM function being executed continues. OS/EM takes an SVC dump for the abending module, takes the abending module out of service, and deletes the abending module from CSA/ECSA. See messages FEMxxx023, FEMxxx026 and FEMxxx029.

Operator Response: Contact the System Programmer.

System Programmer Response: Use IPCS to determine the cause of the ABEND, take the corrective action required, perform a LLA,REFRESH and reload the failing module using the OS/EM ISPF RELOAD facility. If necessary, contact OS/EM Technical Support for assistance with problem resolution.

FEMASY071

DATA AT PSW AREA (aaaaaaaa): dddddddd

Explanation: OS/EM has detected an MVS System ABEND during execution of an OS/EM optional function or a user exit.

aaaaaaaa: The address pointed to by the PSW (if accessible).

dddddddd: The contents of storage.

Source: FEMASYNC

System Action: The OS/EM function being executed continues. OS/EM takes an SVC dump for the abending module, takes the abending module out of service, and deletes the abending module from CSA/ECSA. See messages FEMxxx023, FEMxxx026 and FEMxxx029.

Operator Response: Contact the System Programmer.

System Programmer Response: Use IPCS to determine the cause of the ABEND, take the corrective action required, perform a LLA,REFRESH and reload the failing module using the OS/EM ISPF RELOAD facility. If necessary, contact OS/EM Technical Support for assistance with problem resolution.

FEMCMD071

DATA AT PSW AREA (aaaaaaaa): dddddddd

Explanation: OS/EM has detected an MVS System ABEND during execution of an OS/EM optional function or a user exit.

aaaaaaaa: The address pointed to by the PSW (if accessible).

dddddddd: The contents of storage.

Source: FEMCMD

System Action: The OS/EM function being executed continues. OS/EM takes an SVC dump for the abending module, takes the abending module out of service, and deletes the abending module from CSA/ECSA. See messages FEMxxx023, FEMxxx026 and FEMxxx029.

Operator Response: Contact the System Programmer.

System Programmer Response: Use IPCS to determine the cause of the ABEND, take the corrective action required, perform a LLA,REFRESH and reload the failing module using the OS/EM ISPF RELOAD facility. If necessary, contact OS/EM Technical Support for assistance with problem resolution.

FEMCOM071

DATA AT PSW AREA (aaaaaaaa): dddddddd

Explanation: OS/EM has detected an MVS System ABEND during execution of an OS/EM optional function or a user exit.

aaaaaaaa: The address pointed to by the PSW (if accessible).

dddddddd: The contents of storage.

Source: FEMCOMM

System Action: The OS/EM function being executed continues. OS/EM takes an SVC dump for the abending module, takes the abending module out of service, and deletes the abending module from CSA/ECSA. See messages FEMxxx023, FEMxxx026 and FEMxxx029.

Operator Response: Contact the System Programmer.

System Programmer Response: Use IPCS to determine the cause of the ABEND, take the corrective action required, perform a LLA,REFRESH and reload the failing module using the OS/EM ISPF RELOAD facility. If necessary, contact OS/EM Technical Support for assistance with problem resolution.

FEMDCN071

DATA AT PSW AREA (aaaaaaaa): dddddddd

Explanation: OS/EM has detected an MVS System ABEND during execution of an OS/EM optional function or a user exit.

aaaaaaaa: The address pointed to by the PSW (if accessible).

dddddddd: The contents of storage.

Source: FEMDADCN

System Action: The OS/EM function being executed continues. OS/EM takes an SVC dump for the abending module, takes the abending module out of service, and deletes the abending module from CSA/ECSA. See messages FEMxxx023, FEMxxx026 and FEMxxx029.

Operator Response: Contact the System Programmer.

System Programmer Response: Use IPCS to determine the cause of the ABEND, take the corrective action required, perform a LLA,REFRESH and reload the failing module using the OS/EM ISPF RELOAD facility. If necessary, contact OS/EM Technical Support for assistance with problem resolution.

FEMDC1071

DATA AT PSW AREA (aaaaaaaa): dddddddd

Explanation: OS/EM has detected an MVS System ABEND during execution of an OS/EM optional function or a user exit.

aaaaaaaa: The address pointed to by the PSW (if accessible).

ddddddd: The contents of storage.

Source: FEMDCB1

System Action: The OS/EM function being executed continues. OS/EM takes an SVC dump for the abending module, takes the abending module out of service, and deletes the abending module from CSA/ECSA. See messages FEMxxx023, FEMxxx026 and FEMxxx029.

Operator Response: Contact the System Programmer.

System Programmer Response: Use IPCS to determine the cause of the ABEND, take the corrective action required, perform a LLA,REFRESH and reload the failing module using the OS/EM ISPF RELOAD facility. If necessary, contact OS/EM Technical Support for assistance with problem resolution.

FEMEXR071

DATA AT PSW AREA (aaaaaaa): ddddddd

Explanation: OS/EM has detected an MVS System ABEND during execution of an OS/EM optional function or a user exit.

aaaaaaa: The address pointed to by the PSW (if accessible).

ddddddd: The contents of storage.

Source: FEMEXRTN

System Action: The OS/EM function being executed continues. OS/EM takes an SVC dump for the abending module, takes the abending module out of service, and deletes the abending module from CSA/ECSA. See messages FEMxxx023, FEMxxx026 and FEMxxx029.

Operator Response: Contact the System Programmer.

System Programmer Response: Use IPCS to determine the cause of the ABEND, take the corrective action required, perform a LLA,REFRESH and reload the failing module using the OS/EM ISPF RELOAD facility. If necessary, contact OS/EM Technical Support for assistance with problem resolution.

FEMFRA071

DATA AT PSW AREA (aaaaaaa): ddddddd

Explanation: OS/EM has detected an MVS System ABEND during execution of an OS/EM optional function or a user exit.

aaaaaaa: The address pointed to by the PSW (if accessible).

ddddddd: The contents of storage.

Source: FEMFRACN

System Action: The OS/EM function being executed continues. OS/EM takes an SVC dump for the abending module, takes the abending module out of service, and deletes the abending module from CSA/ECSA. See messages FEMxxx023, FEMxxx026 and FEMxxx029.

Operator Response: Contact the System Programmer.

System Programmer Response: Use IPCS to determine the cause of the ABEND, take the corrective action required, perform a LLA,REFRESH and reload the failing module using the OS/EM ISPF RELOAD facility. If necessary, contact OS/EM Technical Support for assistance with problem resolution.

FEMFTN071

DATA AT PSW AREA (aaaaaaaa): dddddddd

Explanation: OS/EM has detected an MVS System ABEND during execution of an OS/EM optional function or a user exit.

aaaaaaaa: The address pointed to by the PSW (if accessible).

ddddddd: The contents of storage.

Source: FEMFRRTN

System Action: The OS/EM function being executed continues. OS/EM takes an SVC dump for the abending module, takes the abending module out of service, and deletes the abending module from CSA/ECSA. See messages FEMxxx023, FEMxxx026 and FEMxxx029.

Operator Response: Contact the System Programmer.

System Programmer Response: Use IPCS to determine the cause of the ABEND, take the corrective action required, perform a LLA,REFRESH and reload the failing module using the OS/EM ISPF RELOAD facility. If necessary, contact OS/EM Technical Support for assistance with problem resolution.

FEMHCN071

DATA AT PSW AREA (aaaaaaaa): dddddddd

Explanation: OS/EM has detected an MVS System ABEND during execution of an OS/EM optional function or a user exit.

aaaaaaaa: The address pointed to by the PSW (if accessible).

ddddddd: The contents of storage.

Source: FEMHSMCN

System Action: The OS/EM function being executed continues. OS/EM takes an SVC dump for the abending module, takes the abending module out of service, and deletes the abending module from CSA/ECSA. See messages FEMxxx023, FEMxxx026 and FEMxxx029.

Operator Response: Contact the System Programmer.

System Programmer Response: Use IPCS to determine the cause of the ABEND, take the corrective action required, perform a LLA,REFRESH and reload the failing module using the OS/EM ISPF RELOAD facility. If necessary, contact OS/EM Technical Support for assistance with problem resolution.

FEMHSP071

DATA AT PSW AREA (aaaaaaaa): dddddddd

Explanation: OS/EM has detected an MVS System ABEND during execution of an OS/EM optional function or a user exit.

aaaaaaaa: The address pointed to by the PSW (if accessible).

ddddddd: The contents of storage.

Source: FEMHJ20

System Action: The OS/EM function being executed continues. OS/EM takes an SVC dump for the abending module, takes the abending module out of service, and deletes the abending module from CSA/ECSA. See messages FEMxxx023, FEMxxx026 and FEMxxx029.

Operator Response: Contact the System Programmer.

System Programmer Response: Use IPCS to determine the cause of the ABEND, take the corrective action required, perform a LLA,REFRESH and reload the failing module using the OS/EM ISPF RELOAD facility. If necessary, contact OS/EM Technical Support for assistance with problem resolution.

FEMIAT071

DATA AT PSW AREA (aaaaaaaa): dddddddd

Explanation: OS/EM has detected an MVS System ABEND during execution of an OS/EM optional function or a user exit.

aaaaaaaa: The address pointed to by the PSW (if accessible).

dddddddd: The contents of storage.

Source: FEMINTK

System Action: The OS/EM function being executed continues. OS/EM takes an SVC dump for the abending module, takes the abending module out of service, and deletes the abending module from CSA/ECSA. See messages FEMxxx023, FEMxxx026 and FEMxxx029.

Operator Response: Contact the System Programmer.

System Programmer Response: Use IPCS to determine the cause of the ABEND, take the corrective action required, perform a LLA,REFRESH and reload the failing module using the OS/EM ISPF RELOAD facility. If necessary, contact OS/EM Technical Support for assistance with problem resolution.

FEMICN071

DATA AT PSW AREA (aaaaaaaa): dddddddd

Explanation: OS/EM has detected an MVS System ABEND during execution of an OS/EM optional function or a user exit.

aaaaaaaa: The address pointed to by the PSW (if accessible).

dddddddd: The contents of storage.

Source: FEMISPCN

System Action: The OS/EM function being executed continues. OS/EM takes an SVC dump for the abending module, takes the abending module out of service, and deletes the abending module from CSA/ECSA. See messages FEMxxx023, FEMxxx026 and FEMxxx029.

Operator Response: Contact the System Programmer.

System Programmer Response: Use IPCS to determine the cause of the ABEND, take the corrective action required, perform a LLA,REFRESH and reload the failing module using the OS/EM ISPF RELOAD facility. If necessary, contact OS/EM Technical Support for assistance with problem resolution.

FEMIPL071

DATA AT PSW AREA (aaaaaaaa): dddddddd

Explanation: OS/EM has detected an MVS System ABEND during execution of an OS/EM optional function or a user exit.

aaaaaaaa: The address pointed to by the PSW (if accessible).

ddddddd: The contents of storage.

Source: FEM IPL

System Action: The OS/EM function being executed continues. OS/EM takes an SVC dump for the abending module, takes the abending module out of service, and deletes the abending module from CSA/ECSA. See messages FEMxxx023, FEMxxx026 and FEMxxx029.

Operator Response: Contact the System Programmer.

System Programmer Response: Use IPCS to determine the cause of the ABEND, take the corrective action required, perform a LLA,REFRESH and reload the failing module using the OS/EM ISPF RELOAD facility. If necessary, contact OS/EM Technical Support for assistance with problem resolution.

FEMJS2071

DATA AT PSW AREA (aaaaaaaa): dddddddd

Explanation: OS/EM has detected an MVS System ABEND during execution of an OS/EM optional function or a user exit.

aaaaaaaa: The address pointed to by the PSW (if accessible).

ddddddd: The contents of storage.

Source: FEMJES2B,FEMJES2G

System Action: The OS/EM function being executed continues. OS/EM takes an SVC dump for the abending module, takes the abending module out of service, and deletes the abending module from CSA/ECSA. See messages FEMxxx023, FEMxxx026 and FEMxxx029.

Operator Response: Contact the System Programmer.

System Programmer Response: Use IPCS to determine the cause of the ABEND, take the corrective action required, perform a LLA,REFRESH and reload the failing module using the OS/EM ISPF RELOAD facility. If necessary, contact OS/EM Technical Support for assistance with problem resolution.

FEMJ2M071

DATA AT PSW AREA (aaaaaaaa): dddddddd

Explanation: OS/EM has detected an MVS System ABEND during execution of an OS/EM optional function or a user exit.

aaaaaaaa: The address pointed to by the PSW (if accessible).

ddddddd: The contents of storage.

Source: FEMJ2MCx

System Action: The OS/EM function being executed continues. OS/EM takes an SVC dump for the abending module, takes the abending module out of service, and deletes the abending module from CSA/ECSA. See messages FEMxxx023, FEMxxx026 and FEMxxx029.

Operator Response: Contact the System Programmer.

System Programmer Response: Use IPCS to determine the cause of the ABEND, take the corrective action required, perform a LLA,REFRESH and reload the failing module using the OS/EM ISPF RELOAD facility. If necessary, contact OS/EM Technical Support for assistance with problem resolution.

FEMJ2R071

DATA AT PSW AREA (aaaaaaaa): dddddddd

Explanation: OS/EM has detected an MVS System ABEND during execution of an OS/EM optional function or a user exit.

aaaaaaaa: The address pointed to by the PSW (if accessible).

ddddddd: The contents of storage.

Source: FEMJ2ERx

System Action: The OS/EM function being executed continues. OS/EM takes an SVC dump for the abending module, takes the abending module out of service, and deletes the abending module from CSA/ECSA. See messages FEMxxx023, FEMxxx026 and FEMxxx029.

Operator Response: Contact the System Programmer.

System Programmer Response: Use IPCS to determine the cause of the ABEND, take the corrective action required, perform a LLA,REFRESH and reload the failing module using the OS/EM ISPF RELOAD facility. If necessary, contact OS/EM Technical Support for assistance with problem resolution.

FEMJ2S071

DATA AT PSW AREA (aaaaaaaa): dddddddd

Explanation: OS/EM has detected an MVS System ABEND during execution of an OS/EM optional function or a user exit.

aaaaaaaa: The address pointed to by the PSW (if accessible).

ddddddd: The contents of storage.

Source: FEMJ2SCx

System Action: The OS/EM function being executed continues. OS/EM takes an SVC dump for the abending module, takes the abending module out of service, and deletes the abending module from CSA/ECSA. See messages FEMxxx023, FEMxxx026 and FEMxxx029.

Operator Response: Contact the System Programmer.

System Programmer Response: Use IPCS to determine the cause of the ABEND, take the corrective action required, perform a LLA,REFRESH and reload the failing module using the OS/EM ISPF RELOAD facility. If necessary, contact OS/EM Technical Support for assistance with problem resolution.

FEMJ3E071

DATA AT PSW AREA (aaaaaaaa): dddddddd

Explanation: OS/EM has detected an MVS System ABEND during execution of an OS/EM optional function or a user exit.

aaaaaaaa: The address pointed to by the PSW (if accessible).

ddddddd: The contents of storage.

Source: FEMJ3ECN

System Action: The OS/EM function being executed continues. OS/EM takes an SVC dump for the abending module, takes the abending module out of service, and deletes the abending module from CSA/ECSA. See messages FEMxxx023, FEMxxx026 and FEMxxx029.

Operator Response: Contact the System Programmer.

System Programmer Response: Use IPCS to determine the cause of the ABEND, take the corrective action required, perform a LLA,REFRESH and reload the failing module using the OS/EM ISPF RELOAD facility. If necessary, contact OS/EM Technical Support for assistance with problem resolution.

FEMJ3S071

DATA AT PSW AREA (aaaaaaaa): dddddddd

Explanation: OS/EM has detected an MVS System ABEND during execution of an OS/EM optional function or a user exit.

aaaaaaaa: The address pointed to by the PSW (if accessible).

dddddddd: The contents of storage.

Source: FEMJ3SVC

System Action: The OS/EM function being executed continues. OS/EM takes an SVC dump for the abending module, takes the abending module out of service, and deletes the abending module from CSA/ECSA. See messages FEMxxx023, FEMxxx026 and FEMxxx029.

Operator Response: Contact the System Programmer.

System Programmer Response: Use IPCS to determine the cause of the ABEND, take the corrective action required, perform a LLA,REFRESH and reload the failing module using the OS/EM ISPF RELOAD facility. If necessary, contact OS/EM Technical Support for assistance with problem resolution.

FEMLOK071

DATA AT PSW AREA (aaaaaaaa): dddddddd

Explanation: OS/EM has detected an MVS System ABEND during execution of an OS/EM optional function or a user exit.

aaaaaaaa: The address pointed to by the PSW (if accessible).

dddddddd: The contents of storage.

Source: FEMLOCK

System Action: The OS/EM function being executed continues. OS/EM takes an SVC dump for the abending module, takes the abending module out of service, and deletes the abending module from CSA/ECSA. See messages FEMxxx023, FEMxxx026 and FEMxxx029.

Operator Response: Contact the System Programmer.

System Programmer Response: Use IPCS to determine the cause of the ABEND, take the corrective action required, perform a LLA,REFRESH and reload the failing module using the OS/EM ISPF RELOAD facility. If necessary, contact OS/EM Technical Support for assistance with problem resolution.

FEMRCN071

DATA AT PSW AREA (aaaaaaaa): dddddddd

Explanation: OS/EM has detected an MVS System ABEND during execution of an OS/EM optional function or a user exit.

aaaaaaaa: The address pointed to by the PSW (if accessible).

ddddddd: The contents of storage.

Source: FEMRACCN

System Action: The OS/EM function being executed continues. OS/EM takes an SVC dump for the abending module, takes the abending module out of service, and deletes the abending module from CSA/ECSA. See messages FEMxxx023, FEMxxx026 and FEMxxx029.

Operator Response: Contact the System Programmer.

System Programmer Response: Use IPCS to determine the cause of the ABEND, take the corrective action required, perform a LLA,REFRESH and reload the failing module using the OS/EM ISPF RELOAD facility. If necessary, contact OS/EM Technical Support for assistance with problem resolution.

FEMSCN071

DATA AT PSW AREA (aaaaaaaa): dddddddd

Explanation: OS/EM has detected an MVS System ABEND during execution of an OS/EM optional function or a user exit.

aaaaaaaa: The address pointed to by the PSW (if accessible).

ddddddd: The contents of storage.

Source: FEMSAFCN,FEMSMFCN

System Action: The OS/EM function being executed continues. OS/EM takes an SVC dump for the abending module, takes the abending module out of service, and deletes the abending module from CSA/ECSA. See messages FEMxxx023, FEMxxx026 and FEMxxx029.

Operator Response: Contact the System Programmer.

System Programmer Response: Use IPCS to determine the cause of the ABEND, take the corrective action required, perform a LLA,REFRESH and reload the failing module using the OS/EM ISPF RELOAD facility. If necessary, contact OS/EM Technical Support for assistance with problem resolution.

FEMTCN071

DATA AT PSW AREA (aaaaaaaa): dddddddd

Explanation: OS/EM has detected an MVS System ABEND during execution of an OS/EM optional function or a user exit.

aaaaaaaa: The address pointed to by the PSW (if accessible).

ddddddd: The contents of storage.

Source: FEMTSOCN

System Action: The OS/EM function being executed continues. OS/EM takes an SVC dump for the abending module, takes the abending module out of service, and deletes the abending module from CSA/ECSA. See messages FEMxxx023, FEMxxx026 and FEMxxx029.

Operator Response: Contact the System Programmer.

System Programmer Response: Use IPCS to determine the cause of the ABEND, take the corrective action required, perform a LLA,REFRESH and reload the failing module using the OS/EM ISPF RELOAD facility. If necessary, contact OS/EM Technical Support for assistance with problem resolution.

FEMTPS071

DATA AT PSW AREA (aaaaaaaa): dddddddd

Explanation: OS/EM has detected an MVS System ABEND during execution of an OS/EM optional function or a user exit.

aaaaaaaa: The address pointed to by the PSW (if accessible).

dddddddd: The contents of storage.

Source: FEMTPSHR

System Action: The OS/EM function being executed continues. OS/EM takes an SVC dump for the abending module, takes the abending module out of service, and deletes the abending module from CSA/ECSA. See messages FEMxxx023, FEMxxx026 and FEMxxx029.

Operator Response: Contact the System Programmer.

System Programmer Response: Use IPCS to determine the cause of the ABEND, take the corrective action required, perform a LLA,REFRESH and reload the failing module using the OS/EM ISPF RELOAD facility. If necessary, contact OS/EM Technical Support for assistance with problem resolution.

FEMUJI071

DATA AT PSW AREA (aaaaaaaa): dddddddd

Explanation: OS/EM has detected an MVS System ABEND during execution of an OS/EM optional function or a user exit.

aaaaaaaa: The address pointed to by the PSW (if accessible).

dddddddd: The contents of storage.

Source: FEMUJI

System Action: The OS/EM function being executed continues. OS/EM takes an SVC dump for the abending module, takes the abending module out of service, and deletes the abending module from CSA/ECSA. See messages FEMxxx023, FEMxxx026 and FEMxxx029.

Operator Response: Contact the System Programmer.

System Programmer Response: Use IPCS to determine the cause of the ABEND, take the corrective action required, perform a LLA,REFRESH and reload the failing module using the OS/EM ISPF RELOAD facility. If necessary, contact OS/EM Technical Support for assistance with problem resolution.

FEMUSI071

DATA AT PSW AREA (aaaaaaaa): dddddddd

Explanation: OS/EM has detected an MVS System ABEND during execution of an OS/EM optional function or a user exit.

aaaaaaaa: The address pointed to by the PSW (if accessible).

dddddddd: The contents of storage.

Source: FEMUSI

System Action: The OS/EM function being executed continues. OS/EM takes an SVC dump for the abending module, takes the abending module out of service, and deletes the abending module from CSA/ECSA. See messages FEMxxx023, FEMxxx026 and FEMxxx029.

Operator Response: Contact the System Programmer.

System Programmer Response: Use IPCS to determine the cause of the ABEND, take the corrective action required, perform a LLA,REFRESH and reload the failing module using the OS/EM ISPF RELOAD facility. If necessary, contact OS/EM Technical Support for assistance with problem resolution.

FEMVCN071

DATA AT PSW AREA (aaaaaaaa): dddddddd

Explanation: OS/EM has detected an MVS System ABEND during execution of an OS/EM optional function or a user exit.

aaaaaaaa: The address pointed to by the PSW (if accessible).

dddddddd: The contents of storage.

Source: FEMSVCCN

System Action: The OS/EM function being executed continues. OS/EM takes an SVC dump for the abending module, takes the abending module out of service, and deletes the abending module from CSA/ECSA. See messages FEMxxx023, FEMxxx026 and FEMxxx029.

Operator Response: Contact the System Programmer.

System Programmer Response: Use IPCS to determine the cause of the ABEND, take the corrective action required, perform a LLA,REFRESH and reload the failing module using the OS/EM ISPF RELOAD facility. If necessary, contact OS/EM Technical Support for assistance with problem resolution.

FEMX05071

DATA AT PSW AREA (aaaaaaaa): dddddddd

Explanation: OS/EM has detected an MVS System ABEND during execution of an OS/EM optional function or a user exit.

aaaaaaaa: The address pointed to by the PSW (if accessible).

dddddddd: The contents of storage.

Source: FEMJ2X05

System Action: The OS/EM function being executed continues. OS/EM takes an SVC dump for the abending module, takes the abending module out of service, and deletes the abending module from CSA/ECSA. See messages FEMxxx023, FEMxxx026 and FEMxxx029.

Operator Response: Contact the System Programmer.

System Programmer Response: Use IPCS to determine the cause of the ABEND, take the corrective action required, perform a LLA,REFRESH and reload the failing module using the OS/EM ISPF RELOAD facility. If necessary, contact OS/EM Technical Support for assistance with problem resolution.

FEM02F071

DATA AT PSW AREA (aaaaaaaa): dddddddd

Explanation: OS/EM has detected an MVS System ABEND during execution of an OS/EM optional function or a user exit.

aaaaaaaa: The address pointed to by the PSW (if accessible).

ddddddd: The contents of storage.

Source: FEM0002F

System Action: The OS/EM function being executed continues. OS/EM takes an SVC dump for the abending module, takes the abending module out of service, and deletes the abending module from CSA/ECSA. See messages FEMxxx023, FEMxxx026 and FEMxxx029.

Operator Response: Contact the System Programmer.

System Programmer Response: Use IPCS to determine the cause of the ABEND, take the corrective action required, perform a LLA,REFRESH and reload the failing module using the OS/EM ISPF RELOAD facility. If necessary, contact OS/EM Technical Support for assistance with problem resolution.

FEM1PL071

DATA AT PSW AREA (aaaaaaaa): dddddddd

Explanation: OS/EM has detected an MVS System ABEND during execution of an OS/EM optional function or a user exit.

aaaaaaaa: The address pointed to by the PSW (if accessible).

ddddddd: The contents of storage.

Source: FEM1PL1

System Action: The OS/EM function being executed continues. OS/EM takes an SVC dump for the abending module, takes the abending module out of service, and deletes the abending module from CSA/ECSA. See messages FEMxxx023, FEMxxx026 and FEMxxx029.

Operator Response: Contact the System Programmer.

System Programmer Response: Use IPCS to determine the cause of the ABEND, take the corrective action required, perform a LLA,REFRESH and reload the failing module using the OS/EM ISPF RELOAD facility. If necessary, contact OS/EM Technical Support for assistance with problem resolution.

FEM2H5071

DATA AT PSW AREA (aaaaaaaa): dddddddd

Explanation: OS/EM has detected an MVS System ABEND during execution of an OS/EM optional function or a user exit.

aaaaaaaa: The address pointed to by the PSW (if accessible).

ddddddd: The contents of storage.

Source: FEMJ2H5x

System Action: The OS/EM function being executed continues. OS/EM takes an SVC dump for the abending module, takes the abending module out of service, and deletes the abending module from CSA/ECSA. See messages FEMxxx023, FEMxxx026 and FEMxxx029.

Operator Response: Contact the System Programmer.

System Programmer Response: Use IPCS to determine the cause of the ABEND, take the corrective action required, perform a LLA,REFRESH and reload the failing module using the OS/EM ISPF RELOAD facility. If necessary, contact OS/EM Technical Support for assistance with problem resolution.

FEM2P4071

DATA AT PSW AREA (aaaaaaaa): dddddddd

Explanation: OS/EM has detected an MVS System ABEND during execution of an OS/EM optional function or a user exit.

aaaaaaaa: The address pointed to by the PSW (if accessible).

ddddddd: The contents of storage.

Source: FEMJ2P4x

System Action: The OS/EM function being executed continues. OS/EM takes an SVC dump for the abending module, takes the abending module out of service, and deletes the abending module from CSA/ECSA. See messages FEMxxx023, FEMxxx026 and FEMxxx029.

Operator Response: Contact the System Programmer.

System Programmer Response: Use IPCS to determine the cause of the ABEND, take the corrective action required, perform a LLA,REFRESH and reload the failing module using the OS/EM ISPF RELOAD facility. If necessary, contact OS/EM Technical Support for assistance with problem resolution.

FEMACN072

DATA AT PSW AREA IS INACCESSIBLE

Explanation: OS/EM has detected an MVS System ABEND during execution of an OS/EM optional function or a user exit. However, the storage pointed to by the PSW cannot be displayed because it cannot be accessed.

Source: FEMALCCN

System Action: The OS/EM function being executed continues. OS/EM takes an SVC dump for the abending module, takes the abending module out of service, and deletes the abending module from CSA/ECSA. See messages FEMxxx023, FEMxxx026 and FEMxxx029.

Operator Response: Contact the System Programmer.

System Programmer Response: Use IPCS to determine the cause of the ABEND, take the corrective action required, perform a LLA,REFRESH and reload the failing module using the OS/EM ISPF RELOAD facility. If necessary, contact OS/EM Technical Support for assistance with problem resolution.

FEMALC072

DATA AT PSW AREA IS INACCESSIBLE

Explanation: OS/EM has detected an MVS System ABEND during execution of an OS/EM optional function or a user exit. However, the storage pointed to by the PSW cannot be displayed because it cannot be accessed.

Source: FEMALLOC

System Action: The OS/EM function being executed continues. OS/EM takes an SVC dump for the abending module, takes the abending module out of service, and deletes the abending module from CSA/ECSA. See messages FEMxxx023, FEMxxx026 and FEMxxx029.

Operator Response: Contact the System Programmer.

System Programmer Response: Use IPCS to determine the cause of the ABEND, take the corrective action required, perform a LLA,REFRESH and reload the failing module using the OS/EM

ISPF RELOAD facility. If necessary, contact OS/EM Technical Support for assistance with problem resolution.

FEMASY072

DATA AT PSW AREA IS INACCESSIBLE

Explanation: OS/EM has detected an MVS System ABEND during execution of an OS/EM optional function or a user exit. However, the storage pointed to by the PSW cannot be displayed because it cannot be accessed.

Source: FEMASYNC

System Action: The OS/EM function being executed continues. OS/EM takes an SVC dump for the abending module, takes the abending module out of service, and deletes the abending module from CSA/ECSA. See messages FEMxxx023, FEMxxx026 and FEMxxx029.

Operator Response: Contact the System Programmer.

System Programmer Response: Use IPCS to determine the cause of the ABEND, take the corrective action required, perform a LLA,REFRESH and reload the failing module using the OS/EM ISPF RELOAD facility. If necessary, contact OS/EM Technical Support for assistance with problem resolution.

FEMCMD072

DATA AT PSW AREA IS INACCESSIBLE

Explanation: OS/EM has detected an MVS System ABEND during execution of an OS/EM optional function or a user exit. However, the storage pointed to by the PSW cannot be displayed because it cannot be accessed.

Source: FEMCMD

System Action: The OS/EM function being executed continues. OS/EM takes an SVC dump for the abending module, takes the abending module out of service, and deletes the abending module from CSA/ECSA. See messages FEMxxx023, FEMxxx026 and FEMxxx029.

Operator Response: Contact the System Programmer.

System Programmer Response: Use IPCS to determine the cause of the ABEND, take the corrective action required, perform a LLA,REFRESH and reload the failing module using the OS/EM ISPF RELOAD facility. If necessary, contact OS/EM Technical Support for assistance with problem resolution.

FEMCOM072

DATA AT PSW AREA IS INACCESSIBLE

Explanation: OS/EM has detected an MVS System ABEND during execution of an OS/EM optional function or a user exit. However, the storage pointed to by the PSW cannot be displayed because it cannot be accessed.

Source: FEMCOMM

System Action: The OS/EM function being executed continues. OS/EM takes an SVC dump for the abending module, takes the abending module out of service, and deletes the abending module from CSA/ECSA. See messages FEMxxx023, FEMxxx026 and FEMxxx029.

Operator Response: Contact the System Programmer.

System Programmer Response: Use IPCS to determine the cause of the ABEND, take the corrective action required, perform a LLA,REFRESH and reload the failing module using the OS/EM ISPF RELOAD facility. If necessary, contact OS/EM Technical Support for assistance with problem resolution.

FEMDCN072

DATA AT PSW AREA IS INACCESSIBLE

Explanation: OS/EM has detected an MVS System ABEND during execution of an OS/EM optional function or a user exit. However, the storage pointed to by the PSW cannot be displayed because it cannot be accessed.

Source: FEMDADCN

System Action: The OS/EM function being executed continues. OS/EM takes an SVC dump for the abending module, takes the abending module out of service, and deletes the abending module from CSA/ECSA. See messages FEMxxx023, FEMxxx026 and FEMxxx029.

Operator Response: Contact the System Programmer.

System Programmer Response: Use IPCS to determine the cause of the ABEND, take the corrective action required, perform a LLA,REFRESH and reload the failing module using the OS/EM ISPF RELOAD facility. If necessary, contact OS/EM Technical Support for assistance with problem resolution.

FEMDC1072

DATA AT PSW AREA IS INACCESSIBLE

Explanation: OS/EM has detected an MVS System ABEND during execution of an OS/EM optional function or a user exit. However, the storage pointed to by the PSW cannot be displayed because it cannot be accessed.

Source: FEMDCB1

System Action: The OS/EM function being executed continues. OS/EM takes an SVC dump for the abending module, takes the abending module out of service, and deletes the abending module from CSA/ECSA. See messages FEMxxx023, FEMxxx026 and FEMxxx029.

Operator Response: Contact the System Programmer.

System Programmer Response: Use IPCS to determine the cause of the ABEND, take the corrective action required, perform a LLA,REFRESH and reload the failing module using the OS/EM ISPF RELOAD facility. If necessary, contact OS/EM Technical Support for assistance with problem resolution.

FEMEXR072

DATA AT PSW AREA IS INACCESSIBLE

Explanation: OS/EM has detected an MVS System ABEND during execution of an OS/EM optional function or a user exit. However, the storage pointed to by the PSW cannot be displayed because it cannot be accessed.

Source: FEMEXRTN

System Action: The OS/EM function being executed continues. OS/EM takes an SVC dump for the abending module, takes the abending module out of service, and deletes the abending module from CSA/ECSA. See messages FEMxxx023, FEMxxx026 and FEMxxx029.

Operator Response: Contact the System Programmer.

System Programmer Response: Use IPCS to determine the cause of the ABEND, take the corrective action required, perform a LLA,REFRESH and reload the failing module using the OS/EM ISPF RELOAD facility. If necessary, contact OS/EM Technical Support for assistance with problem resolution.

FEMFTN072

DATA AT PSW AREA IS INACCESSIBLE

Explanation: OS/EM has detected an MVS System ABEND during execution of an OS/EM optional function or a user exit. However, the storage pointed to by the PSW cannot be displayed because it cannot be accessed.

Source: FEMFRRTN

System Action: The OS/EM function being executed continues. OS/EM takes an SVC dump for the abending module, takes the abending module out of service, and deletes the abending module from CSA/ECSA. See messages FEMxxx023, FEMxxx026 and FEMxxx029.

Operator Response: Contact the System Programmer.

System Programmer Response: Use IPCS to determine the cause of the ABEND, take the corrective action required, perform a LLA,REFRESH and reload the failing module using the OS/EM ISPF RELOAD facility. If necessary, contact OS/EM Technical Support for assistance with problem resolution.

FEMHCN072

DATA AT PSW AREA IS INACCESSIBLE

Explanation: OS/EM has detected an MVS System ABEND during execution of an OS/EM optional function or a user exit. However, the storage pointed to by the PSW cannot be displayed because it cannot be accessed.

Source: FEMHSMCN

System Action: The OS/EM function being executed continues. OS/EM takes an SVC dump for the abending module, takes the abending module out of service, and deletes the abending module from CSA/ECSA. See messages FEMxxx023, FEMxxx026 and FEMxxx029.

Operator Response: Contact the System Programmer.

System Programmer Response: Use IPCS to determine the cause of the ABEND, take the corrective action required, perform a LLA,REFRESH and reload the failing module using the OS/EM ISPF RELOAD facility. If necessary, contact OS/EM Technical Support for assistance with problem resolution.

FEMHSP072

DATA AT PSW AREA IS INACCESSIBLE

Explanation: OS/EM has detected an MVS System ABEND during execution of an OS/EM optional function or a user exit. However, the storage pointed to by the PSW cannot be displayed because it cannot be accessed.

Source: FEMHJ20

System Action: The OS/EM function being executed continues. OS/EM takes an SVC dump for the abending module, takes the abending module out of service, and deletes the abending module from CSA/ECSA. See messages FEMxxx023, FEMxxx026 and FEMxxx029.

Operator Response: Contact the System Programmer.

System Programmer Response: Use IPCS to determine the cause of the ABEND, take the corrective action required, perform a LLA,REFRESH and reload the failing module using the OS/EM ISPF RELOAD facility. If necessary, contact OS/EM Technical Support for assistance with problem resolution.

FEMIAT072

DATA AT PSW AREA IS INACCESSIBLE

Explanation: OS/EM has detected an MVS System ABEND during execution of an OS/EM optional function or a user exit. However, the storage pointed to by the PSW cannot be displayed because it cannot be accessed.

Source: FEMINTK

System Action: The OS/EM function being executed continues. OS/EM takes an SVC dump for the abending module, takes the abending module out of service, and deletes the abending module from CSA/ECSA. See messages FEMxxx023, FEMxxx026 and FEMxxx029.

Operator Response: Contact the System Programmer.

System Programmer Response: Use IPCS to determine the cause of the ABEND, take the corrective action required, perform a LLA,REFRESH and reload the failing module using the OS/EM ISPF RELOAD facility. If necessary, contact OS/EM Technical Support for assistance with problem resolution.

FEMICN072

DATA AT PSW AREA IS INACCESSIBLE

Explanation: OS/EM has detected an MVS System ABEND during execution of an OS/EM optional function or a user exit. However, the storage pointed to by the PSW cannot be displayed because it cannot be accessed.

Source: FEMISPCN

System Action: The OS/EM function being executed continues. OS/EM takes an SVC dump for the abending module, takes the abending module out of service, and deletes the abending module from CSA/ECSA. See messages FEMxxx023, FEMxxx026 and FEMxxx029.

Operator Response: Contact the System Programmer.

System Programmer Response: Use IPCS to determine the cause of the ABEND, take the corrective action required, perform a LLA,REFRESH and reload the failing module using the OS/EM ISPF RELOAD facility. If necessary, contact OS/EM Technical Support for assistance with problem resolution.

FEMIPL072

DATA AT PSW AREA IS INACCESSIBLE

Explanation: OS/EM has detected an MVS System ABEND during execution of an OS/EM optional function or a user exit. However, the storage pointed to by the PSW cannot be displayed because it cannot be accessed.

Source: FEMIPL

System Action: The OS/EM function being executed continues. OS/EM takes an SVC dump for the abending module, takes the abending module out of service, and deletes the abending module from CSA/ECSA. See messages FEMxxx023, FEMxxx026 and FEMxxx029.

Operator Response: Contact the System Programmer.

System Programmer Response: Use IPCS to determine the cause of the ABEND, take the corrective action required, perform a LLA,REFRESH and reload the failing module using the OS/EM ISPF RELOAD facility. If necessary, contact OS/EM Technical Support for assistance with problem resolution.

FEMJS2072

DATA AT PSW AREA IS INACCESSIBLE

Explanation: OS/EM has detected an MVS System ABEND during execution of an OS/EM optional function or a user exit. However, the storage pointed to by the PSW cannot be displayed because it cannot be accessed.

Source: FEMJES2B,FEMJES2G

System Action: The OS/EM function being executed continues. OS/EM takes an SVC dump for the abending module, takes the abending module out of service, and deletes the abending module from CSA/ECSA. See messages FEMxxx023, FEMxxx026 and FEMxxx029.

Operator Response: Contact the System Programmer.

System Programmer Response: Use IPCS to determine the cause of the ABEND, take the corrective action required, perform a LLA,REFRESH and reload the failing module using the OS/EM ISPF RELOAD facility. If necessary, contact OS/EM Technical Support for assistance with problem resolution.

FEMJ2M072

DATA AT PSW AREA IS INACCESSIBLE

Explanation: OS/EM has detected an MVS System ABEND during execution of an OS/EM optional function or a user exit. However, the storage pointed to by the PSW cannot be displayed because it cannot be accessed.

Source: FEMJ2MCx

System Action: The OS/EM function being executed continues. OS/EM takes an SVC dump for the abending module, takes the abending module out of service, and deletes the abending module from CSA/ECSA. See messages FEMxxx023, FEMxxx026 and FEMxxx029.

Operator Response: Contact the System Programmer.

System Programmer Response: Use IPCS to determine the cause of the ABEND, take the corrective action required, perform a LLA,REFRESH and reload the failing module using the OS/EM ISPF RELOAD facility. If necessary, contact OS/EM Technical Support for assistance with problem resolution.

FEMJ2R072

DATA AT PSW AREA IS INACCESSIBLE

Explanation: OS/EM has detected an MVS System ABEND during execution of an OS/EM optional

function or a user exit. However, the storage pointed to by the PSW cannot be displayed because it cannot be accessed.

Source: FEMJ2ERx

System Action: The OS/EM function being executed continues. OS/EM takes an SVC dump for the abending module, takes the abending module out of service, and deletes the abending module from CSA/ECSA. See messages FEMxxx023, FEMxxx026 and FEMxxx029.

Operator Response: Contact the System Programmer.

System Programmer Response: Use IPCS to determine the cause of the ABEND, take the corrective action required, perform a LLA,REFRESH and reload the failing module using the OS/EM ISPF RELOAD facility. If necessary, contact OS/EM Technical Support for assistance with problem resolution.

FEMJ2S072

DATA AT PSW AREA IS INACCESSIBLE

Explanation: OS/EM has detected an MVS System ABEND during execution of an OS/EM optional function or a user exit. However, the storage pointed to by the PSW cannot be displayed because it cannot be accessed.

Source: FEMJ2SCx

System Action: The OS/EM function being executed continues. OS/EM takes an SVC dump for the abending module, takes the abending module out of service, and deletes the abending module from CSA/ECSA. See messages FEMxxx023, FEMxxx026 and FEMxxx029.

Operator Response: Contact the System Programmer.

System Programmer Response: Use IPCS to determine the cause of the ABEND, take the corrective action required, perform a LLA,REFRESH and reload the failing module using the OS/EM ISPF RELOAD facility. If necessary, contact OS/EM Technical Support for assistance with problem resolution.

FEMJ3E072

DATA AT PSW AREA IS INACCESSIBLE

Explanation: OS/EM has detected an MVS System ABEND during execution of an OS/EM optional function or a user exit. However, the storage pointed to by the PSW cannot be displayed because it cannot be accessed.

Source: FEMJ3ECN

System Action: The OS/EM function being executed continues. OS/EM takes an SVC dump for the abending module, takes the abending module out of service, and deletes the abending module from CSA/ECSA. See messages FEMxxx023, FEMxxx026 and FEMxxx029.

Operator Response: Contact the System Programmer.

System Programmer Response: Use IPCS to determine the cause of the ABEND, take the corrective action required, perform a LLA,REFRESH and reload the failing module using the OS/EM ISPF RELOAD facility. If necessary, contact OS/EM Technical Support for assistance with problem resolution.

FEMJ3S072

DATA AT PSW AREA IS INACCESSIBLE

Explanation: OS/EM has detected an MVS System ABEND during execution of an OS/EM optional function or a user exit. However, the storage pointed to by the PSW cannot be displayed because it cannot be accessed.

Source: FEMJ3SVC

System Action: The OS/EM function being executed continues. OS/EM takes an SVC dump for the abending module, takes the abending module out of service, and deletes the abending module from CSA/ECSA. See messages FEMxxx023, FEMxxx026 and FEMxxx029.

Operator Response: Contact the System Programmer.

System Programmer Response: Use IPCS to determine the cause of the ABEND, take the corrective action required, perform a LLA,REFRESH and reload the failing module using the OS/EM ISPF RELOAD facility. If necessary, contact OS/EM Technical Support for assistance with problem resolution.

FEMLOK072

DATA AT PSW AREA IS INACCESSIBLE

Explanation: OS/EM has detected an MVS System ABEND during execution of an OS/EM optional function or a user exit. However, the storage pointed to by the PSW cannot be displayed because it cannot be accessed.

Source: FEMLOCK

System Action: The OS/EM function being executed continues. OS/EM takes an SVC dump for the abending module, takes the abending module out of service, and deletes the abending module from CSA/ECSA. See messages FEMxxx023, FEMxxx026 and FEMxxx029.

Operator Response: Contact the System Programmer.

System Programmer Response: Use IPCS to determine the cause of the ABEND, take the corrective action required, perform a LLA,REFRESH and reload the failing module using the OS/EM ISPF RELOAD facility. If necessary, contact OS/EM Technical Support for assistance with problem resolution.

FEMRCN072

DATA AT PSW AREA IS INACCESSIBLE

Explanation: OS/EM has detected an MVS System ABEND during execution of an OS/EM optional function or a user exit. However, the storage pointed to by the PSW cannot be displayed because it cannot be accessed.

Source: FEMRACCN

System Action: The OS/EM function being executed continues. OS/EM takes an SVC dump for the abending module, takes the abending module out of service, and deletes the abending module from CSA/ECSA. See messages FEMxxx023, FEMxxx026 and FEMxxx029.

Operator Response: Contact the System Programmer.

System Programmer Response: Use IPCS to determine the cause of the ABEND, take the corrective action required, perform a LLA,REFRESH and reload the failing module using the OS/EM

ISPF RELOAD facility. If necessary, contact OS/EM Technical Support for assistance with problem resolution.

FEMSCN072

DATA AT PSW AREA IS INACCESSIBLE

Explanation: OS/EM has detected an MVS System ABEND during execution of an OS/EM optional function or a user exit. However, the storage pointed to by the PSW cannot be displayed because it cannot be accessed.

Source: FEMSAFCN,FEMSMFCN

System Action: The OS/EM function being executed continues. OS/EM takes an SVC dump for the abending module, takes the abending module out of service, and deletes the abending module from CSA/ECSA. See messages FEMxxx023, FEMxxx026 and FEMxxx029.

Operator Response: Contact the System Programmer.

System Programmer Response: Use IPCS to determine the cause of the ABEND, take the corrective action required, perform a LLA,REFRESH and reload the failing module using the OS/EM ISPF RELOAD facility. If necessary, contact OS/EM Technical Support for assistance with problem resolution.

FEMTCN072

DATA AT PSW AREA IS INACCESSIBLE

Explanation: OS/EM has detected an MVS System ABEND during execution of an OS/EM optional function or a user exit. However, the storage pointed to by the PSW cannot be displayed because it cannot be accessed.

Source: FEMTSOCN

System Action: The OS/EM function being executed continues. OS/EM takes an SVC dump for the abending module, takes the abending module out of service, and deletes the abending module from CSA/ECSA. See messages FEMxxx023, FEMxxx026 and FEMxxx029.

Operator Response: Contact the System Programmer.

System Programmer Response: Use IPCS to determine the cause of the ABEND, take the corrective action required, perform a LLA,REFRESH and reload the failing module using the OS/EM ISPF RELOAD facility. If necessary, contact OS/EM Technical Support for assistance with problem resolution.

FEMTPS072

DATA AT PSW AREA IS INACCESSIBLE

Explanation: OS/EM has detected an MVS System ABEND during execution of an OS/EM optional function or a user exit. However, the storage pointed to by the PSW cannot be displayed because it cannot be accessed.

Source: FEMTPSHR

System Action: The OS/EM function being executed continues. OS/EM takes an SVC dump for the abending module, takes the abending module out of service, and deletes the abending module from CSA/ECSA. See messages FEMxxx023, FEMxxx026 and FEMxxx029.

Operator Response: Contact the System Programmer.

System Programmer Response: Use IPCS to determine the cause of the ABEND, take the corrective action required, perform a LLA,REFRESH and reload the failing module using the OS/EM ISPF RELOAD facility. If necessary, contact OS/EM Technical Support for assistance with problem resolution.

FEMUJI072

DATA AT PSW AREA IS INACCESSIBLE

Explanation: OS/EM has detected an MVS System ABEND during execution of an OS/EM optional function or a user exit. However, the storage pointed to by the PSW cannot be displayed because it cannot be accessed.

Source: FEMUJI

System Action: The OS/EM function being executed continues. OS/EM takes an SVC dump for the abending module, takes the abending module out of service, and deletes the abending module from CSA/ECSA. See messages FEMxxx023, FEMxxx026 and FEMxxx029.

Operator Response: Contact the System Programmer.

System Programmer Response: Use IPCS to determine the cause of the ABEND, take the corrective action required, perform a LLA,REFRESH and reload the failing module using the OS/EM ISPF RELOAD facility. If necessary, contact OS/EM Technical Support for assistance with problem resolution.

FEMUSI072

DATA AT PSW AREA IS INACCESSIBLE

Explanation: OS/EM has detected an MVS System ABEND during execution of an OS/EM optional function or a user exit. However, the storage pointed to by the PSW cannot be displayed because it cannot be accessed.

Source: FEMUSI

System Action: The OS/EM function being executed continues. OS/EM takes an SVC dump for the abending module, takes the abending module out of service, and deletes the abending module from CSA/ECSA. See messages FEMxxx023, FEMxxx026 and FEMxxx029.

Operator Response: Contact the System Programmer.

System Programmer Response: Use IPCS to determine the cause of the ABEND, take the corrective action required, perform a LLA,REFRESH and reload the failing module using the OS/EM ISPF RELOAD facility. If necessary, contact OS/EM Technical Support for assistance with problem resolution.

FEMVCN072

DATA AT PSW AREA IS INACCESSIBLE

Explanation: OS/EM has detected an MVS System ABEND during execution of an OS/EM optional function or a user exit. However, the storage pointed to by the PSW cannot be displayed because it cannot be accessed.

Source: FEMSVCCN

System Action: The OS/EM function being executed continues. OS/EM takes an SVC dump for the abending module, takes the abending module out of service, and deletes the abending module from CSA/ECSA. See messages FEMxxx023, FEMxxx026 and FEMxxx029.

Operator Response: Contact the System Programmer.

System Programmer Response: Use IPCS to determine the cause of the ABEND, take the corrective action required, perform a LLA,REFRESH and reload the failing module using the OS/EM ISPF RELOAD facility. If necessary, contact OS/EM Technical Support for assistance with problem resolution.

FEMX05072

DATA AT PSW AREA IS INACCESSIBLE

Explanation: OS/EM has detected an MVS System ABEND during execution of an OS/EM optional function or a user exit. However, the storage pointed to by the PSW cannot be displayed because it cannot be accessed.

Source: FEMJ2X05

System Action: The OS/EM function being executed continues. OS/EM takes an SVC dump for the abending module, takes the abending module out of service, and deletes the abending module from CSA/ECSA. See messages FEMxxx023, FEMxxx026 and FEMxxx029.

Operator Response: Contact the System Programmer.

System Programmer Response: Use IPCS to determine the cause of the ABEND, take the corrective action required, perform a LLA,REFRESH and reload the failing module using the OS/EM ISPF RELOAD facility. If necessary, contact OS/EM Technical Support for assistance with problem resolution.

FEM02F072

DATA AT PSW AREA IS INACCESSIBLE

Explanation: OS/EM has detected an MVS System ABEND during execution of an OS/EM optional function or a user exit. However, the storage pointed to by the PSW cannot be displayed because it cannot be accessed.

Source: FEM0002F

System Action: The OS/EM function being executed continues. OS/EM takes an SVC dump for the abending module, takes the abending module out of service, and deletes the abending module from CSA/ECSA. See messages FEMxxx023, FEMxxx026 and FEMxxx029.

Operator Response: Contact the System Programmer.

System Programmer Response: Use IPCS to determine the cause of the ABEND, take the corrective action required, perform a LLA,REFRESH and reload the failing module using the OS/EM ISPF RELOAD facility. If necessary, contact OS/EM Technical Support for assistance with problem resolution.

FEM1PL072

DATA AT PSW AREA IS INACCESSIBLE

Explanation: OS/EM has detected an MVS System ABEND during execution of an OS/EM optional function or a user exit. However, the storage pointed to by the PSW cannot be displayed because it cannot be accessed.

Source: FEM1PL1

System Action: The OS/EM function being executed continues. OS/EM takes an SVC dump for the abending module, takes the abending module out of service, and deletes the abending module from CSA/ECSA. See messages FEMxxx023, FEMxxx026 and FEMxxx029.

Operator Response: Contact the System Programmer.

System Programmer Response: Use IPCS to determine the cause of the ABEND, take the corrective action required, perform a LLA,REFRESH and reload the failing module using the OS/EM ISPF RELOAD facility. If necessary, contact OS/EM Technical Support for assistance with problem resolution.

FEM2H5072

DATA AT PSW AREA IS INACCESSIBLE

Explanation: OS/EM has detected an MVS System ABEND during execution of an OS/EM optional function or a user exit. However, the storage pointed to by the PSW cannot be displayed because it cannot be accessed.

Source: FEMJ2H5x

System Action: The OS/EM function being executed continues. OS/EM takes an SVC dump for the abending module, takes the abending module out of service, and deletes the abending module from CSA/ECSA. See messages FEMxxx023, FEMxxx026 and FEMxxx029.

Operator Response: Contact the System Programmer.

System Programmer Response: Use IPCS to determine the cause of the ABEND, take the corrective action required, perform a LLA,REFRESH and reload the failing module using the OS/EM ISPF RELOAD facility. If necessary, contact OS/EM Technical Support for assistance with problem resolution.

FEM2P4072

DATA AT PSW AREA IS INACCESSIBLE

Explanation: OS/EM has detected an MVS System ABEND during execution of an OS/EM optional function or a user exit. However, the storage pointed to by the PSW cannot be displayed because it cannot be accessed.

Source: FEMJ2P4x

System Action: The OS/EM function being executed continues. OS/EM takes an SVC dump for the abending module, takes the abending module out of service, and deletes the abending module from CSA/ECSA. See messages FEMxxx023, FEMxxx026 and FEMxxx029.

Operator Response: Contact the System Programmer.

System Programmer Response: Use IPCS to determine the cause of the ABEND, take the corrective action required, perform a LLA,REFRESH and reload the failing module using the OS/EM ISPF RELOAD facility. If necessary, contact OS/EM Technical Support for assistance with problem resolution.

FEMACN073

ABEND REGS 0-3: nnnnnnnn nnnnnnnn nnnnnnnn nnnnnnnn

Explanation: The OS/EM has detected a MVS System Abend during execution of an OS/EM optional function or a User exit.

nnnnnnnn: Contents of the General Purpose Register.

Source: FEMALCCN

System Action: The OS/EM function being executed continues, OS/EM takes a SVC dump for the abending module, takes the abending module out of service, and deletes the abending module from CSA/ECSA. See messages FEMxxx023, FEMxxx026 and FEMxxx029.

Operator Response: Contact System Programmer.

System Programmer Response: Use IPCS to determine the cause for the ABEND, take the corrective action required, perform an LLA,REFRESH, and reload the failing module using the OS/EM ISPF RELOAD facility. Contact OS/EM support for assistance in problem resolution.

FEMALC073

ABEND REGS 0-3: nnnnnnnn nnnnnnnn nnnnnnnn nnnnnnnn

Explanation: The OS/EM has detected a MVS System Abend during execution of an OS/EM optional function or a User exit.

nnnnnnnn: Contents of the General Purpose Register.

Source: FEMALLO0,FEMALLO1

System Action: The OS/EM function being executed continues, OS/EM takes a SVC dump for the abending module, takes the abending module out of service, and deletes the abending module from CSA/ECSA. See messages FEMxxx023, FEMxxx026 and FEMxxx029.

Operator Response: Contact System Programmer.

System Programmer Response: Use IPCS to determine the cause for the ABEND, take the corrective action required, perform an LLA,REFRESH, and reload the failing module using the OS/EM ISPF RELOAD facility. Contact OS/EM support for assistance in problem resolution.

FEMASY073

ABEND REGS 0-3: nnnnnnnn nnnnnnnn nnnnnnnn nnnnnnnn

Explanation: The OS/EM has detected a MVS System Abend during execution of an OS/EM optional function or a User exit.

nnnnnnnn: Contents of the General Purpose Register.

Source: FEMASYNC

System Action: The OS/EM function being executed continues, OS/EM takes a SVC dump for the abending module, takes the abending module out of service, and deletes the abending module from CSA/ECSA. See messages FEMxxx023, FEMxxx026 and FEMxxx029.

Operator Response: Contact System Programmer.

System Programmer Response: Use IPCS to determine the cause for the ABEND, take the corrective action required, perform an LLA,REFRESH, and reload the failing module using the OS/EM ISPF RELOAD facility. Contact OS/EM support for assistance in problem resolution.

FEMCMD073

ABEND REGS 0-3: nnnnnnnn nnnnnnnn nnnnnnnn nnnnnnnn

Explanation: The OS/EM has detected a MVS System Abend during execution of an OS/EM optional function or a User exit.

nnnnnnnn: Contents of the General Purpose Register.

Source: FEMCMD

System Action: The OS/EM function being executed continues, OS/EM takes a SVC dump for the abending module, takes the abending module out of service, and deletes the abending module from CSA/ECSA. See messages FEMxxx023, FEMxxx026 and FEMxxx029.

Operator Response: Contact System Programmer.

System Programmer Response: Use IPCS to determine the cause for the ABEND, take the corrective action required, perform an LLA,REFRESH, and reload the failing module using the OS/EM ISPF RELOAD facility. Contact OS/EM support for assistance in problem resolution.

FEMCOM073

ABEND REGS 0-3: nnnnnnnn nnnnnnnn nnnnnnnn nnnnnnnn

Explanation: The OS/EM has detected a MVS System Abend during execution of an OS/EM optional function or a User exit.

nnnnnnnn: Contents of the General Purpose Register.

Source: FEMCOMM

System Action: The OS/EM function being executed continues, OS/EM takes a SVC dump for the abending module, takes the abending module out of service, and deletes the abending module from CSA/ECSA. See messages FEMxxx023, FEMxxx026 and FEMxxx029.

Operator Response: Contact System Programmer.

System Programmer Response: Use IPCS to determine the cause for the ABEND, take the corrective action required, perform an LLA,REFRESH, and reload the failing module using the OS/EM ISPF RELOAD facility. Contact OS/EM support for assistance in problem resolution.

FEMDCN073

ABEND REGS 0-3: nnnnnnnn nnnnnnnn nnnnnnnn nnnnnnnn

Explanation: The OS/EM has detected a MVS System Abend during execution of an OS/EM optional function or a User exit.

nnnnnnnn: Contents of the General Purpose Register.

Source: FEMDADCN

System Action: The OS/EM function being executed continues, OS/EM takes a SVC dump for the abending module, takes the abending module out of service, and deletes the abending module from CSA/ECSA. See messages FEMxxx023, FEMxxx026 and FEMxxx029.

Operator Response: Contact System Programmer.

System Programmer Response: Use IPCS to determine the cause for the ABEND, take the corrective action required, perform an LLA,REFRESH, and reload the failing module using the OS/EM ISPF RELOAD facility. Contact OS/EM support for assistance in problem resolution.

FEMDC1073

ABEND REGS 0-3: nnnnnnnn nnnnnnnn nnnnnnnn nnnnnnnn

Explanation: The OS/EM has detected a MVS System Abend during execution of an OS/EM optional function or a User exit.

nnnnnnnn: Contents of the General Purpose Register.

Source: FEMDCB1

System Action: The OS/EM function being executed continues, OS/EM takes a SVC dump for the abending module, takes the abending module out of service, and deletes the abending module from CSA/ECSA. See messages FEMxxx023, FEMxxx026 and FEMxxx029.

Operator Response: Contact System Programmer.

System Programmer Response: Use IPCS to determine the cause for the ABEND, take the corrective action required, perform an LLA,REFRESH, and reload the failing module using the OS/EM ISPF RELOAD facility. Contact OS/EM support for assistance in problem resolution.

FEMEXR073

ABEND REGS 0-3: nnnnnnnn nnnnnnnn nnnnnnnn nnnnnnnn

Explanation: The OS/EM has detected a MVS System Abend during execution of an OS/EM optional function or a User exit.

nnnnnnnn: Contents of the General Purpose Register.

Source: FEMEXRTN

System Action: The OS/EM function being executed continues, OS/EM takes a SVC dump for the abending module, takes the abending module out of service, and deletes the abending module from CSA/ECSA. See messages FEMxxx023, FEMxxx026 and FEMxxx029.

Operator Response: Contact System Programmer.

System Programmer Response: Use IPCS to determine the cause for the ABEND, take the corrective action required, perform an LLA,REFRESH, and reload the failing module using the OS/EM ISPF RELOAD facility. Contact OS/EM support for assistance in problem resolution.

FEMFRA073

ABEND REGS 0-3: nnnnnnnn nnnnnnnn nnnnnnnn nnnnnnnn

Explanation: The OS/EM has detected a MVS System Abend during execution of an OS/EM optional function or a User exit.

nnnnnnnn: Contents of the General Purpose Register.

Source: FEMFRACN

System Action: The OS/EM function being executed continues, OS/EM takes a SVC dump for the abending module, takes the abending module out of service, and deletes the abending module from CSA/ECSA. See messages FEMxxx023, FEMxxx026 and FEMxxx029.

Operator Response: Contact System Programmer.

System Programmer Response: Use IPCS to determine the cause for the ABEND, take the corrective action required, perform an LLA,REFRESH, and reload the failing module using the OS/EM ISPF RELOAD facility. Contact OS/EM support for assistance in problem resolution.

FEMFTN073

ABEND REGS 0-3: nnnnnnnn nnnnnnnn nnnnnnnn nnnnnnnn

Explanation: The OS/EM has detected a MVS System Abend during execution of an OS/EM optional function or a User exit.

nnnnnnnn: Contents of the General Purpose Register.

Source: FEMFRRTN

System Action: The OS/EM function being executed continues, OS/EM takes a SVC dump for the abending module, takes the abending module out of service, and deletes the abending module from CSA/ECSA. See messages FEMxxx023, FEMxxx026 and FEMxxx029.

Operator Response: Contact System Programmer.

System Programmer Response: Use IPCS to determine the cause for the ABEND, take the corrective action required, perform an LLA,REFRESH, and reload the failing module using the OS/EM ISPF RELOAD facility. Contact OS/EM support for assistance in problem resolution.

FEMHCN073

ABEND REGS 0-3: nnnnnnnn nnnnnnnn nnnnnnnn nnnnnnnn

Explanation: The OS/EM has detected a MVS System Abend during execution of an OS/EM optional function or a User exit.

nnnnnnnn: Contents of the General Purpose Register.

Source: FEMHSMCN

System Action: The OS/EM function being executed continues, OS/EM takes a SVC dump for the abending module, takes the abending module out of service, and deletes the abending module from CSA/ECSA. See messages FEMxxx023, FEMxxx026 and FEMxxx029.

Operator Response: Contact System Programmer.

System Programmer Response: Use IPCS to determine the cause for the ABEND, take the corrective action required, perform an LLA,REFRESH, and reload the failing module using the OS/EM ISPF RELOAD facility. Contact OS/EM support for assistance in problem resolution.

FEMHSP073

ABEND REGS 0-3: nnnnnnnn nnnnnnnn nnnnnnnn nnnnnnnn

Explanation: The OS/EM has detected a MVS System Abend during execution of an OS/EM optional function or a User exit.

nnnnnnnn: Contents of the General Purpose Register.

Source: FEMHJ20

System Action: The OS/EM function being executed continues, OS/EM takes a SVC dump for the abending module, takes the abending module out of service, and deletes the abending module from CSA/ECSA. See messages FEMxxx023, FEMxxx026 and FEMxxx029.

Operator Response: Contact System Programmer.

System Programmer Response: Use IPCS to determine the cause for the ABEND, take the corrective action required, perform an LLA,REFRESH, and reload the failing module using the OS/EM ISPF RELOAD facility. Contact OS/EM support for assistance in problem resolution.

FEMIAT073

ABEND REGS 0-3: nnnnnnnn nnnnnnnn nnnnnnnn nnnnnnnn

Explanation: The OS/EM has detected a MVS System Abend during execution of an OS/EM optional function or a User exit.

nnnnnnnn: Contents of the General Purpose Register.

Source: FEMINTK

System Action: The OS/EM function being executed continues, OS/EM takes a SVC dump for the abending module, takes the abending module out of service, and deletes the abending module from CSA/ECSA. See messages FEMxxx023, FEMxxx026 and FEMxxx029.

Operator Response: Contact System Programmer.

System Programmer Response: Use IPCS to determine the cause for the ABEND, take the corrective action required, perform an LLA,REFRESH, and reload the failing module using the OS/EM ISPF RELOAD facility. Contact OS/EM support for assistance in problem resolution.

FEMICN073

ABEND REGS 0-3: nnnnnnnn nnnnnnnn nnnnnnnn nnnnnnnn

Explanation: The OS/EM has detected a MVS System Abend during execution of an OS/EM optional function or a User exit.

nnnnnnnn: Contents of the General Purpose Register.

Source: FEMISPCN

System Action: The OS/EM function being executed continues, OS/EM takes a SVC dump for the abending module, takes the abending module out of service, and deletes the abending module from CSA/ECSA. See messages FEMxxx023, FEMxxx026 and FEMxxx029.

Operator Response: Contact System Programmer.

System Programmer Response: Use IPCS to determine the cause for the ABEND, take the corrective action required, perform an LLA,REFRESH, and reload the failing module using the OS/EM ISPF RELOAD facility. Contact OS/EM support for assistance in problem resolution.

FEMIPL073

ABEND REGS 0-3: nnnnnnnn nnnnnnnn nnnnnnnn nnnnnnnn

Explanation: The OS/EM has detected a MVS System Abend during execution of an OS/EM optional function or a User exit.

nnnnnnnn: Contents of the General Purpose Register.

Source: FEMIPL

System Action: The OS/EM function being executed continues, OS/EM takes a SVC dump for the abending module, takes the abending module out of service, and deletes the abending module from CSA/ECSA. See messages FEMxxx023, FEMxxx026 and FEMxxx029.

Operator Response: Contact System Programmer.

System Programmer Response: Use IPCS to determine the cause for the ABEND, take the corrective action required, perform an LLA,REFRESH, and reload the failing module using the OS/EM ISPF RELOAD facility. Contact OS/EM support for assistance in problem resolution.

FEMJS2073

ABEND REGS 0-3: nnnnnnnn nnnnnnnn nnnnnnnn nnnnnnnn

Explanation: The OS/EM has detected a MVS System Abend during execution of an OS/EM optional function or a User exit.

nnnnnnnn: Contents of the General Purpose Register.

Source: FEMJES2B,FEMJES2G

System Action: The OS/EM function being executed continues, OS/EM takes a SVC dump for the abending module, takes the abending module out of service, and deletes the abending module from CSA/ECSA. See messages FEMxxx023, FEMxxx026 and FEMxxx029.

Operator Response: Contact System Programmer.

System Programmer Response: Use IPCS to determine the cause for the ABEND, take the corrective action required, perform an LLA,REFRESH, and reload the failing module using the OS/EM ISPF RELOAD facility. Contact OS/EM support for assistance in problem resolution.

FEMJ2M073

ABEND REGS 0-3: nnnnnnnn nnnnnnnn nnnnnnnn nnnnnnnn

Explanation: The OS/EM has detected a MVS System Abend during execution of an OS/EM optional function or a User exit.

nnnnnnnn: Contents of the General Purpose Register.

Source: FEMJ2MCx

System Action: The OS/EM function being executed continues, OS/EM takes a SVC dump for the abending module, takes the abending module out of service, and deletes the abending module from CSA/ECSA. See messages FEMxxx023, FEMxxx026 and FEMxxx029.

Operator Response: Contact System Programmer.

System Programmer Response: Use IPCS to determine the cause for the ABEND, take the corrective action required, perform an LLA,REFRESH, and reload the failing module using the OS/EM ISPF RELOAD facility. Contact OS/EM support for assistance in problem resolution.

FEMJ2R073

ABEND REGS 0-3: nnnnnnnn nnnnnnnn nnnnnnnn nnnnnnnn

Explanation: The OS/EM has detected a MVS System Abend during execution of an OS/EM optional function or a User exit.

nnnnnnnn: Contents of the General Purpose Register.

Source: FEMJ2ERx

System Action: The OS/EM function being executed continues, OS/EM takes a SVC dump for the abending module, takes the abending module out of service, and deletes the abending module from CSA/ECSA. See messages FEMxxx023, FEMxxx026 and FEMxxx029.

Operator Response: Contact System Programmer.

System Programmer Response: Use IPCS to determine the cause for the ABEND, take the corrective action required, perform an LLA,REFRESH, and reload the failing module using the OS/EM ISPF RELOAD facility. Contact OS/EM support for assistance in problem resolution.

FEMJ2S073

ABEND REGS 0-3: nnnnnnnn nnnnnnnn nnnnnnnn nnnnnnnn

Explanation: The OS/EM has detected a MVS System Abend during execution of an OS/EM optional function or a User exit.

nnnnnnnn: Contents of the General Purpose Register.

Source: FEMJ2SCx

System Action: The OS/EM function being executed continues, OS/EM takes a SVC dump for the abending module, takes the abending module out of service, and deletes the abending module from CSA/ECSA. See messages FEMxxx023, FEMxxx026 and FEMxxx029.

Operator Response: Contact System Programmer.

System Programmer Response: Use IPCS to determine the cause for the ABEND, take the corrective action required, perform an LLA,REFRESH, and reload the failing module using the OS/EM ISPF RELOAD facility. Contact OS/EM support for assistance in problem resolution.

FEMJ3E073

ABEND REGS 0-3: nnnnnnnn nnnnnnnn nnnnnnnn nnnnnnnn

Explanation: The OS/EM has detected a MVS System Abend during execution of an OS/EM optional function or a User exit.

nnnnnnnn: Contents of the General Purpose Register.

Source: FEMJ3ECN

System Action: The OS/EM function being executed continues, OS/EM takes a SVC dump for the abending module, takes the abending module out of service, and deletes the abending module from CSA/ECSA. See messages FEMxxx023, FEMxxx026 and FEMxxx029.

Operator Response: Contact System Programmer.

System Programmer Response: Use IPCS to determine the cause for the ABEND, take the corrective action required, perform an LLA,REFRESH, and reload the failing module using the OS/EM ISPF RELOAD facility. Contact OS/EM support for assistance in problem resolution.

FEMJ3S073

ABEND REGS 0-3: nnnnnnnn nnnnnnnn nnnnnnnn nnnnnnnn

Explanation: The OS/EM has detected a MVS System Abend during execution of an OS/EM optional function or a User exit.

nnnnnnnn: Contents of the General Purpose Register.

Source: FEMJ3SVC

System Action: The OS/EM function being executed continues, OS/EM takes a SVC dump for the abending module, takes the abending module out of service, and deletes the abending module from CSA/ECSA. See messages FEMxxx023, FEMxxx026 and FEMxxx029.

Operator Response: Contact System Programmer.

System Programmer Response: Use IPCS to determine the cause for the ABEND, take the corrective action required, perform an LLA,REFRESH, and reload the failing module using the OS/EM ISPF RELOAD facility. Contact OS/EM support for assistance in problem resolution.

FEMLOK073

ABEND REGS 0-3: nnnnnnnn nnnnnnnn nnnnnnnn nnnnnnnn

Explanation: The OS/EM has detected a MVS System Abend during execution of an OS/EM optional function or a User exit.

nnnnnnnn: Contents of the General Purpose Register.

Source: FEMLOCK

System Action: The OS/EM function being executed continues, OS/EM takes a SVC dump for the abending module, takes the abending module out of service, and deletes the abending module from CSA/ECSA. See messages FEMxxx023, FEMxxx026 and FEMxxx029.

Operator Response: Contact System Programmer.

System Programmer Response: Use IPCS to determine the cause for the ABEND, take the corrective action required, perform an LLA,REFRESH, and reload the failing module using the OS/EM ISPF RELOAD facility. Contact OS/EM support for assistance in problem resolution.

FEMRCN073

ABEND REGS 0-3: nnnnnnnn nnnnnnnn nnnnnnnn nnnnnnnn

Explanation: The OS/EM has detected a MVS System Abend during execution of an OS/EM optional function or a User exit.

nnnnnnnn: Contents of the General Purpose Register.

Source: FEMRACCN

System Action: The OS/EM function being executed continues, OS/EM takes a SVC dump for the abending module, takes the abending module out of service, and deletes the abending module from CSA/ECSA. See messages FEMxxx023, FEMxxx026 and FEMxxx029.

Operator Response: Contact System Programmer.

System Programmer Response: Use IPCS to determine the cause for the ABEND, take the corrective action required, perform an LLA,REFRESH, and reload the failing module using the OS/EM ISPF RELOAD facility. Contact OS/EM support for assistance in problem resolution.

FEMSCN073

ABEND REGS 0-3: nnnnnnnn nnnnnnnn nnnnnnnn nnnnnnnn

Explanation: The OS/EM has detected a MVS System Abend during execution of an OS/EM optional function or a User exit.

nnnnnnnn: Contents of the General Purpose Register.

Source: FEMSAFCN,FEMSMFCN

System Action: The OS/EM function being executed continues, OS/EM takes a SVC dump for the abending module, takes the abending module out of service, and deletes the abending module from CSA/ECSA. See messages FEMxxx023, FEMxxx026 and FEMxxx029.

Operator Response: Contact System Programmer.

System Programmer Response: Use IPCS to determine the cause for the ABEND, take the corrective action required, perform an LLA,REFRESH, and reload the failing module using the OS/EM ISPF RELOAD facility. Contact OS/EM support for assistance in problem resolution.

FEMTCN073

ABEND REGS 0-3: nnnnnnnn nnnnnnnn nnnnnnnn nnnnnnnn

Explanation: The OS/EM has detected a MVS System Abend during execution of an OS/EM optional function or a User exit.

nnnnnnnn: Contents of the General Purpose Register.

Source: FEMTSOCN

System Action: The OS/EM function being executed continues, OS/EM takes a SVC dump for the abending module, takes the abending module out of service, and deletes the abending module from CSA/ECSA. See messages FEMxxx023, FEMxxx026 and FEMxxx029.

Operator Response: Contact System Programmer.

System Programmer Response: Use IPCS to determine the cause for the ABEND, take the corrective action required, perform an LLA,REFRESH, and reload the failing module using the OS/EM ISPF RELOAD facility. Contact OS/EM support for assistance in problem resolution.

FEMTPS073

ABEND REGS 0-3: nnnnnnnn nnnnnnnn nnnnnnnn nnnnnnnn

Explanation: The OS/EM has detected a MVS System Abend during execution of an OS/EM optional function or a User exit.

nnnnnnnn: Contents of the General Purpose Register.

Source: FEMTPSHR

System Action: The OS/EM function being executed continues, OS/EM takes a SVC dump for the abending module, takes the abending module out of service, and deletes the abending module from CSA/ECSA. See messages FEMxxx023, FEMxxx026 and FEMxxx029.

Operator Response: Contact System Programmer.

System Programmer Response: Use IPCS to determine the cause for the ABEND, take the corrective action required, perform an LLA,REFRESH, and reload the failing module using the OS/EM ISPF RELOAD facility. Contact OS/EM support for assistance in problem resolution.

FEMUJI073

ABEND REGS 0-3: nnnnnnnn nnnnnnnn nnnnnnnn nnnnnnnn

Explanation: The OS/EM has detected a MVS System Abend during execution of an OS/EM optional function or a User exit.

nnnnnnnn: Contents of the General Purpose Register.

Source: FEMUJI

System Action: The OS/EM function being executed continues, OS/EM takes a SVC dump for the abending module, takes the abending module out of service, and deletes the abending module from CSA/ECSA. See messages FEMxxx023, FEMxxx026 and FEMxxx029.

Operator Response: Contact System Programmer.

System Programmer Response: Use IPCS to determine the cause for the ABEND, take the corrective action required, perform an LLA,REFRESH, and reload the failing module using the OS/EM ISPF RELOAD facility. Contact OS/EM support for assistance in problem resolution.

FEMUSI073

ABEND REGS 0-3: nnnnnnnn nnnnnnnn nnnnnnnn nnnnnnnn

Explanation: The OS/EM has detected a MVS System Abend during execution of an OS/EM optional function or a User exit.

nnnnnnnn: Contents of the General Purpose Register.

Source: FEMUSI

System Action: The OS/EM function being executed continues, OS/EM takes a SVC dump for the abending module, takes the abending module out of service, and deletes the abending module from CSA/ECSA. See messages FEMxxx023, FEMxxx026 and FEMxxx029.

Operator Response: Contact System Programmer.

System Programmer Response: Use IPCS to determine the cause for the ABEND, take the corrective action required, perform an LLA,REFRESH, and reload the failing module using the OS/EM ISPF RELOAD facility. Contact OS/EM support for assistance in problem resolution.

FEMVCN073

ABEND REGS 0-3: nnnnnnnn nnnnnnnn nnnnnnnn nnnnnnnn

Explanation: The OS/EM has detected a MVS System Abend during execution of an OS/EM optional function or a User exit.

nnnnnnnn: Contents of the General Purpose Register.

Source: FEMSVCCN

System Action: The OS/EM function being executed continues, OS/EM takes a SVC dump for the abending module, takes the abending module out of service, and deletes the abending module from CSA/ECSA. See messages FEMxxx023, FEMxxx026 and FEMxxx029.

Operator Response: Contact System Programmer.

System Programmer Response: Use IPCS to determine the cause for the ABEND, take the corrective action required, perform an LLA,REFRESH, and reload the failing module using the OS/EM ISPF RELOAD facility. Contact OS/EM support for assistance in problem resolution.

FEMX05073

ABEND REGS 0-3: nnnnnnnn nnnnnnnn nnnnnnnn nnnnnnnn

Explanation: The OS/EM has detected a MVS System Abend during execution of an OS/EM optional function or a User exit.

nnnnnnnn: Contents of the General Purpose Register.

Source: FEMJ2X05

System Action: The OS/EM function being executed continues, OS/EM takes a SVC dump for the abending module, takes the abending module out of service, and deletes the abending module from CSA/ECSA. See messages FEMxxx023, FEMxxx026 and FEMxxx029.

Operator Response: Contact System Programmer.

System Programmer Response: Use IPCS to determine the cause for the ABEND, take the corrective action required, perform an LLA,REFRESH, and reload the failing module using the OS/EM ISPF RELOAD facility. Contact OS/EM support for assistance in problem resolution.

FEM02F073

ABEND REGS 0-3: nnnnnnnn nnnnnnnn nnnnnnnn nnnnnnnn

Explanation: The OS/EM has detected a MVS System Abend during execution of an OS/EM optional function or a User exit.

nnnnnnnn: Contents of the General Purpose Register.

Source: FEM0002F

System Action: The OS/EM function being executed continues, OS/EM takes a SVC dump for the abending module, takes the abending module out of service, and deletes the abending module from CSA/ECSA. See messages FEMxxx023, FEMxxx026 and FEMxxx029.

Operator Response: Contact System Programmer.

System Programmer Response: Use IPCS to determine the cause for the ABEND, take the corrective action required, perform an LLA,REFRESH, and reload the failing module using the OS/EM ISPF RELOAD facility. Contact OS/EM support for assistance in problem resolution.

FEM1PL073

ABEND REGS 0-3: nnnnnnnn nnnnnnnn nnnnnnnn nnnnnnnn

Explanation: The OS/EM has detected a MVS System Abend during execution of an OS/EM optional function or a User exit.

nnnnnnnn: Contents of the General Purpose Register.

Source: FEM1PL1

System Action: The OS/EM function being executed continues, OS/EM takes a SVC dump for the abending module, takes the abending module out of service, and deletes the abending module from CSA/ECSA. See messages FEMxxx023, FEMxxx026 and FEMxxx029.

Operator Response: Contact System Programmer.

System Programmer Response: Use IPCS to determine the cause for the ABEND, take the corrective action required, perform an LLA,REFRESH, and reload the failing module using the OS/EM ISPF RELOAD facility. Contact OS/EM support for assistance in problem resolution.

FEM2H5073

ABEND REGS 0-3: nnnnnnnn nnnnnnnn nnnnnnnn nnnnnnnn

Explanation: The OS/EM has detected a MVS System Abend during execution of an OS/EM optional function or a User exit.

nnnnnnnn: Contents of the General Purpose Register.

Source: FEMJ2H5x

System Action: The OS/EM function being executed continues, OS/EM takes a SVC dump for the abending module, takes the abending module out of service, and deletes the abending module from CSA/ECSA. See messages FEMxxx023, FEMxxx026 and FEMxxx029.

Operator Response: Contact System Programmer.

System Programmer Response: Use IPCS to determine the cause for the ABEND, take the corrective action required, perform an LLA,REFRESH, and reload the failing module using the OS/EM ISPF RELOAD facility. Contact OS/EM support for assistance in problem resolution.

FEM2P4073

ABEND REGS 0-3: nnnnnnnn nnnnnnnn nnnnnnnn nnnnnnnn

Explanation: The OS/EM has detected a MVS System Abend during execution of an OS/EM optional function or a User exit.

nnnnnnnn: Contents of the General Purpose Register.

Source: FEMJ2P4x

System Action: The OS/EM function being executed continues, OS/EM takes a SVC dump for the abending module, takes the abending module out of service, and deletes the abending module from CSA/ECSA. See messages FEMxxx023, FEMxxx026 and FEMxxx029.

Operator Response: Contact System Programmer.

System Programmer Response: Use IPCS to determine the cause for the ABEND, take the corrective action required, perform an LLA,REFRESH, and reload the failing module using the OS/EM ISPF RELOAD facility. Contact OS/EM support for assistance in problem resolution.

FEMACN074

ABEND REGS 4-7: nnnnnnnn nnnnnnnn nnnnnnnn nnnnnnnn

Explanation: The OS/EM has detected a MVS System Abend during execution of an OS/EM optional function or a User exit.

nnnnnnnn: Contents of the General Purpose Register.

Source: FEMALCCN

System Action: The OS/EM function being executed continues, OS/EM takes a SVC dump for the abending module, takes the abending module out of service, and deletes the abending module from CSA/ECSA. See messages FEMxxx023, FEMxxx026 and FEMxxx029.

Operator Response: Contact System Programmer.

System Programmer Response: Use IPCS to determine the cause for the ABEND, take the corrective action required, perform an LLA,REFRESH, and reload the failing module using the OS/EM ISPF RELOAD facility. Contact OS/EM support for assistance in problem resolution.

FEMALC074

ABEND REGS 4-7: nnnnnnnn nnnnnnnn nnnnnnnn nnnnnnnn

Explanation: The OS/EM has detected a MVS System Abend during execution of an OS/EM optional function or a User exit.

nnnnnnnn: Contents of the General Purpose Register.

Source: FEMALLO0,FEMALLO1

System Action: The OS/EM function being executed continues, OS/EM takes a SVC dump for the abending module, takes the abending module out of service, and deletes the abending module from CSA/ECSA. See messages FEMxxx023, FEMxxx026 and FEMxxx029.

Operator Response: Contact System Programmer.

System Programmer Response: Use IPCS to determine the cause for the ABEND, take the corrective action required, perform an LLA,REFRESH, and reload the failing module using the OS/EM ISPF RELOAD facility. Contact OS/EM support for assistance in problem resolution.

FEMASY074

ABEND REGS 4-7: nnnnnnnn nnnnnnnn nnnnnnnn nnnnnnnn

Explanation: The OS/EM has detected a MVS System Abend during execution of an OS/EM optional function or a User exit.

nnnnnnnn: Contents of the General Purpose Register.

Source: FEMASYNC

System Action: The OS/EM function being executed continues, OS/EM takes a SVC dump for the abending module, takes the abending module out of service, and deletes the abending module from CSA/ECSA. See messages FEMxxx023, FEMxxx026 and FEMxxx029.

Operator Response: Contact System Programmer.

System Programmer Response: Use IPCS to determine the cause for the ABEND, take the corrective action required, perform an LLA,REFRESH, and reload the failing module using the OS/EM ISPF RELOAD facility. Contact OS/EM support for assistance in problem resolution.

FEMCMD074

ABEND REGS 4-7: nnnnnnnn nnnnnnnn nnnnnnnn nnnnnnnn

Explanation: The OS/EM has detected a MVS System Abend during execution of an OS/EM optional function or a User exit.

nnnnnnnn: Contents of the General Purpose Register.

Source: FEMCMD

System Action: The OS/EM function being executed continues, OS/EM takes a SVC dump for the abending module, takes the abending module out of service, and deletes the abending module from CSA/ECSA. See messages FEMxxx023, FEMxxx026 and FEMxxx029.

Operator Response: Contact System Programmer.

System Programmer Response: Use IPCS to determine the cause for the ABEND, take the corrective action required, perform an LLA,REFRESH, and reload the failing module using the OS/EM ISPF RELOAD facility. Contact OS/EM support for assistance in problem resolution.

FEMCOM074

ABEND REGS 4-7: nnnnnnnn nnnnnnnn nnnnnnnn nnnnnnnn

Explanation: The OS/EM has detected a MVS System Abend during execution of an OS/EM optional function or a User exit.

nnnnnnnn: Contents of the General Purpose Register.

Source: FEMCOMM

System Action: The OS/EM function being executed continues, OS/EM takes a SVC dump for the abending module, takes the abending module out of service, and deletes the abending module from CSA/ECSA. See messages FEMxxx023, FEMxxx026 and FEMxxx029.

Operator Response: Contact System Programmer.

System Programmer Response: Use IPCS to determine the cause for the ABEND, take the corrective action required, perform an LLA,REFRESH, and reload the failing module using the OS/EM ISPF RELOAD facility. Contact OS/EM support for assistance in problem resolution.

FEMDCN074

ABEND REGS 4-7: nnnnnnnn nnnnnnnn nnnnnnnn nnnnnnnn

Explanation: The OS/EM has detected a MVS System Abend during execution of an OS/EM optional function or a User exit.

nnnnnnnn: Contents of the General Purpose Register.

Source: FEMDADCN

System Action: The OS/EM function being executed continues, OS/EM takes a SVC dump for the abending module, takes the abending module out of service, and deletes the abending module from CSA/ECSA. See messages FEMxxx023, FEMxxx026 and FEMxxx029.

Operator Response: Contact System Programmer.

System Programmer Response: Use IPCS to determine the cause for the ABEND, take the corrective action required, perform an LLA,REFRESH, and reload the failing module using the OS/EM ISPF RELOAD facility. Contact OS/EM support for assistance in problem resolution.

FEMDC1074

ABEND REGS 4-7: nnnnnnnn nnnnnnnn nnnnnnnn nnnnnnnn

Explanation: The OS/EM has detected a MVS System Abend during execution of an OS/EM optional function or a User exit.

nnnnnnnn: Contents of the General Purpose Register.

Source: FEMDCB1

System Action: The OS/EM function being executed continues, OS/EM takes a SVC dump for the abending module, takes the abending module out of service, and deletes the abending module from CSA/ECSA. See messages FEMxxx023, FEMxxx026 and FEMxxx029.

Operator Response: Contact System Programmer.

System Programmer Response: Use IPCS to determine the cause for the ABEND, take the corrective action required, perform an LLA,REFRESH, and reload the failing module using the OS/EM ISPF RELOAD facility. Contact OS/EM support for assistance in problem resolution.

FEMEXR074

ABEND REGS 4-7: nnnnnnnn nnnnnnnn nnnnnnnn nnnnnnnn

Explanation: The OS/EM has detected a MVS System Abend during execution of an OS/EM optional function or a User exit.

nnnnnnnn: Contents of the General Purpose Register.

Source: FEMEXRTN

System Action: The OS/EM function being executed continues, OS/EM takes a SVC dump for the abending module, takes the abending module out of service, and deletes the abending module from CSA/ECSA. See messages FEMxxx023, FEMxxx026 and FEMxxx029.

Operator Response: Contact System Programmer.

System Programmer Response: Use IPCS to determine the cause for the ABEND, take the corrective action required, perform an LLA,REFRESH, and reload the failing module using the OS/EM ISPF RELOAD facility. Contact OS/EM support for assistance in problem resolution.

FEMFRA074

ABEND REGS 4-7: nnnnnnnn nnnnnnnn nnnnnnnn nnnnnnnn

Explanation: The OS/EM has detected a MVS System Abend during execution of an OS/EM optional function or a User exit.

nnnnnnnn: Contents of the General Purpose Register.

Source: FEMFRACN

System Action: The OS/EM function being executed continues, OS/EM takes a SVC dump for the abending module, takes the abending module out of service, and deletes the abending module from CSA/ECSA. See messages FEMxxx023, FEMxxx026 and FEMxxx029.

Operator Response: Contact System Programmer.

System Programmer Response: Use IPCS to determine the cause for the ABEND, take the corrective action required, perform an LLA,REFRESH, and reload the failing module using the OS/EM ISPF RELOAD facility. Contact OS/EM support for assistance in problem resolution.

FEMFTN074

ABEND REGS 4-7: nnnnnnnn nnnnnnnn nnnnnnnn nnnnnnnn

Explanation: The OS/EM has detected a MVS System Abend during execution of an OS/EM optional function or a User exit.

nnnnnnnn: Contents of the General Purpose Register.

Source: FEMFRRTN

System Action: The OS/EM function being executed continues, OS/EM takes a SVC dump for the abending module, takes the abending module out of service, and deletes the abending module from CSA/ECSA. See messages FEMxxx023, FEMxxx026 and FEMxxx029.

Operator Response: Contact System Programmer.

System Programmer Response: Use IPCS to determine the cause for the ABEND, take the corrective action required, perform an LLA,REFRESH, and reload the failing module using the OS/EM ISPF RELOAD facility. Contact OS/EM support for assistance in problem resolution.

FEMHCN074

ABEND REGS 4-7: nnnnnnnn nnnnnnnn nnnnnnnn nnnnnnnn

Explanation: The OS/EM has detected a MVS System Abend during execution of an OS/EM optional function or a User exit.

nnnnnnnn: Contents of the General Purpose Register.

Source: FEMHSMCN

System Action: The OS/EM function being executed continues, OS/EM takes a SVC dump for the abending module, takes the abending module out of service, and deletes the abending module from CSA/ECSA. See messages FEMxxx023, FEMxxx026 and FEMxxx029.

Operator Response: Contact System Programmer.

System Programmer Response: Use IPCS to determine the cause for the ABEND, take the corrective action required, perform an LLA,REFRESH, and reload the failing module using the OS/EM ISPF RELOAD facility. Contact OS/EM support for assistance in problem resolution.

FEMHSP074

ABEND REGS 4-7: nnnnnnnn nnnnnnnn nnnnnnnn nnnnnnnn

Explanation: The OS/EM has detected a MVS System Abend during execution of an OS/EM optional function or a User exit.

nnnnnnnn: Contents of the General Purpose Register.

Source: FEMHJ20

System Action: The OS/EM function being executed continues, OS/EM takes a SVC dump for the abending module, takes the abending module out of service, and deletes the abending module from CSA/ECSA. See messages FEMxxx023, FEMxxx026 and FEMxxx029.

Operator Response: Contact System Programmer.

System Programmer Response: Use IPCS to determine the cause for the ABEND, take the corrective action required, perform an LLA,REFRESH, and reload the failing module using the OS/EM ISPF RELOAD facility. Contact OS/EM support for assistance in problem resolution.

FEMIAT074

ABEND REGS 4-7: nnnnnnnn nnnnnnnn nnnnnnnn nnnnnnnn

Explanation: The OS/EM has detected a MVS System Abend during execution of an OS/EM optional function or a User exit.

nnnnnnnn: Contents of the General Purpose Register.

Source: FEMINTK

System Action: The OS/EM function being executed continues, OS/EM takes a SVC dump for the abending module, takes the abending module out of service, and deletes the abending module from CSA/ECSA. See messages FEMxxx023, FEMxxx026 and FEMxxx029.

Operator Response: Contact System Programmer.

System Programmer Response: Use IPCS to determine the cause for the ABEND, take the corrective action required, perform an LLA,REFRESH, and reload the failing module using the OS/EM ISPF RELOAD facility. Contact OS/EM support for assistance in problem resolution.

FEMICN074

ABEND REGS 4-7: nnnnnnnn nnnnnnnn nnnnnnnn nnnnnnnn

Explanation: The OS/EM has detected a MVS System Abend during execution of an OS/EM optional function or a User exit.

nnnnnnnn: Contents of the General Purpose Register.

Source: FEMISPCN

System Action: The OS/EM function being executed continues, OS/EM takes a SVC dump for the abending module, takes the abending module out of service, and deletes the abending module from CSA/ECSA. See messages FEMxxx023, FEMxxx026 and FEMxxx029.

Operator Response: Contact System Programmer.

System Programmer Response: Use IPCS to determine the cause for the ABEND, take the corrective action required, perform an LLA,REFRESH, and reload the failing module using the OS/EM ISPF RELOAD facility. Contact OS/EM support for assistance in problem resolution.

FEM IPL074

ABEND REGS 4-7: nnnnnnnn nnnnnnnn nnnnnnnn nnnnnnnn

Explanation: The OS/EM has detected a MVS System Abend during execution of an OS/EM optional function or a User exit.

nnnnnnnn: Contents of the General Purpose Register.

Source: FEM IPL

System Action: The OS/EM function being executed continues, OS/EM takes a SVC dump for the abending module, takes the abending module out of service, and deletes the abending module from CSA/ECSA. See messages FEMxxx023, FEMxxx026 and FEMxxx029.

Operator Response: Contact System Programmer.

System Programmer Response: Use IPCS to determine the cause for the ABEND, take the corrective action required, perform an LLA,REFRESH, and reload the failing module using the OS/EM ISPF RELOAD facility. Contact OS/EM support for assistance in problem resolution.

FEM JS2074

ABEND REGS 4-7: nnnnnnnn nnnnnnnn nnnnnnnn nnnnnnnn

Explanation: The OS/EM has detected a MVS System Abend during execution of an OS/EM optional function or a User exit.

nnnnnnnn: Contents of the General Purpose Register.

Source: FEMJES2B,FEMJES2G

System Action: The OS/EM function being executed continues, OS/EM takes a SVC dump for the abending module, takes the abending module out of service, and deletes the abending module from CSA/ECSA. See messages FEMxxx023, FEMxxx026 and FEMxxx029.

Operator Response: Contact System Programmer.

System Programmer Response: Use IPCS to determine the cause for the ABEND, take the corrective action required, perform an LLA,REFRESH, and reload the failing module using the OS/EM ISPF RELOAD facility. Contact OS/EM support for assistance in problem resolution.

FEM J2M074

ABEND REGS 4-7: nnnnnnnn nnnnnnnn nnnnnnnn nnnnnnnn

Explanation: The OS/EM has detected a MVS System Abend during execution of an OS/EM optional function or a User exit.

nnnnnnnn: Contents of the General Purpose Register.

Source: FEMJ2MCx

System Action: The OS/EM function being executed continues, OS/EM takes a SVC dump for the abending module, takes the abending module out of service, and deletes the abending module from CSA/ECSA. See messages FEMxxx023, FEMxxx026 and FEMxxx029.

Operator Response: Contact System Programmer.

System Programmer Response: Use IPCS to determine the cause for the ABEND, take the corrective action required, perform an LLA,REFRESH, and reload the failing module using the OS/EM ISPF RELOAD facility. Contact OS/EM support for assistance in problem resolution.

FEMJ2R074

ABEND REGS 4-7: nnnnnnnn nnnnnnnn nnnnnnnn nnnnnnnn

Explanation: The OS/EM has detected a MVS System Abend during execution of an OS/EM optional function or a User exit.

nnnnnnnn: Contents of the General Purpose Register.

Source: FEMJ2ERx

System Action: The OS/EM function being executed continues, OS/EM takes a SVC dump for the abending module, takes the abending module out of service, and deletes the abending module from CSA/ECSA. See messages FEMxxx023, FEMxxx026 and FEMxxx029.

Operator Response: Contact System Programmer.

System Programmer Response: Use IPCS to determine the cause for the ABEND, take the corrective action required, perform an LLA,REFRESH, and reload the failing module using the OS/EM ISPF RELOAD facility. Contact OS/EM support for assistance in problem resolution.

FEMJ2S074

ABEND REGS 4-7: nnnnnnnn nnnnnnnn nnnnnnnn nnnnnnnn

Explanation: The OS/EM has detected a MVS System Abend during execution of an OS/EM optional function or a User exit.

nnnnnnnn: Contents of the General Purpose Register.

Source: FEMJ2SCx

System Action: The OS/EM function being executed continues, OS/EM takes a SVC dump for the abending module, takes the abending module out of service, and deletes the abending module from CSA/ECSA. See messages FEMxxx023, FEMxxx026 and FEMxxx029.

Operator Response: Contact System Programmer.

System Programmer Response: Use IPCS to determine the cause for the ABEND, take the corrective action required, perform an LLA,REFRESH, and reload the failing module using the OS/EM ISPF RELOAD facility. Contact OS/EM support for assistance in problem resolution.

FEMJ3E074

ABEND REGS 4-7: nnnnnnnn nnnnnnnn nnnnnnnn nnnnnnnn

Explanation: The OS/EM has detected a MVS System Abend during execution of an OS/EM optional function or a User exit.

nnnnnnnn: Contents of the General Purpose Register.

Source: FEMJ3ECN

System Action: The OS/EM function being executed continues, OS/EM takes a SVC dump for the abending module, takes the abending module out of service, and deletes the abending module from CSA/ECSA. See messages FEMxxx023, FEMxxx026 and FEMxxx029.

Operator Response: Contact System Programmer.

System Programmer Response: Use IPCS to determine the cause for the ABEND, take the corrective action required, perform an LLA,REFRESH, and reload the failing module using the OS/EM ISPF RELOAD facility. Contact OS/EM support for assistance in problem resolution.

FEMJ3S074

ABEND REGS 4-7: nnnnnnnn nnnnnnnn nnnnnnnn nnnnnnnn

Explanation: The OS/EM has detected a MVS System Abend during execution of an OS/EM optional function or a User exit.

nnnnnnnn: Contents of the General Purpose Register.

Source: FEMJ3SVC

System Action: The OS/EM function being executed continues, OS/EM takes a SVC dump for the abending module, takes the abending module out of service, and deletes the abending module from CSA/ECSA. See messages FEMxxx023, FEMxxx026 and FEMxxx029.

Operator Response: Contact System Programmer.

System Programmer Response: Use IPCS to determine the cause for the ABEND, take the corrective action required, perform an LLA,REFRESH, and reload the failing module using the OS/EM ISPF RELOAD facility. Contact OS/EM support for assistance in problem resolution.

FEMLOK074

ABEND REGS 4-7: nnnnnnnn nnnnnnnn nnnnnnnn nnnnnnnn

Explanation: The OS/EM has detected a MVS System Abend during execution of an OS/EM optional function or a User exit.

nnnnnnnn: Contents of the General Purpose Register.

Source: FEMLOCK

System Action: The OS/EM function being executed continues, OS/EM takes a SVC dump for the abending module, takes the abending module out of service, and deletes the abending module from CSA/ECSA. See messages FEMxxx023, FEMxxx026 and FEMxxx029.

Operator Response: Contact System Programmer.

System Programmer Response: Use IPCS to determine the cause for the ABEND, take the corrective action required, perform an LLA,REFRESH, and reload the failing module using the OS/EM ISPF RELOAD facility. Contact OS/EM support for assistance in problem resolution.

FEMRCN074

ABEND REGS 4-7: nnnnnnnn nnnnnnnn nnnnnnnn nnnnnnnn

Explanation: The OS/EM has detected a MVS System Abend during execution of an OS/EM optional function or a User exit.

nnnnnnnn: Contents of the General Purpose Register.

Source: FEMRACCN

System Action: The OS/EM function being executed continues, OS/EM takes a SVC dump for the abending module, takes the abending module out of service, and deletes the abending module from CSA/ECSA. See messages FEMxxx023, FEMxxx026 and FEMxxx029.

Operator Response: Contact System Programmer.

System Programmer Response: Use IPCS to determine the cause for the ABEND, take the corrective action required, perform an LLA,REFRESH, and reload the failing module using the OS/EM ISPF RELOAD facility. Contact OS/EM support for assistance in problem resolution.

FEMSCN074

ABEND REGS 4-7: nnnnnnnn nnnnnnnn nnnnnnnn nnnnnnnn

Explanation: The OS/EM has detected a MVS System Abend during execution of an OS/EM optional function or a User exit.

nnnnnnnn: Contents of the General Purpose Register.

Source: FEMSAFCN,FEMSMFCN

System Action: The OS/EM function being executed continues, OS/EM takes a SVC dump for the abending module, takes the abending module out of service, and deletes the abending module from CSA/ECSA. See messages FEMxxx023, FEMxxx026 and FEMxxx029.

Operator Response: Contact System Programmer.

System Programmer Response: Use IPCS to determine the cause for the ABEND, take the corrective action required, perform an LLA,REFRESH, and reload the failing module using the OS/EM ISPF RELOAD facility. Contact OS/EM support for assistance in problem resolution.

FEMTCN074

ABEND REGS 4-7: nnnnnnnn nnnnnnnn nnnnnnnn nnnnnnnn

Explanation: The OS/EM has detected a MVS System Abend during execution of an OS/EM optional function or a User exit.

nnnnnnnn: Contents of the General Purpose Register.

Source: FEMTSOCN

System Action: The OS/EM function being executed continues, OS/EM takes a SVC dump for the abending module, takes the abending module out of service, and deletes the abending module from CSA/ECSA. See messages FEMxxx023, FEMxxx026 and FEMxxx029.

Operator Response: Contact System Programmer.

System Programmer Response: Use IPCS to determine the cause for the ABEND, take the corrective action required, perform an LLA,REFRESH, and reload the failing module using the OS/EM ISPF RELOAD facility. Contact OS/EM support for assistance in problem resolution.

FEMTPS074

ABEND REGS 4-7: nnnnnnnn nnnnnnnn nnnnnnnn nnnnnnnn

Explanation: The OS/EM has detected a MVS System Abend during execution of an OS/EM optional function or a User exit.

nnnnnnnn: Contents of the General Purpose Register.

Source: FEMTPSHR

System Action: The OS/EM function being executed continues, OS/EM takes a SVC dump for the abending module, takes the abending module out of service, and deletes the abending module from CSA/ECSA. See messages FEMxxx023, FEMxxx026 and FEMxxx029.

Operator Response: Contact System Programmer.

System Programmer Response: Use IPCS to determine the cause for the ABEND, take the corrective action required, perform an LLA,REFRESH, and reload the failing module using the OS/EM ISPF RELOAD facility. Contact OS/EM support for assistance in problem resolution.

FEMUJI074

ABEND REGS 4-7: nnnnnnnn nnnnnnnn nnnnnnnn nnnnnnnn

Explanation: The OS/EM has detected a MVS System Abend during execution of an OS/EM optional function or a User exit.

nnnnnnnn: Contents of the General Purpose Register.

Source: FEMUJI

System Action: The OS/EM function being executed continues, OS/EM takes a SVC dump for the abending module, takes the abending module out of service, and deletes the abending module from CSA/ECSA. See messages FEMxxx023, FEMxxx026 and FEMxxx029.

Operator Response: Contact System Programmer.

System Programmer Response: Use IPCS to determine the cause for the ABEND, take the corrective action required, perform an LLA,REFRESH, and reload the failing module using the OS/EM ISPF RELOAD facility. Contact OS/EM support for assistance in problem resolution.

FEMUSI074

ABEND REGS 4-7: nnnnnnnn nnnnnnnn nnnnnnnn nnnnnnnn

Explanation: The OS/EM has detected a MVS System Abend during execution of an OS/EM optional function or a User exit.

nnnnnnnn: Contents of the General Purpose Register.

Source: FEMUSI

System Action: The OS/EM function being executed continues, OS/EM takes a SVC dump for the abending module, takes the abending module out of service, and deletes the abending module from CSA/ECSA. See messages FEMxxx023, FEMxxx026 and FEMxxx029.

Operator Response: Contact System Programmer.

System Programmer Response: Use IPCS to determine the cause for the ABEND, take the corrective action required, perform an LLA,REFRESH, and reload the failing module using the OS/EM ISPF RELOAD facility. Contact OS/EM support for assistance in problem resolution.

FEMVCN074

ABEND REGS 4-7: nnnnnnnn nnnnnnnn nnnnnnnn nnnnnnnn

Explanation: The OS/EM has detected a MVS System Abend during execution of an OS/EM optional function or a User exit.

nnnnnnnn: Contents of the General Purpose Register.

Source: FEMSVCCN

System Action: The OS/EM function being executed continues, OS/EM takes a SVC dump for the abending module, takes the abending module out of service, and deletes the abending module from CSA/ECSA. See messages FEMxxx023, FEMxxx026 and FEMxxx029.

Operator Response: Contact System Programmer.

System Programmer Response: Use IPCS to determine the cause for the ABEND, take the corrective action required, perform an LLA,REFRESH, and reload the failing module using the OS/EM ISPF RELOAD facility. Contact OS/EM support for assistance in problem resolution.

FEMX05074

ABEND REGS 4-7: nnnnnnnn nnnnnnnn nnnnnnnn nnnnnnnn

Explanation: The OS/EM has detected a MVS System Abend during execution of an OS/EM optional function or a User exit.

nnnnnnnn: Contents of the General Purpose Register.

Source: FEMJ2X05

System Action: The OS/EM function being executed continues, OS/EM takes a SVC dump for the abending module, takes the abending module out of service, and deletes the abending module from CSA/ECSA. See messages FEMxxx023, FEMxxx026 and FEMxxx029.

Operator Response: Contact System Programmer.

System Programmer Response: Use IPCS to determine the cause for the ABEND, take the corrective action required, perform an LLA,REFRESH, and reload the failing module using the OS/EM ISPF RELOAD facility. Contact OS/EM support for assistance in problem resolution.

FEM02F074

ABEND REGS 4-7: nnnnnnnn nnnnnnnn nnnnnnnn nnnnnnnn

Explanation: The OS/EM has detected a MVS System Abend during execution of an OS/EM optional function or a User exit.

nnnnnnnn: Contents of the General Purpose Register.

Source: FEM0002F

System Action: The OS/EM function being executed continues, OS/EM takes a SVC dump for the abending module, takes the abending module out of service, and deletes the abending module from CSA/ECSA. See messages FEMxxx023, FEMxxx026 and FEMxxx029.

Operator Response: Contact System Programmer.

System Programmer Response: Use IPCS to determine the cause for the ABEND, take the corrective action required, perform an LLA,REFRESH, and reload the failing module using the OS/EM ISPF RELOAD facility. Contact OS/EM support for assistance in problem resolution.

FEMIPL074

ABEND REGS 4-7: nnnnnnnn nnnnnnnn nnnnnnnn nnnnnnnn

Explanation: The OS/EM has detected a MVS System Abend during execution of an OS/EM optional function or a User exit.

nnnnnnnn: Contents of the General Purpose Register.

Source: FEMIPL1

System Action: The OS/EM function being executed continues, OS/EM takes a SVC dump for the abending module, takes the abending module out of service, and deletes the abending module from CSA/ECSA. See messages FEMxxx023, FEMxxx026 and FEMxxx029.

Operator Response: Contact System Programmer.

System Programmer Response: Use IPCS to determine the cause for the ABEND, take the corrective action required, perform an LLA,REFRESH, and reload the failing module using the OS/EM ISPF RELOAD facility. Contact OS/EM support for assistance in problem resolution.

FEM2H5074

ABEND REGS 4-7: nnnnnnnn nnnnnnnn nnnnnnnn nnnnnnnn

Explanation: The OS/EM has detected a MVS System Abend during execution of an OS/EM optional function or a User exit.

nnnnnnnn: Contents of the General Purpose Register.

Source: FEMJ2H5x

System Action: The OS/EM function being executed continues, OS/EM takes a SVC dump for the abending module, takes the abending module out of service, and deletes the abending module from CSA/ECSA. See messages FEMxxx023, FEMxxx026 and FEMxxx029.

Operator Response: Contact System Programmer.

System Programmer Response: Use IPCS to determine the cause for the ABEND, take the corrective action required, perform an LLA,REFRESH, and reload the failing module using the OS/EM ISPF RELOAD facility. Contact OS/EM support for assistance in problem resolution.

FEM2P4074

ABEND REGS 4-7: nnnnnnnn nnnnnnnn nnnnnnnn nnnnnnnn

Explanation: The OS/EM has detected a MVS System Abend during execution of an OS/EM optional function or a User exit.

nnnnnnnn: Contents of the General Purpose Register.

Source: FEMJ2P4x

System Action: The OS/EM function being executed continues, OS/EM takes a SVC dump for the abending module, takes the abending module out of service, and deletes the abending module from CSA/ECSA. See messages FEMxxx023, FEMxxx026 and FEMxxx029.

Operator Response: Contact System Programmer.

System Programmer Response: Use IPCS to determine the cause for the ABEND, take the corrective action required, perform an LLA,REFRESH, and reload the failing module using the OS/EM ISPF RELOAD facility. Contact OS/EM support for assistance in problem resolution.

FEMACN075

ABEND REGS 8-11: nnnnnnnn nnnnnnnn nnnnnnnn nnnnnnnn

Explanation: The OS/EM has detected a MVS System Abend during execution of an OS/EM optional function or a User exit.

nnnnnnnn: Contents of the General Purpose Register.

Source: FEMALCCN

System Action: The OS/EM function being executed continues, OS/EM takes a SVC dump for the abending module, takes the abending module out of service, and deletes the abending module from CSA/ECSA. See messages FEMxxx023, FEMxxx026 and FEMxxx029.

Operator Response: Contact System Programmer.

System Programmer Response: Use IPCS to determine the cause for the ABEND, take the corrective action required, perform an LLA,REFRESH, and reload the failing module using the OS/EM ISPF RELOAD facility. Contact OS/EM support for assistance in problem resolution.

FEMALC075

ABEND REGS 8-11: nnnnnnnn nnnnnnnn nnnnnnnn nnnnnnnn

Explanation: The OS/EM has detected a MVS System Abend during execution of an OS/EM optional function or a User exit.

nnnnnnnn: Contents of the General Purpose Register.

Source: FEMALLO0,FEMALLO1

System Action: The OS/EM function being executed continues, OS/EM takes a SVC dump for the abending module, takes the abending module out of service, and deletes the abending module from CSA/ECSA. See messages FEMxxx023, FEMxxx026 and FEMxxx029.

Operator Response: Contact System Programmer.

System Programmer Response: Use IPCS to determine the cause for the ABEND, take the corrective action required, perform an LLA,REFRESH, and reload the failing module using the OS/EM ISPF RELOAD facility. Contact OS/EM support for assistance in problem resolution.

FEMASY075

ABEND REGS 8-11: nnnnnnnn nnnnnnnn nnnnnnnn nnnnnnnn

Explanation: The OS/EM has detected a MVS System Abend during execution of an OS/EM optional function or a User exit.

nnnnnnnn: Contents of the General Purpose Register.

Source: FEMASYNC

System Action: The OS/EM function being executed continues, OS/EM takes a SVC dump for the abending module, takes the abending module out of service, and deletes the abending module from CSA/ECSA. See messages FEMxxx023, FEMxxx026 and FEMxxx029.

Operator Response: Contact System Programmer.

System Programmer Response: Use IPCS to determine the cause for the ABEND, take the corrective action required, perform an LLA,REFRESH, and reload the failing module using the OS/EM ISPF RELOAD facility. Contact OS/EM support for assistance in problem resolution.

FEMCMD075

ABEND REGS 8-11: nnnnnnnn nnnnnnnn nnnnnnnn nnnnnnnn

Explanation: The OS/EM has detected a MVS System Abend during execution of an OS/EM optional function or a User exit.

nnnnnnnn: Contents of the General Purpose Register.

Source: FEMCMD

System Action: The OS/EM function being executed continues, OS/EM takes a SVC dump for the abending module, takes the abending module out of service, and deletes the abending module from CSA/ECSA. See messages FEMxxx023, FEMxxx026 and FEMxxx029.

Operator Response: Contact System Programmer.

System Programmer Response: Use IPCS to determine the cause for the ABEND, take the corrective action required, perform an LLA,REFRESH, and reload the failing module using the OS/EM ISPF RELOAD facility. Contact OS/EM support for assistance in problem resolution.

FEMCOM075

ABEND REGS 8-11: nnnnnnnn nnnnnnnn nnnnnnnn nnnnnnnn

Explanation: The OS/EM has detected a MVS System Abend during execution of an OS/EM optional function or a User exit.

nnnnnnnn: Contents of the General Purpose Register.

Source: FEMCOMM

System Action: The OS/EM function being executed continues, OS/EM takes a SVC dump for the abending module, takes the abending module out of service, and deletes the abending module from CSA/ECSA. See messages FEMxxx023, FEMxxx026 and FEMxxx029.

Operator Response: Contact System Programmer.

System Programmer Response: Use IPCS to determine the cause for the ABEND, take the corrective action required, perform an LLA,REFRESH, and reload the failing module using the OS/EM ISPF RELOAD facility. Contact OS/EM support for assistance in problem resolution.

FEMDCN075

ABEND REGS 8-11: nnnnnnnn nnnnnnnn nnnnnnnn nnnnnnnn

Explanation: The OS/EM has detected a MVS System Abend during execution of an OS/EM optional function or a User exit.

nnnnnnnn: Contents of the General Purpose Register.

Source: FEMDADCN

System Action: The OS/EM function being executed continues, OS/EM takes a SVC dump for the abending module, takes the abending module out of service, and deletes the abending module from CSA/ECSA. See messages FEMxxx023, FEMxxx026 and FEMxxx029.

Operator Response: Contact System Programmer.

System Programmer Response: Use IPCS to determine the cause for the ABEND, take the corrective action required, perform an LLA,REFRESH, and reload the failing module using the OS/EM ISPF RELOAD facility. Contact OS/EM support for assistance in problem resolution.

FEMDC1075

ABEND REGS 8-11: nnnnnnnn nnnnnnnn nnnnnnnn nnnnnnnn

Explanation: The OS/EM has detected a MVS System Abend during execution of an OS/EM optional function or a User exit.

nnnnnnnn: Contents of the General Purpose Register.

Source: FEMDCB1

System Action: The OS/EM function being executed continues, OS/EM takes a SVC dump for the abending module, takes the abending module out of service, and deletes the abending module from CSA/ECSA. See messages FEMxxx023, FEMxxx026 and FEMxxx029.

Operator Response: Contact System Programmer.

System Programmer Response: Use IPCS to determine the cause for the ABEND, take the corrective action required, perform an LLA,REFRESH, and reload the failing module using the OS/EM ISPF RELOAD facility. Contact OS/EM support for assistance in problem resolution.

FEMEXR075

ABEND REGS 8-11: nnnnnnnn nnnnnnnn nnnnnnnn nnnnnnnn

Explanation: The OS/EM has detected a MVS System Abend during execution of an OS/EM optional function or a User exit.

nnnnnnnn: Contents of the General Purpose Register.

Source: FEMEXRTN

System Action: The OS/EM function being executed continues, OS/EM takes a SVC dump for the abending module, takes the abending module out of service, and deletes the abending module from CSA/ECSA. See messages FEMxxx023, FEMxxx026 and FEMxxx029.

Operator Response: Contact System Programmer.

System Programmer Response: Use IPCS to determine the cause for the ABEND, take the corrective action required, perform an LLA,REFRESH, and reload the failing module using the OS/EM ISPF RELOAD facility. Contact OS/EM support for assistance in problem resolution.

FEMFRA075

ABEND REGS 8-11: nnnnnnnn nnnnnnnn nnnnnnnn nnnnnnnn

Explanation: The OS/EM has detected a MVS System Abend during execution of an OS/EM optional function or a User exit.

nnnnnnnn: Contents of the General Purpose Register.

Source: FEMFRACN

System Action: The OS/EM function being executed continues, OS/EM takes a SVC dump for the abending module, takes the abending module out of service, and deletes the abending module from CSA/ECSA. See messages FEMxxx023, FEMxxx026 and FEMxxx029.

Operator Response: Contact System Programmer.

System Programmer Response: Use IPCS to determine the cause for the ABEND, take the corrective action required, perform an LLA,REFRESH, and reload the failing module using the OS/EM ISPF RELOAD facility. Contact OS/EM support for assistance in problem resolution.

FEMFTN075

ABEND REGS 8-11: nnnnnnnn nnnnnnnn nnnnnnnn nnnnnnnn

Explanation: The OS/EM has detected a MVS System Abend during execution of an OS/EM optional function or a User exit.

nnnnnnnn: Contents of the General Purpose Register.

Source: FEMFRRTN

System Action: The OS/EM function being executed continues, OS/EM takes a SVC dump for the abending module, takes the abending module out of service, and deletes the abending module from CSA/ECSA. See messages FEMxxx023, FEMxxx026 and FEMxxx029.

Operator Response: Contact System Programmer.

System Programmer Response: Use IPCS to determine the cause for the ABEND, take the corrective action required, perform an LLA,REFRESH, and reload the failing module using the OS/EM ISPF RELOAD facility. Contact OS/EM support for assistance in problem resolution.

FEMHCN075

ABEND REGS 8-11: nnnnnnnn nnnnnnnn nnnnnnnn nnnnnnnn

Explanation: The OS/EM has detected a MVS System Abend during execution of an OS/EM optional function or a User exit.

nnnnnnnn: Contents of the General Purpose Register.

Source: FEMHSMCN

System Action: The OS/EM function being executed continues, OS/EM takes a SVC dump for the abending module, takes the abending module out of service, and deletes the abending module from CSA/ECSA. See messages FEMxxx023, FEMxxx026 and FEMxxx029.

Operator Response: Contact System Programmer.

System Programmer Response: Use IPCS to determine the cause for the ABEND, take the corrective action required, perform an LLA,REFRESH, and reload the failing module using the OS/EM ISPF RELOAD facility. Contact OS/EM support for assistance in problem resolution.

FEMHSP075

ABEND REGS 8-11: nnnnnnnn nnnnnnnn nnnnnnnn nnnnnnnn

Explanation: The OS/EM has detected a MVS System Abend during execution of an OS/EM optional function or a User exit.

nnnnnnnn: Contents of the General Purpose Register.

Source: FEMHJ20

System Action: The OS/EM function being executed continues, OS/EM takes a SVC dump for the abending module, takes the abending module out of service, and deletes the abending module from CSA/ECSA. See messages FEMxxx023, FEMxxx026 and FEMxxx029.

Operator Response: Contact System Programmer.

System Programmer Response: Use IPCS to determine the cause for the ABEND, take the corrective action required, perform an LLA,REFRESH, and reload the failing module using the OS/EM ISPF RELOAD facility. Contact OS/EM support for assistance in problem resolution.

FEMIAT075

ABEND REGS 8-11: nnnnnnnn nnnnnnnn nnnnnnnn nnnnnnnn

Explanation: The OS/EM has detected a MVS System Abend during execution of an OS/EM optional function or a User exit.

nnnnnnnn: Contents of the General Purpose Register.

Source: FEMINTK

System Action: The OS/EM function being executed continues, OS/EM takes a SVC dump for the abending module, takes the abending module out of service, and deletes the abending module from CSA/ECSA. See messages FEMxxx023, FEMxxx026 and FEMxxx029.

Operator Response: Contact System Programmer.

System Programmer Response: Use IPCS to determine the cause for the ABEND, take the corrective action required, perform an LLA,REFRESH, and reload the failing module using the OS/EM ISPF RELOAD facility. Contact OS/EM support for assistance in problem resolution.

FEMICN075

ABEND REGS 8-11: nnnnnnnn nnnnnnnn nnnnnnnn nnnnnnnn

Explanation: The OS/EM has detected a MVS System Abend during execution of an OS/EM optional function or a User exit.

nnnnnnnn: Contents of the General Purpose Register.

Source: FEMISPCN

System Action: The OS/EM function being executed continues, OS/EM takes a SVC dump for the abending module, takes the abending module out of service, and deletes the abending module from CSA/ECSA. See messages FEMxxx023, FEMxxx026 and FEMxxx029.

Operator Response: Contact System Programmer.

System Programmer Response: Use IPCS to determine the cause for the ABEND, take the corrective action required, perform an LLA,REFRESH, and reload the failing module using the OS/EM ISPF RELOAD facility. Contact OS/EM support for assistance in problem resolution.

FEMIPL075

ABEND REGS 8-11: nnnnnnnn nnnnnnnn nnnnnnnn nnnnnnnn

Explanation: The OS/EM has detected a MVS System Abend during execution of an OS/EM optional function or a User exit.

nnnnnnnn: Contents of the General Purpose Register.

Source: FEMIPL

System Action: The OS/EM function being executed continues, OS/EM takes a SVC dump for the abending module, takes the abending module out of service, and deletes the abending module from CSA/ECSA. See messages FEMxxx023, FEMxxx026 and FEMxxx029.

Operator Response: Contact System Programmer.

System Programmer Response: Use IPCS to determine the cause for the ABEND, take the corrective action required, perform an LLA,REFRESH, and reload the failing module using the OS/EM ISPF RELOAD facility. Contact OS/EM support for assistance in problem resolution.

FEMJS2075

ABEND REGS 8-11: nnnnnnnn nnnnnnnn nnnnnnnn nnnnnnnn

Explanation: The OS/EM has detected a MVS System Abend during execution of an OS/EM optional function or a User exit.

nnnnnnnn: Contents of the General Purpose Register.

Source: FEMJES2B,FEMJES2G

System Action: The OS/EM function being executed continues, OS/EM takes a SVC dump for the abending module, takes the abending module out of service, and deletes the abending module from CSA/ECSA. See messages FEMxxx023, FEMxxx026 and FEMxxx029.

Operator Response: Contact System Programmer.

System Programmer Response: Use IPCS to determine the cause for the ABEND, take the corrective action required, perform an LLA,REFRESH, and reload the failing module using the OS/EM ISPF RELOAD facility. Contact OS/EM support for assistance in problem resolution.

FEMJ2M075

ABEND REGS 8-11: nnnnnnnn nnnnnnnn nnnnnnnn nnnnnnnn

Explanation: The OS/EM has detected a MVS System Abend during execution of an OS/EM optional function or a User exit.

nnnnnnnn: Contents of the General Purpose Register.

Source: FEMJ2MCx

System Action: The OS/EM function being executed continues, OS/EM takes a SVC dump for the abending module, takes the abending module out of service, and deletes the abending module from CSA/ECSA. See messages FEMxxx023, FEMxxx026 and FEMxxx029.

Operator Response: Contact System Programmer.

System Programmer Response: Use IPCS to determine the cause for the ABEND, take the corrective action required, perform an LLA,REFRESH, and reload the failing module using the OS/EM ISPF RELOAD facility. Contact OS/EM support for assistance in problem resolution.

FEMJ2R075

ABEND REGS 8-11: nnnnnnnn nnnnnnnn nnnnnnnn nnnnnnnn

Explanation: The OS/EM has detected a MVS System Abend during execution of an OS/EM optional function or a User exit.

nnnnnnnn: Contents of the General Purpose Register.

Source: FEMJ2ERx

System Action: The OS/EM function being executed continues, OS/EM takes a SVC dump for the abending module, takes the abending module out of service, and deletes the abending module from CSA/ECSA. See messages FEMxxx023, FEMxxx026 and FEMxxx029.

Operator Response: Contact System Programmer.

System Programmer Response: Use IPCS to determine the cause for the ABEND, take the corrective action required, perform an LLA,REFRESH, and reload the failing module using the OS/EM ISPF RELOAD facility. Contact OS/EM support for assistance in problem resolution.

FEMJ2S075

ABEND REGS 8-11: nnnnnnnn nnnnnnnn nnnnnnnn nnnnnnnn

Explanation: The OS/EM has detected a MVS System Abend during execution of an OS/EM optional function or a User exit.

nnnnnnnn: Contents of the General Purpose Register.

Source: FEMJ2SCx

System Action: The OS/EM function being executed continues, OS/EM takes a SVC dump for the abending module, takes the abending module out of service, and deletes the abending module from CSA/ECSA. See messages FEMxxx023, FEMxxx026 and FEMxxx029.

Operator Response: Contact System Programmer.

System Programmer Response: Use IPCS to determine the cause for the ABEND, take the corrective action required, perform an LLA,REFRESH, and reload the failing module using the OS/EM ISPF RELOAD facility. Contact OS/EM support for assistance in problem resolution.

FEMJ3E075

ABEND REGS 8-11: nnnnnnnn nnnnnnnn nnnnnnnn nnnnnnnn

Explanation: The OS/EM has detected a MVS System Abend during execution of an OS/EM optional function or a User exit.

nnnnnnnn: Contents of the General Purpose Register.

Source: FEMJ3ECN

System Action: The OS/EM function being executed continues, OS/EM takes a SVC dump for the abending module, takes the abending module out of service, and deletes the abending module from CSA/ECSA. See messages FEMxxx023, FEMxxx026 and FEMxxx029.

Operator Response: Contact System Programmer.

System Programmer Response: Use IPCS to determine the cause for the ABEND, take the corrective action required, perform an LLA,REFRESH, and reload the failing module using the OS/EM ISPF RELOAD facility. Contact OS/EM support for assistance in problem resolution.

FEMJ3S075

ABEND REGS 8-11: nnnnnnnn nnnnnnnn nnnnnnnn nnnnnnnn

Explanation: The OS/EM has detected a MVS System Abend during execution of an OS/EM optional function or a User exit.

nnnnnnnn: Contents of the General Purpose Register.

Source: FEMJ3SVC

System Action: The OS/EM function being executed continues, OS/EM takes a SVC dump for the abending module, takes the abending module out of service, and deletes the abending module from CSA/ECSA. See messages FEMxxx023, FEMxxx026 and FEMxxx029.

Operator Response: Contact System Programmer.

System Programmer Response: Use IPCS to determine the cause for the ABEND, take the corrective action required, perform an LLA,REFRESH, and reload the failing module using the OS/EM ISPF RELOAD facility. Contact OS/EM support for assistance in problem resolution.

FEMLOK075

ABEND REGS 8-11: nnnnnnnn nnnnnnnn nnnnnnnn nnnnnnnn

Explanation: The OS/EM has detected a MVS System Abend during execution of an OS/EM optional function or a User exit.

nnnnnnnn: Contents of the General Purpose Register.

Source: FEMLOCK

System Action: The OS/EM function being executed continues, OS/EM takes a SVC dump for the abending module, takes the abending module out of service, and deletes the abending module from CSA/ECSA. See messages FEMxxx023, FEMxxx026 and FEMxxx029.

Operator Response: Contact System Programmer.

System Programmer Response: Use IPCS to determine the cause for the ABEND, take the corrective action required, perform an LLA,REFRESH, and reload the failing module using the OS/EM ISPF RELOAD facility. Contact OS/EM support for assistance in problem resolution.

FEMRCN075

ABEND REGS 8-11: nnnnnnnn nnnnnnnn nnnnnnnn nnnnnnnn

Explanation: The OS/EM has detected a MVS System Abend during execution of an OS/EM optional function or a User exit.

nnnnnnnn: Contents of the General Purpose Register.

Source: FEMRACCN

System Action: The OS/EM function being executed continues, OS/EM takes a SVC dump for the abending module, takes the abending module out of service, and deletes the abending module from CSA/ECSA. See messages FEMxxx023, FEMxxx026 and FEMxxx029.

Operator Response: Contact System Programmer.

System Programmer Response: Use IPCS to determine the cause for the ABEND, take the corrective action required, perform an LLA,REFRESH, and reload the failing module using the OS/EM ISPF RELOAD facility. Contact OS/EM support for assistance in problem resolution.

FEMSCN075

ABEND REGS 8-11: nnnnnnnn nnnnnnnn nnnnnnnn nnnnnnnn

Explanation: The OS/EM has detected a MVS System Abend during execution of an OS/EM optional function or a User exit.

nnnnnnnn: Contents of the General Purpose Register.

Source: FEMSAFCN,FEMSMFCN

System Action: The OS/EM function being executed continues, OS/EM takes a SVC dump for the abending module, takes the abending module out of service, and deletes the abending module from CSA/ECSA. See messages FEMxxx023, FEMxxx026 and FEMxxx029.

Operator Response: Contact System Programmer.

System Programmer Response: Use IPCS to determine the cause for the ABEND, take the corrective action required, perform an LLA,REFRESH, and reload the failing module using the OS/EM ISPF RELOAD facility. Contact OS/EM support for assistance in problem resolution.

FEMTCN075

ABEND REGS 8-11: nnnnnnnn nnnnnnnn nnnnnnnn nnnnnnnn

Explanation: The OS/EM has detected a MVS System Abend during execution of an OS/EM optional function or a User exit.

nnnnnnnn: Contents of the General Purpose Register.

Source: FEMTSOCN

System Action: The OS/EM function being executed continues, OS/EM takes a SVC dump for the abending module, takes the abending module out of service, and deletes the abending module from CSA/ECSA. See messages FEMxxx023, FEMxxx026 and FEMxxx029.

Operator Response: Contact System Programmer.

System Programmer Response: Use IPCS to determine the cause for the ABEND, take the corrective action required, perform an LLA,REFRESH, and reload the failing module using the OS/EM ISPF RELOAD facility. Contact OS/EM support for assistance in problem resolution.

FEMTPS075

ABEND REGS 8-11: nnnnnnnn nnnnnnnn nnnnnnnn nnnnnnnn

Explanation: The OS/EM has detected a MVS System Abend during execution of an OS/EM optional function or a User exit.

nnnnnnnn: Contents of the General Purpose Register.

Source: FEMTPSHR

System Action: The OS/EM function being executed continues, OS/EM takes a SVC dump for the abending module, takes the abending module out of service, and deletes the abending module from CSA/ECSA. See messages FEMxxx023, FEMxxx026 and FEMxxx029.

Operator Response: Contact System Programmer.

System Programmer Response: Use IPCS to determine the cause for the ABEND, take the corrective action required, perform an LLA,REFRESH, and reload the failing module using the OS/EM ISPF RELOAD facility. Contact OS/EM support for assistance in problem resolution.

FEMUJI075

ABEND REGS 8-11: nnnnnnnn nnnnnnnn nnnnnnnn nnnnnnnn

Explanation: The OS/EM has detected a MVS System Abend during execution of an OS/EM optional function or a User exit.

nnnnnnnn: Contents of the General Purpose Register.

Source: FEMUJI

System Action: The OS/EM function being executed continues, OS/EM takes a SVC dump for the abending module, takes the abending module out of service, and deletes the abending module from CSA/ECSA. See messages FEMxxx023, FEMxxx026 and FEMxxx029.

Operator Response: Contact System Programmer.

System Programmer Response: Use IPCS to determine the cause for the ABEND, take the corrective action required, perform an LLA,REFRESH, and reload the failing module using the OS/EM ISPF RELOAD facility. Contact OS/EM support for assistance in problem resolution.

FEMUSI075

ABEND REGS 8-11: nnnnnnnn nnnnnnnn nnnnnnnn nnnnnnnn

Explanation: The OS/EM has detected a MVS System Abend during execution of an OS/EM optional function or a User exit.

nnnnnnnn: Contents of the General Purpose Register.

Source: FEMUSI

System Action: The OS/EM function being executed continues, OS/EM takes a SVC dump for the abending module, takes the abending module out of service, and deletes the abending module from CSA/ECSA. See messages FEMxxx023, FEMxxx026 and FEMxxx029.

Operator Response: Contact System Programmer.

System Programmer Response: Use IPCS to determine the cause for the ABEND, take the corrective action required, perform an LLA,REFRESH, and reload the failing module using the OS/EM ISPF RELOAD facility. Contact OS/EM support for assistance in problem resolution.

FEMVCN075

ABEND REGS 8-11: nnnnnnnn nnnnnnnn nnnnnnnn nnnnnnnn

Explanation: The OS/EM has detected a MVS System Abend during execution of an OS/EM optional function or a User exit.

nnnnnnnn: Contents of the General Purpose Register.

Source: FEMSVCCN

System Action: The OS/EM function being executed continues, OS/EM takes a SVC dump for the abending module, takes the abending module out of service, and deletes the abending module from CSA/ECSA. See messages FEMxxx023, FEMxxx026 and FEMxxx029.

Operator Response: Contact System Programmer.

System Programmer Response: Use IPCS to determine the cause for the ABEND, take the corrective action required, perform an LLA,REFRESH, and reload the failing module using the OS/EM ISPF RELOAD facility. Contact OS/EM support for assistance in problem resolution.

FEMX05075

ABEND REGS 8-11: nnnnnnnn nnnnnnnn nnnnnnnn nnnnnnnn

Explanation: The OS/EM has detected a MVS System Abend during execution of an OS/EM optional function or a User exit.

nnnnnnnn: Contents of the General Purpose Register.

Source: FEMJ2X05

System Action: The OS/EM function being executed continues, OS/EM takes a SVC dump for the abending module, takes the abending module out of service, and deletes the abending module from CSA/ECSA. See messages FEMxxx023, FEMxxx026 and FEMxxx029.

Operator Response: Contact System Programmer.

System Programmer Response: Use IPCS to determine the cause for the ABEND, take the corrective action required, perform an LLA,REFRESH, and reload the failing module using the OS/EM ISPF RELOAD facility. Contact OS/EM support for assistance in problem resolution.

FEM02F075

ABEND REGS 8-11: nnnnnnnn nnnnnnnn nnnnnnnn nnnnnnnn

Explanation: The OS/EM has detected a MVS System Abend during execution of an OS/EM optional function or a User exit.

nnnnnnnn: Contents of the General Purpose Register.

Source: FEM0002F

System Action: The OS/EM function being executed continues, OS/EM takes a SVC dump for the abending module, takes the abending module out of service, and deletes the abending module from CSA/ECSA. See messages FEMxxx023, FEMxxx026 and FEMxxx029.

Operator Response: Contact System Programmer.

System Programmer Response: Use IPCS to determine the cause for the ABEND, take the corrective action required, perform an LLA,REFRESH, and reload the failing module using the OS/EM ISPF RELOAD facility. Contact OS/EM support for assistance in problem resolution.

FEM1PL075

ABEND REGS 8-11: nnnnnnnn nnnnnnnn nnnnnnnn nnnnnnnn

Explanation: The OS/EM has detected a MVS System Abend during execution of an OS/EM optional function or a User exit.

nnnnnnnn: Contents of the General Purpose Register.

Source: FEM1PL1

System Action: The OS/EM function being executed continues, OS/EM takes a SVC dump for the abending module, takes the abending module out of service, and deletes the abending module from CSA/ECSA. See messages FEMxxx023, FEMxxx026 and FEMxxx029.

Operator Response: Contact System Programmer.

System Programmer Response: Use IPCS to determine the cause for the ABEND, take the corrective action required, perform an LLA,REFRESH, and reload the failing module using the OS/EM ISPF RELOAD facility. Contact OS/EM support for assistance in problem resolution.

FEM2H5075

ABEND REGS 8-11: nnnnnnnn nnnnnnnn nnnnnnnn nnnnnnnn

Explanation: The OS/EM has detected a MVS System Abend during execution of an OS/EM optional function or a User exit.

nnnnnnnn: Contents of the General Purpose Register.

Source: FEMJ2H5x

System Action: The OS/EM function being executed continues, OS/EM takes a SVC dump for the abending module, takes the abending module out of service, and deletes the abending module from CSA/ECSA. See messages FEMxxx023, FEMxxx026 and FEMxxx029.

Operator Response: Contact System Programmer.

System Programmer Response: Use IPCS to determine the cause for the ABEND, take the corrective action required, perform an LLA,REFRESH, and reload the failing module using the OS/EM ISPF RELOAD facility. Contact OS/EM support for assistance in problem resolution.

FEM2P4075

ABEND REGS 8-11: nnnnnnnn nnnnnnnn nnnnnnnn nnnnnnnn

Explanation: The OS/EM has detected a MVS System Abend during execution of an OS/EM optional function or a User exit.

nnnnnnnn: Contents of the General Purpose Register.

Source: FEMJ2P4x

System Action: The OS/EM function being executed continues, OS/EM takes a SVC dump for the abending module, takes the abending module out of service, and deletes the abending module from CSA/ECSA. See messages FEMxxx023, FEMxxx026 and FEMxxx029.

Operator Response: Contact System Programmer.

System Programmer Response: Use IPCS to determine the cause for the ABEND, take the corrective action required, perform an LLA,REFRESH, and reload the failing module using the OS/EM ISPF RELOAD facility. Contact OS/EM support for assistance in problem resolution.

FEMACN076

ABEND REGS 12-15: nnnnnnnn nnnnnnnn nnnnnnnn nnnnnnnn

Explanation: The OS/EM has detected a MVS System Abend during execution of an OS/EM optional function or a User exit.

nnnnnnnn: Contents of the General Purpose Register.

Source: FEMALCCN

System Action: The OS/EM function being executed continues, OS/EM takes a SVC dump for the abending module, takes the abending module out of service, and deletes the abending module from CSA/ECSA. See messages FEMxxx023, FEMxxx026 and FEMxxx029.

Operator Response: Contact System Programmer.

System Programmer Response: Use IPCS to determine the cause for the ABEND, take the corrective action required, perform an LLA,REFRESH, and reload the failing module using the OS/EM ISPF RELOAD facility. Contact OS/EM support for assistance in problem resolution.

FEMALC076

ABEND REGS 12-15: nnnnnnnn nnnnnnnn nnnnnnnn nnnnnnnn

Explanation: The OS/EM has detected a MVS System Abend during execution of an OS/EM optional function or a User exit.

nnnnnnnn: Contents of the General Purpose Register.

Source: FEMALLO0,FEMALLO1

System Action: The OS/EM function being executed continues, OS/EM takes a SVC dump for the abending module, takes the abending module out of service, and deletes the abending module from CSA/ECSA. See messages FEMxxx023, FEMxxx026 and FEMxxx029.

Operator Response: Contact System Programmer.

System Programmer Response: Use IPCS to determine the cause for the ABEND, take the corrective action required, perform an LLA,REFRESH, and reload the failing module using the OS/EM ISPF RELOAD facility. Contact OS/EM support for assistance in problem resolution.

FEMASY076

ABEND REGS 12-15: nnnnnnnn nnnnnnnn nnnnnnnn nnnnnnnn

Explanation: The OS/EM has detected a MVS System Abend during execution of an OS/EM optional function or a User exit.

nnnnnnnn: Contents of the General Purpose Register.

Source: FEMASYNC

System Action: The OS/EM function being executed continues, OS/EM takes a SVC dump for the abending module, takes the abending module out of service, and deletes the abending module from CSA/ECSA. See messages FEMxxx023, FEMxxx026 and FEMxxx029.

Operator Response: Contact System Programmer.

System Programmer Response: Use IPCS to determine the cause for the ABEND, take the corrective action required, perform an LLA,REFRESH, and reload the failing module using the OS/EM ISPF RELOAD facility. Contact OS/EM support for assistance in problem resolution.

FEMCMD076

ABEND REGS 12-15: nnnnnnnn nnnnnnnn nnnnnnnn nnnnnnnn

Explanation: The OS/EM has detected a MVS System Abend during execution of an OS/EM optional function or a User exit.

nnnnnnnn: Contents of the General Purpose Register.

Source: FEMCMD

System Action: The OS/EM function being executed continues, OS/EM takes a SVC dump for the abending module, takes the abending module out of service, and deletes the abending module from CSA/ECSA. See messages FEMxxx023, FEMxxx026 and FEMxxx029.

Operator Response: Contact System Programmer.

System Programmer Response: Use IPCS to determine the cause for the ABEND, take the corrective action required, perform an LLA,REFRESH, and reload the failing module using the OS/EM ISPF RELOAD facility. Contact OS/EM support for assistance in problem resolution.

FEMCOM076

ABEND REGS 12-15: nnnnnnnn nnnnnnnn nnnnnnnn nnnnnnnn

Explanation: The OS/EM has detected a MVS System Abend during execution of an OS/EM optional function or a User exit.

nnnnnnnn: Contents of the General Purpose Register.

Source: FEMCOMM

System Action: The OS/EM function being executed continues, OS/EM takes a SVC dump for the abending module, takes the abending module out of service, and deletes the abending module from CSA/ECSA. See messages FEMxxx023, FEMxxx026 and FEMxxx029.

Operator Response: Contact System Programmer.

System Programmer Response: Use IPCS to determine the cause for the ABEND, take the corrective action required, perform an LLA,REFRESH, and reload the failing module using the OS/EM ISPF RELOAD facility. Contact OS/EM support for assistance in problem resolution.

FEMDCN076

ABEND REGS 12-15: nnnnnnnn nnnnnnnn nnnnnnnn nnnnnnnn

Explanation: The OS/EM has detected a MVS System Abend during execution of an OS/EM optional function or a User exit.

nnnnnnnn: Contents of the General Purpose Register.

Source: FEMDADCN

System Action: The OS/EM function being executed continues, OS/EM takes a SVC dump for the abending module, takes the abending module out of service, and deletes the abending module from CSA/ECSA. See messages FEMxxx023, FEMxxx026 and FEMxxx029.

Operator Response: Contact System Programmer.

System Programmer Response: Use IPCS to determine the cause for the ABEND, take the corrective action required, perform an LLA,REFRESH, and reload the failing module using the OS/EM ISPF RELOAD facility. Contact OS/EM support for assistance in problem resolution.

FEMDC1076

ABEND REGS 12-15: nnnnnnnn nnnnnnnn nnnnnnnn nnnnnnnn

Explanation: The OS/EM has detected a MVS System Abend during execution of an OS/EM optional function or a User exit.

nnnnnnnn: Contents of the General Purpose Register.

Source: FEMDCB1

System Action: The OS/EM function being executed continues, OS/EM takes a SVC dump for the abending module, takes the abending module out of service, and deletes the abending module from CSA/ECSA. See messages FEMxxx023, FEMxxx026 and FEMxxx029.

Operator Response: Contact System Programmer.

System Programmer Response: Use IPCS to determine the cause for the ABEND, take the corrective action required, perform an LLA,REFRESH, and reload the failing module using the OS/EM ISPF RELOAD facility. Contact OS/EM support for assistance in problem resolution.

FEMEXR076

ABEND REGS 12-15: nnnnnnnn nnnnnnnn nnnnnnnn nnnnnnnn

Explanation: The OS/EM has detected a MVS System Abend during execution of an OS/EM optional function or a User exit.

nnnnnnnn: Contents of the General Purpose Register.

Source: FEMEXRTN

System Action: The OS/EM function being executed continues, OS/EM takes a SVC dump for the abending module, takes the abending module out of service, and deletes the abending module from CSA/ECSA. See messages FEMxxx023, FEMxxx026 and FEMxxx029.

Operator Response: Contact System Programmer.

System Programmer Response: Use IPCS to determine the cause for the ABEND, take the corrective action required, perform an LLA,REFRESH, and reload the failing module using the OS/EM ISPF RELOAD facility. Contact OS/EM support for assistance in problem resolution.

FEMFRA076

ABEND REGS 12-15: nnnnnnnn nnnnnnnn nnnnnnnn nnnnnnnn

Explanation: The OS/EM has detected a MVS System Abend during execution of an OS/EM optional function or a User exit.

nnnnnnnn: Contents of the General Purpose Register.

Source: FEMFRACN

System Action: The OS/EM function being executed continues, OS/EM takes a SVC dump for the abending module, takes the abending module out of service, and deletes the abending module from CSA/ECSA. See messages FEMxxx023, FEMxxx026 and FEMxxx029.

Operator Response: Contact System Programmer.

System Programmer Response: Use IPCS to determine the cause for the ABEND, take the corrective action required, perform an LLA,REFRESH, and reload the failing module using the OS/EM ISPF RELOAD facility. Contact OS/EM support for assistance in problem resolution.

FEMFTN076

ABEND REGS 12-15: nnnnnnnn nnnnnnnn nnnnnnnn nnnnnnnn

Explanation: The OS/EM has detected a MVS System Abend during execution of an OS/EM optional function or a User exit.

nnnnnnnn: Contents of the General Purpose Register.

Source: FEMFRRTN

System Action: The OS/EM function being executed continues, OS/EM takes a SVC dump for the abending module, takes the abending module out of service, and deletes the abending module from CSA/ECSA. See messages FEMxxx023, FEMxxx026 and FEMxxx029.

Operator Response: Contact System Programmer.

System Programmer Response: Use IPCS to determine the cause for the ABEND, take the corrective action required, perform an LLA,REFRESH, and reload the failing module using the OS/EM ISPF RELOAD facility. Contact OS/EM support for assistance in problem resolution.

FEMHCN076

ABEND REGS 12-15: nnnnnnnn nnnnnnnn nnnnnnnn nnnnnnnn

Explanation: The OS/EM has detected a MVS System Abend during execution of an OS/EM optional function or a User exit.

nnnnnnnn: Contents of the General Purpose Register.

Source: FEMHSMCN

System Action: The OS/EM function being executed continues, OS/EM takes a SVC dump for the abending module, takes the abending module out of service, and deletes the abending module from CSA/ECSA. See messages FEMxxx023, FEMxxx026 and FEMxxx029.

Operator Response: Contact System Programmer.

System Programmer Response: Use IPCS to determine the cause for the ABEND, take the corrective action required, perform an LLA,REFRESH, and reload the failing module using the OS/EM ISPF RELOAD facility. Contact OS/EM support for assistance in problem resolution.

FEMHSP076

ABEND REGS 12-15: nnnnnnnn nnnnnnnn nnnnnnnn nnnnnnnn

Explanation: The OS/EM has detected a MVS System Abend during execution of an OS/EM optional function or a User exit.

nnnnnnnn: Contents of the General Purpose Register.

Source: FEMHJ20

System Action: The OS/EM function being executed continues, OS/EM takes a SVC dump for the abending module, takes the abending module out of service, and deletes the abending module from CSA/ECSA. See messages FEMxxx023, FEMxxx026 and FEMxxx029.

Operator Response: Contact System Programmer.

System Programmer Response: Use IPCS to determine the cause for the ABEND, take the corrective action required, perform an LLA,REFRESH, and reload the failing module using the OS/EM ISPF RELOAD facility. Contact OS/EM support for assistance in problem resolution.

FEMIAT076

ABEND REGS 12-15: nnnnnnnn nnnnnnnn nnnnnnnn nnnnnnnn

Explanation: The OS/EM has detected a MVS System Abend during execution of an OS/EM optional function or a User exit.

nnnnnnnn: Contents of the General Purpose Register.

Source: FEMINTK

System Action: The OS/EM function being executed continues, OS/EM takes a SVC dump for the abending module, takes the abending module out of service, and deletes the abending module from CSA/ECSA. See messages FEMxxx023, FEMxxx026 and FEMxxx029.

Operator Response: Contact System Programmer.

System Programmer Response: Use IPCS to determine the cause for the ABEND, take the corrective action required, perform an LLA,REFRESH, and reload the failing module using the OS/EM ISPF RELOAD facility. Contact OS/EM support for assistance in problem resolution.

FEMICN076

ABEND REGS 12-15: nnnnnnnn nnnnnnnn nnnnnnnn nnnnnnnn

Explanation: The OS/EM has detected a MVS System Abend during execution of an OS/EM optional function or a User exit.

nnnnnnnn: Contents of the General Purpose Register.

Source: FEMISPCN

System Action: The OS/EM function being executed continues, OS/EM takes a SVC dump for the abending module, takes the abending module out of service, and deletes the abending module from CSA/ECSA. See messages FEMxxx023, FEMxxx026 and FEMxxx029.

Operator Response: Contact System Programmer.

System Programmer Response: Use IPCS to determine the cause for the ABEND, take the corrective action required, perform an LLA,REFRESH, and reload the failing module using the OS/EM ISPF RELOAD facility. Contact OS/EM support for assistance in problem resolution.

FEMIPL076

ABEND REGS 12-15: nnnnnnnn nnnnnnnn nnnnnnnn nnnnnnnn

Explanation: The OS/EM has detected a MVS System Abend during execution of an OS/EM optional function or a User exit.

nnnnnnnn: Contents of the General Purpose Register.

Source: FEMIPL

System Action: The OS/EM function being executed continues, OS/EM takes a SVC dump for the abending module, takes the abending module out of service, and deletes the abending module from CSA/ECSA. See messages FEMxxx023, FEMxxx026 and FEMxxx029.

Operator Response: Contact System Programmer.

System Programmer Response: Use IPCS to determine the cause for the ABEND, take the corrective action required, perform an LLA,REFRESH, and reload the failing module using the OS/EM ISPF RELOAD facility. Contact OS/EM support for assistance in problem resolution.

FEMJS2076

ABEND REGS 12-15: nnnnnnnn nnnnnnnn nnnnnnnn nnnnnnnn

Explanation: The OS/EM has detected a MVS System Abend during execution of an OS/EM optional function or a User exit.

nnnnnnnn: Contents of the General Purpose Register.

Source: FEMJES2B,FEMJES2G

System Action: The OS/EM function being executed continues, OS/EM takes a SVC dump for the abending module, takes the abending module out of service, and deletes the abending module from CSA/ECSA. See messages FEMxxx023, FEMxxx026 and FEMxxx029.

Operator Response: Contact System Programmer.

System Programmer Response: Use IPCS to determine the cause for the ABEND, take the corrective action required, perform an LLA,REFRESH, and reload the failing module using the OS/EM ISPF RELOAD facility. Contact OS/EM support for assistance in problem resolution.

FEMJ2M076

ABEND REGS 12-15: nnnnnnnn nnnnnnnn nnnnnnnn nnnnnnnn

Explanation: The OS/EM has detected a MVS System Abend during execution of an OS/EM optional function or a User exit.

nnnnnnnn: Contents of the General Purpose Register.

Source: FEMJ2MCx

System Action: The OS/EM function being executed continues, OS/EM takes a SVC dump for the abending module, takes the abending module out of service, and deletes the abending module from CSA/ECSA. See messages FEMxxx023, FEMxxx026 and FEMxxx029.

Operator Response: Contact System Programmer.

System Programmer Response: Use IPCS to determine the cause for the ABEND, take the corrective action required, perform an LLA,REFRESH, and reload the failing module using the OS/EM ISPF RELOAD facility. Contact OS/EM support for assistance in problem resolution.

FEMJ2R076

ABEND REGS 12-15: nnnnnnnn nnnnnnnn nnnnnnnn nnnnnnnn

Explanation: The OS/EM has detected a MVS System Abend during execution of an OS/EM optional function or a User exit.

nnnnnnnn: Contents of the General Purpose Register.

Source: FEMJ2ERx

System Action: The OS/EM function being executed continues, OS/EM takes a SVC dump for the abending module, takes the abending module out of service, and deletes the abending module from CSA/ECSA. See messages FEMxxx023, FEMxxx026 and FEMxxx029.

Operator Response: Contact System Programmer.

System Programmer Response: Use IPCS to determine the cause for the ABEND, take the corrective action required, perform an LLA,REFRESH, and reload the failing module using the OS/EM ISPF RELOAD facility. Contact OS/EM support for assistance in problem resolution.

FEMJ2S076

ABEND REGS 12-15: nnnnnnnn nnnnnnnn nnnnnnnn nnnnnnnn

Explanation: The OS/EM has detected a MVS System Abend during execution of an OS/EM optional function or a User exit.

nnnnnnnn: Contents of the General Purpose Register.

Source: FEMJ2SCx

System Action: The OS/EM function being executed continues, OS/EM takes a SVC dump for the abending module, takes the abending module out of service, and deletes the abending module from CSA/ECSA. See messages FEMxxx023, FEMxxx026 and FEMxxx029.

Operator Response: Contact System Programmer.

System Programmer Response: Use IPCS to determine the cause for the ABEND, take the corrective action required, perform an LLA,REFRESH, and reload the failing module using the OS/EM ISPF RELOAD facility. Contact OS/EM support for assistance in problem resolution.

FEMJ3E076

ABEND REGS 12-15: nnnnnnnn nnnnnnnn nnnnnnnn nnnnnnnn

Explanation: The OS/EM has detected a MVS System Abend during execution of an OS/EM optional function or a User exit.

nnnnnnnn: Contents of the General Purpose Register.

Source: FEMJ3ECN

System Action: The OS/EM function being executed continues, OS/EM takes a SVC dump for the abending module, takes the abending module out of service, and deletes the abending module from CSA/ECSA. See messages FEMxxx023, FEMxxx026 and FEMxxx029.

Operator Response: Contact System Programmer.

System Programmer Response: Use IPCS to determine the cause for the ABEND, take the corrective action required, perform an LLA,REFRESH, and reload the failing module using the OS/EM ISPF RELOAD facility. Contact OS/EM support for assistance in problem resolution.

FEMJ3S076

ABEND REGS 12-15: nnnnnnnn nnnnnnnn nnnnnnnn nnnnnnnn

Explanation: The OS/EM has detected a MVS System Abend during execution of an OS/EM optional function or a User exit.

nnnnnnnn: Contents of the General Purpose Register.

Source: FEMJ3SVC

System Action: The OS/EM function being executed continues, OS/EM takes a SVC dump for the abending module, takes the abending module out of service, and deletes the abending module from CSA/ECSA. See messages FEMxxx023, FEMxxx026 and FEMxxx029.

Operator Response: Contact System Programmer.

System Programmer Response: Use IPCS to determine the cause for the ABEND, take the corrective action required, perform an LLA,REFRESH, and reload the failing module using the OS/EM ISPF RELOAD facility. Contact OS/EM support for assistance in problem resolution.

FEMLOK076

ABEND REGS 12-15: nnnnnnnn nnnnnnnn nnnnnnnn nnnnnnnn

Explanation: The OS/EM has detected a MVS System Abend during execution of an OS/EM optional function or a User exit.

nnnnnnnn: Contents of the General Purpose Register.

Source: FEMLOCK

System Action: The OS/EM function being executed continues, OS/EM takes a SVC dump for the abending module, takes the abending module out of service, and deletes the abending module from CSA/ECSA. See messages FEMxxx023, FEMxxx026 and FEMxxx029.

Operator Response: Contact System Programmer.

System Programmer Response: Use IPCS to determine the cause for the ABEND, take the corrective action required, perform an LLA,REFRESH, and reload the failing module using the OS/EM ISPF RELOAD facility. Contact OS/EM support for assistance in problem resolution.

FEMRCN076

ABEND REGS 12-15: nnnnnnnn nnnnnnnn nnnnnnnn nnnnnnnn

Explanation: The OS/EM has detected a MVS System Abend during execution of an OS/EM optional function or a User exit.

nnnnnnnn: Contents of the General Purpose Register.

Source: FEMRACCN

System Action: The OS/EM function being executed continues, OS/EM takes a SVC dump for the abending module, takes the abending module out of service, and deletes the abending module from CSA/ECSA. See messages FEMxxx023, FEMxxx026 and FEMxxx029.

Operator Response: Contact System Programmer.

System Programmer Response: Use IPCS to determine the cause for the ABEND, take the corrective action required, perform an LLA,REFRESH, and reload the failing module using the OS/EM ISPF RELOAD facility. Contact OS/EM support for assistance in problem resolution.

FEMSCN076

ABEND REGS 12-15: nnnnnnnn nnnnnnnn nnnnnnnn nnnnnnnn

Explanation: The OS/EM has detected a MVS System Abend during execution of an OS/EM optional function or a User exit.

nnnnnnnn: Contents of the General Purpose Register.

Source: FEMSAFCN,FEMSMFCN

System Action: The OS/EM function being executed continues, OS/EM takes a SVC dump for the abending module, takes the abending module out of service, and deletes the abending module from CSA/ECSA. See messages FEMxxx023, FEMxxx026 and FEMxxx029.

Operator Response: Contact System Programmer.

System Programmer Response: Use IPCS to determine the cause for the ABEND, take the corrective action required, perform an LLA,REFRESH, and reload the failing module using the OS/EM ISPF RELOAD facility. Contact OS/EM support for assistance in problem resolution.

FEMTCN076

ABEND REGS 12-15: nnnnnnnn nnnnnnnn nnnnnnnn nnnnnnnn

Explanation: The OS/EM has detected a MVS System Abend during execution of an OS/EM optional function or a User exit.

nnnnnnnn: Contents of the General Purpose Register.

Source: FEMTSOCN

System Action: The OS/EM function being executed continues, OS/EM takes a SVC dump for the abending module, takes the abending module out of service, and deletes the abending module from CSA/ECSA. See messages FEMxxx023, FEMxxx026 and FEMxxx029.

Operator Response: Contact System Programmer.

System Programmer Response: Use IPCS to determine the cause for the ABEND, take the corrective action required, perform an LLA,REFRESH, and reload the failing module using the OS/EM ISPF RELOAD facility. Contact OS/EM support for assistance in problem resolution.

FEMTPS076

ABEND REGS 12-15: nnnnnnnn nnnnnnnn nnnnnnnn nnnnnnnn

Explanation: The OS/EM has detected a MVS System Abend during execution of an OS/EM optional function or a User exit.

nnnnnnnn: Contents of the General Purpose Register.

Source: FEMTPSHR

System Action: The OS/EM function being executed continues, OS/EM takes a SVC dump for the abending module, takes the abending module out of service, and deletes the abending module from CSA/ECSA. See messages FEMxxx023, FEMxxx026 and FEMxxx029.

Operator Response: Contact System Programmer.

System Programmer Response: Use IPCS to determine the cause for the ABEND, take the corrective action required, perform an LLA,REFRESH, and reload the failing module using the OS/EM ISPF RELOAD facility. Contact OS/EM support for assistance in problem resolution.

FEMUJI076

ABEND REGS 12-15: nnnnnnnn nnnnnnnn nnnnnnnn nnnnnnnn

Explanation: The OS/EM has detected a MVS System Abend during execution of an OS/EM optional function or a User exit.

nnnnnnnn: Contents of the General Purpose Register.

Source: FEMUJI

System Action: The OS/EM function being executed continues, OS/EM takes a SVC dump for the abending module, takes the abending module out of service, and deletes the abending module from CSA/ECSA. See messages FEMxxx023, FEMxxx026 and FEMxxx029.

Operator Response: Contact System Programmer.

System Programmer Response: Use IPCS to determine the cause for the ABEND, take the corrective action required, perform an LLA,REFRESH, and reload the failing module using the OS/EM ISPF RELOAD facility. Contact OS/EM support for assistance in problem resolution.

FEMUSI076

ABEND REGS 12-15: nnnnnnnn nnnnnnnn nnnnnnnn nnnnnnnn

Explanation: The OS/EM has detected a MVS System Abend during execution of an OS/EM optional function or a User exit.

nnnnnnnn: Contents of the General Purpose Register.

Source: FEMUSI

System Action: The OS/EM function being executed continues, OS/EM takes a SVC dump for the abending module, takes the abending module out of service, and deletes the abending module from CSA/ECSA. See messages FEMxxx023, FEMxxx026 and FEMxxx029.

Operator Response: Contact System Programmer.

System Programmer Response: Use IPCS to determine the cause for the ABEND, take the corrective action required, perform an LLA,REFRESH, and reload the failing module using the OS/EM ISPF RELOAD facility. Contact OS/EM support for assistance in problem resolution.

FEMVCN076

ABEND REGS 12-15: nnnnnnnn nnnnnnnn nnnnnnnn nnnnnnnn

Explanation: The OS/EM has detected a MVS System Abend during execution of an OS/EM optional function or a User exit.

nnnnnnnn: Contents of the General Purpose Register.

Source: FEMSVCCN

System Action: The OS/EM function being executed continues, OS/EM takes a SVC dump for the abending module, takes the abending module out of service, and deletes the abending module from CSA/ECSA. See messages FEMxxx023, FEMxxx026 and FEMxxx029.

Operator Response: Contact System Programmer.

System Programmer Response: Use IPCS to determine the cause for the ABEND, take the corrective action required, perform an LLA,REFRESH, and reload the failing module using the OS/EM ISPF RELOAD facility. Contact OS/EM support for assistance in problem resolution.

FEMX05076

ABEND REGS 12-15: nnnnnnnn nnnnnnnn nnnnnnnn nnnnnnnn

Explanation: The OS/EM has detected a MVS System Abend during execution of an OS/EM optional function or a User exit.

nnnnnnnn: Contents of the General Purpose Register.

Source: FEMJ2X05

System Action: The OS/EM function being executed continues, OS/EM takes a SVC dump for the abending module, takes the abending module out of service, and deletes the abending module from CSA/ECSA. See messages FEMxxx023, FEMxxx026 and FEMxxx029.

Operator Response: Contact System Programmer.

System Programmer Response: Use IPCS to determine the cause for the ABEND, take the corrective action required, perform an LLA,REFRESH, and reload the failing module using the OS/EM ISPF RELOAD facility. Contact OS/EM support for assistance in problem resolution.

FEM02F076

ABEND REGS 12-15: nnnnnnnn nnnnnnnn nnnnnnnn nnnnnnnn

Explanation: The OS/EM has detected a MVS System Abend during execution of an OS/EM optional function or a User exit.

nnnnnnnn: Contents of the General Purpose Register.

Source: FEM0002F

System Action: The OS/EM function being executed continues, OS/EM takes a SVC dump for the abending module, takes the abending module out of service, and deletes the abending module from CSA/ECSA. See messages FEMxxx023, FEMxxx026 and FEMxxx029.

Operator Response: Contact System Programmer.

System Programmer Response: Use IPCS to determine the cause for the ABEND, take the corrective action required, perform an LLA,REFRESH, and reload the failing module using the OS/EM ISPF RELOAD facility. Contact OS/EM support for assistance in problem resolution.

FEMIPL076

ABEND REGS 12-15: nnnnnnnn nnnnnnnn nnnnnnnn nnnnnnnn

Explanation: The OS/EM has detected a MVS System Abend during execution of an OS/EM optional function or a User exit.

nnnnnnnn: Contents of the General Purpose Register.

Source: FEMIPL1

System Action: The OS/EM function being executed continues, OS/EM takes a SVC dump for the abending module, takes the abending module out of service, and deletes the abending module from CSA/ECSA. See messages FEMxxx023, FEMxxx026 and FEMxxx029.

Operator Response: Contact System Programmer.

System Programmer Response: Use IPCS to determine the cause for the ABEND, take the corrective action required, perform an LLA,REFRESH, and reload the failing module using the OS/EM ISPF RELOAD facility. Contact OS/EM support for assistance in problem resolution.

FEM2H5076

ABEND REGS 12-15: nnnnnnnn nnnnnnnn nnnnnnnn nnnnnnnn

Explanation: The OS/EM has detected a MVS System Abend during execution of an OS/EM optional function or a User exit.

nnnnnnnn: Contents of the General Purpose Register.

Source: FEMJ2H5x

System Action: The OS/EM function being executed continues, OS/EM takes a SVC dump for the abending module, takes the abending module out of service, and deletes the abending module from CSA/ECSA. See messages FEMxxx023, FEMxxx026 and FEMxxx029.

Operator Response: Contact System Programmer.

System Programmer Response: Use IPCS to determine the cause for the ABEND, take the corrective action required, perform an LLA,REFRESH, and reload the failing module using the OS/EM ISPF RELOAD facility. Contact OS/EM support for assistance in problem resolution.

FEM2P4076

ABEND REGS 12-15: nnnnnnnn nnnnnnnn nnnnnnnn nnnnnnnn

Explanation: The OS/EM has detected a MVS System Abend during execution of an OS/EM optional function or a User exit.

nnnnnnnn: Contents of the General Purpose Register.

Source: FEMJ2P4x

System Action: The OS/EM function being executed continues, OS/EM takes a SVC dump for the abending module, takes the abending module out of service, and deletes the abending module from CSA/ECSA. See messages FEMxxx023, FEMxxx026 and FEMxxx029.

Operator Response: Contact System Programmer.

System Programmer Response: Use IPCS to determine the cause for the ABEND, take the corrective action required, perform an LLA,REFRESH, and reload the failing module using the OS/EM ISPF RELOAD facility. Contact OS/EM support for assistance in problem resolution.

FEMLOD077

FILE ddname OPEN FAILED

Explanation: An OPEN failed for a user-supplied load library while attempting to load a module from that library. This message is preceded by message FEMLOD017 which will indicate which load module OS/EM was attempting to load.

ddname: The DDNAME of the library that could not be opened.

Source: FEMLOAD

System Action: OS/EM function being executed continues. The requested load module will not be executed.

Operator Response: Contact System Programmer.

System Programmer Response: Verify that the user library specification is correct and the library is available. RELOAD the failing module using the OS/EM ISPF RELOAD facility.

FEMDEL078

MODULE program DELETED (xxxxxxx)

Explanation: User exit program has been deleted from CSA/ECSA. If this message is the result of an ABEND, messages FEMxxx024, FEMxxx029, FEMxxx025 and others may be issued.

program: Exit module name.

xxxxxxx: The load address of the exit module.

Source: FEMDEL

System Action: OS/EM function being executed continues, OS/EM takes a SVC dump for the abending module, takes the abending module out of service, and deletes the abending module from CSA/ECSA. Other messages will accompany this including FEMxxx024, FEMxxx025, and FEMxxx026. The module will show in a NOT LOADED status if a QUERY is done.

Operator Response: If this message is the result of an ABEND, contact the System Programmer.

System Programmer Response: Use IPCS to determine the cause for the ABEND, take the corrective action required, perform an LLA,REFRESH, and RELOAD the failing module using the OS/EM ISPF RELOAD facility.

FEMLOD079

JES2 MODULE HAS INVALID FORMAT

Explanation: During execution of a FEMCNTL command for either loading or reloading a JES2 module the module was found to not meet requirements for a JES2 exit.

Source: FEMLOAD

System Action: The JES2 exit module is not loaded.

Operator Response: None.

System Programmer Response: The JES2 exit does not conform to the requirements for a JES2 exit. Probable errors, the JES2 MIT is either missing or invalid, or the linkedit name is not the same as the \$MODULE name.

FEMLOD080

MODULE AT DIFFERENT LEVEL THAN jes2

Explanation: During either JES2 initialization or the execution of FEMCNTL to load / reload an exit module, the level of the JES2 macros used to assemble the JES2 Offset Table or the user exit are not the same level as the macros used to assemble the JES2 system.

jes2: The Jesname for this JES2 system.

Source: FEMLOAD

System Action: OS/EM initialization fails or the JES2 exit module is not loaded.

Operator Response: None.

System Programmer Response: If this occurs during start up of JES2, the JES2 Offset Table (FEMJ2OFx) was not assembled using the correct SYS1.HASPSRC. To correct this, re-assemble the FEMJ2OFx module using the correct SYS1.HASPSRC and RE-IPL the system. If this occurs with a JES2 user

Alternately, if this occurs with a JES2 user exit, re-assemble the JES2 user exit using the correct SYS1.HASPSRC, perform an LLA,REFRESH and reload the exit using OS/EM ISPF reload facility. Contact OS/EM support for assistance in problem resolution.

FEMLOD081

***WARNING* MODULE program ASSEMBLED WITH DIFFERENT MACRO LEVEL THAN jes2**

Explanation: During either JES2 initialization or the execution of FEMCNTL to load / reload a JES2 exit module, the level of the MVS macros used to assemble the JES2 Offset Table or the user exit are not the same level as the macros used to assemble the JES2 modules.

program: Exit module name.

jes2: The Jesname for this JES2 system.

Source: FEMLOAD

System Action: The JES2 exit module is loaded.

Operator Response: None.

System Programmer Response: If this occurs during start-up of JES2, the JES2 Offset Table (FEMJ2OFx) was not assembled using the correct SYS1.MACLIB. To correct this, re-assemble the FEMJ2OFx module using the correct SYS1.MACLIB.

Alternately, if this occurs with a JES2 user exit, re-assemble the user exit using the correct SYS1.MACLIB, perform a LLA REFRESH and reload the exit using the OS/EM ISPF reload facility. Contact OS/EM support for assistance in problem resolution.

FEMCAL082

ENTRY entryname NOT FOUND IN LOAD MODULE program

Explanation: When using the FEMCNTL command for loading or reloading of an exit module, the \$EXIT statement was not found in User module program specifying the exit entry point.

entryname: The JES2 exit entry point.
program: Exit module name.

Source: FEMECALL

System Action: The JES2 exit module is not loaded.

Operator Response: None.

System Programmer Response: Verify that the exit name specified in the command is the same as that specified on the \$EXIT macro in the JES2 User exit. Correct the User exit program, re-assemble the User exit program, perform a LLA REFRESH and use the OS/EM reload facility to reload the JES2 User exit. Contact OS/EM support for assistance in problem resolution.

FEMHSP082

ENTRY entryname NOT FOUND IN LOAD MODULE program

Explanation: When using the FEMCNTL command for loading or reloading of an exit module, the \$EXIT statement was not found in User module program specifying the exit entry point.

entryname: The JES2 exit entry point.
program: Exit module name.

Source: FEMHJ20

System Action: The JES2 exit module is not loaded.

Operator Response: None.

System Programmer Response: Verify that the exit name specified in the command is the same as that specified on the \$EXIT macro in the JES2 User exit. Correct the User exit program, re-assemble the User exit program, perform a LLA REFRESH and use the OS/EM reload facility to reload the JES2 User exit. Contact OS/EM support for assistance in problem resolution.

FEMJ2J082

ENTRY entryname NOT FOUND IN LOAD MODULE program

Explanation: When using the FEMCNTL command for loading or reloading of an exit module, the \$EXIT statement was not found in User module program specifying the exit entry point.

entryname: The JES2 exit entry point.
program: Exit module name.

Source: FEMJ2JCx

System Action: The JES2 exit module is not loaded.

Operator Response: None.

System Programmer Response: Verify that the exit name specified in the command is the same as that specified on the \$EXIT macro in the JES2 User exit. Correct the User exit program, re-assemble the User exit program, perform a LLA REFRESH and use the OS/EM reload facility to reload the JES2 User exit. Contact OS/EM support for assistance in problem resolution.

FEMLOD082

ENTRY entryname NOT FOUND IN LOAD MODULE program

Explanation: When using the FEMCNTL command for loading or reloading of an exit module, the \$EXIT statement was not found in User module program specifying the exit entry point.

entryname: The JES2 exit entry point.

program: Exit module name.

Source: FEMLOAD

System Action: The JES2 exit module is not loaded.

Operator Response: None.

System Programmer Response: Verify that the exit name specified in the command is the same as that specified on the \$EXIT macro in the JES2 User exit. Correct the User exit program, re-assemble the User exit program, perform a LLA REFRESH and use the OS/EM reload facility to reload the JES2 User exit. Contact OS/EM support for assistance in problem resolution.

FEMREL082

ENTRY entryname NOT FOUND IN LOAD MODULE program

Explanation: When using the FEMCNTL command for loading or reloading of an exit module, the \$EXIT statement was not found in User module program specifying the exit entry point.

entryname: The JES2 exit entry point.

program: Exit module name.

Source: FEMRELOD

System Action: The JES2 exit module is not loaded.

Operator Response: None.

System Programmer Response: Verify that the exit name specified in the command is the same as that specified on the \$EXIT macro in the JES2 User exit. Correct the User exit program, re-assemble the User exit program, perform a LLA REFRESH and use the OS/EM reload facility to reload the JES2 User exit. Contact OS/EM support for assistance in problem resolution.

FEMX00082

ENTRY entryname NOT FOUND IN LOAD MODULE program

Explanation: When using the FEMCNTL command for loading or reloading of an exit module, the \$EXIT statement was not found in User module program specifying the exit entry point.

entryname: The JES2 exit entry point.

program: Exit module name.

Source: FEMJ2X00

System Action: The JES2 exit module is not loaded.

Operator Response: None.

System Programmer Response: Verify that the exit name specified in the command is the same as that specified on the \$EXIT macro in the JES2 User exit. Correct the User exit program, re-assemble the User exit program, perform a LLA REFRESH and use the OS/EM reload facility to reload the JES2 User exit. Contact OS/EM support for assistance in problem resolution.

FEM2TP082

ENTRY entryname NOT FOUND IN LOAD MODULE program

Explanation: When using the FEMCNTL command for loading or reloading of an exit module, the \$EXIT statement was not found in User module program specifying the exit entry point.

entryname: The JES2 exit entry point.

program: Exit module name.

Source: FEMJ2TPx

System Action: The JES2 exit module is not loaded.

Operator Response: None.

System Programmer Response: Verify that the exit name specified in the command is the same as that specified on the \$EXIT macro in the JES2 User exit. Correct the User exit program, re-assemble the User exit program, perform a LLA REFRESH and use the OS/EM reload facility to reload the JES2 User exit. Contact OS/EM support for assistance in problem resolution.

FEMHSP083

OS/EM jjjj INITIALIZATION ERRORS. ENTER 'Y' TO CONTINUE STARTUP, 'N' TO TERMINATE jjjj

Explanation: During the initialization of JES2 or JES3 other errors have occurred that could effect the usability of JES2 or JES3.

jjjj: The subsystem name of the JES system.

Source: FEMHJ20

System Action: The system waits for an Operator response before continuing.

Operator Response: Reply as instructed by the System Programmer.

System Programmer Response: Verify that previous errors that were detected will not effect the integrity of either JES2 or JES3, if this is the case instruct the Operator to reply **Y**, otherwise instruct the Operator to reply **N**. If the reply is **N** refer to the other messages and take the actions as indicated by those messages. Contact OS/EM support for assistance in problem resolution.

FEMIAT083

OS/EM jjjj INITIALIZATION ERRORS. ENTER 'Y' TO CONTINUE STARTUP, 'N' TO TERMINATE jjjj

Explanation: During the initialization of JES2 or JES3 other errors have occurred that could effect the usability of JES2 or JES3.

jjjj: The subsystem name of the JES system.

Source: FEMINTK

System Action: The system waits for an Operator response before continuing.

Operator Response: Reply as instructed by the System Programmer.

System Programmer Response: Verify that previous errors that were detected will not effect the integrity of either JES2 or JES3, if this is the case instruct the Operator to reply **Y**, otherwise instruct the Operator to reply **N**. If the reply is **N** refer to the other messages and take the actions as indicated by those messages. Contact OS/EM support for assistance in problem resolution.

FEMX24083

OS/EM jjjj INITIALIZATION ERRORS. ENTER 'Y' TO CONTINUE STARTUP, 'N' TO TERMINATE jjjj

Explanation: During the initialization of JES2 or JES3 other errors have occurred that could effect the usability of JES2 or JES3.

jjjj: The subsystem name of the JES system.

Source: FEMJ2X24

System Action: The system waits for an Operator response before continuing.

Operator Response: Reply as instructed by the System Programmer.

System Programmer Response: Verify that previous errors that were detected will not effect the integrity of either JES2 or JES3, if this is the case instruct the Operator to reply **Y**, otherwise instruct the Operator to reply **N**. If the reply is **N** refer to the other messages and take the actions as indicated by those messages. Contact OS/EM support for assistance in problem resolution.

FEMREL084

NO EXIT NAME HAS BEEN SPECIFIED

Explanation: During processing of the FEMCNTL command for reloading of an exit module no exit name was specified.

Source: FEMRELOD

System Action: The command is ignored and no exit is loaded.

Operator Response: None.

System Programmer Response: If using the OS/EM ISPF reload facility, verify that a valid module name was specified and re-submit the command. Contact OS/EM support for assistance in problem resolution.

FEMREL085

BACKUP CANNOT BE SPECIFIED FOR OS/EM EXIT

Explanation: During processing of the FEMCNTL command for loading of a OS/EM optional function module the BACKUP keyword was specified.

Source: FEMRELOD

System Action: The BACKUP keyword is ignored.

Operator Response: None.

System Programmer Response: Re-submit the command without the BACKUP keyword. Contact OS/EM support for assistance in problem resolution.

FEMJS2086

PASSWORD TABLE LOADED

Explanation: During processing of the FEMCNTL a JES2 password table was requested to be loaded for surrogate password processing.

Source: FEMJES2B

System Action: The new password table is loaded in ECSA.

Operator Response: None.

System Programmer Response: None.

FEMALC087

ddname DCB OPEN FAILURE

Explanation: During processing of FEMCNTL the ddname indicated failed to open successfully.

ddname: The DDNAME that could not be opened.

Source: FEMALLOC

System Action: The FEMCNTL command being processed is ignored

Operator Response: None.

System Programmer Response: If performing a query, verify that the User can create a dataset named 'USERID.OSEM.QUERY' on UNIT=SYSALLDA. If updating or loading the password table for surrogate password processing table, verify that no other user has control of that dataset. Examine the system log at the time of the failure to locate other standard IBM messages that indicate the exact cause of the open failure. Take appropriate action to correct the reason for the failure.

FEMIPL087

ddname DCB OPEN FAILURE

Explanation: During processing of FEMCNTL the ddname indicated failed to open successfully.

ddname: The DDNAME that could not be opened.

Source: FEMIPL

System Action: The FEMCNTL command being processed is ignored

Operator Response: None.

System Programmer Response: If performing a query, verify that the User can create a dataset named 'USERID.OSEM.QUERY' on UNIT=SYSALLDA. If updating or loading the password table for surrogate password processing table, verify that no other user has control of that dataset. Examine the system log at the time of the failure to locate other standard IBM messages that indicate the exact cause of the open failure. Take appropriate action to correct the reason for the failure.

FEMJS2087

ddname DCB OPEN FAILURE

Explanation: During processing of FEMCNTL the ddname indicated failed to open successfully.

ddname: The DDNAME that could not be opened.

Source: FEMJES2B,FEMJES2G

System Action: The FEMCNTL command being processed is ignored

Operator Response: None.

System Programmer Response: If performing a query, verify that the User can create a dataset named 'USERID.OSEM.QUERY' on UNIT=SYSALLDA. If updating or loading the password table for surrogate password processing table, verify that no other user has control of that dataset. Examine the system log at the time of the failure to locate other standard IBM messages that indicate the exact cause of the open failure. Take appropriate action to correct the reason for the failure.

FEMLIB087

ddname DCB OPEN FAILURE

Explanation: During processing of FEMCNTL the ddname indicated failed to open successfully.

ddname: The DDNAME that could not be opened.

Source: FEMLIB

System Action: The FEMCNTL command being processed is ignored

Operator Response: None.

System Programmer Response: If performing a query, verify that the User can create a dataset named 'USERID.OSEM.QUERY' on UNIT=SYSALLDA. If updating or loading the password table for surrogate password processing table, verify that no other user has control of that dataset. Examine the system log at the time of the failure to locate other standard IBM messages that indicate the exact cause of the open failure. Take appropriate action to correct the reason for the failure.

FEMQRY087

ddname DCB OPEN FAILURE

Explanation: During processing of FEMCNTL the ddname indicated failed to open successfully.

ddname: The DDNAME that could not be opened.

Source: FEMQUERY

System Action: The FEMCNTL command being processed is ignored

Operator Response: None.

System Programmer Response: If performing a query, verify that the User can create a dataset named 'USERID.OSEM.QUERY' on UNIT=SYSALLDA. If updating or loading the password table for surrogate password processing table, verify that no other user has control of that dataset. Examine the system log at the time of the failure to locate other standard IBM messages that indicate the exact cause of the open failure. Take appropriate action to correct the reason for the failure.

FEMTPS087

ddname DCB OPEN FAILURE

Explanation: During processing of FEMCNTL the ddname indicated failed to open successfully.

ddname: The DDNAME that could not be opened.

Source: FEMTPSHR

System Action: The FEMCNTL command being processed is ignored

Operator Response: None.

System Programmer Response: If performing a query, verify that the User can create a dataset named 'USERID.OSEM.QUERY' on UNIT=SYSALLDA. If updating or loading the password table for surrogate password processing table, verify that no other user has control of that dataset. Examine the system log at the time of the failure to locate other standard IBM messages that indicate the exact cause of the open failure. Take appropriate action to correct the reason for the failure.

FEM2M0087

ddname DCB OPEN FAILURE

Explanation: During processing of FEMCNTL the ddname indicated failed to open successfully.

ddname: The DDNAME that could not be opened.

Source: FEMJ2M0x

System Action: The FEMCNTL command being processed is ignored

Operator Response: None.

System Programmer Response: If performing a query, verify that the User can create a dataset named 'USERID.OSEM.QUERY' on UNIT=SYSALLDA. If updating or loading the password table for surrogate password processing table, verify that no other user has control of that dataset. Examine the system log at the time of the failure to locate other standard IBM messages that indicate the exact cause of the open failure. Take appropriate action to correct the reason for the failure.

FEMJS2088

USERID TABLE OVERFLOW

Explanation: During loading of the password table, the password dataset has more entries than can be loaded into the password table in ECSA.

Source: FEMJES2B

System Action: The password table is not loaded.

Operator Response: None.

System Programmer Response: The password table is 32K bytes in size. Contact OS/EM support for assistance in problem resolution.

FEMJ2M089

INVALID RETURN CODE rc FROM jes2 EXITnn (module:entry)

Explanation: The OS/EM controller manager for JES2 has detected that the exit point nn has been passed an invalid return code from the specified user exit.

rc: The return code passed back by the user exit.
jes2: The Jesname of the JES2 System.
nn: JES2 exit number.
module:entry: The load module and entry names of the user exit.

Source: FEMJ2MCx

System Action: The module module:entry for exit point nn is disabled, because the nn exit requested optional valid return code checking or module module:entry returned an invalid return code for exit nn.

Operator Response: Contact System Programmer.

System Programmer Response: Review the JES2 exit module:entry to determine why the exit returned an invalid return code. Correct the JES2 exit module:entry, and reload the JES2 exit with OS/EM reload facilities. Contact OS/EM support for assistance in problem resolution.

FEMJ2S089

INVALID RETURN CODE rc FROM jes2 EXITnn (module:entry)

Explanation: The OS/EM controller manager for JES2 has detected that the exit point nn has been passed an invalid return code from the specified user exit.

rc: The return code passed back by the user exit.
jes2: The Jesname of the JES2 System.
nn: JES2 exit number.
module:entry: The load module and entry names of the user exit.

Source: FEMJ2SCx

System Action: The module module:entry for exit point nn is disabled, because the nn exit requested optional valid return code checking or module module:entry returned an invalid return code for exit nn.

Operator Response: Contact System Programmer.

System Programmer Response: Review the JES2 exit module:entry to determine why the exit returned an invalid return code. Correct the JES2 exit module:entry, and reload the JES2 exit with OS/EM reload facilities. Contact OS/EM support for assistance in problem resolution.

FEMJ2R090

ABEND IN jes2 module(entry) AT OFFSET xxxxx

Explanation: An ABEND has occurred in a JES2 exit

jes2: The Jesname of the JES2 System.
module(entry): The load module and entry name of the exit that had the ABEND.
xxxxx: The offset into the exit where the ABEND occurred.

Source: FEMJ2ERx

System Action: The exit module is disabled and an SVC dump is taken.

Operator Response: Contact System Programmer.

System Programmer Response: Perform the corrective action as indicated by the other messages that accompany this one, perform a LLA, REFRESH and reload the JES2 User exit using the OS/EM ISPF reload facility. Contact OS/EM support for assistance in problem resolution.

FEMJ2M091

name EXIT module DISABLED

Explanation: The specified user exit is disabled, no services will be provided by the effected component.

name: The exit name.

module: The module used for this exit.

Source: FEMJ2MCx

System Action: The exit is disabled.

Operator Response: Contact System Programmer.

System Programmer Response: Check the other messages and take the appropriate action as indicated. Contact OS/EM support for assistance in problem resolution.

FEMJ2S091

name EXIT module DISABLED

Explanation: The specified user exit is disabled, no services will be provided by the effected component.

name: The exit name.

module: The module used for this exit.

Source: FEMJ2SCx

System Action: The exit is disabled.

Operator Response: Contact System Programmer.

System Programmer Response: Check the other messages and take the appropriate action as indicated. Contact OS/EM support for assistance in problem resolution.

FEM02F091

name EXIT module DISABLED

Explanation: The specified user exit is disabled, no services will be provided by the effected component.

name: The exit name.

module: The module used for this exit.

Source: FEM0002F

System Action: The exit is disabled.

Operator Response: Contact System Programmer.

System Programmer Response: Check the other messages and take the appropriate action as indicated. Contact OS/EM support for assistance in problem resolution.

FEMJ2M092

jes2 EXITnn (module:exitname) DEACTIVATED

Explanation: The abend has occurred in JES2 EXITnn User exit module:exitname and the exit point has been deactivated.

jes2: The Jesname of the JES2 System.
nn: JES2 exit number.
module:exitname: Module that abended.

Source: FEMJ2MCx

System Action: The module module:exitname for exit point nn is disabled, a SVC dump is taken and the module:exitname is taken out of service.

Operator Response: Contact System Programmer.

System Programmer Response: Perform the corrective action as indicated by the other messages that accompany this one, perform a LLA, REFRESH and reload the JES2 User exit using the OS/EM ISPF reload facility. Contact OS/EM support for assistance in problem resolution.

FEMJ2S092

jes2 EXITnn (module:exitname) DEACTIVATED

Explanation: The abend has occurred in JES2 EXITnn User exit module:exitname and the exit point has been deactivated.

jes2: The Jesname of the JES2 System.
nn: JES2 exit number.
module:exitname: Module that abended.

Source: FEMJ2SCx

System Action: The module module:exitname for exit point nn is disabled, a SVC dump is taken and the module:exitname is taken out of service.

Operator Response: Contact System Programmer.

System Programmer Response: Perform the corrective action as indicated by the other messages that accompany this one, perform a LLA, REFRESH and reload the JES2 User exit using the OS/EM ISPF reload facility. Contact OS/EM support for assistance in problem resolution.

FEMACN093

SDUMP FAILED IN MODULE module, RC = rc RSN = reason

Explanation: OS/EM controller module attempted to take a SVC dump for a User exit program or a OS/EM optional program and the SDUMP macro failed.

module: The load module name.
rc: Return code.
reason: Reason code.

Source: FEMALCCN

System Action: The SVC dump for the abending module fails and no dump will be taken for the abending exit.

Operator Response: Contact the System Programmer.

System Programmer Response: Review the return codes for the SDUMP macro in Application Development Reference and determine the reason for the failure. Contact OS/EM support for assistance in problem resolution.

FEMALC093

SDUMP FAILED IN MODULE module, RC = rc RSN = reason

Explanation: OS/EM controller module attempted to take a SVC dump for a User exit program or a OS/EM optional program and the SDUMP macro failed.

module: The load module name.
rc: Return code.
reason: Reason code.

Source: FEMALLOC

System Action: The SVC dump for the abending module fails and no dump will be taken for the abending exit.

Operator Response: Contact the System Programmer.

System Programmer Response: Review the return codes for the SDUMP macro in Application Development Reference and determine the reason for the failure. Contact OS/EM support for assistance in problem resolution.

FEMASY093

SDUMP FAILED IN MODULE module, RC = rc RSN = reason

Explanation: OS/EM controller module attempted to take a SVC dump for a User exit program or a OS/EM optional program and the SDUMP macro failed.

module: The load module name.
rc: Return code.
reason: Reason code.

Source: FEMASYNC

System Action: The SVC dump for the abending module fails and no dump will be taken for the abending exit.

Operator Response: Contact the System Programmer.

System Programmer Response: Review the return codes for the SDUMP macro in Application Development Reference and determine the reason for the failure. Contact OS/EM support for assistance in problem resolution.

FEMCMD093

SDUMP FAILED IN MODULE module, RC = rc RSN = reason

Explanation: OS/EM controller module attempted to take a SVC dump for a User exit program or a OS/EM optional program and the SDUMP macro failed.

module: The load module name.
rc: Return code.
reason: Reason code.

Source: FEMCMD

System Action: The SVC dump for the abending module fails and no dump will be taken for the abending exit.

Operator Response: Contact the System Programmer.

System Programmer Response: Review the return codes for the SDUMP macro in Application Development Reference and determine the reason for the failure. Contact OS/EM support for assistance in problem resolution.

FEMCOM093

SDUMP FAILED IN MODULE *module*, RC = *rc* RSN = *reason*

Explanation: OS/EM controller module attempted to take a SVC dump for a User exit program or a OS/EM optional program and the SDUMP macro failed.

module: The load module name.

rc: Return code.

reason: Reason code.

Source: FEMCOMM

System Action: The SVC dump for the abending module fails and no dump will be taken for the abending exit.

Operator Response: Contact the System Programmer.

System Programmer Response: Review the return codes for the SDUMP macro in Application Development Reference and determine the reason for the failure. Contact OS/EM support for assistance in problem resolution.

FEMDCN093

SDUMP FAILED IN MODULE *module*, RC = *rc* RSN = *reason*

Explanation: OS/EM controller module attempted to take a SVC dump for a User exit program or a OS/EM optional program and the SDUMP macro failed.

module: The load module name.

rc: Return code.

reason: Reason code.

Source: FEMDADCN

System Action: The SVC dump for the abending module fails and no dump will be taken for the abending exit.

Operator Response: Contact the System Programmer.

System Programmer Response: Review the return codes for the SDUMP macro in Application Development Reference and determine the reason for the failure. Contact OS/EM support for assistance in problem resolution.

FEMDCI093

SDUMP FAILED IN MODULE *module*, RC = *rc* RSN = *reason*

Explanation: OS/EM controller module attempted to take a SVC dump for a User exit program or a OS/EM optional program and the SDUMP macro failed.

module: The load module name.

rc: Return code.
reason: Reason code.

Source: FEMDCB1

System Action: The SVC dump for the abending module fails and no dump will be taken for the abending exit.

Operator Response: Contact the System Programmer.

System Programmer Response: Review the return codes for the SDUMP macro in Application Development Reference and determine the reason for the failure. Contact OS/EM support for assistance in problem resolution.

FEMEXR093

SDUMP FAILED IN MODULE module, RC = rc RSN = reason

Explanation: OS/EM controller module attempted to take a SVC dump for a User exit program or a OS/EM optional program and the SDUMP macro failed.

module: The load module name.
rc: Return code.
reason: Reason code.

Source: FEMEXRTN

System Action: The SVC dump for the abending module fails and no dump will be taken for the abending exit.

Operator Response: Contact the System Programmer.

System Programmer Response: Review the return codes for the SDUMP macro in Application Development Reference and determine the reason for the failure. Contact OS/EM support for assistance in problem resolution.

FEMFRA093

SDUMP FAILED IN MODULE module, RC = rc RSN = reason

Explanation: OS/EM controller module attempted to take a SVC dump for a User exit program or a OS/EM optional program and the SDUMP macro failed.

module: The load module name.
rc: Return code.
reason: Reason code.

Source: FEMFRACN

System Action: The SVC dump for the abending module fails and no dump will be taken for the abending exit.

Operator Response: Contact the System Programmer.

System Programmer Response: Review the return codes for the SDUMP macro in Application Development Reference and determine the reason for the failure. Contact OS/EM support for assistance in problem resolution.

FEMFTN093

SDUMP FAILED IN MODULE module, RC = rc RSN = reason

Explanation: OS/EM controller module attempted to take a SVC dump for a User exit program or a OS/EM optional program and the SDUMP macro failed.

module: The load module name.

rc: Return code.

reason: Reason code.

Source: FEMFRRTN

System Action: The SVC dump for the abending module fails and no dump will be taken for the abending exit.

Operator Response: Contact the System Programmer.

System Programmer Response: Review the return codes for the SDUMP macro in Application Development Reference and determine the reason for the failure. Contact OS/EM support for assistance in problem resolution.

FEMHCN093

SDUMP FAILED IN MODULE module, RC = rc RSN = reason

Explanation: OS/EM controller module attempted to take a SVC dump for a User exit program or a OS/EM optional program and the SDUMP macro failed.

module: The load module name.

rc: Return code.

reason: Reason code.

Source: FEMHSMCN

System Action: The SVC dump for the abending module fails and no dump will be taken for the abending exit.

Operator Response: Contact the System Programmer.

System Programmer Response: Review the return codes for the SDUMP macro in Application Development Reference and determine the reason for the failure. Contact OS/EM support for assistance in problem resolution.

FEMIAT093

SDUMP FAILED IN MODULE module, RC = rc RSN = reason

Explanation: OS/EM controller module attempted to take a SVC dump for a User exit program or a OS/EM optional program and the SDUMP macro failed.

module: The load module name.

rc: Return code.

reason: Reason code.

Source: FEMINTK

System Action: The SVC dump for the abending module fails and no dump will be taken for the abending exit.

Operator Response: Contact the System Programmer.

System Programmer Response: Review the return codes for the SDUMP macro in Application Development Reference and determine the reason for the failure. Contact OS/EM support for assistance in problem resolution.

FEMICN093

SDUMP FAILED IN MODULE module, RC = rc RSN = reason

Explanation: OS/EM controller module attempted to take a SVC dump for a User exit program or a OS/EM optional program and the SDUMP macro failed.

module: The load module name.
rc: Return code.
reason: Reason code.

Source: FEMISPCN

System Action: The SVC dump for the abending module fails and no dump will be taken for the abending exit.

Operator Response: Contact the System Programmer.

System Programmer Response: Review the return codes for the SDUMP macro in Application Development Reference and determine the reason for the failure. Contact OS/EM support for assistance in problem resolution.

FEMIPL093

SDUMP FAILED IN MODULE module, RC = rc RSN = reason

Explanation: OS/EM controller module attempted to take a SVC dump for a User exit program or a OS/EM optional program and the SDUMP macro failed.

module: The load module name.
rc: Return code.
reason: Reason code.

Source: FEMIPL

System Action: The SVC dump for the abending module fails and no dump will be taken for the abending exit.

Operator Response: Contact the System Programmer.

System Programmer Response: Review the return codes for the SDUMP macro in Application Development Reference and determine the reason for the failure. Contact OS/EM support for assistance in problem resolution.

FEMJS2093

SDUMP FAILED IN MODULE module, RC = rc RSN = reason

Explanation: OS/EM controller module attempted to take a SVC dump for a User exit program or a OS/EM optional program and the SDUMP macro failed.

module: The load module name.
rc: Return code.
reason: Reason code.

Source: FEMJES2B,FEMJES2G

System Action: The SVC dump for the abending module fails and no dump will be taken for the abending exit.

Operator Response: Contact the System Programmer.

System Programmer Response: Review the return codes for the SDUMP macro in Application Development Reference and determine the reason for the failure. Contact OS/EM support for assistance in problem resolution.

FEMJ2M093

SDUMP FAILED IN MODULE module, RC = rc RSN = reason

Explanation: OS/EM controller module attempted to take a SVC dump for a User exit program or a OS/EM optional program and the SDUMP macro failed.

module: The load module name.
rc: Return code.
reason: Reason code.

Source: FEMJ2MCx

System Action: The SVC dump for the abending module fails and no dump will be taken for the abending exit.

Operator Response: Contact the System Programmer.

System Programmer Response: Review the return codes for the SDUMP macro in Application Development Reference and determine the reason for the failure. Contact OS/EM support for assistance in problem resolution.

FEMJ2R093

SDUMP FAILED IN MODULE module, RC = rc RSN = reason

Explanation: OS/EM controller module attempted to take a SVC dump for a User exit program or a OS/EM optional program and the SDUMP macro failed.

module: The load module name.
rc: Return code.
reason: Reason code.

Source: FEMJ2ERx

System Action: The SVC dump for the abending module fails and no dump will be taken for the abending exit.

Operator Response: Contact the System Programmer.

System Programmer Response: Review the return codes for the SDUMP macro in Application Development Reference and determine the reason for the failure. Contact OS/EM support for assistance in problem resolution.

FEMJ2S093

SDUMP FAILED IN MODULE module, RC = rc RSN = reason

Explanation: OS/EM controller module attempted to take a SVC dump for a User exit program or a OS/EM optional program and the SDUMP macro failed.

module: The load module name.

rc: Return code.
reason: Reason code.

Source: FEMJ2SCx

System Action: The SVC dump for the abending module fails and no dump will be taken for the abending exit.

Operator Response: Contact the System Programmer.

System Programmer Response: Review the return codes for the SDUMP macro in Application Development Reference and determine the reason for the failure. Contact OS/EM support for assistance in problem resolution.

FEMJ3E093

SDUMP FAILED IN MODULE module, RC = rc RSN = reason

Explanation: OS/EM controller module attempted to take a SVC dump for a User exit program or a OS/EM optional program and the SDUMP macro failed.

module: The load module name.
rc: Return code.
reason: Reason code.

Source: FEMJ3ECx

System Action: The SVC dump for the abending module fails and no dump will be taken for the abending exit.

Operator Response: Contact the System Programmer.

System Programmer Response: Review the return codes for the SDUMP macro in Application Development Reference and determine the reason for the failure. Contact OS/EM support for assistance in problem resolution.

FEMJ3S093

SDUMP FAILED IN MODULE module, RC = rc RSN = reason

Explanation: OS/EM controller module attempted to take a SVC dump for a User exit program or a OS/EM optional program and the SDUMP macro failed.

module: The load module name.
rc: Return code.
reason: Reason code.

Source: FEMJ3SVC

System Action: The SVC dump for the abending module fails and no dump will be taken for the abending exit.

Operator Response: Contact the System Programmer.

System Programmer Response: Review the return codes for the SDUMP macro in Application Development Reference and determine the reason for the failure. Contact OS/EM support for assistance in problem resolution.

FEMLOK093

SDUMP FAILED IN MODULE module, RC = rc RSN = reason

Explanation: OS/EM controller module attempted to take a SVC dump for a User exit program or a OS/EM optional program and the SDUMP macro failed.

module: The load module name.

rc: Return code.

reason: Reason code.

Source: FEMLOCK

System Action: The SVC dump for the abending module fails and no dump will be taken for the abending exit.

Operator Response: Contact the System Programmer.

System Programmer Response: Review the return codes for the SDUMP macro in Application Development Reference and determine the reason for the failure. Contact OS/EM support for assistance in problem resolution.

FEMRCN093

SDUMP FAILED IN MODULE module, RC = rc RSN = reason

Explanation: OS/EM controller module attempted to take a SVC dump for a User exit program or a OS/EM optional program and the SDUMP macro failed.

module: The load module name.

rc: Return code.

reason: Reason code.

Source: FEMRACCN

System Action: The SVC dump for the abending module fails and no dump will be taken for the abending exit.

Operator Response: Contact the System Programmer.

System Programmer Response: Review the return codes for the SDUMP macro in Application Development Reference and determine the reason for the failure. Contact OS/EM support for assistance in problem resolution.

FEMSCN093

SDUMP FAILED IN MODULE module, RC = rc RSN = reason

Explanation: OS/EM controller module attempted to take a SVC dump for a User exit program or a OS/EM optional program and the SDUMP macro failed.

module: The load module name.

rc: Return code.

reason: Reason code.

Source: FEMSAFCN,FEMSMFCN

System Action: The SVC dump for the abending module fails and no dump will be taken for the abending exit.

Operator Response: Contact the System Programmer.

System Programmer Response: Review the return codes for the SDUMP macro in Application Development Reference and determine the reason for the failure. Contact OS/EM support for assistance in problem resolution.

FEMTCN093

SDUMP FAILED IN MODULE module, RC = rc RSN = reason

Explanation: OS/EM controller module attempted to take a SVC dump for a User exit program or a OS/EM optional program and the SDUMP macro failed.

module: The load module name.
rc: Return code.
reason: Reason code.

Source: FEMTSOCN

System Action: The SVC dump for the abending module fails and no dump will be taken for the abending exit.

Operator Response: Contact the System Programmer.

System Programmer Response: Review the return codes for the SDUMP macro in Application Development Reference and determine the reason for the failure. Contact OS/EM support for assistance in problem resolution.

FEMTHI093

SDUMP FAILED IN MODULE module, RC = rc RSN = reason

Explanation: OS/EM controller module attempted to take a SVC dump for a User exit program or a OS/EM optional program and the SDUMP macro failed.

module: The load module name.
rc: Return code.
reason: Reason code.

Source: FEMTHRDI

System Action: The SVC dump for the abending module fails and no dump will be taken for the abending exit.

Operator Response: Contact the System Programmer.

System Programmer Response: Review the return codes for the SDUMP macro in Application Development Reference and determine the reason for the failure. Contact OS/EM support for assistance in problem resolution.

FEMTPS093

SDUMP FAILED IN MODULE module, RC = rc RSN = reason

Explanation: OS/EM controller module attempted to take a SVC dump for a User exit program or a OS/EM optional program and the SDUMP macro failed.

module: The load module name.
rc: Return code.
reason: Reason code.

Source: FEMTPSHR

System Action: The SVC dump for the abending module fails and no dump will be taken for the abending exit.

Operator Response: Contact the System Programmer.

System Programmer Response: Review the return codes for the SDUMP macro in Application Development Reference and determine the reason for the failure. Contact OS/EM support for assistance in problem resolution.

FEMUJI093

SDUMP FAILED IN MODULE *module*, RC = *rc* RSN = *reason*

Explanation: OS/EM controller module attempted to take a SVC dump for a User exit program or a OS/EM optional program and the SDUMP macro failed.

module: The load module name.
rc: Return code.
reason: Reason code.

Source: FEMUJI

System Action: The SVC dump for the abending module fails and no dump will be taken for the abending exit.

Operator Response: Contact the System Programmer.

System Programmer Response: Review the return codes for the SDUMP macro in Application Development Reference and determine the reason for the failure. Contact OS/EM support for assistance in problem resolution.

FEMUSI093

SDUMP FAILED IN MODULE *module*, RC = *rc* RSN = *reason*

Explanation: OS/EM controller module attempted to take a SVC dump for a User exit program or a OS/EM optional program and the SDUMP macro failed.

module: The load module name.
rc: Return code.
reason: Reason code.

Source: FEMUSI

System Action: The SVC dump for the abending module fails and no dump will be taken for the abending exit.

Operator Response: Contact the System Programmer.

System Programmer Response: Review the return codes for the SDUMP macro in Application Development Reference and determine the reason for the failure. Contact OS/EM support for assistance in problem resolution.

FEMVCN093

SDUMP FAILED IN MODULE *module*, RC = *rc* RSN = *reason*

Explanation: OS/EM controller module attempted to take a SVC dump for a User exit program or a OS/EM optional program and the SDUMP macro failed.

module: The load module name.

rc: Return code.
reason: Reason code.

Source: FEMSVCCN

System Action: The SVC dump for the abending module fails and no dump will be taken for the abending exit.

Operator Response: Contact the System Programmer.

System Programmer Response: Review the return codes for the SDUMP macro in Application Development Reference and determine the reason for the failure. Contact OS/EM support for assistance in problem resolution.

FEMX05093

SDUMP FAILED IN MODULE module, RC = rc RSN = reason

Explanation: OS/EM controller module attempted to take a SVC dump for a User exit program or a OS/EM optional program and the SDUMP macro failed.

module: The load module name.
rc: Return code.
reason: Reason code.

Source: FEMJ2X05

System Action: The SVC dump for the abending module fails and no dump will be taken for the abending exit.

Operator Response: Contact the System Programmer.

System Programmer Response: Review the return codes for the SDUMP macro in Application Development Reference and determine the reason for the failure. Contact OS/EM support for assistance in problem resolution.

FEM1PL093

SDUMP FAILED IN MODULE module, RC = rc RSN = reason

Explanation: OS/EM controller module attempted to take a SVC dump for a User exit program or a OS/EM optional program and the SDUMP macro failed.

module: The load module name.
rc: Return code.
reason: Reason code.

Source: FEM1PL1

System Action: The SVC dump for the abending module fails and no dump will be taken for the abending exit.

Operator Response: Contact the System Programmer.

System Programmer Response: Review the return codes for the SDUMP macro in Application Development Reference and determine the reason for the failure. Contact OS/EM support for assistance in problem resolution.

FEM02F093

SDUMP FAILED IN MODULE *module*, RC = *rc* RSN = *reason*

Explanation: OS/EM controller module attempted to take a SVC dump for a User exit program or a OS/EM optional program and the SDUMP macro failed.

module: The load module name.

rc: Return code.

reason: Reason code.

Source: FEM0002F

System Action: The SVC dump for the abending module fails and no dump will be taken for the abending exit.

Operator Response: Contact the System Programmer.

System Programmer Response: Review the return codes for the SDUMP macro in Application Development Reference and determine the reason for the failure. Contact OS/EM support for assistance in problem resolution.

FEM2H5093

SDUMP FAILED IN MODULE *module*, RC = *rc* RSN = *reason*

Explanation: OS/EM controller module attempted to take a SVC dump for a User exit program or a OS/EM optional program and the SDUMP macro failed.

module: The load module name.

rc: Return code.

reason: Reason code.

Source: FEMJ2H5x

System Action: The SVC dump for the abending module fails and no dump will be taken for the abending exit.

Operator Response: Contact the System Programmer.

System Programmer Response: Review the return codes for the SDUMP macro in Application Development Reference and determine the reason for the failure. Contact OS/EM support for assistance in problem resolution.

FEMDAP094

NO OPERANDS PERMITTED WITH *type* DELETE

Explanation: The FEMCNTL command for Quick Pool has been passed a delete request for either a volume group, a dataset name group or a Quick Pool definition. No other operands are allowed on a delete.

type:

DSNGROUP group name

VOLGROUP group name

POOL pool name

Source: FEMPOOL

System Action: The command is ignored, and the group is not deleted.

Operator Response: None.

System Programmer Response: Correct the FEMCNTL command so that no other operands are specified. If using the the ISPF interface verify that no other operands are specified for the definition being deleted. Contact OS/EM support for assistance in problem resolution.

FEMACT096

JOB jobname ABENDED TIME = hh.mm.ss, DATE = mm/dd/yy

Explanation: The OS/EM optional ABEND MESSAGE has been requested for Jobs that Abend in this Jobclass.

jobname: Jobname.
hh.mm.ss: Time in hours, minutes and seconds.
mm/dd/yy: Date in month, day and year.

Source: FEMACTRT

System Action: This message is left in a Non-deletable mode for the Operator to take appropriate action.

Operator Response: Notify the person responsible for running the Job that it has Abended, and delete the message from the console.

System Programmer Response: None.

FEMACT097

jobname/jobstep/sss/program COND = rc

Explanation: The OS/EM optional STEPENDWTO has been requested for Jobs.

jobname: Jobname.
jobstep: Job step name.
sss: Proc step name.
program: Program name.
rc: Return Code for this step.

Source: FEMACTRT

System Action: Job continues, Information only.

Operator Response: None.

System Programmer Response: None.

FEMACT098

JOB jobname WAS CANCELED BECAUSE -

Explanation: The OS/EM optional CANCEL WTOR has been requested for Jobs that are cancelled by the Operator in this Jobclass.

jobname: Jobname.

Source: FEMACTRT

System Action: Job waits for the reply from the Operator.

Operator Response: Reply with the reason as to why the Job was cancelled.

System Programmer Response: None.

FEMACT099

JOB jobname CANCELED DUE TO NOT CATALOGED 2

Explanation: The OS/EM optional NOT CATALOGED 2 feature is active in FAIL mode, and this job has created a dataset with the NOT CATALOGED 2 condition, and the option in effect for the NOT CATALOGED 2 condition is to cancel the Job.

jobname: Jobname.

Source: FEMACTRT

System Action: The Job is cancelled.

Operator Response: None.

System Programmer Response: None.

User Response: Correct the JCL, or delete and uncatalog the dataset at the beginning of the Job.

FEMX06100

USER userid NOT AUTHORIZED TO USE function PARM 'value'

Explanation: The OS/EM optional facilities for checking JCL parameters has been requested and the User does not have access to both the function and the value specified. Other messages from optional RACROUTE checking with an external security system may also appear i.e. ICH for RACF etc. The actual resource type checked if using an optional external security system is: **function.value**.

userid: Userid that is not authorized.

function: OS/EM optional resource type to be checked.

value: Value of the resource to be checked.

Source: FEMJ2X06

System Action: The Job is cancelled during reader/interpreter processing.

Operator Response: None.

System Programmer Response: None.

User Response: Resubmit the Job using a resource type that you have access to. If other messages appear ICH for RACF or other security facility messages (CA-TOPSECRET, or CA-ACF2), contact Security Administration and request that you be granted access to the resource and value in this message. Else contact the System programmer and request that you be granted access to the resource and value in this message.

FEMACN101

sssssss EXIT INVALID RETURN CODE rc FROM program

Explanation: The OS/EM controller manager has detected that the exit point ssssss has been passed return code rc from module program and it was not a valid return code.

sssssss: MVS Exit point.

rc: Return code.

program: Module that set the invalid return code.

Source: FEMALCCN

System Action: The module program for exit point sssssss is disabled, because the ssssss exit requested optional valid return code checking or module ppppppp returned an invalid return code for exit sssssss.

Operator Response: Contact System Programmer.

System Programmer Response: Review the User exit program to determine why the exit returned an invalid return code. Correct the User exit program, and reload the USer exit with OS/EM reload facilities.

FEMDCN101

sssssss EXIT INVALID RETURN CODE rc FROM program

Explanation: The OS/EM controller manager has detected that the exit point ssssss has been passed return code rc from module program and it was not a valid return code.

sssssss: MVS Exit point.

rc: Return code.

program: Module that set the invalid return code.

Source: FEMDADCN

System Action: The module program for exit point sssssss is disabled, because the ssssss exit requested optional valid return code checking or module ppppppp returned an invalid return code for exit sssssss.

Operator Response: Contact System Programmer.

System Programmer Response: Review the User exit program to determine why the exit returned an invalid return code. Correct the User exit program, and reload the USer exit with OS/EM reload facilities.

FEMFRA101

sssssss EXIT INVALID RETURN CODE rc FROM program

Explanation: The OS/EM controller manager has detected that the exit point ssssss has been passed return code rc from module program and it was not a valid return code.

sssssss: MVS Exit point.

rc: Return code.

program: Module that set the invalid return code.

Source: FEMFRACN

System Action: The module program for exit point sssssss is disabled, because the ssssss exit requested optional valid return code checking or module ppppppp returned an invalid return code for exit sssssss.

Operator Response: Contact System Programmer.

System Programmer Response: Review the User exit program to determine why the exit returned an invalid return code. Correct the User exit program, and reload the USer exit with OS/EM reload facilities.

FEMHCN101

sssssss EXIT INVALID RETURN CODE rc FROM program

Explanation: The OS/EM controller manager has detected that the exit point ssssss has been passed return code rc from module program and it was not a valid return code.

sssssss: MVS Exit point.

rc: Return code.

program: Module that set the invalid return code.

Source: FEMHSMCN

System Action: The module program for exit point ssssssss is disabled, because the ssssss exit requested optional valid return code checking or module ppppppp returned an invalid return code for exit ssssssss.

Operator Response: Contact System Programmer.

System Programmer Response: Review the User exit program to determine why the exit returned an invalid return code. Correct the User exit program, and reload the USer exit with OS/EM reload facilities.

FEMICN101

sssssss EXIT INVALID RETURN CODE rc FROM program

Explanation: The OS/EM controller manager has detected that the exit point ssssss has been passed return code rc from module program and it was not a valid return code.

sssssss: MVS Exit point.

rc: Return code.

program: Module that set the invalid return code.

Source: FEMISPCN

System Action: The module program for exit point ssssssss is disabled, because the ssssss exit requested optional valid return code checking or module ppppppp returned an invalid return code for exit ssssssss.

Operator Response: Contact System Programmer.

System Programmer Response: Review the User exit program to determine why the exit returned an invalid return code. Correct the User exit program, and reload the USer exit with OS/EM reload facilities.

FEMRCN101

sssssss EXIT INVALID RETURN CODE rc FROM program

Explanation: The OS/EM controller manager has detected that the exit point ssssss has been passed return code rc from module program and it was not a valid return code.

sssssss: MVS Exit point.

rc: Return code.

program: Module that set the invalid return code.

Source: FEMRACCN

System Action: The module program for exit point ssssssss is disabled, because the ssssss exit requested optional valid return code checking or module ppppppp returned an invalid return code for exit ssssssss.

Operator Response: Contact System Programmer.

System Programmer Response: Review the User exit program to determine why the exit returned an invalid return code. Correct the User exit program, and reload the User exit with OS/EM reload facilities.

FEMSCN101

sssssss EXIT INVALID RETURN CODE rc FROM program

Explanation: The OS/EM controller manager has detected that the exit point ssssss has been passed return code rc from module program and it was not a valid return code.

sssssss: MVS Exit point.

rc: Return code.

program: Module that set the invalid return code.

Source: FEMSAFCN,FEMSMFCN

System Action: The module program for exit point ssssssss is disabled, because the ssssss exit requested optional valid return code checking or module ppppppp returned an invalid return code for exit ssssssss.

Operator Response: Contact System Programmer.

System Programmer Response: Review the User exit program to determine why the exit returned an invalid return code. Correct the User exit program, and reload the User exit with OS/EM reload facilities.

FEMTCN101

sssssss EXIT INVALID RETURN CODE rc FROM program

Explanation: The OS/EM controller manager has detected that the exit point ssssss has been passed return code rc from module program and it was not a valid return code.

sssssss: MVS Exit point.

rc: Return code.

program: Module that set the invalid return code.

Source: FEMTSOCN

System Action: The module program for exit point ssssssss is disabled, because the ssssss exit requested optional valid return code checking or module ppppppp returned an invalid return code for exit ssssssss.

Operator Response: Contact System Programmer.

System Programmer Response: Review the User exit program to determine why the exit returned an invalid return code. Correct the User exit program, and reload the User exit with OS/EM reload facilities.

FEMJ3E102

JES3 EXIT nn INVALID RETURN CODE rc FROM program

Explanation: The OS/EM JES3 exit controller has detected that JES3 nn exit point has been passed return code rc from module program.

nn: JES3 exit number.

rc: Return code.

program: Module that set the invalid return code.

Source: FEMJ3ECN

System Action: The module program in JES3 exit point nn is disabled, because the JES3 exit nn requested optional valid return code checking or module ppppppp returned an invalid return code for JES3 exit nn.

Operator Response: Contact System Programmer.

System Programmer Response: Review the JES3 exit program to determine why the exit returned an invalid return code. Correct the JES3 exit program, and reload the JES3 exit with OS/EM reload facilities.

FEM02F103

***WARNING* JOB WOULD FAIL FOR NOT CATALOGED 2**

Explanation: The OS/EM optional NOT CATALOGED 2 feature is active in WARN mode, and this job has created a dataset with the NOT CATALOGED 2 condition. If OS/EM optional NOT CATALOGED 2 feature is implemented in fail mode, the Job would be cancelled.

Source: FEM0002F.

System Action: The Job continues creating an uncataloged dataset.

Operator Response: None.

System Programmer Response: None.

User Response: Correct the JCL, or delete and uncatalog the dataset at the beginning of the Job.

FEMREL104

NO OS/EM FUNCTIONS ACTIVE - MODULE NOT LOADED

Explanation: A optional OS/EM module was requested to be reloaded, using the OS/EM reload facility but the module was not previously loaded.

Source: FEMRELOD

System Action: The module is not reloaded because there are have been no optional OS/EM features selected, that require the module selected for reload to be present.

Operator Response: None.

System Programmer Response: None.

FEMDB4105

***WARNING* DYNAMIC ALLOCATION WOULD FAIL**

Explanation: The OS/EM optional tape control by Jobclass is active in WARN mode, and this job has exceeded the number of tape devices allowed in this Jobclass. Also see message FEMxxx038. If OS/EM tape control by Jobclass is implemented in fail mode, the Job would be cancelled.

Source: FEMDB401

System Action: Allocation continues.

Operator Response: None.

System Programmer Response: None.

User Response: Submit the Job in a class that allows the the number of tape devices required.

FEMF10106

USER userid NOT DEFINED TO RACF - SUBMIT DISALLOWED

Explanation: During TSO SUBMIT processing, OS/EM options have requested verification of the USERID on the JOBCARD and the USERID that is specified on the JOB card is not a valid RACF USER.

userid: Userid that is not defined to RACF.

Source: FEMEFF10

System Action: The JOB submission is stopped.

Operator Response: None.

System Programmer Response: None.

User Response: Code a valid RACF USERID on the JOBCARD and re-submit the JOB.

FEMF10107

USER userid NOT AUTHORIZED TO SUBMIT JOBS IN CLASS x

Explanation: During TSO SUBMIT processing, OS/EM options have requested Jobclass access enforcement and the Jobclass that is specified on the JOB card is not a valid Jobclass for the USER submitting the JOB.

userid: Userid that is not authorized.

x: Jobclass Job is being submitted to.

Source: FEMEFF10

System Action: The JOB submission is stopped.

Operator Response: None.

System Programmer Response: None.

User Response: Change the Jobclass to one that the USER has access to.

FEMF10108

JOBNAME MUST START WITH USERID

Explanation: During TSO SUBMIT processing, OS/EM options have requested enforcement of Jobname standards, and the first characters of the Jobname must contain the USERID of the USER submitting the JOB.

Source: FEMEFF10

System Action: The JOB submission is stopped.

Operator Response: None.

System Programmer Response: None.

User Response: Change the Jobname to include the USERID of the USER submitting the Job.

FEMX02109

UNABLE TO ADD USERID/PASSWORD TO JOBCARD

Explanation: During TSO SUBMIT processing, OS/EM options have requested that the USERID and/or PASSWORD parameter(s) be added to all Jobs and the USERID and/or PASSWORD parameter(s) cannot be added to the Jobcard because the account number continues into column 71 and there is no room to add a comma to continue the Jobcard.

Source: FEMJ2X02

System Action: The JOB submission continues without the USERID and/or PASSWORD parameter(s) being added to the Jobcard.

Operator Response: None.

System Programmer Response: None.

User Response: None.

FEMF10110

UNABLE TO ADD NOTIFY PARAMETER

Explanation: During TSO SUBMIT processing, OS/EM options have requested that the NOTIFY parameter be added to all Jobs. The NOTIFY parameter cannot be added to the Jobcard because the account number continues into column 71, and there is no room to add a comma to continue the Jobcard.

Source: FEMEFF10

System Action: The JOB submission continues without the NOTIFY parameter being added to the Jobcard.

Operator Response: None.

System Programmer Response: None.

User Response: None.

FEMF10111

USER userid NOT AUTHORIZED TO ISSUE cmd COMMAND

Explanation: During TSO SUBMIT processing, OS/EM options have requested that the input data be scanned for imbedded MVS Commands, and the USERID on the Job being submitted is not authorized to issue MVS commands.

userid: Userid that is not authorized.

cmd: The MVS command that is not authorized.

Source: FEMEFF10

System Action: The JOB submission stops.

Operator Response: None.

System Programmer Response: None.

User Response: Remove the MVS command from the Job and re-submit the Job.

FEMF10112

USER userid NOT AUTHORIZED TO ISSUE cmd JES2 COMMAND

Explanation: During TSO SUBMIT processing, OS/EM options have requested that the input data be scanned for imbedded JES2 Commands, and the USERID on the Job being submitted is not authorized to issue JES2 commands.

userid: Userid that is not authorized.

cmd: The JES2 command that is not authorized.

Source: FEMEFF10

System Action: The JOB submission stops.

Operator Response: None.

System Programmer Response: None.

User Response: Remove the JES2 command from the Job and re-submit the Job.

FEMJ3S113

JES3 EXIT nn NOT {RE}LOADED

Explanation: During the execution of a FEMCNTL command for either the loading or reloading of JES3 exit number nn an error condition has stopped the command from completing successfully.

nn: JES3 exit number.

Source: FEMJ3SVC

System Action: The FEMCNTL fails and the JES3 exit nn is not loaded or reloaded.

Operator Response: None.

System Programmer Response: Other messages will follow FEMxxx013, and FEMxxx017. Message FEMxxx013 will give the reason for either the LOAD or RELOAD failure. Take the corrective action as indicated by FEMxxx013 and re-issue the command. Contact OS/EM support for assistance in problem resolution.

FEMUTL114

SHOULD JOB jobname type CPU LIMIT BE EXTENDED nnnn SECONDS ? (Y OR N)

Explanation: The JOB CPU time limit for JOB jobname has expired, and the options selected for OS/EM require a confirmation by the operator to extend the JOB jobname CPU time.

jobname: JOBNAME.

type: JOB, STEP.

nnnn: The amount of CPU seconds that JOB jobname will be extended if the operator reply is Y.

Source: FEMUTL

System Action: The JOB jobname stops executing until the operator responds to the message.

Operator Response: Reply Y if the JOB should continue or reply N if the JOB should stop. If the reply is N, the JOB jobname will abend with System Abend S322.

System Programmer Response: None.

FEMUTL115

JOB jobname WAITING FOR REPLY TO MESSAGE nn

Explanation: The SMF wait time limit for JOB jobname has expired, and the options selected for OS/EM require a confirmation by the operator to extend the JOB jobname. Message FEMUTL115 has been issued and the SMF Wait Time as specified in member SMFPRM00 in SYS1.PARMLIB has expired and the operator has not replied to message nn.

jobname: JOBNAME.

nn: The message number for FEMUTL114 that needs a reply.

Source: FEMUTL

System Action: The JOB jobname stops executing until the operator responds to message nn.

Operator Response: Reply as indicated in message FEMUTL114.

System Programmer Response: None.

FEMUTL116

JOB jobname WAITING FOR MOUNT ON DEVICE dddd. VOLSER=vvvvvv

Explanation: The SMF wait time limit for JOB jobname has expired, and mount for volume serial vvvvvv on device dddd has not been completed.

jobname: JOBNAME.

dddd: The device number.

vvvvvv: Volume serial.

Source: FEMUTL

System Action: The JOB jobname continues to wait for the operator to mount volume serial vvvvvv on device dddd.

Operator Response: Mount volume serial vvvvvv on device dddd.

System Programmer Response: None.

FEMUTL117

JOB jobname WAITING FOR DEVICE dddd TO BECOME READY

Explanation: The SMF wait time limit for JOB jobname has expired, and device dddd is not ready.

jobname: JOBNAME.

dddd: The device number.

Source: FEMUTL

System Action: The JOB jobname continues to wait for the operator to ready device dddd.

Operator Response: Ready device dddd.

System Programmer Response: None.

FEMUTL118

STEP CPU TIME LIMIT FOR JOB *jobname* EXTENDED BY *nnnn* SECONDS

Explanation: The step CPU time limit for JOB *jobname* has expired, and OS/EM has extended the CPU step time by *nnnn* seconds.

jobname: JOBNAME.

nnnn: The amount of CPU seconds that the step for JOB *jobname* been extended.

Source: FEMUTL

System Action: The JOB *jobname* continues to execute.

Operator Response: None.

System Programmer Response: None.

FEMUTL119

WAIT TIME LIMIT FOR JOB *jobname* EXTENDED BY *nnnn* MINUTES

Explanation: The wait time limit as specified in member SMFPRM00 in SYS1.PARMLIB has expired for JOB *jobname*, and OS/EM has extended the wait time limit by *nnnn* minutes.

jobname: Jobname.

nnnn: The amount of wait time in minutes that the JOB has been extended.

Source: FEMUTL

System Action: The JOB *jobname* continues to execute.

Operator Response: None.

System Programmer Response: None.

FEMUTL120

JOB CPU TIME LIMIT FOR JOB *jobname* EXTENDED BY *nnnn* SECONDS

Explanation: The JOB CPU time limit for JOB *jobname* has expired, and OS/EM has extended the CPU JOB time by *nnnn* seconds.

jobname: JOBNAME.

nnnn: The amount of CPU seconds that JOB *jobname* been extended.

Source: FEMUTL

System Action: The JOB *jobname* continues to execute.

Operator Response: None.

System Programmer Response: None.

FEMACT121

jobname MAXRC=*rc* CPU=*hh.mm.ss* ELAPSED=*hh.mm* I/O=*xxxx*

Explanation: The JOB *jobname* has completed.

jobname: JOBNAME.

rc: The maximum return code for the JOB *jobname*.

CPU=hh.mm.ss: CPU time for this JOB in hours, minutes and seconds.
ELAPSED=hh.mm: Elapsed time for this JOB in hours and minutes.
xxxx: The total Input / Output request for JOB jobname.

Source: FEMACTRT

System Action: The JOB jobname has completed execution.

Operator Response: None.

System Programmer Response: None.

FEMUJI122

JOB jobname NOT ALLOWED TO EXECUTE IN JOBCLASS x

Explanation: During Job initialization processing, OS/EM options have requested Jobclass / Jobname authorization checking, and the Jobname specified on the JOB card is not allowed to execute in the Jobclass requested.

jobname: Jobclass requested.
x: Jobclass Job is being submitted to.

Source: FEMUJI

System Action: The JOB is cancelled.

Operator Response: None.

System Programmer Response: None.

User Response: Change the Jobclass to one that the Jobname has access to.

FEMPRE123

RENAME FAILED

Explanation: The OS/EM optional QuickPool function has been activated in FAIL mode, and this job has attempted to rename datasets on a volume where they are not allowed. Message FEMPRE125 is also issued.

Source: FEMPRE00

System Action: The RENAME fails.

Operator Response: None.

System Programmer Response: None.

User Response: Allocate the new name for the dataset that you are attempting to rename on a volume where the newname dataset is allowed, and copy the the old named dataset to the new named dataset. Contact the System Programmer for information on the QuickPool implementation at your site.

FEMPRE124

WARNING - RENAME WOULD FAIL

Explanation: The OS/EM optional QuickPool function has been activated in WARN mode, and this job has renamed datasets on a volume where they are not allowed, and if the QuickPool function is activated in FAIL mode the rename will fail. Message FEMPRE125 is also issued.

Source: FEMPRE00

System Action: The RENAME continues.

Operator Response: None.

System Programmer Response: None.

User Response: None.

FEMPRE125

NEW DATASET NAME NOT ALLOWED ON VOLUME

Explanation: The OS/EM optional QuickPool function has been activated in FAIL mode, and this job is attempting to allocate datasets on a volume where they are not allowed. Message FEMPRE123 or FEMPRE124 is issued depending if QuickPool is in FAIL or WARN mode respectively.

Source: FEMPRE00

System Action: The RENAME fails if QuickPool is in FAIL mode, or continues if QuickPool is in WARN mode.

Operator Response: None.

System Programmer Response: None.

User Response: Allocate the new name for the dataset that you are attempting to rename on a volume where the newname dataset is allowed, and copy the the old named dataset to the new named dataset. Contact the System Programmer for information on the QuickPool implementation at your site.

FEMPRE126

DATASET ALLOCATION REJECTED

Explanation: The OS/EM optional QuickPool function has been activated in FAIL mode, and this job is attempting to allocate a dataset on a volume where it is not allowed.

Source: FEMPRE00

System Action: The allocation fails.

Operator Response: None.

System Programmer Response: None.

User Response: If you are allocating a dataset on a volume with a VOL=SER=xxxxxx, remove the VOL=SER parameter and allow QuickPool to select the volume. Contact the System Programmer for information on the QuickPool implementation at your site.

FEMPRE127

WARNING - DATASET ALLOCATION WOULD BE REJECTED

Explanation: The OS/EM optional QuickPool function has been activated in WARN mode, and this job is attempting to allocate datasets on a volume where they are not allowed, according to the QuickPool implementation at your site.

Source: FEMPRE00

System Action: The allocation continues.

Operator Response: None.

System Programmer Response: None.

User Response: Correct your JCL so that when QuickPool is activated in FAIL mode, your job will not fail. Contact the System Programmer for information on the QuickPool implementation at your site.

FEMPRE128

UNMOVABLE DATASET NOT ALLOWED

Explanation: The OS/EM optional QuickPool function has been activated in FAIL mode, and this job is attempting to allocate UNMOVABLE datasets which have been disallowed according to the QuickPool options selected at your site.

Source: FEMPRE00

System Action: The allocation fails.

Operator Response: None.

System Programmer Response: None.

User Response: Remove the UNMOVABLE attribute from the DSORG in the allocation and re-submit the job. Contact the System Programmer for information on the QuickPool implementation at your site.

FEMPRE129

SECONDARY ALLOCATION NOT ALLOWED

Explanation: The OS/EM optional QuickPool function has been activated in FAIL mode, and this job is attempting to allocate SECONDARY ALLOCATION datasets which have been disallowed according to the QuickPool options selected at your site.

Source: FEMPRE00

System Action: The allocation fails.

Operator Response: None.

System Programmer Response: None.

User Response: Remove the SECONDARY ALLOCATION from the SPACE PARAMETER and re-submit the job. Contact the System Programmer for information on the QuickPool implementation at your site.

FEMPRE130

DATASET NOT ALLOWED ON VOLUME

Explanation: The OS/EM optional QuickPool function has been activated in FAIL mode, and this job has attempted to allocate a dataset on a volume where it is not allowed, according to the QuickPool implementation at your site.

Source: FEMPRE00

System Action: The allocation fails.

Operator Response: None.

System Programmer Response: None.

User Response: Remove the VOL=SER parameter from the JCL and re-submit the Job. Contact the System Programmer for information on the QuickPool implementation at your site.

FEMPRE131

DATASET NAME IS NOT VALID

Explanation: The OS/EM optional QuickPool function has been activated in FAIL mode, and this job is attempting to allocate a single level dataset which have been disallowed, according to the QuickPool options selected at your site.

Source: FEMPRE00

System Action: The allocation fails.

Operator Response: None.

System Programmer Response: None.

User Response: Create a multi-level dataset name in the allocation and re-submit the job. Contact the System Programmer for information on the QuickPool implementation at your site.

FEMPRE132

ABSTR ALLOCATION NOT ALLOWED

Explanation: The OS/EM optional QuickPool function has been activated in FAIL mode, and this job is attempting to allocate a dataset with absolute track allocation which has been disallowed, according to the QuickPool options selected at your site.

Source: FEMPRE00

System Action: The allocation fails.

Operator Response: None.

System Programmer Response: None.

User Response: Re-specify the allocation in cylinders, tracks kilobytes or megabytes and re-submit the job. Contact the System Programmer for information on the QuickPool implementation at your site.

FEMPRE133

ADSP NOT ALLOWED

Explanation: The OS/EM optional QuickPool function has been activated in FAIL mode, and this job is attempting to allocate a dataset with automatic dataset protection bit on, (a RACF SETR options) and automatic dataset protection is not allowed, according to the QuickPool options selected at your site.

Source: FEMPRE00

System Action: The allocation fails.

Operator Response: None.

System Programmer Response: None.

User Response: Contact the Security Administrator and/or the System Programmer for a resolution with the inconsistencies between the options selected for QuickPool and the RACF SETR options.

FEMPRE134

ISAM DATASET NOT ALLOWED

Explanation: The OS/EM optional QuickPool function has been activated in FAIL mode, and this job is attempting to allocate an ISAM dataset which is not allowed, according to the QuickPool options selected at your site.

Source: FEMPRE00

System Action: The allocation fails.

Operator Response: None.

System Programmer Response: None.

User Response: Contact the System Programmer.

FEMPRE135

CONTIG ALLOCATION NOT ALLOWED

Explanation: The OS/EM optional QuickPool function has been activated in FAIL mode, and this job is attempting to allocate a dataset with the CONTIG option as a sub-parameter of the SPACE parameter which is not allowed, according to the QuickPool options selected at your site.

Source: FEMPRE00

System Action: The allocation fails.

Operator Response: None.

System Programmer Response: None.

User Response: Remove the CONTIG sub-parameter from the SPACE allocation and re-submit the Job. Contact the System Programmer.

FEMPRE136

ALX ALLOCATION NOT ALLOWED

Explanation: The OS/EM optional QuickPool function has been activated in FAIL mode, and this job is attempting to allocate a dataset with the ALX option as a sub-parameter of the SPACE parameter which is not allowed, according to the QuickPool options selected at your site.

Source: FEMPRE00

System Action: The allocation fails.

Operator Response: None.

System Programmer Response: None.

User Response: Remove the ALX sub-parameter from the SPACE allocation and re-submit the Job. Contact the System Programmer.

FEMPRE137

MXIG ALLOCATION NOT ALLOWED

Explanation: The OS/EM optional QuickPool function has been activated in FAIL mode, and this job is attempting to allocate a dataset with the MXIG option as a sub-parameter of the SPACE parameter which is not allowed, according to the QuickPool options selected at your site.

Source: FEMPRE00

System Action: The allocation fails.

Operator Response: None.

System Programmer Response: None.

User Response: Remove the MXIG sub-parameter from the SPACE allocation and re-submit the Job. Contact the System Programmer for information on the QuickPool implementation at your site.

FEMPRE138

PROT=YES NOT ALLOWED

Explanation: The OS/EM optional QuickPool function has been activated in FAIL mode, and this job is attempting to allocate a dataset with PROTECT=YES sub-parameter specified which has been disallowed, according to the QuickPool options selected at your site.

Source: FEMPRE00

System Action: The allocation fails.

Operator Response: None.

System Programmer Response: None.

User Response: Remove the PROTECT=YES sub-parameter from the DD and re-submit the Job. Contact the System Programmer for information on the QuickPool implementation at your site.

FEMALC139

type OPTION IS NOT ENABLED

Explanation: During OS/EM command processing an optional OS/EM parameter has been specified, but your Option code does not allow the use of this feature.

type:

- HSM OPTIMIZER
- JES3
- Job Class Standards
- QuickPool

Source: FEMALLO0,FEMALLO1

System Action: The FEMCNTL command being processed is ignored.

Operator Response: None.

System Programmer Response: Check the command format in this manual for the function being performed. If using the ISPF interface, check the command format for the verb being used. Contact OS/EM support for assistance in obtaining the use of the requested option.

FEMCOD139

type OPTION IS NOT ENABLED

Explanation: During OS/EM command processing an optional OS/EM parameter has been specified, but your Option code does not allow the use of this feature.

type:

HSM OPTIMIZER
JES3
Job Class Standards
QuickPool

Source: FEMCODE

System Action: The FEMCNTL command being processed is ignored.

Operator Response: None.

System Programmer Response: Check the command format in this manual for the function being performed. If using the ISPF interface, check the command format for the verb being used. Contact OS/EM support for assistance in obtaining the use of the requested option.

FEMDAD139

type OPTION IS NOT ENABLED

Explanation: During OS/EM command processing an optional OS/EM parameter has been specified, but your Option code does not allow the use of this feature.

type:

HSM OPTIMIZER
JES3
Job Class Standards
QuickPool

Source: FEMDASD

System Action: The FEMCNTL command being processed is ignored.

Operator Response: None.

System Programmer Response: Check the command format in this manual for the function being performed. If using the ISPF interface, check the command format for the verb being used. Contact OS/EM support for assistance in obtaining the use of the requested option.

FEMDAP139

type OPTION IS NOT ENABLED

Explanation: During OS/EM command processing an optional OS/EM parameter has been specified, but your Option code does not allow the use of this feature.

type:

HSM OPTIMIZER
JES3
Job Class Standards
QuickPool

Source: FEMPOOL

System Action: The FEMCNTL command being processed is ignored.

Operator Response: None.

System Programmer Response: Check the command format in this manual for the function being performed. If using the ISPF interface, check the command format for the verb being used. Contact OS/EM support for assistance in obtaining the use of the requested option.

FEMHSM139

type OPTION IS NOT ENABLED

Explanation: During OS/EM command processing an optional OS/EM parameter has been specified, but your Option code does not allow the use of this feature.

type:

HSM OPTIMIZER
JES3
Job Class Standards
QuickPool

Source: FEMHSM0,FEMHSM1,FEMHSM2,FEMHSM3

System Action: The FEMCNTL command being processed is ignored.

Operator Response: None.

System Programmer Response: Check the command format in this manual for the function being performed. If using the ISPF interface, check the command format for the verb being used. Contact OS/EM support for assistance in obtaining the use of the requested option.

FEMISP139

type OPTION IS NOT ENABLED

Explanation: During OS/EM command processing an optional OS/EM parameter has been specified, but your Option code does not allow the use of this feature.

type:

HSM OPTIMIZER
JES3
Job Class Standards
QuickPool

Source: FEMISPF

System Action: The FEMCNTL command being processed is ignored.

Operator Response: None.

System Programmer Response: Check the command format in this manual for the function being performed. If using the ISPF interface, check the command format for the verb being used. Contact OS/EM support for assistance in obtaining the use of the requested option.

FEMJS2139

type OPTION IS NOT ENABLED

Explanation: During OS/EM command processing an optional OS/EM parameter has been specified, but your Option code does not allow the use of this feature.

type:

HSM OPTIMIZER

JES3
Job Class Standards
QuickPool

Source: FEMJES2A through FEMJES2H

System Action: The FEMCNTL command being processed is ignored.

Operator Response: None.

System Programmer Response: Check the command format in this manual for the function being performed. If using the ISPF interface, check the command format for the verb being used. Contact OS/EM support for assistance in obtaining the use of the requested option.

FEMJS3139

type OPTION IS NOT ENABLED

Explanation: During OS/EM command processing an optional OS/EM parameter has been specified, but your Option code does not allow the use of this feature.

type:
HSM OPTIMIZER
JES3
Job Class Standards
QuickPool

Source: FEMJES3

System Action: The FEMCNTL command being processed is ignored.

Operator Response: None.

System Programmer Response: Check the command format in this manual for the function being performed. If using the ISPF interface, check the command format for the verb being used. Contact OS/EM support for assistance in obtaining the use of the requested option.

FEMMIS139

type OPTION IS NOT ENABLED

Explanation: During OS/EM command processing an optional OS/EM parameter has been specified, but your Option code does not allow the use of this feature.

type:
HSM OPTIMIZER
JES3
Job Class Standards
QuickPool

Source: FEMMISC

System Action: The FEMCNTL command being processed is ignored.

Operator Response: None.

System Programmer Response: Check the command format in this manual for the function being performed. If using the ISPF interface, check the command format for the verb being used. Contact OS/EM support for assistance in obtaining the use of the requested option.

FEMRAC139

type OPTION IS NOT ENABLED

Explanation: During OS/EM command processing an optional OS/EM parameter has been specified, but your Option code does not allow the use of this feature.

type:

HSM OPTIMIZER
JES3
Job Class Standards
QuickPool

Source: FEMRACF

System Action: The FEMCNTL command being processed is ignored.

Operator Response: None.

System Programmer Response: Check the command format in this manual for the function being performed. If using the ISPF interface, check the command format for the verb being used. Contact OS/EM support for assistance in obtaining the use of the requested option.

FEMSAF139

type OPTION IS NOT ENABLED

Explanation: During OS/EM command processing an optional OS/EM parameter has been specified, but your Option code does not allow the use of this feature.

type:

HSM OPTIMIZER
JES3
Job Class Standards
QuickPool

Source: FEMSAF

System Action: The FEMCNTL command being processed is ignored.

Operator Response: None.

System Programmer Response: Check the command format in this manual for the function being performed. If using the ISPF interface, check the command format for the verb being used. Contact OS/EM support for assistance in obtaining the use of the requested option.

FEMSMF139

type OPTION IS NOT ENABLED

Explanation: During OS/EM command processing an optional OS/EM parameter has been specified, but your Option code does not allow the use of this feature.

type:

HSM OPTIMIZER
JES3
Job Class Standards
QuickPool

Source: FEMSMF0,FEMSMF1,FEMSMF2,FEMSMF3,FEMSMF4,FEMSMF5

System Action: The FEMCNTL command being processed is ignored.

Operator Response: None.

System Programmer Response: Check the command format in this manual for the function being performed. If using the ISPF interface, check the command format for the verb being used. Contact OS/EM support for assistance in obtaining the use of the requested option.

FEMTSO139

type OPTION IS NOT ENABLED

Explanation: During OS/EM command processing an optional OS/EM parameter has been specified, but your Option code does not allow the use of this feature.

type:

HSM OPTIMIZER
JES3
Job Class Standards
QuickPool

Source: FEMTSO

System Action: The FEMCNTL command being processed is ignored.

Operator Response: None.

System Programmer Response: Check the command format in this manual for the function being performed. If using the ISPF interface, check the command format for the verb being used. Contact OS/EM support for assistance in obtaining the use of the requested option.

FEMCMD140

DEVICE addr IS CONTROLLED BY OS/EM xxxx

Explanation: The OS/EM optional restrict device control or tape share control is active, and the Operator has attempted to VARY the device online or offline; has entered the SWAP command or the Operator has responded to message 'IEF238D jobname REPLY DEVICE NAME OR CANCEL' with the device number of the controlled device. For tape share, the device is not currently available because it is online on another system or it is flagged to be offline to this system or all systems.

addr: The controlled device address

xxxx: The OS/EM option in control of the device, either restrict device or tape share.

Source: FEMCMD

System Action: The command or Reply is ignored.

Operator Response: For tape share, choose another device and reissue the command. If this specific device must be used, issue a display command for the device, determine to what system the device is allocated or if the device is flagged to be locally or globally offline. If the device is online to another system, issue a vary offline command on that system. If the device is flagged as locally or globally offline, and it is now permissible to use the device on this system, issue a command to bring the device locally or globally online. Then reissue the original command.

System Programmer Response: None

FEMCMD141

RE-ENTER xxxxx

Explanation: The OS/EM optional restrict device control is activated, and the Operator has attempted to VARY the restricted device online or offline, or the Operator has responded to message

'IEF238D jobname REPLY DEVICE NAME OR CANCEL' with the device number of the restricted device.

xxxx: REPLY or VARY Command.

Source: FEMCMD2

System Action: The command or Reply is ignored.

Operator Response: If the message is issued as the result of a VARY ONLINE/OFFLINE command, verify the device number was entered correctly, because the device is controlled by OS/EM device restriction. If the device is required to be varied online/offline, contact the System Programmer so that they can remove the device from the OS/EM device restriction options. If the message is the result of message IEF238D, respond to message IEF238D with a device that is not controlled by OS/EM optional device restriction control.

System Programmer Response: Remove the device from the OS/EM device restriction processing if required.

FEMALC143

CANNOT CONTROL DEVICE devnum

Explanation: Device is not available for OS/EM control because it is in use by OLTEP, a SYSRES device, a console, controlled by JES3 or has no paths available.

devnum: Device number.

Source: FEMALLO1

System Action: OS/EM does not attempt to control the device.

Operator Response: Contact System Programmer.

System Programmer Response: Do a DU command to determine the problem and correct it.

FEMRD1144

DEFINE OF DISCRETE PROFILE DISALLOWED

Explanation: OS/EM has been requested to disallow discrete profile creation and an attempt has been made to define a discrete profile.

Source: FEMRDX01

System Action: The profile is not created.

Operator Response: None. Informational message only.

System Programmer Response: None. Informational message only.

FEMRD1145

WARNING - DEFINE OF DISCRETE PROFILE WOULD BE DISALLOWED

Explanation: The discrete profile control feature of OS/EM is operating in WARN mode and a request to define a discrete profile is being processed.

Source: FEMRDX01

System Action: The DEFINE continues.

Operator Response: None. Informational message only.

System Programmer Response: None. Informational message only.

FEMX02146

JES2 macroname MACRO FAILED. RC = nn.

Explanation: A JES2 macro did not complete properly.

macroname: The name of the failed JES2 macro.

rc: The return code from the macro execution.

Source: FEMJ2X02

System Action: OS/EM continues.

Operator Response: Notify System Programmer.

System Programmer Response: Check for other messages and correct errors. Contact OS/EM support for assistance in problem resolution.

FEMX04146

JES2 macroname MACRO FAILED. RC = nn.

Explanation: A JES2 macro did not complete properly.

macroname: The name of the failed JES2 macro.

rc: The return code from the macro execution.

Source: FEMJ2X04

System Action: OS/EM continues.

Operator Response: Notify System Programmer.

System Programmer Response: Check for other messages and correct errors. Contact OS/EM support for assistance in problem resolution.

FEMX05146

JES2 macroname MACRO FAILED. RC = nn.

Explanation: A JES2 macro did not complete properly.

macroname: The name of the failed JES2 macro.

rc: The return code from the macro execution.

Source: FEMJ2X05

System Action: OS/EM continues.

Operator Response: Notify System Programmer.

System Programmer Response: Check for other messages and correct errors. Contact OS/EM support for assistance in problem resolution.

FEMX06146

JES2 macroname MACRO FAILED. RC = nn.

Explanation: A JES2 macro did not complete properly.

macroname: The name of the failed JES2 macro.
rc: The return code from the macro execution.

Source: FEMJ2X06

System Action: OS/EM continues.

Operator Response: Notify System Programmer.

System Programmer Response: Check for other messages and correct errors. Contact OS/EM support for assistance in problem resolution.

FEMX24146

JES2 macroname MACRO FAILED. RC = nn.

Explanation: A JES2 macro did not complete properly.

macroname: The name of the failed JES2 macro.
rc: The return code from the macro execution.

Source: FEMJ2X24

System Action: OS/EM continues.

Operator Response: Notify System Programmer.

System Programmer Response: Check for other messages and correct errors. Contact OS/EM support for assistance in problem resolution.

FEMX32146

JES2 macroname MACRO FAILED. RC = nn.

Explanation: A JES2 macro did not complete properly.

macroname: The name of the failed JES2 macro.
rc: The return code from the macro execution.

Source: FEMJ2N32

System Action: OS/EM continues.

Operator Response: Notify System Programmer.

System Programmer Response: Check for other messages and correct errors. Contact OS/EM support for assistance in problem resolution.

FEMX44146

JES2 macroname MACRO FAILED. RC = nn.

Explanation: A JES2 macro did not complete properly.

macroname: The name of the failed JES2 macro.
rc: The return code from the macro execution.

Source: FEMJ2X44

System Action: OS/EM continues.

Operator Response: Notify System Programmer.

System Programmer Response: Check for other messages and correct errors. Contact OS/EM support for assistance in problem resolution.

FEM2G3146

JES2 macroname MACRO FAILED. RC = nn.

Explanation: A JES2 macro did not complete properly.

macroname: The name of the failed JES2 macro.

rc: The return code from the macro execution.

Source: FEMJ2G3x

System Action: OS/EM continues.

Operator Response: Notify System Programmer.

System Programmer Response: Check for other messages and correct errors. Contact OS/EM support for assistance in problem resolution.

FEM2H0146

JES2 macroname MACRO FAILED. RC = nn.

Explanation: A JES2 macro did not complete properly.

macroname: The name of the failed JES2 macro.

rc: The return code from the macro execution.

Source: FEMJ2H0x

System Action: OS/EM continues.

Operator Response: Notify System Programmer.

System Programmer Response: Check for other messages and correct errors. Contact OS/EM support for assistance in problem resolution.

FEM2L0146

JES2 macroname MACRO FAILED. RC = nn.

Explanation: A JES2 macro did not complete properly.

macroname: The name of the failed JES2 macro.

rc: The return code from the macro execution.

Source: FEMJ2L0x

System Action: OS/EM continues.

Operator Response: Notify System Programmer.

System Programmer Response: Check for other messages and correct errors. Contact OS/EM support for assistance in problem resolution.

FEM2MM146

JES2 macroname MACRO FAILED. RC = nn.

Explanation: A JES2 macro did not complete properly.

macroname: The name of the failed JES2 macro.
rc: The return code from the macro execution.

Source: FEMJ2MMx

System Action: OS/EM continues.

Operator Response: Notify System Programmer.

System Programmer Response: Check for other messages and correct errors. Contact OS/EM support for assistance in problem resolution.

FEM2M3146

JES2 macroname MACRO FAILED. RC = nn.

Explanation: A JES2 macro did not complete properly.

macroname: The name of the failed JES2 macro.
rc: The return code from the macro execution.

Source: FEMJ2M3x

System Action: OS/EM continues.

Operator Response: Notify System Programmer.

System Programmer Response: Check for other messages and correct errors. Contact OS/EM support for assistance in problem resolution.

FEM IPL147

PAGEFIX OF SSCT FOR SUBSYSTEM subsys FAILED. RC = nn.

Explanation: The PGSER macro to pagefix the SSCT's before the OS/EM SSCT failed.

subsys: Name of the subsystem.
nn: Return Code.

Source: FEM IPL

System Action: FEM IPL continues. There is a slight chance that some OS/EM function will get an S0C4 abend attempting to locate the OS/EM SSCT.

Operator Response: Contact System Programmer.

System Programmer Response: Determine cause of pagefix failure and take appropriate action.

FEMX06148

JOB CPU TIME LIMIT SET TO (mm,ss)

Explanation: The jobs CPU time limit has been reset to (mm,ss) because of the JES2 Exit6 OS/EM Optional Control settings.

mm: minutes.

ss: seconds.

Source: FEMJ2X06

System Action: The execution time limit is reset.

Operator Response: None. Informational message only.

System Programmer Response: None. Informational message only.

FEMUSO149

SYSOUT LIMIT FOR JOB jjjjjjj DDNAME ddddddd EXTENDED BY nn LINES

Explanation: The sysout limit for the specified job has been extended by the number of lines shown. The extension was given because of the IEFUSO OS/EM Optional Control settings.

jjjjjjj: Jobname.

ddddddd: DDNAME.

nn: number of lines.

Source: FEMUSO

System Action: The sysout limit is extended.

Operator Response: None. Informational message only.

System Programmer Response: None. Informational message only.

FEMIPL150

CSVSYNEX LIST FAILED, RC= xx RSN= yy

Explanation: During IPL processing OS/EM was unable to obtain a list of the exits in use by the MVS Dynamic Exit Facility. This will disable all OS/EM processing for any exit that should be specified to the Dynamic Exit Facility.

xx: The return code from the system request.

yy: The reason code from the system request.

Source: FEMIPL

System Action: Processing continues.

Operator Response: Notify System Programmer.

System Programmer Response: Verify that there is a valid entry in the 'PROG=' parameter of your IEASYSxx member in SYS1.PARMLIB pointing to the 'EXIT ADD' statements.

FEMIPL151

ADD OF OS/EM EXIT modname TO EXIT POINT extpnt FAILED, CSVSYNEX RC = xx RSN = yy

Explanation: During IPL processing OS/EM determined that the OS/EM interface module was not defined to the MVS Dynamic Exit Facility for the specified exit point. This will disable all OS/EM processing which would be controlled by the specified interface module.

modname: The exit load module name.

extpnt: The exit point name.

xx: The return code from the CSVSYNEX request.

yy: The reason code from the CSVSYNEX request.

Source: FEM IPL

System Action: Processing continues.

Operator Response: Notify System Programmer.

System Programmer Response: Verify that there is a valid entry in the 'PROG=' parameter of your IEASYSxx member in SYS1.PARMLIB pointing to the 'EXIT ADD' statements.

FEMUSO152

SHOULD SYSOUT LIMIT FOR JOB xxxxxxxx DDNAME yyyyyyyy BE EXTENDED BY nnnn LINES ? (Y OR N)

Explanation: OS/EM's Optional Control settings for IEFUSO specifies that before sysout limits are extended the operator must OK the extension.

xxxxxxx: The job name.

yyyyyyy: The ddname that will be extended.

nnnn: The number of lines that the SYSOUT dataset will be extended by.

Source: FEMUSO

System Action: Waits for the Operator to respond.

Operator Response: Respond **Y** to have the jobs sysout limit increased. Respond **N** to have the job cancelled. Be aware that multiple extensions may have already been granted.

System Programmer Response: None.

FEMX32153

xxxxxxx (JOBnnnn) STARTED AT hh mm

Explanation: OS/EM's JES2 Exit32 Optional Control settings have been set to issue a message when a job starts execution.

xxxxxxx: Jobname.

nnnn: Job number.

hh mm: Time of day.

Source: FEMJ2N32,FEMJ2X32

System Action: The message is sent to the TSO ID specified on the NOTIFY parameter of the JOBCARD.

Operator Response: None. Informational message.

System Programmer Response: None. Informational message.

FEMREL154

SECURITY SYSTEM IS NOT RACF

Explanation: A RACF table reload has been attempted but RACF is not the active security system.

Source: FEMRELOD

System Action: The table is not reloaded.

Operator Response: None.

System Programmer Response: None.

FEMREL155

RACF xxxxxxxx MODULE HAS INVALID FORMAT

Explanation: The format of the RACF table to be reloaded is invalid.

xxxxxxx: Name of RACF module.

Source: FEMRELOD

System Action: The table is not reloaded.

Operator Response: None.

System Programmer Response: Correct the table format.

FEMSVU156

SVC TYPE IS REQUIRED TO PROCESS RELOAD

Explanation: The SVC type was not specified on a SVC reload command.

Source: FEMSVUCUD

System Action: The SVC is not reloaded.

Operator Response: None.

System Programmer Response: Specify the correct SVC type and retry the command.

FEMALC157

DEVICE xxxx NOT PRESENT ON SYSTEM

Explanation: OS/EM was requested to control a device which is not connected to the system.

xxxx: Device ID.

Source: FEMALLO1

System Action: The OS/EM command is ignored. Other devices specified in the same command may be processed however.

Operator Response: Specify a valid device number.

System Programmer Response: None.

FEMINT158

OS/EM INITIALIZATION FAILED. REPLY "U" TO ACKNOWLEDGE.

Explanation: An error has occurred during OS/EM initialization. No valid authorization code was supplied.

Source: FEMINIT

System Action: Wait for operator response.

Operator Response: Reply U to acknowledge and then notify the System Programmer.

System Programmer Response: Review the IPL report and correct any indicated error.

FEM2P1159

MAILBOX CREATE FAILED. RC = nn, RSN = nn.

Explanation: The IXZXIXMC or IXZXIXMB macro to create a JES2 mailbox for XCF failed.

nn Return code and Reason code.

Source: FEMJ2P1x

System Action: Job Routing option initialization is terminated.

Operator Response: Notify the system programmer.

System Programmer Response: Examine the return codes and reason codes provided in the message. If the cause of the problem is not apparent, call OS/EM technical support.

FEM2P2159

MAILBOX DELETE FAILED. RC = nn, RSN = nn.

Explanation: The IXZXIXMC or IXZXIXMB macro to delete a JES2 mailbox for XCF failed.

nn Return code and Reason code.

Source: FEMJ2P2x

System Action: Job Routing option initialization is terminated.

Operator Response: Notify the system programmer.

System Programmer Response: Examine the return codes and reason codes provided in the message. If the cause of the problem is not apparent, call OS/EM technical support.

FEMALC160

name FAILED IN MODULE modulename. RC = xx, RSN = yy.

Explanation: The named MVS macro did not execute correctly.

name The name of the macro that failed.

xx The return code from the macro request.

yy The reason code from the macro request.

Source: FEMALLO1

System Action: Various. Usually the function that was being performed is terminated and some function of OS/EM will not operate correctly.

Operator Response: Notify the system programmer.

System Programmer Response: Examine the return codes and reason codes provided in the message. If the cause of the problem is not apparent, call OS/EM technical support.

FEMDMP160

name FAILED IN MODULE modulename. RC = xx, RSN = yy.

Explanation: The named MVS macro did not execute correctly.

name The name of the macro that failed.
xx The return code from the macro request.
yy The reason code from the macro request.

Source: FEMDUMP

System Action: Various. Usually the function that was being performed is terminated and some function of OS/EM will not operate correctly.

Operator Response: Notify the system programmer.

System Programmer Response: Examine the return codes and reason codes provided in the message. If the cause of the problem is not apparent, call OS/EM technical support.

FEMHSP160

name FAILED IN MODULE modulename. RC = xx, RSN = yy.

Explanation: The named MVS macro did not execute correctly.

name The name of the macro that failed.
xx The return code from the macro request.
yy The reason code from the macro request.

Source: FEMHJ20

System Action: Various. Usually the function that was being performed is terminated and some function of OS/EM will not operate correctly.

Operator Response: Notify the system programmer.

System Programmer Response: Examine the return codes and reason codes provided in the message. If the cause of the problem is not apparent, call OS/EM technical support.

FEMLIB160

name FAILED IN MODULE modulename. RC = xx, RSN = yy.

Explanation: The named MVS macro did not execute correctly.

name The name of the macro that failed.
xx The return code from the macro request.
yy The reason code from the macro request.

Source: FEMLIB

System Action: Various. Usually the function that was being performed is terminated and some function of OS/EM will not operate correctly.

Operator Response: Notify the system programmer.

System Programmer Response: Examine the return codes and reason codes provided in the message. If the cause of the problem is not apparent, call OS/EM technical support.

FEMREL160

name FAILED IN MODULE modulename. RC = xx, RSN = yy.

Explanation: The named MVS macro did not execute correctly.

name The name of the macro that failed.
xx The return code from the macro request.

yy The reason code from the macro request.

Source: FEMRELOD

System Action: Various. Usually the function that was being performed is terminated and some function of OS/EM will not operate correctly.

Operator Response: Notify the system programmer.

System Programmer Response: Examine the return codes and reason codes provided in the message. If the cause of the problem is not apparent, call OS/EM technical support.

FEMTPS160

name FAILED IN MODULE modulename. RC = xx, RSN = yy.

Explanation: The named MVS macro did not execute correctly.

name The name of the macro that failed.
xx The return code from the macro request.
yy The reason code from the macro request.

Source: FEMTPSHR

System Action: Various. Usually the function that was being performed is terminated and some function of OS/EM will not operate correctly.

Operator Response: Notify the system programmer.

System Programmer Response: Examine the return codes and reason codes provided in the message. If the cause of the problem is not apparent, call OS/EM technical support.

FEMW21160

name FAILED IN MODULE modulename. RC = xx, RSN = yy.

Explanation: The named MVS macro did not execute correctly.

name The name of the macro that failed.
xx The return code from the macro request.
yy The reason code from the macro request.

Source: FEMW21SD

System Action: Various. Usually the function that was being performed is terminated and some function of OS/EM will not operate correctly.

Operator Response: Notify the system programmer.

System Programmer Response: Examine the return codes and reason codes provided in the message. If the cause of the problem is not apparent, call OS/EM technical support.

FEMX32160

name FAILED IN MODULE modulename. RC = xx, RSN = yy.

Explanation: The named MVS macro did not execute correctly.

name The name of the macro that failed.
xx The return code from the macro request.
yy The reason code from the macro request.

Source: FEMJ2N32,FEMJ2X32

System Action: Various. Usually the function that was being performed is terminated and some function of OS/EM will not operate correctly.

Operator Response: Notify the system programmer.

System Programmer Response: Examine the return codes and reason codes provided in the message. If the cause of the problem is not apparent, call OS/EM technical support.

FEM2G2160

name FAILED IN MODULE modulename. RC = xx, RSN = yy.

Explanation: The named MVS macro did not execute correctly.

name The name of the macro that failed.
xx The return code from the macro request.
yy The reason code from the macro request.

Source: FEMJ2G2x

System Action: Various. Usually the function that was being performed is terminated and some function of OS/EM will not operate correctly.

Operator Response: Notify the system programmer.

System Programmer Response: Examine the return codes and reason codes provided in the message. If the cause of the problem is not apparent, call OS/EM technical support.

FEM2G3160

name FAILED IN MODULE modulename. RC = xx, RSN = yy.

Explanation: The named MVS macro did not execute correctly.

name The name of the macro that failed.
xx The return code from the macro request.
yy The reason code from the macro request.

Source: FEMJ2G3x

System Action: Various. Usually the function that was being performed is terminated and some function of OS/EM will not operate correctly.

Operator Response: Notify the system programmer.

System Programmer Response: Examine the return codes and reason codes provided in the message. If the cause of the problem is not apparent, call OS/EM technical support.

FEM2G4160

name FAILED IN MODULE modulename. RC = xx, RSN = yy.

Explanation: The named MVS macro did not execute correctly.

name The name of the macro that failed.
xx The return code from the macro request.
yy The reason code from the macro request.

Source: FEMJ2G4x

System Action: Various. Usually the function that was being performed is terminated and some function of OS/EM will not operate correctly.

Operator Response: Notify the system programmer.

System Programmer Response: Examine the return codes and reason codes provided in the message. If the cause of the problem is not apparent, call OS/EM technical support.

FEM2P1160

name FAILED IN MODULE modulename. RC = xx, RSN = yy.

Explanation: The named MVS macro did not execute correctly.

name The name of the macro that failed.
xx The return code from the macro request.
yy The reason code from the macro request.

Source: FEMJ2P1x

System Action: Various. Usually the function that was being performed is terminated and some function of OS/EM will not operate correctly.

Operator Response: Notify the system programmer.

System Programmer Response: Examine the return codes and reason codes provided in the message. If the cause of the problem is not apparent, call OS/EM technical support.

FEM2P3160

name FAILED IN MODULE modulename. RC = xx, RSN = yy.

Explanation: The named MVS macro did not execute correctly.

name The name of the macro that failed.
xx The return code from the macro request.
yy The reason code from the macro request.

Source: FEMJ2P3x

System Action: Various. Usually the function that was being performed is terminated and some function of OS/EM will not operate correctly.

Operator Response: Notify the system programmer.

System Programmer Response: Examine the return codes and reason codes provided in the message. If the cause of the problem is not apparent, call OS/EM technical support.

FEM2S0160

name FAILED IN MODULE modulename. RC = xx, RSN = yy.

Explanation: The named MVS macro did not execute correctly.

name The name of the macro that failed.
xx The return code from the macro request.
yy The reason code from the macro request.

Source: FEMJ2S0x

System Action: Various. Usually the function that was being performed is terminated and some function of OS/EM will not operate correctly.

Operator Response: Notify the system programmer.

System Programmer Response: Examine the return codes and reason codes provided in the message. If the cause of the problem is not apparent, call OS/EM technical support.

FEM IPL161

JES2 SUBSYSTEM subname NOT DEFINED.

Explanation: The named JES2 subsystem has not been defined to MVS by an IEFSSNxx parmlib member.

subname JES2 Subsystem name

Source: FEM IPL

System Action: OS/EM will be unable to process JES2 exits for the subsystem.

Operator Response: Notify the system programmer.

System Programmer Response: Check the spelling with the subsystem name. If it is correct and you wish to have OS/EM process exits for the subsystem, then add the subsystem name to an IEFSSNxx member in parmlib and re-IPL the system.

FEM IPL163

osem SUBSYSTEM NOT DEFINED TO MVS

Explanation: The OS/EM subsystem is not defined to MVS in an active IEFSSNxx member of SYS1.PARMLIB.

osem: The OS/EM subsystem name.

Source: FEM IPL

System Action: FEM IPL terminates.

Operator Response: Notify the System Programmer.

System Programmer Response: Correct the IEFSSNxx member of SYS1.PARMLIB and re-IPL.

FEM IPL165

WRONG SUBSYSTEM NAME - FEM IPL TERMINATING

Explanation: During OS/EM sub-system initialization, the sub-system name that was entered in the IEFSSNxx member was not 'OSEM'.

Source: FEM IPL

System Action: Sub-system initialization terminates.

Operator Response: Contact the System Programmer.

System Programmer Response: Correct the IEFSSNxx member and re-ipl the system.

FEM J3E166

JES3 EXIT nn INVALID R15 VALUE vv FROM module

Explanation: OS/EM detected an invalid R15 value for exit nn.

nn: The JES3 exit name.
vv: The value contained in the return code (R15).

module: The name of the load module.

Source: FEMJ3ECN

System Action: The value is ignored.

Operator Response: Contact the System Programmer.

System Programmer Response: Correct the user exit to ensure that it returns valid return codes.

FEMALC167

dsname FILE function ERROR, DECB CODE = nn

Explanation: An I/O error has occurred on the named file. A code other than a x'7F' was posted back into the DECB upon completion of a BSAM file I/O operation.

dsname: The name of the dataset.
function: The I/O function being performed.
nn: The DECB code.

Source: FEMALLO1

System Action: Initialization of the OS/EM function is terminated.

Operator Response: Notify the system programmer.

System Programmer Response: Verify that the hardware is functioning correctly. Examine the DECB code and any error messages which may have been issued at the time of the error to determine the cause of the error. It may also be necessary to examine the dataset and catalog entry. If there is no apparent reason for an I/O error, contact OS/EM technical support.

FEMJS2167

dsname FILE function ERROR, DECB CODE = nn

Explanation: An I/O error has occurred on the named file. A code other than a x'7F' was posted back into the DECB upon completion of a BSAM file I/O operation.

dsname: The name of the dataset.
function: The I/O function being performed.
nn: The DECB code.

Source: FEMJES2G

System Action: Initialization of the OS/EM function is terminated.

Operator Response: Notify the system programmer.

System Programmer Response: Verify that the hardware is functioning correctly. Examine the DECB code and any error messages which may have been issued at the time of the error to determine the cause of the error. It may also be necessary to examine the dataset and catalog entry. If there is no apparent reason for an I/O error, contact OS/EM technical support.

FEMTPS167

dsname FILE function ERROR, DECB CODE = nn

Explanation: An I/O error has occurred on the named file. A code other than a x'7F' was posted back into the DECB upon completion of a BSAM file I/O operation.

dsname: The name of the dataset.

function: The I/O function being performed.

nn: The DECB code.

Source: FEMTPSHR

System Action: Initialization of the OS/EM function is terminated.

Operator Response: Notify the system programmer.

System Programmer Response: Verify that the hardware is functioning correctly. Examine the DECB code and any error messages which may have been issued at the time of the error to determine the cause of the error. It may also be necessary to examine the dataset and catalog entry. If there is no apparent reason for an I/O error, contact OS/EM technical support.

FEM2S0167

dsname FILE function ERROR, DECB CODE = nn

Explanation: An I/O error has occurred on the named file. A code other than a x'7F' was posted back into the DECB upon completion of a BSAM file I/O operation.

dsname: The name of the dataset.

function: The I/O function being performed.

nn: The DECB code.

Source: FEMJ2S0x

System Action: Initialization of the OS/EM function is terminated.

Operator Response: Notify the system programmer.

System Programmer Response: Verify that the hardware is functioning correctly. Examine the DECB code and any error messages which may have been issued at the time of the error to determine the cause of the error. It may also be necessary to examine the dataset and catalog entry. If there is no apparent reason for an I/O error, contact OS/EM technical support.

FEMJS2168

dsname DATASET IS TOO SMALL

Explanation: The resource dataset is not large enough.

dsname: The name of the dataset.

Source: FEMJES2G

System Action: The initialization of the OS/EM function is terminated.

Operator Response: Notify the system programmer.

System Programmer Response: Check the OS/EM installation instructions and increase the size of the dataset to the size indicated. Then reactivate the OS/EM function.

FEMX00169

NO SPACE AVAILABLE IN HCT PATCH AREA FOR OS/EM USE

Explanation: During JES2 initialization, OS/EM requires 3 words (12 bytes) in the HASP Control Table (HCT) patch area. However, local modifications have exhausted the HCT patch area.

Source: FEMJ2X00

System Action: JES2 initialization fails.

Operator Response: Notify the system programmer.

System Programmer Response: Check all local JES2 modifications and make necessary changes to ensure that three (not necessarily contiguous) words are available in the HCT patch area for OS/EM initialization.

FEMHSP170

OS/EM OPTION NOT SUPPORTED FOR JES2 RELEASE rel

Explanation: While initializing a JES2 function, OS/EM has determined that the current JES2 release is not supported.

rel: The JES2 release that is currently active.

Source: FEMHJ20

System Action: The OS/EM JES2 function initialization fails.

Operator Response: Notify the system programmer.

System Programmer Response: Disable the OS/EM JES2 functions until JES2 is upgraded to a supported release.

FEMJS2170

OS/EM OPTION NOT SUPPORTED FOR JES2 RELEASE rel

Explanation: While initializing a JES2 function, OS/EM has determined that the current JES2 release is not supported.

rel: The JES2 release that is currently active.

Source: FEMJES2A through FEMJES2H

System Action: The OS/EM JES2 function initialization fails.

Operator Response: Notify the system programmer.

System Programmer Response: Disable the OS/EM JES2 functions until JES2 is upgraded to a supported release.

FEMRELI70

OS/EM OPTION NOT SUPPORTED FOR JES2 RELEASE rel

Explanation: While initializing a JES2 function, OS/EM has determined that the current JES2 release is not supported.

rel: The JES2 release that is currently active.

Source: FEMRELOD

System Action: The OS/EM JES2 function initialization fails.

Operator Response: Notify the system programmer.

System Programmer Response: Disable the OS/EM JES2 functions until JES2 is upgraded to a supported release.

FEMLOD171

OFFSET ADJUSTMENT FAILED FOR subsys MODULE modname.

Explanation: The adjustment of the JES2 offsets in the named module failed.

subsys: The name of the JES2 subsystem.

modname: The load module name.

Source: FEMLOAD

System Action: The module is deleted.

Operator Response: Notify the system programmer.

System Programmer Response: Check that the load module is for the correct JES2 and OS/EM. Check that the module has not been corrupted. If necessary, call OS/EM technical support.

FEMRELI71

OFFSET ADJUSTMENT FAILED FOR subsys MODULE modname.

Explanation: The adjustment of the JES2 offsets in the named module failed.

subsys: The name of the JES2 subsystem.

modname: The load module name.

Source: FEMRELOD

System Action: The module is deleted.

Operator Response: Notify the system programmer.

System Programmer Response: Check that the load module is for the correct JES2 and OS/EM. Check that the module has not been corrupted. If necessary, call OS/EM technical support.

FEMTPS172

JOB xxx IS WAITING FOR A SHARED TAPE DEVICE

Explanation: The named job requires a tape device but no device is currently available. The system may have issued an IEF238D message if no suitable device is currently attached to this system or may be waiting with no message if a device that can satisfy the allocation is on this system but is currently in use by another job. If a WTOR has been issued, tape share will respond to the message as soon as a device can be acquired from another system.

xxx: Job name

Source: FEMTPSHR

System Action: Waits for device.

Operator Response: None. Informational message only.

System Programmer Response: None.

FEMALC173

TAPESHR IS ACTIVE. CANNOT CHANGE DATASET NAME

Explanation: The FEMCNTL command was issued to activate TAPESHR and a new communication dataset name was specified. TAPESHR is already active and using a different communication dataset name so the name cannot be changed. The currently active dataset name will continue to be used.

Source: FEMALLO1

System Action: No action taken. TAPESHR continues with the currently active communication dataset.

Operator Response: None.

System Programmer Response: None.

FEMALC174

TAPESHR DSN IS REQUIRED

Explanation: The FEMCNTL command was issued to activate TAPESHR and a name for the communication dataset was not given. The communication dataset is required and a name must be specified.

Source: FEMALLO1

System Action: TAPESHR is not started.

Operator Response: Reissue the FEMCNTL command specifying the name of the previously allocated dataset to be used.

System Programmer Response: None.

FEMALC175

DEVICE xx(x) CANNOT BE action TAPESHR. REASON rr

Explanation: An FEMCNTL command was issued to request that TAPESHR either **add** the device(s) to its control, **delete** the device(s) from its control, or **vary** the device online or offline, globally or locally. TAPESHR is unable to complete the request for the reason indicated by the reason code:

4 = The device cannot be added because it is already controlled.

8 = The device cannot be added because it is not a valid tape device present on this system, or cannot be varied because it is not controlled by TAPESHR.

xx(x): Device address.

action: Either **ADDED TO**, **DELETED FROM**, or **VARIED BY**.

Source: FEMALLO1

System Action: The FEMCNTL does not complete.

Operator Response: Reissue the command specifying a valid device number.

System Programmer Response: None.

FEMTPS176

TAPESHR UNABLE TO START. ALREADY 32 ACTIVE SYSTEMS.

Explanation: There are already 32 systems participating in the TAPESHR complex. That is the maximum number of systems that can be active concurrently.

Source: FEMTPSHR

System Action: TAPESHR does not start.

Operator Response: Do not attempt to start TAPESHR on more than 32 systems.

System Programmer Response: None.

FEMTPS177

TAPESHR SHUTDOWN WAITING FOR DEVICES TO GO OFFLINE

Explanation: Shutdown of TAPESHR was requested specifying (or defaulting to) the **GLOBALOFFLINE**, or the **WAIT** option. TAPESHR has attempted to vary offline all the TAPESHR devices present on the system that are currently online, in order to make them available to other systems. It is now waiting for those devices to go offline.

Source: FEMTPSHR

System Action: TAPESHR waits for devices to become available.

Operator Response: None. If the **WAIT** option was specified, TAPESHR will continue to wait until all the devices have gone offline. If the **GLOBALOFFLINE** option was chosen or was taken as a default, TAPESHR will wait for 15 seconds for devices to go offline and will then mark those that have not gone offline as **GLOBALLY OFFLINE**.

Note: It is the operator's responsibility to ensure that the devices which did not go offline are not made eligible for TAPESHR selection (by issuing **VARY ONLINE,GLOBAL**) until those devices are actually offline on the system where TAPESHR was shut down.

System Programmer Response: None.

FEMALC178

FEMTPSHR IS NOT ACTIVE; REQUEST NOT PROCESSED

Explanation: An FEMCNTL command to change TAPESHR parameters was issued but TAPESHR is not currently active.

Source: FEMALLO1

System Action: The command is ignored.

Operator Response: Start TAPESHR via the FEMCNTL function if desired.

System Programmer Response: None.

FEMALC179

DEVICE xxx(yyy) ADDED/DELETED.

Explanation: The named device has been added to or deleted from TAPESHR control in response to an FEMCNTL command or an operator command.

Source: FEMALLO1

System Action: TAPESHR continues with the new list of devices.

Operator Response: None. This message is informational only.

System Programmer Response: None

FEMTPS179

DEVICE xxx(yyy) ADDED/DELETED.

Explanation: The named device has been added to or deleted from TAPESHR control in response to an FEMCNTL command or an operator command.

Source: FEMTPSHR

System Action: TAPESHR continues with the new list of devices.

Operator Response: None. This message is informational only.

System Programmer Response: None

FEMTPS180

TAPESHR COMMUNICATION FILE IS INVALID

Explanation: FEMTPSHR has found that the communication file does not contain valid data.

Source: FEMTPSHR

System Action: FEMTPSHR terminates.

Operator Response: Notify the system programmer.

System Programmer Response: Shutdown TAPESHR on all systems, delete and reallocate the communication file. Restart TAPESHR, verifying that all the desired devices are being controlled correctly. If the error was not caused by a hardware problem, it may be that some TSO user opened the communication dataset for output. Consider using RACF or some other security product to protect the dataset from corruption.

FEMTPS181

TAPESHR ALREADY ACTIVE

Explanation: FEMTPSHR is being started and has determined that another FEMTPSHR is already active.

System Action: The second FEMTPSHR ends.

Source: FEMTPSHR

Operator Response: Verify that another copy of FEMTPSHR is actually running. If it is, do not attempt to start another. If it is not then this indicates a problem with the TAPESHR system; notify the system programmer.

System Programmer Response: Determine the circumstances where this message was issued. If it was not caused by an operator issuing a start for a second FEMTPSHR then issue a **FEMCNTL DUMP ALLOC** command, save the output, and contact Trident Services for support.

FEMTPS182

***WARNING* DEV xxx(yyy) IS ONLINE TO MULTIPLE SYSTEMS**

Explanation: FEMTPSHR has found that the named device is online to more than one system. A **VARY OFFLINE** command has been issued to attempt to correct this problem. This condition should never be created by TAPESHR, though it may be detected by TAPESHR at startup time.

xxx: Device address.

System Action: The device is varied offline.

Source: FEMTPSHR

Operator Response: Vary the device offline on other systems and verify that the device is not allocated by more than one job. If it is allocated by more than one job, any tape on the drive may be corrupted and the persons responsible for the jobs should be notified of that possibility.

System Programmer Response: If this message occurred at other than startup time, it may indicate a problem with TAPESHR. Determine the circumstances under which it was issued, including any operator commands and messages regarding the tape device, and call Trident Services for support.

FEMALC183

DEVICE xxx(yyy) IN/PENDING LOCAL/GLOBAL ON/OFFLINE MODE

Explanation: This message is issued in response to an FEMCNTL command or an operator command to change the TAPESHR status of a device.

xxx: Device address.

Source: FEMALLO1

System Action: None. Informational message only.

Operator Response: None.

System Programmer Response: None.

FEMTPS183

DEVICE xxx(yyy) IN/PENDING LOCAL/GLOBAL ON/OFFLINE MODE

Explanation: This message is issued in response to an FEMCNTL command or an operator command to change the TAPESHR status of a device.

xxx: Device address.

Source: FEMTPSHR

System Action: None. Informational message only.

Operator Response: None.

System Programmer Response: None.

FEMTPS184

CONFIRM RESET OF SYSTEM xxxx. REPLY "Y" TO CONFIRM, "N" TO DENY

Explanation: FEMTPSHR has determined, by noting that the timestamps in the communication file have not changed recently, that the named system may have stopped running. This may be caused

by a system reset, a loop, a failure of FEMTPSHR on that system, or a reserve lockout. It is asking the operator to verify that the system is really shutdown and that the tapes that were attached to that system may be returned to the available device pool.

xxxx: System ID.

Source: FEMTPSHR

System Action: Waits for reply from operator.

Operator Response: If the system is really shut down, reply "Y" and the tapes that were owned by that system will be released. If FEMTPSHR has accidentally terminated on that system, issue the command:

```
S FEMTPSHR.FEMTPSHR, SUB=MSTR
```

to restart it. If there is some other unusual reason that the system is temporarily not active but will resume shortly, reply "N" to allow the system to retain possession of the tape resources that it owns. In any other case notify the system programmer.

System Programmer Response: Determine why FEMTPSHR is not running on the named system and either reply to the message or restart FEMTPSHR.

FEMCMD185

DEVICE xxx IS NOT CONTROLLED BY TAPESHR - IGNORED

Explanation: The operator has issued a vary command to change the TAPESHR status of a device, but that device is not controlled by TAPESHR.

xxx: Device address.

Source: FEMCMD

System Action: The command is ignored.

Operator Response: If the device should be controlled by TAPESHR, issue a command to add it to TAPESHR's control. Otherwise the device is ignored and no action is required.

System Programmer Response: None.

FEMTPS186

INVALID MODIFY COMMAND

Explanation: The operator issued a modify command to TAPESHR that was syntactically incorrect.

Source: FEMTPSHR

System Action: The command is ignored.

Operator Response: Reissue the modify command with the correct syntax.

System Programmer Response: None.

FEMTPS187

FEMTPSHR INITIALIZATION COMPLETE

Explanation: FEMTPSHR has completed initialization and is now processing normally.

Source: FEMTPSHR

Operator Response: None.

System Programmer Response: None.

FEMCMD188

DEVICE xxx(xxx) IS UNAVAILABLE

Explanation: The operator has issued a vary online command for the named device. The device is not currently available, either because it is marked as offline (locally or globally), or because it is currently owned by another system.

xxx: Device address.

Source: FEMCMD

System Action: The command is ignored.

Operator Response: Issue a display command for the device to determine why it is not available. If the device must be brought online on this system, vary it offline on the owning system, vary it online globally, or vary it online locally as indicated by the display command. Then reissue the vary online command.

System Programmer Response: None.

FEMCMD189

UNABLE TO DETERMINE DEVICE STATUS

Explanation: The operator has issued a vary online command for the named device and the command processing routine is unable to communicate with FEMTPSHR to determine the current status of the device.

Source: FEMCMD

System Action: The command is ignored.

Operator Response: Verify that FEMTPSHR is active. If not, start it by issuing a start command:

```
S FEMTPSHR.FEMTPSHR, SUB=MSTR
```

If it is active, notify the system programmer.

System Programmer Response: Attempt to determine why FEMTPSHR is not responding to requests. If able, dump the FEMTPSHR address space, restart FEMTPSHR, and call Trident Services for support.

FEMALC190

START OF FEMTPSHR FAILED. CHECK SYSLOG.

Explanation: FEMCNTL has issued a start command for FEMTPSHR, but FEMTPSHR has failed to initialize.

Source: FEMALLO1

Operator Response: Notify the system programmer.

System Programmer Response: Check the syslog to verify that the start command was issued successfully. Check for JCL errors. When the cause of the error has been determined, reissue the failing start command.

FEMIP191

DYNAMIC CONCATENTION FAILED. RC = nn

Explanation: OS/EM was unable to concatenate the libraries specified for the Dynamic Steplib facility.

nn: The return code from the dynamic allocation request.

Source: FEMIP1

System Action: The job will either continue without the specified library, or will be failed based on the Steplib Controls.

Operator Response: Notify the system programmer.

System Programmer Response: Verify that the library is available and that the job has RACF authority to read the dataset.

FEMLIB191

DYNAMIC CONCATENTION FAILED. RC = nn

Explanation: OS/EM was unable to concatenate the libraries specified for the Dynamic Steplib facility.

nn: The return code from the dynamic allocation request.

Source: FEMLIB

System Action: The job will either continue without the specified library, or will be failed based on the Steplib Controls.

Operator Response: Notify the system programmer.

System Programmer Response: Verify that the library is available and that the job has RACF authority to read the dataset.

FEMW21191

DYNAMIC CONCATENTION FAILED. RC = nn

Explanation: OS/EM was unable to concatenate the libraries specified for the Dynamic Steplib facility.

nn: The return code from the dynamic allocation request.

Source: FEMW21SD

System Action: The job will either continue without the specified library, or will be failed based on the Steplib Controls.

Operator Response: Notify the system programmer.

System Programmer Response: Verify that the library is available and that the job has RACF authority to read the dataset.

FEMW21192

ACTIVE STEPLIB CONCATENATION: xxxx.xxxx.xxxx

Explanation: OS/EM has added to or created a steplib for the effected job.

Source: FEMW21SD

Operator Response: None.

System Programmer Response: None.

FEMUTL193

USER xxxx DISCONNECTED FROM TERMINAL yyyy.

Explanation: FEMUTL has disconnected user xxxx from terminal yyyy based on OS/EM Time Limit Controls.

Source: FEMUTL

Operator Response: None.

System Programmer Response: None.

FEMS19194

OS/EM MONITORING xxxx DCB.

Explanation: OS/EM is monitoring the file allocated to the specified DCB for messages to be transferred to the SYSLOG. See the WTO Function.

Source: FEM0001I

Operator Response: None.

System Programmer Response: None.

FEMS22194

OS/EM MONITORING xxxx DCB.

Explanation: OS/EM is monitoring the file allocated to the specified DCB for messages to be transferred to the SYSLOG. See the WTO Function.

Source: FEM0002B

Operator Response: None.

System Programmer Response: None.

FEMREL196

NO OS/EM EXIT SUPPORTED FOR JES2 VERSION xx EXIT yyyy

Explanation: The User has tried to reload an OS/EM exit on a system running JES2 version xx which does not support the specified exit at exit point yyyy.

Source: FEMRELOD

Operator Response: Notify the System Programmer.

System Programmer Response: Provide the user with the proper OS/EM exit to reload, or provide the proper system name where the reload command should be executed.

FEMJS2197

NO LONGER ABLE TO CHANGE JES2 VERSION

Explanation: Attempted to change the version number of a JES2 subsystem after it has become active.

Source: FEMJES2

Source: FEMJES2A through FEMJES2H

Operator Response: Notify the System Programmer.

System Programmer Response: After an alternate JES2 subsystem has become active you may no longer change the version number of exits that OS/EM will load. If the incorrect version was specified, the JES2 subsystem must be stopped before the version can be changed.

FEMREL197

NO LONGER ABLE TO CHANGE JES2 VERSION

Explanation: Attempted to change the version number of a JES2 subsystem after it has become active.

Source: FEMRELOD

Operator Response: Notify the System Programmer.

System Programmer Response: After an alternate JES2 subsystem has become active you may no longer change the version number of exits that OS/EM will load. If the incorrect version was specified, the JES2 subsystem must be stopped before the version can be changed.

FEMLOD198

subsys OFFSET TABLE NOT AVAILABLE

Explanation: The JES subsystem could not locate the appropriate JES2 Offset Table (FEMJ2OFx).

subsys: The JES2 subsystem name.

Source: FEMLOAD

System Action: Load of JES2 module fails.

Operator Response: None.

System Programmer Response: Assemble the JES2 Offset Table using the SYS1.MACLIB and SYS1.HASPSRC datasets that are appropriate for that JES2 subsystem. Refer to the OS/EM Installation Guide and OS/EM User Guide for more information.

FEMUXW199

FEMUXWTO ABENDING TO PREVENT WTO LOOP

Explanation: The JES3 test WTO module has detected that it has been called by the JES3 WTO user exit IATUX31. To avoid a WTO loop, an ABEND will be invoked.

Source: FEMUXWTO

System Action: The module ABENDS.

Operator Response: None.

System Programmer Response: Ensure that the JES3 user exit IATUX31 does not invoke the OS/EM test module FEMUXWTO.

FEMUXW200

OS/EM EXIT exitname ENTERED

Explanation: The JES3 test exit module FEMUXWTO has been invoked.

exitname: The name of the JES3 exit that has called FEMUXWTO.

Source: FEMUXWTO

System Action: Information message.

Operator Response: None.

System Programmer Response: None.

FEMUXA201

OS/EM JES3 EXIT exitname INTENTIONAL ABEND

Explanation: The JES3 test exit module FEMUXABN has been invoked and will initiate an intentional ABEND.

exitname: The name of the JES3 exit that has called FEMUXABN.

Source: FEMUXABN

System Action: Information message.

Operator Response: None.

System Programmer Response: None.

FEMLOD202

***WARNING* - UNABLE TO LOCATE VERSION IN MODULE modname; MAY BE INCORRECT**

Explanation: An OS/EM module or a JES2 user module has been loaded but the version information could not be located.

modname: The name of the JES2 module that was loaded.

Source: FEMLOAD

System Action: Information message.

Operator Response: None.

System Programmer Response: If the module is a JES2 user module, check the source code of the named module and ensure that the \$ENTRY macro is correctly coded. If the module is an OS/EM module, contact OS/EM customer support.

FEM IPL203

PROCESSOR DOES NOT SUPPORT REQUIRED function HARDWARE FEATURE

Explanation: The user is attempting to initialize OS/EM 6.0 or later on a processor that does not support required hardware functions.

function: The hardware function that OS/EM requires. Essential hardware functions are 'Perform Locked Operation' and 'Relative Branch'.

Source: FEM IPL

System Action: OS/EM initialization fails.

Operator Response: None.

System Programmer Response: This OS/EM version will not operate on the current processor. Revert back to your previous version of OS/EM (5.6 or earlier) until your processor is upgraded. If this is a new OS/EM installation, contact OS/EM support and request the OS/EM 5.6 installation tapes.

FEMREL204

RACF modname MODULE status

Explanation: A RACF module was activated or reset.

modname: The RACF module name (ICHRIN03, ICHRCDE or ICHFR01).

status: The status of the module (ACTIVATED or RESET).

Source: FEMRELOD

Operator Response: None.

System Programmer Response: None.

FEMREL205

NO subsys VERSION AVAILABLE; UNABLE TO LOAD MODULE modname

Explanation: OS/EM could not locate a version of the OS/EM module that coincides with the release level of the named JES2 subsystem.

subsys: The name of the JES2 subsystem.

modname: The name of the OS/EM module.

Source: FEMRELOD

System Action: The load of the module fails and the associated OS/EM JES2 function is disabled.

Operator Response: None.

System Programmer Response: OS/EM JES2 modules have a one-byte suffix and, when a module is to be loaded, the system determines the suffix based on the release level of the JES2 system (e.g. FEMJ2D0G & FEMJ2D0H are the OS/EM FEMJ2D0 modules for different JES2 releases). When this message is issued, OS/EM could not locate the OS/EM module for that JES2 system could not be found.

Check the LINKLST to ensure that the current OS/EM load library is included in the search list. If it is present, contact OS/EM support (note your JES2 release level).

FEMACN206

ABEND AREGS 0-3: nnnnnnnn nnnnnnnn nnnnnnnn nnnnnnnn

Explanation: The OS/EM has detected a MVS System Abend during execution of an OS/EM optional function or a User exit.

nnnnnnnn: Contents of the Access Register.

Source: FEMALCCN

System Action: The OS/EM function being executed continues, OS/EM takes a SVC dump for the abending module, takes the abending module out of service, and deletes the abending module from CSA/ECSA. See messages FEMxxx023, FEMxxx026 and FEMxxx029.

Operator Response: Contact System Programmer.

System Programmer Response: Use IPCS to determine the cause for the ABEND, take the corrective action required, perform an LLA,REFRESH, and reload the failing module using the OS/EM ISPF RELOAD facility. Contact OS/EM support for assistance in problem resolution.

FEMALC206

ABEND AREGS 0-3: nnnnnnnn nnnnnnnn nnnnnnnn nnnnnnnn

Explanation: The OS/EM has detected a MVS System Abend during execution of an OS/EM optional function or a User exit.

nnnnnnnn: Contents of the Access Register.

Source: FEMALLO0,FEMALLO1

System Action: The OS/EM function being executed continues, OS/EM takes a SVC dump for the abending module, takes the abending module out of service, and deletes the abending module from CSA/ECSA. See messages FEMxxx023, FEMxxx026 and FEMxxx029.

Operator Response: Contact System Programmer.

System Programmer Response: Use IPCS to determine the cause for the ABEND, take the corrective action required, perform an LLA,REFRESH, and reload the failing module using the OS/EM ISPF RELOAD facility. Contact OS/EM support for assistance in problem resolution.

FEMASY206

ABEND AREGS 0-3: nnnnnnnn nnnnnnnn nnnnnnnn nnnnnnnn

Explanation: The OS/EM has detected a MVS System Abend during execution of an OS/EM optional function or a User exit.

nnnnnnnn: Contents of the Access Register.

Source: FEMASYNC

System Action: The OS/EM function being executed continues, OS/EM takes a SVC dump for the abending module, takes the abending module out of service, and deletes the abending module from CSA/ECSA. See messages FEMxxx023, FEMxxx026 and FEMxxx029.

Operator Response: Contact System Programmer.

System Programmer Response: Use IPCS to determine the cause for the ABEND, take the corrective action required, perform an LLA,REFRESH, and reload the failing module using the OS/EM ISPF RELOAD facility. Contact OS/EM support for assistance in problem resolution.

FEMCMD206

ABEND AREGS 0-3: nnnnnnnn nnnnnnnn nnnnnnnn nnnnnnnn

Explanation: The OS/EM has detected a MVS System Abend during execution of an OS/EM optional function or a User exit.

nnnnnnnn: Contents of the Access Register.

Source: FEMCMD

System Action: The OS/EM function being executed continues, OS/EM takes a SVC dump for the abending module, takes the abending module out of service, and deletes the abending module from CSA/ECSA. See messages FEMxxx023, FEMxxx026 and FEMxxx029.

Operator Response: Contact System Programmer.

System Programmer Response: Use IPCS to determine the cause for the ABEND, take the corrective action required, perform an LLA,REFRESH, and reload the failing module using the OS/EM ISPF RELOAD facility. Contact OS/EM support for assistance in problem resolution.

FEMCOM206

ABEND AREGS 0-3: nnnnnnnn nnnnnnnn nnnnnnnn nnnnnnnn

Explanation: The OS/EM has detected a MVS System Abend during execution of an OS/EM optional function or a User exit.

nnnnnnnn: Contents of the Access Register.

Source: FEMCOMM

System Action: The OS/EM function being executed continues, OS/EM takes a SVC dump for the abending module, takes the abending module out of service, and deletes the abending module from CSA/ECSA. See messages FEMxxx023, FEMxxx026 and FEMxxx029.

Operator Response: Contact System Programmer.

System Programmer Response: Use IPCS to determine the cause for the ABEND, take the corrective action required, perform an LLA,REFRESH, and reload the failing module using the OS/EM ISPF RELOAD facility. Contact OS/EM support for assistance in problem resolution.

FEMDCN206

ABEND AREGS 0-3: nnnnnnnn nnnnnnnn nnnnnnnn nnnnnnnn

Explanation: The OS/EM has detected a MVS System Abend during execution of an OS/EM optional function or a User exit.

nnnnnnnn: Contents of the Access Register.

Source: FEMDADCN

System Action: The OS/EM function being executed continues, OS/EM takes a SVC dump for the abending module, takes the abending module out of service, and deletes the abending module from CSA/ECSA. See messages FEMxxx023, FEMxxx026 and FEMxxx029.

Operator Response: Contact System Programmer.

System Programmer Response: Use IPCS to determine the cause for the ABEND, take the corrective action required, perform an LLA,REFRESH, and reload the failing module using the OS/EM ISPF RELOAD facility. Contact OS/EM support for assistance in problem resolution.

FEMDC1206

ABEND AREGS 0-3: nnnnnnnn nnnnnnnn nnnnnnnn nnnnnnnn

Explanation: The OS/EM has detected a MVS System Abend during execution of an OS/EM optional function or a User exit.

nnnnnnnn: Contents of the Access Register.

Source: FEMDCB1

System Action: The OS/EM function being executed continues, OS/EM takes a SVC dump for the abending module, takes the abending module out of service, and deletes the abending module from CSA/ECSA. See messages FEMxxx023, FEMxxx026 and FEMxxx029.

Operator Response: Contact System Programmer.

System Programmer Response: Use IPCS to determine the cause for the ABEND, take the corrective action required, perform an LLA,REFRESH, and reload the failing module using the OS/EM ISPF RELOAD facility. Contact OS/EM support for assistance in problem resolution.

FEMEXR206

ABEND AREGS 0-3: nnnnnnnn nnnnnnnn nnnnnnnn nnnnnnnn

Explanation: The OS/EM has detected a MVS System Abend during execution of an OS/EM optional function or a User exit.

nnnnnnnn: Contents of the Access Register.

Source: FEMEXRTN

System Action: The OS/EM function being executed continues, OS/EM takes a SVC dump for the abending module, takes the abending module out of service, and deletes the abending module from CSA/ECSA. See messages FEMxxx023, FEMxxx026 and FEMxxx029.

Operator Response: Contact System Programmer.

System Programmer Response: Use IPCS to determine the cause for the ABEND, take the corrective action required, perform an LLA,REFRESH, and reload the failing module using the OS/EM ISPF RELOAD facility. Contact OS/EM support for assistance in problem resolution.

FEMFRA206

ABEND AREGS 0-3: nnnnnnnn nnnnnnnn nnnnnnnn nnnnnnnn

Explanation: The OS/EM has detected a MVS System Abend during execution of an OS/EM optional function or a User exit.

nnnnnnnn: Contents of the Access Register.

Source: FEMFRACN

System Action: The OS/EM function being executed continues, OS/EM takes a SVC dump for the abending module, takes the abending module out of service, and deletes the abending module from CSA/ECSA. See messages FEMxxx023, FEMxxx026 and FEMxxx029.

Operator Response: Contact System Programmer.

System Programmer Response: Use IPCS to determine the cause for the ABEND, take the corrective action required, perform an LLA,REFRESH, and reload the failing module using the OS/EM ISPF RELOAD facility. Contact OS/EM support for assistance in problem resolution.

FEMFTN206

ABEND AREGS 0-3: nnnnnnnn nnnnnnnn nnnnnnnn nnnnnnnn

Explanation: The OS/EM has detected a MVS System Abend during execution of an OS/EM optional function or a User exit.

nnnnnnnn: Contents of the Access Register.

Source: FEMFRRTN

System Action: The OS/EM function being executed continues, OS/EM takes a SVC dump for the abending module, takes the abending module out of service, and deletes the abending module from CSA/ECSA. See messages FEMxxx023, FEMxxx026 and FEMxxx029.

Operator Response: Contact System Programmer.

System Programmer Response: Use IPCS to determine the cause for the ABEND, take the corrective action required, perform an LLA,REFRESH, and reload the failing module using the OS/EM ISPF RELOAD facility. Contact OS/EM support for assistance in problem resolution.

FEMHCN206

ABEND AREGS 0-3: nnnnnnnn nnnnnnnn nnnnnnnn nnnnnnnn

Explanation: The OS/EM has detected a MVS System Abend during execution of an OS/EM optional function or a User exit.

nnnnnnnn: Contents of the Access Register.

Source: FEMHSMCN

System Action: The OS/EM function being executed continues, OS/EM takes a SVC dump for the abending module, takes the abending module out of service, and deletes the abending module from CSA/ECSA. See messages FEMxxx023, FEMxxx026 and FEMxxx029.

Operator Response: Contact System Programmer.

System Programmer Response: Use IPCS to determine the cause for the ABEND, take the corrective action required, perform an LLA,REFRESH, and reload the failing module using the OS/EM ISPF RELOAD facility. Contact OS/EM support for assistance in problem resolution.

FEMHSP206

ABEND AREGS 0-3: nnnnnnnn nnnnnnnn nnnnnnnn nnnnnnnn

Explanation: The OS/EM has detected a MVS System Abend during execution of an OS/EM optional function or a User exit.

nnnnnnnn: Contents of the Access Register.

Source: FEMHJ20

System Action: The OS/EM function being executed continues, OS/EM takes a SVC dump for the abending module, takes the abending module out of service, and deletes the abending module from CSA/ECSA. See messages FEMxxx023, FEMxxx026 and FEMxxx029.

Operator Response: Contact System Programmer.

System Programmer Response: Use IPCS to determine the cause for the ABEND, take the corrective action required, perform an LLA,REFRESH, and reload the failing module using the OS/EM ISPF RELOAD facility. Contact OS/EM support for assistance in problem resolution.

FEMIAT206

ABEND AREGS 0-3: nnnnnnnn nnnnnnnn nnnnnnnn nnnnnnnn

Explanation: The OS/EM has detected a MVS System Abend during execution of an OS/EM optional function or a User exit.

nnnnnnnn: Contents of the Access Register.

Source: FEMINTK

System Action: The OS/EM function being executed continues, OS/EM takes a SVC dump for the abending module, takes the abending module out of service, and deletes the abending module from CSA/ECSA. See messages FEMxxx023, FEMxxx026 and FEMxxx029.

Operator Response: Contact System Programmer.

System Programmer Response: Use IPCS to determine the cause for the ABEND, take the corrective action required, perform an LLA,REFRESH, and reload the failing module using the OS/EM ISPF RELOAD facility. Contact OS/EM support for assistance in problem resolution.

FEMICN206

ABEND AREGS 0-3: nnnnnnnn nnnnnnnn nnnnnnnn nnnnnnnn

Explanation: The OS/EM has detected a MVS System Abend during execution of an OS/EM optional function or a User exit.

nnnnnnnn: Contents of the Access Register.

Source: FEMISPCN

System Action: The OS/EM function being executed continues, OS/EM takes a SVC dump for the abending module, takes the abending module out of service, and deletes the abending module from CSA/ECSA. See messages FEMxxx023, FEMxxx026 and FEMxxx029.

Operator Response: Contact System Programmer.

System Programmer Response: Use IPCS to determine the cause for the ABEND, take the corrective action required, perform an LLA,REFRESH, and reload the failing module using the OS/EM ISPF RELOAD facility. Contact OS/EM support for assistance in problem resolution.

FEMIPL206

ABEND AREGS 0-3: nnnnnnnn nnnnnnnn nnnnnnnn nnnnnnnn

Explanation: The OS/EM has detected a MVS System Abend during execution of an OS/EM optional function or a User exit.

nnnnnnnn: Contents of the Access Register.

Source: FEMIPL

System Action: The OS/EM function being executed continues, OS/EM takes a SVC dump for the abending module, takes the abending module out of service, and deletes the abending module from CSA/ECSA. See messages FEMxxx023, FEMxxx026 and FEMxxx029.

Operator Response: Contact System Programmer.

System Programmer Response: Use IPCS to determine the cause for the ABEND, take the corrective action required, perform an LLA,REFRESH, and reload the failing module using the OS/EM ISPF RELOAD facility. Contact OS/EM support for assistance in problem resolution.

FEMJS2206

ABEND AREGS 0-3: nnnnnnnn nnnnnnnn nnnnnnnn nnnnnnnn

Explanation: The OS/EM has detected a MVS System Abend during execution of an OS/EM optional function or a User exit.

nnnnnnnn: Contents of the Access Register.

Source: FEMJES2B,FEMJES2G

System Action: The OS/EM function being executed continues, OS/EM takes a SVC dump for the abending module, takes the abending module out of service, and deletes the abending module from CSA/ECSA. See messages FEMxxx023, FEMxxx026 and FEMxxx029.

Operator Response: Contact System Programmer.

System Programmer Response: Use IPCS to determine the cause for the ABEND, take the corrective action required, perform an LLA,REFRESH, and reload the failing module using the OS/EM ISPF RELOAD facility. Contact OS/EM support for assistance in problem resolution.

FEMJ2M206

ABEND AREGS 0-3: nnnnnnnn nnnnnnnn nnnnnnnn nnnnnnnn

Explanation: The OS/EM has detected a MVS System Abend during execution of an OS/EM optional function or a User exit.

nnnnnnnn: Contents of the Access Register.

Source: FEMJ2MCx

System Action: The OS/EM function being executed continues, OS/EM takes a SVC dump for the abending module, takes the abending module out of service, and deletes the abending module from CSA/ECSA. See messages FEMxxx023, FEMxxx026 and FEMxxx029.

Operator Response: Contact System Programmer.

System Programmer Response: Use IPCS to determine the cause for the ABEND, take the corrective action required, perform an LLA,REFRESH, and reload the failing module using the OS/EM ISPF RELOAD facility. Contact OS/EM support for assistance in problem resolution.

FEMJ2R206

ABEND AREGS 0-3: nnnnnnnn nnnnnnnn nnnnnnnn nnnnnnnn

Explanation: The OS/EM has detected a MVS System Abend during execution of an OS/EM optional function or a User exit.

nnnnnnnn: Contents of the Access Register.

Source: FEMJ2ERx

System Action: The OS/EM function being executed continues, OS/EM takes a SVC dump for the abending module, takes the abending module out of service, and deletes the abending module from CSA/ECSA. See messages FEMxxx023, FEMxxx026 and FEMxxx029.

Operator Response: Contact System Programmer.

System Programmer Response: Use IPCS to determine the cause for the ABEND, take the corrective action required, perform an LLA,REFRESH, and reload the failing module using the OS/EM ISPF RELOAD facility. Contact OS/EM support for assistance in problem resolution.

FEMJ2S206

ABEND AREGS 0-3: nnnnnnnn nnnnnnnn nnnnnnnn nnnnnnnn

Explanation: The OS/EM has detected a MVS System Abend during execution of an OS/EM optional function or a User exit.

nnnnnnnn: Contents of the Access Register.

Source: FEMJ2SCx

System Action: The OS/EM function being executed continues, OS/EM takes a SVC dump for the abending module, takes the abending module out of service, and deletes the abending module from CSA/ECSA. See messages FEMxxx023, FEMxxx026 and FEMxxx029.

Operator Response: Contact System Programmer.

System Programmer Response: Use IPCS to determine the cause for the ABEND, take the corrective action required, perform an LLA,REFRESH, and reload the failing module using the OS/EM ISPF RELOAD facility. Contact OS/EM support for assistance in problem resolution.

FEMJ3E206

ABEND AREGS 0-3: nnnnnnnn nnnnnnnn nnnnnnnn nnnnnnnn

Explanation: The OS/EM has detected a MVS System Abend during execution of an OS/EM optional function or a User exit.

nnnnnnnn: Contents of the Access Register.

Source: FEMJ3ECN

System Action: The OS/EM function being executed continues, OS/EM takes a SVC dump for the abending module, takes the abending module out of service, and deletes the abending module from CSA/ECSA. See messages FEMxxx023, FEMxxx026 and FEMxxx029.

Operator Response: Contact System Programmer.

System Programmer Response: Use IPCS to determine the cause for the ABEND, take the corrective action required, perform an LLA,REFRESH, and reload the failing module using the OS/EM ISPF RELOAD facility. Contact OS/EM support for assistance in problem resolution.

FEMJ3S206

ABEND AREGS 0-3: nnnnnnnn nnnnnnnn nnnnnnnn nnnnnnnn

Explanation: The OS/EM has detected a MVS System Abend during execution of an OS/EM optional function or a User exit.

nnnnnnnn: Contents of the Access Register.

Source: FEMJ3SVC

System Action: The OS/EM function being executed continues, OS/EM takes a SVC dump for the abending module, takes the abending module out of service, and deletes the abending module from CSA/ECSA. See messages FEMxxx023, FEMxxx026 and FEMxxx029.

Operator Response: Contact System Programmer.

System Programmer Response: Use IPCS to determine the cause for the ABEND, take the corrective action required, perform an LLA,REFRESH, and reload the failing module using the OS/EM ISPF RELOAD facility. Contact OS/EM support for assistance in problem resolution.

FEMLOK206

ABEND AREGS 0-3: nnnnnnnn nnnnnnnn nnnnnnnn nnnnnnnn

Explanation: The OS/EM has detected a MVS System Abend during execution of an OS/EM optional function or a User exit.

nnnnnnnn: Contents of the Access Register.

Source: FEMLOCK

System Action: The OS/EM function being executed continues, OS/EM takes a SVC dump for the abending module, takes the abending module out of service, and deletes the abending module from CSA/ECSA. See messages FEMxxx023, FEMxxx026 and FEMxxx029.

Operator Response: Contact System Programmer.

System Programmer Response: Use IPCS to determine the cause for the ABEND, take the corrective action required, perform an LLA,REFRESH, and reload the failing module using the OS/EM ISPF RELOAD facility. Contact OS/EM support for assistance in problem resolution.

FEMRCN206

ABEND AREGS 0-3: nnnnnnnn nnnnnnnn nnnnnnnn nnnnnnnn

Explanation: The OS/EM has detected a MVS System Abend during execution of an OS/EM optional function or a User exit.

nnnnnnnn: Contents of the Access Register.

Source: FEMRACCN

System Action: The OS/EM function being executed continues, OS/EM takes a SVC dump for the abending module, takes the abending module out of service, and deletes the abending module from CSA/ECSA. See messages FEMxxx023, FEMxxx026 and FEMxxx029.

Operator Response: Contact System Programmer.

System Programmer Response: Use IPCS to determine the cause for the ABEND, take the corrective action required, perform an LLA,REFRESH, and reload the failing module using the OS/EM ISPF RELOAD facility. Contact OS/EM support for assistance in problem resolution.

FEMSCN206

ABEND AREGS 0-3: nnnnnnnn nnnnnnnn nnnnnnnn nnnnnnnn

Explanation: The OS/EM has detected a MVS System Abend during execution of an OS/EM optional function or a User exit.

nnnnnnnn: Contents of the Access Register.

Source: FEMSAFCN,FEMSMFCN

System Action: The OS/EM function being executed continues, OS/EM takes a SVC dump for the abending module, takes the abending module out of service, and deletes the abending module from CSA/ECSA. See messages FEMxxx023, FEMxxx026 and FEMxxx029.

Operator Response: Contact System Programmer.

System Programmer Response: Use IPCS to determine the cause for the ABEND, take the corrective action required, perform an LLA,REFRESH, and reload the failing module using the OS/EM ISPF RELOAD facility. Contact OS/EM support for assistance in problem resolution.

FEMTCN206

ABEND AREGS 0-3: nnnnnnnn nnnnnnnn nnnnnnnn nnnnnnnn

Explanation: The OS/EM has detected a MVS System Abend during execution of an OS/EM optional function or a User exit.

nnnnnnnn: Contents of the Access Register.

Source: FEMTSOCN

System Action: The OS/EM function being executed continues, OS/EM takes a SVC dump for the abending module, takes the abending module out of service, and deletes the abending module from CSA/ECSA. See messages FEMxxx023, FEMxxx026 and FEMxxx029.

Operator Response: Contact System Programmer.

System Programmer Response: Use IPCS to determine the cause for the ABEND, take the corrective action required, perform an LLA,REFRESH, and reload the failing module using the OS/EM ISPF RELOAD facility. Contact OS/EM support for assistance in problem resolution.

FEMTPS206

ABEND AREGS 0-3: nnnnnnnn nnnnnnnn nnnnnnnn nnnnnnnn

Explanation: The OS/EM has detected a MVS System Abend during execution of an OS/EM optional function or a User exit.

nnnnnnnn: Contents of the Access Register.

Source: FEMTPSHR

System Action: The OS/EM function being executed continues, OS/EM takes a SVC dump for the abending module, takes the abending module out of service, and deletes the abending module from CSA/ECSA. See messages FEMxxx023, FEMxxx026 and FEMxxx029.

Operator Response: Contact System Programmer.

System Programmer Response: Use IPCS to determine the cause for the ABEND, take the corrective action required, perform an LLA,REFRESH, and reload the failing module using the OS/EM ISPF RELOAD facility. Contact OS/EM support for assistance in problem resolution.

FEMUJI206

ABEND AREGS 0-3: nnnnnnnn nnnnnnnn nnnnnnnn nnnnnnnn

Explanation: The OS/EM has detected a MVS System Abend during execution of an OS/EM optional function or a User exit.

nnnnnnnn: Contents of the Access Register.

Source: FEMUJI

System Action: The OS/EM function being executed continues, OS/EM takes a SVC dump for the abending module, takes the abending module out of service, and deletes the abending module from CSA/ECSA. See messages FEMxxx023, FEMxxx026 and FEMxxx029.

Operator Response: Contact System Programmer.

System Programmer Response: Use IPCS to determine the cause for the ABEND, take the corrective action required, perform an LLA,REFRESH, and reload the failing module using the OS/EM ISPF RELOAD facility. Contact OS/EM support for assistance in problem resolution.

FEMUSI206

ABEND AREGS 0-3: nnnnnnnn nnnnnnnn nnnnnnnn nnnnnnnn

Explanation: The OS/EM has detected a MVS System Abend during execution of an OS/EM optional function or a User exit.

nnnnnnnn: Contents of the Access Register.

Source: FEMUSI

System Action: The OS/EM function being executed continues, OS/EM takes a SVC dump for the abending module, takes the abending module out of service, and deletes the abending module from CSA/ECSA. See messages FEMxxx023, FEMxxx026 and FEMxxx029.

Operator Response: Contact System Programmer.

System Programmer Response: Use IPCS to determine the cause for the ABEND, take the corrective action required, perform an LLA,REFRESH, and reload the failing module using the OS/EM ISPF RELOAD facility. Contact OS/EM support for assistance in problem resolution.

FEMVCN206

ABEND AREGS 0-3: nnnnnnnn nnnnnnnn nnnnnnnn nnnnnnnn

Explanation: The OS/EM has detected a MVS System Abend during execution of an OS/EM optional function or a User exit.

nnnnnnnn: Contents of the Access Register.

Source: FEMSVCCN

System Action: The OS/EM function being executed continues, OS/EM takes a SVC dump for the abending module, takes the abending module out of service, and deletes the abending module from CSA/ECSA. See messages FEMxxx023, FEMxxx026 and FEMxxx029.

Operator Response: Contact System Programmer.

System Programmer Response: Use IPCS to determine the cause for the ABEND, take the corrective action required, perform an LLA,REFRESH, and reload the failing module using the OS/EM ISPF RELOAD facility. Contact OS/EM support for assistance in problem resolution.

FEMX05206

ABEND AREGS 0-3: nnnnnnnn nnnnnnnn nnnnnnnn nnnnnnnn

Explanation: The OS/EM has detected a MVS System Abend during execution of an OS/EM optional function or a User exit.

nnnnnnnn: Contents of the Access Register.

Source: FEMJ2X05

System Action: The OS/EM function being executed continues, OS/EM takes a SVC dump for the abending module, takes the abending module out of service, and deletes the abending module from CSA/ECSA. See messages FEMxxx023, FEMxxx026 and FEMxxx029.

Operator Response: Contact System Programmer.

System Programmer Response: Use IPCS to determine the cause for the ABEND, take the corrective action required, perform an LLA,REFRESH, and reload the failing module using the OS/EM ISPF RELOAD facility. Contact OS/EM support for assistance in problem resolution.

FEM02F206

ABEND AREGS 0-3: nnnnnnnn nnnnnnnn nnnnnnnn nnnnnnnn

Explanation: The OS/EM has detected a MVS System Abend during execution of an OS/EM optional function or a User exit.

nnnnnnnn: Contents of the Access Register.

Source: FEM0002F

System Action: The OS/EM function being executed continues, OS/EM takes a SVC dump for the abending module, takes the abending module out of service, and deletes the abending module from CSA/ECSA. See messages FEMxxx023, FEMxxx026 and FEMxxx029.

Operator Response: Contact System Programmer.

System Programmer Response: Use IPCS to determine the cause for the ABEND, take the corrective action required, perform an LLA,REFRESH, and reload the failing module using the OS/EM ISPF RELOAD facility. Contact OS/EM support for assistance in problem resolution.

FEM1PL206

ABEND AREGS 0-3: nnnnnnnn nnnnnnnn nnnnnnnn nnnnnnnn

Explanation: The OS/EM has detected a MVS System Abend during execution of an OS/EM optional function or a User exit.

nnnnnnnn: Contents of the Access Register.

Source: FEM1PL1

System Action: The OS/EM function being executed continues, OS/EM takes a SVC dump for the abending module, takes the abending module out of service, and deletes the abending module from CSA/ECSA. See messages FEMxxx023, FEMxxx026 and FEMxxx029.

Operator Response: Contact System Programmer.

System Programmer Response: Use IPCS to determine the cause for the ABEND, take the corrective action required, perform an LLA,REFRESH, and reload the failing module using the OS/EM ISPF RELOAD facility. Contact OS/EM support for assistance in problem resolution.

FEM2H5206

ABEND AREGS 0-3: nnnnnnnn nnnnnnnn nnnnnnnn nnnnnnnn

Explanation: The OS/EM has detected a MVS System Abend during execution of an OS/EM optional function or a User exit.

nnnnnnnn: Contents of the Access Register.

Source: FEMJ2H5x

System Action: The OS/EM function being executed continues, OS/EM takes a SVC dump for the abending module, takes the abending module out of service, and deletes the abending module from CSA/ECSA. See messages FEMxxx023, FEMxxx026 and FEMxxx029.

Operator Response: Contact System Programmer.

System Programmer Response: Use IPCS to determine the cause for the ABEND, take the corrective action required, perform an LLA,REFRESH, and reload the failing module using the OS/EM ISPF RELOAD facility. Contact OS/EM support for assistance in problem resolution.

FEM2P4206

ABEND AREGS 0-3: nnnnnnnn nnnnnnnn nnnnnnnn nnnnnnnn

Explanation: The OS/EM has detected a MVS System Abend during execution of an OS/EM optional function or a User exit.

nnnnnnnn: Contents of the Access Register.

Source: FEMJ2P4x

System Action: The OS/EM function being executed continues, OS/EM takes a SVC dump for the abending module, takes the abending module out of service, and deletes the abending module from CSA/ECSA. See messages FEMxxx023, FEMxxx026 and FEMxxx029.

Operator Response: Contact System Programmer.

System Programmer Response: Use IPCS to determine the cause for the ABEND, take the corrective action required, perform an LLA,REFRESH, and reload the failing module using the OS/EM ISPF RELOAD facility. Contact OS/EM support for assistance in problem resolution.

FEMACN207

ABEND AREGS 4-7: nnnnnnnn nnnnnnnn nnnnnnnn nnnnnnnn

Explanation: The OS/EM has detected a MVS System Abend during execution of an OS/EM optional function or a User exit.

nnnnnnnn: Contents of the Access Register.

Source: FEMALCCN

System Action: The OS/EM function being executed continues, OS/EM takes a SVC dump for the abending module, takes the abending module out of service, and deletes the abending module from CSA/ECSA. See messages FEMxxx023, FEMxxx026 and FEMxxx029.

Operator Response: Contact System Programmer.

System Programmer Response: Use IPCS to determine the cause for the ABEND, take the corrective action required, perform an LLA,REFRESH, and reload the failing module using the OS/EM ISPF RELOAD facility. Contact OS/EM support for assistance in problem resolution.

FEMALC207

ABEND AREGS 4-7: nnnnnnnn nnnnnnnn nnnnnnnn nnnnnnnn

Explanation: The OS/EM has detected a MVS System Abend during execution of an OS/EM optional function or a User exit.

nnnnnnnn: Contents of the Access Register.

Source: FEMALLO0,FEMALLO1

System Action: The OS/EM function being executed continues, OS/EM takes a SVC dump for the abending module, takes the abending module out of service, and deletes the abending module from CSA/ECSA. See messages FEMxxx023, FEMxxx026 and FEMxxx029.

Operator Response: Contact System Programmer.

System Programmer Response: Use IPCS to determine the cause for the ABEND, take the corrective action required, perform an LLA,REFRESH, and reload the failing module using the OS/EM ISPF RELOAD facility. Contact OS/EM support for assistance in problem resolution.

FEMASY207

ABEND AREGS 4-7: nnnnnnnn nnnnnnnn nnnnnnnn nnnnnnnn

Explanation: The OS/EM has detected a MVS System Abend during execution of an OS/EM optional function or a User exit.

nnnnnnnn: Contents of the Access Register.

Source: FEMASYNC

System Action: The OS/EM function being executed continues, OS/EM takes a SVC dump for the abending module, takes the abending module out of service, and deletes the abending module from CSA/ECSA. See messages FEMxxx023, FEMxxx026 and FEMxxx029.

Operator Response: Contact System Programmer.

System Programmer Response: Use IPCS to determine the cause for the ABEND, take the corrective action required, perform an LLA,REFRESH, and reload the failing module using the OS/EM ISPF RELOAD facility. Contact OS/EM support for assistance in problem resolution.

FEMCMD207

ABEND AREGS 4-7: nnnnnnnn nnnnnnnn nnnnnnnn nnnnnnnn

Explanation: The OS/EM has detected a MVS System Abend during execution of an OS/EM optional function or a User exit.

nnnnnnnn: Contents of the Access Register.

Source: FEMCMD

System Action: The OS/EM function being executed continues, OS/EM takes a SVC dump for the abending module, takes the abending module out of service, and deletes the abending module from CSA/ECSA. See messages FEMxxx023, FEMxxx026 and FEMxxx029.

Operator Response: Contact System Programmer.

System Programmer Response: Use IPCS to determine the cause for the ABEND, take the corrective action required, perform an LLA,REFRESH, and reload the failing module using the OS/EM ISPF RELOAD facility. Contact OS/EM support for assistance in problem resolution.

FEMCOM207

ABEND AREGS 4-7: nnnnnnnn nnnnnnnn nnnnnnnn nnnnnnnn

Explanation: The OS/EM has detected a MVS System Abend during execution of an OS/EM optional function or a User exit.

nnnnnnnn: Contents of the Access Register.

Source: FEMCOMM

System Action: The OS/EM function being executed continues, OS/EM takes a SVC dump for the abending module, takes the abending module out of service, and deletes the abending module from CSA/ECSA. See messages FEMxxx023, FEMxxx026 and FEMxxx029.

Operator Response: Contact System Programmer.

System Programmer Response: Use IPCS to determine the cause for the ABEND, take the corrective action required, perform an LLA,REFRESH, and reload the failing module using the OS/EM ISPF RELOAD facility. Contact OS/EM support for assistance in problem resolution.

FEMDCN207

ABEND AREGS 4-7: nnnnnnnn nnnnnnnn nnnnnnnn nnnnnnnn

Explanation: The OS/EM has detected a MVS System Abend during execution of an OS/EM optional function or a User exit.

nnnnnnnn: Contents of the Access Register.

Source: FEMDADCN

System Action: The OS/EM function being executed continues, OS/EM takes a SVC dump for the abending module, takes the abending module out of service, and deletes the abending module from CSA/ECSA. See messages FEMxxx023, FEMxxx026 and FEMxxx029.

Operator Response: Contact System Programmer.

System Programmer Response: Use IPCS to determine the cause for the ABEND, take the corrective action required, perform an LLA,REFRESH, and reload the failing module using the OS/EM ISPF RELOAD facility. Contact OS/EM support for assistance in problem resolution.

FEMDC1207

ABEND AREGS 4-7: nnnnnnnn nnnnnnnn nnnnnnnn nnnnnnnn

Explanation: The OS/EM has detected a MVS System Abend during execution of an OS/EM optional function or a User exit.

nnnnnnnn: Contents of the Access Register.

Source: FEMDCB1

System Action: The OS/EM function being executed continues, OS/EM takes a SVC dump for the abending module, takes the abending module out of service, and deletes the abending module from CSA/ECSA. See messages FEMxxx023, FEMxxx026 and FEMxxx029.

Operator Response: Contact System Programmer.

System Programmer Response: Use IPCS to determine the cause for the ABEND, take the corrective action required, perform an LLA,REFRESH, and reload the failing module using the OS/EM ISPF RELOAD facility. Contact OS/EM support for assistance in problem resolution.

FEMEXR207

ABEND AREGS 4-7: nnnnnnnn nnnnnnnn nnnnnnnn nnnnnnnn

Explanation: The OS/EM has detected a MVS System Abend during execution of an OS/EM optional function or a User exit.

nnnnnnnn: Contents of the Access Register.

Source: FEMEXRTN

System Action: The OS/EM function being executed continues, OS/EM takes a SVC dump for the abending module, takes the abending module out of service, and deletes the abending module from CSA/ECSA. See messages FEMxxx023, FEMxxx026 and FEMxxx029.

Operator Response: Contact System Programmer.

System Programmer Response: Use IPCS to determine the cause for the ABEND, take the corrective action required, perform an LLA,REFRESH, and reload the failing module using the OS/EM ISPF RELOAD facility. Contact OS/EM support for assistance in problem resolution.

FEMFRA207

ABEND AREGS 4-7: nnnnnnnn nnnnnnnn nnnnnnnn nnnnnnnn

Explanation: The OS/EM has detected a MVS System Abend during execution of an OS/EM optional function or a User exit.

nnnnnnnn: Contents of the Access Register.

Source: FEMFRACN

System Action: The OS/EM function being executed continues, OS/EM takes a SVC dump for the abending module, takes the abending module out of service, and deletes the abending module from CSA/ECSA. See messages FEMxxx023, FEMxxx026 and FEMxxx029.

Operator Response: Contact System Programmer.

System Programmer Response: Use IPCS to determine the cause for the ABEND, take the corrective action required, perform an LLA,REFRESH, and reload the failing module using the OS/EM ISPF RELOAD facility. Contact OS/EM support for assistance in problem resolution.

FEMFTN207

ABEND AREGS 4-7: nnnnnnnn nnnnnnnn nnnnnnnn nnnnnnnn

Explanation: The OS/EM has detected a MVS System Abend during execution of an OS/EM optional function or a User exit.

nnnnnnnn: Contents of the Access Register.

Source: FEMFRRTN

System Action: The OS/EM function being executed continues, OS/EM takes a SVC dump for the abending module, takes the abending module out of service, and deletes the abending module from CSA/ECSA. See messages FEMxxx023, FEMxxx026 and FEMxxx029.

Operator Response: Contact System Programmer.

System Programmer Response: Use IPCS to determine the cause for the ABEND, take the corrective action required, perform an LLA,REFRESH, and reload the failing module using the OS/EM ISPF RELOAD facility. Contact OS/EM support for assistance in problem resolution.

FEMHCN207

ABEND AREGS 4-7: nnnnnnnn nnnnnnnn nnnnnnnn nnnnnnnn

Explanation: The OS/EM has detected a MVS System Abend during execution of an OS/EM optional function or a User exit.

nnnnnnnn: Contents of the Access Register.

Source: FEMHSMCN

System Action: The OS/EM function being executed continues, OS/EM takes a SVC dump for the abending module, takes the abending module out of service, and deletes the abending module from CSA/ECSA. See messages FEMxxx023, FEMxxx026 and FEMxxx029.

Operator Response: Contact System Programmer.

System Programmer Response: Use IPCS to determine the cause for the ABEND, take the corrective action required, perform an LLA,REFRESH, and reload the failing module using the OS/EM ISPF RELOAD facility. Contact OS/EM support for assistance in problem resolution.

FEMHSP207

ABEND AREGS 4-7: nnnnnnnn nnnnnnnn nnnnnnnn nnnnnnnn

Explanation: The OS/EM has detected a MVS System Abend during execution of an OS/EM optional function or a User exit.

nnnnnnnn: Contents of the Access Register.

Source: FEMHJ20

System Action: The OS/EM function being executed continues, OS/EM takes a SVC dump for the abending module, takes the abending module out of service, and deletes the abending module from CSA/ECSA. See messages FEMxxx023, FEMxxx026 and FEMxxx029.

Operator Response: Contact System Programmer.

System Programmer Response: Use IPCS to determine the cause for the ABEND, take the corrective action required, perform an LLA,REFRESH, and reload the failing module using the OS/EM ISPF RELOAD facility. Contact OS/EM support for assistance in problem resolution.

FEMIAT207

ABEND AREGS 4-7: nnnnnnnn nnnnnnnn nnnnnnnn nnnnnnnn

Explanation: The OS/EM has detected a MVS System Abend during execution of an OS/EM optional function or a User exit.

nnnnnnnn: Contents of the Access Register.

Source: FEMINTK

System Action: The OS/EM function being executed continues, OS/EM takes a SVC dump for the abending module, takes the abending module out of service, and deletes the abending module from CSA/ECSA. See messages FEMxxx023, FEMxxx026 and FEMxxx029.

Operator Response: Contact System Programmer.

System Programmer Response: Use IPCS to determine the cause for the ABEND, take the corrective action required, perform an LLA,REFRESH, and reload the failing module using the OS/EM ISPF RELOAD facility. Contact OS/EM support for assistance in problem resolution.

FEMICN207

ABEND AREGS 4-7: nnnnnnnn nnnnnnnn nnnnnnnn nnnnnnnn

Explanation: The OS/EM has detected a MVS System Abend during execution of an OS/EM optional function or a User exit.

nnnnnnnn: Contents of the Access Register.

Source: FEMISPCN

System Action: The OS/EM function being executed continues, OS/EM takes a SVC dump for the abending module, takes the abending module out of service, and deletes the abending module from CSA/ECSA. See messages FEMxxx023, FEMxxx026 and FEMxxx029.

Operator Response: Contact System Programmer.

System Programmer Response: Use IPCS to determine the cause for the ABEND, take the corrective action required, perform an LLA,REFRESH, and reload the failing module using the OS/EM ISPF RELOAD facility. Contact OS/EM support for assistance in problem resolution.

FEM IPL207

ABEND AREGS 4-7: nnnnnnnn nnnnnnnn nnnnnnnn nnnnnnnn

Explanation: The OS/EM has detected a MVS System Abend during execution of an OS/EM optional function or a User exit.

nnnnnnnn: Contents of the Access Register.

Source: FEM IPL

System Action: The OS/EM function being executed continues, OS/EM takes a SVC dump for the abending module, takes the abending module out of service, and deletes the abending module from CSA/ECSA. See messages FEMxxx023, FEMxxx026 and FEMxxx029.

Operator Response: Contact System Programmer.

System Programmer Response: Use IPCS to determine the cause for the ABEND, take the corrective action required, perform an LLA,REFRESH, and reload the failing module using the OS/EM ISPF RELOAD facility. Contact OS/EM support for assistance in problem resolution.

FEM JS2207

ABEND AREGS 4-7: nnnnnnnn nnnnnnnn nnnnnnnn nnnnnnnn

Explanation: The OS/EM has detected a MVS System Abend during execution of an OS/EM optional function or a User exit.

nnnnnnnn: Contents of the Access Register.

Source: FEMJES2B,FEMJES2G

System Action: The OS/EM function being executed continues, OS/EM takes a SVC dump for the abending module, takes the abending module out of service, and deletes the abending module from CSA/ECSA. See messages FEMxxx023, FEMxxx026 and FEMxxx029.

Operator Response: Contact System Programmer.

System Programmer Response: Use IPCS to determine the cause for the ABEND, take the corrective action required, perform an LLA,REFRESH, and reload the failing module using the OS/EM ISPF RELOAD facility. Contact OS/EM support for assistance in problem resolution.

FEM J2M207

ABEND AREGS 4-7: nnnnnnnn nnnnnnnn nnnnnnnn nnnnnnnn

Explanation: The OS/EM has detected a MVS System Abend during execution of an OS/EM optional function or a User exit.

nnnnnnnn: Contents of the Access Register.

Source: FEMJ2MCx

System Action: The OS/EM function being executed continues, OS/EM takes a SVC dump for the abending module, takes the abending module out of service, and deletes the abending module from CSA/ECSA. See messages FEMxxx023, FEMxxx026 and FEMxxx029.

Operator Response: Contact System Programmer.

System Programmer Response: Use IPCS to determine the cause for the ABEND, take the corrective action required, perform an LLA,REFRESH, and reload the failing module using the OS/EM ISPF RELOAD facility. Contact OS/EM support for assistance in problem resolution.

FEMJ2R207

ABEND AREGS 4-7: nnnnnnnn nnnnnnnn nnnnnnnn nnnnnnnn

Explanation: The OS/EM has detected a MVS System Abend during execution of an OS/EM optional function or a User exit.

nnnnnnnn: Contents of the Access Register.

Source: FEMJ2ERx

System Action: The OS/EM function being executed continues, OS/EM takes a SVC dump for the abending module, takes the abending module out of service, and deletes the abending module from CSA/ECSA. See messages FEMxxx023, FEMxxx026 and FEMxxx029.

Operator Response: Contact System Programmer.

System Programmer Response: Use IPCS to determine the cause for the ABEND, take the corrective action required, perform an LLA,REFRESH, and reload the failing module using the OS/EM ISPF RELOAD facility. Contact OS/EM support for assistance in problem resolution.

FEMJ2S207

ABEND AREGS 4-7: nnnnnnnn nnnnnnnn nnnnnnnn nnnnnnnn

Explanation: The OS/EM has detected a MVS System Abend during execution of an OS/EM optional function or a User exit.

nnnnnnnn: Contents of the Access Register.

Source: FEMJ2SCx

System Action: The OS/EM function being executed continues, OS/EM takes a SVC dump for the abending module, takes the abending module out of service, and deletes the abending module from CSA/ECSA. See messages FEMxxx023, FEMxxx026 and FEMxxx029.

Operator Response: Contact System Programmer.

System Programmer Response: Use IPCS to determine the cause for the ABEND, take the corrective action required, perform an LLA,REFRESH, and reload the failing module using the OS/EM ISPF RELOAD facility. Contact OS/EM support for assistance in problem resolution.

FEMJ3E207

ABEND AREGS 4-7: nnnnnnnn nnnnnnnn nnnnnnnn nnnnnnnn

Explanation: The OS/EM has detected a MVS System Abend during execution of an OS/EM optional function or a User exit.

nnnnnnnn: Contents of the Access Register.

Source: FEMJ3ECN

System Action: The OS/EM function being executed continues, OS/EM takes a SVC dump for the abending module, takes the abending module out of service, and deletes the abending module from CSA/ECSA. See messages FEMxxx023, FEMxxx026 and FEMxxx029.

Operator Response: Contact System Programmer.

System Programmer Response: Use IPCS to determine the cause for the ABEND, take the corrective action required, perform an LLA,REFRESH, and reload the failing module using the OS/EM ISPF RELOAD facility. Contact OS/EM support for assistance in problem resolution.

FEMJ3S207

ABEND AREGS 4-7: nnnnnnnn nnnnnnnn nnnnnnnn nnnnnnnn

Explanation: The OS/EM has detected a MVS System Abend during execution of an OS/EM optional function or a User exit.

nnnnnnnn: Contents of the Access Register.

Source: FEMJ3SVC

System Action: The OS/EM function being executed continues, OS/EM takes a SVC dump for the abending module, takes the abending module out of service, and deletes the abending module from CSA/ECSA. See messages FEMxxx023, FEMxxx026 and FEMxxx029.

Operator Response: Contact System Programmer.

System Programmer Response: Use IPCS to determine the cause for the ABEND, take the corrective action required, perform an LLA,REFRESH, and reload the failing module using the OS/EM ISPF RELOAD facility. Contact OS/EM support for assistance in problem resolution.

FEMLOK207

ABEND AREGS 4-7: nnnnnnnn nnnnnnnn nnnnnnnn nnnnnnnn

Explanation: The OS/EM has detected a MVS System Abend during execution of an OS/EM optional function or a User exit.

nnnnnnnn: Contents of the Access Register.

Source: FEMLOCK

System Action: The OS/EM function being executed continues, OS/EM takes a SVC dump for the abending module, takes the abending module out of service, and deletes the abending module from CSA/ECSA. See messages FEMxxx023, FEMxxx026 and FEMxxx029.

Operator Response: Contact System Programmer.

System Programmer Response: Use IPCS to determine the cause for the ABEND, take the corrective action required, perform an LLA,REFRESH, and reload the failing module using the OS/EM ISPF RELOAD facility. Contact OS/EM support for assistance in problem resolution.

FEMRCN207

ABEND AREGS 4-7: nnnnnnnn nnnnnnnn nnnnnnnn nnnnnnnn

Explanation: The OS/EM has detected a MVS System Abend during execution of an OS/EM optional function or a User exit.

nnnnnnnn: Contents of the Access Register.

Source: FEMRACCN

System Action: The OS/EM function being executed continues, OS/EM takes a SVC dump for the abending module, takes the abending module out of service, and deletes the abending module from CSA/ECSA. See messages FEMxxx023, FEMxxx026 and FEMxxx029.

Operator Response: Contact System Programmer.

System Programmer Response: Use IPCS to determine the cause for the ABEND, take the corrective action required, perform an LLA,REFRESH, and reload the failing module using the OS/EM ISPF RELOAD facility. Contact OS/EM support for assistance in problem resolution.

FEMSCN207

ABEND AREGS 4-7: nnnnnnnn nnnnnnnn nnnnnnnn nnnnnnnn

Explanation: The OS/EM has detected a MVS System Abend during execution of an OS/EM optional function or a User exit.

nnnnnnnn: Contents of the Access Register.

Source: FEMSAFCN,FEMSMFCN

System Action: The OS/EM function being executed continues, OS/EM takes a SVC dump for the abending module, takes the abending module out of service, and deletes the abending module from CSA/ECSA. See messages FEMxxx023, FEMxxx026 and FEMxxx029.

Operator Response: Contact System Programmer.

System Programmer Response: Use IPCS to determine the cause for the ABEND, take the corrective action required, perform an LLA,REFRESH, and reload the failing module using the OS/EM ISPF RELOAD facility. Contact OS/EM support for assistance in problem resolution.

FEMTCN207

ABEND AREGS 4-7: nnnnnnnn nnnnnnnn nnnnnnnn nnnnnnnn

Explanation: The OS/EM has detected a MVS System Abend during execution of an OS/EM optional function or a User exit.

nnnnnnnn: Contents of the Access Register.

Source: FEMTSOCN

System Action: The OS/EM function being executed continues, OS/EM takes a SVC dump for the abending module, takes the abending module out of service, and deletes the abending module from CSA/ECSA. See messages FEMxxx023, FEMxxx026 and FEMxxx029.

Operator Response: Contact System Programmer.

System Programmer Response: Use IPCS to determine the cause for the ABEND, take the corrective action required, perform an LLA,REFRESH, and reload the failing module using the OS/EM ISPF RELOAD facility. Contact OS/EM support for assistance in problem resolution.

FEMTPS207

ABEND AREGS 4-7: nnnnnnnn nnnnnnnn nnnnnnnn nnnnnnnn

Explanation: The OS/EM has detected a MVS System Abend during execution of an OS/EM optional function or a User exit.

nnnnnnnn: Contents of the Access Register.

Source: FEMTPSHR

System Action: The OS/EM function being executed continues, OS/EM takes a SVC dump for the abending module, takes the abending module out of service, and deletes the abending module from CSA/ECSA. See messages FEMxxx023, FEMxxx026 and FEMxxx029.

Operator Response: Contact System Programmer.

System Programmer Response: Use IPCS to determine the cause for the ABEND, take the corrective action required, perform an LLA,REFRESH, and reload the failing module using the OS/EM ISPF RELOAD facility. Contact OS/EM support for assistance in problem resolution.

FEMUJI207

ABEND AREGS 4-7: nnnnnnnn nnnnnnnn nnnnnnnn nnnnnnnn

Explanation: The OS/EM has detected a MVS System Abend during execution of an OS/EM optional function or a User exit.

nnnnnnnn: Contents of the Access Register.

Source: FEMUJI

System Action: The OS/EM function being executed continues, OS/EM takes a SVC dump for the abending module, takes the abending module out of service, and deletes the abending module from CSA/ECSA. See messages FEMxxx023, FEMxxx026 and FEMxxx029.

Operator Response: Contact System Programmer.

System Programmer Response: Use IPCS to determine the cause for the ABEND, take the corrective action required, perform an LLA,REFRESH, and reload the failing module using the OS/EM ISPF RELOAD facility. Contact OS/EM support for assistance in problem resolution.

FEMUSI207

ABEND AREGS 4-7: nnnnnnnn nnnnnnnn nnnnnnnn nnnnnnnn

Explanation: The OS/EM has detected a MVS System Abend during execution of an OS/EM optional function or a User exit.

nnnnnnnn: Contents of the Access Register.

Source: FEMUSI

System Action: The OS/EM function being executed continues, OS/EM takes a SVC dump for the abending module, takes the abending module out of service, and deletes the abending module from CSA/ECSA. See messages FEMxxx023, FEMxxx026 and FEMxxx029.

Operator Response: Contact System Programmer.

System Programmer Response: Use IPCS to determine the cause for the ABEND, take the corrective action required, perform an LLA,REFRESH, and reload the failing module using the OS/EM ISPF RELOAD facility. Contact OS/EM support for assistance in problem resolution.

FEMVCN207

ABEND AREGS 4-7: nnnnnnnn nnnnnnnn nnnnnnnn nnnnnnnn

Explanation: The OS/EM has detected a MVS System Abend during execution of an OS/EM optional function or a User exit.

nnnnnnnn: Contents of the Access Register.

Source: FEMSVCCN

System Action: The OS/EM function being executed continues, OS/EM takes a SVC dump for the abending module, takes the abending module out of service, and deletes the abending module from CSA/ECSA. See messages FEMxxx023, FEMxxx026 and FEMxxx029.

Operator Response: Contact System Programmer.

System Programmer Response: Use IPCS to determine the cause for the ABEND, take the corrective action required, perform an LLA,REFRESH, and reload the failing module using the OS/EM ISPF RELOAD facility. Contact OS/EM support for assistance in problem resolution.

FEMX05207

ABEND AREGS 4-7: nnnnnnnn nnnnnnnn nnnnnnnn nnnnnnnn

Explanation: The OS/EM has detected a MVS System Abend during execution of an OS/EM optional function or a User exit.

nnnnnnnn: Contents of the Access Register.

Source: FEMJ2X05

System Action: The OS/EM function being executed continues, OS/EM takes a SVC dump for the abending module, takes the abending module out of service, and deletes the abending module from CSA/ECSA. See messages FEMxxx023, FEMxxx026 and FEMxxx029.

Operator Response: Contact System Programmer.

System Programmer Response: Use IPCS to determine the cause for the ABEND, take the corrective action required, perform an LLA,REFRESH, and reload the failing module using the OS/EM ISPF RELOAD facility. Contact OS/EM support for assistance in problem resolution.

FEM02F207

ABEND AREGS 4-7: nnnnnnnn nnnnnnnn nnnnnnnn nnnnnnnn

Explanation: The OS/EM has detected a MVS System Abend during execution of an OS/EM optional function or a User exit.

nnnnnnnn: Contents of the Access Register.

Source: FEM0002F

System Action: The OS/EM function being executed continues, OS/EM takes a SVC dump for the abending module, takes the abending module out of service, and deletes the abending module from CSA/ECSA. See messages FEMxxx023, FEMxxx026 and FEMxxx029.

Operator Response: Contact System Programmer.

System Programmer Response: Use IPCS to determine the cause for the ABEND, take the corrective action required, perform an LLA,REFRESH, and reload the failing module using the OS/EM ISPF RELOAD facility. Contact OS/EM support for assistance in problem resolution.

FEMIPL207

ABEND AREGS 4-7: nnnnnnnn nnnnnnnn nnnnnnnn nnnnnnnn

Explanation: The OS/EM has detected a MVS System Abend during execution of an OS/EM optional function or a User exit.

nnnnnnnn: Contents of the Access Register.

Source: FEMIPL1

System Action: The OS/EM function being executed continues, OS/EM takes a SVC dump for the abending module, takes the abending module out of service, and deletes the abending module from CSA/ECSA. See messages FEMxxx023, FEMxxx026 and FEMxxx029.

Operator Response: Contact System Programmer.

System Programmer Response: Use IPCS to determine the cause for the ABEND, take the corrective action required, perform an LLA,REFRESH, and reload the failing module using the OS/EM ISPF RELOAD facility. Contact OS/EM support for assistance in problem resolution.

FEM2H5207

ABEND AREGS 4-7: nnnnnnnn nnnnnnnn nnnnnnnn nnnnnnnn

Explanation: The OS/EM has detected a MVS System Abend during execution of an OS/EM optional function or a User exit.

nnnnnnnn: Contents of the Access Register.

Source: FEMJ2H5x

System Action: The OS/EM function being executed continues, OS/EM takes a SVC dump for the abending module, takes the abending module out of service, and deletes the abending module from CSA/ECSA. See messages FEMxxx023, FEMxxx026 and FEMxxx029.

Operator Response: Contact System Programmer.

System Programmer Response: Use IPCS to determine the cause for the ABEND, take the corrective action required, perform an LLA,REFRESH, and reload the failing module using the OS/EM ISPF RELOAD facility. Contact OS/EM support for assistance in problem resolution.

FEM2P4207

ABEND AREGS 4-7: nnnnnnnn nnnnnnnn nnnnnnnn nnnnnnnn

Explanation: The OS/EM has detected a MVS System Abend during execution of an OS/EM optional function or a User exit.

nnnnnnnn: Contents of the Access Register.

Source: FEMJ2P4x

System Action: The OS/EM function being executed continues, OS/EM takes a SVC dump for the abending module, takes the abending module out of service, and deletes the abending module from CSA/ECSA. See messages FEMxxx023, FEMxxx026 and FEMxxx029.

Operator Response: Contact System Programmer.

System Programmer Response: Use IPCS to determine the cause for the ABEND, take the corrective action required, perform an LLA,REFRESH, and reload the failing module using the OS/EM ISPF RELOAD facility. Contact OS/EM support for assistance in problem resolution.

FEMACN208

ABEND AREGS 8-11: nnnnnnnn nnnnnnnn nnnnnnnn nnnnnnnn

Explanation: The OS/EM has detected a MVS System Abend during execution of an OS/EM optional function or a User exit.

nnnnnnnn: Contents of the Access Register.

Source: FEMALCCN

System Action: The OS/EM function being executed continues, OS/EM takes a SVC dump for the abending module, takes the abending module out of service, and deletes the abending module from CSA/ECSA. See messages FEMxxx023, FEMxxx026 and FEMxxx029.

Operator Response: Contact System Programmer.

System Programmer Response: Use IPCS to determine the cause for the ABEND, take the corrective action required, perform an LLA,REFRESH, and reload the failing module using the OS/EM ISPF RELOAD facility. Contact OS/EM support for assistance in problem resolution.

FEMALC208

ABEND AREGS 8-11: nnnnnnnn nnnnnnnn nnnnnnnn nnnnnnnn

Explanation: The OS/EM has detected a MVS System Abend during execution of an OS/EM optional function or a User exit.

nnnnnnnn: Contents of the Access Register.

Source: FEMALLO0,FEMALLO1

System Action: The OS/EM function being executed continues, OS/EM takes a SVC dump for the abending module, takes the abending module out of service, and deletes the abending module from CSA/ECSA. See messages FEMxxx023, FEMxxx026 and FEMxxx029.

Operator Response: Contact System Programmer.

System Programmer Response: Use IPCS to determine the cause for the ABEND, take the corrective action required, perform an LLA,REFRESH, and reload the failing module using the OS/EM ISPF RELOAD facility. Contact OS/EM support for assistance in problem resolution.

FEMASY208

ABEND AREGS 8-11: nnnnnnnn nnnnnnnn nnnnnnnn nnnnnnnn

Explanation: The OS/EM has detected a MVS System Abend during execution of an OS/EM optional function or a User exit.

nnnnnnnn: Contents of the Access Register.

Source: FEMASYNC

System Action: The OS/EM function being executed continues, OS/EM takes a SVC dump for the abending module, takes the abending module out of service, and deletes the abending module from CSA/ECSA. See messages FEMxxx023, FEMxxx026 and FEMxxx029.

Operator Response: Contact System Programmer.

System Programmer Response: Use IPCS to determine the cause for the ABEND, take the corrective action required, perform an LLA,REFRESH, and reload the failing module using the OS/EM ISPF RELOAD facility. Contact OS/EM support for assistance in problem resolution.

FEMCMD208

ABEND AREGS 8-11: nnnnnnnn nnnnnnnn nnnnnnnn nnnnnnnn

Explanation: The OS/EM has detected a MVS System Abend during execution of an OS/EM optional function or a User exit.

nnnnnnnn: Contents of the Access Register.

Source: FEMCMD

System Action: The OS/EM function being executed continues, OS/EM takes a SVC dump for the abending module, takes the abending module out of service, and deletes the abending module from CSA/ECSA. See messages FEMxxx023, FEMxxx026 and FEMxxx029.

Operator Response: Contact System Programmer.

System Programmer Response: Use IPCS to determine the cause for the ABEND, take the corrective action required, perform an LLA,REFRESH, and reload the failing module using the OS/EM ISPF RELOAD facility. Contact OS/EM support for assistance in problem resolution.

FEMCOM208

ABEND AREGS 8-11: nnnnnnnn nnnnnnnn nnnnnnnn nnnnnnnn

Explanation: The OS/EM has detected a MVS System Abend during execution of an OS/EM optional function or a User exit.

nnnnnnnn: Contents of the Access Register.

Source: FEMCOMM

System Action: The OS/EM function being executed continues, OS/EM takes a SVC dump for the abending module, takes the abending module out of service, and deletes the abending module from CSA/ECSA. See messages FEMxxx023, FEMxxx026 and FEMxxx029.

Operator Response: Contact System Programmer.

System Programmer Response: Use IPCS to determine the cause for the ABEND, take the corrective action required, perform an LLA,REFRESH, and reload the failing module using the OS/EM ISPF RELOAD facility. Contact OS/EM support for assistance in problem resolution.

FEMDCN208

ABEND AREGS 8-11: nnnnnnnn nnnnnnnn nnnnnnnn nnnnnnnn

Explanation: The OS/EM has detected a MVS System Abend during execution of an OS/EM optional function or a User exit.

nnnnnnnn: Contents of the Access Register.

Source: FEMDADCN

System Action: The OS/EM function being executed continues, OS/EM takes a SVC dump for the abending module, takes the abending module out of service, and deletes the abending module from CSA/ECSA. See messages FEMxxx023, FEMxxx026 and FEMxxx029.

Operator Response: Contact System Programmer.

System Programmer Response: Use IPCS to determine the cause for the ABEND, take the corrective action required, perform an LLA,REFRESH, and reload the failing module using the OS/EM ISPF RELOAD facility. Contact OS/EM support for assistance in problem resolution.

FEMDC1208

ABEND AREGS 8-11: nnnnnnnn nnnnnnnn nnnnnnnn nnnnnnnn

Explanation: The OS/EM has detected a MVS System Abend during execution of an OS/EM optional function or a User exit.

nnnnnnnn: Contents of the Access Register.

Source: FEMDCB1

System Action: The OS/EM function being executed continues, OS/EM takes a SVC dump for the abending module, takes the abending module out of service, and deletes the abending module from CSA/ECSA. See messages FEMxxx023, FEMxxx026 and FEMxxx029.

Operator Response: Contact System Programmer.

System Programmer Response: Use IPCS to determine the cause for the ABEND, take the corrective action required, perform an LLA,REFRESH, and reload the failing module using the OS/EM ISPF RELOAD facility. Contact OS/EM support for assistance in problem resolution.

FEMEXR208

ABEND AREGS 8-11: nnnnnnnn nnnnnnnn nnnnnnnn nnnnnnnn

Explanation: The OS/EM has detected a MVS System Abend during execution of an OS/EM optional function or a User exit.

nnnnnnnn: Contents of the Access Register.

Source: FEMEXRTN

System Action: The OS/EM function being executed continues, OS/EM takes a SVC dump for the abending module, takes the abending module out of service, and deletes the abending module from CSA/ECSA. See messages FEMxxx023, FEMxxx026 and FEMxxx029.

Operator Response: Contact System Programmer.

System Programmer Response: Use IPCS to determine the cause for the ABEND, take the corrective action required, perform an LLA,REFRESH, and reload the failing module using the OS/EM ISPF RELOAD facility. Contact OS/EM support for assistance in problem resolution.

FEMFRA208

ABEND AREGS 8-11: nnnnnnnn nnnnnnnn nnnnnnnn nnnnnnnn

Explanation: The OS/EM has detected a MVS System Abend during execution of an OS/EM optional function or a User exit.

nnnnnnnn: Contents of the Access Register.

Source: FEMFRACN

System Action: The OS/EM function being executed continues, OS/EM takes a SVC dump for the abending module, takes the abending module out of service, and deletes the abending module from CSA/ECSA. See messages FEMxxx023, FEMxxx026 and FEMxxx029.

Operator Response: Contact System Programmer.

System Programmer Response: Use IPCS to determine the cause for the ABEND, take the corrective action required, perform an LLA,REFRESH, and reload the failing module using the OS/EM ISPF RELOAD facility. Contact OS/EM support for assistance in problem resolution.

FEMFTN208

ABEND AREGS 8-11: nnnnnnnn nnnnnnnn nnnnnnnn nnnnnnnn

Explanation: The OS/EM has detected a MVS System Abend during execution of an OS/EM optional function or a User exit.

nnnnnnnn: Contents of the Access Register.

Source: FEMFRRTN

System Action: The OS/EM function being executed continues, OS/EM takes a SVC dump for the abending module, takes the abending module out of service, and deletes the abending module from CSA/ECSA. See messages FEMxxx023, FEMxxx026 and FEMxxx029.

Operator Response: Contact System Programmer.

System Programmer Response: Use IPCS to determine the cause for the ABEND, take the corrective action required, perform an LLA,REFRESH, and reload the failing module using the OS/EM ISPF RELOAD facility. Contact OS/EM support for assistance in problem resolution.

FEMHCN208

ABEND AREGS 8-11: nnnnnnnn nnnnnnnn nnnnnnnn nnnnnnnn

Explanation: The OS/EM has detected a MVS System Abend during execution of an OS/EM optional function or a User exit.

nnnnnnnn: Contents of the Access Register.

Source: FEMHSMCN

System Action: The OS/EM function being executed continues, OS/EM takes a SVC dump for the abending module, takes the abending module out of service, and deletes the abending module from CSA/ECSA. See messages FEMxxx023, FEMxxx026 and FEMxxx029.

Operator Response: Contact System Programmer.

System Programmer Response: Use IPCS to determine the cause for the ABEND, take the corrective action required, perform an LLA,REFRESH, and reload the failing module using the OS/EM ISPF RELOAD facility. Contact OS/EM support for assistance in problem resolution.

FEMHSP208

ABEND AREGS 8-11: nnnnnnnn nnnnnnnn nnnnnnnn nnnnnnnn

Explanation: The OS/EM has detected a MVS System Abend during execution of an OS/EM optional function or a User exit.

nnnnnnnn: Contents of the Access Register.

Source: FEMHJ20

System Action: The OS/EM function being executed continues, OS/EM takes a SVC dump for the abending module, takes the abending module out of service, and deletes the abending module from CSA/ECSA. See messages FEMxxx023, FEMxxx026 and FEMxxx029.

Operator Response: Contact System Programmer.

System Programmer Response: Use IPCS to determine the cause for the ABEND, take the corrective action required, perform an LLA,REFRESH, and reload the failing module using the OS/EM ISPF RELOAD facility. Contact OS/EM support for assistance in problem resolution.

FEMIAT208

ABEND AREGS 8-11: nnnnnnnn nnnnnnnn nnnnnnnn nnnnnnnn

Explanation: The OS/EM has detected a MVS System Abend during execution of an OS/EM optional function or a User exit.

nnnnnnnn: Contents of the Access Register.

Source: FEMINTK

System Action: The OS/EM function being executed continues, OS/EM takes a SVC dump for the abending module, takes the abending module out of service, and deletes the abending module from CSA/ECSA. See messages FEMxxx023, FEMxxx026 and FEMxxx029.

Operator Response: Contact System Programmer.

System Programmer Response: Use IPCS to determine the cause for the ABEND, take the corrective action required, perform an LLA,REFRESH, and reload the failing module using the OS/EM ISPF RELOAD facility. Contact OS/EM support for assistance in problem resolution.

FEMICN208

ABEND AREGS 8-11: nnnnnnnn nnnnnnnn nnnnnnnn nnnnnnnn

Explanation: The OS/EM has detected a MVS System Abend during execution of an OS/EM optional function or a User exit.

nnnnnnnn: Contents of the Access Register.

Source: FEMISPCN

System Action: The OS/EM function being executed continues, OS/EM takes a SVC dump for the abending module, takes the abending module out of service, and deletes the abending module from CSA/ECSA. See messages FEMxxx023, FEMxxx026 and FEMxxx029.

Operator Response: Contact System Programmer.

System Programmer Response: Use IPCS to determine the cause for the ABEND, take the corrective action required, perform an LLA,REFRESH, and reload the failing module using the OS/EM ISPF RELOAD facility. Contact OS/EM support for assistance in problem resolution.

FEMIPL208

ABEND AREGS 8-11: nnnnnnnn nnnnnnnn nnnnnnnn nnnnnnnn

Explanation: The OS/EM has detected a MVS System Abend during execution of an OS/EM optional function or a User exit.

nnnnnnnn: Contents of the Access Register.

Source: FEMIPL

System Action: The OS/EM function being executed continues, OS/EM takes a SVC dump for the abending module, takes the abending module out of service, and deletes the abending module from CSA/ECSA. See messages FEMxxx023, FEMxxx026 and FEMxxx029.

Operator Response: Contact System Programmer.

System Programmer Response: Use IPCS to determine the cause for the ABEND, take the corrective action required, perform an LLA,REFRESH, and reload the failing module using the OS/EM ISPF RELOAD facility. Contact OS/EM support for assistance in problem resolution.

FEMJS2208

ABEND AREGS 8-11: nnnnnnnn nnnnnnnn nnnnnnnn nnnnnnnn

Explanation: The OS/EM has detected a MVS System Abend during execution of an OS/EM optional function or a User exit.

nnnnnnnn: Contents of the Access Register.

Source: FEMJES2B,FEMJES2G

System Action: The OS/EM function being executed continues, OS/EM takes a SVC dump for the abending module, takes the abending module out of service, and deletes the abending module from CSA/ECSA. See messages FEMxxx023, FEMxxx026 and FEMxxx029.

Operator Response: Contact System Programmer.

System Programmer Response: Use IPCS to determine the cause for the ABEND, take the corrective action required, perform an LLA,REFRESH, and reload the failing module using the OS/EM ISPF RELOAD facility. Contact OS/EM support for assistance in problem resolution.

FEMJ2M208

ABEND AREGS 8-11: nnnnnnnn nnnnnnnn nnnnnnnn nnnnnnnn

Explanation: The OS/EM has detected a MVS System Abend during execution of an OS/EM optional function or a User exit.

nnnnnnnn: Contents of the Access Register.

Source: FEMJ2MCx

System Action: The OS/EM function being executed continues, OS/EM takes a SVC dump for the abending module, takes the abending module out of service, and deletes the abending module from CSA/ECSA. See messages FEMxxx023, FEMxxx026 and FEMxxx029.

Operator Response: Contact System Programmer.

System Programmer Response: Use IPCS to determine the cause for the ABEND, take the corrective action required, perform an LLA,REFRESH, and reload the failing module using the OS/EM ISPF RELOAD facility. Contact OS/EM support for assistance in problem resolution.

FEMJ2R208

ABEND AREGS 8-11: nnnnnnnn nnnnnnnn nnnnnnnn nnnnnnnn

Explanation: The OS/EM has detected a MVS System Abend during execution of an OS/EM optional function or a User exit.

nnnnnnnn: Contents of the Access Register.

Source: FEMJ2ERx

System Action: The OS/EM function being executed continues, OS/EM takes a SVC dump for the abending module, takes the abending module out of service, and deletes the abending module from CSA/ECSA. See messages FEMxxx023, FEMxxx026 and FEMxxx029.

Operator Response: Contact System Programmer.

System Programmer Response: Use IPCS to determine the cause for the ABEND, take the corrective action required, perform an LLA,REFRESH, and reload the failing module using the OS/EM ISPF RELOAD facility. Contact OS/EM support for assistance in problem resolution.

FEMJ2S208

ABEND AREGS 8-11: nnnnnnnn nnnnnnnn nnnnnnnn nnnnnnnn

Explanation: The OS/EM has detected a MVS System Abend during execution of an OS/EM optional function or a User exit.

nnnnnnnn: Contents of the Access Register.

Source: FEMJ2SCx

System Action: The OS/EM function being executed continues, OS/EM takes a SVC dump for the abending module, takes the abending module out of service, and deletes the abending module from CSA/ECSA. See messages FEMxxx023, FEMxxx026 and FEMxxx029.

Operator Response: Contact System Programmer.

System Programmer Response: Use IPCS to determine the cause for the ABEND, take the corrective action required, perform an LLA,REFRESH, and reload the failing module using the OS/EM ISPF RELOAD facility. Contact OS/EM support for assistance in problem resolution.

FEMJ3E208

ABEND AREGS 8-11: nnnnnnnn nnnnnnnn nnnnnnnn nnnnnnnn

Explanation: The OS/EM has detected a MVS System Abend during execution of an OS/EM optional function or a User exit.

nnnnnnnn: Contents of the Access Register.

Source: FEMJ3ECN

System Action: The OS/EM function being executed continues, OS/EM takes a SVC dump for the abending module, takes the abending module out of service, and deletes the abending module from CSA/ECSA. See messages FEMxxx023, FEMxxx026 and FEMxxx029.

Operator Response: Contact System Programmer.

System Programmer Response: Use IPCS to determine the cause for the ABEND, take the corrective action required, perform an LLA,REFRESH, and reload the failing module using the OS/EM ISPF RELOAD facility. Contact OS/EM support for assistance in problem resolution.

FEMJ3S208

ABEND AREGS 8-11: nnnnnnnn nnnnnnnn nnnnnnnn nnnnnnnn

Explanation: The OS/EM has detected a MVS System Abend during execution of an OS/EM optional function or a User exit.

nnnnnnnn: Contents of the Access Register.

Source: FEMJ3SVC

System Action: The OS/EM function being executed continues, OS/EM takes a SVC dump for the abending module, takes the abending module out of service, and deletes the abending module from CSA/ECSA. See messages FEMxxx023, FEMxxx026 and FEMxxx029.

Operator Response: Contact System Programmer.

System Programmer Response: Use IPCS to determine the cause for the ABEND, take the corrective action required, perform an LLA,REFRESH, and reload the failing module using the OS/EM ISPF RELOAD facility. Contact OS/EM support for assistance in problem resolution.

FEMLOK208

ABEND AREGS 8-11: nnnnnnnn nnnnnnnn nnnnnnnn nnnnnnnn

Explanation: The OS/EM has detected a MVS System Abend during execution of an OS/EM optional function or a User exit.

nnnnnnnn: Contents of the Access Register.

Source: FEMLOCK

System Action: The OS/EM function being executed continues, OS/EM takes a SVC dump for the abending module, takes the abending module out of service, and deletes the abending module from CSA/ECSA. See messages FEMxxx023, FEMxxx026 and FEMxxx029.

Operator Response: Contact System Programmer.

System Programmer Response: Use IPCS to determine the cause for the ABEND, take the corrective action required, perform an LLA,REFRESH, and reload the failing module using the OS/EM ISPF RELOAD facility. Contact OS/EM support for assistance in problem resolution.

FEMRCN208

ABEND AREGS 8-11: nnnnnnnn nnnnnnnn nnnnnnnn nnnnnnnn

Explanation: The OS/EM has detected a MVS System Abend during execution of an OS/EM optional function or a User exit.

nnnnnnnn: Contents of the Access Register.

Source: FEMRACCN

System Action: The OS/EM function being executed continues, OS/EM takes a SVC dump for the abending module, takes the abending module out of service, and deletes the abending module from CSA/ECSA. See messages FEMxxx023, FEMxxx026 and FEMxxx029.

Operator Response: Contact System Programmer.

System Programmer Response: Use IPCS to determine the cause for the ABEND, take the corrective action required, perform an LLA,REFRESH, and reload the failing module using the OS/EM ISPF RELOAD facility. Contact OS/EM support for assistance in problem resolution.

FEMSCN208

ABEND AREGS 8-11: nnnnnnnn nnnnnnnn nnnnnnnn nnnnnnnn

Explanation: The OS/EM has detected a MVS System Abend during execution of an OS/EM optional function or a User exit.

nnnnnnnn: Contents of the Access Register.

Source: FEMSAFCN,FEMSMFCN

System Action: The OS/EM function being executed continues, OS/EM takes a SVC dump for the abending module, takes the abending module out of service, and deletes the abending module from CSA/ECSA. See messages FEMxxx023, FEMxxx026 and FEMxxx029.

Operator Response: Contact System Programmer.

System Programmer Response: Use IPCS to determine the cause for the ABEND, take the corrective action required, perform an LLA,REFRESH, and reload the failing module using the OS/EM ISPF RELOAD facility. Contact OS/EM support for assistance in problem resolution.

FEMTCN208

ABEND AREGS 8-11: nnnnnnnn nnnnnnnn nnnnnnnn nnnnnnnn

Explanation: The OS/EM has detected a MVS System Abend during execution of an OS/EM optional function or a User exit.

nnnnnnnn: Contents of the Access Register.

Source: FEMTSOCN

System Action: The OS/EM function being executed continues, OS/EM takes a SVC dump for the abending module, takes the abending module out of service, and deletes the abending module from CSA/ECSA. See messages FEMxxx023, FEMxxx026 and FEMxxx029.

Operator Response: Contact System Programmer.

System Programmer Response: Use IPCS to determine the cause for the ABEND, take the corrective action required, perform an LLA,REFRESH, and reload the failing module using the OS/EM ISPF RELOAD facility. Contact OS/EM support for assistance in problem resolution.

FEMTPS208

ABEND AREGS 8-11: nnnnnnnn nnnnnnnn nnnnnnnn nnnnnnnn

Explanation: The OS/EM has detected a MVS System Abend during execution of an OS/EM optional function or a User exit.

nnnnnnnn: Contents of the Access Register.

Source: FEMTPSHR

System Action: The OS/EM function being executed continues, OS/EM takes a SVC dump for the abending module, takes the abending module out of service, and deletes the abending module from CSA/ECSA. See messages FEMxxx023, FEMxxx026 and FEMxxx029.

Operator Response: Contact System Programmer.

System Programmer Response: Use IPCS to determine the cause for the ABEND, take the corrective action required, perform an LLA,REFRESH, and reload the failing module using the OS/EM ISPF RELOAD facility. Contact OS/EM support for assistance in problem resolution.

FEMUJI208

ABEND AREGS 8-11: nnnnnnnn nnnnnnnn nnnnnnnn nnnnnnnn

Explanation: The OS/EM has detected a MVS System Abend during execution of an OS/EM optional function or a User exit.

nnnnnnnn: Contents of the Access Register.

Source: FEMUJI

System Action: The OS/EM function being executed continues, OS/EM takes a SVC dump for the abending module, takes the abending module out of service, and deletes the abending module from CSA/ECSA. See messages FEMxxx023, FEMxxx026 and FEMxxx029.

Operator Response: Contact System Programmer.

System Programmer Response: Use IPCS to determine the cause for the ABEND, take the corrective action required, perform an LLA,REFRESH, and reload the failing module using the OS/EM ISPF RELOAD facility. Contact OS/EM support for assistance in problem resolution.

FEMUSI208

ABEND AREGS 8-11: nnnnnnnn nnnnnnnn nnnnnnnn nnnnnnnn

Explanation: The OS/EM has detected a MVS System Abend during execution of an OS/EM optional function or a User exit.

nnnnnnnn: Contents of the Access Register.

Source: FEMUSI

System Action: The OS/EM function being executed continues, OS/EM takes a SVC dump for the abending module, takes the abending module out of service, and deletes the abending module from CSA/ECSA. See messages FEMxxx023, FEMxxx026 and FEMxxx029.

Operator Response: Contact System Programmer.

System Programmer Response: Use IPCS to determine the cause for the ABEND, take the corrective action required, perform an LLA,REFRESH, and reload the failing module using the OS/EM ISPF RELOAD facility. Contact OS/EM support for assistance in problem resolution.

FEMVCN208

ABEND AREGS 8-11: nnnnnnnn nnnnnnnn nnnnnnnn nnnnnnnn

Explanation: The OS/EM has detected a MVS System Abend during execution of an OS/EM optional function or a User exit.

nnnnnnnn: Contents of the Access Register.

Source: FEMSVCCN

System Action: The OS/EM function being executed continues, OS/EM takes a SVC dump for the abending module, takes the abending module out of service, and deletes the abending module from CSA/ECSA. See messages FEMxxx023, FEMxxx026 and FEMxxx029.

Operator Response: Contact System Programmer.

System Programmer Response: Use IPCS to determine the cause for the ABEND, take the corrective action required, perform an LLA,REFRESH, and reload the failing module using the OS/EM ISPF RELOAD facility. Contact OS/EM support for assistance in problem resolution.

FEMX05208

ABEND AREGS 8-11: nnnnnnnn nnnnnnnn nnnnnnnn nnnnnnnn

Explanation: The OS/EM has detected a MVS System Abend during execution of an OS/EM optional function or a User exit.

nnnnnnnn: Contents of the Access Register.

Source: FEMJ2X05

System Action: The OS/EM function being executed continues, OS/EM takes a SVC dump for the abending module, takes the abending module out of service, and deletes the abending module from CSA/ECSA. See messages FEMxxx023, FEMxxx026 and FEMxxx029.

Operator Response: Contact System Programmer.

System Programmer Response: Use IPCS to determine the cause for the ABEND, take the corrective action required, perform an LLA,REFRESH, and reload the failing module using the OS/EM ISPF RELOAD facility. Contact OS/EM support for assistance in problem resolution.

FEM02F208

ABEND AREGS 8-11: nnnnnnnn nnnnnnnn nnnnnnnn nnnnnnnn

Explanation: The OS/EM has detected a MVS System Abend during execution of an OS/EM optional function or a User exit.

nnnnnnnn: Contents of the Access Register.

Source: FEM0002F

System Action: The OS/EM function being executed continues, OS/EM takes a SVC dump for the abending module, takes the abending module out of service, and deletes the abending module from CSA/ECSA. See messages FEMxxx023, FEMxxx026 and FEMxxx029.

Operator Response: Contact System Programmer.

System Programmer Response: Use IPCS to determine the cause for the ABEND, take the corrective action required, perform an LLA,REFRESH, and reload the failing module using the OS/EM ISPF RELOAD facility. Contact OS/EM support for assistance in problem resolution.

FEM1PL208

ABEND AREGS 8-11: nnnnnnnn nnnnnnnn nnnnnnnn nnnnnnnn

Explanation: The OS/EM has detected a MVS System Abend during execution of an OS/EM optional function or a User exit.

nnnnnnnn: Contents of the Access Register.

Source: FEM1PL1

System Action: The OS/EM function being executed continues, OS/EM takes a SVC dump for the abending module, takes the abending module out of service, and deletes the abending module from CSA/ECSA. See messages FEMxxx023, FEMxxx026 and FEMxxx029.

Operator Response: Contact System Programmer.

System Programmer Response: Use IPCS to determine the cause for the ABEND, take the corrective action required, perform an LLA,REFRESH, and reload the failing module using the OS/EM ISPF RELOAD facility. Contact OS/EM support for assistance in problem resolution.

FEM2H5208

ABEND AREGS 8-11: nnnnnnnn nnnnnnnn nnnnnnnn nnnnnnnn

Explanation: The OS/EM has detected a MVS System Abend during execution of an OS/EM optional function or a User exit.

nnnnnnnn: Contents of the Access Register.

Source: FEMJ2H5x

System Action: The OS/EM function being executed continues, OS/EM takes a SVC dump for the abending module, takes the abending module out of service, and deletes the abending module from CSA/ECSA. See messages FEMxxx023, FEMxxx026 and FEMxxx029.

Operator Response: Contact System Programmer.

System Programmer Response: Use IPCS to determine the cause for the ABEND, take the corrective action required, perform an LLA,REFRESH, and reload the failing module using the OS/EM ISPF RELOAD facility. Contact OS/EM support for assistance in problem resolution.

FEM2P4208

ABEND AREGS 8-11: nnnnnnnn nnnnnnnn nnnnnnnn nnnnnnnn

Explanation: The OS/EM has detected a MVS System Abend during execution of an OS/EM optional function or a User exit.

nnnnnnnn: Contents of the Access Register.

Source: FEMJ2P4x

System Action: The OS/EM function being executed continues, OS/EM takes a SVC dump for the abending module, takes the abending module out of service, and deletes the abending module from CSA/ECSA. See messages FEMxxx023, FEMxxx026 and FEMxxx029.

Operator Response: Contact System Programmer.

System Programmer Response: Use IPCS to determine the cause for the ABEND, take the corrective action required, perform an LLA,REFRESH, and reload the failing module using the OS/EM ISPF RELOAD facility. Contact OS/EM support for assistance in problem resolution.

FEMACN209

ABEND AREGS 12-15: nnnnnnnn nnnnnnnn nnnnnnnn nnnnnnnn

Explanation: The OS/EM has detected a MVS System Abend during execution of an OS/EM optional function or a User exit.

nnnnnnnn: Contents of the Access Register.

Source: FEMALCCN

System Action: The OS/EM function being executed continues, OS/EM takes a SVC dump for the abending module, takes the abending module out of service, and deletes the abending module from CSA/ECSA. See messages FEMxxx023, FEMxxx026 and FEMxxx029.

Operator Response: Contact System Programmer.

System Programmer Response: Use IPCS to determine the cause for the ABEND, take the corrective action required, perform an LLA,REFRESH, and reload the failing module using the OS/EM ISPF RELOAD facility. Contact OS/EM support for assistance in problem resolution.

FEMALC209

ABEND AREGS 12-15: nnnnnnnn nnnnnnnn nnnnnnnn nnnnnnnn

Explanation: The OS/EM has detected a MVS System Abend during execution of an OS/EM optional function or a User exit.

nnnnnnnn: Contents of the Access Register.

Source: FEMALLO0,FEMALLO1

System Action: The OS/EM function being executed continues, OS/EM takes a SVC dump for the abending module, takes the abending module out of service, and deletes the abending module from CSA/ECSA. See messages FEMxxx023, FEMxxx026 and FEMxxx029.

Operator Response: Contact System Programmer.

System Programmer Response: Use IPCS to determine the cause for the ABEND, take the corrective action required, perform an LLA,REFRESH, and reload the failing module using the OS/EM ISPF RELOAD facility. Contact OS/EM support for assistance in problem resolution.

FEMASY209

ABEND AREGS 12-15: nnnnnnnn nnnnnnnn nnnnnnnn nnnnnnnn

Explanation: The OS/EM has detected a MVS System Abend during execution of an OS/EM optional function or a User exit.

nnnnnnnn: Contents of the Access Register.

Source: FEMASYNC

System Action: The OS/EM function being executed continues, OS/EM takes a SVC dump for the abending module, takes the abending module out of service, and deletes the abending module from CSA/ECSA. See messages FEMxxx023, FEMxxx026 and FEMxxx029.

Operator Response: Contact System Programmer.

System Programmer Response: Use IPCS to determine the cause for the ABEND, take the corrective action required, perform an LLA,REFRESH, and reload the failing module using the OS/EM ISPF RELOAD facility. Contact OS/EM support for assistance in problem resolution.

FEMCMD209

ABEND AREGS 12-15: nnnnnnnn nnnnnnnn nnnnnnnn nnnnnnnn

Explanation: The OS/EM has detected a MVS System Abend during execution of an OS/EM optional function or a User exit.

nnnnnnnn: Contents of the Access Register.

Source: FEMCMD

System Action: The OS/EM function being executed continues, OS/EM takes a SVC dump for the abending module, takes the abending module out of service, and deletes the abending module from CSA/ECSA. See messages FEMxxx023, FEMxxx026 and FEMxxx029.

Operator Response: Contact System Programmer.

System Programmer Response: Use IPCS to determine the cause for the ABEND, take the corrective action required, perform an LLA,REFRESH, and reload the failing module using the OS/EM ISPF RELOAD facility. Contact OS/EM support for assistance in problem resolution.

FEMCOM209

ABEND AREGS 12-15: nnnnnnnn nnnnnnnn nnnnnnnn nnnnnnnn

Explanation: The OS/EM has detected a MVS System Abend during execution of an OS/EM optional function or a User exit.

nnnnnnnn: Contents of the Access Register.

Source: FEMCOMM

System Action: The OS/EM function being executed continues, OS/EM takes a SVC dump for the abending module, takes the abending module out of service, and deletes the abending module from CSA/ECSA. See messages FEMxxx023, FEMxxx026 and FEMxxx029.

Operator Response: Contact System Programmer.

System Programmer Response: Use IPCS to determine the cause for the ABEND, take the corrective action required, perform an LLA,REFRESH, and reload the failing module using the OS/EM ISPF RELOAD facility. Contact OS/EM support for assistance in problem resolution.

FEMDCN209

ABEND AREGS 12-15: nnnnnnnn nnnnnnnn nnnnnnnn nnnnnnnn

Explanation: The OS/EM has detected a MVS System Abend during execution of an OS/EM optional function or a User exit.

nnnnnnnn: Contents of the Access Register.

Source: FEMDADCN

System Action: The OS/EM function being executed continues, OS/EM takes a SVC dump for the abending module, takes the abending module out of service, and deletes the abending module from CSA/ECSA. See messages FEMxxx023, FEMxxx026 and FEMxxx029.

Operator Response: Contact System Programmer.

System Programmer Response: Use IPCS to determine the cause for the ABEND, take the corrective action required, perform an LLA,REFRESH, and reload the failing module using the OS/EM ISPF RELOAD facility. Contact OS/EM support for assistance in problem resolution.

FEMDC1209

ABEND AREGS 12-15: nnnnnnnn nnnnnnnn nnnnnnnn nnnnnnnn

Explanation: The OS/EM has detected a MVS System Abend during execution of an OS/EM optional function or a User exit.

nnnnnnnn: Contents of the Access Register.

Source: FEMDCB1

System Action: The OS/EM function being executed continues, OS/EM takes a SVC dump for the abending module, takes the abending module out of service, and deletes the abending module from CSA/ECSA. See messages FEMxxx023, FEMxxx026 and FEMxxx029.

Operator Response: Contact System Programmer.

System Programmer Response: Use IPCS to determine the cause for the ABEND, take the corrective action required, perform an LLA,REFRESH, and reload the failing module using the OS/EM ISPF RELOAD facility. Contact OS/EM support for assistance in problem resolution.

FEMEXR209

ABEND AREGS 12-15: nnnnnnnn nnnnnnnn nnnnnnnn nnnnnnnn

Explanation: The OS/EM has detected a MVS System Abend during execution of an OS/EM optional function or a User exit.

nnnnnnnn: Contents of the Access Register.

Source: FEMEXRTN

System Action: The OS/EM function being executed continues, OS/EM takes a SVC dump for the abending module, takes the abending module out of service, and deletes the abending module from CSA/ECSA. See messages FEMxxx023, FEMxxx026 and FEMxxx029.

Operator Response: Contact System Programmer.

System Programmer Response: Use IPCS to determine the cause for the ABEND, take the corrective action required, perform an LLA,REFRESH, and reload the failing module using the OS/EM ISPF RELOAD facility. Contact OS/EM support for assistance in problem resolution.

FEMFRA209

ABEND AREGS 12-15: nnnnnnnn nnnnnnnn nnnnnnnn nnnnnnnn

Explanation: The OS/EM has detected a MVS System Abend during execution of an OS/EM optional function or a User exit.

nnnnnnnn: Contents of the Access Register.

Source: FEMFRACN

System Action: The OS/EM function being executed continues, OS/EM takes a SVC dump for the abending module, takes the abending module out of service, and deletes the abending module from CSA/ECSA. See messages FEMxxx023, FEMxxx026 and FEMxxx029.

Operator Response: Contact System Programmer.

System Programmer Response: Use IPCS to determine the cause for the ABEND, take the corrective action required, perform an LLA,REFRESH, and reload the failing module using the OS/EM ISPF RELOAD facility. Contact OS/EM support for assistance in problem resolution.

FEMFTN209

ABEND AREGS 12-15: nnnnnnnn nnnnnnnn nnnnnnnn nnnnnnnn

Explanation: The OS/EM has detected a MVS System Abend during execution of an OS/EM optional function or a User exit.

nnnnnnnn: Contents of the Access Register.

Source: FEMFRRTN

System Action: The OS/EM function being executed continues, OS/EM takes a SVC dump for the abending module, takes the abending module out of service, and deletes the abending module from CSA/ECSA. See messages FEMxxx023, FEMxxx026 and FEMxxx029.

Operator Response: Contact System Programmer.

System Programmer Response: Use IPCS to determine the cause for the ABEND, take the corrective action required, perform an LLA,REFRESH, and reload the failing module using the OS/EM ISPF RELOAD facility. Contact OS/EM support for assistance in problem resolution.

FEMHCN209

ABEND AREGS 12-15: nnnnnnnn nnnnnnnn nnnnnnnn nnnnnnnn

Explanation: The OS/EM has detected a MVS System Abend during execution of an OS/EM optional function or a User exit.

nnnnnnnn: Contents of the Access Register.

Source: FEMHSMCN

System Action: The OS/EM function being executed continues, OS/EM takes a SVC dump for the abending module, takes the abending module out of service, and deletes the abending module from CSA/ECSA. See messages FEMxxx023, FEMxxx026 and FEMxxx029.

Operator Response: Contact System Programmer.

System Programmer Response: Use IPCS to determine the cause for the ABEND, take the corrective action required, perform an LLA,REFRESH, and reload the failing module using the OS/EM ISPF RELOAD facility. Contact OS/EM support for assistance in problem resolution.

FEMHSP209

ABEND AREGS 12-15: nnnnnnnn nnnnnnnn nnnnnnnn nnnnnnnn

Explanation: The OS/EM has detected a MVS System Abend during execution of an OS/EM optional function or a User exit.

nnnnnnnn: Contents of the Access Register.

Source: FEMHJ20

System Action: The OS/EM function being executed continues, OS/EM takes a SVC dump for the abending module, takes the abending module out of service, and deletes the abending module from CSA/ECSA. See messages FEMxxx023, FEMxxx026 and FEMxxx029.

Operator Response: Contact System Programmer.

System Programmer Response: Use IPCS to determine the cause for the ABEND, take the corrective action required, perform an LLA,REFRESH, and reload the failing module using the OS/EM ISPF RELOAD facility. Contact OS/EM support for assistance in problem resolution.

FEMIAT209

ABEND AREGS 12-15: nnnnnnnn nnnnnnnn nnnnnnnn nnnnnnnn

Explanation: The OS/EM has detected a MVS System Abend during execution of an OS/EM optional function or a User exit.

nnnnnnnn: Contents of the Access Register.

Source: FEMINTK

System Action: The OS/EM function being executed continues, OS/EM takes a SVC dump for the abending module, takes the abending module out of service, and deletes the abending module from CSA/ECSA. See messages FEMxxx023, FEMxxx026 and FEMxxx029.

Operator Response: Contact System Programmer.

System Programmer Response: Use IPCS to determine the cause for the ABEND, take the corrective action required, perform an LLA,REFRESH, and reload the failing module using the OS/EM ISPF RELOAD facility. Contact OS/EM support for assistance in problem resolution.

FEMICN209

ABEND AREGS 12-15: nnnnnnnn nnnnnnnn nnnnnnnn nnnnnnnn

Explanation: The OS/EM has detected a MVS System Abend during execution of an OS/EM optional function or a User exit.

nnnnnnnn: Contents of the Access Register.

Source: FEMISPCN

System Action: The OS/EM function being executed continues, OS/EM takes a SVC dump for the abending module, takes the abending module out of service, and deletes the abending module from CSA/ECSA. See messages FEMxxx023, FEMxxx026 and FEMxxx029.

Operator Response: Contact System Programmer.

System Programmer Response: Use IPCS to determine the cause for the ABEND, take the corrective action required, perform an LLA,REFRESH, and reload the failing module using the OS/EM ISPF RELOAD facility. Contact OS/EM support for assistance in problem resolution.

FEMIPL209

ABEND AREGS 12-15: nnnnnnnn nnnnnnnn nnnnnnnn nnnnnnnn

Explanation: The OS/EM has detected a MVS System Abend during execution of an OS/EM optional function or a User exit.

nnnnnnnn: Contents of the Access Register.

Source: FEMIPL

System Action: The OS/EM function being executed continues, OS/EM takes a SVC dump for the abending module, takes the abending module out of service, and deletes the abending module from CSA/ECSA. See messages FEMxxx023, FEMxxx026 and FEMxxx029.

Operator Response: Contact System Programmer.

System Programmer Response: Use IPCS to determine the cause for the ABEND, take the corrective action required, perform an LLA,REFRESH, and reload the failing module using the OS/EM ISPF RELOAD facility. Contact OS/EM support for assistance in problem resolution.

FEMJS2209

ABEND AREGS 12-15: nnnnnnnn nnnnnnnn nnnnnnnn nnnnnnnn

Explanation: The OS/EM has detected a MVS System Abend during execution of an OS/EM optional function or a User exit.

nnnnnnnn: Contents of the Access Register.

Source: FEMJES2B,FEMJES2G

System Action: The OS/EM function being executed continues, OS/EM takes a SVC dump for the abending module, takes the abending module out of service, and deletes the abending module from CSA/ECSA. See messages FEMxxx023, FEMxxx026 and FEMxxx029.

Operator Response: Contact System Programmer.

System Programmer Response: Use IPCS to determine the cause for the ABEND, take the corrective action required, perform an LLA,REFRESH, and reload the failing module using the OS/EM ISPF RELOAD facility. Contact OS/EM support for assistance in problem resolution.

FEMJ2M209

ABEND AREGS 12-15: nnnnnnnn nnnnnnnn nnnnnnnn nnnnnnnn

Explanation: The OS/EM has detected a MVS System Abend during execution of an OS/EM optional function or a User exit.

nnnnnnnn: Contents of the Access Register.

Source: FEMJ2MCx

System Action: The OS/EM function being executed continues, OS/EM takes a SVC dump for the abending module, takes the abending module out of service, and deletes the abending module from CSA/ECSA. See messages FEMxxx023, FEMxxx026 and FEMxxx029.

Operator Response: Contact System Programmer.

System Programmer Response: Use IPCS to determine the cause for the ABEND, take the corrective action required, perform an LLA,REFRESH, and reload the failing module using the OS/EM ISPF RELOAD facility. Contact OS/EM support for assistance in problem resolution.

FEMJ2R209

ABEND AREGS 12-15: nnnnnnnn nnnnnnnn nnnnnnnn nnnnnnnn

Explanation: The OS/EM has detected a MVS System Abend during execution of an OS/EM optional function or a User exit.

nnnnnnnn: Contents of the Access Register.

Source: FEMJ2ERx

System Action: The OS/EM function being executed continues, OS/EM takes a SVC dump for the abending module, takes the abending module out of service, and deletes the abending module from CSA/ECSA. See messages FEMxxx023, FEMxxx026 and FEMxxx029.

Operator Response: Contact System Programmer.

System Programmer Response: Use IPCS to determine the cause for the ABEND, take the corrective action required, perform an LLA,REFRESH, and reload the failing module using the OS/EM ISPF RELOAD facility. Contact OS/EM support for assistance in problem resolution.

FEMJ2S209

ABEND AREGS 12-15: nnnnnnnn nnnnnnnn nnnnnnnn nnnnnnnn

Explanation: The OS/EM has detected a MVS System Abend during execution of an OS/EM optional function or a User exit.

nnnnnnnn: Contents of the Access Register.

Source: FEMJ2SCx

System Action: The OS/EM function being executed continues, OS/EM takes a SVC dump for the abending module, takes the abending module out of service, and deletes the abending module from CSA/ECSA. See messages FEMxxx023, FEMxxx026 and FEMxxx029.

Operator Response: Contact System Programmer.

System Programmer Response: Use IPCS to determine the cause for the ABEND, take the corrective action required, perform an LLA,REFRESH, and reload the failing module using the OS/EM ISPF RELOAD facility. Contact OS/EM support for assistance in problem resolution.

FEMJ3E209

ABEND AREGS 12-15: nnnnnnnn nnnnnnnn nnnnnnnn nnnnnnnn

Explanation: The OS/EM has detected a MVS System Abend during execution of an OS/EM optional function or a User exit.

nnnnnnnn: Contents of the Access Register.

Source: FEMJ3ECN

System Action: The OS/EM function being executed continues, OS/EM takes a SVC dump for the abending module, takes the abending module out of service, and deletes the abending module from CSA/ECSA. See messages FEMxxx023, FEMxxx026 and FEMxxx029.

Operator Response: Contact System Programmer.

System Programmer Response: Use IPCS to determine the cause for the ABEND, take the corrective action required, perform an LLA,REFRESH, and reload the failing module using the OS/EM ISPF RELOAD facility. Contact OS/EM support for assistance in problem resolution.

FEMJ3S209

ABEND AREGS 12-15: nnnnnnnn nnnnnnnn nnnnnnnn nnnnnnnn

Explanation: The OS/EM has detected a MVS System Abend during execution of an OS/EM optional function or a User exit.

nnnnnnnn: Contents of the Access Register.

Source: FEMJ3SVC

System Action: The OS/EM function being executed continues, OS/EM takes a SVC dump for the abending module, takes the abending module out of service, and deletes the abending module from CSA/ECSA. See messages FEMxxx023, FEMxxx026 and FEMxxx029.

Operator Response: Contact System Programmer.

System Programmer Response: Use IPCS to determine the cause for the ABEND, take the corrective action required, perform an LLA,REFRESH, and reload the failing module using the OS/EM ISPF RELOAD facility. Contact OS/EM support for assistance in problem resolution.

FEMLOK209

ABEND AREGS 12-15: nnnnnnnn nnnnnnnn nnnnnnnn nnnnnnnn

Explanation: The OS/EM has detected a MVS System Abend during execution of an OS/EM optional function or a User exit.

nnnnnnnn: Contents of the Access Register.

Source: FEMLOCK

System Action: The OS/EM function being executed continues, OS/EM takes a SVC dump for the abending module, takes the abending module out of service, and deletes the abending module from CSA/ECSA. See messages FEMxxx023, FEMxxx026 and FEMxxx029.

Operator Response: Contact System Programmer.

System Programmer Response: Use IPCS to determine the cause for the ABEND, take the corrective action required, perform an LLA,REFRESH, and reload the failing module using the OS/EM ISPF RELOAD facility. Contact OS/EM support for assistance in problem resolution.

FEMRCN209

ABEND AREGS 12-15: nnnnnnnn nnnnnnnn nnnnnnnn nnnnnnnn

Explanation: The OS/EM has detected a MVS System Abend during execution of an OS/EM optional function or a User exit.

nnnnnnnn: Contents of the Access Register.

Source: FEMRACCN

System Action: The OS/EM function being executed continues, OS/EM takes a SVC dump for the abending module, takes the abending module out of service, and deletes the abending module from CSA/ECSA. See messages FEMxxx023, FEMxxx026 and FEMxxx029.

Operator Response: Contact System Programmer.

System Programmer Response: Use IPCS to determine the cause for the ABEND, take the corrective action required, perform an LLA,REFRESH, and reload the failing module using the OS/EM ISPF RELOAD facility. Contact OS/EM support for assistance in problem resolution.

FEMSCN209

ABEND AREGS 12-15: nnnnnnnn nnnnnnnn nnnnnnnn nnnnnnnn

Explanation: The OS/EM has detected a MVS System Abend during execution of an OS/EM optional function or a User exit.

nnnnnnnn: Contents of the Access Register.

Source: FEMSAFCN,FEMSMFCN

System Action: The OS/EM function being executed continues, OS/EM takes a SVC dump for the abending module, takes the abending module out of service, and deletes the abending module from CSA/ECSA. See messages FEMxxx023, FEMxxx026 and FEMxxx029.

Operator Response: Contact System Programmer.

System Programmer Response: Use IPCS to determine the cause for the ABEND, take the corrective action required, perform an LLA,REFRESH, and reload the failing module using the OS/EM ISPF RELOAD facility. Contact OS/EM support for assistance in problem resolution.

FEMTCN209

ABEND AREGS 12-15: nnnnnnnn nnnnnnnn nnnnnnnn nnnnnnnn

Explanation: The OS/EM has detected a MVS System Abend during execution of an OS/EM optional function or a User exit.

nnnnnnnn: Contents of the Access Register.

Source: FEMTSOCN

System Action: The OS/EM function being executed continues, OS/EM takes a SVC dump for the abending module, takes the abending module out of service, and deletes the abending module from CSA/ECSA. See messages FEMxxx023, FEMxxx026 and FEMxxx029.

Operator Response: Contact System Programmer.

System Programmer Response: Use IPCS to determine the cause for the ABEND, take the corrective action required, perform an LLA,REFRESH, and reload the failing module using the OS/EM ISPF RELOAD facility. Contact OS/EM support for assistance in problem resolution.

FEMTPS209

ABEND AREGS 12-15: nnnnnnnn nnnnnnnn nnnnnnnn nnnnnnnn

Explanation: The OS/EM has detected a MVS System Abend during execution of an OS/EM optional function or a User exit.

nnnnnnnn: Contents of the Access Register.

Source: FEMTPSHR

System Action: The OS/EM function being executed continues, OS/EM takes a SVC dump for the abending module, takes the abending module out of service, and deletes the abending module from CSA/ECSA. See messages FEMxxx023, FEMxxx026 and FEMxxx029.

Operator Response: Contact System Programmer.

System Programmer Response: Use IPCS to determine the cause for the ABEND, take the corrective action required, perform an LLA,REFRESH, and reload the failing module using the OS/EM ISPF RELOAD facility. Contact OS/EM support for assistance in problem resolution.

FEMUJI209

ABEND AREGS 12-15: nnnnnnnn nnnnnnnn nnnnnnnn nnnnnnnn

Explanation: The OS/EM has detected a MVS System Abend during execution of an OS/EM optional function or a User exit.

nnnnnnnn: Contents of the Access Register.

Source: FEMUJI

System Action: The OS/EM function being executed continues, OS/EM takes a SVC dump for the abending module, takes the abending module out of service, and deletes the abending module from CSA/ECSA. See messages FEMxxx023, FEMxxx026 and FEMxxx029.

Operator Response: Contact System Programmer.

System Programmer Response: Use IPCS to determine the cause for the ABEND, take the corrective action required, perform an LLA,REFRESH, and reload the failing module using the OS/EM ISPF RELOAD facility. Contact OS/EM support for assistance in problem resolution.

FEMUSI209

ABEND AREGS 12-15: nnnnnnnn nnnnnnnn nnnnnnnn nnnnnnnn

Explanation: The OS/EM has detected a MVS System Abend during execution of an OS/EM optional function or a User exit.

nnnnnnnn: Contents of the Access Register.

Source: FEMUSI

System Action: The OS/EM function being executed continues, OS/EM takes a SVC dump for the abending module, takes the abending module out of service, and deletes the abending module from CSA/ECSA. See messages FEMxxx023, FEMxxx026 and FEMxxx029.

Operator Response: Contact System Programmer.

System Programmer Response: Use IPCS to determine the cause for the ABEND, take the corrective action required, perform an LLA,REFRESH, and reload the failing module using the OS/EM ISPF RELOAD facility. Contact OS/EM support for assistance in problem resolution.

FEMVCN209

ABEND AREGS 12-15: nnnnnnnn nnnnnnnn nnnnnnnn nnnnnnnn

Explanation: The OS/EM has detected a MVS System Abend during execution of an OS/EM optional function or a User exit.

nnnnnnnn: Contents of the Access Register.

Source: FEMSVCCN

System Action: The OS/EM function being executed continues, OS/EM takes a SVC dump for the abending module, takes the abending module out of service, and deletes the abending module from CSA/ECSA. See messages FEMxxx023, FEMxxx026 and FEMxxx029.

Operator Response: Contact System Programmer.

System Programmer Response: Use IPCS to determine the cause for the ABEND, take the corrective action required, perform an LLA,REFRESH, and reload the failing module using the OS/EM ISPF RELOAD facility. Contact OS/EM support for assistance in problem resolution.

FEMX05209

ABEND AREGS 12-15: nnnnnnnn nnnnnnnn nnnnnnnn nnnnnnnn

Explanation: The OS/EM has detected a MVS System Abend during execution of an OS/EM optional function or a User exit.

nnnnnnnn: Contents of the Access Register.

Source: FEMJ2X05

System Action: The OS/EM function being executed continues, OS/EM takes a SVC dump for the abending module, takes the abending module out of service, and deletes the abending module from CSA/ECSA. See messages FEMxxx023, FEMxxx026 and FEMxxx029.

Operator Response: Contact System Programmer.

System Programmer Response: Use IPCS to determine the cause for the ABEND, take the corrective action required, perform an LLA,REFRESH, and reload the failing module using the OS/EM ISPF RELOAD facility. Contact OS/EM support for assistance in problem resolution.

FEM02F209

ABEND AREGS 12-15: nnnnnnnn nnnnnnnn nnnnnnnn nnnnnnnn

Explanation: The OS/EM has detected a MVS System Abend during execution of an OS/EM optional function or a User exit.

nnnnnnnn: Contents of the Access Register.

Source: FEM0002F

System Action: The OS/EM function being executed continues, OS/EM takes a SVC dump for the abending module, takes the abending module out of service, and deletes the abending module from CSA/ECSA. See messages FEMxxx023, FEMxxx026 and FEMxxx029.

Operator Response: Contact System Programmer.

System Programmer Response: Use IPCS to determine the cause for the ABEND, take the corrective action required, perform an LLA,REFRESH, and reload the failing module using the OS/EM ISPF RELOAD facility. Contact OS/EM support for assistance in problem resolution.

FEM1PL209

ABEND AREGS 12-15: nnnnnnnn nnnnnnnn nnnnnnnn nnnnnnnn

Explanation: The OS/EM has detected a MVS System Abend during execution of an OS/EM optional function or a User exit.

nnnnnnnn: Contents of the Access Register.

Source: FEM1PL1

System Action: The OS/EM function being executed continues, OS/EM takes a SVC dump for the abending module, takes the abending module out of service, and deletes the abending module from CSA/ECSA. See messages FEMxxx023, FEMxxx026 and FEMxxx029.

Operator Response: Contact System Programmer.

System Programmer Response: Use IPCS to determine the cause for the ABEND, take the corrective action required, perform an LLA,REFRESH, and reload the failing module using the OS/EM ISPF RELOAD facility. Contact OS/EM support for assistance in problem resolution.

FEM2H5209

ABEND AREGS 12-15: nnnnnnnn nnnnnnnn nnnnnnnn nnnnnnnn

Explanation: The OS/EM has detected a MVS System Abend during execution of an OS/EM optional function or a User exit.

nnnnnnnn: Contents of the Access Register.

Source: FEMJ2H5x

System Action: The OS/EM function being executed continues, OS/EM takes a SVC dump for the abending module, takes the abending module out of service, and deletes the abending module from CSA/ECSA. See messages FEMxxx023, FEMxxx026 and FEMxxx029.

Operator Response: Contact System Programmer.

System Programmer Response: Use IPCS to determine the cause for the ABEND, take the corrective action required, perform an LLA,REFRESH, and reload the failing module using the OS/EM ISPF RELOAD facility. Contact OS/EM support for assistance in problem resolution.

FEM2P4209

ABEND AREGS 12-15: nnnnnnnn nnnnnnnn nnnnnnnn nnnnnnnn

Explanation: The OS/EM has detected a MVS System Abend during execution of an OS/EM optional function or a User exit.

nnnnnnnn: Contents of the Access Register.

Source: FEMJ2P4x

System Action: The OS/EM function being executed continues, OS/EM takes a SVC dump for the abending module, takes the abending module out of service, and deletes the abending module from CSA/ECSA. See messages FEMxxx023, FEMxxx026 and FEMxxx029.

Operator Response: Contact System Programmer.

System Programmer Response: Use IPCS to determine the cause for the ABEND, take the corrective action required, perform an LLA,REFRESH, and reload the failing module using the OS/EM ISPF RELOAD facility. Contact OS/EM support for assistance in problem resolution.

FEMACN210

ABEND AREGS 0-1: nnnnnnnnnnnnnnnn nnnnnnnnnnnnnnnn

Explanation: The OS/EM has detected a MVS System Abend during execution of an OS/EM optional function or a User exit. This message applies to z/OS environments operating in 64-bit mode.

nnnnnnnnnnnnnnnn: Contents of the General Purpose Register.

Source: FEMALCCN

System Action: The OS/EM function being executed continues, OS/EM takes a SVC dump for the abending module, takes the abending module out of service, and deletes the abending module from CSA/ECSA. See messages FEMxxx023, FEMxxx026 and FEMxxx029.

Operator Response: Contact System Programmer.

System Programmer Response: Use IPCS to determine the cause for the ABEND, take the corrective action required, perform an LLA,REFRESH, and reload the failing module using the OS/EM ISPF RELOAD facility. Contact OS/EM support for assistance in problem resolution.

FEMALC210

ABEND AREGS 0-1: nnnnnnnnnnnnnnnn nnnnnnnnnnnnnnnn

Explanation: The OS/EM has detected a MVS System Abend during execution of an OS/EM optional function or a User exit. This message applies to z/OS environments operating in 64-bit mode.

nnnnnnnnnnnnnnnn: Contents of the General Purpose Register.

Source: FEMALLO0,FEMALLO1

System Action: The OS/EM function being executed continues, OS/EM takes a SVC dump for the abending module, takes the abending module out of service, and deletes the abending module from CSA/ECSA. See messages FEMxxx023, FEMxxx026 and FEMxxx029.

Operator Response: Contact System Programmer.

System Programmer Response: Use IPCS to determine the cause for the ABEND, take the corrective action required, perform an LLA,REFRESH, and reload the failing module using the OS/EM ISPF RELOAD facility. Contact OS/EM support for assistance in problem resolution.

FEMFRA210

ABEND AREGS 0-1: nnnnnnnnnnnnnnnn nnnnnnnnnnnnnnnn

Explanation: The OS/EM has detected a MVS System Abend during execution of an OS/EM optional function or a User exit. This message applies to z/OS environments operating in 64-bit mode.

nnnnnnnnnnnnnnnn: Contents of the General Purpose Register.

Source: FEMFRACN

System Action: The OS/EM function being executed continues, OS/EM takes a SVC dump for the abending module, takes the abending module out of service, and deletes the abending module from CSA/ECSA. See messages FEMxxx023, FEMxxx026 and FEMxxx029.

Operator Response: Contact System Programmer.

System Programmer Response: Use IPCS to determine the cause for the ABEND, take the corrective action required, perform an LLA,REFRESH, and reload the failing module using the OS/EM ISPF RELOAD facility. Contact OS/EM support for assistance in problem resolution.

FEMFTN210

ABEND AREGS 0-1: nnnnnnnnnnnnnnnn nnnnnnnnnnnnnnnn

Explanation: The OS/EM has detected a MVS System Abend during execution of an OS/EM optional function or a User exit. This message applies to z/OS environments operating in 64-bit mode.

nnnnnnnnnnnnnnnn: Contents of the General Purpose Register.

Source: FEMFRRTN

System Action: The OS/EM function being executed continues, OS/EM takes a SVC dump for the abending module, takes the abending module out of service, and deletes the abending module from CSA/ECSA. See messages FEMxxx023, FEMxxx026 and FEMxxx029.

Operator Response: Contact System Programmer.

System Programmer Response: Use IPCS to determine the cause for the ABEND, take the corrective action required, perform an LLA,REFRESH, and reload the failing module using the OS/EM ISPF RELOAD facility. Contact OS/EM support for assistance in problem resolution.

FEMHCN210

ABEND AREGS 0-1: nnnnnnnnnnnnnnnn nnnnnnnnnnnnnnnn

Explanation: The OS/EM has detected a MVS System Abend during execution of an OS/EM optional function or a User exit. This message applies to z/OS environments operating in 64-bit mode.

nnnnnnnnnnnnnnnn: Contents of the General Purpose Register.

Source: FEMHSMCN

System Action: The OS/EM function being executed continues, OS/EM takes a SVC dump for the abending module, takes the abending module out of service, and deletes the abending module from CSA/ECSA. See messages FEMxxx023, FEMxxx026 and FEMxxx029.

Operator Response: Contact System Programmer.

System Programmer Response: Use IPCS to determine the cause for the ABEND, take the corrective action required, perform an LLA,REFRESH, and reload the failing module using the OS/EM ISPF RELOAD facility. Contact OS/EM support for assistance in problem resolution.

FEMHSP210

ABEND AREGS 0-1: nnnnnnnnnnnnnnnn nnnnnnnnnnnnnnnn

Explanation: The OS/EM has detected a MVS System Abend during execution of an OS/EM optional function or a User exit. This message applies to z/OS environments operating in 64-bit mode.

nnnnnnnnnnnnnnnn: Contents of the General Purpose Register.

Source: FEMHJ20

System Action: The OS/EM function being executed continues, OS/EM takes a SVC dump for the abending module, takes the abending module out of service, and deletes the abending module from CSA/ECSA. See messages FEMxxx023, FEMxxx026 and FEMxxx029.

Operator Response: Contact System Programmer.

System Programmer Response: Use IPCS to determine the cause for the ABEND, take the corrective action required, perform an LLA,REFRESH, and reload the failing module using the OS/EM ISPF RELOAD facility. Contact OS/EM support for assistance in problem resolution.

FEMIAT210

ABEND AREGS 0-1: nnnnnnnnnnnnnnnn nnnnnnnnnnnnnnnn

Explanation: The OS/EM has detected a MVS System Abend during execution of an OS/EM optional function or a User exit. This message applies to z/OS environments operating in 64-bit mode.

nnnnnnnnnnnnnnnn: Contents of the General Purpose Register.

Source: FEMINTK

System Action: The OS/EM function being executed continues, OS/EM takes a SVC dump for the abending module, takes the abending module out of service, and deletes the abending module from CSA/ECSA. See messages FEMxxx023, FEMxxx026 and FEMxxx029.

Operator Response: Contact System Programmer.

System Programmer Response: Use IPCS to determine the cause for the ABEND, take the corrective action required, perform an LLA,REFRESH, and reload the failing module using the OS/EM ISPF RELOAD facility. Contact OS/EM support for assistance in problem resolution.

FEMICN210

ABEND AREGS 0-1: nnnnnnnnnnnnnnnn nnnnnnnnnnnnnnnn

Explanation: The OS/EM has detected a MVS System Abend during execution of an OS/EM optional function or a User exit. This message applies to z/OS environments operating in 64-bit mode.

nnnnnnnnnnnnnnnn: Contents of the General Purpose Register.

Source: FEMISPCN

System Action: The OS/EM function being executed continues, OS/EM takes a SVC dump for the abending module, takes the abending module out of service, and deletes the abending module from CSA/ECSA. See messages FEMxxx023, FEMxxx026 and FEMxxx029.

Operator Response: Contact System Programmer.

System Programmer Response: Use IPCS to determine the cause for the ABEND, take the corrective action required, perform an LLA,REFRESH, and reload the failing module using the OS/EM ISPF RELOAD facility. Contact OS/EM support for assistance in problem resolution.

FEM IPL210

ABEND AREGS 0-1: nnnnnnnnnnnnnnnn nnnnnnnnnnnnnnnn

Explanation: The OS/EM has detected a MVS System Abend during execution of an OS/EM optional function or a User exit. This message applies to z/OS environments operating in 64-bit mode.

nnnnnnnnnnnnnnnn: Contents of the General Purpose Register.

Source: FEM IPL

System Action: The OS/EM function being executed continues, OS/EM takes a SVC dump for the abending module, takes the abending module out of service, and deletes the abending module from CSA/ECSA. See messages FEMxxx023, FEMxxx026 and FEMxxx029.

Operator Response: Contact System Programmer.

System Programmer Response: Use IPCS to determine the cause for the ABEND, take the corrective action required, perform an LLA,REFRESH, and reload the failing module using the OS/EM ISPF RELOAD facility. Contact OS/EM support for assistance in problem resolution.

FEM JS2210

ABEND AREGS 0-1: nnnnnnnnnnnnnnnn nnnnnnnnnnnnnnnn

Explanation: The OS/EM has detected a MVS System Abend during execution of an OS/EM optional function or a User exit. This message applies to z/OS environments operating in 64-bit mode.

nnnnnnnnnnnnnnnn: Contents of the General Purpose Register.

Source: FEMJES2B,FEMJES2G

System Action: The OS/EM function being executed continues, OS/EM takes a SVC dump for the abending module, takes the abending module out of service, and deletes the abending module from CSA/ECSA. See messages FEMxxx023, FEMxxx026 and FEMxxx029.

Operator Response: Contact System Programmer.

System Programmer Response: Use IPCS to determine the cause for the ABEND, take the corrective action required, perform an LLA,REFRESH, and reload the failing module using the OS/EM ISPF RELOAD facility. Contact OS/EM support for assistance in problem resolution.

FEM J2M210

ABEND AREGS 0-1: nnnnnnnnnnnnnnnn nnnnnnnnnnnnnnnn

Explanation: The OS/EM has detected a MVS System Abend during execution of an OS/EM optional function or a User exit. This message applies to z/OS environments operating in 64-bit mode.

nnnnnnnnnnnnnnnn: Contents of the General Purpose Register.

Source: FEMJ2MCx

System Action: The OS/EM function being executed continues, OS/EM takes a SVC dump for the abending module, takes the abending module out of service, and deletes the abending module from CSA/ECSA. See messages FEMxxx023, FEMxxx026 and FEMxxx029.

Operator Response: Contact System Programmer.

System Programmer Response: Use IPCS to determine the cause for the ABEND, take the corrective action required, perform an LLA,REFRESH, and reload the failing module using the OS/EM ISPF RELOAD facility. Contact OS/EM support for assistance in problem resolution.

FEMUJI210

ABEND AREGS 0-1: nnnnnnnnnnnnnnnnnnnn nnnnnnnnnnnnnnnnnnnn

Explanation: The OS/EM has detected a MVS System Abend during execution of an OS/EM optional function or a User exit. This message applies to z/OS environments operating in 64-bit mode.

nnnnnnnnnnnnnnnnnnn: Contents of the General Purpose Register.

Source: FEMUJI

System Action: The OS/EM function being executed continues, OS/EM takes a SVC dump for the abending module, takes the abending module out of service, and deletes the abending module from CSA/ECSA. See messages FEMxxx023, FEMxxx026 and FEMxxx029.

Operator Response: Contact System Programmer.

System Programmer Response: Use IPCS to determine the cause for the ABEND, take the corrective action required, perform an LLA,REFRESH, and reload the failing module using the OS/EM ISPF RELOAD facility. Contact OS/EM support for assistance in problem resolution.

FEMUSI210

ABEND AREGS 0-1: nnnnnnnnnnnnnnnnnnnn nnnnnnnnnnnnnnnnnnnn

Explanation: The OS/EM has detected a MVS System Abend during execution of an OS/EM optional function or a User exit. This message applies to z/OS environments operating in 64-bit mode.

nnnnnnnnnnnnnnnnnnn: Contents of the General Purpose Register.

Source: FEMUSI

System Action: The OS/EM function being executed continues, OS/EM takes a SVC dump for the abending module, takes the abending module out of service, and deletes the abending module from CSA/ECSA. See messages FEMxxx023, FEMxxx026 and FEMxxx029.

Operator Response: Contact System Programmer.

System Programmer Response: Use IPCS to determine the cause for the ABEND, take the corrective action required, perform an LLA,REFRESH, and reload the failing module using the OS/EM ISPF RELOAD facility. Contact OS/EM support for assistance in problem resolution.

FEMVCN210

ABEND AREGS 0-1: nnnnnnnnnnnnnnnnnnnn nnnnnnnnnnnnnnnnnnnn

Explanation: The OS/EM has detected a MVS System Abend during execution of an OS/EM optional function or a User exit. This message applies to z/OS environments operating in 64-bit mode.

nnnnnnnnnnnnnnnnnnn: Contents of the General Purpose Register.

Source: FEMSVCCN

System Action: The OS/EM function being executed continues, OS/EM takes a SVC dump for the abending module, takes the abending module out of service, and deletes the abending module from CSA/ECSA. See messages FEMxxx023, FEMxxx026 and FEMxxx029.

Operator Response: Contact System Programmer.

System Programmer Response: Use IPCS to determine the cause for the ABEND, take the corrective action required, perform an LLA,REFRESH, and reload the failing module using the OS/EM ISPF RELOAD facility. Contact OS/EM support for assistance in problem resolution.

FEMX05210

ABEND AREGS 0-1: nnnnnnnnnnnnnnnn nnnnnnnnnnnnnnnn

Explanation: The OS/EM has detected a MVS System Abend during execution of an OS/EM optional function or a User exit. This message applies to z/OS environments operating in 64-bit mode.

nnnnnnnnnnnnnnnnn: Contents of the General Purpose Register.

Source: FEMJ2X05

System Action: The OS/EM function being executed continues, OS/EM takes a SVC dump for the abending module, takes the abending module out of service, and deletes the abending module from CSA/ECSA. See messages FEMxxx023, FEMxxx026 and FEMxxx029.

Operator Response: Contact System Programmer.

System Programmer Response: Use IPCS to determine the cause for the ABEND, take the corrective action required, perform an LLA,REFRESH, and reload the failing module using the OS/EM ISPF RELOAD facility. Contact OS/EM support for assistance in problem resolution.

FEM02F210

ABEND AREGS 0-1: nnnnnnnnnnnnnnnn nnnnnnnnnnnnnnnn

Explanation: The OS/EM has detected a MVS System Abend during execution of an OS/EM optional function or a User exit. This message applies to z/OS environments operating in 64-bit mode.

nnnnnnnnnnnnnnnnn: Contents of the General Purpose Register.

Source: FEM0002F

System Action: The OS/EM function being executed continues, OS/EM takes a SVC dump for the abending module, takes the abending module out of service, and deletes the abending module from CSA/ECSA. See messages FEMxxx023, FEMxxx026 and FEMxxx029.

Operator Response: Contact System Programmer.

System Programmer Response: Use IPCS to determine the cause for the ABEND, take the corrective action required, perform an LLA,REFRESH, and reload the failing module using the OS/EM ISPF RELOAD facility. Contact OS/EM support for assistance in problem resolution.

FEMIPL210

ABEND AREGS 0-1: nnnnnnnnnnnnnnnn nnnnnnnnnnnnnnnn

Explanation: The OS/EM has detected a MVS System Abend during execution of an OS/EM optional function or a User exit. This message applies to z/OS environments operating in 64-bit mode.

nnnnnnnnnnnnnnnnn: Contents of the General Purpose Register.

Source: FEMIPL1

System Action: The OS/EM function being executed continues, OS/EM takes a SVC dump for the abending module, takes the abending module out of service, and deletes the abending module from CSA/ECSA. See messages FEMxxx023, FEMxxx026 and FEMxxx029.

Operator Response: Contact System Programmer.

System Programmer Response: Use IPCS to determine the cause for the ABEND, take the corrective action required, perform an LLA,REFRESH, and reload the failing module using the OS/EM ISPF RELOAD facility. Contact OS/EM support for assistance in problem resolution.

FEM2H5210

ABEND AREGS 0-1: nnnnnnnnnnnnnnnnnnnn nnnnnnnnnnnnnnnnnnnn

Explanation: The OS/EM has detected a MVS System Abend during execution of an OS/EM optional function or a User exit. This message applies to z/OS environments operating in 64-bit mode.

nnnnnnnnnnnnnnnnnnn: Contents of the General Purpose Register.

Source: FEMJ2H5x

System Action: The OS/EM function being executed continues, OS/EM takes a SVC dump for the abending module, takes the abending module out of service, and deletes the abending module from CSA/ECSA. See messages FEMxxx023, FEMxxx026 and FEMxxx029.

Operator Response: Contact System Programmer.

System Programmer Response: Use IPCS to determine the cause for the ABEND, take the corrective action required, perform an LLA,REFRESH, and reload the failing module using the OS/EM ISPF RELOAD facility. Contact OS/EM support for assistance in problem resolution.

FEM2P4210

ABEND AREGS 0-1: nnnnnnnnnnnnnnnnnnnn nnnnnnnnnnnnnnnnnnnn

Explanation: The OS/EM has detected a MVS System Abend during execution of an OS/EM optional function or a User exit. This message applies to z/OS environments operating in 64-bit mode.

nnnnnnnnnnnnnnnnnnn: Contents of the General Purpose Register.

Source: FEMJ2P4x

System Action: The OS/EM function being executed continues, OS/EM takes a SVC dump for the abending module, takes the abending module out of service, and deletes the abending module from CSA/ECSA. See messages FEMxxx023, FEMxxx026 and FEMxxx029.

Operator Response: Contact System Programmer.

System Programmer Response: Use IPCS to determine the cause for the ABEND, take the corrective action required, perform an LLA,REFRESH, and reload the failing module using the OS/EM ISPF RELOAD facility. Contact OS/EM support for assistance in problem resolution.

FEMACN211

ABEND AREGS 2-3: nnnnnnnnnnnnnnnnnnnn nnnnnnnnnnnnnnnnnnnn

Explanation: The OS/EM has detected a MVS System Abend during execution of an OS/EM optional function or a User exit. This message applies to z/OS environments operating in 64-bit mode.

nnnnnnnnnnnnnnnnnnn: Contents of the General Purpose Register.

Source: FEMALCCN

System Action: The OS/EM function being executed continues, OS/EM takes a SVC dump for the abending module, takes the abending module out of service, and deletes the abending module from CSA/ECSA. See messages FEMxxx023, FEMxxx026 and FEMxxx029.

Operator Response: Contact System Programmer.

System Programmer Response: Use IPCS to determine the cause for the ABEND, take the corrective action required, perform an LLA,REFRESH, and reload the failing module using the OS/EM ISPF RELOAD facility. Contact OS/EM support for assistance in problem resolution.

FEMALC211

ABEND AREGS 2-3: nnnnnnnnnnnnnnnn nnnnnnnnnnnnnnnn

Explanation: The OS/EM has detected a MVS System Abend during execution of an OS/EM optional function or a User exit. This message applies to z/OS environments operating in 64-bit mode.

nnnnnnnnnnnnnnnnn: Contents of the General Purpose Register.

Source: FEMALLO0,FEMALLO1

System Action: The OS/EM function being executed continues, OS/EM takes a SVC dump for the abending module, takes the abending module out of service, and deletes the abending module from CSA/ECSA. See messages FEMxxx023, FEMxxx026 and FEMxxx029.

Operator Response: Contact System Programmer.

System Programmer Response: Use IPCS to determine the cause for the ABEND, take the corrective action required, perform an LLA,REFRESH, and reload the failing module using the OS/EM ISPF RELOAD facility. Contact OS/EM support for assistance in problem resolution.

FEMASY211

ABEND AREGS 2-3: nnnnnnnnnnnnnnnn nnnnnnnnnnnnnnnn

Explanation: The OS/EM has detected a MVS System Abend during execution of an OS/EM optional function or a User exit. This message applies to z/OS environments operating in 64-bit mode.

nnnnnnnnnnnnnnnnn: Contents of the General Purpose Register.

Source: FEMASYNC

System Action: The OS/EM function being executed continues, OS/EM takes a SVC dump for the abending module, takes the abending module out of service, and deletes the abending module from CSA/ECSA. See messages FEMxxx023, FEMxxx026 and FEMxxx029.

Operator Response: Contact System Programmer.

System Programmer Response: Use IPCS to determine the cause for the ABEND, take the corrective action required, perform an LLA,REFRESH, and reload the failing module using the OS/EM ISPF RELOAD facility. Contact OS/EM support for assistance in problem resolution.

FEMCMD211

ABEND AREGS 2-3: nnnnnnnnnnnnnnnn nnnnnnnnnnnnnnnn

Explanation: The OS/EM has detected a MVS System Abend during execution of an OS/EM optional function or a User exit. This message applies to z/OS environments operating in 64-bit mode.

nnnnnnnnnnnnnnnnn: Contents of the General Purpose Register.

Source: FEMCMD

System Action: The OS/EM function being executed continues, OS/EM takes a SVC dump for the abending module, takes the abending module out of service, and deletes the abending module from CSA/ECSA. See messages FEMxxx023, FEMxxx026 and FEMxxx029.

Operator Response: Contact System Programmer.

System Programmer Response: Use IPCS to determine the cause for the ABEND, take the corrective action required, perform an LLA,REFRESH, and reload the failing module using the OS/EM ISPF RELOAD facility. Contact OS/EM support for assistance in problem resolution.

FEMCOM211

ABEND AREGS 2-3: nnnnnnnnnnnnnnnn nnnnnnnnnnnnnnnn

Explanation: The OS/EM has detected a MVS System Abend during execution of an OS/EM optional function or a User exit. This message applies to z/OS environments operating in 64-bit mode.

nnnnnnnnnnnnnnnnn: Contents of the General Purpose Register.

Source: FEMCOMM

System Action: The OS/EM function being executed continues, OS/EM takes a SVC dump for the abending module, takes the abending module out of service, and deletes the abending module from CSA/ECSA. See messages FEMxxx023, FEMxxx026 and FEMxxx029.

Operator Response: Contact System Programmer.

System Programmer Response: Use IPCS to determine the cause for the ABEND, take the corrective action required, perform an LLA,REFRESH, and reload the failing module using the OS/EM ISPF RELOAD facility. Contact OS/EM support for assistance in problem resolution.

FEMDCN211

ABEND AREGS 2-3: nnnnnnnnnnnnnnnn nnnnnnnnnnnnnnnn

Explanation: The OS/EM has detected a MVS System Abend during execution of an OS/EM optional function or a User exit. This message applies to z/OS environments operating in 64-bit mode.

nnnnnnnnnnnnnnnnn: Contents of the General Purpose Register.

Source: FEMDADCN

System Action: The OS/EM function being executed continues, OS/EM takes a SVC dump for the abending module, takes the abending module out of service, and deletes the abending module from CSA/ECSA. See messages FEMxxx023, FEMxxx026 and FEMxxx029.

Operator Response: Contact System Programmer.

System Programmer Response: Use IPCS to determine the cause for the ABEND, take the corrective action required, perform an LLA,REFRESH, and reload the failing module using the OS/EM ISPF RELOAD facility. Contact OS/EM support for assistance in problem resolution.

FEMDC1211

ABEND AREGS 2-3: nnnnnnnnnnnnnnnn nnnnnnnnnnnnnnnn

Explanation: The OS/EM has detected a MVS System Abend during execution of an OS/EM optional function or a User exit. This message applies to z/OS environments operating in 64-bit mode.

nnnnnnnnnnnnnnnnn: Contents of the General Purpose Register.

Source: FEMDCB1

System Action: The OS/EM function being executed continues, OS/EM takes a SVC dump for the abending module, takes the abending module out of service, and deletes the abending module from CSA/ECSA. See messages FEMxxx023, FEMxxx026 and FEMxxx029.

Operator Response: Contact System Programmer.

System Programmer Response: Use IPCS to determine the cause for the ABEND, take the corrective action required, perform an LLA,REFRESH, and reload the failing module using the OS/EM ISPF RELOAD facility. Contact OS/EM support for assistance in problem resolution.

FEMEXR211

ABEND AREGS 2-3: nnnnnnnnnnnnnnnn nnnnnnnnnnnnnnnn

Explanation: The OS/EM has detected a MVS System Abend during execution of an OS/EM optional function or a User exit. This message applies to z/OS environments operating in 64-bit mode.

nnnnnnnnnnnnnnnn: Contents of the General Purpose Register.

Source: FEMEXRTN

System Action: The OS/EM function being executed continues, OS/EM takes a SVC dump for the abending module, takes the abending module out of service, and deletes the abending module from CSA/ECSA. See messages FEMxxx023, FEMxxx026 and FEMxxx029.

Operator Response: Contact System Programmer.

System Programmer Response: Use IPCS to determine the cause for the ABEND, take the corrective action required, perform an LLA,REFRESH, and reload the failing module using the OS/EM ISPF RELOAD facility. Contact OS/EM support for assistance in problem resolution.

FEMFRA211

ABEND AREGS 2-3: nnnnnnnnnnnnnnnn nnnnnnnnnnnnnnnn

Explanation: The OS/EM has detected a MVS System Abend during execution of an OS/EM optional function or a User exit. This message applies to z/OS environments operating in 64-bit mode.

nnnnnnnnnnnnnnnn: Contents of the General Purpose Register.

Source: FEMFRACN

System Action: The OS/EM function being executed continues, OS/EM takes a SVC dump for the abending module, takes the abending module out of service, and deletes the abending module from CSA/ECSA. See messages FEMxxx023, FEMxxx026 and FEMxxx029.

Operator Response: Contact System Programmer.

System Programmer Response: Use IPCS to determine the cause for the ABEND, take the corrective action required, perform an LLA,REFRESH, and reload the failing module using the OS/EM ISPF RELOAD facility. Contact OS/EM support for assistance in problem resolution.

FEMFTN211

ABEND AREGS 2-3: nnnnnnnnnnnnnnnn nnnnnnnnnnnnnnnn

Explanation: The OS/EM has detected a MVS System Abend during execution of an OS/EM optional function or a User exit. This message applies to z/OS environments operating in 64-bit mode.

nnnnnnnnnnnnnnnn: Contents of the General Purpose Register.

Source: FEMFRRTN

System Action: The OS/EM function being executed continues, OS/EM takes a SVC dump for the abending module, takes the abending module out of service, and deletes the abending module from CSA/ECSA. See messages FEMxxx023, FEMxxx026 and FEMxxx029.

Operator Response: Contact System Programmer.

System Programmer Response: Use IPCS to determine the cause for the ABEND, take the corrective action required, perform an LLA,REFRESH, and reload the failing module using the OS/EM ISPF RELOAD facility. Contact OS/EM support for assistance in problem resolution.

FEMJ3E211

ABEND AREGS 2-3: nnnnnnnnnnnnnnnn nnnnnnnnnnnnnnnn

Explanation: The OS/EM has detected a MVS System Abend during execution of an OS/EM optional function or a User exit. This message applies to z/OS environments operating in 64-bit mode.

nnnnnnnnnnnnnnnn: Contents of the General Purpose Register.

Source: FEMJ3ECN

System Action: The OS/EM function being executed continues, OS/EM takes a SVC dump for the abending module, takes the abending module out of service, and deletes the abending module from CSA/ECSA. See messages FEMxxx023, FEMxxx026 and FEMxxx029.

Operator Response: Contact System Programmer.

System Programmer Response: Use IPCS to determine the cause for the ABEND, take the corrective action required, perform an LLA,REFRESH, and reload the failing module using the OS/EM ISPF RELOAD facility. Contact OS/EM support for assistance in problem resolution.

FEMJ3S211

ABEND AREGS 2-3: nnnnnnnnnnnnnnnn nnnnnnnnnnnnnnnn

Explanation: The OS/EM has detected a MVS System Abend during execution of an OS/EM optional function or a User exit. This message applies to z/OS environments operating in 64-bit mode.

nnnnnnnnnnnnnnnn: Contents of the General Purpose Register.

Source: FEMJ3SVC

System Action: The OS/EM function being executed continues, OS/EM takes a SVC dump for the abending module, takes the abending module out of service, and deletes the abending module from CSA/ECSA. See messages FEMxxx023, FEMxxx026 and FEMxxx029.

Operator Response: Contact System Programmer.

System Programmer Response: Use IPCS to determine the cause for the ABEND, take the corrective action required, perform an LLA,REFRESH, and reload the failing module using the OS/EM ISPF RELOAD facility. Contact OS/EM support for assistance in problem resolution.

FEMLOK211

ABEND AREGS 2-3: nnnnnnnnnnnnnnnn nnnnnnnnnnnnnnnn

Explanation: The OS/EM has detected a MVS System Abend during execution of an OS/EM optional function or a User exit. This message applies to z/OS environments operating in 64-bit mode.

nnnnnnnnnnnnnnnn: Contents of the General Purpose Register.

Source: FEMLOCK

System Action: The OS/EM function being executed continues, OS/EM takes a SVC dump for the abending module, takes the abending module out of service, and deletes the abending module from CSA/ECSA. See messages FEMxxx023, FEMxxx026 and FEMxxx029.

Operator Response: Contact System Programmer.

System Programmer Response: Use IPCS to determine the cause for the ABEND, take the corrective action required, perform an LLA,REFRESH, and reload the failing module using the OS/EM ISPF RELOAD facility. Contact OS/EM support for assistance in problem resolution.

FEMRCN211

ABEND AREGS 2-3: nnnnnnnnnnnnnnnnnn nnnnnnnnnnnnnnnnnn

Explanation: The OS/EM has detected a MVS System Abend during execution of an OS/EM optional function or a User exit. This message applies to z/OS environments operating in 64-bit mode.

nnnnnnnnnnnnnnnnn: Contents of the General Purpose Register.

Source: FEMRACCN

System Action: The OS/EM function being executed continues, OS/EM takes a SVC dump for the abending module, takes the abending module out of service, and deletes the abending module from CSA/ECSA. See messages FEMxxx023, FEMxxx026 and FEMxxx029.

Operator Response: Contact System Programmer.

System Programmer Response: Use IPCS to determine the cause for the ABEND, take the corrective action required, perform an LLA,REFRESH, and reload the failing module using the OS/EM ISPF RELOAD facility. Contact OS/EM support for assistance in problem resolution.

FEMSCN211

ABEND AREGS 2-3: nnnnnnnnnnnnnnnnnn nnnnnnnnnnnnnnnnnn

Explanation: The OS/EM has detected a MVS System Abend during execution of an OS/EM optional function or a User exit. This message applies to z/OS environments operating in 64-bit mode.

nnnnnnnnnnnnnnnnn: Contents of the General Purpose Register.

Source: FEMSAFCN,FEMSMFCN

System Action: The OS/EM function being executed continues, OS/EM takes a SVC dump for the abending module, takes the abending module out of service, and deletes the abending module from CSA/ECSA. See messages FEMxxx023, FEMxxx026 and FEMxxx029.

Operator Response: Contact System Programmer.

System Programmer Response: Use IPCS to determine the cause for the ABEND, take the corrective action required, perform an LLA,REFRESH, and reload the failing module using the OS/EM ISPF RELOAD facility. Contact OS/EM support for assistance in problem resolution.

FEMTCN211

ABEND AREGS 2-3: nnnnnnnnnnnnnnnnnn nnnnnnnnnnnnnnnnnn

Explanation: The OS/EM has detected a MVS System Abend during execution of an OS/EM optional function or a User exit. This message applies to z/OS environments operating in 64-bit mode.

nnnnnnnnnnnnnnnnn: Contents of the General Purpose Register.

Source: FEMTSOCN

System Action: The OS/EM function being executed continues, OS/EM takes a SVC dump for the abending module, takes the abending module out of service, and deletes the abending module from CSA/ECSA. See messages FEMxxx023, FEMxxx026 and FEMxxx029.

Operator Response: Contact System Programmer.

System Programmer Response: Use IPCS to determine the cause for the ABEND, take the corrective action required, perform an LLA,REFRESH, and reload the failing module using the OS/EM ISPF RELOAD facility. Contact OS/EM support for assistance in problem resolution.

FEMTPS211

ABEND AREGS 2-3: nnnnnnnnnnnnnnnn nnnnnnnnnnnnnnnn

Explanation: The OS/EM has detected a MVS System Abend during execution of an OS/EM optional function or a User exit. This message applies to z/OS environments operating in 64-bit mode.

nnnnnnnnnnnnnnnn: Contents of the General Purpose Register.

Source: FEMTPSHR

System Action: The OS/EM function being executed continues, OS/EM takes a SVC dump for the abending module, takes the abending module out of service, and deletes the abending module from CSA/ECSA. See messages FEMxxx023, FEMxxx026 and FEMxxx029.

Operator Response: Contact System Programmer.

System Programmer Response: Use IPCS to determine the cause for the ABEND, take the corrective action required, perform an LLA,REFRESH, and reload the failing module using the OS/EM ISPF RELOAD facility. Contact OS/EM support for assistance in problem resolution.

FEMUJI211

ABEND AREGS 2-3: nnnnnnnnnnnnnnnn nnnnnnnnnnnnnnnn

Explanation: The OS/EM has detected a MVS System Abend during execution of an OS/EM optional function or a User exit. This message applies to z/OS environments operating in 64-bit mode.

nnnnnnnnnnnnnnnn: Contents of the General Purpose Register.

Source: FEMUJI

System Action: The OS/EM function being executed continues, OS/EM takes a SVC dump for the abending module, takes the abending module out of service, and deletes the abending module from CSA/ECSA. See messages FEMxxx023, FEMxxx026 and FEMxxx029.

Operator Response: Contact System Programmer.

System Programmer Response: Use IPCS to determine the cause for the ABEND, take the corrective action required, perform an LLA,REFRESH, and reload the failing module using the OS/EM ISPF RELOAD facility. Contact OS/EM support for assistance in problem resolution.

FEMUSI211

ABEND AREGS 2-3: nnnnnnnnnnnnnnnn nnnnnnnnnnnnnnnn

Explanation: The OS/EM has detected a MVS System Abend during execution of an OS/EM optional function or a User exit. This message applies to z/OS environments operating in 64-bit mode.

nnnnnnnnnnnnnnnn: Contents of the General Purpose Register.

Source: FEMUSI

System Action: The OS/EM function being executed continues, OS/EM takes a SVC dump for the abending module, takes the abending module out of service, and deletes the abending module from CSA/ECSA. See messages FEMxxx023, FEMxxx026 and FEMxxx029.

Operator Response: Contact System Programmer.

System Programmer Response: Use IPCS to determine the cause for the ABEND, take the corrective action required, perform an LLA,REFRESH, and reload the failing module using the OS/EM ISPF RELOAD facility. Contact OS/EM support for assistance in problem resolution.

FEM1PL211

ABEND AREGS 2-3: nnnnnnnnnnnnnnnnnn nnnnnnnnnnnnnnnnnn

Explanation: The OS/EM has detected a MVS System Abend during execution of an OS/EM optional function or a User exit. This message applies to z/OS environments operating in 64-bit mode.

nnnnnnnnnnnnnnnnn: Contents of the General Purpose Register.

Source: FEM1PL1

System Action: The OS/EM function being executed continues, OS/EM takes a SVC dump for the abending module, takes the abending module out of service, and deletes the abending module from CSA/ECSA. See messages FEMxxx023, FEMxxx026 and FEMxxx029.

Operator Response: Contact System Programmer.

System Programmer Response: Use IPCS to determine the cause for the ABEND, take the corrective action required, perform an LLA,REFRESH, and reload the failing module using the OS/EM ISPF RELOAD facility. Contact OS/EM support for assistance in problem resolution.

FEM2H5211

ABEND AREGS 2-3: nnnnnnnnnnnnnnnnnn nnnnnnnnnnnnnnnnnn

Explanation: The OS/EM has detected a MVS System Abend during execution of an OS/EM optional function or a User exit. This message applies to z/OS environments operating in 64-bit mode.

nnnnnnnnnnnnnnnnn: Contents of the General Purpose Register.

Source: FEMJ2H5x

System Action: The OS/EM function being executed continues, OS/EM takes a SVC dump for the abending module, takes the abending module out of service, and deletes the abending module from CSA/ECSA. See messages FEMxxx023, FEMxxx026 and FEMxxx029.

Operator Response: Contact System Programmer.

System Programmer Response: Use IPCS to determine the cause for the ABEND, take the corrective action required, perform an LLA,REFRESH, and reload the failing module using the OS/EM ISPF RELOAD facility. Contact OS/EM support for assistance in problem resolution.

FEM2P4211

ABEND AREGS 2-3: nnnnnnnnnnnnnnnnnn nnnnnnnnnnnnnnnnnn

Explanation: The OS/EM has detected a MVS System Abend during execution of an OS/EM optional function or a User exit. This message applies to z/OS environments operating in 64-bit mode.

nnnnnnnnnnnnnnnnn: Contents of the General Purpose Register.

Source: FEMJ2P4x

System Action: The OS/EM function being executed continues, OS/EM takes a SVC dump for the abending module, takes the abending module out of service, and deletes the abending module from CSA/ECSA. See messages FEMxxx023, FEMxxx026 and FEMxxx029.

Operator Response: Contact System Programmer.

System Programmer Response: Use IPCS to determine the cause for the ABEND, take the corrective action required, perform an LLA,REFRESH, and reload the failing module using the OS/EM ISPF RELOAD facility. Contact OS/EM support for assistance in problem resolution.

FEMACN212

ABEND AREGS 4-5: nnnnnnnnnnnnnnnn nnnnnnnnnnnnnnnn

Explanation: The OS/EM has detected a MVS System Abend during execution of an OS/EM optional function or a User exit. This message applies to z/OS environments operating in 64-bit mode.

nnnnnnnnnnnnnnnnn: Contents of the General Purpose Register.

Source: FEMALCCN

System Action: The OS/EM function being executed continues, OS/EM takes a SVC dump for the abending module, takes the abending module out of service, and deletes the abending module from CSA/ECSA. See messages FEMxxx023, FEMxxx026 and FEMxxx029.

Operator Response: Contact System Programmer.

System Programmer Response: Use IPCS to determine the cause for the ABEND, take the corrective action required, perform an LLA,REFRESH, and reload the failing module using the OS/EM ISPF RELOAD facility. Contact OS/EM support for assistance in problem resolution.

FEMALC212

ABEND AREGS 4-5: nnnnnnnnnnnnnnnn nnnnnnnnnnnnnnnn

Explanation: The OS/EM has detected a MVS System Abend during execution of an OS/EM optional function or a User exit. This message applies to z/OS environments operating in 64-bit mode.

nnnnnnnnnnnnnnnnn: Contents of the General Purpose Register.

Source: FEMALLO0,FEMALLO1

System Action: The OS/EM function being executed continues, OS/EM takes a SVC dump for the abending module, takes the abending module out of service, and deletes the abending module from CSA/ECSA. See messages FEMxxx023, FEMxxx026 and FEMxxx029.

Operator Response: Contact System Programmer.

System Programmer Response: Use IPCS to determine the cause for the ABEND, take the corrective action required, perform an LLA,REFRESH, and reload the failing module using the OS/EM ISPF RELOAD facility. Contact OS/EM support for assistance in problem resolution.

FEMASY212

ABEND AREGS 4-5: nnnnnnnnnnnnnnnn nnnnnnnnnnnnnnnn

Explanation: The OS/EM has detected a MVS System Abend during execution of an OS/EM optional function or a User exit. This message applies to z/OS environments operating in 64-bit mode.

nnnnnnnnnnnnnnnnn: Contents of the General Purpose Register.

Source: FEMASYNC

System Action: The OS/EM function being executed continues, OS/EM takes a SVC dump for the abending module, takes the abending module out of service, and deletes the abending module from CSA/ECSA. See messages FEMxxx023, FEMxxx026 and FEMxxx029.

Operator Response: Contact System Programmer.

System Programmer Response: Use IPCS to determine the cause for the ABEND, take the corrective action required, perform an LLA,REFRESH, and reload the failing module using the OS/EM ISPF RELOAD facility. Contact OS/EM support for assistance in problem resolution.

FEMDC1212

ABEND AREGS 4-5: nnnnnnnnnnnnnnnn nnnnnnnnnnnnnnnn

Explanation: The OS/EM has detected a MVS System Abend during execution of an OS/EM optional function or a User exit. This message applies to z/OS environments operating in 64-bit mode.

nnnnnnnnnnnnnnnn: Contents of the General Purpose Register.

Source: FEMDCB1

System Action: The OS/EM function being executed continues, OS/EM takes a SVC dump for the abending module, takes the abending module out of service, and deletes the abending module from CSA/ECSA. See messages FEMxxx023, FEMxxx026 and FEMxxx029.

Operator Response: Contact System Programmer.

System Programmer Response: Use IPCS to determine the cause for the ABEND, take the corrective action required, perform an LLA,REFRESH, and reload the failing module using the OS/EM ISPF RELOAD facility. Contact OS/EM support for assistance in problem resolution.

FEMEXR212

ABEND AREGS 4-5: nnnnnnnnnnnnnnnn nnnnnnnnnnnnnnnn

Explanation: The OS/EM has detected a MVS System Abend during execution of an OS/EM optional function or a User exit. This message applies to z/OS environments operating in 64-bit mode.

nnnnnnnnnnnnnnnn: Contents of the General Purpose Register.

Source: FEMEXRTN

System Action: The OS/EM function being executed continues, OS/EM takes a SVC dump for the abending module, takes the abending module out of service, and deletes the abending module from CSA/ECSA. See messages FEMxxx023, FEMxxx026 and FEMxxx029.

Operator Response: Contact System Programmer.

System Programmer Response: Use IPCS to determine the cause for the ABEND, take the corrective action required, perform an LLA,REFRESH, and reload the failing module using the OS/EM ISPF RELOAD facility. Contact OS/EM support for assistance in problem resolution.

FEMFRA212

ABEND AREGS 4-5: nnnnnnnnnnnnnnnn nnnnnnnnnnnnnnnn

Explanation: The OS/EM has detected a MVS System Abend during execution of an OS/EM optional function or a User exit. This message applies to z/OS environments operating in 64-bit mode.

nnnnnnnnnnnnnnnn: Contents of the General Purpose Register.

Source: FEMFRACN

System Action: The OS/EM function being executed continues, OS/EM takes a SVC dump for the abending module, takes the abending module out of service, and deletes the abending module from CSA/ECSA. See messages FEMxxx023, FEMxxx026 and FEMxxx029.

Operator Response: Contact System Programmer.

System Programmer Response: Use IPCS to determine the cause for the ABEND, take the corrective action required, perform an LLA,REFRESH, and reload the failing module using the OS/EM ISPF RELOAD facility. Contact OS/EM support for assistance in problem resolution.

FEMFTN212

ABEND AREGS 4-5: nnnnnnnnnnnnnnnn nnnnnnnnnnnnnnnn

Explanation: The OS/EM has detected a MVS System Abend during execution of an OS/EM optional function or a User exit. This message applies to z/OS environments operating in 64-bit mode.

nnnnnnnnnnnnnnnn: Contents of the General Purpose Register.

Source: FEMFRRTN

System Action: The OS/EM function being executed continues, OS/EM takes a SVC dump for the abending module, takes the abending module out of service, and deletes the abending module from CSA/ECSA. See messages FEMxxx023, FEMxxx026 and FEMxxx029.

Operator Response: Contact System Programmer.

System Programmer Response: Use IPCS to determine the cause for the ABEND, take the corrective action required, perform an LLA,REFRESH, and reload the failing module using the OS/EM ISPF RELOAD facility. Contact OS/EM support for assistance in problem resolution.

FEMHCN212

ABEND AREGS 4-5: nnnnnnnnnnnnnnnn nnnnnnnnnnnnnnnn

Explanation: The OS/EM has detected a MVS System Abend during execution of an OS/EM optional function or a User exit. This message applies to z/OS environments operating in 64-bit mode.

nnnnnnnnnnnnnnnn: Contents of the General Purpose Register.

Source: FEMHSMCN

System Action: The OS/EM function being executed continues, OS/EM takes a SVC dump for the abending module, takes the abending module out of service, and deletes the abending module from CSA/ECSA. See messages FEMxxx023, FEMxxx026 and FEMxxx029.

Operator Response: Contact System Programmer.

System Programmer Response: Use IPCS to determine the cause for the ABEND, take the corrective action required, perform an LLA,REFRESH, and reload the failing module using the OS/EM ISPF RELOAD facility. Contact OS/EM support for assistance in problem resolution.

FEMHSP212

ABEND AREGS 4-5: nnnnnnnnnnnnnnnn nnnnnnnnnnnnnnnn

Explanation: The OS/EM has detected a MVS System Abend during execution of an OS/EM optional function or a User exit. This message applies to z/OS environments operating in 64-bit mode.

nnnnnnnnnnnnnnnn: Contents of the General Purpose Register.

Source: FEMHJ20

System Action: The OS/EM function being executed continues, OS/EM takes a SVC dump for the abending module, takes the abending module out of service, and deletes the abending module from CSA/ECSA. See messages FEMxxx023, FEMxxx026 and FEMxxx029.

Operator Response: Contact System Programmer.

System Programmer Response: Use IPCS to determine the cause for the ABEND, take the corrective action required, perform an LLA,REFRESH, and reload the failing module using the OS/EM ISPF RELOAD facility. Contact OS/EM support for assistance in problem resolution.

FEMIAT212

ABEND AREGS 4-5: nnnnnnnnnnnnnnnn nnnnnnnnnnnnnnnn

Explanation: The OS/EM has detected a MVS System Abend during execution of an OS/EM optional function or a User exit. This message applies to z/OS environments operating in 64-bit mode.

nnnnnnnnnnnnnnnn: Contents of the General Purpose Register.

Source: FEMINTK

System Action: The OS/EM function being executed continues, OS/EM takes a SVC dump for the abending module, takes the abending module out of service, and deletes the abending module from CSA/ECSA. See messages FEMxxx023, FEMxxx026 and FEMxxx029.

Operator Response: Contact System Programmer.

System Programmer Response: Use IPCS to determine the cause for the ABEND, take the corrective action required, perform an LLA,REFRESH, and reload the failing module using the OS/EM ISPF RELOAD facility. Contact OS/EM support for assistance in problem resolution.

FEMICN212

ABEND AREGS 4-5: nnnnnnnnnnnnnnnn nnnnnnnnnnnnnnnn

Explanation: The OS/EM has detected a MVS System Abend during execution of an OS/EM optional function or a User exit. This message applies to z/OS environments operating in 64-bit mode.

nnnnnnnnnnnnnnnn: Contents of the General Purpose Register.

Source: FEMISPCN

System Action: The OS/EM function being executed continues, OS/EM takes a SVC dump for the abending module, takes the abending module out of service, and deletes the abending module from CSA/ECSA. See messages FEMxxx023, FEMxxx026 and FEMxxx029.

Operator Response: Contact System Programmer.

System Programmer Response: Use IPCS to determine the cause for the ABEND, take the corrective action required, perform an LLA,REFRESH, and reload the failing module using the OS/EM ISPF RELOAD facility. Contact OS/EM support for assistance in problem resolution.

FEMIPL212

ABEND AREGS 4-5: nnnnnnnnnnnnnnnn nnnnnnnnnnnnnnnn

Explanation: The OS/EM has detected a MVS System Abend during execution of an OS/EM optional function or a User exit. This message applies to z/OS environments operating in 64-bit mode.

nnnnnnnnnnnnnnnn: Contents of the General Purpose Register.

Source: FEMIPL

System Action: The OS/EM function being executed continues, OS/EM takes a SVC dump for the abending module, takes the abending module out of service, and deletes the abending module from CSA/ECSA. See messages FEMxxx023, FEMxxx026 and FEMxxx029.

Operator Response: Contact System Programmer.

System Programmer Response: Use IPCS to determine the cause for the ABEND, take the corrective action required, perform an LLA,REFRESH, and reload the failing module using the OS/EM ISPF RELOAD facility. Contact OS/EM support for assistance in problem resolution.

FEMJS2212

ABEND AREGS 4-5: nnnnnnnnnnnnnnnnnn nnnnnnnnnnnnnnnnnn

Explanation: The OS/EM has detected a MVS System Abend during execution of an OS/EM optional function or a User exit. This message applies to z/OS environments operating in 64-bit mode.

nnnnnnnnnnnnnnnnn: Contents of the General Purpose Register.

Source: FEMJES2B,FEMJES2G

System Action: The OS/EM function being executed continues, OS/EM takes a SVC dump for the abending module, takes the abending module out of service, and deletes the abending module from CSA/ECSA. See messages FEMxxx023, FEMxxx026 and FEMxxx029.

Operator Response: Contact System Programmer.

System Programmer Response: Use IPCS to determine the cause for the ABEND, take the corrective action required, perform an LLA,REFRESH, and reload the failing module using the OS/EM ISPF RELOAD facility. Contact OS/EM support for assistance in problem resolution.

FEMJ2M212

ABEND AREGS 4-5: nnnnnnnnnnnnnnnnnn nnnnnnnnnnnnnnnnnn

Explanation: The OS/EM has detected a MVS System Abend during execution of an OS/EM optional function or a User exit. This message applies to z/OS environments operating in 64-bit mode.

nnnnnnnnnnnnnnnnn: Contents of the General Purpose Register.

Source: FEMJ2MCx

System Action: The OS/EM function being executed continues, OS/EM takes a SVC dump for the abending module, takes the abending module out of service, and deletes the abending module from CSA/ECSA. See messages FEMxxx023, FEMxxx026 and FEMxxx029.

Operator Response: Contact System Programmer.

System Programmer Response: Use IPCS to determine the cause for the ABEND, take the corrective action required, perform an LLA,REFRESH, and reload the failing module using the OS/EM ISPF RELOAD facility. Contact OS/EM support for assistance in problem resolution.

FEMJ2R212

ABEND AREGS 4-5: nnnnnnnnnnnnnnnnnn nnnnnnnnnnnnnnnnnn

Explanation: The OS/EM has detected a MVS System Abend during execution of an OS/EM optional function or a User exit. This message applies to z/OS environments operating in 64-bit mode.

nnnnnnnnnnnnnnnnn: Contents of the General Purpose Register.

Source: FEMJ2ERx

System Action: The OS/EM function being executed continues, OS/EM takes a SVC dump for the abending module, takes the abending module out of service, and deletes the abending module from CSA/ECSA. See messages FEMxxx023, FEMxxx026 and FEMxxx029.

Operator Response: Contact System Programmer.

System Programmer Response: Use IPCS to determine the cause for the ABEND, take the corrective action required, perform an LLA,REFRESH, and reload the failing module using the OS/EM ISPF RELOAD facility. Contact OS/EM support for assistance in problem resolution.

FEMJ2S212

ABEND AREGS 4-5: nnnnnnnnnnnnnnnnnnnn nnnnnnnnnnnnnnnnnnn

Explanation: The OS/EM has detected a MVS System Abend during execution of an OS/EM optional function or a User exit. This message applies to z/OS environments operating in 64-bit mode.

nnnnnnnnnnnnnnnnnn: Contents of the General Purpose Register.

Source: FEMJ2SCx

System Action: The OS/EM function being executed continues, OS/EM takes a SVC dump for the abending module, takes the abending module out of service, and deletes the abending module from CSA/ECSA. See messages FEMxxx023, FEMxxx026 and FEMxxx029.

Operator Response: Contact System Programmer.

System Programmer Response: Use IPCS to determine the cause for the ABEND, take the corrective action required, perform an LLA,REFRESH, and reload the failing module using the OS/EM ISPF RELOAD facility. Contact OS/EM support for assistance in problem resolution.

FEMJ3E212

ABEND AREGS 4-5: nnnnnnnnnnnnnnnnnnnn nnnnnnnnnnnnnnnnnnn

Explanation: The OS/EM has detected a MVS System Abend during execution of an OS/EM optional function or a User exit. This message applies to z/OS environments operating in 64-bit mode.

nnnnnnnnnnnnnnnnnn: Contents of the General Purpose Register.

Source: FEMJ3ECN

System Action: The OS/EM function being executed continues, OS/EM takes a SVC dump for the abending module, takes the abending module out of service, and deletes the abending module from CSA/ECSA. See messages FEMxxx023, FEMxxx026 and FEMxxx029.

Operator Response: Contact System Programmer.

System Programmer Response: Use IPCS to determine the cause for the ABEND, take the corrective action required, perform an LLA,REFRESH, and reload the failing module using the OS/EM ISPF RELOAD facility. Contact OS/EM support for assistance in problem resolution.

FEMJ3S212

ABEND AREGS 4-5: nnnnnnnnnnnnnnnnnnnn nnnnnnnnnnnnnnnnnnn

Explanation: The OS/EM has detected a MVS System Abend during execution of an OS/EM optional function or a User exit. This message applies to z/OS environments operating in 64-bit mode.

nnnnnnnnnnnnnnnnnn: Contents of the General Purpose Register.

Source: FEMJ3SVC

System Action: The OS/EM function being executed continues, OS/EM takes a SVC dump for the abending module, takes the abending module out of service, and deletes the abending module from CSA/ECSA. See messages FEMxxx023, FEMxxx026 and FEMxxx029.

Operator Response: Contact System Programmer.

System Programmer Response: Use IPCS to determine the cause for the ABEND, take the corrective action required, perform an LLA,REFRESH, and reload the failing module using the OS/EM ISPF RELOAD facility. Contact OS/EM support for assistance in problem resolution.

FEMLOK212

ABEND AREGS 4-5: nnnnnnnnnnnnnnnn nnnnnnnnnnnnnnnn

Explanation: The OS/EM has detected a MVS System Abend during execution of an OS/EM optional function or a User exit. This message applies to z/OS environments operating in 64-bit mode.

nnnnnnnnnnnnnnnn: Contents of the General Purpose Register.

Source: FEMLOCK

System Action: The OS/EM function being executed continues, OS/EM takes a SVC dump for the abending module, takes the abending module out of service, and deletes the abending module from CSA/ECSA. See messages FEMxxx023, FEMxxx026 and FEMxxx029.

Operator Response: Contact System Programmer.

System Programmer Response: Use IPCS to determine the cause for the ABEND, take the corrective action required, perform an LLA,REFRESH, and reload the failing module using the OS/EM ISPF RELOAD facility. Contact OS/EM support for assistance in problem resolution.

FEMRCN212

ABEND AREGS 4-5: nnnnnnnnnnnnnnnn nnnnnnnnnnnnnnnn

Explanation: The OS/EM has detected a MVS System Abend during execution of an OS/EM optional function or a User exit. This message applies to z/OS environments operating in 64-bit mode.

nnnnnnnnnnnnnnnn: Contents of the General Purpose Register.

Source: FEMRACCN

System Action: The OS/EM function being executed continues, OS/EM takes a SVC dump for the abending module, takes the abending module out of service, and deletes the abending module from CSA/ECSA. See messages FEMxxx023, FEMxxx026 and FEMxxx029.

Operator Response: Contact System Programmer.

System Programmer Response: Use IPCS to determine the cause for the ABEND, take the corrective action required, perform an LLA,REFRESH, and reload the failing module using the OS/EM ISPF RELOAD facility. Contact OS/EM support for assistance in problem resolution.

FEMSCN212

ABEND AREGS 4-5: nnnnnnnnnnnnnnnn nnnnnnnnnnnnnnnn

Explanation: The OS/EM has detected a MVS System Abend during execution of an OS/EM optional function or a User exit. This message applies to z/OS environments operating in 64-bit mode.

nnnnnnnnnnnnnnnn: Contents of the General Purpose Register.

Source: FEMSAFCN,FEMSMFCN

System Action: The OS/EM function being executed continues, OS/EM takes a SVC dump for the abending module, takes the abending module out of service, and deletes the abending module from CSA/ECSA. See messages FEMxxx023, FEMxxx026 and FEMxxx029.

Operator Response: Contact System Programmer.

System Programmer Response: Use IPCS to determine the cause for the ABEND, take the corrective action required, perform an LLA,REFRESH, and reload the failing module using the OS/EM ISPF RELOAD facility. Contact OS/EM support for assistance in problem resolution.

FEMTCN212

ABEND AREGS 4-5: nnnnnnnnnnnnnnnn nnnnnnnnnnnnnnnn

Explanation: The OS/EM has detected a MVS System Abend during execution of an OS/EM optional function or a User exit. This message applies to z/OS environments operating in 64-bit mode.

nnnnnnnnnnnnnnnn: Contents of the General Purpose Register.

Source: FEMTSOCN

System Action: The OS/EM function being executed continues, OS/EM takes a SVC dump for the abending module, takes the abending module out of service, and deletes the abending module from CSA/ECSA. See messages FEMxxx023, FEMxxx026 and FEMxxx029.

Operator Response: Contact System Programmer.

System Programmer Response: Use IPCS to determine the cause for the ABEND, take the corrective action required, perform an LLA,REFRESH, and reload the failing module using the OS/EM ISPF RELOAD facility. Contact OS/EM support for assistance in problem resolution.

FEMTPS212

ABEND AREGS 4-5: nnnnnnnnnnnnnnnn nnnnnnnnnnnnnnnn

Explanation: The OS/EM has detected a MVS System Abend during execution of an OS/EM optional function or a User exit. This message applies to z/OS environments operating in 64-bit mode.

nnnnnnnnnnnnnnnn: Contents of the General Purpose Register.

Source: FEMTPSHR

System Action: The OS/EM function being executed continues, OS/EM takes a SVC dump for the abending module, takes the abending module out of service, and deletes the abending module from CSA/ECSA. See messages FEMxxx023, FEMxxx026 and FEMxxx029.

Operator Response: Contact System Programmer.

System Programmer Response: Use IPCS to determine the cause for the ABEND, take the corrective action required, perform an LLA,REFRESH, and reload the failing module using the OS/EM ISPF RELOAD facility. Contact OS/EM support for assistance in problem resolution.

FEMUJI212

ABEND AREGS 4-5: nnnnnnnnnnnnnnnn nnnnnnnnnnnnnnnn

Explanation: The OS/EM has detected a MVS System Abend during execution of an OS/EM optional function or a User exit. This message applies to z/OS environments operating in 64-bit mode.

nnnnnnnnnnnnnnnn: Contents of the General Purpose Register.

Source: FEMUJI

System Action: The OS/EM function being executed continues, OS/EM takes a SVC dump for the abending module, takes the abending module out of service, and deletes the abending module from CSA/ECSA. See messages FEMxxx023, FEMxxx026 and FEMxxx029.

Operator Response: Contact System Programmer.

System Programmer Response: Use IPCS to determine the cause for the ABEND, take the corrective action required, perform an LLA,REFRESH, and reload the failing module using the OS/EM ISPF RELOAD facility. Contact OS/EM support for assistance in problem resolution.

FEMUSI212

ABEND AREGS 4-5: nnnnnnnnnnnnnnnnnn nnnnnnnnnnnnnnnnnn

Explanation: The OS/EM has detected a MVS System Abend during execution of an OS/EM optional function or a User exit. This message applies to z/OS environments operating in 64-bit mode.

nnnnnnnnnnnnnnnnnn: Contents of the General Purpose Register.

Source: FEMUSI

System Action: The OS/EM function being executed continues, OS/EM takes a SVC dump for the abending module, takes the abending module out of service, and deletes the abending module from CSA/ECSA. See messages FEMxxx023, FEMxxx026 and FEMxxx029.

Operator Response: Contact System Programmer.

System Programmer Response: Use IPCS to determine the cause for the ABEND, take the corrective action required, perform an LLA,REFRESH, and reload the failing module using the OS/EM ISPF RELOAD facility. Contact OS/EM support for assistance in problem resolution.

FEMVCN212

ABEND AREGS 4-5: nnnnnnnnnnnnnnnnnn nnnnnnnnnnnnnnnnnn

Explanation: The OS/EM has detected a MVS System Abend during execution of an OS/EM optional function or a User exit. This message applies to z/OS environments operating in 64-bit mode.

nnnnnnnnnnnnnnnnnn: Contents of the General Purpose Register.

Source: FEMSVCCN

System Action: The OS/EM function being executed continues, OS/EM takes a SVC dump for the abending module, takes the abending module out of service, and deletes the abending module from CSA/ECSA. See messages FEMxxx023, FEMxxx026 and FEMxxx029.

Operator Response: Contact System Programmer.

System Programmer Response: Use IPCS to determine the cause for the ABEND, take the corrective action required, perform an LLA,REFRESH, and reload the failing module using the OS/EM ISPF RELOAD facility. Contact OS/EM support for assistance in problem resolution.

FEMX05212

ABEND AREGS 4-5: nnnnnnnnnnnnnnnnnn nnnnnnnnnnnnnnnnnn

Explanation: The OS/EM has detected a MVS System Abend during execution of an OS/EM optional function or a User exit. This message applies to z/OS environments operating in 64-bit mode.

nnnnnnnnnnnnnnnnnn: Contents of the General Purpose Register.

Source: FEMJ2X05

System Action: The OS/EM function being executed continues, OS/EM takes a SVC dump for the abending module, takes the abending module out of service, and deletes the abending module from CSA/ECSA. See messages FEMxxx023, FEMxxx026 and FEMxxx029.

Operator Response: Contact System Programmer.

System Programmer Response: Use IPCS to determine the cause for the ABEND, take the corrective action required, perform an LLA,REFRESH, and reload the failing module using the OS/EM ISPF RELOAD facility. Contact OS/EM support for assistance in problem resolution.

FEM02F212

ABEND AREGS 4-5: nnnnnnnnnnnnnnnn nnnnnnnnnnnnnnnn

Explanation: The OS/EM has detected a MVS System Abend during execution of an OS/EM optional function or a User exit. This message applies to z/OS environments operating in 64-bit mode.

nnnnnnnnnnnnnnnn: Contents of the General Purpose Register.

Source: FEM0002F

System Action: The OS/EM function being executed continues, OS/EM takes a SVC dump for the abending module, takes the abending module out of service, and deletes the abending module from CSA/ECSA. See messages FEMxxx023, FEMxxx026 and FEMxxx029.

Operator Response: Contact System Programmer.

System Programmer Response: Use IPCS to determine the cause for the ABEND, take the corrective action required, perform an LLA,REFRESH, and reload the failing module using the OS/EM ISPF RELOAD facility. Contact OS/EM support for assistance in problem resolution.

FEM1PL212

ABEND AREGS 4-5: nnnnnnnnnnnnnnnn nnnnnnnnnnnnnnnn

Explanation: The OS/EM has detected a MVS System Abend during execution of an OS/EM optional function or a User exit. This message applies to z/OS environments operating in 64-bit mode.

nnnnnnnnnnnnnnnn: Contents of the General Purpose Register.

Source: FEM1PL1

System Action: The OS/EM function being executed continues, OS/EM takes a SVC dump for the abending module, takes the abending module out of service, and deletes the abending module from CSA/ECSA. See messages FEMxxx023, FEMxxx026 and FEMxxx029.

Operator Response: Contact System Programmer.

System Programmer Response: Use IPCS to determine the cause for the ABEND, take the corrective action required, perform an LLA,REFRESH, and reload the failing module using the OS/EM ISPF RELOAD facility. Contact OS/EM support for assistance in problem resolution.

FEM2H5212

ABEND AREGS 4-5: nnnnnnnnnnnnnnnn nnnnnnnnnnnnnnnn

Explanation: The OS/EM has detected a MVS System Abend during execution of an OS/EM optional function or a User exit. This message applies to z/OS environments operating in 64-bit mode.

nnnnnnnnnnnnnnnn: Contents of the General Purpose Register.

Source: FEMJ2H5x

System Action: The OS/EM function being executed continues, OS/EM takes a SVC dump for the abending module, takes the abending module out of service, and deletes the abending module from CSA/ECSA. See messages FEMxxx023, FEMxxx026 and FEMxxx029.

Operator Response: Contact System Programmer.

System Programmer Response: Use IPCS to determine the cause for the ABEND, take the corrective action required, perform an LLA,REFRESH, and reload the failing module using the OS/EM ISPF RELOAD facility. Contact OS/EM support for assistance in problem resolution.

FEM2P4212

ABEND AREGS 4-5: nnnnnnnnnnnnnnnn nnnnnnnnnnnnnnnn

Explanation: The OS/EM has detected a MVS System Abend during execution of an OS/EM optional function or a User exit. This message applies to z/OS environments operating in 64-bit mode.

nnnnnnnnnnnnnnnn: Contents of the General Purpose Register.

Source: FEMJ2P4x

System Action: The OS/EM function being executed continues, OS/EM takes a SVC dump for the abending module, takes the abending module out of service, and deletes the abending module from CSA/ECSA. See messages FEMxxx023, FEMxxx026 and FEMxxx029.

Operator Response: Contact System Programmer.

System Programmer Response: Use IPCS to determine the cause for the ABEND, take the corrective action required, perform an LLA,REFRESH, and reload the failing module using the OS/EM ISPF RELOAD facility. Contact OS/EM support for assistance in problem resolution.

FEMACN213

ABEND AREGS 6-7: nnnnnnnnnnnnnnnn nnnnnnnnnnnnnnnn

Explanation: The OS/EM has detected a MVS System Abend during execution of an OS/EM optional function or a User exit. This message applies to z/OS environments operating in 64-bit mode.

nnnnnnnnnnnnnnnn: Contents of the General Purpose Register.

Source: FEMALCCN

System Action: The OS/EM function being executed continues, OS/EM takes a SVC dump for the abending module, takes the abending module out of service, and deletes the abending module from CSA/ECSA. See messages FEMxxx023, FEMxxx026 and FEMxxx029.

Operator Response: Contact System Programmer.

System Programmer Response: Use IPCS to determine the cause for the ABEND, take the corrective action required, perform an LLA,REFRESH, and reload the failing module using the OS/EM ISPF RELOAD facility. Contact OS/EM support for assistance in problem resolution.

FEMALC213

ABEND AREGS 6-7: nnnnnnnnnnnnnnnn nnnnnnnnnnnnnnnn

Explanation: The OS/EM has detected a MVS System Abend during execution of an OS/EM optional function or a User exit. This message applies to z/OS environments operating in 64-bit mode.

nnnnnnnnnnnnnnnn: Contents of the General Purpose Register.

Source: FEMALLO0,FEMALLO1

System Action: The OS/EM function being executed continues, OS/EM takes a SVC dump for the abending module, takes the abending module out of service, and deletes the abending module from CSA/ECSA. See messages FEMxxx023, FEMxxx026 and FEMxxx029.

Operator Response: Contact System Programmer.

System Programmer Response: Use IPCS to determine the cause for the ABEND, take the corrective action required, perform an LLA,REFRESH, and reload the failing module using the OS/EM ISPF RELOAD facility. Contact OS/EM support for assistance in problem resolution.

FEMFRA213

ABEND AREGS 6-7: nnnnnnnnnnnnnnnn nnnnnnnnnnnnnnnn

Explanation: The OS/EM has detected a MVS System Abend during execution of an OS/EM optional function or a User exit. This message applies to z/OS environments operating in 64-bit mode.

nnnnnnnnnnnnnnnn: Contents of the General Purpose Register.

Source: FEMFRACN

System Action: The OS/EM function being executed continues, OS/EM takes a SVC dump for the abending module, takes the abending module out of service, and deletes the abending module from CSA/ECSA. See messages FEMxxx023, FEMxxx026 and FEMxxx029.

Operator Response: Contact System Programmer.

System Programmer Response: Use IPCS to determine the cause for the ABEND, take the corrective action required, perform an LLA,REFRESH, and reload the failing module using the OS/EM ISPF RELOAD facility. Contact OS/EM support for assistance in problem resolution.

FEMFTN213

ABEND AREGS 6-7: nnnnnnnnnnnnnnnn nnnnnnnnnnnnnnnn

Explanation: The OS/EM has detected a MVS System Abend during execution of an OS/EM optional function or a User exit. This message applies to z/OS environments operating in 64-bit mode.

nnnnnnnnnnnnnnnn: Contents of the General Purpose Register.

Source: FEMFRRTN

System Action: The OS/EM function being executed continues, OS/EM takes a SVC dump for the abending module, takes the abending module out of service, and deletes the abending module from CSA/ECSA. See messages FEMxxx023, FEMxxx026 and FEMxxx029.

Operator Response: Contact System Programmer.

System Programmer Response: Use IPCS to determine the cause for the ABEND, take the corrective action required, perform an LLA,REFRESH, and reload the failing module using the OS/EM ISPF RELOAD facility. Contact OS/EM support for assistance in problem resolution.

FEMHCN213

ABEND AREGS 6-7: nnnnnnnnnnnnnnnn nnnnnnnnnnnnnnnn

Explanation: The OS/EM has detected a MVS System Abend during execution of an OS/EM optional function or a User exit. This message applies to z/OS environments operating in 64-bit mode.

nnnnnnnnnnnnnnnn: Contents of the General Purpose Register.

Source: FEMHSMCN

System Action: The OS/EM function being executed continues, OS/EM takes a SVC dump for the abending module, takes the abending module out of service, and deletes the abending module from CSA/ECSA. See messages FEMxxx023, FEMxxx026 and FEMxxx029.

Operator Response: Contact System Programmer.

System Programmer Response: Use IPCS to determine the cause for the ABEND, take the corrective action required, perform an LLA,REFRESH, and reload the failing module using the OS/EM ISPF RELOAD facility. Contact OS/EM support for assistance in problem resolution.

FEMHSP213

ABEND AREGS 6-7: nnnnnnnnnnnnnnnnnnn nnnnnnnnnnnnnnnnnnn

Explanation: The OS/EM has detected a MVS System Abend during execution of an OS/EM optional function or a User exit. This message applies to z/OS environments operating in 64-bit mode.

nnnnnnnnnnnnnnnnnn: Contents of the General Purpose Register.

Source: FEMHJ20

System Action: The OS/EM function being executed continues, OS/EM takes a SVC dump for the abending module, takes the abending module out of service, and deletes the abending module from CSA/ECSA. See messages FEMxxx023, FEMxxx026 and FEMxxx029.

Operator Response: Contact System Programmer.

System Programmer Response: Use IPCS to determine the cause for the ABEND, take the corrective action required, perform an LLA,REFRESH, and reload the failing module using the OS/EM ISPF RELOAD facility. Contact OS/EM support for assistance in problem resolution.

FEMMAT213

ABEND AREGS 6-7: nnnnnnnnnnnnnnnnnnn nnnnnnnnnnnnnnnnnnn

Explanation: The OS/EM has detected a MVS System Abend during execution of an OS/EM optional function or a User exit. This message applies to z/OS environments operating in 64-bit mode.

nnnnnnnnnnnnnnnnnn: Contents of the General Purpose Register.

Source: FEMINTK

System Action: The OS/EM function being executed continues, OS/EM takes a SVC dump for the abending module, takes the abending module out of service, and deletes the abending module from CSA/ECSA. See messages FEMxxx023, FEMxxx026 and FEMxxx029.

Operator Response: Contact System Programmer.

System Programmer Response: Use IPCS to determine the cause for the ABEND, take the corrective action required, perform an LLA,REFRESH, and reload the failing module using the OS/EM ISPF RELOAD facility. Contact OS/EM support for assistance in problem resolution.

FEMICN213

ABEND AREGS 6-7: nnnnnnnnnnnnnnnnnnn nnnnnnnnnnnnnnnnnnn

Explanation: The OS/EM has detected a MVS System Abend during execution of an OS/EM optional function or a User exit. This message applies to z/OS environments operating in 64-bit mode.

nnnnnnnnnnnnnnnnnn: Contents of the General Purpose Register.

Source: FEMISPCN

System Action: The OS/EM function being executed continues, OS/EM takes a SVC dump for the abending module, takes the abending module out of service, and deletes the abending module from CSA/ECSA. See messages FEMxxx023, FEMxxx026 and FEMxxx029.

Operator Response: Contact System Programmer.

System Programmer Response: Use IPCS to determine the cause for the ABEND, take the corrective action required, perform an LLA,REFRESH, and reload the failing module using the OS/EM ISPF RELOAD facility. Contact OS/EM support for assistance in problem resolution.

FEMIPL213

ABEND AREGS 6-7: nnnnnnnnnnnnnnnn nnnnnnnnnnnnnnnn

Explanation: The OS/EM has detected a MVS System Abend during execution of an OS/EM optional function or a User exit. This message applies to z/OS environments operating in 64-bit mode.

nnnnnnnnnnnnnnnn: Contents of the General Purpose Register.

Source: FEMIPL

System Action: The OS/EM function being executed continues, OS/EM takes a SVC dump for the abending module, takes the abending module out of service, and deletes the abending module from CSA/ECSA. See messages FEMxxx023, FEMxxx026 and FEMxxx029.

Operator Response: Contact System Programmer.

System Programmer Response: Use IPCS to determine the cause for the ABEND, take the corrective action required, perform an LLA,REFRESH, and reload the failing module using the OS/EM ISPF RELOAD facility. Contact OS/EM support for assistance in problem resolution.

FEMJS2213

ABEND AREGS 6-7: nnnnnnnnnnnnnnnn nnnnnnnnnnnnnnnn

Explanation: The OS/EM has detected a MVS System Abend during execution of an OS/EM optional function or a User exit. This message applies to z/OS environments operating in 64-bit mode.

nnnnnnnnnnnnnnnn: Contents of the General Purpose Register.

Source: FEMJES2B,FEMJES2G

System Action: The OS/EM function being executed continues, OS/EM takes a SVC dump for the abending module, takes the abending module out of service, and deletes the abending module from CSA/ECSA. See messages FEMxxx023, FEMxxx026 and FEMxxx029.

Operator Response: Contact System Programmer.

System Programmer Response: Use IPCS to determine the cause for the ABEND, take the corrective action required, perform an LLA,REFRESH, and reload the failing module using the OS/EM ISPF RELOAD facility. Contact OS/EM support for assistance in problem resolution.

FEMJ2M213

ABEND AREGS 6-7: nnnnnnnnnnnnnnnn nnnnnnnnnnnnnnnn

Explanation: The OS/EM has detected a MVS System Abend during execution of an OS/EM optional function or a User exit. This message applies to z/OS environments operating in 64-bit mode.

nnnnnnnnnnnnnnnn: Contents of the General Purpose Register.

Source: FEMJ2MCx

System Action: The OS/EM function being executed continues, OS/EM takes a SVC dump for the abending module, takes the abending module out of service, and deletes the abending module from CSA/ECSA. See messages FEMxxx023, FEMxxx026 and FEMxxx029.

Operator Response: Contact System Programmer.

System Programmer Response: Use IPCS to determine the cause for the ABEND, take the corrective action required, perform an LLA,REFRESH, and reload the failing module using the OS/EM ISPF RELOAD facility. Contact OS/EM support for assistance in problem resolution.

FEMJ2R213

ABEND AREGS 6-7: nnnnnnnnnnnnnnnn nnnnnnnnnnnnnnnn

Explanation: The OS/EM has detected a MVS System Abend during execution of an OS/EM optional function or a User exit. This message applies to z/OS environments operating in 64-bit mode.

nnnnnnnnnnnnnnnn: Contents of the General Purpose Register.

Source: FEMJ2ERx

System Action: The OS/EM function being executed continues, OS/EM takes a SVC dump for the abending module, takes the abending module out of service, and deletes the abending module from CSA/ECSA. See messages FEMxxx023, FEMxxx026 and FEMxxx029.

Operator Response: Contact System Programmer.

System Programmer Response: Use IPCS to determine the cause for the ABEND, take the corrective action required, perform an LLA,REFRESH, and reload the failing module using the OS/EM ISPF RELOAD facility. Contact OS/EM support for assistance in problem resolution.

FEMJ2S213

ABEND AREGS 6-7: nnnnnnnnnnnnnnnn nnnnnnnnnnnnnnnn

Explanation: The OS/EM has detected a MVS System Abend during execution of an OS/EM optional function or a User exit. This message applies to z/OS environments operating in 64-bit mode.

nnnnnnnnnnnnnnnn: Contents of the General Purpose Register.

Source: FEMJ2SCx

System Action: The OS/EM function being executed continues, OS/EM takes a SVC dump for the abending module, takes the abending module out of service, and deletes the abending module from CSA/ECSA. See messages FEMxxx023, FEMxxx026 and FEMxxx029.

Operator Response: Contact System Programmer.

System Programmer Response: Use IPCS to determine the cause for the ABEND, take the corrective action required, perform an LLA,REFRESH, and reload the failing module using the OS/EM ISPF RELOAD facility. Contact OS/EM support for assistance in problem resolution.

FEMJ3E213

ABEND AREGS 6-7: nnnnnnnnnnnnnnnn nnnnnnnnnnnnnnnn

Explanation: The OS/EM has detected a MVS System Abend during execution of an OS/EM optional function or a User exit. This message applies to z/OS environments operating in 64-bit mode.

nnnnnnnnnnnnnnnn: Contents of the General Purpose Register.

Source: FEMJ3ECN

System Action: The OS/EM function being executed continues, OS/EM takes a SVC dump for the abending module, takes the abending module out of service, and deletes the abending module from CSA/ECSA. See messages FEMxxx023, FEMxxx026 and FEMxxx029.

Operator Response: Contact System Programmer.

System Programmer Response: Use IPCS to determine the cause for the ABEND, take the corrective action required, perform an LLA,REFRESH, and reload the failing module using the OS/EM ISPF RELOAD facility. Contact OS/EM support for assistance in problem resolution.

FEMJ3S213

ABEND AREGS 6-7: nnnnnnnnnnnnnnnn nnnnnnnnnnnnnnnn

Explanation: The OS/EM has detected a MVS System Abend during execution of an OS/EM optional function or a User exit. This message applies to z/OS environments operating in 64-bit mode.

nnnnnnnnnnnnnnnn: Contents of the General Purpose Register.

Source: FEMJ3SVC

System Action: The OS/EM function being executed continues, OS/EM takes a SVC dump for the abending module, takes the abending module out of service, and deletes the abending module from CSA/ECSA. See messages FEMxxx023, FEMxxx026 and FEMxxx029.

Operator Response: Contact System Programmer.

System Programmer Response: Use IPCS to determine the cause for the ABEND, take the corrective action required, perform an LLA,REFRESH, and reload the failing module using the OS/EM ISPF RELOAD facility. Contact OS/EM support for assistance in problem resolution.

FEMLOK213

ABEND AREGS 6-7: nnnnnnnnnnnnnnnn nnnnnnnnnnnnnnnn

Explanation: The OS/EM has detected a MVS System Abend during execution of an OS/EM optional function or a User exit. This message applies to z/OS environments operating in 64-bit mode.

nnnnnnnnnnnnnnnn: Contents of the General Purpose Register.

Source: FEMLOCK

System Action: The OS/EM function being executed continues, OS/EM takes a SVC dump for the abending module, takes the abending module out of service, and deletes the abending module from CSA/ECSA. See messages FEMxxx023, FEMxxx026 and FEMxxx029.

Operator Response: Contact System Programmer.

System Programmer Response: Use IPCS to determine the cause for the ABEND, take the corrective action required, perform an LLA,REFRESH, and reload the failing module using the OS/EM ISPF RELOAD facility. Contact OS/EM support for assistance in problem resolution.

FEMRCN213

ABEND AREGS 6-7: nnnnnnnnnnnnnnnn nnnnnnnnnnnnnnnn

Explanation: The OS/EM has detected a MVS System Abend during execution of an OS/EM optional function or a User exit. This message applies to z/OS environments operating in 64-bit mode.

nnnnnnnnnnnnnnnn: Contents of the General Purpose Register.

Source: FEMRACCN

System Action: The OS/EM function being executed continues, OS/EM takes a SVC dump for the abending module, takes the abending module out of service, and deletes the abending module from CSA/ECSA. See messages FEMxxx023, FEMxxx026 and FEMxxx029.

Operator Response: Contact System Programmer.

System Programmer Response: Use IPCS to determine the cause for the ABEND, take the corrective action required, perform an LLA,REFRESH, and reload the failing module using the OS/EM ISPF RELOAD facility. Contact OS/EM support for assistance in problem resolution.

FEMSCN213

ABEND AREGS 6-7: nnnnnnnnnnnnnnnn nnnnnnnnnnnnnnnn

Explanation: The OS/EM has detected a MVS System Abend during execution of an OS/EM optional function or a User exit. This message applies to z/OS environments operating in 64-bit mode.

nnnnnnnnnnnnnnnn: Contents of the General Purpose Register.

Source: FEMSAFCN,FEMSMFCN

System Action: The OS/EM function being executed continues, OS/EM takes a SVC dump for the abending module, takes the abending module out of service, and deletes the abending module from CSA/ECSA. See messages FEMxxx023, FEMxxx026 and FEMxxx029.

Operator Response: Contact System Programmer.

System Programmer Response: Use IPCS to determine the cause for the ABEND, take the corrective action required, perform an LLA,REFRESH, and reload the failing module using the OS/EM ISPF RELOAD facility. Contact OS/EM support for assistance in problem resolution.

FEMTCN213

ABEND AREGS 6-7: nnnnnnnnnnnnnnnn nnnnnnnnnnnnnnnn

Explanation: The OS/EM has detected a MVS System Abend during execution of an OS/EM optional function or a User exit. This message applies to z/OS environments operating in 64-bit mode.

nnnnnnnnnnnnnnnn: Contents of the General Purpose Register.

Source: FEMTSOCN

System Action: The OS/EM function being executed continues, OS/EM takes a SVC dump for the abending module, takes the abending module out of service, and deletes the abending module from CSA/ECSA. See messages FEMxxx023, FEMxxx026 and FEMxxx029.

Operator Response: Contact System Programmer.

System Programmer Response: Use IPCS to determine the cause for the ABEND, take the corrective action required, perform an LLA,REFRESH, and reload the failing module using the OS/EM ISPF RELOAD facility. Contact OS/EM support for assistance in problem resolution.

FEMTPS213

ABEND AREGS 6-7: nnnnnnnnnnnnnnnn nnnnnnnnnnnnnnnn

Explanation: The OS/EM has detected a MVS System Abend during execution of an OS/EM optional function or a User exit. This message applies to z/OS environments operating in 64-bit mode.

nnnnnnnnnnnnnnnn: Contents of the General Purpose Register.

Source: FEMTPSHR

System Action: The OS/EM function being executed continues, OS/EM takes a SVC dump for the abending module, takes the abending module out of service, and deletes the abending module from CSA/ECSA. See messages FEMxxx023, FEMxxx026 and FEMxxx029.

Operator Response: Contact System Programmer.

System Programmer Response: Use IPCS to determine the cause for the ABEND, take the corrective action required, perform an LLA,REFRESH, and reload the failing module using the OS/EM ISPF RELOAD facility. Contact OS/EM support for assistance in problem resolution.

FEMX05213

ABEND AREGS 6-7: nnnnnnnnnnnnnnnnnnnn nnnnnnnnnnnnnnnnnnn

Explanation: The OS/EM has detected a MVS System Abend during execution of an OS/EM optional function or a User exit. This message applies to z/OS environments operating in 64-bit mode.

nnnnnnnnnnnnnnnnnn: Contents of the General Purpose Register.

Source: FEMJ2X05

System Action: The OS/EM function being executed continues, OS/EM takes a SVC dump for the abending module, takes the abending module out of service, and deletes the abending module from CSA/ECSA. See messages FEMxxx023, FEMxxx026 and FEMxxx029.

Operator Response: Contact System Programmer.

System Programmer Response: Use IPCS to determine the cause for the ABEND, take the corrective action required, perform an LLA,REFRESH, and reload the failing module using the OS/EM ISPF RELOAD facility. Contact OS/EM support for assistance in problem resolution.

FEM02F213

ABEND AREGS 6-7: nnnnnnnnnnnnnnnnnnnn nnnnnnnnnnnnnnnnnnn

Explanation: The OS/EM has detected a MVS System Abend during execution of an OS/EM optional function or a User exit. This message applies to z/OS environments operating in 64-bit mode.

nnnnnnnnnnnnnnnnnn: Contents of the General Purpose Register.

Source: FEM0002F

System Action: The OS/EM function being executed continues, OS/EM takes a SVC dump for the abending module, takes the abending module out of service, and deletes the abending module from CSA/ECSA. See messages FEMxxx023, FEMxxx026 and FEMxxx029.

Operator Response: Contact System Programmer.

System Programmer Response: Use IPCS to determine the cause for the ABEND, take the corrective action required, perform an LLA,REFRESH, and reload the failing module using the OS/EM ISPF RELOAD facility. Contact OS/EM support for assistance in problem resolution.

FEMIPL213

ABEND AREGS 6-7: nnnnnnnnnnnnnnnnnnnn nnnnnnnnnnnnnnnnnnn

Explanation: The OS/EM has detected a MVS System Abend during execution of an OS/EM optional function or a User exit. This message applies to z/OS environments operating in 64-bit mode.

nnnnnnnnnnnnnnnnnn: Contents of the General Purpose Register.

Source: FEMIPL1

System Action: The OS/EM function being executed continues, OS/EM takes a SVC dump for the abending module, takes the abending module out of service, and deletes the abending module from CSA/ECSA. See messages FEMxxx023, FEMxxx026 and FEMxxx029.

Operator Response: Contact System Programmer.

System Programmer Response: Use IPCS to determine the cause for the ABEND, take the corrective action required, perform an LLA,REFRESH, and reload the failing module using the OS/EM ISPF RELOAD facility. Contact OS/EM support for assistance in problem resolution.

FEM2H5213

ABEND AREGS 6-7: nnnnnnnnnnnnnnnn nnnnnnnnnnnnnnnn

Explanation: The OS/EM has detected a MVS System Abend during execution of an OS/EM optional function or a User exit. This message applies to z/OS environments operating in 64-bit mode.

nnnnnnnnnnnnnnnn: Contents of the General Purpose Register.

Source: FEMJ2H5x

System Action: The OS/EM function being executed continues, OS/EM takes a SVC dump for the abending module, takes the abending module out of service, and deletes the abending module from CSA/ECSA. See messages FEMxxx023, FEMxxx026 and FEMxxx029.

Operator Response: Contact System Programmer.

System Programmer Response: Use IPCS to determine the cause for the ABEND, take the corrective action required, perform an LLA,REFRESH, and reload the failing module using the OS/EM ISPF RELOAD facility. Contact OS/EM support for assistance in problem resolution.

FEM2P4213

ABEND AREGS 6-7: nnnnnnnnnnnnnnnn nnnnnnnnnnnnnnnn

Explanation: The OS/EM has detected a MVS System Abend during execution of an OS/EM optional function or a User exit. This message applies to z/OS environments operating in 64-bit mode.

nnnnnnnnnnnnnnnn: Contents of the General Purpose Register.

Source: FEMJ2P4x

System Action: The OS/EM function being executed continues, OS/EM takes a SVC dump for the abending module, takes the abending module out of service, and deletes the abending module from CSA/ECSA. See messages FEMxxx023, FEMxxx026 and FEMxxx029.

Operator Response: Contact System Programmer.

System Programmer Response: Use IPCS to determine the cause for the ABEND, take the corrective action required, perform an LLA,REFRESH, and reload the failing module using the OS/EM ISPF RELOAD facility. Contact OS/EM support for assistance in problem resolution.

FEMACN214

ABEND AREGS 8-9: nnnnnnnnnnnnnnnn nnnnnnnnnnnnnnnn

Explanation: The OS/EM has detected a MVS System Abend during execution of an OS/EM optional function or a User exit. This message applies to z/OS environments operating in 64-bit mode.

nnnnnnnnnnnnnnnn: Contents of the General Purpose Register.

Source: FEMALCCN

System Action: The OS/EM function being executed continues, OS/EM takes a SVC dump for the abending module, takes the abending module out of service, and deletes the abending module from CSA/ECSA. See messages FEMxxx023, FEMxxx026 and FEMxxx029.

Operator Response: Contact System Programmer.

System Programmer Response: Use IPCS to determine the cause for the ABEND, take the corrective action required, perform an LLA,REFRESH, and reload the failing module using the OS/EM ISPF RELOAD facility. Contact OS/EM support for assistance in problem resolution.

FEMALC214

ABEND AREGS 8-9: nnnnnnnnnnnnnnnnnnnn nnnnnnnnnnnnnnnnnnn

Explanation: The OS/EM has detected a MVS System Abend during execution of an OS/EM optional function or a User exit. This message applies to z/OS environments operating in 64-bit mode.

nnnnnnnnnnnnnnnnnn: Contents of the General Purpose Register.

Source: FEMALLO0,FEMALLO1

System Action: The OS/EM function being executed continues, OS/EM takes a SVC dump for the abending module, takes the abending module out of service, and deletes the abending module from CSA/ECSA. See messages FEMxxx023, FEMxxx026 and FEMxxx029.

Operator Response: Contact System Programmer.

System Programmer Response: Use IPCS to determine the cause for the ABEND, take the corrective action required, perform an LLA,REFRESH, and reload the failing module using the OS/EM ISPF RELOAD facility. Contact OS/EM support for assistance in problem resolution.

FEMASY214

ABEND AREGS 8-9: nnnnnnnnnnnnnnnnnnnn nnnnnnnnnnnnnnnnnnn

Explanation: The OS/EM has detected a MVS System Abend during execution of an OS/EM optional function or a User exit. This message applies to z/OS environments operating in 64-bit mode.

nnnnnnnnnnnnnnnnnn: Contents of the General Purpose Register.

Source: FEMASYNC

System Action: The OS/EM function being executed continues, OS/EM takes a SVC dump for the abending module, takes the abending module out of service, and deletes the abending module from CSA/ECSA. See messages FEMxxx023, FEMxxx026 and FEMxxx029.

Operator Response: Contact System Programmer.

System Programmer Response: Use IPCS to determine the cause for the ABEND, take the corrective action required, perform an LLA,REFRESH, and reload the failing module using the OS/EM ISPF RELOAD facility. Contact OS/EM support for assistance in problem resolution.

FEMCMD214

ABEND AREGS 8-9: nnnnnnnnnnnnnnnnnnnn nnnnnnnnnnnnnnnnnnn

Explanation: The OS/EM has detected a MVS System Abend during execution of an OS/EM optional function or a User exit. This message applies to z/OS environments operating in 64-bit mode.

nnnnnnnnnnnnnnnnnn: Contents of the General Purpose Register.

Source: FEMCMD

System Action: The OS/EM function being executed continues, OS/EM takes a SVC dump for the abending module, takes the abending module out of service, and deletes the abending module from CSA/ECSA. See messages FEMxxx023, FEMxxx026 and FEMxxx029.

Operator Response: Contact System Programmer.

System Programmer Response: Use IPCS to determine the cause for the ABEND, take the corrective action required, perform an LLA,REFRESH, and reload the failing module using the OS/EM ISPF RELOAD facility. Contact OS/EM support for assistance in problem resolution.

FEMCOM214

ABEND AREGS 8-9: nnnnnnnnnnnnnnnnnnnn nnnnnnnnnnnnnnnnnnn

Explanation: The OS/EM has detected a MVS System Abend during execution of an OS/EM optional function or a User exit. This message applies to z/OS environments operating in 64-bit mode.

nnnnnnnnnnnnnnnnnn: Contents of the General Purpose Register.

Source: FEMCOMM

System Action: The OS/EM function being executed continues, OS/EM takes a SVC dump for the abending module, takes the abending module out of service, and deletes the abending module from CSA/ECSA. See messages FEMxxx023, FEMxxx026 and FEMxxx029.

Operator Response: Contact System Programmer.

System Programmer Response: Use IPCS to determine the cause for the ABEND, take the corrective action required, perform an LLA,REFRESH, and reload the failing module using the OS/EM ISPF RELOAD facility. Contact OS/EM support for assistance in problem resolution.

FEMDCN214

ABEND AREGS 8-9: nnnnnnnnnnnnnnnnnnnn nnnnnnnnnnnnnnnnnnn

Explanation: The OS/EM has detected a MVS System Abend during execution of an OS/EM optional function or a User exit. This message applies to z/OS environments operating in 64-bit mode.

nnnnnnnnnnnnnnnnnn: Contents of the General Purpose Register.

Source: FEMDADCN

System Action: The OS/EM function being executed continues, OS/EM takes a SVC dump for the abending module, takes the abending module out of service, and deletes the abending module from CSA/ECSA. See messages FEMxxx023, FEMxxx026 and FEMxxx029.

Operator Response: Contact System Programmer.

System Programmer Response: Use IPCS to determine the cause for the ABEND, take the corrective action required, perform an LLA,REFRESH, and reload the failing module using the OS/EM ISPF RELOAD facility. Contact OS/EM support for assistance in problem resolution.

FEMDC1214

ABEND AREGS 8-9: nnnnnnnnnnnnnnnnnnnn nnnnnnnnnnnnnnnnnnn

Explanation: The OS/EM has detected a MVS System Abend during execution of an OS/EM optional function or a User exit. This message applies to z/OS environments operating in 64-bit mode.

nnnnnnnnnnnnnnnnnn: Contents of the General Purpose Register.

Source: FEMDCB1

System Action: The OS/EM function being executed continues, OS/EM takes a SVC dump for the abending module, takes the abending module out of service, and deletes the abending module from CSA/ECSA. See messages FEMxxx023, FEMxxx026 and FEMxxx029.

Operator Response: Contact System Programmer.

System Programmer Response: Use IPCS to determine the cause for the ABEND, take the corrective action required, perform an LLA,REFRESH, and reload the failing module using the OS/EM ISPF RELOAD facility. Contact OS/EM support for assistance in problem resolution.

FEMHCN214

ABEND AREGS 8-9: nnnnnnnnnnnnnnnn nnnnnnnnnnnnnnnn

Explanation: The OS/EM has detected a MVS System Abend during execution of an OS/EM optional function or a User exit. This message applies to z/OS environments operating in 64-bit mode.

nnnnnnnnnnnnnnnn: Contents of the General Purpose Register.

Source: FEMHSMCN

System Action: The OS/EM function being executed continues, OS/EM takes a SVC dump for the abending module, takes the abending module out of service, and deletes the abending module from CSA/ECSA. See messages FEMxxx023, FEMxxx026 and FEMxxx029.

Operator Response: Contact System Programmer.

System Programmer Response: Use IPCS to determine the cause for the ABEND, take the corrective action required, perform an LLA,REFRESH, and reload the failing module using the OS/EM ISPF RELOAD facility. Contact OS/EM support for assistance in problem resolution.

FEMHSP214

ABEND AREGS 8-9: nnnnnnnnnnnnnnnn nnnnnnnnnnnnnnnn

Explanation: The OS/EM has detected a MVS System Abend during execution of an OS/EM optional function or a User exit. This message applies to z/OS environments operating in 64-bit mode.

nnnnnnnnnnnnnnnn: Contents of the General Purpose Register.

Source: FEMHJ20

System Action: The OS/EM function being executed continues, OS/EM takes a SVC dump for the abending module, takes the abending module out of service, and deletes the abending module from CSA/ECSA. See messages FEMxxx023, FEMxxx026 and FEMxxx029.

Operator Response: Contact System Programmer.

System Programmer Response: Use IPCS to determine the cause for the ABEND, take the corrective action required, perform an LLA,REFRESH, and reload the failing module using the OS/EM ISPF RELOAD facility. Contact OS/EM support for assistance in problem resolution.

FEMIAT214

ABEND AREGS 8-9: nnnnnnnnnnnnnnnn nnnnnnnnnnnnnnnn

Explanation: The OS/EM has detected a MVS System Abend during execution of an OS/EM optional function or a User exit. This message applies to z/OS environments operating in 64-bit mode.

nnnnnnnnnnnnnnnn: Contents of the General Purpose Register.

Source: FEMINTK

System Action: The OS/EM function being executed continues, OS/EM takes a SVC dump for the abending module, takes the abending module out of service, and deletes the abending module from CSA/ECSA. See messages FEMxxx023, FEMxxx026 and FEMxxx029.

Operator Response: Contact System Programmer.

System Programmer Response: Use IPCS to determine the cause for the ABEND, take the corrective action required, perform an LLA,REFRESH, and reload the failing module using the OS/EM ISPF RELOAD facility. Contact OS/EM support for assistance in problem resolution.

FEMICN214

ABEND AREGS 8-9: nnnnnnnnnnnnnnnn nnnnnnnnnnnnnnnn

Explanation: The OS/EM has detected a MVS System Abend during execution of an OS/EM optional function or a User exit. This message applies to z/OS environments operating in 64-bit mode.

nnnnnnnnnnnnnnnn: Contents of the General Purpose Register.

Source: FEMISPCN

System Action: The OS/EM function being executed continues, OS/EM takes a SVC dump for the abending module, takes the abending module out of service, and deletes the abending module from CSA/ECSA. See messages FEMxxx023, FEMxxx026 and FEMxxx029.

Operator Response: Contact System Programmer.

System Programmer Response: Use IPCS to determine the cause for the ABEND, take the corrective action required, perform an LLA,REFRESH, and reload the failing module using the OS/EM ISPF RELOAD facility. Contact OS/EM support for assistance in problem resolution.

FEMIPL214

ABEND AREGS 8-9: nnnnnnnnnnnnnnnn nnnnnnnnnnnnnnnn

Explanation: The OS/EM has detected a MVS System Abend during execution of an OS/EM optional function or a User exit. This message applies to z/OS environments operating in 64-bit mode.

nnnnnnnnnnnnnnnn: Contents of the General Purpose Register.

Source: FEMIPL

System Action: The OS/EM function being executed continues, OS/EM takes a SVC dump for the abending module, takes the abending module out of service, and deletes the abending module from CSA/ECSA. See messages FEMxxx023, FEMxxx026 and FEMxxx029.

Operator Response: Contact System Programmer.

System Programmer Response: Use IPCS to determine the cause for the ABEND, take the corrective action required, perform an LLA,REFRESH, and reload the failing module using the OS/EM ISPF RELOAD facility. Contact OS/EM support for assistance in problem resolution.

FEMJS2214

ABEND AREGS 8-9: nnnnnnnnnnnnnnnn nnnnnnnnnnnnnnnn

Explanation: The OS/EM has detected a MVS System Abend during execution of an OS/EM optional function or a User exit. This message applies to z/OS environments operating in 64-bit mode.

nnnnnnnnnnnnnnnn: Contents of the General Purpose Register.

Source: FEMJES2B,FEMJES2G

System Action: The OS/EM function being executed continues, OS/EM takes a SVC dump for the abending module, takes the abending module out of service, and deletes the abending module from CSA/ECSA. See messages FEMxxx023, FEMxxx026 and FEMxxx029.

Operator Response: Contact System Programmer.

System Programmer Response: Use IPCS to determine the cause for the ABEND, take the corrective action required, perform an LLA,REFRESH, and reload the failing module using the OS/EM ISPF RELOAD facility. Contact OS/EM support for assistance in problem resolution.

FEMRCN214

ABEND AREGS 8-9: nnnnnnnnnnnnnnnn nnnnnnnnnnnnnnnn

Explanation: The OS/EM has detected a MVS System Abend during execution of an OS/EM optional function or a User exit. This message applies to z/OS environments operating in 64-bit mode.

nnnnnnnnnnnnnnnn: Contents of the General Purpose Register.

Source: FEMRACCN

System Action: The OS/EM function being executed continues, OS/EM takes a SVC dump for the abending module, takes the abending module out of service, and deletes the abending module from CSA/ECSA. See messages FEMxxx023, FEMxxx026 and FEMxxx029.

Operator Response: Contact System Programmer.

System Programmer Response: Use IPCS to determine the cause for the ABEND, take the corrective action required, perform an LLA,REFRESH, and reload the failing module using the OS/EM ISPF RELOAD facility. Contact OS/EM support for assistance in problem resolution.

FEMSCN214

ABEND AREGS 8-9: nnnnnnnnnnnnnnnn nnnnnnnnnnnnnnnn

Explanation: The OS/EM has detected a MVS System Abend during execution of an OS/EM optional function or a User exit. This message applies to z/OS environments operating in 64-bit mode.

nnnnnnnnnnnnnnnn: Contents of the General Purpose Register.

Source: FEMSAFCN,FEMSMFCN

System Action: The OS/EM function being executed continues, OS/EM takes a SVC dump for the abending module, takes the abending module out of service, and deletes the abending module from CSA/ECSA. See messages FEMxxx023, FEMxxx026 and FEMxxx029.

Operator Response: Contact System Programmer.

System Programmer Response: Use IPCS to determine the cause for the ABEND, take the corrective action required, perform an LLA,REFRESH, and reload the failing module using the OS/EM ISPF RELOAD facility. Contact OS/EM support for assistance in problem resolution.

FEMTCN214

ABEND AREGS 8-9: nnnnnnnnnnnnnnnn nnnnnnnnnnnnnnnn

Explanation: The OS/EM has detected a MVS System Abend during execution of an OS/EM optional function or a User exit. This message applies to z/OS environments operating in 64-bit mode.

nnnnnnnnnnnnnnnn: Contents of the General Purpose Register.

Source: FEMTSOCN

System Action: The OS/EM function being executed continues, OS/EM takes a SVC dump for the abending module, takes the abending module out of service, and deletes the abending module from CSA/ECSA. See messages FEMxxx023, FEMxxx026 and FEMxxx029.

Operator Response: Contact System Programmer.

System Programmer Response: Use IPCS to determine the cause for the ABEND, take the corrective action required, perform an LLA,REFRESH, and reload the failing module using the OS/EM ISPF RELOAD facility. Contact OS/EM support for assistance in problem resolution.

FEMTPS214

ABEND AREGS 8-9: nnnnnnnnnnnnnnnn nnnnnnnnnnnnnnnn

Explanation: The OS/EM has detected a MVS System Abend during execution of an OS/EM optional function or a User exit. This message applies to z/OS environments operating in 64-bit mode.

nnnnnnnnnnnnnnnn: Contents of the General Purpose Register.

Source: FEMTPSHR

System Action: The OS/EM function being executed continues, OS/EM takes a SVC dump for the abending module, takes the abending module out of service, and deletes the abending module from CSA/ECSA. See messages FEMxxx023, FEMxxx026 and FEMxxx029.

Operator Response: Contact System Programmer.

System Programmer Response: Use IPCS to determine the cause for the ABEND, take the corrective action required, perform an LLA,REFRESH, and reload the failing module using the OS/EM ISPF RELOAD facility. Contact OS/EM support for assistance in problem resolution.

FEMUJI214

ABEND AREGS 8-9: nnnnnnnnnnnnnnnn nnnnnnnnnnnnnnnn

Explanation: The OS/EM has detected a MVS System Abend during execution of an OS/EM optional function or a User exit. This message applies to z/OS environments operating in 64-bit mode.

nnnnnnnnnnnnnnnn: Contents of the General Purpose Register.

Source: FEMUJI

System Action: The OS/EM function being executed continues, OS/EM takes a SVC dump for the abending module, takes the abending module out of service, and deletes the abending module from CSA/ECSA. See messages FEMxxx023, FEMxxx026 and FEMxxx029.

Operator Response: Contact System Programmer.

System Programmer Response: Use IPCS to determine the cause for the ABEND, take the corrective action required, perform an LLA,REFRESH, and reload the failing module using the OS/EM ISPF RELOAD facility. Contact OS/EM support for assistance in problem resolution.

FEMUSI214

ABEND AREGS 8-9: nnnnnnnnnnnnnnnn nnnnnnnnnnnnnnnn

Explanation: The OS/EM has detected a MVS System Abend during execution of an OS/EM optional function or a User exit. This message applies to z/OS environments operating in 64-bit mode.

nnnnnnnnnnnnnnnn: Contents of the General Purpose Register.

Source: FEMUSI

System Action: The OS/EM function being executed continues, OS/EM takes a SVC dump for the abending module, takes the abending module out of service, and deletes the abending module from CSA/ECSA. See messages FEMxxx023, FEMxxx026 and FEMxxx029.

Operator Response: Contact System Programmer.

System Programmer Response: Use IPCS to determine the cause for the ABEND, take the corrective action required, perform an LLA,REFRESH, and reload the failing module using the OS/EM ISPF RELOAD facility. Contact OS/EM support for assistance in problem resolution.

FEMVCN214

ABEND AREGS 8-9: nnnnnnnnnnnnnnnnnnn nnnnnnnnnnnnnnnnnnn

Explanation: The OS/EM has detected a MVS System Abend during execution of an OS/EM optional function or a User exit. This message applies to z/OS environments operating in 64-bit mode.

nnnnnnnnnnnnnnnnnn: Contents of the General Purpose Register.

Source: FEMSVCCN

System Action: The OS/EM function being executed continues, OS/EM takes a SVC dump for the abending module, takes the abending module out of service, and deletes the abending module from CSA/ECSA. See messages FEMxxx023, FEMxxx026 and FEMxxx029.

Operator Response: Contact System Programmer.

System Programmer Response: Use IPCS to determine the cause for the ABEND, take the corrective action required, perform an LLA,REFRESH, and reload the failing module using the OS/EM ISPF RELOAD facility. Contact OS/EM support for assistance in problem resolution.

FEMX05214

ABEND AREGS 8-9: nnnnnnnnnnnnnnnnnnn nnnnnnnnnnnnnnnnnnn

Explanation: The OS/EM has detected a MVS System Abend during execution of an OS/EM optional function or a User exit. This message applies to z/OS environments operating in 64-bit mode.

nnnnnnnnnnnnnnnnnn: Contents of the General Purpose Register.

Source: FEMJ2X05

System Action: The OS/EM function being executed continues, OS/EM takes a SVC dump for the abending module, takes the abending module out of service, and deletes the abending module from CSA/ECSA. See messages FEMxxx023, FEMxxx026 and FEMxxx029.

Operator Response: Contact System Programmer.

System Programmer Response: Use IPCS to determine the cause for the ABEND, take the corrective action required, perform an LLA,REFRESH, and reload the failing module using the OS/EM ISPF RELOAD facility. Contact OS/EM support for assistance in problem resolution.

FEM02F214

ABEND AREGS 8-9: nnnnnnnnnnnnnnnnnnn nnnnnnnnnnnnnnnnnnn

Explanation: The OS/EM has detected a MVS System Abend during execution of an OS/EM optional function or a User exit. This message applies to z/OS environments operating in 64-bit mode.

nnnnnnnnnnnnnnnnnn: Contents of the General Purpose Register.

Source: FEM0002F

System Action: The OS/EM function being executed continues, OS/EM takes a SVC dump for the abending module, takes the abending module out of service, and deletes the abending module from CSA/ECSA. See messages FEMxxx023, FEMxxx026 and FEMxxx029.

Operator Response: Contact System Programmer.

System Programmer Response: Use IPCS to determine the cause for the ABEND, take the corrective action required, perform an LLA,REFRESH, and reload the failing module using the OS/EM ISPF RELOAD facility. Contact OS/EM support for assistance in problem resolution.

FEM1PL214

ABEND AREGS 8-9: nnnnnnnnnnnnnnnn nnnnnnnnnnnnnnnn

Explanation: The OS/EM has detected a MVS System Abend during execution of an OS/EM optional function or a User exit. This message applies to z/OS environments operating in 64-bit mode.

nnnnnnnnnnnnnnnn: Contents of the General Purpose Register.

Source: FEM1PL1

System Action: The OS/EM function being executed continues, OS/EM takes a SVC dump for the abending module, takes the abending module out of service, and deletes the abending module from CSA/ECSA. See messages FEMxxx023, FEMxxx026 and FEMxxx029.

Operator Response: Contact System Programmer.

System Programmer Response: Use IPCS to determine the cause for the ABEND, take the corrective action required, perform an LLA,REFRESH, and reload the failing module using the OS/EM ISPF RELOAD facility. Contact OS/EM support for assistance in problem resolution.

FEM2H5214

ABEND AREGS 8-9: nnnnnnnnnnnnnnnn nnnnnnnnnnnnnnnn

Explanation: The OS/EM has detected a MVS System Abend during execution of an OS/EM optional function or a User exit. This message applies to z/OS environments operating in 64-bit mode.

nnnnnnnnnnnnnnnn: Contents of the General Purpose Register.

Source: FEMJ2H5x

System Action: The OS/EM function being executed continues, OS/EM takes a SVC dump for the abending module, takes the abending module out of service, and deletes the abending module from CSA/ECSA. See messages FEMxxx023, FEMxxx026 and FEMxxx029.

Operator Response: Contact System Programmer.

System Programmer Response: Use IPCS to determine the cause for the ABEND, take the corrective action required, perform an LLA,REFRESH, and reload the failing module using the OS/EM ISPF RELOAD facility. Contact OS/EM support for assistance in problem resolution.

FEM2P4214

ABEND AREGS 8-9: nnnnnnnnnnnnnnnn nnnnnnnnnnnnnnnn

Explanation: The OS/EM has detected a MVS System Abend during execution of an OS/EM optional function or a User exit. This message applies to z/OS environments operating in 64-bit mode.

nnnnnnnnnnnnnnnn: Contents of the General Purpose Register.

Source: FEMJ2P4x

System Action: The OS/EM function being executed continues, OS/EM takes a SVC dump for the abending module, takes the abending module out of service, and deletes the abending module from CSA/ECSA. See messages FEMxxx023, FEMxxx026 and FEMxxx029.

Operator Response: Contact System Programmer.

System Programmer Response: Use IPCS to determine the cause for the ABEND, take the corrective action required, perform an LLA,REFRESH, and reload the failing module using the OS/EM ISPF RELOAD facility. Contact OS/EM support for assistance in problem resolution.

FEMACN215

ABEND AREGS 10-11: nnnnnnnnnnnnnnnn nnnnnnnnnnnnnnnn

Explanation: The OS/EM has detected a MVS System Abend during execution of an OS/EM optional function or a User exit. This message applies to z/OS environments operating in 64-bit mode.

nnnnnnnnnnnnnnnn: Contents of the General Purpose Register.

Source: FEMALCCN

System Action: The OS/EM function being executed continues, OS/EM takes a SVC dump for the abending module, takes the abending module out of service, and deletes the abending module from CSA/ECSA. See messages FEMxxx023, FEMxxx026 and FEMxxx029.

Operator Response: Contact System Programmer.

System Programmer Response: Use IPCS to determine the cause for the ABEND, take the corrective action required, perform an LLA,REFRESH, and reload the failing module using the OS/EM ISPF RELOAD facility. Contact OS/EM support for assistance in problem resolution.

FEMALC215

ABEND AREGS 10-11: nnnnnnnnnnnnnnnn nnnnnnnnnnnnnnnn

Explanation: The OS/EM has detected a MVS System Abend during execution of an OS/EM optional function or a User exit. This message applies to z/OS environments operating in 64-bit mode.

nnnnnnnnnnnnnnnn: Contents of the General Purpose Register.

Source: FEMALLO0,FEMALLO1

System Action: The OS/EM function being executed continues, OS/EM takes a SVC dump for the abending module, takes the abending module out of service, and deletes the abending module from CSA/ECSA. See messages FEMxxx023, FEMxxx026 and FEMxxx029.

Operator Response: Contact System Programmer.

System Programmer Response: Use IPCS to determine the cause for the ABEND, take the corrective action required, perform an LLA,REFRESH, and reload the failing module using the OS/EM ISPF RELOAD facility. Contact OS/EM support for assistance in problem resolution.

FEMASY215

ABEND AREGS 10-11: nnnnnnnnnnnnnnnn nnnnnnnnnnnnnnnn

Explanation: The OS/EM has detected a MVS System Abend during execution of an OS/EM optional function or a User exit. This message applies to z/OS environments operating in 64-bit mode.

nnnnnnnnnnnnnnnn: Contents of the General Purpose Register.

Source: FEMASYNC

System Action: The OS/EM function being executed continues, OS/EM takes a SVC dump for the abending module, takes the abending module out of service, and deletes the abending module from CSA/ECSA. See messages FEMxxx023, FEMxxx026 and FEMxxx029.

Operator Response: Contact System Programmer.

System Programmer Response: Use IPCS to determine the cause for the ABEND, take the corrective action required, perform an LLA,REFRESH, and reload the failing module using the OS/EM ISPF RELOAD facility. Contact OS/EM support for assistance in problem resolution.

FEMCMD215

ABEND AREGS 10-11: nnnnnnnnnnnnnnnn nnnnnnnnnnnnnnnn

Explanation: The OS/EM has detected a MVS System Abend during execution of an OS/EM optional function or a User exit. This message applies to z/OS environments operating in 64-bit mode.

nnnnnnnnnnnnnnnn: Contents of the General Purpose Register.

Source: FEMCMD

System Action: The OS/EM function being executed continues, OS/EM takes a SVC dump for the abending module, takes the abending module out of service, and deletes the abending module from CSA/ECSA. See messages FEMxxx023, FEMxxx026 and FEMxxx029.

Operator Response: Contact System Programmer.

System Programmer Response: Use IPCS to determine the cause for the ABEND, take the corrective action required, perform an LLA,REFRESH, and reload the failing module using the OS/EM ISPF RELOAD facility. Contact OS/EM support for assistance in problem resolution.

FEMCOM215

ABEND AREGS 10-11: nnnnnnnnnnnnnnnn nnnnnnnnnnnnnnnn

Explanation: The OS/EM has detected a MVS System Abend during execution of an OS/EM optional function or a User exit. This message applies to z/OS environments operating in 64-bit mode.

nnnnnnnnnnnnnnnn: Contents of the General Purpose Register.

Source: FEMCOMM

System Action: The OS/EM function being executed continues, OS/EM takes a SVC dump for the abending module, takes the abending module out of service, and deletes the abending module from CSA/ECSA. See messages FEMxxx023, FEMxxx026 and FEMxxx029.

Operator Response: Contact System Programmer.

System Programmer Response: Use IPCS to determine the cause for the ABEND, take the corrective action required, perform an LLA,REFRESH, and reload the failing module using the OS/EM ISPF RELOAD facility. Contact OS/EM support for assistance in problem resolution.

FEMDCN215

ABEND AREGS 10-11: nnnnnnnnnnnnnnnn nnnnnnnnnnnnnnnn

Explanation: The OS/EM has detected a MVS System Abend during execution of an OS/EM optional function or a User exit. This message applies to z/OS environments operating in 64-bit mode.

nnnnnnnnnnnnnnnn: Contents of the General Purpose Register.

Source: FEMDADCN

System Action: The OS/EM function being executed continues, OS/EM takes a SVC dump for the abending module, takes the abending module out of service, and deletes the abending module from CSA/ECSA. See messages FEMxxx023, FEMxxx026 and FEMxxx029.

Operator Response: Contact System Programmer.

System Programmer Response: Use IPCS to determine the cause for the ABEND, take the corrective action required, perform an LLA,REFRESH, and reload the failing module using the OS/EM ISPF RELOAD facility. Contact OS/EM support for assistance in problem resolution.

FEMDC1215

ABEND AREGS 10-11: nnnnnnnnnnnnnnnn nnnnnnnnnnnnnnnn

Explanation: The OS/EM has detected a MVS System Abend during execution of an OS/EM optional function or a User exit. This message applies to z/OS environments operating in 64-bit mode.

nnnnnnnnnnnnnnnn: Contents of the General Purpose Register.

Source: FEMDCB1

System Action: The OS/EM function being executed continues, OS/EM takes a SVC dump for the abending module, takes the abending module out of service, and deletes the abending module from CSA/ECSA. See messages FEMxxx023, FEMxxx026 and FEMxxx029.

Operator Response: Contact System Programmer.

System Programmer Response: Use IPCS to determine the cause for the ABEND, take the corrective action required, perform an LLA,REFRESH, and reload the failing module using the OS/EM ISPF RELOAD facility. Contact OS/EM support for assistance in problem resolution.

FEMEXR215

ABEND AREGS 10-11: nnnnnnnnnnnnnnnn nnnnnnnnnnnnnnnn

Explanation: The OS/EM has detected a MVS System Abend during execution of an OS/EM optional function or a User exit. This message applies to z/OS environments operating in 64-bit mode.

nnnnnnnnnnnnnnnn: Contents of the General Purpose Register.

Source: FEMEXRTN

System Action: The OS/EM function being executed continues, OS/EM takes a SVC dump for the abending module, takes the abending module out of service, and deletes the abending module from CSA/ECSA. See messages FEMxxx023, FEMxxx026 and FEMxxx029.

Operator Response: Contact System Programmer.

System Programmer Response: Use IPCS to determine the cause for the ABEND, take the corrective action required, perform an LLA,REFRESH, and reload the failing module using the OS/EM ISPF RELOAD facility. Contact OS/EM support for assistance in problem resolution.

FEMFRA215

ABEND AREGS 10-11: nnnnnnnnnnnnnnnn nnnnnnnnnnnnnnnn

Explanation: The OS/EM has detected a MVS System Abend during execution of an OS/EM optional function or a User exit. This message applies to z/OS environments operating in 64-bit mode.

nnnnnnnnnnnnnnnn: Contents of the General Purpose Register.

Source: FEMFRACN

System Action: The OS/EM function being executed continues, OS/EM takes a SVC dump for the abending module, takes the abending module out of service, and deletes the abending module from CSA/ECSA. See messages FEMxxx023, FEMxxx026 and FEMxxx029.

Operator Response: Contact System Programmer.

System Programmer Response: Use IPCS to determine the cause for the ABEND, take the corrective action required, perform an LLA,REFRESH, and reload the failing module using the OS/EM ISPF RELOAD facility. Contact OS/EM support for assistance in problem resolution.

FEMIAT215

ABEND AREGS 10-11: nnnnnnnnnnnnnnnn nnnnnnnnnnnnnnnn

Explanation: The OS/EM has detected a MVS System Abend during execution of an OS/EM optional function or a User exit. This message applies to z/OS environments operating in 64-bit mode.

nnnnnnnnnnnnnnnnn: Contents of the General Purpose Register.

Source: FEMINTK

System Action: The OS/EM function being executed continues, OS/EM takes a SVC dump for the abending module, takes the abending module out of service, and deletes the abending module from CSA/ECSA. See messages FEMxxx023, FEMxxx026 and FEMxxx029.

Operator Response: Contact System Programmer.

System Programmer Response: Use IPCS to determine the cause for the ABEND, take the corrective action required, perform an LLA,REFRESH, and reload the failing module using the OS/EM ISPF RELOAD facility. Contact OS/EM support for assistance in problem resolution.

FEMICN215

ABEND AREGS 10-11: nnnnnnnnnnnnnnnn nnnnnnnnnnnnnnnn

Explanation: The OS/EM has detected a MVS System Abend during execution of an OS/EM optional function or a User exit. This message applies to z/OS environments operating in 64-bit mode.

nnnnnnnnnnnnnnnnn: Contents of the General Purpose Register.

Source: FEMISPCN

System Action: The OS/EM function being executed continues, OS/EM takes a SVC dump for the abending module, takes the abending module out of service, and deletes the abending module from CSA/ECSA. See messages FEMxxx023, FEMxxx026 and FEMxxx029.

Operator Response: Contact System Programmer.

System Programmer Response: Use IPCS to determine the cause for the ABEND, take the corrective action required, perform an LLA,REFRESH, and reload the failing module using the OS/EM ISPF RELOAD facility. Contact OS/EM support for assistance in problem resolution.

FEMIPL215

ABEND AREGS 10-11: nnnnnnnnnnnnnnnn nnnnnnnnnnnnnnnn

Explanation: The OS/EM has detected a MVS System Abend during execution of an OS/EM optional function or a User exit. This message applies to z/OS environments operating in 64-bit mode.

nnnnnnnnnnnnnnnnn: Contents of the General Purpose Register.

Source: FEMIPL

System Action: The OS/EM function being executed continues, OS/EM takes a SVC dump for the abending module, takes the abending module out of service, and deletes the abending module from CSA/ECSA. See messages FEMxxx023, FEMxxx026 and FEMxxx029.

Operator Response: Contact System Programmer.

System Programmer Response: Use IPCS to determine the cause for the ABEND, take the corrective action required, perform an LLA,REFRESH, and reload the failing module using the OS/EM ISPF RELOAD facility. Contact OS/EM support for assistance in problem resolution.

FEMJS2215

ABEND AREGS 10-11: nnnnnnnnnnnnnnnn nnnnnnnnnnnnnnnn

Explanation: The OS/EM has detected a MVS System Abend during execution of an OS/EM optional function or a User exit. This message applies to z/OS environments operating in 64-bit mode.

nnnnnnnnnnnnnnnn: Contents of the General Purpose Register.

Source: FEMJES2B,FEMJES2G

System Action: The OS/EM function being executed continues, OS/EM takes a SVC dump for the abending module, takes the abending module out of service, and deletes the abending module from CSA/ECSA. See messages FEMxxx023, FEMxxx026 and FEMxxx029.

Operator Response: Contact System Programmer.

System Programmer Response: Use IPCS to determine the cause for the ABEND, take the corrective action required, perform an LLA,REFRESH, and reload the failing module using the OS/EM ISPF RELOAD facility. Contact OS/EM support for assistance in problem resolution.

FEMJ2M215

ABEND AREGS 10-11: nnnnnnnnnnnnnnnn nnnnnnnnnnnnnnnn

Explanation: The OS/EM has detected a MVS System Abend during execution of an OS/EM optional function or a User exit. This message applies to z/OS environments operating in 64-bit mode.

nnnnnnnnnnnnnnnn: Contents of the General Purpose Register.

Source: FEMJ2MCx

System Action: The OS/EM function being executed continues, OS/EM takes a SVC dump for the abending module, takes the abending module out of service, and deletes the abending module from CSA/ECSA. See messages FEMxxx023, FEMxxx026 and FEMxxx029.

Operator Response: Contact System Programmer.

System Programmer Response: Use IPCS to determine the cause for the ABEND, take the corrective action required, perform an LLA,REFRESH, and reload the failing module using the OS/EM ISPF RELOAD facility. Contact OS/EM support for assistance in problem resolution.

FEMJ2R215

ABEND AREGS 10-11: nnnnnnnnnnnnnnnn nnnnnnnnnnnnnnnn

Explanation: The OS/EM has detected a MVS System Abend during execution of an OS/EM optional function or a User exit. This message applies to z/OS environments operating in 64-bit mode.

nnnnnnnnnnnnnnnn: Contents of the General Purpose Register.

Source: FEMJ2ERx

System Action: The OS/EM function being executed continues, OS/EM takes a SVC dump for the abending module, takes the abending module out of service, and deletes the abending module from CSA/ECSA. See messages FEMxxx023, FEMxxx026 and FEMxxx029.

Operator Response: Contact System Programmer.

System Programmer Response: Use IPCS to determine the cause for the ABEND, take the corrective action required, perform an LLA,REFRESH, and reload the failing module using the OS/EM ISPF RELOAD facility. Contact OS/EM support for assistance in problem resolution.

FEMJ2S215

ABEND AREGS 10-11: nnnnnnnnnnnnnnnnnn nnnnnnnnnnnnnnnnnn

Explanation: The OS/EM has detected a MVS System Abend during execution of an OS/EM optional function or a User exit. This message applies to z/OS environments operating in 64-bit mode.

nnnnnnnnnnnnnnnnn: Contents of the General Purpose Register.

Source: FEMJ2SCx

System Action: The OS/EM function being executed continues, OS/EM takes a SVC dump for the abending module, takes the abending module out of service, and deletes the abending module from CSA/ECSA. See messages FEMxxx023, FEMxxx026 and FEMxxx029.

Operator Response: Contact System Programmer.

System Programmer Response: Use IPCS to determine the cause for the ABEND, take the corrective action required, perform an LLA,REFRESH, and reload the failing module using the OS/EM ISPF RELOAD facility. Contact OS/EM support for assistance in problem resolution.

FEMJ3E215

ABEND AREGS 10-11: nnnnnnnnnnnnnnnnnn nnnnnnnnnnnnnnnnnn

Explanation: The OS/EM has detected a MVS System Abend during execution of an OS/EM optional function or a User exit. This message applies to z/OS environments operating in 64-bit mode.

nnnnnnnnnnnnnnnnn: Contents of the General Purpose Register.

Source: FEMJ3ECN

System Action: The OS/EM function being executed continues, OS/EM takes a SVC dump for the abending module, takes the abending module out of service, and deletes the abending module from CSA/ECSA. See messages FEMxxx023, FEMxxx026 and FEMxxx029.

Operator Response: Contact System Programmer.

System Programmer Response: Use IPCS to determine the cause for the ABEND, take the corrective action required, perform an LLA,REFRESH, and reload the failing module using the OS/EM ISPF RELOAD facility. Contact OS/EM support for assistance in problem resolution.

FEMJ3S215

ABEND AREGS 10-11: nnnnnnnnnnnnnnnnnn nnnnnnnnnnnnnnnnnn

Explanation: The OS/EM has detected a MVS System Abend during execution of an OS/EM optional function or a User exit. This message applies to z/OS environments operating in 64-bit mode.

nnnnnnnnnnnnnnnnn: Contents of the General Purpose Register.

Source: FEMJ3SVC

System Action: The OS/EM function being executed continues, OS/EM takes a SVC dump for the abending module, takes the abending module out of service, and deletes the abending module from CSA/ECSA. See messages FEMxxx023, FEMxxx026 and FEMxxx029.

Operator Response: Contact System Programmer.

System Programmer Response: Use IPCS to determine the cause for the ABEND, take the corrective action required, perform an LLA,REFRESH, and reload the failing module using the OS/EM ISPF RELOAD facility. Contact OS/EM support for assistance in problem resolution.

FEMLOK215

ABEND AREGS 10-11: nnnnnnnnnnnnnnnn nnnnnnnnnnnnnnnn

Explanation: The OS/EM has detected a MVS System Abend during execution of an OS/EM optional function or a User exit. This message applies to z/OS environments operating in 64-bit mode.

nnnnnnnnnnnnnnnn: Contents of the General Purpose Register.

Source: FEMLOCK

System Action: The OS/EM function being executed continues, OS/EM takes a SVC dump for the abending module, takes the abending module out of service, and deletes the abending module from CSA/ECSA. See messages FEMxxx023, FEMxxx026 and FEMxxx029.

Operator Response: Contact System Programmer.

System Programmer Response: Use IPCS to determine the cause for the ABEND, take the corrective action required, perform an LLA,REFRESH, and reload the failing module using the OS/EM ISPF RELOAD facility. Contact OS/EM support for assistance in problem resolution.

FEMRCN215

ABEND AREGS 10-11: nnnnnnnnnnnnnnnn nnnnnnnnnnnnnnnn

Explanation: The OS/EM has detected a MVS System Abend during execution of an OS/EM optional function or a User exit. This message applies to z/OS environments operating in 64-bit mode.

nnnnnnnnnnnnnnnn: Contents of the General Purpose Register.

Source: FEMRACCN

System Action: The OS/EM function being executed continues, OS/EM takes a SVC dump for the abending module, takes the abending module out of service, and deletes the abending module from CSA/ECSA. See messages FEMxxx023, FEMxxx026 and FEMxxx029.

Operator Response: Contact System Programmer.

System Programmer Response: Use IPCS to determine the cause for the ABEND, take the corrective action required, perform an LLA,REFRESH, and reload the failing module using the OS/EM ISPF RELOAD facility. Contact OS/EM support for assistance in problem resolution.

FEMSCN215

ABEND AREGS 10-11: nnnnnnnnnnnnnnnn nnnnnnnnnnnnnnnn

Explanation: The OS/EM has detected a MVS System Abend during execution of an OS/EM optional function or a User exit. This message applies to z/OS environments operating in 64-bit mode.

nnnnnnnnnnnnnnnn: Contents of the General Purpose Register.

Source: FEMSAFCN,FEMSMFCN

System Action: The OS/EM function being executed continues, OS/EM takes a SVC dump for the abending module, takes the abending module out of service, and deletes the abending module from CSA/ECSA. See messages FEMxxx023, FEMxxx026 and FEMxxx029.

Operator Response: Contact System Programmer.

System Programmer Response: Use IPCS to determine the cause for the ABEND, take the corrective action required, perform an LLA,REFRESH, and reload the failing module using the OS/EM ISPF RELOAD facility. Contact OS/EM support for assistance in problem resolution.

FEMUSI215

ABEND AREGS 10-11: nnnnnnnnnnnnnnnn nnnnnnnnnnnnnnnn

Explanation: The OS/EM has detected a MVS System Abend during execution of an OS/EM optional function or a User exit. This message applies to z/OS environments operating in 64-bit mode.

nnnnnnnnnnnnnnnn: Contents of the General Purpose Register.

Source: FEMUSI

System Action: The OS/EM function being executed continues, OS/EM takes a SVC dump for the abending module, takes the abending module out of service, and deletes the abending module from CSA/ECSA. See messages FEMxxx023, FEMxxx026 and FEMxxx029.

Operator Response: Contact System Programmer.

System Programmer Response: Use IPCS to determine the cause for the ABEND, take the corrective action required, perform an LLA,REFRESH, and reload the failing module using the OS/EM ISPF RELOAD facility. Contact OS/EM support for assistance in problem resolution.

FEMVCN215

ABEND AREGS 10-11: nnnnnnnnnnnnnnnn nnnnnnnnnnnnnnnn

Explanation: The OS/EM has detected a MVS System Abend during execution of an OS/EM optional function or a User exit. This message applies to z/OS environments operating in 64-bit mode.

nnnnnnnnnnnnnnnn: Contents of the General Purpose Register.

Source: FEMSVCCN

System Action: The OS/EM function being executed continues, OS/EM takes a SVC dump for the abending module, takes the abending module out of service, and deletes the abending module from CSA/ECSA. See messages FEMxxx023, FEMxxx026 and FEMxxx029.

Operator Response: Contact System Programmer.

System Programmer Response: Use IPCS to determine the cause for the ABEND, take the corrective action required, perform an LLA,REFRESH, and reload the failing module using the OS/EM ISPF RELOAD facility. Contact OS/EM support for assistance in problem resolution.

FEMX05215

ABEND AREGS 10-11: nnnnnnnnnnnnnnnn nnnnnnnnnnnnnnnn

Explanation: The OS/EM has detected a MVS System Abend during execution of an OS/EM optional function or a User exit. This message applies to z/OS environments operating in 64-bit mode.

nnnnnnnnnnnnnnnn: Contents of the General Purpose Register.

Source: FEMJ2X05

System Action: The OS/EM function being executed continues, OS/EM takes a SVC dump for the abending module, takes the abending module out of service, and deletes the abending module from CSA/ECSA. See messages FEMxxx023, FEMxxx026 and FEMxxx029.

Operator Response: Contact System Programmer.

System Programmer Response: Use IPCS to determine the cause for the ABEND, take the corrective action required, perform an LLA,REFRESH, and reload the failing module using the OS/EM ISPF RELOAD facility. Contact OS/EM support for assistance in problem resolution.

FEM02F215

ABEND AREGS 10-11: nnnnnnnnnnnnnnnn nnnnnnnnnnnnnnnn

Explanation: The OS/EM has detected a MVS System Abend during execution of an OS/EM optional function or a User exit. This message applies to z/OS environments operating in 64-bit mode.

nnnnnnnnnnnnnnnnn: Contents of the General Purpose Register.

Source: FEM0002F

System Action: The OS/EM function being executed continues, OS/EM takes a SVC dump for the abending module, takes the abending module out of service, and deletes the abending module from CSA/ECSA. See messages FEMxxx023, FEMxxx026 and FEMxxx029.

Operator Response: Contact System Programmer.

System Programmer Response: Use IPCS to determine the cause for the ABEND, take the corrective action required, perform an LLA,REFRESH, and reload the failing module using the OS/EM ISPF RELOAD facility. Contact OS/EM support for assistance in problem resolution.

FEM1PL215

ABEND AREGS 10-11: nnnnnnnnnnnnnnnn nnnnnnnnnnnnnnnn

Explanation: The OS/EM has detected a MVS System Abend during execution of an OS/EM optional function or a User exit. This message applies to z/OS environments operating in 64-bit mode.

nnnnnnnnnnnnnnnnn: Contents of the General Purpose Register.

Source: FEM1PL1

System Action: The OS/EM function being executed continues, OS/EM takes a SVC dump for the abending module, takes the abending module out of service, and deletes the abending module from CSA/ECSA. See messages FEMxxx023, FEMxxx026 and FEMxxx029.

Operator Response: Contact System Programmer.

System Programmer Response: Use IPCS to determine the cause for the ABEND, take the corrective action required, perform an LLA,REFRESH, and reload the failing module using the OS/EM ISPF RELOAD facility. Contact OS/EM support for assistance in problem resolution.

FEM2H5215

ABEND AREGS 10-11: nnnnnnnnnnnnnnnn nnnnnnnnnnnnnnnn

Explanation: The OS/EM has detected a MVS System Abend during execution of an OS/EM optional function or a User exit. This message applies to z/OS environments operating in 64-bit mode.

nnnnnnnnnnnnnnnnn: Contents of the General Purpose Register.

Source: FEMJ2H5x

System Action: The OS/EM function being executed continues, OS/EM takes a SVC dump for the abending module, takes the abending module out of service, and deletes the abending module from CSA/ECSA. See messages FEMxxx023, FEMxxx026 and FEMxxx029.

Operator Response: Contact System Programmer.

System Programmer Response: Use IPCS to determine the cause for the ABEND, take the corrective action required, perform an LLA,REFRESH, and reload the failing module using the OS/EM ISPF RELOAD facility. Contact OS/EM support for assistance in problem resolution.

FEM2P4215

ABEND AREGS 10-11: nnnnnnnnnnnnnnnnnnnn nnnnnnnnnnnnnnnnnnnn

Explanation: The OS/EM has detected a MVS System Abend during execution of an OS/EM optional function or a User exit. This message applies to z/OS environments operating in 64-bit mode.

nnnnnnnnnnnnnnnnnnn: Contents of the General Purpose Register.

Source: FEMJ2P4x

System Action: The OS/EM function being executed continues, OS/EM takes a SVC dump for the abending module, takes the abending module out of service, and deletes the abending module from CSA/ECSA. See messages FEMxxx023, FEMxxx026 and FEMxxx029.

Operator Response: Contact System Programmer.

System Programmer Response: Use IPCS to determine the cause for the ABEND, take the corrective action required, perform an LLA,REFRESH, and reload the failing module using the OS/EM ISPF RELOAD facility. Contact OS/EM support for assistance in problem resolution.

FEMACN216

ABEND AREGS 12-13: nnnnnnnnnnnnnnnnnnnn nnnnnnnnnnnnnnnnnnnn

Explanation: The OS/EM has detected a MVS System Abend during execution of an OS/EM optional function or a User exit. This message applies to z/OS environments operating in 64-bit mode.

nnnnnnnnnnnnnnnnnnn: Contents of the General Purpose Register.

Source: FEMALCCN

System Action: The OS/EM function being executed continues, OS/EM takes a SVC dump for the abending module, takes the abending module out of service, and deletes the abending module from CSA/ECSA. See messages FEMxxx023, FEMxxx026 and FEMxxx029.

Operator Response: Contact System Programmer.

System Programmer Response: Use IPCS to determine the cause for the ABEND, take the corrective action required, perform an LLA,REFRESH, and reload the failing module using the OS/EM ISPF RELOAD facility. Contact OS/EM support for assistance in problem resolution.

FEMALC216

ABEND AREGS 12-13: nnnnnnnnnnnnnnnnnnnn nnnnnnnnnnnnnnnnnnnn

Explanation: The OS/EM has detected a MVS System Abend during execution of an OS/EM optional function or a User exit. This message applies to z/OS environments operating in 64-bit mode.

nnnnnnnnnnnnnnnnnnn: Contents of the General Purpose Register.

Source: FEMALLO0,FEMALLO1

System Action: The OS/EM function being executed continues, OS/EM takes a SVC dump for the abending module, takes the abending module out of service, and deletes the abending module from CSA/ECSA. See messages FEMxxx023, FEMxxx026 and FEMxxx029.

Operator Response: Contact System Programmer.

System Programmer Response: Use IPCS to determine the cause for the ABEND, take the corrective action required, perform an LLA,REFRESH, and reload the failing module using the OS/EM ISPF RELOAD facility. Contact OS/EM support for assistance in problem resolution.

FEMASY216

ABEND AREGS 12-13: nnnnnnnnnnnnnnnn nnnnnnnnnnnnnnnn

Explanation: The OS/EM has detected a MVS System Abend during execution of an OS/EM optional function or a User exit. This message applies to z/OS environments operating in 64-bit mode.

nnnnnnnnnnnnnnnn: Contents of the General Purpose Register.

Source: FEMASYNC

System Action: The OS/EM function being executed continues, OS/EM takes a SVC dump for the abending module, takes the abending module out of service, and deletes the abending module from CSA/ECSA. See messages FEMxxx023, FEMxxx026 and FEMxxx029.

Operator Response: Contact System Programmer.

System Programmer Response: Use IPCS to determine the cause for the ABEND, take the corrective action required, perform an LLA,REFRESH, and reload the failing module using the OS/EM ISPF RELOAD facility. Contact OS/EM support for assistance in problem resolution.

FEMCMD216

ABEND AREGS 12-13: nnnnnnnnnnnnnnnn nnnnnnnnnnnnnnnn

Explanation: The OS/EM has detected a MVS System Abend during execution of an OS/EM optional function or a User exit. This message applies to z/OS environments operating in 64-bit mode.

nnnnnnnnnnnnnnnn: Contents of the General Purpose Register.

Source: FEMCMD

System Action: The OS/EM function being executed continues, OS/EM takes a SVC dump for the abending module, takes the abending module out of service, and deletes the abending module from CSA/ECSA. See messages FEMxxx023, FEMxxx026 and FEMxxx029.

Operator Response: Contact System Programmer.

System Programmer Response: Use IPCS to determine the cause for the ABEND, take the corrective action required, perform an LLA,REFRESH, and reload the failing module using the OS/EM ISPF RELOAD facility. Contact OS/EM support for assistance in problem resolution.

FEMCOM216

ABEND AREGS 12-13: nnnnnnnnnnnnnnnn nnnnnnnnnnnnnnnn

Explanation: The OS/EM has detected a MVS System Abend during execution of an OS/EM optional function or a User exit. This message applies to z/OS environments operating in 64-bit mode.

nnnnnnnnnnnnnnnn: Contents of the General Purpose Register.

Source: FEMCOMM

System Action: The OS/EM function being executed continues, OS/EM takes a SVC dump for the abending module, takes the abending module out of service, and deletes the abending module from CSA/ECSA. See messages FEMxxx023, FEMxxx026 and FEMxxx029.

Operator Response: Contact System Programmer.

System Programmer Response: Use IPCS to determine the cause for the ABEND, take the corrective action required, perform an LLA,REFRESH, and reload the failing module using the OS/EM ISPF RELOAD facility. Contact OS/EM support for assistance in problem resolution.

FEMDCN216

ABEND AREGS 12-13: nnnnnnnnnnnnnnnn nnnnnnnnnnnnnnnn

Explanation: The OS/EM has detected a MVS System Abend during execution of an OS/EM optional function or a User exit. This message applies to z/OS environments operating in 64-bit mode.

nnnnnnnnnnnnnnnn: Contents of the General Purpose Register.

Source: FEMDADCN

System Action: The OS/EM function being executed continues, OS/EM takes a SVC dump for the abending module, takes the abending module out of service, and deletes the abending module from CSA/ECSA. See messages FEMxxx023, FEMxxx026 and FEMxxx029.

Operator Response: Contact System Programmer.

System Programmer Response: Use IPCS to determine the cause for the ABEND, take the corrective action required, perform an LLA,REFRESH, and reload the failing module using the OS/EM ISPF RELOAD facility. Contact OS/EM support for assistance in problem resolution.

FEMDC1216

ABEND AREGS 12-13: nnnnnnnnnnnnnnnn nnnnnnnnnnnnnnnn

Explanation: The OS/EM has detected a MVS System Abend during execution of an OS/EM optional function or a User exit. This message applies to z/OS environments operating in 64-bit mode.

nnnnnnnnnnnnnnnn: Contents of the General Purpose Register.

Source: FEMDCB1

System Action: The OS/EM function being executed continues, OS/EM takes a SVC dump for the abending module, takes the abending module out of service, and deletes the abending module from CSA/ECSA. See messages FEMxxx023, FEMxxx026 and FEMxxx029.

Operator Response: Contact System Programmer.

System Programmer Response: Use IPCS to determine the cause for the ABEND, take the corrective action required, perform an LLA,REFRESH, and reload the failing module using the OS/EM ISPF RELOAD facility. Contact OS/EM support for assistance in problem resolution.

FEMEXR216

ABEND AREGS 12-13: nnnnnnnnnnnnnnnn nnnnnnnnnnnnnnnn

Explanation: The OS/EM has detected a MVS System Abend during execution of an OS/EM optional function or a User exit. This message applies to z/OS environments operating in 64-bit mode.

nnnnnnnnnnnnnnnn: Contents of the General Purpose Register.

Source: FEMEXRTN

System Action: The OS/EM function being executed continues, OS/EM takes a SVC dump for the abending module, takes the abending module out of service, and deletes the abending module from CSA/ECSA. See messages FEMxxx023, FEMxxx026 and FEMxxx029.

Operator Response: Contact System Programmer.

System Programmer Response: Use IPCS to determine the cause for the ABEND, take the corrective action required, perform an LLA,REFRESH, and reload the failing module using the OS/EM ISPF RELOAD facility. Contact OS/EM support for assistance in problem resolution.

FEMFRA216

ABEND AREGS 12-13: nnnnnnnnnnnnnnnn nnnnnnnnnnnnnnnn

Explanation: The OS/EM has detected a MVS System Abend during execution of an OS/EM optional function or a User exit. This message applies to z/OS environments operating in 64-bit mode.

nnnnnnnnnnnnnnnn: Contents of the General Purpose Register.

Source: FEMFRACN

System Action: The OS/EM function being executed continues, OS/EM takes a SVC dump for the abending module, takes the abending module out of service, and deletes the abending module from CSA/ECSA. See messages FEMxxx023, FEMxxx026 and FEMxxx029.

Operator Response: Contact System Programmer.

System Programmer Response: Use IPCS to determine the cause for the ABEND, take the corrective action required, perform an LLA,REFRESH, and reload the failing module using the OS/EM ISPF RELOAD facility. Contact OS/EM support for assistance in problem resolution.

FEMFTN216

ABEND AREGS 12-13: nnnnnnnnnnnnnnnn nnnnnnnnnnnnnnnn

Explanation: The OS/EM has detected a MVS System Abend during execution of an OS/EM optional function or a User exit. This message applies to z/OS environments operating in 64-bit mode.

nnnnnnnnnnnnnnnn: Contents of the General Purpose Register.

Source: FEMFRRTN

System Action: The OS/EM function being executed continues, OS/EM takes a SVC dump for the abending module, takes the abending module out of service, and deletes the abending module from CSA/ECSA. See messages FEMxxx023, FEMxxx026 and FEMxxx029.

Operator Response: Contact System Programmer.

System Programmer Response: Use IPCS to determine the cause for the ABEND, take the corrective action required, perform an LLA,REFRESH, and reload the failing module using the OS/EM ISPF RELOAD facility. Contact OS/EM support for assistance in problem resolution.

FEMHCN216

ABEND AREGS 12-13: nnnnnnnnnnnnnnnn nnnnnnnnnnnnnnnn

Explanation: The OS/EM has detected a MVS System Abend during execution of an OS/EM optional function or a User exit. This message applies to z/OS environments operating in 64-bit mode.

nnnnnnnnnnnnnnnn: Contents of the General Purpose Register.

Source: FEMHSMCN

System Action: The OS/EM function being executed continues, OS/EM takes a SVC dump for the abending module, takes the abending module out of service, and deletes the abending module from CSA/ECSA. See messages FEMxxx023, FEMxxx026 and FEMxxx029.

Operator Response: Contact System Programmer.

System Programmer Response: Use IPCS to determine the cause for the ABEND, take the corrective action required, perform an LLA,REFRESH, and reload the failing module using the OS/EM ISPF RELOAD facility. Contact OS/EM support for assistance in problem resolution.

FEMHSP216

ABEND AREGS 12-13: nnnnnnnnnnnnnnnnnnnnnnnnnnnnnnnnnnnnn

Explanation: The OS/EM has detected a MVS System Abend during execution of an OS/EM optional function or a User exit. This message applies to z/OS environments operating in 64-bit mode.

nnnnnnnnnnnnnnnnnn: Contents of the General Purpose Register.

Source: FEMHJ20

System Action: The OS/EM function being executed continues, OS/EM takes a SVC dump for the abending module, takes the abending module out of service, and deletes the abending module from CSA/ECSA. See messages FEMxxx023, FEMxxx026 and FEMxxx029.

Operator Response: Contact System Programmer.

System Programmer Response: Use IPCS to determine the cause for the ABEND, take the corrective action required, perform an LLA,REFRESH, and reload the failing module using the OS/EM ISPF RELOAD facility. Contact OS/EM support for assistance in problem resolution.

FEMIAT216

ABEND AREGS 12-13: nnnnnnnnnnnnnnnnnnnnnnnnnnnnnnnnnnnnn

Explanation: The OS/EM has detected a MVS System Abend during execution of an OS/EM optional function or a User exit. This message applies to z/OS environments operating in 64-bit mode.

nnnnnnnnnnnnnnnnnn: Contents of the General Purpose Register.

Source: FEMINTK

System Action: The OS/EM function being executed continues, OS/EM takes a SVC dump for the abending module, takes the abending module out of service, and deletes the abending module from CSA/ECSA. See messages FEMxxx023, FEMxxx026 and FEMxxx029.

Operator Response: Contact System Programmer.

System Programmer Response: Use IPCS to determine the cause for the ABEND, take the corrective action required, perform an LLA,REFRESH, and reload the failing module using the OS/EM ISPF RELOAD facility. Contact OS/EM support for assistance in problem resolution.

FEMICN216

ABEND AREGS 12-13: nnnnnnnnnnnnnnnnnnnnnnnnnnnnnnnnnnnnn

Explanation: The OS/EM has detected a MVS System Abend during execution of an OS/EM optional function or a User exit. This message applies to z/OS environments operating in 64-bit mode.

nnnnnnnnnnnnnnnnnn: Contents of the General Purpose Register.

Source: FEMISPCN

System Action: The OS/EM function being executed continues, OS/EM takes a SVC dump for the abending module, takes the abending module out of service, and deletes the abending module from CSA/ECSA. See messages FEMxxx023, FEMxxx026 and FEMxxx029.

Operator Response: Contact System Programmer.

System Programmer Response: Use IPCS to determine the cause for the ABEND, take the corrective action required, perform an LLA,REFRESH, and reload the failing module using the OS/EM ISPF RELOAD facility. Contact OS/EM support for assistance in problem resolution.

FEMJ3S216

ABEND AREGS 12-13: nnnnnnnnnnnnnnnn nnnnnnnnnnnnnnnn

Explanation: The OS/EM has detected a MVS System Abend during execution of an OS/EM optional function or a User exit. This message applies to z/OS environments operating in 64-bit mode.

nnnnnnnnnnnnnnnn: Contents of the General Purpose Register.

Source: FEMJ3SVC

System Action: The OS/EM function being executed continues, OS/EM takes a SVC dump for the abending module, takes the abending module out of service, and deletes the abending module from CSA/ECSA. See messages FEMxxx023, FEMxxx026 and FEMxxx029.

Operator Response: Contact System Programmer.

System Programmer Response: Use IPCS to determine the cause for the ABEND, take the corrective action required, perform an LLA,REFRESH, and reload the failing module using the OS/EM ISPF RELOAD facility. Contact OS/EM support for assistance in problem resolution.

FEMLOK216

ABEND AREGS 12-13: nnnnnnnnnnnnnnnn nnnnnnnnnnnnnnnn

Explanation: The OS/EM has detected a MVS System Abend during execution of an OS/EM optional function or a User exit. This message applies to z/OS environments operating in 64-bit mode.

nnnnnnnnnnnnnnnn: Contents of the General Purpose Register.

Source: FEMLOCK

System Action: The OS/EM function being executed continues, OS/EM takes a SVC dump for the abending module, takes the abending module out of service, and deletes the abending module from CSA/ECSA. See messages FEMxxx023, FEMxxx026 and FEMxxx029.

Operator Response: Contact System Programmer.

System Programmer Response: Use IPCS to determine the cause for the ABEND, take the corrective action required, perform an LLA,REFRESH, and reload the failing module using the OS/EM ISPF RELOAD facility. Contact OS/EM support for assistance in problem resolution.

FEMRCN216

ABEND AREGS 12-13: nnnnnnnnnnnnnnnn nnnnnnnnnnnnnnnn

Explanation: The OS/EM has detected a MVS System Abend during execution of an OS/EM optional function or a User exit. This message applies to z/OS environments operating in 64-bit mode.

nnnnnnnnnnnnnnnn: Contents of the General Purpose Register.

Source: FEMRACCN

System Action: The OS/EM function being executed continues, OS/EM takes a SVC dump for the abending module, takes the abending module out of service, and deletes the abending module from CSA/ECSA. See messages FEMxxx023, FEMxxx026 and FEMxxx029.

Operator Response: Contact System Programmer.

System Programmer Response: Use IPCS to determine the cause for the ABEND, take the corrective action required, perform an LLA,REFRESH, and reload the failing module using the OS/EM ISPF RELOAD facility. Contact OS/EM support for assistance in problem resolution.

FEMSCN216

ABEND AREGS 12-13: nnnnnnnnnnnnnnnnnn nnnnnnnnnnnnnnnnnn

Explanation: The OS/EM has detected a MVS System Abend during execution of an OS/EM optional function or a User exit. This message applies to z/OS environments operating in 64-bit mode.

nnnnnnnnnnnnnnnnn: Contents of the General Purpose Register.

Source: FEMSAFCN,FEMSMFCN

System Action: The OS/EM function being executed continues, OS/EM takes a SVC dump for the abending module, takes the abending module out of service, and deletes the abending module from CSA/ECSA. See messages FEMxxx023, FEMxxx026 and FEMxxx029.

Operator Response: Contact System Programmer.

System Programmer Response: Use IPCS to determine the cause for the ABEND, take the corrective action required, perform an LLA,REFRESH, and reload the failing module using the OS/EM ISPF RELOAD facility. Contact OS/EM support for assistance in problem resolution.

FEMTCN216

ABEND AREGS 12-13: nnnnnnnnnnnnnnnnnn nnnnnnnnnnnnnnnnnn

Explanation: The OS/EM has detected a MVS System Abend during execution of an OS/EM optional function or a User exit. This message applies to z/OS environments operating in 64-bit mode.

nnnnnnnnnnnnnnnnn: Contents of the General Purpose Register.

Source: FEMTSOCN

System Action: The OS/EM function being executed continues, OS/EM takes a SVC dump for the abending module, takes the abending module out of service, and deletes the abending module from CSA/ECSA. See messages FEMxxx023, FEMxxx026 and FEMxxx029.

Operator Response: Contact System Programmer.

System Programmer Response: Use IPCS to determine the cause for the ABEND, take the corrective action required, perform an LLA,REFRESH, and reload the failing module using the OS/EM ISPF RELOAD facility. Contact OS/EM support for assistance in problem resolution.

FEMTPS216

ABEND AREGS 12-13: nnnnnnnnnnnnnnnnnn nnnnnnnnnnnnnnnnnn

Explanation: The OS/EM has detected a MVS System Abend during execution of an OS/EM optional function or a User exit. This message applies to z/OS environments operating in 64-bit mode.

nnnnnnnnnnnnnnnnn: Contents of the General Purpose Register.

Source: FEMTPSHR

System Action: The OS/EM function being executed continues, OS/EM takes a SVC dump for the abending module, takes the abending module out of service, and deletes the abending module from CSA/ECSA. See messages FEMxxx023, FEMxxx026 and FEMxxx029.

Operator Response: Contact System Programmer.

System Programmer Response: Use IPCS to determine the cause for the ABEND, take the corrective action required, perform an LLA,REFRESH, and reload the failing module using the OS/EM ISPF RELOAD facility. Contact OS/EM support for assistance in problem resolution.

FEMUJI216

ABEND AREGS 12-13: nnnnnnnnnnnnnnnn nnnnnnnnnnnnnnnn

Explanation: The OS/EM has detected a MVS System Abend during execution of an OS/EM optional function or a User exit. This message applies to z/OS environments operating in 64-bit mode.

nnnnnnnnnnnnnnnnn: Contents of the General Purpose Register.

Source: FEMUJI

System Action: The OS/EM function being executed continues, OS/EM takes a SVC dump for the abending module, takes the abending module out of service, and deletes the abending module from CSA/ECSA. See messages FEMxxx023, FEMxxx026 and FEMxxx029.

Operator Response: Contact System Programmer.

System Programmer Response: Use IPCS to determine the cause for the ABEND, take the corrective action required, perform an LLA,REFRESH, and reload the failing module using the OS/EM ISPF RELOAD facility. Contact OS/EM support for assistance in problem resolution.

FEMUSI216

ABEND AREGS 12-13: nnnnnnnnnnnnnnnn nnnnnnnnnnnnnnnn

Explanation: The OS/EM has detected a MVS System Abend during execution of an OS/EM optional function or a User exit. This message applies to z/OS environments operating in 64-bit mode.

nnnnnnnnnnnnnnnnn: Contents of the General Purpose Register.

Source: FEMUSI

System Action: The OS/EM function being executed continues, OS/EM takes a SVC dump for the abending module, takes the abending module out of service, and deletes the abending module from CSA/ECSA. See messages FEMxxx023, FEMxxx026 and FEMxxx029.

Operator Response: Contact System Programmer.

System Programmer Response: Use IPCS to determine the cause for the ABEND, take the corrective action required, perform an LLA,REFRESH, and reload the failing module using the OS/EM ISPF RELOAD facility. Contact OS/EM support for assistance in problem resolution.

FEMVCN216

ABEND AREGS 12-13: nnnnnnnnnnnnnnnn nnnnnnnnnnnnnnnn

Explanation: The OS/EM has detected a MVS System Abend during execution of an OS/EM optional function or a User exit. This message applies to z/OS environments operating in 64-bit mode.

nnnnnnnnnnnnnnnnn: Contents of the General Purpose Register.

Source: FEMSVCCN

System Action: The OS/EM function being executed continues, OS/EM takes a SVC dump for the abending module, takes the abending module out of service, and deletes the abending module from CSA/ECSA. See messages FEMxxx023, FEMxxx026 and FEMxxx029.

Operator Response: Contact System Programmer.

System Programmer Response: Use IPCS to determine the cause for the ABEND, take the corrective action required, perform an LLA,REFRESH, and reload the failing module using the OS/EM ISPF RELOAD facility. Contact OS/EM support for assistance in problem resolution.

FEMX05216

ABEND AREGS 12-13: nnnnnnnnnnnnnnnn nnnnnnnnnnnnnnnn

Explanation: The OS/EM has detected a MVS System Abend during execution of an OS/EM optional function or a User exit. This message applies to z/OS environments operating in 64-bit mode.

nnnnnnnnnnnnnnnn: Contents of the General Purpose Register.

Source: FEMJ2X05

System Action: The OS/EM function being executed continues, OS/EM takes a SVC dump for the abending module, takes the abending module out of service, and deletes the abending module from CSA/ECSA. See messages FEMxxx023, FEMxxx026 and FEMxxx029.

Operator Response: Contact System Programmer.

System Programmer Response: Use IPCS to determine the cause for the ABEND, take the corrective action required, perform an LLA,REFRESH, and reload the failing module using the OS/EM ISPF RELOAD facility. Contact OS/EM support for assistance in problem resolution.

FEM02F216

ABEND AREGS 12-13: nnnnnnnnnnnnnnnn nnnnnnnnnnnnnnnn

Explanation: The OS/EM has detected a MVS System Abend during execution of an OS/EM optional function or a User exit. This message applies to z/OS environments operating in 64-bit mode.

nnnnnnnnnnnnnnnn: Contents of the General Purpose Register.

Source: FEM0002F

System Action: The OS/EM function being executed continues, OS/EM takes a SVC dump for the abending module, takes the abending module out of service, and deletes the abending module from CSA/ECSA. See messages FEMxxx023, FEMxxx026 and FEMxxx029.

Operator Response: Contact System Programmer.

System Programmer Response: Use IPCS to determine the cause for the ABEND, take the corrective action required, perform an LLA,REFRESH, and reload the failing module using the OS/EM ISPF RELOAD facility. Contact OS/EM support for assistance in problem resolution.

FEMIPL216

ABEND AREGS 12-13: nnnnnnnnnnnnnnnn nnnnnnnnnnnnnnnn

Explanation: The OS/EM has detected a MVS System Abend during execution of an OS/EM optional function or a User exit. This message applies to z/OS environments operating in 64-bit mode.

nnnnnnnnnnnnnnnn: Contents of the General Purpose Register.

Source: FEMIPL1

System Action: The OS/EM function being executed continues, OS/EM takes a SVC dump for the abending module, takes the abending module out of service, and deletes the abending module from CSA/ECSA. See messages FEMxxx023, FEMxxx026 and FEMxxx029.

Operator Response: Contact System Programmer.

System Programmer Response: Use IPCS to determine the cause for the ABEND, take the corrective action required, perform an LLA,REFRESH, and reload the failing module using the OS/EM ISPF RELOAD facility. Contact OS/EM support for assistance in problem resolution.

FEM2H5216

ABEND AREGS 12-13: nnnnnnnnnnnnnnnnnn nnnnnnnnnnnnnnnnnn

Explanation: The OS/EM has detected a MVS System Abend during execution of an OS/EM optional function or a User exit. This message applies to z/OS environments operating in 64-bit mode.

nnnnnnnnnnnnnnnnnn: Contents of the General Purpose Register.

Source: FEMJ2H5x

System Action: The OS/EM function being executed continues, OS/EM takes a SVC dump for the abending module, takes the abending module out of service, and deletes the abending module from CSA/ECSA. See messages FEMxxx023, FEMxxx026 and FEMxxx029.

Operator Response: Contact System Programmer.

System Programmer Response: Use IPCS to determine the cause for the ABEND, take the corrective action required, perform an LLA,REFRESH, and reload the failing module using the OS/EM ISPF RELOAD facility. Contact OS/EM support for assistance in problem resolution.

FEM2P4216

ABEND AREGS 12-13: nnnnnnnnnnnnnnnnnn nnnnnnnnnnnnnnnnnn

Explanation: The OS/EM has detected a MVS System Abend during execution of an OS/EM optional function or a User exit. This message applies to z/OS environments operating in 64-bit mode.

nnnnnnnnnnnnnnnnnn: Contents of the General Purpose Register.

Source: FEMJ2P4x

System Action: The OS/EM function being executed continues, OS/EM takes a SVC dump for the abending module, takes the abending module out of service, and deletes the abending module from CSA/ECSA. See messages FEMxxx023, FEMxxx026 and FEMxxx029.

Operator Response: Contact System Programmer.

System Programmer Response: Use IPCS to determine the cause for the ABEND, take the corrective action required, perform an LLA,REFRESH, and reload the failing module using the OS/EM ISPF RELOAD facility. Contact OS/EM support for assistance in problem resolution.

FEMACN217

ABEND AREGS 14-15: nnnnnnnnnnnnnnnnnn nnnnnnnnnnnnnnnnnn

Explanation: The OS/EM has detected a MVS System Abend during execution of an OS/EM optional function or a User exit. This message applies to z/OS environments operating in 64-bit mode.

nnnnnnnnnnnnnnnnnn: Contents of the General Purpose Register.

Source: FEMALCCN

System Action: The OS/EM function being executed continues, OS/EM takes a SVC dump for the abending module, takes the abending module out of service, and deletes the abending module from CSA/ECSA. See messages FEMxxx023, FEMxxx026 and FEMxxx029.

Operator Response: Contact System Programmer.

System Programmer Response: Use IPCS to determine the cause for the ABEND, take the corrective action required, perform an LLA,REFRESH, and reload the failing module using the OS/EM ISPF RELOAD facility. Contact OS/EM support for assistance in problem resolution.

FEMALC217

ABEND AREGS 14-15: nnnnnnnnnnnnnnnn nnnnnnnnnnnnnnnn

Explanation: The OS/EM has detected a MVS System Abend during execution of an OS/EM optional function or a User exit. This message applies to z/OS environments operating in 64-bit mode.

nnnnnnnnnnnnnnnn: Contents of the General Purpose Register.

Source: FEMALLO0,FEMALLO1

System Action: The OS/EM function being executed continues, OS/EM takes a SVC dump for the abending module, takes the abending module out of service, and deletes the abending module from CSA/ECSA. See messages FEMxxx023, FEMxxx026 and FEMxxx029.

Operator Response: Contact System Programmer.

System Programmer Response: Use IPCS to determine the cause for the ABEND, take the corrective action required, perform an LLA,REFRESH, and reload the failing module using the OS/EM ISPF RELOAD facility. Contact OS/EM support for assistance in problem resolution.

FEMASY217

ABEND AREGS 14-15: nnnnnnnnnnnnnnnn nnnnnnnnnnnnnnnn

Explanation: The OS/EM has detected a MVS System Abend during execution of an OS/EM optional function or a User exit. This message applies to z/OS environments operating in 64-bit mode.

nnnnnnnnnnnnnnnn: Contents of the General Purpose Register.

Source: FEMASYNC

System Action: The OS/EM function being executed continues, OS/EM takes a SVC dump for the abending module, takes the abending module out of service, and deletes the abending module from CSA/ECSA. See messages FEMxxx023, FEMxxx026 and FEMxxx029.

Operator Response: Contact System Programmer.

System Programmer Response: Use IPCS to determine the cause for the ABEND, take the corrective action required, perform an LLA,REFRESH, and reload the failing module using the OS/EM ISPF RELOAD facility. Contact OS/EM support for assistance in problem resolution.

FEMCMD217

ABEND AREGS 14-15: nnnnnnnnnnnnnnnn nnnnnnnnnnnnnnnn

Explanation: The OS/EM has detected a MVS System Abend during execution of an OS/EM optional function or a User exit. This message applies to z/OS environments operating in 64-bit mode.

nnnnnnnnnnnnnnnn: Contents of the General Purpose Register.

Source: FEMCMD

System Action: The OS/EM function being executed continues, OS/EM takes a SVC dump for the abending module, takes the abending module out of service, and deletes the abending module from CSA/ECSA. See messages FEMxxx023, FEMxxx026 and FEMxxx029.

Operator Response: Contact System Programmer.

System Programmer Response: Use IPCS to determine the cause for the ABEND, take the corrective action required, perform an LLA,REFRESH, and reload the failing module using the OS/EM ISPF RELOAD facility. Contact OS/EM support for assistance in problem resolution.

FEMCOM217

ABEND AREGS 14-15: nnnnnnnnnnnnnnnn nnnnnnnnnnnnnnnn

Explanation: The OS/EM has detected a MVS System Abend during execution of an OS/EM optional function or a User exit. This message applies to z/OS environments operating in 64-bit mode.

nnnnnnnnnnnnnnnn: Contents of the General Purpose Register.

Source: FEMCOMM

System Action: The OS/EM function being executed continues, OS/EM takes a SVC dump for the abending module, takes the abending module out of service, and deletes the abending module from CSA/ECSA. See messages FEMxxx023, FEMxxx026 and FEMxxx029.

Operator Response: Contact System Programmer.

System Programmer Response: Use IPCS to determine the cause for the ABEND, take the corrective action required, perform an LLA,REFRESH, and reload the failing module using the OS/EM ISPF RELOAD facility. Contact OS/EM support for assistance in problem resolution.

FEMDCN217

ABEND AREGS 14-15: nnnnnnnnnnnnnnnn nnnnnnnnnnnnnnnn

Explanation: The OS/EM has detected a MVS System Abend during execution of an OS/EM optional function or a User exit. This message applies to z/OS environments operating in 64-bit mode.

nnnnnnnnnnnnnnnn: Contents of the General Purpose Register.

Source: FEMDADCN

System Action: The OS/EM function being executed continues, OS/EM takes a SVC dump for the abending module, takes the abending module out of service, and deletes the abending module from CSA/ECSA. See messages FEMxxx023, FEMxxx026 and FEMxxx029.

Operator Response: Contact System Programmer.

System Programmer Response: Use IPCS to determine the cause for the ABEND, take the corrective action required, perform an LLA,REFRESH, and reload the failing module using the OS/EM ISPF RELOAD facility. Contact OS/EM support for assistance in problem resolution.

FEMDC1217

ABEND AREGS 14-15: nnnnnnnnnnnnnnnn nnnnnnnnnnnnnnnn

Explanation: The OS/EM has detected a MVS System Abend during execution of an OS/EM optional function or a User exit. This message applies to z/OS environments operating in 64-bit mode.

nnnnnnnnnnnnnnnn: Contents of the General Purpose Register.

Source: FEMDCB1

System Action: The OS/EM function being executed continues, OS/EM takes a SVC dump for the abending module, takes the abending module out of service, and deletes the abending module from CSA/ECSA. See messages FEMxxx023, FEMxxx026 and FEMxxx029.

Operator Response: Contact System Programmer.

System Programmer Response: Use IPCS to determine the cause for the ABEND, take the corrective action required, perform an LLA,REFRESH, and reload the failing module using the OS/EM ISPF RELOAD facility. Contact OS/EM support for assistance in problem resolution.

FEMEXR217

ABEND AREGS 14-15: nnnnnnnnnnnnnnnn nnnnnnnnnnnnnnnn

Explanation: The OS/EM has detected a MVS System Abend during execution of an OS/EM optional function or a User exit. This message applies to z/OS environments operating in 64-bit mode.

nnnnnnnnnnnnnnnn: Contents of the General Purpose Register.

Source: FEMEXRTN

System Action: The OS/EM function being executed continues, OS/EM takes a SVC dump for the abending module, takes the abending module out of service, and deletes the abending module from CSA/ECSA. See messages FEMxxx023, FEMxxx026 and FEMxxx029.

Operator Response: Contact System Programmer.

System Programmer Response: Use IPCS to determine the cause for the ABEND, take the corrective action required, perform an LLA,REFRESH, and reload the failing module using the OS/EM ISPF RELOAD facility. Contact OS/EM support for assistance in problem resolution.

FEMFRA217

ABEND AREGS 14-15: nnnnnnnnnnnnnnnn nnnnnnnnnnnnnnnn

Explanation: The OS/EM has detected a MVS System Abend during execution of an OS/EM optional function or a User exit. This message applies to z/OS environments operating in 64-bit mode.

nnnnnnnnnnnnnnnn: Contents of the General Purpose Register.

Source: FEMFRACN

System Action: The OS/EM function being executed continues, OS/EM takes a SVC dump for the abending module, takes the abending module out of service, and deletes the abending module from CSA/ECSA. See messages FEMxxx023, FEMxxx026 and FEMxxx029.

Operator Response: Contact System Programmer.

System Programmer Response: Use IPCS to determine the cause for the ABEND, take the corrective action required, perform an LLA,REFRESH, and reload the failing module using the OS/EM ISPF RELOAD facility. Contact OS/EM support for assistance in problem resolution.

FEMFTN217

ABEND AREGS 14-15: nnnnnnnnnnnnnnnn nnnnnnnnnnnnnnnn

Explanation: The OS/EM has detected a MVS System Abend during execution of an OS/EM optional function or a User exit. This message applies to z/OS environments operating in 64-bit mode.

nnnnnnnnnnnnnnnn: Contents of the General Purpose Register.

Source: FEMFRRTN

System Action: The OS/EM function being executed continues, OS/EM takes a SVC dump for the abending module, takes the abending module out of service, and deletes the abending module from CSA/ECSA. See messages FEMxxx023, FEMxxx026 and FEMxxx029.

Operator Response: Contact System Programmer.

System Programmer Response: Use IPCS to determine the cause for the ABEND, take the corrective action required, perform an LLA,REFRESH, and reload the failing module using the OS/EM ISPF RELOAD facility. Contact OS/EM support for assistance in problem resolution.

FEMHCN217

ABEND AREGS 14-15: nnnnnnnnnnnnnnnnnn nnnnnnnnnnnnnnnnnn

Explanation: The OS/EM has detected a MVS System Abend during execution of an OS/EM optional function or a User exit. This message applies to z/OS environments operating in 64-bit mode.

nnnnnnnnnnnnnnnnnn: Contents of the General Purpose Register.

Source: FEMHSMCN

System Action: The OS/EM function being executed continues, OS/EM takes a SVC dump for the abending module, takes the abending module out of service, and deletes the abending module from CSA/ECSA. See messages FEMxxx023, FEMxxx026 and FEMxxx029.

Operator Response: Contact System Programmer.

System Programmer Response: Use IPCS to determine the cause for the ABEND, take the corrective action required, perform an LLA,REFRESH, and reload the failing module using the OS/EM ISPF RELOAD facility. Contact OS/EM support for assistance in problem resolution.

FEMHSP217

ABEND AREGS 14-15: nnnnnnnnnnnnnnnnnn nnnnnnnnnnnnnnnnnn

Explanation: The OS/EM has detected a MVS System Abend during execution of an OS/EM optional function or a User exit. This message applies to z/OS environments operating in 64-bit mode.

nnnnnnnnnnnnnnnnnn: Contents of the General Purpose Register.

Source: FEMHJ20

System Action: The OS/EM function being executed continues, OS/EM takes a SVC dump for the abending module, takes the abending module out of service, and deletes the abending module from CSA/ECSA. See messages FEMxxx023, FEMxxx026 and FEMxxx029.

Operator Response: Contact System Programmer.

System Programmer Response: Use IPCS to determine the cause for the ABEND, take the corrective action required, perform an LLA,REFRESH, and reload the failing module using the OS/EM ISPF RELOAD facility. Contact OS/EM support for assistance in problem resolution.

FEMIAT217

ABEND AREGS 14-15: nnnnnnnnnnnnnnnnnn nnnnnnnnnnnnnnnnnn

Explanation: The OS/EM has detected a MVS System Abend during execution of an OS/EM optional function or a User exit. This message applies to z/OS environments operating in 64-bit mode.

nnnnnnnnnnnnnnnnnn: Contents of the General Purpose Register.

Source: FEMINTK

System Action: The OS/EM function being executed continues, OS/EM takes a SVC dump for the abending module, takes the abending module out of service, and deletes the abending module from CSA/ECSA. See messages FEMxxx023, FEMxxx026 and FEMxxx029.

Operator Response: Contact System Programmer.

System Programmer Response: Use IPCS to determine the cause for the ABEND, take the corrective action required, perform an LLA,REFRESH, and reload the failing module using the OS/EM ISPF RELOAD facility. Contact OS/EM support for assistance in problem resolution.

FEMJ2M217

ABEND AREGS 14-15: nnnnnnnnnnnnnnnn nnnnnnnnnnnnnnnn

Explanation: The OS/EM has detected a MVS System Abend during execution of an OS/EM optional function or a User exit. This message applies to z/OS environments operating in 64-bit mode.

nnnnnnnnnnnnnnnn: Contents of the General Purpose Register.

Source: FEMJ2MCx

System Action: The OS/EM function being executed continues, OS/EM takes a SVC dump for the abending module, takes the abending module out of service, and deletes the abending module from CSA/ECSA. See messages FEMxxx023, FEMxxx026 and FEMxxx029.

Operator Response: Contact System Programmer.

System Programmer Response: Use IPCS to determine the cause for the ABEND, take the corrective action required, perform an LLA,REFRESH, and reload the failing module using the OS/EM ISPF RELOAD facility. Contact OS/EM support for assistance in problem resolution.

FEMJ2R217

ABEND AREGS 14-15: nnnnnnnnnnnnnnnn nnnnnnnnnnnnnnnn

Explanation: The OS/EM has detected a MVS System Abend during execution of an OS/EM optional function or a User exit. This message applies to z/OS environments operating in 64-bit mode.

nnnnnnnnnnnnnnnn: Contents of the General Purpose Register.

Source: FEMJ2ERx

System Action: The OS/EM function being executed continues, OS/EM takes a SVC dump for the abending module, takes the abending module out of service, and deletes the abending module from CSA/ECSA. See messages FEMxxx023, FEMxxx026 and FEMxxx029.

Operator Response: Contact System Programmer.

System Programmer Response: Use IPCS to determine the cause for the ABEND, take the corrective action required, perform an LLA,REFRESH, and reload the failing module using the OS/EM ISPF RELOAD facility. Contact OS/EM support for assistance in problem resolution.

FEMJ2S217

ABEND AREGS 14-15: nnnnnnnnnnnnnnnn nnnnnnnnnnnnnnnn

Explanation: The OS/EM has detected a MVS System Abend during execution of an OS/EM optional function or a User exit. This message applies to z/OS environments operating in 64-bit mode.

nnnnnnnnnnnnnnnn: Contents of the General Purpose Register.

Source: FEMJ2SCx

System Action: The OS/EM function being executed continues, OS/EM takes a SVC dump for the abending module, takes the abending module out of service, and deletes the abending module from CSA/ECSA. See messages FEMxxx023, FEMxxx026 and FEMxxx029.

Operator Response: Contact System Programmer.

System Programmer Response: Use IPCS to determine the cause for the ABEND, take the corrective action required, perform an LLA,REFRESH, and reload the failing module using the OS/EM ISPF RELOAD facility. Contact OS/EM support for assistance in problem resolution.

FEMJ3E217

ABEND AREGS 14-15: nnnnnnnnnnnnnnnn nnnnnnnnnnnnnnnn

Explanation: The OS/EM has detected a MVS System Abend during execution of an OS/EM optional function or a User exit. This message applies to z/OS environments operating in 64-bit mode.

nnnnnnnnnnnnnnnn: Contents of the General Purpose Register.

Source: FEMJ3ECN

System Action: The OS/EM function being executed continues, OS/EM takes a SVC dump for the abending module, takes the abending module out of service, and deletes the abending module from CSA/ECSA. See messages FEMxxx023, FEMxxx026 and FEMxxx029.

Operator Response: Contact System Programmer.

System Programmer Response: Use IPCS to determine the cause for the ABEND, take the corrective action required, perform an LLA,REFRESH, and reload the failing module using the OS/EM ISPF RELOAD facility. Contact OS/EM support for assistance in problem resolution.

FEMJ3S217

ABEND AREGS 14-15: nnnnnnnnnnnnnnnn nnnnnnnnnnnnnnnn

Explanation: The OS/EM has detected a MVS System Abend during execution of an OS/EM optional function or a User exit. This message applies to z/OS environments operating in 64-bit mode.

nnnnnnnnnnnnnnnn: Contents of the General Purpose Register.

Source: FEMJ3SVC

System Action: The OS/EM function being executed continues, OS/EM takes a SVC dump for the abending module, takes the abending module out of service, and deletes the abending module from CSA/ECSA. See messages FEMxxx023, FEMxxx026 and FEMxxx029.

Operator Response: Contact System Programmer.

System Programmer Response: Use IPCS to determine the cause for the ABEND, take the corrective action required, perform an LLA,REFRESH, and reload the failing module using the OS/EM ISPF RELOAD facility. Contact OS/EM support for assistance in problem resolution.

FEMLOK217

ABEND AREGS 14-15: nnnnnnnnnnnnnnnn nnnnnnnnnnnnnnnn

Explanation: The OS/EM has detected a MVS System Abend during execution of an OS/EM optional function or a User exit. This message applies to z/OS environments operating in 64-bit mode.

nnnnnnnnnnnnnnnn: Contents of the General Purpose Register.

Source: FEMLOCK

System Action: The OS/EM function being executed continues, OS/EM takes a SVC dump for the abending module, takes the abending module out of service, and deletes the abending module from CSA/ECSA. See messages FEMxxx023, FEMxxx026 and FEMxxx029.

Operator Response: Contact System Programmer.

System Programmer Response: Use IPCS to determine the cause for the ABEND, take the corrective action required, perform an LLA,REFRESH, and reload the failing module using the OS/EM ISPF RELOAD facility. Contact OS/EM support for assistance in problem resolution.

FEMRCN217

ABEND AREGS 14-15: nnnnnnnnnnnnnnnn nnnnnnnnnnnnnnnn

Explanation: The OS/EM has detected a MVS System Abend during execution of an OS/EM optional function or a User exit. This message applies to z/OS environments operating in 64-bit mode.

nnnnnnnnnnnnnnnn: Contents of the General Purpose Register.

Source: FEMRACCN

System Action: The OS/EM function being executed continues, OS/EM takes a SVC dump for the abending module, takes the abending module out of service, and deletes the abending module from CSA/ECSA. See messages FEMxxx023, FEMxxx026 and FEMxxx029.

Operator Response: Contact System Programmer.

System Programmer Response: Use IPCS to determine the cause for the ABEND, take the corrective action required, perform an LLA,REFRESH, and reload the failing module using the OS/EM ISPF RELOAD facility. Contact OS/EM support for assistance in problem resolution.

FEMSCN217

ABEND AREGS 14-15: nnnnnnnnnnnnnnnn nnnnnnnnnnnnnnnn

Explanation: The OS/EM has detected a MVS System Abend during execution of an OS/EM optional function or a User exit. This message applies to z/OS environments operating in 64-bit mode.

nnnnnnnnnnnnnnnn: Contents of the General Purpose Register.

Source: FEMSAFCN,FEMSMFCN

System Action: The OS/EM function being executed continues, OS/EM takes a SVC dump for the abending module, takes the abending module out of service, and deletes the abending module from CSA/ECSA. See messages FEMxxx023, FEMxxx026 and FEMxxx029.

Operator Response: Contact System Programmer.

System Programmer Response: Use IPCS to determine the cause for the ABEND, take the corrective action required, perform an LLA,REFRESH, and reload the failing module using the OS/EM ISPF RELOAD facility. Contact OS/EM support for assistance in problem resolution.

FEMTCN217

ABEND AREGS 14-15: nnnnnnnnnnnnnnnn nnnnnnnnnnnnnnnn

Explanation: The OS/EM has detected a MVS System Abend during execution of an OS/EM optional function or a User exit. This message applies to z/OS environments operating in 64-bit mode.

nnnnnnnnnnnnnnnn: Contents of the General Purpose Register.

Source: FEMTSOCN

System Action: The OS/EM function being executed continues, OS/EM takes a SVC dump for the abending module, takes the abending module out of service, and deletes the abending module from CSA/ECSA. See messages FEMxxx023, FEMxxx026 and FEMxxx029.

Operator Response: Contact System Programmer.

System Programmer Response: Use IPCS to determine the cause for the ABEND, take the corrective action required, perform an LLA,REFRESH, and reload the failing module using the OS/EM ISPF RELOAD facility. Contact OS/EM support for assistance in problem resolution.

FEMTPS217

ABEND AREGS 14-15: nnnnnnnnnnnnnnnnnn nnnnnnnnnnnnnnnnnn

Explanation: The OS/EM has detected a MVS System Abend during execution of an OS/EM optional function or a User exit. This message applies to z/OS environments operating in 64-bit mode.

nnnnnnnnnnnnnnnnnn: Contents of the General Purpose Register.

Source: FEMTPSHR

System Action: The OS/EM function being executed continues, OS/EM takes a SVC dump for the abending module, takes the abending module out of service, and deletes the abending module from CSA/ECSA. See messages FEMxxx023, FEMxxx026 and FEMxxx029.

Operator Response: Contact System Programmer.

System Programmer Response: Use IPCS to determine the cause for the ABEND, take the corrective action required, perform an LLA,REFRESH, and reload the failing module using the OS/EM ISPF RELOAD facility. Contact OS/EM support for assistance in problem resolution.

FEMUJI217

ABEND AREGS 14-15: nnnnnnnnnnnnnnnnnn nnnnnnnnnnnnnnnnnn

Explanation: The OS/EM has detected a MVS System Abend during execution of an OS/EM optional function or a User exit. This message applies to z/OS environments operating in 64-bit mode.

nnnnnnnnnnnnnnnnnn: Contents of the General Purpose Register.

Source: FEMUJI

System Action: The OS/EM function being executed continues, OS/EM takes a SVC dump for the abending module, takes the abending module out of service, and deletes the abending module from CSA/ECSA. See messages FEMxxx023, FEMxxx026 and FEMxxx029.

Operator Response: Contact System Programmer.

System Programmer Response: Use IPCS to determine the cause for the ABEND, take the corrective action required, perform an LLA,REFRESH, and reload the failing module using the OS/EM ISPF RELOAD facility. Contact OS/EM support for assistance in problem resolution.

FEMUSI217

ABEND AREGS 14-15: nnnnnnnnnnnnnnnnnn nnnnnnnnnnnnnnnnnn

Explanation: The OS/EM has detected a MVS System Abend during execution of an OS/EM optional function or a User exit. This message applies to z/OS environments operating in 64-bit mode.

nnnnnnnnnnnnnnnnnn: Contents of the General Purpose Register.

Source: FEMUSI

System Action: The OS/EM function being executed continues, OS/EM takes a SVC dump for the abending module, takes the abending module out of service, and deletes the abending module from CSA/ECSA. See messages FEMxxx023, FEMxxx026 and FEMxxx029.

Operator Response: Contact System Programmer.

System Programmer Response: Use IPCS to determine the cause for the ABEND, take the corrective action required, perform an LLA,REFRESH, and reload the failing module using the OS/EM ISPF RELOAD facility. Contact OS/EM support for assistance in problem resolution.

FEM1PL217

ABEND AREGS 14-15: nnnnnnnnnnnnnnnn nnnnnnnnnnnnnnnn

Explanation: The OS/EM has detected a MVS System Abend during execution of an OS/EM optional function or a User exit. This message applies to z/OS environments operating in 64-bit mode.

nnnnnnnnnnnnnnnnn: Contents of the General Purpose Register.

Source: FEM1PL1

System Action: The OS/EM function being executed continues, OS/EM takes a SVC dump for the abending module, takes the abending module out of service, and deletes the abending module from CSA/ECSA. See messages FEMxxx023, FEMxxx026 and FEMxxx029.

Operator Response: Contact System Programmer.

System Programmer Response: Use IPCS to determine the cause for the ABEND, take the corrective action required, perform an LLA,REFRESH, and reload the failing module using the OS/EM ISPF RELOAD facility. Contact OS/EM support for assistance in problem resolution.

FEM2H5217

ABEND AREGS 14-15: nnnnnnnnnnnnnnnn nnnnnnnnnnnnnnnn

Explanation: The OS/EM has detected a MVS System Abend during execution of an OS/EM optional function or a User exit. This message applies to z/OS environments operating in 64-bit mode.

nnnnnnnnnnnnnnnnn: Contents of the General Purpose Register.

Source: FEMJ2H5x

System Action: The OS/EM function being executed continues, OS/EM takes a SVC dump for the abending module, takes the abending module out of service, and deletes the abending module from CSA/ECSA. See messages FEMxxx023, FEMxxx026 and FEMxxx029.

Operator Response: Contact System Programmer.

System Programmer Response: Use IPCS to determine the cause for the ABEND, take the corrective action required, perform an LLA,REFRESH, and reload the failing module using the OS/EM ISPF RELOAD facility. Contact OS/EM support for assistance in problem resolution.

FEM2P4217

ABEND AREGS 14-15: nnnnnnnnnnnnnnnn nnnnnnnnnnnnnnnn

Explanation: The OS/EM has detected a MVS System Abend during execution of an OS/EM optional function or a User exit. This message applies to z/OS environments operating in 64-bit mode.

nnnnnnnnnnnnnnnnn: Contents of the General Purpose Register.

Source: FEMJ2P4x

System Action: The OS/EM function being executed continues, OS/EM takes a SVC dump for the abending module, takes the abending module out of service, and deletes the abending module from CSA/ECSA. See messages FEMxxx023, FEMxxx026 and FEMxxx029.

Operator Response: Contact System Programmer.

System Programmer Response: Use IPCS to determine the cause for the ABEND, take the corrective action required, perform an LLA,REFRESH, and reload the failing module using the OS/EM ISPF RELOAD facility. Contact OS/EM support for assistance in problem resolution.

FEMACT218

DSN=xxxx.xxxx.xxxx DELETED BY OS/EM QUICKDELETE

Explanation: A migrated dataset has been deleted by the OS/EM Quickdelete function.

xxxx.xxxx.xxxx: The deleted dataset name.

Source: FEMACTRT

System Action: None. Informational message only.

Operator Response: None.

System Programmer Response: None.

FEMB14218

DSN=xxxx.xxxx.xxxx DELETED BY OS/EM QUICKDELETE

Explanation: A migrated dataset has been deleted by the OS/EM Quickdelete function.

xxxx.xxxx.xxxx: The deleted dataset name.

Source: FEMBR14

System Action: None. Informational message only.

Operator Response: None.

System Programmer Response: None.

FEM IPL219

req MACRO/SERVICE FAILED, RC= rc REAS = rsn

Explanation: A macro or service request failed.

req: The name of the macro or service.

rc: The return code.

rsn: The reason code.

Source: FEM IPL

System Action: The OS/EM function is terminated.

Operator Response: Notify the Systems Programmer.

System Programmer Response: Contact OS/EM Technical Support.

FEMX06219

req MACRO/SERVICE FAILED, RC= rc REAS = rsn

Explanation: A macro or service request failed.

req: The name of the macro or service.

rc: The return code.

rsn: The reason code.

Source: FEMJ2X06

System Action: The OS/EM function is terminated.

Operator Response: Notify the Systems Programmer.

System Programmer Response: Contact OS/EM Technical Support.

FEMX44219

req MACRO/SERVICE FAILED, RC= rc REAS = rsn

Explanation: A macro or service request failed.

req: The name of the macro or service.

rc: The return code.

rsn: The reason code.

Source: FEMJ2X44

System Action: The OS/EM function is terminated.

Operator Response: Notify the Systems Programmer.

System Programmer Response: Contact OS/EM Technical Support.

FEMACN220

OS/EM LOAD LIBRARY INCORRECT FOR PROCESSOR MODE

Explanation: The OS/EM load library defined in the LINKLST is not supported by the current system addressing mode. For example, your environment uses 31-bit addressing and the LINKLST points to the 64-bit load library.

Source: FEMALCCN

System Action: The OS/EM function is terminated.

Operator Response: Notify the Systems Programmer.

System Programmer Response: Correct the LINKLST definition to point to the correct OS/EM load library. Using OS/EM distribution naming conventions, LOAD1 is the 31-bit mode load library, LOAD2 is the 64-bit mode load library.

FEMDCN220

OS/EM LOAD LIBRARY INCORRECT FOR PROCESSOR MODE

Explanation: The OS/EM load library defined in the LINKLST is not supported by the current system addressing mode. For example, your environment uses 31-bit addressing and the LINKLST points to the 64-bit load library.

Source: FEMDADCN

System Action: The OS/EM function is terminated.

Operator Response: Notify the Systems Programmer.

System Programmer Response: Correct the LINKLST definition to point to the correct OS/EM load library. Using OS/EM distribution naming conventions, LOAD1 is the 31-bit mode load library, LOAD2 is the 64-bit mode load library.

FEMFRA220

OS/EM LOAD LIBRARY INCORRECT FOR PROCESSOR MODE

Explanation: The OS/EM load library defined in the LINKLST is not supported by the current system addressing mode. For example, your environment uses 31-bit addressing and the LINKLST points to the 64-bit load library.

Source: FEMFRACN

System Action: The OS/EM function is terminated.

Operator Response: Notify the Systems Programmer.

System Programmer Response: Correct the LINKLST definition to point to the correct OS/EM load library. Using OS/EM distribution naming conventions, LOAD1 is the 31-bit mode load library, LOAD2 is the 64-bit mode load library.

FEMHCN220

OS/EM LOAD LIBRARY INCORRECT FOR PROCESSOR MODE

Explanation: The OS/EM load library defined in the LINKLST is not supported by the current system addressing mode. For example, your environment uses 31-bit addressing and the LINKLST points to the 64-bit load library.

Source: FEMHSMCN

System Action: The OS/EM function is terminated.

Operator Response: Notify the Systems Programmer.

System Programmer Response: Correct the LINKLST definition to point to the correct OS/EM load library. Using OS/EM distribution naming conventions, LOAD1 is the 31-bit mode load library, LOAD2 is the 64-bit mode load library.

FEMHSP220

OS/EM LOAD LIBRARY INCORRECT FOR PROCESSOR MODE

Explanation: The OS/EM load library defined in the LINKLST is not supported by the current system addressing mode. For example, your environment uses 31-bit addressing and the LINKLST points to the 64-bit load library.

Source: FEMHJ20

System Action: The OS/EM function is terminated.

Operator Response: Notify the Systems Programmer.

System Programmer Response: Correct the LINKLST definition to point to the correct OS/EM load library. Using OS/EM distribution naming conventions, LOAD1 is the 31-bit mode load library, LOAD2 is the 64-bit mode load library.

FEMICN220

OS/EM LOAD LIBRARY INCORRECT FOR PROCESSOR MODE

Explanation: The OS/EM load library defined in the LINKLST is not supported by the current system addressing mode. For example, your environment uses 31-bit addressing and the LINKLST points to the 64-bit load library.

Source: FEMISPCN

System Action: The OS/EM function is terminated.

Operator Response: Notify the Systems Programmer.

System Programmer Response: Correct the LINKLST definition to point to the correct OS/EM load library. Using OS/EM distribution naming conventions, LOAD1 is the 31-bit mode load library, LOAD2 is the 64-bit mode load library.

FEMIPL220

OS/EM LOAD LIBRARY INCORRECT FOR PROCESSOR MODE

Explanation: The OS/EM load library defined in the LINKLST is not supported by the current system addressing mode. For example, your environment uses 31-bit addressing and the LINKLST points to the 64-bit load library.

Source: FEMIPL

System Action: The OS/EM function is terminated.

Operator Response: Notify the Systems Programmer.

System Programmer Response: Correct the LINKLST definition to point to the correct OS/EM load library. Using OS/EM distribution naming conventions, LOAD1 is the 31-bit mode load library, LOAD2 is the 64-bit mode load library.

FEMLIB220

OS/EM LOAD LIBRARY INCORRECT FOR PROCESSOR MODE

Explanation: The OS/EM load library defined in the LINKLST is not supported by the current system addressing mode. For example, your environment uses 31-bit addressing and the LINKLST points to the 64-bit load library.

Source: FEMLIB

System Action: The OS/EM function is terminated.

Operator Response: Notify the Systems Programmer.

System Programmer Response: Correct the LINKLST definition to point to the correct OS/EM load library. Using OS/EM distribution naming conventions, LOAD1 is the 31-bit mode load library, LOAD2 is the 64-bit mode load library.

FEMRCN220

OS/EM LOAD LIBRARY INCORRECT FOR PROCESSOR MODE

Explanation: The OS/EM load library defined in the LINKLST is not supported by the current system addressing mode. For example, your environment uses 31-bit addressing and the LINKLST points to the 64-bit load library.

Source: FEMRACCN

System Action: The OS/EM function is terminated.

Operator Response: Notify the Systems Programmer.

System Programmer Response: Correct the LINKLST definition to point to the correct OS/EM load library. Using OS/EM distribution naming conventions, LOAD1 is the 31-bit mode load library, LOAD2 is the 64-bit mode load library.

FEMSCN220

OS/EM LOAD LIBRARY INCORRECT FOR PROCESSOR MODE

Explanation: The OS/EM load library defined in the LINKLST is not supported by the current system addressing mode. For example, your environment uses 31-bit addressing and the LINKLST points to the 64-bit load library.

Source: FEMSAFCN,FEMSMFCN

System Action: The OS/EM function is terminated.

Operator Response: Notify the Systems Programmer.

System Programmer Response: Correct the LINKLST definition to point to the correct OS/EM load library. Using OS/EM distribution naming conventions, LOAD1 is the 31-bit mode load library, LOAD2 is the 64-bit mode load library.

FEMTCN220

OS/EM LOAD LIBRARY INCORRECT FOR PROCESSOR MODE

Explanation: The OS/EM load library defined in the LINKLST is not supported by the current system addressing mode. For example, your environment uses 31-bit addressing and the LINKLST points to the 64-bit load library.

Source: FEMTSOCN

System Action: The OS/EM function is terminated.

Operator Response: Notify the Systems Programmer.

System Programmer Response: Correct the LINKLST definition to point to the correct OS/EM load library. Using OS/EM distribution naming conventions, LOAD1 is the 31-bit mode load library, LOAD2 is the 64-bit mode load library.

FEMX06222

TIME PARAMETER MUST MATCH JES2 FOR THIS CLASS

Explanation: OS/EM Job Time Controls has been activated and a job has one of the following attributes:

- TIME=MAXIMUM is specified
- TIME=NOLIMIT is specified
- The TIME= value is greater than the JES2 value for this jobclass

Source: FEMJ2X06

System Action: If the Cancel Option is set to **YES** in Job Time Controls, the job is flushed. If the Cancel Option is set to **NO**, the TIME= value is reset to the maximum value set in JES2 for that jobclass.

Operator Response: Correct the TIME= value for the job to avoid warning messages or to allow the job to execute.

System Programmer Response: None.

FEMX09223

SYSOUT LIMIT FOR JOB jobname EXTENDED BY 99999 LINES/PAGES/BYTES.

Explanation: OS/EM has extended the number of lines/pages/bytes of sysout for the listed job.

Source: FEMJ2X09

Operator Response: None.

System Programmer Response: None.

FEMX09224

SHOULD SYSOUT LIMIT FOR JOB jobname BE EXTENDED BY 99999 LINES/PAGES/BYTES?

Explanation: Should OS/EM extend the sysout limit for the listed job?

Source: FEMJ2X09

Operator Response: Enter **Y** to allow the sysout extension or **N** to cancel the job.

System Programmer Response: None.

FEMHSP225

OS/EM FUNCTIONS WILL NOT BE AVAILABLE FOR THIS JES

Explanation: Errors occurred during the initialization of OS/EM JES2 services and so JES2 functions will not be available.

Source: FEMHJ20

System Action: OS/EM services continue without JES2 functionality.

Operator Response: Contact the systems programmer.

System Programmer Response: Look for other OS/EM messages that will indicate the source of the errors. If correction procedures are not evident contact OS/EM Technical Support.

FEMHSP226

OS/EM FUNCTIONS WILL BE IMPAIRED FOR THIS JES

Explanation: Errors occurred during the initialization of OS/EM JES2 services and certain JES2 functions will not be available.

Source: FEMHJ20

System Action: OS/EM services continue without some JES2 functionality.

Operator Response: Contact the systems programmer.

System Programmer Response: Look for other OS/EM messages that will indicate the source of the errors. If correction procedures are not evident contact OS/EM Technical support.

FEMX24226

OS/EM FUNCTIONS WILL BE IMPAIRED FOR THIS JES

Explanation: Errors occurred during the initialization of OS/EM JES2 services and certain JES2 functions will not be available.

Source: FEMJ2X24

System Action: OS/EM services continue without some JES2 functionality.

Operator Response: Contact the systems programmer.

System Programmer Response: Look for other OS/EM messages that will indicate the source of the errors. If correction procedures are not evident contact OS/EM Technical support.

FEMX00227

TOO MANY OS/EM type EXIT name ROUTINES

Explanation: The specified exit has more than 255 exit points defined to OS/EM.

type: The exit type.

name: The exit name.

Source: FEMJ2X00

System Action: Exit processing continues. The 256th and subsequent entries for the exit are ignored.

Operator Response: Contact the systems programmer.

System Programmer Response: Review the exit definitions for this exit point. It may be necessary to consolidate functionality into a single user exit to overcome the limitation.

FEM2TP227

TOO MANY OS/EM type EXIT name ROUTINES

Explanation: The specified exit has more than 255 exit points defined to OS/EM.

type: The exit type.

name: The exit name.

Source: FEMJ2TPx

System Action: Exit processing continues. The 256th and subsequent entries for the exit are ignored.

Operator Response: Contact the systems programmer.

System Programmer Response: Review the exit definitions for this exit point. It may be necessary to consolidate functionality into a single user exit to overcome the limitation.

FEMJS2228

COMMAND IGNORED - VALID RESOURCE DATASET REQUIRED.

Explanation: A valid dataset name for the Job Routing Resources has not been entered. No Job Routing commands can be processed.

Source: FEMJES2G

Operator Response: Notify System Programmer.

System Programmer Response: Enter a valid Job Routing Resource dataset.

FEMREL229

modname:entry ENABLED

Explanation: The user exit has been loaded and enabled.

Source: FEMRELOD

System Action: None. Informational message.

Operator Response: None.

System Programmer Response: None.

FEMX06230

JOB SCHENV CONVERTED TO OS/EM JOBRROUTE

Explanation: A Workload Manager scheduling environment was coded for this job and OS/EM has converted it to a Job Routing RESOURCE name.

Source: FEMJ2X06

Operator Response: None

System Programmer Response: None

FEMUSI232

CATALOG SEARCH FOR xxx FAILED. RC = n, RSN = n

Explanation: The QuickDelete function has done a catalog search for dataset 'xxx' and the catalog search has failed. QuickDelete will not try to process this dataset.

Source: FEMUSI

Operator Response: None

System Programmer Response: None

FEMACT233

ARCHDEL FOR datasetname FAILED. RC = nnnn

Explanation: The QuickDelete function has requested that DFSMSHSM delete the DSN 'datasetname', however DFSMSHSM was unable to process the request.

Source: FEMACTRT

Operator Response: Notify the System Programmer

System Programmer Response: Determine why DFSMSHSM was unable to process the delete request then resubmit the job.

FEMB14233

ARCHDEL FOR datasetname FAILED. RC = nnnn

Explanation: The QuickDelete function has requested that DFSMSHSM delete the DSN 'datasetname', however DFSMSHSM was unable to process the request.

Source: FEMBR14

Operator Response: Notify the System Programmer

System Programmer Response: Determine why DFSMSHSM was unable to process the delete request then resubmit the job.

FEMX06234

VALID TIME PARAMETER REQUIRED ON JOB CARD

Explanation: This job requires a valid time parameter on the jobcard.

Source: FEMJ2X06

Operator Response: Add a valid time parameter to the jobcard and resubmit the job.

System Programmer Response: None

FEM2TP235

OVER 254 ROUTINES FOR function EXIT name, LAST ROUTINE IGNORED

Explanation: Too many user exit routines have been defined in OS/EM for the specified exit point.

function - The functional group for the user exit (e.g. SMF, JES2).
name - The user exit point name.

Source: FEMJ2TP

System Action: The 255th and subsequent exit definitions are ignored.

Operator Response: None

System Programmer Response: Ensure that no more than 254 routines are defined for the user exit point (OS/EM Basic Exit Functions).

FEMREL236

module LOAD SUPPRESSED. UNABLE TO ACCESS jessys A.S. RSN = rescocode

Explanation: The specified module could not be loaded because the required JES2 address space could not be accessed.

module: The name of the load module that could not be loaded.
jessys: The subsystem name of the JES2 address space that could not be accessed.
rescocode: The reason code from the LOCASCB system request. Consult the MVS Programming: Authorized Assembler Services Reference for the reason code explanations.

Source: FEMRELOD

System Action: The specified module is not loaded.

Operator Response: Contact the Systems Programmer.

System Programmer Response: Correct the problem that is causing the JES2 system to be inaccessible.

FEM IPL237

OS/EM EXIT name NOT FOUND IN DYNAMIC LPA

Explanation: The specified OS/EM exit module was not located in the Dynamic Link Pack Area (LPA).

name: The name of the load module that could not be located.

Source: FEM IPL

System Action: OS/EM will not be initialized or will operate with limited functionality.

Operator Response: None

System Programmer Response: Verify that the load module is correctly defined to the IEALPAXX MVS initialization parameter member. Refer to the OS/EM Installation Guide and the MVS Initialization and Tuning Reference.

FEM IPL238

REMOVAL OF NULL EXIT module FROM EXITPOINT exit-name FAILED, CSVDYNEX RC = retcode RSN = rsncode

Explanation: OS/EM attempted to remove a null exit routine that was defined to a particular exit point, but the request failed.

module: The name of the load module that contained the null exit routine.

exit-name: The name of the exit.

retcode: The return code from the CSVDYNEX function request.

rsncode: The reason code from the CSVDYNEX function request.

Source: FEM IPL

System Action: OS/EM initialization continues. The user exit module is disabled but remains loaded.

Operator Response: None

System Programmer Response: Determine the reason for failure (consult the MVS Authorized Assembler Services Reference for the CSVDYNEX function). Also, it may be useful to disable and/or delete the null exit module from the exit definitions for future initializations of OS/EM (Basic Exit Functions).

FEM IPL239

{NULL | DUPLICATE} EXIT module REMOVED FROM EXITPOINT exit-name

Explanation: One of the following conditions occurred :

- OS/EM found a load module that was defined as a user exit routine but did no real processing (i.e. is a NULL or stub exit). The module was successfully removed from the exit list.
- A load module for the exit point name was defined to both MVS and OS/EM. The module was successfully removed from the MVS exit definition and placed under the control of OS/EM.

module: The name of the load module.

exit-name: The name of the exit.

Source: FEM IPL

Operator Response: None

System Programmer Response: To avoid this message, perform one of the following:

- For a NULL EXIT - remove or rename the exit module from the LNKLST / LPA library (for standard named exit modules). You may also have to remove the module definition from OS/EM exit definitions.
- For a DUPLICATE EXIT - remove the EXIT ADD statements from the PROGxx member in your MVS PARMLIB OR from the OS/EM exit module definitions. It is strongly recommended that the PROGxx EXIT definitions be removed so OS/EM will report and manage all exit modules.

FEM I PL 240

OS/EM EXIT module DEFINED TO EXITPOINT exit-name

Explanation: An OS/EM module has been successfully defined to the specified exit point.

module: The name of the OS/EM load module.

exit-name: The name of the exit point.

Source: FEM IPL

Operator Response: None

System Programmer Response: None

FEM JS 2241

subsys OS/EM function FUNCTION REQUESTED

Explanation: An OS/EM function has been requested for the specified JES2 subsystem name.

subsys: The name of the JES2 subsystem requesting the OS/EM functionality

function: The name of the OS/EM function being requested.

Source: FEM JES 2D,FEM JES 2F,FEM JES 2G

Operator Response: None

System Programmer Response: None

FEM 2D 0242

subsys OS/EM function INITIALIZATION STARTING

Explanation: The OS/EM function has begun initialization.

subsys: The name of the JES2 subsystem requesting the OS/EM functionality.

function: The name of the OS/EM function being initialized.

Source FEM J 2D 0x

Operator Response: None

System Programmer Response: None

FEM2H0242

subsys OS/EM function INITIALIZATION STARTING

Explanation: The OS/EM function has begun initialization.

subsys: The name of the JES2 subsystem requesting the OS/EM functionality.

function: The name of the OS/EM function being initialized.

Source FEMJ2H0x

Operator Response: None

System Programmer Response: None

FEM2L0242

subsys OS/EM function INITIALIZATION STARTING

Explanation: The OS/EM function has begun initialization.

subsys: The name of the JES2 subsystem requesting the OS/EM functionality.

function: The name of the OS/EM function being initialized.

Source FEMJ2L0x

Operator Response: None

System Programmer Response: None

FEM2M0242

subsys OS/EM function INITIALIZATION STARTING

Explanation: The OS/EM function has begun initialization.

subsys: The name of the JES2 subsystem requesting the OS/EM functionality.

function: The name of the OS/EM function being initialized.

Source FEMJ2M0x

Operator Response: None

System Programmer Response: None

FEM2D0243

subsys OS/EM function phase PHASE COMPLETE

Explanation: Initialization of the OS/EM function has completed successfully.

subsys: The name of the JES2 subsystem requesting the OS/EM functionality (e.g. JES2, SMF).

function: The name of the OS/EM function being requested.

phase: The initialization phase that has completed (e.g. FIRST, FINAL).

Source: FEMJ2D0x

Operator Response: None

System Programmer Response: None

FEM2H0243

subsys OS/EM function phase PHASE COMPLETE

Explanation: Initialization of the OS/EM function has completed successfully.

subsys: The name of the JES2 subsystem requesting the OS/EM functionality (e.g. JES2, SMF).

function: The name of the OS/EM function being requested.

phase: The initialization phase that has completed (e.g. FIRST, FINAL).

Source: FEMJ2H0x

Operator Response: None

System Programmer Response: None

FEM2H4243

subsys OS/EM function phase PHASE COMPLETE

Explanation: Initialization of the OS/EM function has completed successfully.

subsys: The name of the JES2 subsystem requesting the OS/EM functionality (e.g. JES2, SMF).

function: The name of the OS/EM function being requested.

phase: The initialization phase that has completed (e.g. FIRST, FINAL).

Source: FEMJ2H4x

Operator Response: None

System Programmer Response: None

FEM2L4243

subsys OS/EM function phase PHASE COMPLETE

Explanation: Initialization of the OS/EM function has completed successfully.

subsys: The name of the JES2 subsystem requesting the OS/EM functionality (e.g. JES2, SMF).

function: The name of the OS/EM function being requested.

phase: The initialization phase that has completed (e.g. FIRST, FINAL).

Source: FEMJ2L4x

Operator Response: None

System Programmer Response: None

FEM2M0243

subsys OS/EM function phase PHASE COMPLETE

Explanation: Initialization of the OS/EM function has completed successfully.

subsys: The name of the JES2 subsystem requesting the OS/EM functionality (e.g. JES2, SMF).

function: The name of the OS/EM function being requested.

phase: The initialization phase that has completed (e.g. FIRST, FINAL).

Source: FEMJ2M0x

Operator Response: None

System Programmer Response: None

FEM2M4243

subsys OS/EM function phase PHASE COMPLETE

Explanation: Initialization of the OS/EM function has completed successfully.

subsys: The name of the JES2 subsystem requesting the OS/EM functionality (e.g. JES2, SMF).

function: The name of the OS/EM function being requested.

phase: The initialization phase that has completed (e.g. FIRST, FINAL).

Source: FEMJ2M4x

Operator Response: None

System Programmer Response: None

FEM2G0244

OS/EM subsys function INITIALIZATION FAILED - ERROR errcode

Explanation: Initialization of an OS/EM function has failed.

subsys: The name of the JES2 subsystem requesting the OS/EM functionality.

function: The name of the OS/EM function that failed.

errcode: The error code (R15).

Source: FEMJ2G0x

Operator Response: None

System Programmer Response: Determine the cause of the error and correct. Re-initialize OS/EM by executing the OS/EM started task (i.e. S OSEM,{PROG=FEMINIT,}SUB=MSTR).

FEM2G9244

OS/EM subsys function INITIALIZATION FAILED - ERROR errcode

Explanation: Initialization of an OS/EM function has failed.

subsys: The name of the JES2 subsystem requesting the OS/EM functionality.

function: The name of the OS/EM function that failed.

errcode: The error code (R15).

Source: FEMJ2G9x

Operator Response: None

System Programmer Response: Determine the cause of the error and correct. Re-initialize OS/EM by executing the OS/EM started task (i.e. S OSEM,{PROG=FEMINIT,}SUB=MSTR).

FEM2D0245

ENTER 'Y' TO CONTINUE WITHOUT function, 'N' TO TERMINATE subsys

Explanation: The operator is being prompted to instruct OS/EM how proceed following an initialization failure of the specified function.

function: The name of the OS/EM function that failed.

subsys: The name of the JES2 subsystem that is affected by the initialization failure.

Source: FEMJ2D0x

Operator Response: Reply **Y** to proceed with initialization without the failed function, or **N** to terminate the JES2 system.

System Programmer Response: Determine the cause of the error and correct. Re-initialize OS/EM by executing the OS/EM started task (i.e. S OSEM,{PROG=FEMINIT,}SUB=MSTR).

FEM2H0245

ENTER 'Y' TO CONTINUE WITHOUT function, 'N' TO TERMINATE subsystem

Explanation: The operator is being prompted to instruct OS/EM how proceed following an initialization failure of the specified function.

function: The name of the OS/EM function that failed.

subsys: The name of the JES2 subsystem that is affected by the initialization failure.

Source: FEMJ2H0x

Operator Response: Reply **Y** to proceed with initialization without the failed function, or **N** to terminate the JES2 system.

System Programmer Response: Determine the cause of the error and correct. Re-initialize OS/EM by executing the OS/EM started task (i.e. S OSEM,{PROG=FEMINIT,}SUB=MSTR).

FEM2H4245

ENTER 'Y' TO CONTINUE WITHOUT function, 'N' TO TERMINATE subsystem

Explanation: The operator is being prompted to instruct OS/EM how proceed following an initialization failure of the specified function.

function: The name of the OS/EM function that failed.

subsys: The name of the JES2 subsystem that is affected by the initialization failure.

Source: FEMJ2H4x

Operator Response: Reply **Y** to proceed with initialization without the failed function, or **N** to terminate the JES2 system.

System Programmer Response: Determine the cause of the error and correct. Re-initialize OS/EM by executing the OS/EM started task (i.e. S OSEM,{PROG=FEMINIT,}SUB=MSTR).

FEM2L0245

ENTER 'Y' TO CONTINUE WITHOUT function, 'N' TO TERMINATE subsystem

Explanation: The operator is being prompted to instruct OS/EM how proceed following an initialization failure of the specified function.

function: The name of the OS/EM function that failed.

subsys: The name of the JES2 subsystem that is affected by the initialization failure.

Source: FEMJ2L0x

Operator Response: Reply **Y** to proceed with initialization without the failed function, or **N** to terminate the JES2 system.

System Programmer Response: Determine the cause of the error and correct. Re-initialize OS/EM by executing the OS/EM started task (i.e. S OSEM,{PROG=FEMINIT,}SUB=MSTR).

FEM2L4245

ENTER 'Y' TO CONTINUE WITHOUT function, 'N' TO TERMINATE subsystem

Explanation: The operator is being prompted to instruct OS/EM how proceed following an initialization failure of the specified function.

function: The name of the OS/EM function that failed.

subsys: The name of the JES2 subsystem that is affected by the initialization failure.

Source: FEMJ2L4x

Operator Response: Reply **Y** to proceed with initialization without the failed function, or **N** to terminate the JES2 system.

System Programmer Response: Determine the cause of the error and correct. Re-initialize OS/EM by executing the OS/EM started task (i.e. S OSEM,{PROG=FEMINIT,}SUB=MSTR).

FEM2M0245

ENTER 'Y' TO CONTINUE WITHOUT function, 'N' TO TERMINATE subsystem

Explanation: The operator is being prompted to instruct OS/EM how proceed following an initialization failure of the specified function.

function: The name of the OS/EM function that failed.

subsys: The name of the JES2 subsystem that is affected by the initialization failure.

Source: FEMJ2M0x

Operator Response: Reply **Y** to proceed with initialization without the failed function, or **N** to terminate the JES2 system.

System Programmer Response: Determine the cause of the error and correct. Re-initialize OS/EM by executing the OS/EM started task (i.e. S OSEM,{PROG=FEMINIT,}SUB=MSTR).

FEM2M4245

ENTER 'Y' TO CONTINUE WITHOUT function, 'N' TO TERMINATE subsystem

Explanation: The operator is being prompted to instruct OS/EM how proceed following an initialization failure of the specified function.

function: The name of the OS/EM function that failed.

subsys: The name of the JES2 subsystem that is affected by the initialization failure.

Source: FEMJ2M4x

Operator Response: Reply **Y** to proceed with initialization without the failed function, or **N** to terminate the JES2 system.

System Programmer Response: Determine the cause of the error and correct. Re-initialize OS/EM by executing the OS/EM started task (i.e. S OSEM,{PROG=FEMINIT,}SUB=MSTR).

FEMX24245

ENTER 'Y' TO CONTINUE WITHOUT function, 'N' TO TERMINATE subsystem

Explanation: The operator is being prompted to instruct OS/EM how proceed following an initialization failure of the specified function.

function: The name of the OS/EM function that failed.
subsys: The name of the JES2 subsystem that is affected by the initialization failure.

Source: FEMJ2X24

Operator Response: Reply **Y** to proceed with initialization without the failed function, or **N** to terminate the JES2 system.

System Programmer Response: Determine the cause of the error and correct. Re-initialize OS/EM by executing the OS/EM started task (i.e. S OSEM,{PROG=FEMINIT,}SUB=MSTR).

FEM2D1246

subsys OS/EM function TERMINATION STARTING

Explanation: OS/EM has commenced terminating the specified function.

subsys: The name of the JES2 subsystem that was executing the OS/EM function.
function: The name of the OS/EM function being terminated.

Source: FEMJ2D1x

Operator Response: None

System Programmer Response: None

FEM2H1246

subsys OS/EM function TERMINATION STARTING

Explanation: OS/EM has commenced terminating the specified function.

subsys: The name of the JES2 subsystem that was executing the OS/EM function.
function: The name of the OS/EM function being terminated.

Source: FEMJ2H1x

Operator Response: None

System Programmer Response: None

FEM2L1246

subsys OS/EM function TERMINATION STARTING

Explanation: OS/EM has commenced terminating the specified function.

subsys: The name of the JES2 subsystem that was executing the OS/EM function.
function: The name of the OS/EM function being terminated.

Source: FEMJ2L1x

Operator Response: None

System Programmer Response: None

FEM2M1246

subsys OS/EM function TERMINATION STARTING

Explanation: OS/EM has commenced terminating the specified function.

subsys: The name of the JES2 subsystem that was executing the OS/EM function.
function: The name of the OS/EM function being terminated.

Source: FEMJ2M1x

Operator Response: None

System Programmer Response: None

FEM2D1247

subsys OS/EM function TERMINATION COMPLETE

Explanation: OS/EM has terminated the specified function.

subsys: The name of the JES2 subsystem that was executing the OS/EM function.
function: The name of the OS/EM function that was terminated.

Source: FEMJ2D1x

Operator Response: None

System Programmer Response: None

FEM2H1247

subsys OS/EM function TERMINATION COMPLETE

Explanation: OS/EM has terminated the specified function.

subsys: The name of the JES2 subsystem that was executing the OS/EM function.
function: The name of the OS/EM function that was terminated.

Source: FEMJ2H1x

Operator Response: None

System Programmer Response: None

FEM2L1247

subsys OS/EM function TERMINATION COMPLETE

Explanation: OS/EM has terminated the specified function.

subsys: The name of the JES2 subsystem that was executing the OS/EM function.
function: The name of the OS/EM function that was terminated.

Source: FEMJ2L1x

Operator Response: None

System Programmer Response: None

FEM2M1247

subsys OS/EM function TERMINATION COMPLETE

Explanation: OS/EM has terminated the specified function.

subsys: The name of the JES2 subsystem that was executing the OS/EM function.
function: The name of the OS/EM function that was terminated.

Source: FEMJ2M1x

Operator Response: None

System Programmer Response: None

FEMACT248

jobname/procname/stepname/program COND = condcode CPU=cputime I/O=iocount

Explanation: This message displays the completion statistics at the completion of the job step.

jobname: The name of job.

procname: The name of PROC (if any) that was executed.

stepname: The name of job step (if any) that was executed.

program: The name of the program that was executed.

condcode: The condition code returned by the program.

cputime: The CPU time (in minutes) that was consumed by the job step.

iocount: The number of I/O operations performed by the job step.

Source: FEMACTRT

Operator Response: None

System Programmer Response: None

FEMX32249

jobname(jobnum) NOT ELIGIBLE TO RUN NOW{: reason}

Explanation: The job cannot be immediately executed due to the stated reason.

jobname: The name of job.

jobnum: The JES job number.

reason: The reason that the job cannot be executed.

Source: FEMJ2X32

Operator Response: If necessary, correct the situation that has caused the delay so the job will start.

System Programmer Response: None

FEMX49249

jobname(jobnum) NOT ELIGIBLE TO RUN NOW{: reason}

Explanation: The job cannot be immediately executed due to the stated reason.

jobname: The name of job.

jobnum: The JES job number.

reason: The reason that the job cannot be executed.

Source: FEMJ2X49

Operator Response: If necessary, correct the situation that has caused the delay so the job will start.

System Programmer Response: None

FEM2DM249

jobname(jobnum) NOT ELIGIBLE TO RUN NOW{: reason}

Explanation: The job cannot be immediately executed due to the stated reason.

jobname: The name of job.

jobnum: The JES job number.

reason: The reason that the job cannot be executed.

Source: FEMJ2DJx

Operator Response: If necessary, correct the situation that has caused the delay so the job will start.

System Programmer Response: None

FEM2DM250

OS/EM subsys function OPTIONS SET BY SYSTEM sysid JOB jobname

Explanation: MAS-wide options for an OS/EM function has been set by a job on another system operating within the MAS.

subsys: The name of the JES2 subsystem.

function: The name of the OS/EM function.

sysid: The name of the system that set the options.

jobname: The name of the job that set the options.

Source: FEMJ2DMx

Operator Response: None

System Programmer Response: None

FEM2D0250

OS/EM subsys function OPTIONS SET BY SYSTEM sysid JOB jobname

Explanation: MAS-wide options for an OS/EM function has been set by a job on another system operating within the MAS.

subsys: The name of the JES2 subsystem.

function: The name of the OS/EM function.

sysid: The name of the system that set the options.

jobname: The name of the job that set the options.

Source: FEMJ2D0x

Operator Response: None

System Programmer Response: None

FEM2HM250

OS/EM subsys function OPTIONS SET BY SYSTEM sysid JOB jobname

Explanation: MAS-wide options for an OS/EM function has been set by a job on another system operating within the MAS.

subsys: The name of the JES2 subsystem.

function: The name of the OS/EM function.

sysid: The name of the system that set the options.

jobname: The name of the job that set the options.

Source: FEMJ2HMx

Operator Response: None

System Programmer Response: None

FEM2H0250

OS/EM subsys function OPTIONS SET BY SYSTEM sysid JOB jobname

Explanation: MAS-wide options for an OS/EM function has been set by a job on another system operating within the MAS.

subsys: The name of the JES2 subsystem.

function: The name of the OS/EM function.

sysid: The name of the system that set the options.

jobname: The name of the job that set the options.

Source: FEMJ2H0x

Operator Response: None

System Programmer Response: None

FEM2LM250

OS/EM subsys function OPTIONS SET BY SYSTEM sysid JOB jobname

Explanation: MAS-wide options for an OS/EM function has been set by a job on another system operating within the MAS.

subsys: The name of the JES2 subsystem.

function: The name of the OS/EM function.

sysid: The name of the system that set the options.

jobname: The name of the job that set the options.

Source: FEMJ2LMx

Operator Response: None

System Programmer Response: None

FEM2L0250

OS/EM subsys function OPTIONS SET BY SYSTEM sysid JOB jobname

Explanation: MAS-wide options for an OS/EM function has been set by a job on another system operating within the MAS.

subsys: The name of the JES2 subsystem.

function: The name of the OS/EM function.

sysid: The name of the system that set the options.

jobname: The name of the job that set the options.

Source: FEMJ2L0x

Operator Response: None

System Programmer Response: None

FEM2MM250

OS/EM subsys function OPTIONS SET BY SYSTEM sysid JOB jobname

Explanation: MAS-wide options for an OS/EM function has been set by a job on another system operating within the MAS.

subsys: The name of the JES2 subsystem.
function: The name of the OS/EM function.
sysid: The name of the system that set the options.
jobname: The name of the job that set the options.

Source: FEMJ2MMx

Operator Response: None

System Programmer Response: None

FEM2M0250

OS/EM subsys function OPTIONS SET BY SYSTEM sysid JOB jobname

Explanation: MAS-wide options for an OS/EM function has been set by a job on another system operating within the MAS.

subsys: The name of the JES2 subsystem.
function: The name of the OS/EM function.
sysid: The name of the system that set the options.
jobname: The name of the job that set the options.

Source: FEMJ2M0x

Operator Response: None

System Programmer Response: None

FEM2HM251

OS/EM INITIATING HRECALL OF dataset

Explanation: A job has been submitted that requires a dataset that has been migrated to secondary storage. The OS/EM Early Recall function has initiated an HSM Recall to restore the dataset.

dataset: The name of the dataset that is to be recalled.

Source: FEMJ2HMx

Operator Response: None

System Programmer Response: None

FEMALC252

DATAAREA area ALREADY DEFINED WITH LENGTH len

Explanation: OS/EM is attempting to define a data area that already exists.

area: The name of the data area that was being defined.
len: The length of the data area.

Source: FEMALLO0,FEMALLO1

System Action: OS/EM initialization terminates.

Operator Response: None

System Programmer Response: This is an internal error in OS/EM. Contact OS/EM Technical Support.

FEMDAD252

DATAAREA area ALREADY DEFINED WITH LENGTH len

Explanation: OS/EM is attempting to define a data area that already exists.

area: The name of the data area that was being defined.

len: The length of the data area.

Source: FEMDASD

System Action: OS/EM initialization terminates.

Operator Response: None

System Programmer Response: This is an internal error in OS/EM. Contact OS/EM Technical Support.

FEMHSM252

DATAAREA area ALREADY DEFINED WITH LENGTH len

Explanation: OS/EM is attempting to define a data area that already exists.

area: The name of the data area that was being defined.

len: The length of the data area.

Source: FEMHSM0,FEMHSM1,FEMHSM2,FEMHSM3

System Action: OS/EM initialization terminates.

Operator Response: None

System Programmer Response: This is an internal error in OS/EM. Contact OS/EM Technical Support.

FEMISP252

DATAAREA area ALREADY DEFINED WITH LENGTH len

Explanation: OS/EM is attempting to define a data area that already exists.

area: The name of the data area that was being defined.

len: The length of the data area.

Source: FEMISPF

System Action: OS/EM initialization terminates.

Operator Response: None

System Programmer Response: This is an internal error in OS/EM. Contact OS/EM Technical Support.

FEMJS2252

DATAAREA area ALREADY DEFINED WITH LENGTH len

Explanation: OS/EM is attempting to define a data area that already exists.

area: The name of the data area that was being defined.

len: The length of the data area.

Source: FEMJES2A through FEMJES2H

System Action: OS/EM initialization terminates.

Operator Response: None

System Programmer Response: This is an internal error in OS/EM. Contact OS/EM Technical Support.

FEMJS3252

DATAAREA area ALREADY DEFINED WITH LENGTH len

Explanation: OS/EM is attempting to define a data area that already exists.

area: The name of the data area that was being defined.

len: The length of the data area.

Source: FEMJES3

System Action: OS/EM initialization terminates.

Operator Response: None

System Programmer Response: This is an internal error in OS/EM. Contact OS/EM Technical Support.

FEMMIS252

DATAAREA area ALREADY DEFINED WITH LENGTH len

Explanation: OS/EM is attempting to define a data area that already exists.

area: The name of the data area that was being defined.

len: The length of the data area.

Source: FEMMISC

System Action: OS/EM initialization terminates.

Operator Response: None

System Programmer Response: This is an internal error in OS/EM. Contact OS/EM Technical Support.

FEMRAC252

DATAAREA area ALREADY DEFINED WITH LENGTH len

Explanation: OS/EM is attempting to define a data area that already exists.

area: The name of the data area that was being defined.

len: The length of the data area.

Source: FEMRACF

System Action: OS/EM initialization terminates.

Operator Response: None

System Programmer Response: This is an internal error in OS/EM. Contact OS/EM Technical Support.

FEMSAF252

DATAAREA area ALREADY DEFINED WITH LENGTH len

Explanation: OS/EM is attempting to define a data area that already exists.

area: The name of the data area that was being defined.

len: The length of the data area.

Source: FEMSAF

System Action: OS/EM initialization terminates.

Operator Response: None

System Programmer Response: This is an internal error in OS/EM. Contact OS/EM Technical Support.

FEMSMF252

DATAAREA area ALREADY DEFINED WITH LENGTH len

Explanation: OS/EM is attempting to define a data area that already exists.

area: The name of the data area that was being defined.

len: The length of the data area.

Source: FEMSMF0 through FEMSMF5

System Action: OS/EM initialization terminates.

Operator Response: None

System Programmer Response: This is an internal error in OS/EM. Contact OS/EM Technical Support.

FEMTSO252

DATAAREA area ALREADY DEFINED WITH LENGTH len

Explanation: OS/EM is attempting to define a data area that already exists.

area: The name of the data area that was being defined.

len: The length of the data area.

Source: FEMTSO

System Action: OS/EM initialization terminates.

Operator Response: None

System Programmer Response: This is an internal error in OS/EM. Contact OS/EM Technical Support.

FEM2H3253

jobname(jobnum{ FROM sysid}) WAITING FOR HSM RECALL

Explanation: The job cannot be immediately executed because it is waiting for the OS/EM Early Recall function to restore one or more migrated datasets.

jobname: The name of job.
jobnum: The job number.
sysid: The originating system.

Source: FEMJ2H3x

Operator Response: None

System Programmer Response: None

FEM2D3254

jobname(jobnum {FROM sysid}) WAITING FOR DATASETS

Explanation: The job cannot be immediately executed because another job is using one or more datasets to be processed.

jobname: The name of job.
jobnum: The job number.
sysid: The originating system.

Source: FEMJ2D3x

System Action: The job will not be executed until the required dataset(s) are available.

Operator Response: This could be a temporary situation. If this is unexpected or is not resolved, use the MVS command 'D GRS,CONTENTION' to show which job or jobs are causing the wait.

System Programmer Response: None

FEMCMD255

DEVICE devnum OWNER = ownerid STATUS = devstatus

Explanation: This message is displayed in response to the **D TAPESH** command (Display Tapeshare Device Status).

devnum: The device number being displayed.
ownerid: The owner of the device.
devstatus: The status of the device.

Source: FEMCMD

Operator Response: None.

System Programmer Response: None

FEM2D3256

jobname1(jobnum1) HOLDS dsn NEEDED BY jobname2(jobnum2)

Explanation: A job is preventing another job from executing because it currently holds a dataset that one or both of the jobs request for exclusive use.

jobname1: The name of job that is using the dataset.

jobnum1: The JES job number that is using the dataset.
dsn: The dataset that is in contention.
jobname2: The name of job that is waiting for the dataset.
jobnum2: The JES job number that is waiting for the dataset.

Source: FEMJ2D3x

System Action: The second job will not be executed until the first job releases the dataset.

Operator Response: This may be a temporary situation. If this is a persistent problem, the user may wish to more closely coordinate the submission of the jobs (e.g. control the jobs with a job scheduling system). Also, verify that the job(s) actually require exclusive use (e.g. DISP=OLD / MOD) rather than shared access (i.e. DISP=SHR).

System Programmer Response: None

FEM2TP258

subsys EXIT exitname AUTOINSTALL COMPLETE FOR MODULE modname:entry

Explanation: OS/EM has activated a JES2 User Exit point with the OS/EM Autoinstall facility (i.e. no EXIT(nnn) statement was defined in the JES2 initialization parameters for an exit point required by OS/EM).

subsys: The name of the JES2 subsystem.
exitname: The user exit point name.
modname:entry: The load module and entry point that is activated for the user exit.

Source: FEMJ2TPx

Operator Response: None

System Programmer Response: None

FEMAOD259

UNAUTHORIZED RESTRICTED DEVICE REQUEST

Explanation: A job has tried to use a device that has been defined to OS/EM as a restricted device and the job is not defined to that device's authorized groups.

Source: FEMALLOD

System Action: The job is cancelled.

Operator Response: Correct the JCL to use a device that the job is authorized to use.

System Programmer Response: None

FEM2D0260

OS/EM subsys function OPTIONS SET FROM SPOOL VALUES

Explanation: Option settings for the named OS/EM function has been obtained from information saved in the JES2 spool.

subsys: The name of the JES2 subsystem.
function: The OS/EM function.

Source: FEMJ2D0x

System Action: None.

Operator Response: None.

System Programmer Response: None

FEM2H0260

OS/EM subsys function OPTIONS SET FROM SPOOL VALUES

Explanation: Option settings for the named OS/EM function has been obtained from information saved in the JES2 spool.

subsys: The name of the JES2 subsystem.

function: The OS/EM function.

Source: FEMJ2H0x

System Action: None.

Operator Response: None.

System Programmer Response: None

FEM2L0260

OS/EM subsys function OPTIONS SET FROM SPOOL VALUES

Explanation: Option settings for the named OS/EM function has been obtained from information saved in the JES2 spool.

subsys: The name of the JES2 subsystem.

function: The OS/EM function.

Source: FEMJ2L0x

System Action: None.

Operator Response: None.

System Programmer Response: None

FEM2M0260

OS/EM subsys function OPTIONS SET FROM SPOOL VALUES

Explanation: Option settings for the named OS/EM function has been obtained from information saved in the JES2 spool.

subsys: The name of the JES2 subsystem.

function: The OS/EM function.

Source: FEMJ2M0x

System Action: None.

Operator Response: None.

System Programmer Response: None

FEMTEX261

EXIT exitname ENTERED IN {HOME | XMEM} MODE, RUNNING UNDER A {TCB | SRB},

Explanation: The OS/EM test exit routine FEMTEXIT has been invoked by the named exit.

exitname: The exit name that invoked the test exit module.

Source: FEMTEXIT

System Action: Information message only. This message will be accompanied by messages FEMTEX262 and FEMTEX263.

Operator Response: None.

System Programmer Response: The test exit module FEMTEXIT should not be defined to OS/EM as an active user exit point unless instructed by technical support.

FEMTEX262

IN {PRIMARY | AR | HOME | SECONDARY} ASC MODE, {PROBLEM | SUPVR} STATE, KEY {0 | 1}, {ENABLED | DISABLED},

Explanation: The OS/EM test exit routine FEMTEXIT has been invoked by an exit point (indicated by message FEMTEX261).

Source: FEMTEXIT

System Action: Information message only. This message will be accompanied by messages FEMTEX261 and FEMTEX263.

Operator Response: None.

System Programmer Response: The test exit module FEMTEXIT should not be defined to OS/EM as an active user exit point unless instructed by technical support.

FEMTEX263

AMODE {24 | 31 | 64}, WITH lockinfo

Explanation: The OS/EM test exit routine FEMTEXIT has been invoked by an exit point (indicated by message FEMTEX261).

lockinfo: The details of any locks that are active.

Source: FEMTEXIT

System Action: Information message only. This message will be accompanied by messages FEMTEX261 and FEMTEX262.

Operator Response: None.

System Programmer Response: The test exit module FEMTEXIT should not be defined to OS/EM as an active user exit point unless instructed by technical support.

FEM2LM264

OS/EM jesid progname PGM LIMITS (local mas) SET BY SYSTEM sysid JOB jobname

Explanation: Program execution limits have been set by the specified job.

jesid: The name of the JES2 subsystem that is affected.

progname: The name of program that is being limited.
local: The execution limits for the program on an individual system.
mas: The MAS-wide execution limits for the program.
sysid: The system name that set the execution limits.
jobname: The job name that set the execution limits.

Source: FEMJ2LMx

System Action: OS/EM will limit concurrent execution of the program as per the specified values.

Operator Response: None.

System Programmer Response: None.

FEMSTM265

FUNCTION REQUIRES ACF2 SECURITY SYSTEM

Explanation: A request was made to set the OS/EM SYSTEM option ACF2CAN / NOACF2CAN (i.e. override of the ACF2 non-cancel user attribute) but ACF2 is not the active security system.

Source: FEMSYSTEM

System Action: The request is ignored.

Operator Response: None.

System Programmer Response: None

FEM2S0266

OS/EM jesid SUBTASK {INITIALIZATION COMPLETE | TERMINATING}

Explanation: The OS/EM management subtask for the named JES2 system has been initialized or is being terminated.

jesid: The name of the JES2 subsystem that is affected.

Source: FEMJ2S0x

System Action: Processing continues.

Operator Response: None.

System Programmer Response: None.

FEMLOD267

{subsystem} MODULE program NOT RELOADED (loadaddr) {VERSION verinfo}

Explanation: The specified module was not reloaded because a identical copy of the module had already been loaded.

subsystem: The subsystem that the module operates with (e.g. JES2)

program: Exit point name being processed.

loadaddr: The load address of the module.

verinfo: The version number and generation date & time of module. This applies only to OS/EM system modules.

Source: FEMLOAD

System Action: OS/EM continues.

Operator Response: None.

System Programmer Response: None.

FEMPW1268

PASSWORD newpwd REJECTED BY EXIT - VIOLATES ruledesc RULE

Explanation: A new password was rejected by the OS/EM password validation routine.

newpwd: The new password that was submitted

ruledesc: The description of the validation rule that made the new password invalid

Source: FEMPWX01

System Action: None.

Operator Response: None.

System Programmer Response: None.

User Response: Specify a password that that conforms with your site's password standards.

FEMLIB269

SCRNLIB MAY ONLY BE USED WITHIN ISPF

Explanation: The FEMLIB utility attempted to modify the allocation for the 'SCRNLIB' DD but was rejected because the user was not operating under ISPF.

Source: FEMLIB

System Action: None.

Operator Response: None.

System Programmer Response: None.

User Response: Do not attempt to alter allocation for the 'SCRNLIB' DD when not operating under ISPF.

FEMLIB270

A TASKLIB, ddname, IS ALREADY ALLOCATED

Explanation: The FEMLIB utility was being used to allocate a task library but the DDNAME was already allocated and the ISPF environment does not permit the DD to be modified.

ddname: The DDNAME that was being allocated

Source: FEMLIB

System Action: None.

Operator Response: None.

System Programmer Response: None.

User Response: Re-initialize the ISPF environment to release the existing DDNAME allocation.

FEMLIB271

DDNAME ddname IS NOT ALLOCATED

Explanation: The FEMLIB utility was being used to modify a task library definition but the DDNAME is not allocated.

ddname: The DDNAME that was being allocated

Source: FEMLIB

System Action: None.

Operator Response: None.

System Programmer Response: None.

User Response: If you are attempting an FEMLIB ADD, modify your request to perform an ALLOCATE.

FEMLIB272

parm REQUIRED - MISSING

Explanation: The FEMLIB command did not have a required parameter.

parm: The parameter that should have been provided

Source: FEMLIB

System Action: None.

Operator Response: None.

System Programmer Response: None.

User Response: Re-issue the FEMLIB with the appropriate parameters.

FEMLIB272

{BEFORE/AFTER | DELETE} DSN 'libname' {ALREADY | NOT} ALLOCATED

Explanation: An FEMLIB request to modify an existing task library failed for one of the following reasons:

- The request attempted to add a library that was already allocated to the task library
- The request attempted to delete a library that was not allocated to the task library

ddname: The DDNAME that was being allocated

Source: FEMLIB

System Action: None.

Operator Response: None.

System Programmer Response: None.

User Response: None.

FEMLIB274

DDNAME ddname STILL OPEN

Explanation: An FEMLIB UNALLOC command failed because one or more of the library datasets are in use.

ddname: The DDNAME of the task library.

Source: FEMLIB

System Action: None.

Operator Response: None.

System Programmer Response: None.

User Response: Close the task library and re-issue the FEMLIB UNALLOC command.

FEMLIB275

NO PUSHED ALLOCATIONS FOR ddname

Explanation: A FEMLIB POP request failed because there is nothing in the stack for that DDNAME.

ddname: The DDNAME of the task library.

Source: FEMLIB

System Action: None.

Operator Response: None.

System Programmer Response: None.

User Response: None.

FEMLIB276

ddname dsname volser

Explanation: This message is task library information in response to an FEMLIB LIST command or other FEMLIB command without the NOLIST option specified.

ddname: The DDNAME of the task library.

dsname: The dataset name allocated to the task library.

volser: The volume serial number where the dataset resides.

Source: FEMLIB

System Action: None.

Operator Response: None.

System Programmer Response: None.

User Response: None.

FEMLIB277

ddname STACK ENTRY NUMBER nn:

Explanation: This message is displayed in response to an FEMLIB LIST or FEMLIB POP command.

ddname: The DDNAME of the task library.

nn: The stack entry number.

Source: FEMLIB

System Action: None.

Operator Response: None.

System Programmer Response: None.

User Response: None.

FEMLIB278

DCB FOUND THAT IS NOT OPEN FOR INPUT FOR DDNAME ddname

Explanation: The requested FEMLIB function failed because it found a DCB in the task library concatenation that is not open for input.

ddname: The DDNAME of the task library.

Source: FEMLIB

System Action: The FEMLIB request fails.

Operator Response: None.

System Programmer Response: None.

User Response: Reallocate the affected task library and retry the FEMLIB function.

FEMLIB279

UNABLE TO LOCATE ALL OPEN DCBS FOR DDNAME ddname

Explanation: The requested FEMLIB function failed because it could not find all the DCBs in the task library concatenation list.

ddname: The DDNAME of the task library.

Source: FEMLIB

System Action: The FEMLIB request fails.

Operator Response: None.

System Programmer Response: None.

User Response: Reallocate the affected task library and retry the FEMLIB function.

FEMLIB280

ddname DCB CLOSE FAILURE

Explanation: The requested FEMLIB function failed because it could not successfully close a DCB in the task library concatenation list.

ddname: The DDNAME of the task library.

Source: FEMLIB

System Action: The FEMLIB request fails.

Operator Response: None.

System Programmer Response: None.

User Response: Reallocate the affected task library and retry the FEMLIB function.

FEMLIB281

DATASET 'dsn' IS NOT PARTITIONED

Explanation: The requested FEMLIB function failed because the user specified a dataset that is not a partitioned dataset (PDS).

dsn: The name of the non-partitioned dataset.

Source: FEMLIB

System Action: The FEMLIB request fails.

Operator Response: None.

System Programmer Response: None.

User Response: Only specify partitioned datasets to be concatenated in a task library.

FEMLIB282

UNAUTHORIZED STEPLIB CANNOT BE USED BY PRIVILEGED PROGRAM

Explanation: The requested FEMLIB function against the STEPLIB ddname has resulted in one or more unauthorized load libraries being part of the concatenation. This disables authorization for all libraries in STEPLIB and, as a result, no privileged programs will be permitted to execute from STEPLIB.

Source: FEMLIB

System Action: The FEMLIB request fails.

Operator Response: None.

System Programmer Response: None.

User Response: Ensure that only authorized libraries are specified in your STEPLIB concatenation.

FEMU29283

PRIMARY JES INACTIVE - NO START COMMAND ISSUED

Explanation: An SMF log dataset has been closed but the SMF dump started task could not be executed because the primary JES subsystem is not active.

Source: FEMU29

System Action: The SMF lod dataset stays unprocessed.

Operator Response: Insure that the SMF dataset is dumped once the primary JES subsystem is active.

System Programmer Response: None.

FEMSMF284

START COMMAND ISSUED TO DUMP SMF DATASET(S)

Explanation: An SMF log dataset has been closed and OS/EM has issued a start command to execute the SMF dump process.

Source: FEMSMF0

System Action: None.

Operator Response: None.

System Programmer Response: None.

FEMU29284

START COMMAND ISSUED TO DUMP SMF DATASET(S)

Explanation: An SMF log dataset has been closed and OS/EM has issued a start command to execute the SMF dump process.

Source: FEMU29

System Action: None.

Operator Response: None.

System Programmer Response: None.

FEMRAC285

TOTAL MINIMUM CHARACTERS EXCEEDS MAXIMUM PASSWORD LENGTH

Explanation: The sum of the parameter values for ALPHAMIN, NUMERICMIN and SPECIALMIN exceeds the maximum allowable password length (8).

Source: FEMRACF

System Action: The ALPHAMIN, NUMERICMIN and SPECIALMIN parameters are set to zero.

Operator Response: None.

System Programmer Response: None.

User Response: Correct the parameter specifications to ensure that the sum of these parameters is less than or equal to 8.

FEMLIB286

DDNAME ddname ALREADY ALLOCATED BUT REUSE NOT SPECIFIED

Explanation: An FEMLIB ALLOCATE command was issued without a REUSE option for a task library that was already allocated.

ddname: The DDNAME of the task library.

Source: FEMLIB

System Action: FEMCNTL command is ignored.

Operator Response: None.

System Programmer Response: None.

User Response: If you intended to replace the existing task library definition, re-issue the command with the REUSE option.

FEMLOD287

JES2 AMODE24 MODULE modname LOADED IN AMODE31

Explanation: A JES2 load module that has been compiled & linked in 24-bit addressing mode has been loaded in 31-bit mode.

modname: The name of the load module.

Source: FEMLOAD

System Action: Operation continues.

Operator Response: None.

System Programmer Response: None.

User Response: Information message only.

FEMBB4288

DATASET dsname PROCESSED BY OS/EM FORCE-OPEN

Explanation: The named dataset was created by the job but was not opened. The OS/EM FORCE-OPEN function opened this dataset so unused DASD space would be freed.

dsname: The name of the dataset that was opened by OS/EM.

Source: FEMBB410

System Action: None.

Operator Response: None.

System Programmer Response: None.

User Response: Contact the OS/EM administrator if this dataset should not be opened before the completion of the job that created it.

FEMHSP289

WARNING: MAINTENANCE HAS BEEN APPLIED TO jessys BUT THE OS/EM OFFSET TABLE HAS NOT BEEN REASSEMBLED

Explanation: OS/EM has detected a mismatch between the JES2 environment and the OS/EM JES2 Offset Table. This has occurred because maintenance has been applied to the JES2 system but the Offset Table has not been regenerated.

OS/EM will attempt to complete JES2 initialization, but OS/EM functionality may be compromised.

jessys: The name of the JES2 subsystem.

Source: FEMHJ20

System Action: This message will be followed by messages FEMxxx226 and FEMxxx083.

Operator Response: The operator will be required to respond to message FEMxxx083 to determine whether JES2 initialization should continue. Contact the OS/EM administrator.

System Programmer Response: It is recommended that the OS/EM JES2 Offset Table be regenerated. Refer to the OS/EM Installation Guide and/or User Guide for more information about generating the JES2 Offset Table.

If the JES2 Offset Table is not regenerated and the JES2 system executes uninterrupted for 8 hours, OS/EM will assume that the system is stable and will not issue this message in the future. If JES2 is reinitialized within an 8 hour period, this message will be reissued.

Typical symptoms of a bad JES2 Offset Table are S0C1 and S0C4 abends in OS/EM, JES2 and/or user exit modules. If these occur, the Offset Table should be regenerated as soon as possible.

User Response: None.

FEMX24289

WARNING: MAINTENANCE HAS BEEN APPLIED TO jessys BUT THE OS/EM OFFSET TABLE HAS NOT BEEN REASSEMBLED

Explanation: OS/EM has detected a mismatch between the JES2 environment and the OS/EM JES2 Offset Table. This has occurred because maintenance has been applied to the JES2 system but the Offset Table has not been regenerated.

OS/EM will attempt to complete JES2 initialization, but OS/EM functionality may be compromised.

jessys: The name of the JES2 subsystem.

Source: FEMJ2X24

System Action: This message will be followed by messages FEMxxx226 and FEMxxx083.

Operator Response: The operator will be required to respond to message FEMxxx083 to determine whether JES2 initialization should continue. Contact the OS/EM administrator.

System Programmer Response: It is recommended that the OS/EM JES2 Offset Table be regenerated. Refer to the OS/EM Installation Guide and/or User Guide for more information about generating the JES2 Offset Table.

If the JES2 Offset Table is not regenerated and the JES2 system executes uninterrupted for 8 hours, OS/EM will assume that the system is stable and will not issue this message in the future. If JES2 is reinitialized within an 8 hour period, this message will be reissued.

Typical symptoms of a bad JES2 Offset Table are S0C1 and S0C4 abends in OS/EM, JES2 and/or user exit modules. If these occur, the Offset Table should be regenerated as soon as possible.

User Response: None.

FEMHSP290

THE OS/EM jessys OFFSET TABLE IS INVALID

Explanation: OS/EM has an invalid JES2 Offset Table for the JES2 system that is being initialized. OS/EM functions will not be initialized for this system.

jessys: The name of the JES2 subsystem.

Source: FEMHJ20

System Action: This message will be followed by messages FEMxxx225 and FEMxxx083.

Operator Response: The operator will be required to respond to message FEMxxx083 to determine whether JES2 initialization should continue. Contact the OS/EM administrator.

System Programmer Response: The OS/EM JES2 Offset Table must be regenerated (refer to the OS/EM Installation Guide and/or User Guide for more information about generating the JES2 Offset Table) and JES2 reinitialized.

User Response: None.

FEMHSP291

OS/EM TRAP INSERTION FAILED IN JES2 MODULE modname

Explanation: OS/EM attempted to insert a dynamic TRAP into the named JES2 module, but there was a mismatch between the contents of the module and the data in the OS/EM JES2 Offset Table.

modname: The name of the JES2 module that could not be loaded

Source: FEMHJ20

System Action: OS/EM JES2 initialization is terminated with an abend and/or JES2 termination. This message will be followed by messages FEMHSP292 through FEMHSP295.

Operator Response: Contact the OS/EM System Programmer.

System Programmer Response: The OS/EM JES2 Offset Table must be regenerated (refer to the OS/EM Installation Guide and/or User Guide for more information about generating the JES2 Offset Table) and JES2 reinitialized.

User Response: None.

FEMX24291

OS/EM TRAP INSERTION FAILED IN JES2 MODULE modname

Explanation: OS/EM attempted to insert a dynamic TRAP into the named JES2 module, but there was a mismatch between the contents of the module and the data in the OS/EM JES2 Offset Table.

modname: The name of the JES2 module that could not be loaded

Source: FEMJ2X24

System Action: OS/EM JES2 initialization is terminated with an abend and/or JES2 termination. This message will be followed by messages FEMX24292 through FEMX24295.

Operator Response: Contact the OS/EM System Programmer.

System Programmer Response: The OS/EM JES2 Offset Table must be regenerated (refer to the OS/EM Installation Guide and/or User Guide for more information about generating the JES2 Offset Table) and JES2 reinitialized.

User Response: None.

FEMHSP292

THE OS/EM OFFSET TABLE ASSEMBLED ON date AT time SHOWS

Explanation: This message provides additional diagnostic information in support of error message FEMHSP291. This details the assembly time and date of the OS/EM JES2 Offset Table.

date: The date that the Offset Table was assembled

time: The time that the Offset Table was assembled

Source: FEMHJ20

System Action: Refer to message FEMHSP291 for the system action taken for this error condition.

Operator Response: Refer to message FEMHSP291 for the appropriate response for this error condition.

System Programmer Response: Refer to message FEMHSP291 for appropriate response for this error condition.

User Response: None.

FEMX24292

THE OS/EM OFFSET TABLE ASSEMBLED ON date AT time SHOWS

Explanation: This message provides additional diagnostic information in support of error message FEMX24291. This details the assembly time and date of the OS/EM JES2 Offset Table.

date: The date that the Offset Table was assembled

time: The time that the Offset Table was assembled

Source: FEMJ2X24

System Action: Refer to message FEMX24291 for the system action taken for this error condition.

Operator Response: Refer to message FEMX24291 for the appropriate response for this error condition.

System Programmer Response: Refer to message FEMX24291 for appropriate response for this error condition.

User Response: None.

FEMHSP293

LABEL label TO BE AT OFFSET X'xxxx'

Explanation: This message provides additional diagnostic information in support of error message FEMHSP291. This details the expected offset for the given label (based on the OS/EM JES2 Offset Table).

label: The label being referenced in the JES2 module

Source: FEMHJ20

System Action: Refer to message FEMHSP291 for the system action taken for this error condition.

Operator Response: Refer to message FEMHSP291 for the appropriate response for this error condition.

System Programmer Response: Refer to message FEMHSP291 for appropriate response for this error condition.

User Response: None.

FEMX24293

LABEL label TO BE AT OFFSET X'xxxx'

Explanation: This message provides additional diagnostic information in support of error message FEMX24291. This details the expected offset for the given label (based on the OS/EM JES2 Offset Table).

label: The label being referenced in the JES2 module

Source: FEMJ2X24

System Action: Refer to message FEMX24291 for the system action taken for this error condition.

Operator Response: Refer to message FEMX24291 for the appropriate response for this error condition.

System Programmer Response: Refer to message FEMX24291 for appropriate response for this error condition.

User Response: None.

FEMHSP294

WHERE OS/EM EXPECTS TO FIND X'xxxx'.

Explanation: This message provides additional diagnostic information in support of error message FEMHSP291. This details the expected data for the given location in the JES2 module (based on the OS/EM JES2 Offset Table).

Source: FEMHJ20

System Action: Refer to message FEMHSP291 for the system action taken for this error condition.

Operator Response: Refer to message FEMHSP291 for the appropriate response for this error condition.

System Programmer Response: Refer to message FEMHSP291 for appropriate response for this error condition.

User Response: None.

FEMX24294

WHERE OS/EM EXPECTS TO FIND X'xxxx'.

Explanation: This message provides additional diagnostic information in support of error message FEMX24291. This details the expected data for the given location in the JES2 module (based on the OS/EM JES2 Offset Table).

Source: FEMJ2X24

System Action: Refer to message FEMX24291 for the system action taken for this error condition.

Operator Response: Refer to message FEMX24291 for the appropriate response for this error condition.

System Programmer Response: Refer to message FEMX24291 for appropriate response for this error condition.

User Response: None.

FEMHSP295

THE ACTUAL CODE AT OFFSET X'xxxx' IN modname IS X'xxxx'.

Explanation: This message provides additional diagnostic information in support of error message FEMHSP291. This details the the contents of the given module and offset location.

modname: The name of the JES2 module

Source: FEMHJ20

System Action: Refer to message FEMHSP291 for the system action taken for this error condition.

Operator Response: Refer to message FEMHSP291 for the appropriate response for this error condition.

System Programmer Response: Refer to message FEMHSP291 for appropriate response for this error condition.

User Response: None.

FEMX24295

THE ACTUAL CODE AT OFFSET X'xxxx' IN modname IS X'xxxx'.

Explanation: This message provides additional diagnostic information in support of error message FEMX24291. This details the the contents of the given module and offset location.

modname: The name of the JES2 module

Source: FEMJ2X24

System Action: Refer to message FEMX24291 for the system action taken for this error condition.

Operator Response: Refer to message FEMX24291 for the appropriate response for this error condition.

System Programmer Response: Refer to message FEMX24291 for appropriate response for this error condition.

User Response: None.

FEMREL296

MODULE modname IS NOT USED BY jessys RELEASE relnum

Explanation: An attempt to reload an OS/EM JES2 module was rejected because it is not supported by that release of JES2.

modname: The name of the OS/EM JES2 module

jessys: The JES2 subsystem name

relnum: The release level for the given JES2 subsystem

Source: FEMRELOD

System Action: The reload request is ignored.

Operator Response: None.

System Programmer Response: None.

User Response: None.

FEMHSP297

THE OS/EM OFFSET TABLE ASSEMBLED ON mm/dd/yy AT hh:mm USING

Explanation: This is one of a series of messages (FEMHSP297 - FEMHSP302). OS/EM has detected a mismatch between the currently executing copy of JES2 and the OS/EM JES2 Offset Table.

mm/dd/yy: The date that the OS/EM JES2 Offset Table was assembled.

hh:mm:ss: The time that the OS/EM JES2 Offset Table was assembled.

Source: FEMHJ20

System Action: The initialization of OS/EM JES2 functions is discontinued.

Operator Response: Contact the Systems Programmer immediately.

System Programmer Response:

Regenerate the JES2 Offset Table using the current JES2 libraries. The most common reason for this error is that maintenance has been applied to JES2 but the OS/EM JES2 Offset Table has not been regenerated using the updated JES2 libraries.

Care should be taken when running multiple JES2 systems with different levels of maintenance. The JES2 Offset Table must be generated for each environment. Since the Offset Table will have the same load module name (FEMJ2OFx), the load module must be placed in a load library that is accessible to the appropriate system.

Refer to the OS/EM Installation Guide and OS/EM User Guide for more information regarding the generation of the JES2 Offset Table.

User Response: None.

FEMLOD297

THE OS/EM OFFSET TABLE ASSEMBLED ON mm/dd/yy AT hh:mm USING

Explanation: This is one of a series of messages (FEMLOD297 - FEMLOD302). OS/EM has detected a mismatch between the currently executing copy of JES2 and the OS/EM JES2 Offset Table.

mm/dd/yy: The date that the OS/EM JES2 Offset Table was assembled.

hh:mm:ss: The time that the OS/EM JES2 Offset Table was assembled.

Source: FEMLOAD

System Action: The initialization of OS/EM JES2 functions is discontinued.

Operator Response: Contact the Systems Programmer immediately.

System Programmer Response:

Regenerate the JES2 Offset Table using the current JES2 libraries. The most common reason for this error is that maintenance has been applied to JES2 but the OS/EM JES2 Offset Table has not been regenerated using the updated JES2 libraries.

Care should be taken when running multiple JES2 systems with different levels of maintenance. The JES2 Offset Table must be generated for each environment. Since the Offset Table will have the same load module name (FEMJ2OFx), the load module must be placed in a load library that is accessible to the appropriate system.

Refer to the OS/EM Installaton Guide and OS/EM User Guide for more information regarding the generation of the JES2 Offset Table.

User Response: None.

FEMHSP298

MACLIB xxxxxxxx AND

Explanation: This is one of a series of messages (FEMHSP297 - FEMHSP302). OS/EM has detected a mismatch between the currently executing copy of JES2 and the OS/EM JES2 Offset Table.

xxxxxxx: The name of the JES2 macro library that was used when the current Offset Table was assembled.

Source: FEMHJ20

System Action: The initialization of OS/EM JES2 functions is discontinued.

Operator Response: Contact the Systems Programmer immediately.

System Programmer Response:

Regenerate the JES2 Offset Table using the current JES2 libraries. The most common reason for this error is that maintenance has been applied to JES2 but the OS/EM JES2 Offset Table has not been regenerated using the updated JES2 libraries.

Care should be taken when running multiple JES2 systems with different levels of maintenance. The JES2 Offset Table must be generated for each environment. Since the Offset Table will have the same load module name (FEMJ2OFx), the load module must be placed in a load library that is accessible to the appropriate system.

Refer to the OS/EM Installaton Guide and OS/EM User Guide for more information regarding the generation of the JES2 Offset Table.

User Response: None.

FEMLOD298

MACLIB xxxxxxxx AND

Explanation: This is one of a series of messages (FEMLOD297 - FEMLOD302). OS/EM has detected a mismatch between the currently executing copy of JES2 and the OS/EM JES2 Offset Table.

xxxxxxx: The name of the JES2 macro library that was used when the current Offset Table was assembled.

Source: FEMLOAD

System Action: The initialization of OS/EM JES2 functions is discontinued.

Operator Response: Contact the Systems Programmer immediately.

System Programmer Response:

Regenerate the JES2 Offset Table using the current JES2 libraries. The most common reason for this error is that maintenance has been applied to JES2 but the OS/EM JES2 Offset Table has not been regenerated using the updated JES2 libraries.

Care should be taken when running multiple JES2 systems with different levels of maintenance. The JES2 Offset Table must be generated for each environment. Since the Offset Table will have the same load module name (FEMJ2OFx), the load module must be placed in a load library that is accessible to the appropriate system.

Refer to the OS/EM Installaton Guide and OS/EM User Guide for more information regarding the generation of the JES2 Offset Table.

User Response: None.

FEMHSP299

LINKLIB xxxxxxxx AND

Explanation: This is one of a series of messages (FEMHSP297 - FEMHSP302). OS/EM has detected a mismatch between the currently executing copy of JES2 and the OS/EM JES2 Offset Table.

xxxxxxx: The name of the JES2 load library that was used when the current Offset Table was assembled.

Source: FEMHJ20

System Action: The initialization of OS/EM JES2 functions is discontinued.

Operator Response: Contact the Systems Programmer immediately.

System Programmer Response:

Regenerate the JES2 Offset Table using the current JES2 libraries. The most common reason for this error is that maintenance has been applied to JES2 but the OS/EM JES2 Offset Table has not been regenerated using the updated JES2 libraries.

Care should be taken when running multiple JES2 systems with different levels of maintenance. The JES2 Offset Table must be generated for each environment. Since the Offset Table will have the same load module name (FEMJ2OFx), the load module must be placed in a load library that is accessible to the appropriate system.

Refer to the OS/EM Installaton Guide and OS/EM User Guide for more information regarding the generation of the JES2 Offset Table.

User Response: None.

FEMLOD299

LINKLIB xxxxxxxx AND

Explanation: This is one of a series of messages (FEMLOD297 - FEMLOD302). OS/EM has detected a mismatch between the currently executing copy of JES2 and the OS/EM JES2 Offset Table.

xxxxxxx: The name of the JES2 load library that was used when the current Offset Table was assembled.

Source: FEMLOAD

System Action: The initialization of OS/EM JES2 functions is discontinued.

Operator Response: Contact the Systems Programmer immediately.

System Programmer Response:

Regenerate the JES2 Offset Table using the current JES2 libraries. The most common reason for this error is that maintenance has been applied to JES2 but the OS/EM JES2 Offset Table has not been regenerated using the updated JES2 libraries.

Care should be taken when running multiple JES2 systems with different levels of maintenance. The JES2 Offset Table must be generated for each environment. Since the Offset Table will have the same load module name (FEMJ2OFx), the load module must be placed in a load library that is accessible to the appropriate system.

Refer to the OS/EM Installaton Guide and OS/EM User Guide for more information regarding the generation of the JES2 Offset Table.

User Response: None.

FEMHSP300**DOES NOT MATCH THE RUNNING xxxx. THE DIFFERENCES ARE:**

Explanation: This is one of a series of messages (FEMHSP297 - FEMHSP302). OS/EM has detected a mismatch between the currently executing copy of JES2 and the OS/EM JES2 Offset Table.

xxxx: The name of the JES2 subsystem that has the mismatch with the current Offset Table.

Source: FEMHJ20

System Action: The initialization of OS/EM JES2 functions is discontinued.

Operator Response: Contact the Systems Programmer immediately.

System Programmer Response:

Regenerate the JES2 Offset Table using the current JES2 libraries. The most common reason for this error is that maintenance has been applied to JES2 but the OS/EM JES2 Offset Table has not been regenerated using the updated JES2 libraries.

Care should be taken when running multiple JES2 systems with different levels of maintenance. The JES2 Offset Table must be generated for each environment. Since the Offset Table will have the same load module name (FEMJ2OFx), the load module must be placed in a load library that is accessible to the appropriate system.

Refer to the OS/EM Installaton Guide and OS/EM User Guide for more information regarding the generation of the JES2 Offset Table.

User Response: None.

FEMLOD300**DOES NOT MATCH THE RUNNING xxxx. THE DIFFERENCES ARE:**

Explanation: This is one of a series of messages (FEMLOD297 - FEMLOD302). OS/EM has detected a mismatch between the currently executing copy of JES2 and the OS/EM JES2 Offset Table.

xxxx: The name of the JES2 subsystem that has the mismatch with the current Offset Table.

Source: FEMLOAD

System Action: The initialization of OS/EM JES2 functions is discontinued.

Operator Response: Contact the Systems Programmer immediately.

System Programmer Response:

Regenerate the JES2 Offset Table using the current JES2 libraries. The most common reason for this error is that maintenance has been applied to JES2 but the OS/EM JES2 Offset Table has not been regenerated using the updated JES2 libraries.

Care should be taken when running multiple JES2 systems with different levels of maintenance. The JES2 Offset Table must be generated for each environment. Since the Offset Table will have the same load module name (FEMJ2OFx), the load module must be placed in a load library that is accessible to the appropriate system.

Refer to the OS/EM Installaton Guide and OS/EM User Guide for more information regarding the generation of the JES2 Offset Table.

User Response: None.

FEMHSP301

CSECT xxxx DATA OFFSET DATA:

Explanation: This is one of a series of messages (FEMHSP297 - FEMHSP302). OS/EM has detected a mismatch between the currently executing copy of JES2 and the OS/EM JES2 Offset Table.

xxxx: The name of the JES2 subsystem that has the mismatch with the current Offset Table.

Source: FEMHJ20

System Action: The initialization of OS/EM JES2 functions is discontinued.

Operator Response: Contact the Systems Programmer immediately.

System Programmer Response:

Regenerate the JES2 Offset Table using the current JES2 libraries. The most common reason for this error is that maintenance has been applied to JES2 but the OS/EM JES2 Offset Table has not been regenerated using the updated JES2 libraries.

Care should be taken when running multiple JES2 systems with different levels of maintenance. The JES2 Offset Table must be generated for each environment. Since the Offset Table will have the same load module name (FEMJ2OFx), the load module must be placed in a load library that is accessible to the appropriate system.

Refer to the OS/EM Installaton Guide and OS/EM User Guide for more information regarding the generation of the JES2 Offset Table.

User Response: None.

FEMLOD301

CSECT xxxx DATA OFFSET DATA:

Explanation: This is one of a series of messages (FEMLOD297 - FEMLOD302). OS/EM has detected a mismatch between the currently executing copy of JES2 and the OS/EM JES2 Offset Table.

xxxx: The name of the JES2 subsystem that has the mismatch with the current Offset Table.

Source: FEMLOAD

System Action: The initialization of OS/EM JES2 functions is discontinued.

Operator Response: Contact the Systems Programmer immediately.

System Programmer Response:

Regenerate the JES2 Offset Table using the current JES2 libraries. The most common reason for this error is that maintenance has been applied to JES2 but the OS/EM JES2 Offset Table has not been regenerated using the updated JES2 libraries.

Care should be taken when running multiple JES2 systems with different levels of maintenance. The JES2 Offset Table must be generated for each environment. Since the Offset Table will have the same load module name (FEMJ2OFx), the load module must be placed in a load library that is accessible to the appropriate system.

Refer to the OS/EM Installaton Guide and OS/EM User Guide for more information regarding the generation of the JES2 Offset Table.

User Response: None.

FEMHSP302

xxxxxxx yy/yy/yy zz:zz aa/aa/aa bb:bb

Explanation: This is one of a series of messages (FEMHSP297 - FEMHSP302). OS/EM has detected a mismatch between the currently executing copy of JES2 and the OS/EM JES2 Offset Table.

xxxxxxx: The name of the JES2 CSECT that has a mismatch with the current Offset Table.

yy/yy/yy: The date extracted from the MIT of the JES2 load module.

zz:zz: The time extracted from the MIT of the JES2 load module.

aa/aa/aa: The date that was saved in the Offset Table. This was taken from the MIT of the JES2 load module when the table was generated.

bb:bb: The time that was saved in the Offset Table. This was taken from the MIT of the JES2 load module when the table was generated.

Source: FEMHJ20

System Action: The initialization of OS/EM JES2 functions is discontinued.

Operator Response: Contact the Systems Programmer immediately.

System Programmer Response:

Regenerate the JES2 Offset Table using the current JES2 libraries. The most common reason for this error is that maintenance has been applied to JES2 but the OS/EM JES2 Offset Table has not been regenerated using the updated JES2 libraries.

Care should be taken when running multiple JES2 systems with different levels of maintenance. The JES2 Offset Table must be generated for each environment. Since the Offset Table will have the same load module name (FEMJ2OFx), the load module must be placed in a load library that is accessible to the appropriate system.

Refer to the OS/EM Installaton Guide and OS/EM User Guide for more information regarding the generation of the JES2 Offset Table.

User Response: None.

FEMLOD302

xxxxxxx yy/yy/yy zz:zz aa/aa/aa bb:bb

Explanation: This is one of a series of messages (FEMLOD297 - FEMLOD302). OS/EM has detected a mismatch between the currently executing copy of JES2 and the OS/EM JES2 Offset Table.

xxxxxxx: The name of the JES2 CSECT that has a mismatch with the current Offset Table.

yy/yy/yy: The date extracted from the MIT of the JES2 load module.

zz:zz: The time extracted from the MIT of the JES2 load module.

aa/aa/aa: The date that was saved in the Offset Table. This was taken from the MIT of the JES2 load module when the table was generated.

bb:bb: The time that was saved in the Offset Table. This was taken from the MIT of the JES2 load module when the table was generated.

Source: FEMLOAD

System Action: The initialization of OS/EM JES2 functions is discontinued.

Operator Response: Contact the Systems Programmer immediately.

System Programmer Response:

Regenerate the JES2 Offset Table using the current JES2 libraries. The most common reason for this error is that maintenance has been applied to JES2 but the OS/EM JES2 Offset Table has not been regenerated using the updated JES2 libraries.

Care should be taken when running multiple JES2 systems with different levels of maintenance. The JES2 Offset Table must be generated for each environment. Since the Offset Table will have the same load module name (FEMJ2OFx), the load module must be placed in a load library that is accessible to the appropriate system.

Refer to the OS/EM Installaton Guide and OS/EM User Guide for more information regarding the generation of the JES2 Offset Table.

User Response: None.

FEMJS2303

KEY SPECIFICATION FOR JES2 DEFINED EXIT nnn IGNORED

Explanation: A storage key value has been specified for a JES2 defined exit. This value will be ignored and will be assigned the storage key that is appropriate for the specific exit.

nnn: The JES2 exit number.

Source: FEMJES2A through FEMJES2H

System Action: The initialization of the JES2 exit continues normally.

Operator Response: None.

System Programmer Response: Correct the JES2 exit definition for the exit. This can be done by rebuilding the JES2 basic exit initialization parameters (Option 8 on the main menu of the OS/EM ISPF dialog).

User Response: None.

FEMLOD304

FROM xxxLIB yyyyyyyy

Explanation: This message accompanies message FEMLOD018 to indicate the source of the JES2 Offset Table.

xxx: The type of load library (PVT, LPA or LNK)

yyyyyyyy: The name of the load library

Source: FEMLOAD

System Action: OS/EM initialization continues

Operator Response: None

System Programmer Response: None

User Response: None.

FEMHSP305

xxxx IS ALREADY ACTIVE. THIS INSTANCE TERMINATING

Explanation: An attempt was made to start a JES2 system that is already active.

xxxx: The JES2 subsystem name.

Source: FEMHJ20

System Action: Initialization of the JES2 subsystem is terminated.

Operator Response: None

System Programmer Response: None

User Response: None.

FEMHSP306

OS/EM RESOURCE MANAGER FAILED TO CLEAN UP xxxx DATA

Explanation: OS/EM failed to release control block storage associated with a terminating JES2 subsystem.

xxxx: The JES2 subsystem name.

Source: FEMHJ20

System Action: Termination of the JES2 subsystem continues. The affected storage will not be reusable until the next IPL.

Operator Response: None

System Programmer Response: Gather any related diagnostic information and contact OS/EM customer support.

User Response: None.

FEMLOD307

MODULE modname REQUIRES OFFSET MODULE AT PTF ptfvl OR HIGHER

Explanation: The named OS/EM module could not be loaded because the OS/EM JES2 Offset Table (FEMJ2OFx) was not at a sufficiently recent maintenance level.

modname: The OS/EM load module that could not be loaded.

ptfvl: The minimum maintenance level that the OS/EM JES2 Offset Table must be assembled with.

This can occur after applying OS/EM maintenance and the user failed to reassemble the JES2 Offset Table. Instructions to perform this process is contained in the SMP/E HOLDDATA associated with the appropriate PTF.

Source: FEMLOAD

System Action: OS/EM initialization continues but functions relating to the affected module will not be available until the JES2 Offset Table is corrected.

Operator Response: Contact your OS/EM system programming support personnel.

System Programmer Response: Reassemble the OS/EM JES2 Offset Table and reinitialize the OS/EM environment by invoking the OS/EM started task (i.e. S OSEM,PROG=FEMINIT,SUB=MSTR).

User Response: None.

FEM2TP308

OS/EM xxxx EXIT nnn MOVED TO LAST POSITION

Explanation: The user has defined JES2 user exits that are to be loaded outside of OS/EM control. The OS/EM JES2 exit controller module has been loaded after the defined exit module(s) and will be called after the defined user exits.

xxxx: The JES2 subsystem name.

nnn: The JES2 user exit point.

Source: FEMJ2TPx

System Action: OS/EM initialization continues.

Operator Response: None.

System Programmer Response: No action needs to be taken if this desired. If not, change the user exit point is defined with AUTOINSTALL set to YES so OS/EM will manage the loading and execution of the modules for this exit.

Refer to the OS/EM Installation Guide under the section titled '**JES2 EXIT Implementation**'.

User Response: None.

FEMHSP312

OS/EM xxxx EXITS NOT INSTALLED ON PRIOR STARTUP

Explanation: During a hot restart of JES2, it was determined that the OS/EM JES2 exit controller modules were not installed on the named JES2 subsystem when it was last warm/cold started. This situation could arise if the JES2 subsystem had been defined to OS/EM and a subsequent hot start of JES2 occurred.

xxxx: The JES2 subsystem name.

Source: FEMHJ20

System Action: JES2 initialization continues but OS/EM support for this subsystem will not be initialized until the next warm/cold start.

Operator Response: Notify the System Programmer.

System Programmer Response: Schedule a warm/cold start of the JES2 subsystem to install OS/EM support. If OS/EM was successfully installed during the last warm/cold start of JES2, contact OS/EM customer support.

User Response: None.

FEMHSP313

OS/EM CODE VERIFICATION FAILED IN JES2 MODULE modname

Explanation: During initialization of OS/EM JES2 functions, the object code in the named module

does not match what was expected. This usually indicates that the OS/EM JES2 Offset Table (FEMJ2OFx) was not generated using the current JES2 libraries.

modname: The name of the JES2 module that failed code verification.

Source: FEMHJ20

System Action: Initialization of the OS/EM JES2 functions is terminated.

Operator Response: Notify the System Programmer.

System Programmer Response: Generate the OS/EM JES2 Offset Table using the current JES2 libraries and re-initialize OS/EM. If the error persists, contact OS/EM customer support.

User Response: None.

FEM2TP314

jesname EXIT exitname AUTOINSTALL EXIT modname : entrypt REMOVED

Explanation: A JES2 \$DEL command was issued for a user exit module that had been placed under OS/EM management by AUTOINSTALL processing during JES2 initialization (i.e. a LOADMOD statement was defined in the JES2 initialization parameters and the AUTOINSTALL option for that exit point was active).

jesname: The name of the JES2 subsystem.

exitname: The name of the JES2 exit point.

modname: The name of the JES2 exit load module.

entrypt: The name of the entry point in the JES2 exit load module.

Source: FEMJ2TPx

System Action: The load module for the specified JES2 exit point has been deleted and will no longer be called by OS/EM.

Operator Response: None.

System Programmer Response: None.

User Response: None.

FEMDMP1001

asid DATA AREA

Explanation: This is an information message that indicates the address space or JES2 system that is being dumped.

asid: The address space number or the JES2 subsystem name.

Source: FEMJ2TPx

System Action: None.

Operator Response: None.

System Programmer Response: None

FEMDMP1002

hex dump data

Explanation: This message contains a hex display of the selected storage location.

Source: FEMJ2TPx

System Action: None.

Operator Response: None.

System Programmer Response: None

FEMDMP1003

DATA AREA IS INVALID

Explanation: The data area cannot be displayed.

Source: FEMJ2TPx

System Action: None.

Operator Response: None.

System Programmer Response: None

FEMDMP1004

subsys DATA AREA IS NOT PRESENT

Explanation: The data area for the named JES2 system is no longer available to be displayed.

Source: FEMJ2TPx

System Action: None.

Operator Response: None.

System Programmer Response: None

FEM285I

dsname dsp rc VOL SER NOS= ser,ser,ser,ser,ser VOL SER NOS= ser,ser,ser.

Explanation: This message displays the disposition of a dataset when OS/EM has encountered a NOT CATALOGED 2 condition.

This message is issued only when the OS/EM NOT CATALOGED 2 controls are active and is a replacement for IEF285I. For a detailed description of the message contents refer to the MVS System Messages (IEF - IDG) manual (Document Number SA22-7638).

Source: FEM0002F

System Action: None.

Operator Response: None.

System Programmer Response:

If the resulting disposition is not the desired result of the NOT CATALOGED 2 condition, check your OS/EM definitions for this function (refer to Job Controls in the OS/EM User's Guide for more information).

User Response: None.

Appendix A. \$HASP Messages for Job Routing (\$HASP6xx & \$HASP9xx)

The following messages may be issued by the OS/EM Job Routing option:

\$HASP606 INSUFFICIENT OPERANDS

Produced by the \$LN command.

\$HASP608 OS/EM STATUS UNKNOWN

\$HASP610 JOB(S) NOT FOUND

\$HASP619 NO OUTPUT QUEUED

Produced by the \$LF command.

\$HASP624 'CMD' 'JOBNAME' MULTIPLE JOBS FOUND

Produced by a \$Qx command.

\$HASP646 mn PERCENT SPOOL UTILIZATION

Produced by the \$LN command.

\$HASP668 NO DEVICE(S) FOUND

Produced by the \$DP command.

\$HASP687 UNABLE TO OBTAIN SECURITY PRODUCT MESSAGES

\$HASP690 COMMAND REJECTED - AUTHORIZATION FAILURE

\$HASP900 TOO {MANY | FEW} OPERANDS

\$HASP901 INVALID OPERAND xxxxx

\$HASP902 TOO MANY RESOURCES ALREADY DEFINED

\$HASP903 UNABLE TO ACCESS RESOURCE DATASET

\$HASP904 jjjj(nnn) JOB {HELD | CANCELLED}

\$HASP905 RESOURCE IN USE. YOU MUST USE FORCE TO DELETE

Produced by the \$QD command.

\$HASP906 jjjj(nnn) BAD JCTX DATA - RC = retcode

\$HASP907 JOBNAME xxxx IS NOT SUITABLE FOR DJC

Produced by a \$Qx command.

\$HASP908 NO MATCH FOUND FOR SPECIFIED RESOURCE

Produced by the \$QJ command.

\$HASP921 free-format message

Produced by the \$LF command.

\$HASP922 free-format message

Produced by the \$LQ command.

\$HASP928 free-format message

Produced by the \$DP command.

\$HASP929 jjjj(nnn) /*djc statement REMOVED

Produced by the \$QJ / \$Q'xxx' command.

\$HASP930 jjjj(nnn) EXECUTION IMPOSSIBLE /*djc statement ALREADY {HELD | FLUSHED
| COMPLETED | EXECUTING}

\$HASP931 * -- JOBROUTE FAILED - ALREADY 127 ROUTES IN USE

\$HASP932 jjjj(nnn) * -- EXCLUDE JOBNAME = xxxx -- {SYSTEM | TIME}

\$HASP933 jjjj(nnn) SYNTAX ON /*PRED IS INVALID

\$HASP934 jjjj(nnn) SYNTAX ON /*EXCLUDE IS INVALID

\$HASP935 jjjj(nnn) SYNTAX ON /*BEFORE IS INVALID

\$HASP936 jjjj(nnn) SYNTAX ON /*AFTER IS INVALID

\$HASP937 jjjj(nnn) PARM SPECIFIED ON /*CNTL STATEMENT IS INVALID

\$HASP938 jjjj(nnn) TOO MANY {DJC | CNTL/THREAD | ROUTE} STATEMENTS

\$HASP939 jjjj(nnn) SYNTAX ON /*WITH IS INVALID

\$HASP940 jjjj(nnn) * -- AFTER JOBNAME = xxxx --

\$HASP941 jjjj(nnn) * -- WITH JOBNAME = xxxx -- {SYSTEM | TIME}

\$HASP942 jjjj(nnn) * -- RESOURCE ROUTING = xxxxxx --

\$HASP943 jjjj(nnn) * -- CONTROL INFO = xxxxxx -- {SHR | EXC}

\$HASP944 jjjj(nnn) * -- BEFORE JOBNAME = xxxx --

\$HASP945 jjjj(nnn) * -- PRED JOBNAME = xxxx --

\$HASP946 sid - NO RESOURCES ATTACHED

Produced by the \$DRESOURCE command.

\$HASP947 sid - resname resname resname

Produced by the \$DRESOURCE command.

\$HASP948 NO RESOURCE CONFLICTS

Produced by the \$DC command.

\$HASP949 nnn AWAITING {EXECUTION | SPIN | OUTPUT | HARDCOPY | TRANSMISSION}

Produced by the \$DB command.

\$HASP950 jjjj(JOBnnnnn) * -- JOBROUTE rulenum ruletype = value --

Produced when OS/EM generates an automatic route or a change to jobclass/priority, scheduling environment, service class or xeq node. Where:

rulenum is the OS/EM Resource Routing and Classing rule number.

ruletype is the OS/EM Resource Routing and Classing resource being set.

value is the value being assigned.

\$HASP951 OS/EM VER n.n - JOBROUTING ACTIVE ON subsys FOR sid

\$HASP952 TOTAL JOBS nnn-BATCH nnn-STC nnn-TSO nnn-APPC

Produced by the \$DB command.

\$HASP953 nnn JOBS NEED RESOURCE resname

Produced by the \$DC command.

\$HASP954 nnn JOBS NEED nnn UNDEFINED RESOURCES

Produced by the \$DC command.

\$HASP955 jjjj(nnn) NEEDS RESOURCE resname

Produced by the \$DC command.

\$HASP956 jjjj(nnn) /*djC JOB xxxxxxxx IS NOT SUITABLE

Produced by the \$QJ / \$Q'xxx' command.

djC is AFTER, WITH, BEFORE, EXCLUDE OR PRED

\$HASP957 FOR DJC - djC

Produced by the \$QJ / \$Q'xxx' command.

djC is AFTER, WITH, BEFORE, EXCLUDE OR PRED

\$HASP958 jjjj(nnn) ONLY nnn {RESOURCE | DJC | CNTL/THREAD} STATEMENTS ALLOWED

\$HASP959 jjjj(nnn) UNABLE TO ADD {ROUTE | CNTL | THREAD | djC} - JCTX IS FULL

djC is AFTER, WITH, BEFORE, EXCLUDE OR PRED

\$HASP960 jjjj(nnn) NEEDS RESOURCES ASSIGNED TO MULTIPLE SYSTEMS

\$HASP961 nnn JOBS NEED RESOURCES ASSIGNED TO MULTIPLE SYSTEMS

Produced by the \$DC command.

\$HASP962 jjjj(nnn) DJC {ADDED | DELETED}: AFTER JOBNAME = xxxxx

Produced by the \$QJ / \$Q'xxx' command.

\$HASP963 jjjj(nnn) DJC {ADDED | DELETED}: BEFORE JOBNAME = xxxxx

Produced by the \$QJ / \$Q'xxx' command.

\$HASP964 jjjj(nnn) DJC {ADDED | DELETED}: EXCLUDE JOBNAME = xxxxx

Produced by the \$QJ / \$Q'xxx' command.

\$HASP965 jjjj(nnn) DJC {ADDED | DELETED}: PRED JOBNAME = xxxxx

Produced by the \$QJ / \$Q'xxx' command.

\$HASP966 jjjj(nnn) DJC {ADDED | DELETED}: WITH JOBNAME = xxxxx

Produced by the \$QJ / \$Q'xxx' command.

\$HASP967 jjjj(nnn) RESOURCE ROUTING {ADDED | DELETED}: xxxxx

Produced by the \$QJ / \$Q'xxx' command.

\$HASP968 jjjj(nnn) CONTROL INFO {ADDED | DELETED}: xxxxx-**{SHR | EXC}**

Produced by the \$QJ / \$Q'xxx' command.

\$HASP969 jjjj(nnn) EXEMPTED FROM {DSNENQ | HSM | PGMLIMIT | USERLIMIT} PROC-
ESSING

Produced by the \$QJ / \$Q'xxx' command.

\$HASP970 jjjj(nnn) INCLUDED IN {DSNENQ | HSM | PGMLIMIT | USERLIMIT} PROCESSING

Produced by the \$QJ / \$Q'xxx' command.

\$HASP971 OS/EM VER v.r - JCL CONVERTED BY jes ON sid

\$HASP972 JOB jjjj(nnn) CANCELLED DUE TO OS/EM ERROR - reason

\$HASP973 INVALID \$OSEM DATA | MTTR FOUND IN JOB jjjj(nnn), CODE xxx

When this message is issued, an SVC dump is obtained and the job is canceled. Normal processing continues. Contact OS/EM customer support to arrange for the dump to be sent for analysis.

Index

A

Abend Messages

AFF-0000, MSG-1
AFF-0004, MSG-1
AFF-0008, MSG-1
AFF-0012, MSG-2
AFF-0016, MSG-2
AFF-0020, MSG-2
AFF-0024, MSG-2
AFF-0028, MSG-3
AFF-0032, MSG-3
AFF-0036, MSG-3
System Code Format, MSG-1

M

Messages

\$HASP Messages for Job Routing, A-1
AFF-0000, MSG-1
AFF-0004, MSG-1
AFF-0008, MSG-1
AFF-0012, MSG-2
AFF-0016, MSG-2
AFF-0020, MSG-2
AFF-0024, MSG-2
AFF-0028, MSG-3
AFF-0032, MSG-3
AFF-0036, MSG-3
Allocation Messages Format, MSG-4
FEM02F027, MSG-44
FEM02F070, MSG-103
FEM02F071, MSG-116
FEM02F072, MSG-128
FEM02F073, MSG-139
FEM02F074, MSG-151
FEM02F075, MSG-162
FEM02F076, MSG-173
FEM02F091, MSG-185
FEM02F093, MSG-197
FEM02F103, MSG-204
FEM02F206, MSG-259
FEM02F207, MSG-271
FEM02F208, MSG-282

FEM02F209, MSG-293
FEM02F210, MSG-305
FEM02F211, MSG-316
FEM02F212, MSG-327
FEM02F213, MSG-339
FEM02F214, MSG-350
FEM02F215, MSG-361
FEM02F216, MSG-373
FEM02F217, MSG-384
FEM1PL070, MSG-104
FEM1PL071, MSG-117
FEM1PL072, MSG-128
FEM1PL073, MSG-140
FEM1PL074, MSG-151
FEM1PL075, MSG-162
FEM1PL076, MSG-174
FEM1PL093, MSG-197
FEM1PL206, MSG-260
FEM1PL207, MSG-271
FEM1PL208, MSG-282
FEM1PL209, MSG-294
FEM1PL210, MSG-305
FEM1PL211, MSG-316
FEM1PL212, MSG-328
FEM1PL213, MSG-339
FEM1PL214, MSG-350
FEM1PL215, MSG-362
FEM1PL216, MSG-373
FEM1PL217, MSG-384
FEM285I, MSG-4, MSG-438
FEM2D0055, MSG-75
FEM2D0242, MSG-396
FEM2D0243, MSG-397
FEM2D0245, MSG-399
FEM2D0250, MSG-405
FEM2D0260, MSG-412
FEM2D1246, MSG-402
FEM2D1247, MSG-403
FEM2D3254, MSG-411
FEM2D3256, MSG-411
FEM2DM249, MSG-404
FEM2DM250, MSG-405
FEM2G0244, MSG-399
FEM2G2160, MSG-232
FEM2G3146, MSG-224
FEM2G3160, MSG-232
FEM2G4160, MSG-232

FEM2G9244,	MSG-399	FEM2M1247,	MSG-403
FEM2H0055,	MSG-75	FEM2M3146,	MSG-225
FEM2H0146,	MSG-224	FEM2M4055,	MSG-77
FEM2H0242,	MSG-396	FEM2M4243,	MSG-399
FEM2H0243,	MSG-397	FEM2M4245,	MSG-401
FEM2H0245,	MSG-400	FEM2MM146,	MSG-224
FEM2H0250,	MSG-406	FEM2MM250,	MSG-406
FEM2H0260,	MSG-413	FEM2P1159,	MSG-229
FEM2H1246,	MSG-402	FEM2P1160,	MSG-233
FEM2H1247,	MSG-403	FEM2P2159,	MSG-229
FEM2H3253,	MSG-410	FEM2P3160,	MSG-233
FEM2H4055,	MSG-75	FEM2P4023,	MSG-25
FEM2H4243,	MSG-398	FEM2P4024,	MSG-35
FEM2H4245,	MSG-400	FEM2P4030,	MSG-58
FEM2H5070,	MSG-104	FEM2P4070,	MSG-105
FEM2H5071,	MSG-117	FEM2P4071,	MSG-117
FEM2H5072,	MSG-129	FEM2P4072,	MSG-129
FEM2H5073,	MSG-140	FEM2P4073,	MSG-140
FEM2H5074,	MSG-151	FEM2P4074,	MSG-152
FEM2H5075,	MSG-163	FEM2P4075,	MSG-163
FEM2H5076,	MSG-174	FEM2P4076,	MSG-174
FEM2H5093,	MSG-198	FEM2P4206,	MSG-260
FEM2H5206,	MSG-260	FEM2P4207,	MSG-272
FEM2H5207,	MSG-271	FEM2P4208,	MSG-283
FEM2H5208,	MSG-283	FEM2P4209,	MSG-294
FEM2H5209,	MSG-294	FEM2P4210,	MSG-306
FEM2H5210,	MSG-305	FEM2P4211,	MSG-317
FEM2H5211,	MSG-317	FEM2P4212,	MSG-328
FEM2H5212,	MSG-328	FEM2P4213,	MSG-340
FEM2H5213,	MSG-339	FEM2P4214,	MSG-351
FEM2H5214,	MSG-351	FEM2P4215,	MSG-362
FEM2H5215,	MSG-362	FEM2P4216,	MSG-374
FEM2H5216,	MSG-373	FEM2P4217,	MSG-385
FEM2H5217,	MSG-385	FEM2S0160,	MSG-233
FEM2HM250,	MSG-405	FEM2S0167,	MSG-236
FEM2HM251,	MSG-407	FEM2S0266,	MSG-415
FEM2L0055,	MSG-76	FEM2TP082,	MSG-179
FEM2L0146,	MSG-224	FEM2TP227,	MSG-392
FEM2L0242,	MSG-397	FEM2TP235,	MSG-394
FEM2L0245,	MSG-400	FEM2TP258,	MSG-412
FEM2L0250,	MSG-406	FEM2TP308,	MSG-436
FEM2L0260,	MSG-413	FEM2TP314,	MSG-437
FEM2L1246,	MSG-402	FEMABN032,	MSG-59
FEM2L1247,	MSG-403	FEMACN024,	MSG-26
FEM2L4055,	MSG-76	FEMACN025,	MSG-35
FEM2L4243,	MSG-398	FEMACN026,	MSG-39
FEM2L4245,	MSG-400	FEMACN030,	MSG-44
FEM2LM250,	MSG-406	FEMACN070,	MSG-91
FEM2LM264,	MSG-414	FEMACN071,	MSG-105
FEM2M0055,	MSG-76	FEMACN072,	MSG-118
FEM2M0066,	MSG-90	FEMACN073,	MSG-129
FEM2M0087,	MSG-183	FEMACN074,	MSG-141
FEM2M0242,	MSG-397	FEMACN075,	MSG-152
FEM2M0243,	MSG-398	FEMACN076,	MSG-163
FEM2M0245,	MSG-401	FEMACN093,	MSG-186
FEM2M0250,	MSG-407	FEMACN101,	MSG-200
FEM2M0260,	MSG-413	FEMACN206,	MSG-249
FEM2M1066,	MSG-90	FEMACN207,	MSG-261
FEM2M1246,	MSG-402	FEMACN208,	MSG-272

FEMACN209,	MSG-283	FEMAOD259,	MSG-412
FEMACN210,	MSG-295	FEMASY024,	MSG-26
FEMACN211,	MSG-306	FEMASY030,	MSG-45
FEMACN212,	MSG-317	FEMASY070,	MSG-92
FEMACN213,	MSG-329	FEMASY071,	MSG-106
FEMACN214,	MSG-340	FEMASY072,	MSG-119
FEMACN215,	MSG-351	FEMASY073,	MSG-130
FEMACN216,	MSG-363	FEMASY074,	MSG-141
FEMACN217,	MSG-374	FEMASY075,	MSG-153
FEMACN220,	MSG-387	FEMASY076,	MSG-164
FEMACT096,	MSG-199	FEMASY093,	MSG-187
FEMACT097,	MSG-199	FEMASY206,	MSG-250
FEMACT098,	MSG-199	FEMASY207,	MSG-261
FEMACT099,	MSG-199	FEMASY208,	MSG-273
FEMACT121,	MSG-209	FEMASY209,	MSG-284
FEMACT218,	MSG-385	FEMASY210,	MSG-295
FEMACT233,	MSG-393	FEMASY211,	MSG-307
FEMACT248,	MSG-404	FEMASY212,	MSG-318
FEMAIF021,	MSG-18	FEMASY213,	MSG-329
FEMALC003,	MSG-7	FEMASY214,	MSG-341
FEMALC030,	MSG-45	FEMASY215,	MSG-352
FEMALC048,	MSG-66	FEMASY216,	MSG-363
FEMALC057,	MSG-77	FEMASY217,	MSG-375
FEMALC058,	MSG-81	FEMATH047,	MSG-66
FEMALC066,	MSG-87	FEMB14066,	MSG-87
FEMALC070,	MSG-92	FEMB14218,	MSG-386
FEMALC071,	MSG-105	FEMB14233,	MSG-393
FEMALC072,	MSG-118	FEMBB4288,	MSG-422
FEMALC073,	MSG-130	FEMCAL082,	MSG-177
FEMALC074,	MSG-141	FEMCMD027,	MSG-42
FEMALC075,	MSG-152	FEMCMD070,	MSG-93
FEMALC076,	MSG-164	FEMCMD071,	MSG-106
FEMALC087,	MSG-181	FEMCMD072,	MSG-119
FEMALC093,	MSG-187	FEMCMD073,	MSG-130
FEMALC139,	MSG-215	FEMCMD074,	MSG-142
FEMALC143,	MSG-221	FEMCMD075,	MSG-153
FEMALC157,	MSG-228	FEMCMD076,	MSG-164
FEMALC160,	MSG-229	FEMCMD093,	MSG-187
FEMALC167,	MSG-235	FEMCMD140,	MSG-220
FEMALC173,	MSG-239	FEMCMD141,	MSG-220
FEMALC174,	MSG-239	FEMCMD185,	MSG-243
FEMALC175,	MSG-239	FEMCMD188,	MSG-244
FEMALC178,	MSG-240	FEMCMD189,	MSG-244
FEMALC179,	MSG-240	FEMCMD206,	MSG-250
FEMALC183,	MSG-242	FEMCMD207,	MSG-262
FEMALC190,	MSG-244	FEMCMD208,	MSG-273
FEMALC206,	MSG-250	FEMCMD209,	MSG-284
FEMALC207,	MSG-261	FEMCMD210,	MSG-296
FEMALC208,	MSG-272	FEMCMD211,	MSG-307
FEMALC209,	MSG-284	FEMCMD212,	MSG-318
FEMALC210,	MSG-295	FEMCMD213,	MSG-330
FEMALC211,	MSG-306	FEMCMD214,	MSG-341
FEMALC212,	MSG-318	FEMCMD215,	MSG-352
FEMALC213,	MSG-329	FEMCMD216,	MSG-364
FEMALC214,	MSG-340	FEMCMD217,	MSG-375
FEMALC215,	MSG-352	FEMCMD255,	MSG-411
FEMALC216,	MSG-363	FEMCOD048,	MSG-67
FEMALC217,	MSG-374	FEMCOD049,	MSG-72
FEMALC252,	MSG-407	FEMCOD050,	MSG-72

FEMCOD051, MSG-72
FEMCOD139, MSG-215
FEMCOM024, MSG-27
FEMCOM070, MSG-93
FEMCOM071, MSG-107
FEMCOM072, MSG-119
FEMCOM073, MSG-131
FEMCOM074, MSG-142
FEMCOM075, MSG-153
FEMCOM076, MSG-165
FEMCOM093, MSG-188
FEMCOM206, MSG-251
FEMCOM207, MSG-262
FEMCOM208, MSG-273
FEMCOM209, MSG-285
FEMCOM210, MSG-296
FEMCOM211, MSG-307
FEMCOM212, MSG-319
FEMCOM213, MSG-330
FEMCOM214, MSG-341
FEMCOM215, MSG-353
FEMCOM216, MSG-364
FEMCOM217, MSG-375
FEMCTL004, MSG-8
FEMCTL022, MSG-22
FEMCTL040, MSG-62
FEMCTL041, MSG-64
FEMCTL042, MSG-64
FEMCTL043, MSG-64
FEMCTL044, MSG-64
FEMCTL045, MSG-65
FEMCTL046, MSG-66
FEMDAD030, MSG-45
FEMDAD048, MSG-67
FEMDAD057, MSG-78
FEMDAD058, MSG-82
FEMDAD139, MSG-216
FEMDAD252, MSG-408
FEMDAP048, MSG-67
FEMDAP052, MSG-73
FEMDAP094, MSG-198
FEMDAP139, MSG-216
FEMDB4038, MSG-61
FEMDB4105, MSG-204
FEMDC1022, MSG-22
FEMDC1027, MSG-43
FEMDC1070, MSG-94
FEMDC1071, MSG-107
FEMDC1072, MSG-120
FEMDC1073, MSG-131
FEMDC1074, MSG-143
FEMDC1075, MSG-154
FEMDC1076, MSG-165
FEMDC1093, MSG-188
FEMDC1206, MSG-251
FEMDC1207, MSG-263
FEMDC1208, MSG-274
FEMDC1209, MSG-285
FEMDC1210, MSG-297

FEMDC1211, MSG-308
FEMDC1212, MSG-319
FEMDC1213, MSG-331
FEMDC1214, MSG-342
FEMDC1215, MSG-353
FEMDC1216, MSG-365
FEMDC1217, MSG-376
FEMDCN024, MSG-27
FEMDCN025, MSG-36
FEMDCN026, MSG-39
FEMDCN030, MSG-46
FEMDCN031, MSG-59
FEMDCN070, MSG-93
FEMDCN071, MSG-107
FEMDCN072, MSG-120
FEMDCN073, MSG-131
FEMDCN074, MSG-142
FEMDCN075, MSG-154
FEMDCN076, MSG-165
FEMDCN093, MSG-188
FEMDCN101, MSG-201
FEMDCN206, MSG-251
FEMDCN207, MSG-262
FEMDCN208, MSG-274
FEMDCN209, MSG-285
FEMDCN210, MSG-296
FEMDCN211, MSG-308
FEMDCN212, MSG-319
FEMDCN213, MSG-330
FEMDCN214, MSG-342
FEMDCN215, MSG-353
FEMDCN216, MSG-364
FEMDCN217, MSG-376
FEMDCN220, MSG-387
FEMDEL078, MSG-175
FEMDIF021, MSG-18
FEMDMP048, MSG-67
FEMDMP1001, MSG-437
FEMDMP1002, MSG-437
FEMDMP1003, MSG-438
FEMDMP1004, MSG-438
FEMDMP160, MSG-229
FEMEXR024, MSG-27
FEMEXR070, MSG-94
FEMEXR071, MSG-108
FEMEXR072, MSG-120
FEMEXR073, MSG-132
FEMEXR074, MSG-143
FEMEXR075, MSG-154
FEMEXR076, MSG-166
FEMEXR093, MSG-189
FEMEXR206, MSG-252
FEMEXR207, MSG-263
FEMEXR208, MSG-274
FEMEXR209, MSG-286
FEMEXR210, MSG-297
FEMEXR211, MSG-308
FEMEXR212, MSG-320
FEMEXR213, MSG-331

FEMEXR214,	MSG-342	FEMHCN025,	MSG-37
FEMEXR215,	MSG-354	FEMHCN026,	MSG-40
FEMEXR216,	MSG-365	FEMHCN030,	MSG-47
FEMEXR217,	MSG-376	FEMHCN070,	MSG-95
FEMF10030,	MSG-46	FEMHCN071,	MSG-109
FEMF10106,	MSG-205	FEMHCN072,	MSG-121
FEMF10107,	MSG-205	FEMHCN073,	MSG-133
FEMF10108,	MSG-205	FEMHCN074,	MSG-144
FEMF10110,	MSG-206	FEMHCN075,	MSG-155
FEMF10111,	MSG-206	FEMHCN076,	MSG-167
FEMF10112,	MSG-206	FEMHCN093,	MSG-190
FEMFCN024,	MSG-28	FEMHCN101,	MSG-201
FEMFCN026,	MSG-40	FEMHCN206,	MSG-253
FEMFIF021,	MSG-19	FEMHCN207,	MSG-264
FEMFRA025,	MSG-36	FEMHCN208,	MSG-275
FEMFRA030,	MSG-46	FEMHCN209,	MSG-287
FEMFRA070,	MSG-95	FEMHCN210,	MSG-298
FEMFRA071,	MSG-108	FEMHCN211,	MSG-309
FEMFRA073,	MSG-132	FEMHCN212,	MSG-321
FEMFRA074,	MSG-143	FEMHCN213,	MSG-332
FEMFRA075,	MSG-155	FEMHCN214,	MSG-343
FEMFRA076,	MSG-166	FEMHCN215,	MSG-355
FEMFRA093,	MSG-189	FEMHCN216,	MSG-366
FEMFRA101,	MSG-201	FEMHCN217,	MSG-377
FEMFRA206,	MSG-252	FEMHCN220,	MSG-388
FEMFRA207,	MSG-263	FEMHIF021,	MSG-19
FEMFRA208,	MSG-275	FEMHSM030,	MSG-47
FEMFRA209,	MSG-286	FEMHSM048,	MSG-68
FEMFRA210,	MSG-297	FEMHSM057,	MSG-78
FEMFRA211,	MSG-309	FEMHSM058,	MSG-82
FEMFRA212,	MSG-320	FEMHSM139,	MSG-217
FEMFRA213,	MSG-331	FEMHSM252,	MSG-408
FEMFRA214,	MSG-343	FEMHSP004,	MSG-8
FEMFRA215,	MSG-354	FEMHSP013,	MSG-12
FEMFRA216,	MSG-365	FEMHSP017,	MSG-15
FEMFRA217,	MSG-377	FEMHSP030,	MSG-47
FEMFRA220,	MSG-387	FEMHSP040,	MSG-62
FEMFTN024,	MSG-28	FEMHSP053,	MSG-73
FEMFTN070,	MSG-95	FEMHSP054,	MSG-74
FEMFTN071,	MSG-108	FEMHSP055,	MSG-74
FEMFTN072,	MSG-121	FEMHSP070,	MSG-96
FEMFTN073,	MSG-132	FEMHSP071,	MSG-109
FEMFTN074,	MSG-144	FEMHSP072,	MSG-121
FEMFTN075,	MSG-155	FEMHSP073,	MSG-133
FEMFTN076,	MSG-166	FEMHSP074,	MSG-144
FEMFTN093,	MSG-189	FEMHSP075,	MSG-156
FEMFTN206,	MSG-252	FEMHSP076,	MSG-167
FEMFTN207,	MSG-264	FEMHSP082,	MSG-177
FEMFTN208,	MSG-275	FEMHSP083,	MSG-179
FEMFTN209,	MSG-286	FEMHSP160,	MSG-230
FEMFTN210,	MSG-298	FEMHSP170,	MSG-237
FEMFTN211,	MSG-309	FEMHSP206,	MSG-253
FEMFTN212,	MSG-320	FEMHSP207,	MSG-264
FEMFTN213,	MSG-332	FEMHSP208,	MSG-276
FEMFTN214,	MSG-343	FEMHSP209,	MSG-287
FEMFTN215,	MSG-354	FEMHSP210,	MSG-298
FEMFTN216,	MSG-366	FEMHSP211,	MSG-310
FEMFTN217,	MSG-377	FEMHSP212,	MSG-321
FEMHCN024,	MSG-29	FEMHSP213,	MSG-332

FEMHSP214,	MSG-344	FEMICN074,	MSG-145
FEMHSP215,	MSG-355	FEMICN075,	MSG-156
FEMHSP216,	MSG-366	FEMICN076,	MSG-168
FEMHSP217,	MSG-378	FEMICN093,	MSG-191
FEMHSP220,	MSG-388	FEMICN101,	MSG-202
FEMHSP225,	MSG-391	FEMICN206,	MSG-254
FEMHSP226,	MSG-391	FEMICN207,	MSG-265
FEMHSP289,	MSG-422	FEMICN208,	MSG-276
FEMHSP290,	MSG-424	FEMICN209,	MSG-288
FEMHSP291,	MSG-424	FEMICN210,	MSG-299
FEMHSP292,	MSG-425	FEMICN211,	MSG-310
FEMHSP293,	MSG-425	FEMICN212,	MSG-322
FEMHSP294,	MSG-426	FEMICN213,	MSG-333
FEMHSP295,	MSG-427	FEMICN214,	MSG-344
FEMHSP297,	MSG-428	FEMICN215,	MSG-356
FEMHSP298,	MSG-429	FEMICN216,	MSG-367
FEMHSP299,	MSG-430	FEMICN217,	MSG-378
FEMHSP300,	MSG-431	FEMICN220,	MSG-388
FEMHSP301,	MSG-432	FEMHIF021,	MSG-19
FEMHSP302,	MSG-433	FEMINT004,	MSG-9
FEMHSP305,	MSG-435	FEMINT040,	MSG-63
FEMHSP306,	MSG-435	FEMINT059,	MSG-84
FEMHSP312,	MSG-436	FEMINT060,	MSG-85
FEMHSP313,	MSG-436	FEMINT061,	MSG-85
FEMIAT004,	MSG-8	FEMINT062,	MSG-85
FEMIAT030,	MSG-48	FEMINT063,	MSG-86
FEMIAT040,	MSG-62	FEMINT064,	MSG-86
FEMIAT053,	MSG-73	FEMINT065,	MSG-86
FEMIAT054,	MSG-74	FEMINT066,	MSG-87
FEMIAT055,	MSG-75	FEMINT158,	MSG-228
FEMIAT070,	MSG-96	FEMIPL001,	MSG-7
FEMIAT071,	MSG-110	FEMIPL002,	MSG-7
FEMIAT072,	MSG-122	FEMIPL003,	MSG-8
FEMIAT073,	MSG-133	FEMIPL004,	MSG-9
FEMIAT074,	MSG-145	FEMIPL006,	MSG-10
FEMIAT075,	MSG-156	FEMIPL007,	MSG-11
FEMIAT076,	MSG-167	FEMIPL008,	MSG-11
FEMIAT083,	MSG-179	FEMIPL009,	MSG-11
FEMIAT093,	MSG-190	FEMIPL010,	MSG-12
FEMIAT206,	MSG-253	FEMIPL012,	MSG-12
FEMIAT207,	MSG-265	FEMIPL016,	MSG-15
FEMIAT208,	MSG-276	FEMIPL019,	MSG-17
FEMIAT209,	MSG-287	FEMIPL020,	MSG-17
FEMIAT210,	MSG-299	FEMIPL022,	MSG-22
FEMIAT211,	MSG-310	FEMIPL027,	MSG-43
FEMIAT212,	MSG-321	FEMIPL056,	MSG-77
FEMIAT213,	MSG-333	FEMIPL066,	MSG-88
FEMIAT214,	MSG-344	FEMIPL070,	MSG-97
FEMIAT215,	MSG-355	FEMIPL071,	MSG-110
FEMIAT216,	MSG-367	FEMIPL072,	MSG-122
FEMIAT217,	MSG-378	FEMIPL073,	MSG-134
FEMICN024,	MSG-29	FEMIPL074,	MSG-145
FEMICN025,	MSG-37	FEMIPL075,	MSG-157
FEMICN026,	MSG-40	FEMIPL076,	MSG-168
FEMICN030,	MSG-48	FEMIPL087,	MSG-181
FEMICN070,	MSG-97	FEMIPL093,	MSG-191
FEMICN071,	MSG-110	FEMIPL147,	MSG-225
FEMICN072,	MSG-122	FEMIPL150,	MSG-226
FEMICN073,	MSG-134	FEMIPL151,	MSG-226

FEM IPL161,	MSG-234	FEM J2R024,	MSG-30
FEM IPL163,	MSG-234	FEM J2R070,	MSG-98
FEM IPL165,	MSG-234	FEM J2R071,	MSG-111
FEM IPL191,	MSG-244	FEM J2R072,	MSG-123
FEM IPL203,	MSG-248	FEM J2R073,	MSG-135
FEM IPL206,	MSG-254	FEM J2R074,	MSG-146
FEM IPL207,	MSG-265	FEM J2R075,	MSG-158
FEM IPL208,	MSG-277	FEM J2R076,	MSG-169
FEM IPL209,	MSG-288	FEM J2R090,	MSG-184
FEM IPL210,	MSG-299	FEM J2R093,	MSG-192
FEM IPL211,	MSG-311	FEM J2R206,	MSG-255
FEM IPL212,	MSG-322	FEM J2R207,	MSG-266
FEM IPL213,	MSG-333	FEM J2R208,	MSG-278
FEM IPL214,	MSG-345	FEM J2R209,	MSG-289
FEM IPL215,	MSG-356	FEM J2R210,	MSG-300
FEM IPL216,	MSG-367	FEM J2R211,	MSG-312
FEM IPL217,	MSG-379	FEM J2R212,	MSG-323
FEM IPL219,	MSG-386	FEM J2R213,	MSG-334
FEM IPL220,	MSG-389	FEM J2R214,	MSG-346
FEM IPL237,	MSG-395	FEM J2R215,	MSG-357
FEM IPL238,	MSG-395	FEM J2R216,	MSG-368
FEM IPL239,	MSG-395	FEM J2R217,	MSG-380
FEM IPL240,	MSG-396	FEM J2S023,	MSG-25
FEM ISP030,	MSG-48	FEM J2S024,	MSG-30
FEM ISP048,	MSG-68	FEM J2S030,	MSG-50
FEM ISP057,	MSG-78	FEM J2S070,	MSG-99
FEM ISP058,	MSG-82	FEM J2S071,	MSG-112
FEM ISP139,	MSG-217	FEM J2S072,	MSG-124
FEM ISP252,	MSG-408	FEM J2S073,	MSG-135
FEM J2#048,	MSG-68	FEM J2S074,	MSG-147
FEM J2I021,	MSG-20	FEM J2S075,	MSG-158
FEM J2I030,	MSG-49	FEM J2S076,	MSG-169
FEM J2J082,	MSG-177	FEM J2S089,	MSG-184
FEM J2M023,	MSG-24	FEM J2S091,	MSG-185
FEM J2M024,	MSG-29	FEM J2S092,	MSG-186
FEM J2M030,	MSG-50	FEM J2S093,	MSG-192
FEM J2M070,	MSG-98	FEM J2S206,	MSG-255
FEM J2M071,	MSG-111	FEM J2S207,	MSG-267
FEM J2M072,	MSG-123	FEM J2S208,	MSG-278
FEM J2M073,	MSG-135	FEM J2S209,	MSG-289
FEM J2M074,	MSG-146	FEM J2S210,	MSG-301
FEM J2M075,	MSG-157	FEM J2S211,	MSG-312
FEM J2M076,	MSG-169	FEM J2S212,	MSG-323
FEM J2M089,	MSG-183	FEM J2S213,	MSG-335
FEM J2M091,	MSG-184	FEM J2S214,	MSG-346
FEM J2M092,	MSG-185	FEM J2S215,	MSG-357
FEM J2M093,	MSG-192	FEM J2S216,	MSG-369
FEM J2M206,	MSG-255	FEM J2S217,	MSG-380
FEM J2M207,	MSG-266	FEM J3E024,	MSG-31
FEM J2M208,	MSG-277	FEM J3E025,	MSG-37
FEM J2M209,	MSG-289	FEM J3E026,	MSG-41
FEM J2M210,	MSG-300	FEM J3E030,	MSG-50
FEM J2M211,	MSG-311	FEM J3E070,	MSG-99
FEM J2M212,	MSG-323	FEM J3E071,	MSG-112
FEM J2M213,	MSG-334	FEM J3E072,	MSG-124
FEM J2M214,	MSG-345	FEM J3E073,	MSG-136
FEM J2M215,	MSG-357	FEM J3E074,	MSG-147
FEM J2M216,	MSG-368	FEM J3E075,	MSG-158
FEM J2M217,	MSG-379	FEM J3E076,	MSG-170

FEMJ3E093, MSG-193
 FEMJ3E102, MSG-203
 FEMJ3E166, MSG-234
 FEMJ3E206, MSG-256
 FEMJ3E207, MSG-267
 FEMJ3E208, MSG-278
 FEMJ3E209, MSG-290
 FEMJ3E210, MSG-301
 FEMJ3E211, MSG-312
 FEMJ3E212, MSG-324
 FEMJ3E213, MSG-335
 FEMJ3E214, MSG-346
 FEMJ3E215, MSG-358
 FEMJ3E216, MSG-369
 FEMJ3E217, MSG-380
 FEMJ3I021, MSG-20
 FEMJ3I030, MSG-51
 FEMJ3S024, MSG-31
 FEMJ3S030, MSG-51
 FEMJ3S070, MSG-99
 FEMJ3S071, MSG-113
 FEMJ3S072, MSG-124
 FEMJ3S073, MSG-136
 FEMJ3S074, MSG-147
 FEMJ3S075, MSG-159
 FEMJ3S076, MSG-170
 FEMJ3S093, MSG-193
 FEMJ3S113, MSG-207
 FEMJ3S206, MSG-256
 FEMJ3S207, MSG-267
 FEMJ3S208, MSG-279
 FEMJ3S209, MSG-290
 FEMJ3S210, MSG-301
 FEMJ3S211, MSG-313
 FEMJ3S212, MSG-324
 FEMJ3S213, MSG-335
 FEMJ3S214, MSG-347
 FEMJ3S215, MSG-358
 FEMJ3S216, MSG-369
 FEMJ3S217, MSG-381
 FEMJS2030, MSG-49
 FEMJS2057, MSG-79
 FEMJS2058, MSG-83
 FEMJS2066, MSG-88
 FEMJS2070, MSG-97
 FEMJS2071, MSG-111
 FEMJS2072, MSG-123
 FEMJS2073, MSG-134
 FEMJS2074, MSG-146
 FEMJS2075, MSG-157
 FEMJS2076, MSG-168
 FEMJS2086, MSG-181
 FEMJS2087, MSG-181
 FEMJS2088, MSG-183
 FEMJS2093, MSG-191
 FEMJS2139, MSG-217
 FEMJS2167, MSG-235
 FEMJS2168, MSG-236
 FEMJS2170, MSG-237

FEMJS2197, MSG-246
 FEMJS2206, MSG-254
 FEMJS2207, MSG-266
 FEMJS2208, MSG-277
 FEMJS2209, MSG-288
 FEMJS2210, MSG-300
 FEMJS2211, MSG-311
 FEMJS2212, MSG-322
 FEMJS2213, MSG-334
 FEMJS2214, MSG-345
 FEMJS2215, MSG-356
 FEMJS2216, MSG-368
 FEMJS2217, MSG-379
 FEMJS2228, MSG-392
 FEMJS2241, MSG-396
 FEMJS2252, MSG-408
 FEMJS2303, MSG-434
 FEMJS3030, MSG-49
 FEMJS3048, MSG-69
 FEMJS3057, MSG-79
 FEMJS3058, MSG-83
 FEMJS3139, MSG-218
 FEMJS3252, MSG-409
 FEMLIB004, MSG-9
 FEMLIB022, MSG-23
 FEMLIB040, MSG-63
 FEMLIB044, MSG-65
 FEMLIB045, MSG-65
 FEMLIB048, MSG-69
 FEMLIB066, MSG-88
 FEMLIB087, MSG-182
 FEMLIB160, MSG-230
 FEMLIB191, MSG-245
 FEMLIB220, MSG-389
 FEMLIB269, MSG-416
 FEMLIB270, MSG-416
 FEMLIB271, MSG-416
 FEMLIB272, MSG-417
 FEMLIB274, MSG-417
 FEMLIB275, MSG-418
 FEMLIB276, MSG-418
 FEMLIB277, MSG-418
 FEMLIB278, MSG-419
 FEMLIB279, MSG-419
 FEMLIB280, MSG-419
 FEMLIB281, MSG-420
 FEMLIB282, MSG-420
 FEMLIB286, MSG-422
 FEMLIM033, MSG-59
 FEMLIM034, MSG-60
 FEMLOD013, MSG-13
 FEMLOD014, MSG-14
 FEMLOD015, MSG-15
 FEMLOD017, MSG-16
 FEMLOD018, MSG-17
 FEMLOD066, MSG-89
 FEMLOD077, MSG-175
 FEMLOD079, MSG-176
 FEMLOD080, MSG-176

FEMLOD081,	MSG-176	FEMPRE138,	MSG-215
FEMLOD082,	MSG-178	FEMPW1268,	MSG-416
FEMLOD171,	MSG-238	FEMQRY048,	MSG-69
FEMLOD198,	MSG-247	FEMQRY087,	MSG-182
FEMLOD202,	MSG-248	FEMRAC030,	MSG-52
FEMLOD267,	MSG-415	FEMRAC048,	MSG-70
FEMLOD287,	MSG-422	FEMRAC057,	MSG-80
FEMLOD297,	MSG-428	FEMRAC058,	MSG-83
FEMLOD298,	MSG-429	FEMRAC139,	MSG-218
FEMLOD299,	MSG-430	FEMRAC252,	MSG-409
FEMLOD300,	MSG-431	FEMRAC285,	MSG-421
FEMLOD301,	MSG-432	FEMRC2030,	MSG-52
FEMLOD302,	MSG-433	FEMRCN024,	MSG-32
FEMLOD304,	MSG-434	FEMRCN025,	MSG-38
FEMLOD307,	MSG-435	FEMRCN026,	MSG-41
FEMLOK024,	MSG-31	FEMRCN030,	MSG-52
FEMLOK029,	MSG-44	FEMRCN070,	MSG-100
FEMLOK070,	MSG-100	FEMRCN071,	MSG-113
FEMLOK071,	MSG-113	FEMRCN072,	MSG-125
FEMLOK072,	MSG-125	FEMRCN073,	MSG-137
FEMLOK073,	MSG-136	FEMRCN074,	MSG-148
FEMLOK074,	MSG-148	FEMRCN075,	MSG-159
FEMLOK075,	MSG-159	FEMRCN076,	MSG-171
FEMLOK076,	MSG-170	FEMRCN093,	MSG-194
FEMLOK093,	MSG-193	FEMRCN101,	MSG-202
FEMLOK206,	MSG-256	FEMRCN206,	MSG-257
FEMLOK207,	MSG-268	FEMRCN207,	MSG-268
FEMLOK208,	MSG-279	FEMRCN208,	MSG-279
FEMLOK209,	MSG-290	FEMRCN209,	MSG-291
FEMLOK210,	MSG-302	FEMRCN210,	MSG-302
FEMLOK211,	MSG-313	FEMRCN211,	MSG-313
FEMLOK212,	MSG-324	FEMRCN212,	MSG-325
FEMLOK213,	MSG-336	FEMRCN213,	MSG-336
FEMLOK214,	MSG-347	FEMRCN214,	MSG-347
FEMLOK215,	MSG-358	FEMRCN215,	MSG-359
FEMLOK216,	MSG-370	FEMRCN216,	MSG-370
FEMLOK217,	MSG-381	FEMRCN217,	MSG-381
FEMMIS030,	MSG-51	FEMRCN220,	MSG-389
FEMMIS048,	MSG-69	FEMRD1030,	MSG-53
FEMMIS057,	MSG-79	FEMRD1144,	MSG-221
FEMMIS058,	MSG-83	FEMRD1145,	MSG-221
FEMMIS139,	MSG-218	FEMREL030,	MSG-53
FEMMIS252,	MSG-409	FEMREL046,	MSG-66
FEMNUL035,	MSG-60	FEMREL048,	MSG-70
FEMPRE123,	MSG-210	FEMREL057,	MSG-80
FEMPRE124,	MSG-210	FEMREL082,	MSG-178
FEMPRE125,	MSG-211	FEMREL084,	MSG-180
FEMPRE126,	MSG-211	FEMREL085,	MSG-180
FEMPRE127,	MSG-211	FEMREL104,	MSG-204
FEMPRE128,	MSG-212	FEMREL154,	MSG-227
FEMPRE129,	MSG-212	FEMREL155,	MSG-228
FEMPRE130,	MSG-212	FEMREL160,	MSG-230
FEMPRE131,	MSG-213	FEMREL170,	MSG-237
FEMPRE132,	MSG-213	FEMREL171,	MSG-238
FEMPRE133,	MSG-213	FEMREL196,	MSG-246
FEMPRE134,	MSG-214	FEMREL197,	MSG-247
FEMPRE135,	MSG-214	FEMREL204,	MSG-249
FEMPRE136,	MSG-214	FEMREL205,	MSG-249
FEMPRE137,	MSG-214	FEMREL229,	MSG-393

FEMREL236,	MSG-394	FEMTCN070,	MSG-101
FEMREL296,	MSG-427	FEMTCN071,	MSG-114
FEMRIF021,	MSG-20	FEMTCN072,	MSG-126
FEMS19013,	MSG-13	FEMTCN073,	MSG-137
FEMS19017,	MSG-16	FEMTCN074,	MSG-149
FEMS19194,	MSG-246	FEMTCN075,	MSG-160
FEMS22013,	MSG-14	FEMTCN076,	MSG-171
FEMS22017,	MSG-16	FEMTCN093,	MSG-195
FEMS22194,	MSG-246	FEMTCN101,	MSG-203
FEMSAF030,	MSG-53	FEMTCN206,	MSG-257
FEMSAF048,	MSG-70	FEMTCN207,	MSG-269
FEMSAF057,	MSG-80	FEMTCN208,	MSG-280
FEMSAF058,	MSG-84	FEMTCN209,	MSG-291
FEMSAF139,	MSG-219	FEMTCN210,	MSG-303
FEMSAF252,	MSG-410	FEMTCN211,	MSG-314
FEMSCH030,	MSG-54	FEMTCN212,	MSG-325
FEMSCN024,	MSG-32	FEMTCN213,	MSG-337
FEMSCN025,	MSG-38	FEMTCN214,	MSG-348
FEMSCN026,	MSG-41	FEMTCN215,	MSG-359
FEMSCN030,	MSG-54	FEMTCN216,	MSG-371
FEMSCN070,	MSG-101	FEMTCN217,	MSG-382
FEMSCN071,	MSG-114	FEMTCN220,	MSG-390
FEMSCN072,	MSG-126	FEMTEX261,	MSG-413
FEMSCN073,	MSG-137	FEMTEX262,	MSG-414
FEMSCN074,	MSG-148	FEMTEX263,	MSG-414
FEMSCN075,	MSG-160	FEMTHI022,	MSG-23
FEMSCN076,	MSG-171	FEMTHI093,	MSG-195
FEMSCN093,	MSG-194	FEMTIF021,	MSG-21
FEMSCN101,	MSG-203	FEMTPS004,	MSG-10
FEMSCN206,	MSG-257	FEMTPS022,	MSG-23
FEMSCN207,	MSG-268	FEMTPS027,	MSG-43
FEMSCN208,	MSG-280	FEMTPS040,	MSG-63
FEMSCN209,	MSG-291	FEMTPS057,	MSG-81
FEMSCN210,	MSG-302	FEMTPS059,	MSG-85
FEMSCN211,	MSG-314	FEMTPS066,	MSG-89
FEMSCN212,	MSG-325	FEMTPS070,	MSG-101
FEMSCN213,	MSG-336	FEMTPS071,	MSG-114
FEMSCN214,	MSG-348	FEMTPS072,	MSG-126
FEMSCN215,	MSG-359	FEMTPS073,	MSG-138
FEMSCN216,	MSG-370	FEMTPS074,	MSG-149
FEMSCN217,	MSG-382	FEMTPS075,	MSG-160
FEMSCN220,	MSG-390	FEMTPS076,	MSG-172
FEMSIF021,	MSG-21	FEMTPS087,	MSG-182
FEMSMF030,	MSG-54	FEMTPS093,	MSG-195
FEMSMF048,	MSG-71	FEMTPS160,	MSG-231
FEMSMF057,	MSG-81	FEMTPS167,	MSG-235
FEMSMF058,	MSG-84	FEMTPS172,	MSG-238
FEMSMF139,	MSG-219	FEMTPS176,	MSG-239
FEMSMF252,	MSG-410	FEMTPS177,	MSG-240
FEMSMF284,	MSG-421	FEMTPS179,	MSG-241
FEMSTM048,	MSG-71	FEMTPS180,	MSG-241
FEMSTM265,	MSG-415	FEMTPS181,	MSG-241
FEMSVU006,	MSG-10	FEMTPS182,	MSG-241
FEMSVU048,	MSG-71	FEMTPS183,	MSG-242
FEMSVU156,	MSG-228	FEMTPS184,	MSG-242
FEMTCN024,	MSG-33	FEMTPS186,	MSG-243
FEMTCN025,	MSG-38	FEMTPS187,	MSG-243
FEMTCN026,	MSG-42	FEMTPS206,	MSG-258
FEMTCN030,	MSG-55	FEMTPS207,	MSG-269

FEMTPS208,	MSG-280	FEMUSI212,	MSG-326
FEMTPS209,	MSG-292	FEMUSI213,	MSG-338
FEMTPS210,	MSG-303	FEMUSI214,	MSG-349
FEMTPS211,	MSG-314	FEMUSI215,	MSG-360
FEMTPS212,	MSG-326	FEMUSI216,	MSG-372
FEMTPS213,	MSG-337	FEMUSI217,	MSG-383
FEMTPS214,	MSG-348	FEMUSI232,	MSG-393
FEMTPS215,	MSG-360	FEMUSO030,	MSG-56
FEMTPS216,	MSG-371	FEMUSO149,	MSG-226
FEMTPS217,	MSG-382	FEMUSO152,	MSG-227
FEMTSO030,	MSG-55	FEMUTL030,	MSG-56
FEMTSO048,	MSG-71	FEMUTL114,	MSG-207
FEMTSO057,	MSG-81	FEMUTL115,	MSG-207
FEMTSO058,	MSG-84	FEMUTL116,	MSG-208
FEMTSO139,	MSG-220	FEMUTL117,	MSG-208
FEMTSO252,	MSG-410	FEMUTL118,	MSG-208
FEMU29283,	MSG-420	FEMUTL119,	MSG-209
FEMU29284,	MSG-421	FEMUTL120,	MSG-209
FEMUJI024,	MSG-33	FEMUTL193,	MSG-246
FEMUJI030,	MSG-55	FEMUXA201,	MSG-248
FEMUJI036,	MSG-60	FEMUXW199,	MSG-247
FEMUJI070,	MSG-102	FEMUXW200,	MSG-248
FEMUJI071,	MSG-115	FEMVCN024,	MSG-34
FEMUJI072,	MSG-127	FEMVCN030,	MSG-57
FEMUJI073,	MSG-138	FEMVCN067,	MSG-91
FEMUJI074,	MSG-149	FEMVCN069,	MSG-91
FEMUJI075,	MSG-161	FEMVCN070,	MSG-103
FEMUJI076,	MSG-172	FEMVCN071,	MSG-116
FEMUJI093,	MSG-196	FEMVCN072,	MSG-127
FEMUJI122,	MSG-210	FEMVCN073,	MSG-139
FEMUJI206,	MSG-258	FEMVCN074,	MSG-150
FEMUJI207,	MSG-269	FEMVCN075,	MSG-161
FEMUJI208,	MSG-281	FEMVCN076,	MSG-173
FEMUJI209,	MSG-292	FEMVCN093,	MSG-196
FEMUJI210,	MSG-303	FEMVCN206,	MSG-259
FEMUJI211,	MSG-315	FEMVCN207,	MSG-270
FEMUJI212,	MSG-326	FEMVCN208,	MSG-281
FEMUJI213,	MSG-337	FEMVCN209,	MSG-293
FEMUJI214,	MSG-349	FEMVCN210,	MSG-304
FEMUJI215,	MSG-360	FEMVCN211,	MSG-315
FEMUJI216,	MSG-371	FEMVCN212,	MSG-327
FEMUJI217,	MSG-383	FEMVCN213,	MSG-338
FEMUSI022,	MSG-24	FEMVCN214,	MSG-349
FEMUSI024,	MSG-33	FEMVCN215,	MSG-361
FEMUSI030,	MSG-56	FEMVCN216,	MSG-372
FEMUSI070,	MSG-102	FEMVCN217,	MSG-383
FEMUSI071,	MSG-115	FEMW21038,	MSG-61
FEMUSI072,	MSG-127	FEMW21039,	MSG-62
FEMUSI073,	MSG-138	FEMW21066,	MSG-90
FEMUSI074,	MSG-150	FEMW21160,	MSG-231
FEMUSI075,	MSG-161	FEMW21191,	MSG-245
FEMUSI076,	MSG-172	FEMW21192,	MSG-245
FEMUSI093,	MSG-196	FEMWTO037,	MSG-61
FEMUSI206,	MSG-258	FEMX00021,	MSG-21
FEMUSI207,	MSG-270	FEMX00030,	MSG-57
FEMUSI208,	MSG-281	FEMX00069,	MSG-236
FEMUSI209,	MSG-292	FEMX00082,	MSG-178
FEMUSI210,	MSG-304	FEMX00227,	MSG-392
FEMUSI211,	MSG-315	FEMX02109,	MSG-205

FEMX02146, MSG-222
 FEMX04146, MSG-222
 FEMX05023, MSG-25
 FEMX05024, MSG-34
 FEMX05070, MSG-103
 FEMX05071, MSG-116
 FEMX05072, MSG-128
 FEMX05073, MSG-139
 FEMX05074, MSG-150
 FEMX05075, MSG-162
 FEMX05076, MSG-173
 FEMX05093, MSG-197
 FEMX05146, MSG-222
 FEMX05206, MSG-259
 FEMX05207, MSG-270
 FEMX05208, MSG-282
 FEMX05209, MSG-293
 FEMX05210, MSG-304
 FEMX05211, MSG-316
 FEMX05212, MSG-327
 FEMX05213, MSG-338
 FEMX05214, MSG-350
 FEMX05215, MSG-361
 FEMX05216, MSG-372
 FEMX05217, MSG-384
 FEMX06030, MSG-57
 FEMX06100, MSG-200
 FEMX06146, MSG-222
 FEMX06148, MSG-225
 FEMX06219, MSG-386
 FEMX06222, MSG-390
 FEMX06230, MSG-393
 FEMX06234, MSG-394
 FEMX09030, MSG-58
 FEMX09223, MSG-390
 FEMX09224, MSG-391
 FEMX24055, MSG-77
 FEMX24083, MSG-180
 FEMX24146, MSG-223

FEMX24226, MSG-391
 FEMX24245, MSG-401
 FEMX24289, MSG-423
 FEMX24291, MSG-424
 FEMX24292, MSG-425
 FEMX24293, MSG-426
 FEMX24294, MSG-426
 FEMX24295, MSG-427
 FEMX32146, MSG-223
 FEMX32153, MSG-227
 FEMX32160, MSG-231
 FEMX32249, MSG-404
 FEMX44146, MSG-223
 FEMX44219, MSG-387
 FEMX49030, MSG-58
 FEMX49249, MSG-404
 FEMxxx000, MSG-7
 Message Module Identifier, MSG-5
 Not Cataloged 2, MSG-4
 SYSLOG Message Format, MSG-5
 System Code Format, MSG-1
 TSO Message Format, MSG-5

S

System Codes

AFF-0000, MSG-1
 AFF-0004, MSG-1
 AFF-0008, MSG-1
 AFF-0012, MSG-2
 AFF-0016, MSG-2
 AFF-0020, MSG-2
 AFF-0024, MSG-2
 AFF-0028, MSG-3
 AFF-0032, MSG-3
 AFF-0036, MSG-3
 Format, MSG-1
 User Completion Code, MSG-1

Reader's Comment Form

The success of this manual depends solely on its usefulness to you. To ensure such usefulness, we solicit your comments concerning the clarity, accuracy, completeness, and organization of this manual. Please enter your comments below and mail this form to the address on the front page of this manual. If you wish a reply, give your name, company, and mailing address. We would also appreciate an indication of your occupation and how you use this manual.

Please rate this manual on the following points:

accurate	1	2	3	4	5	inaccurate
readable	1	2	3	4	5	unreadable
well laid out	1	2	3	4	5	badly laid out
well organized	1	2	3	4	5	badly organized
easy to understand	1	2	3	4	5	incomprehensible
has enough examples	1	2	3	4	5	has too few examples

Thank you for your time and effort.