

IBM Rational Portfolio Manager Version 6.1.1.5 DB2 for Windows Migration Guide

Revision: 1.0

Last Revision: 16.09.2005

Licensed Materials – Property of IBM

(C) Copyright IBM Corp. 1997, 2005

US Government Users Restricted Rights –

Use, duplication or disclosure restricted by

GSA ADP Schedule Contract with IBM Corp.

TABLE OF CONTENTS

SCOPE.....	3
AUDIENCE.....	3
ASSUMPTIONS	3
PRE-MIGRATION STEPS	4
INSTRUCTIONS	4

SCOPE

This document outlines the steps to migrate IBM Rational Portfolio Manager Database from Version 6.1.1.4 to 6.1.1.5

AUDIENCE

This document is intended for Database Administrators, Application Servers administrators and/or personnel responsible for the installation and configuration of IBM Rational Portfolio Manager server environment.

ASSUMPTIONS

It's assumed that your RPM database is at 6.1.1.4 level (Code and Schema). If it is not, please follow the upgrade steps as outlined below.

RPM supports incremental database migration procedure, which means you have to gradually apply the subsequent database migrations.

Ex:

I) 5.0.x.x

5.0.x.x → 6.0.0.0
6.0.0.0 → 6.0.0.1
6.0.0.1 → 6.1.0.0
6.1.0.0 → 6.1.1.1
6.1.1.2 → 6.1.1.3
6.1.1.3 → 6.1.1.4
6.1.1.4 → 6.1.1.5

II) 6.0.x.x

6.0.0.1 → 6.1.0.0
6.1.0.0 → 6.1.1.1
6.1.1.2 → 6.1.1.3
6.1.1.3 → 6.1.1.4
6.1.1.4 → 6.1.1.5

...

PRE-MIGRATION STEPS

Before you proceed you need to backup the IBM Rational Portfolio Manager database. Make sure that total recovery of the database is possible from this backup. All database migration instructions listed below must be done by the instance owner and the user used to connect to the database from the web server.

INSTRUCTIONS

1- Stop the web application, the Alert server associated with the RPM database.

2- Open db2 command window (DB2CMD) under RPM Database instance owner and perform the following: Stop and start the DB2 instance in which the RPM database is created in. Run:

```
db2 force applications all
db2stop force
db2start
```

3- Go to %MIGPACKAGE_HOME%\Database\DB2\Migration\6.1.1.4_6.1.1.5, for DB2 V7 database

- i. Execute db2_setV7 by typing at the prompt: db2_setV7.bat
- ii. Execute db_cfgV7 by typing at the prompt: db_cfgV7.bat DBNAME

DBNAME is the database name you are migrating

- iii. Execute dbm_cfgV7 by typing at the prompt: dbm_cfgV7.bat

For DB2 V8 databases

- i. Execute db2_setV8 by typing at the prompt: db2_setV8.bat
- ii. Execute db_cfgV8 by typing at the prompt: db_cfgV8.bat DBNAME

DBNAME is the database name you are migrating

iii. Execute dbm_cfgV8 by typing at the prompt: dbm_cfgV8.bat
4- Open migration.sql for editing, replace DBNAME with the name of RPM Database Name, USERNAME with the instance owner's userName, USERPSSWD with its password and DBSCHEMA to the schema of db you are running against.

Then run:

```
db2 -tvf migration.sql -z migration.out
```

If no error move to the next step

5- Go to %MIGPACKAGE_HOME%\Database\DB2\CSP\V8 (V7 folder if you are migrating RPM under DB2 V7.2), run createsp.bat by typing:

```
createsp DBNAME USERNAME PASSWORD
```

DBNAME is the name of the database
USERNAME is the username of the user that is used to connect to the database from web application PASSWORD is its password

If no error move to the next step

6- Build database. Follow the steps below:

a. Run bindall.bat by typing:

```
bindall DBNAME USERNAME PASSWORD DBSCHEMA
```

DBNAME is the name of the database
USERNAME is the username of the user that is used to connect to database from web application PASSWORD is its password DBSCHEMA is the schema name you are running against

b. After bind is finished, verify if pmoffice.dll is copied to both %DB2FencedHome% and %DB2UnfencedHome% directories. If not copy it manually to both locations.

7- Go to %MIGPACKAGE_HOME%\Database\DB2\Migration\6.1.1.4_6.1.1.5, open Reorgstats.sql for editing, replace DBNAME with the name of RPM

Database Name, USERNAME with the instance owner's userName, USERPSSWD with its password and DBSCHEMA to the schema of db you are running against.

Then run:

```
db2 -tvf Reorgstats.sql -z Reorgstats.out
```

8- Go to %MIGPACKAGE_HOME%\WebServer folder, copy RPMVersion.xml file to %IBMRPM_WAR_HOME%\WEB-INF\classes folder.

9- Copy RPM installers from the %MIGPACKAGE_HOME%\Clients to %IBMRPM_WAR_HOME%\client_installer of the WebServer. %MIGPACKAGE_HOME% is the folder where the package was extracted % IBMRPM_WAR_HOME % is the folder of web server application where client installers are

10- Start the web application, after making sure RPM database is started.