

IBM Software

Getting Started with IBM Backup and Restore Manager for z/VM

VMSES/E Installation, SFS Setup, and Initial Configuration on z/VM V6.2 or V6.3

Tracy Dean, IBM tld1@us.ibm.com August 2013

© 2013 IBM Corporation

2



Important Disclaimer

- THE INFORMATION CONTAINED IN THIS PRESENTATION IS PROVIDED FOR INFORMATIONAL PURPOSES ONLY.
- WHILE EFFORTS WERE MADE TO VERIFY THE COMPLETENESS AND ACCURACY OF THE INFORMATION CONTAINED IN THIS PRESENTATION, IT IS PROVIDED "AS IS", WITHOUT WARRANTY OF ANY KIND, EXPRESS OR IMPLIED.
- IN ADDITION, THIS INFORMATION IS BASED ON IBM'S CURRENT PRODUCT PLANS AND STRATEGY, WHICH ARE SUBJECT TO CHANGE BY IBM WITHOUT NOTICE.
- IBM SHALL NOT BE RESPONSIBLE FOR ANY DAMAGES ARISING OUT OF THE USE OF, OR OTHERWISE RELATED TO, THIS PRESENTATION OR ANY OTHER DOCUMENTATION.
- NOTHING CONTAINED IN THIS PRESENTATION IS INTENDED TO, OR SHALL HAVE THE EFFECT OF:
 - CREATING ANY WARRANTY OR REPRESENTATION FROM IBM (OR ITS AFFILIATES OR ITS OR THEIR SUPPLIERS AND/OR LICENSORS); OR
 - ALTERING THE TERMS AND CONDITIONS OF THE APPLICABLE LICENSE AGREEMENT GOVERNING THE USE OF IBM SOFTWARE.



Agenda

3

- Assumptions
- Preparing to install
- Installing using VMSES/E
- Configuring
- Verifying installation and configuration

IBM Software

_	
-	 ==
_	
	 = 7 =

Assumptions

Installing on z/VM V6.2 or z/VM V6.3

- Standalone system, no SSI cluster
- See separate presentation for z/VM V5.4 or V6.1
- DIRMAINT is installed for directory management
 - MAINT620 or MAINT630 is authorized to issue AMDISK commands
 - AUTOG is available for group USER for minidisk definitions
- Shared File System is available
- Installation ID is 5697J06B
 - No PPF overrides
- 3390 DASD

4

- REXX Library (5695-014) is installed and available
 - Alternatively use free download of REXX Alternate Library at: http://www.ibm.com/software/awdtools/rexx/rexxzseries/altlibrary.html
 - Strongly suggest installing this on MAINT620 or MAINT630 19E to simplify access to it
- Installing on minidisk (not SFS)
- Operations Manager is running on user ID OPMGRM1
- Tape Manager is installed and running, or tapes are mounted manually via messages to the OPERATOR console
- This is not the only way to perform the install
 - Not all options are discussed
 - See product documentation for full details



Don't Forget

5

If you are also installing Operations Manager, install it first

REXX must already be installed and available

- REXX Library (5695-014), or
- REXX Alternate Library, free download at: http://www.ibm.com/software/awdtools/rexx/rexxzseries/altlibrary. html
- Strongly suggest installing this on MAINT620 or MAINT630 19E to simplify access to it
 - If on MAINT620 or MAINT630 19E, make sure all files have filemode number of 2 (not the default of 1)
 - Required for loading into the CMS saved segment
- More information about running Backup and Restore Manager in a z/VM V6.2 or later environment:

http://www.ibm.com/support/docview.wss?rs=0&context=SSMR4R&q1=SSI&uid=swg21615651



IBM Software

Preparing to Install

Create installation ID Create an SFS server Prepare system for VMSES/E installation

© 2013 IBM Corporation

IBM Software



Define the Installation ID: 5697J06B

From MAINT620 or MAINT630

Create a file called 5697J06B DIRECT

USER 5697J06B password 64M 256M BG * 5697-J06 - SES install & admin for Backup Mgr V1.2 MACHINE ESA IPL CMS OPTION LNKNOPAS CONSOLE 01F 3215 SPOOL 00C 2540 READER A SPOOL 00D 2540 PUNCH A SPOOL 00E 1403 A LINK MAINT 190 190 RR LINK MAINT 19D 19D R LINK MAINT 19E 19E RR LINK MAINT 51D 51D MR LINK MAINT 555 5E5 RR

- Issue the command DIRM ADD 5697J06B

_	
-	
-	

Define the Installation ID: 5697J06B

Add required minidisks

8

- From MAINT620 or MAINT630, issue

DIRMFOR5697J06BAMD1913390AUTOG40USERMRPW<readpw><writepw></multpw>DIRMFOR5697J06BAMD1983390AUTOG2USERMRPW<readpw><writepw><multpw>DIRMFOR5697J06BAMD1993390AUTOG5USERMRPW<readpw><writepw><multpw>DIRMFOR5697J06BAMD2A23390AUTOG1USERMRPW<readpw><writepw><multpw>DIRMFOR5697J06BAMD2A63390AUTOG1USERMRPW<readpw><writepw><multpw>DIRMFOR5697J06BAMD2A63390AUTOG1USERMRPW<readpw><writepw><multpw>DIRMFOR5697J06BAMD2A23390AUTOG5USERMRPW<readpw><writepw><multpw>DIRMFOR5697J06BAMD2C23390AUTOG2USERMRPW<readpw><writepw><multpw>DIRMFOR5697J06BAMD2D23390AUTOG7USERMRPW<readpw><writepw><multpw>DIRMFOR5697J06BAMD4913390AUTOG7USERMRPW<readpw><writepw><multpw>DIRMFOR5697J06BAMD</

_	
_	
_	
_	

9

Resulting Minidisk Statements in Directory Entry for 5697J06B

MDISK 0191 3390 <start> 040 <vol> MR <readpw> <writepw> <multpw> MDISK 0198 3390 <start> 002 <vol> MR <readpw> <writepw> <multpw> MDISK 0199 3390 <start> 005 <vol> MR <readpw> <writepw> <multpw> MDISK 02A2 3390 <start> 001 <vol> MR <readpw> <writepw> <multpw> MDISK 02A6 3390 <start> 001 <vol> MR <readpw> <writepw> <multpw> MDISK 02B2 3390 <start> 005 <vol> MR <readpw> <writepw> <multpw> MDISK 02C2 3390 <start> 002 <vol> MR <readpw> <writepw> <multpw> MDISK 02D2 3390 <start> 050 <vol> MR <readpw> <writepw> <multpw> MDISK 0491 3390 <start> 007 <vol> MR <readpw> <writepw> <multpw> MDISK 0492 3390 <start> 007 <vol> MR <readpw> <writepw> <multpw> MDISK 049D 3390 <start> 005 <vol> MR <readpw> <writepw> <multpw> MDISK 0591 3390 <start> 007 <vol> MR <readpw> <writepw> <multpw> MDISK 0592 3390 <start> 007 <vol> MR <readpw> <writepw> <multpw>

_	
_	
_	
_	

Format All Minidisks

From MAINT620 or MAINT630, issue

link 5697J06B 191 333 MR

format 333 z

10

release z (det

Repeat for each 5697J06B disk



Create New SFS Server and File Pool

Background

- Backup catalog is stored in SFS
 - Separate file pool dedicated to Backup is recommended
 - Should not use VMSYS: or VMSYSU:
 - We'll use BKRSFS: here, with BKRSVSFS as the server
- Recommend starting with at least 3000 cylinders
 - Large sites will need more
 - Your mileage may vary



- Need space for service machine work areas also
 - We'll use BKRSFS: for this also
- Recommend putting Backup Manager TEMPLATE and DISKPOOL files in SFS also. We'll use BKRSFS for this also.
- BKRSVSFS is a repository file pool server
 - Does not perform Coordinated Resource Recovery (CRR)
- Reference: "CMS File Pool Planning, Administration, and Operation" (SC24-6074)



Create New SFS Server: BKRSVSFS

- From MAINT620 or MAINT630, create and add directory entry for BKRSVSFS, using most of the sample values
 - Same procedure used to create user ID 5679J06B
 - Do not format the disks after you've added them


BKRSVSFS DIRECT		
USER BKRSVSFS password 6	4M 64M BG	
OPTION MAXCONN 2000 NOMD	CFS APPLMON QUICKDSP SVMSTAT	
SHARE REL 1500	ired to use data apaces	
MACHINE XC	ired to use data spaces	
IUCV ALLOW		
IUCV *IDENT RESANY GLOBA	L	
IPL CMS	Make Ops Mgr the secondary console	
CONSOLE 009 3215 T OPMGR	M1	
SPOOL 00C 2540 READER *		
SPOOL 00D 2540 PUNCH A		
SPOOL 00E 1403		
LINK MAINT 190 190 RR		
LINK MAINT 193 193 RR		
LINK MAINT 19D 19D RR		
LINK MAINT 19E 19E RR		
Issue the command		
DIRM ADD BKRSVSFS		

Getting Started with IBM Backup and Restore Manager for z/VM on z/VM V6.2 or V6.3 August 2013 © 2013 IBM Corporation



BKRSVSFS Directory Entry (continued)

From MAINT620 or MAINT630, issue



Resulting Minidisk Statements in Directory Entry for BKRSVSFS

MDISK 0191 3390 <start> 002 <vol> MR <readpw> <writepw> <multpw> MDISK 0250 3390 <start> 080 <vol> MR <readpw> <writepw> <multpw> MINIOPT NOMDC

MDISK 0405 3390 <start> 010 <vol> MR <readpw> <writepw> <multpw> MINIOPT NOMDC

MDISK 0406 3390 <start> 010 <vol> MR <readpw> <writepw> <multpw> MINIOPT NOMDC

MDISK 0260 3390 <start> 050 <vol> MR <readpw> <writepw> <multpw>
MDISK 0310 3390 <start> 750 <vol> MR <readpw> <writepw> <multpw>
MDISK 0311 3390 <start> 750 <vol> MR <readpw> <writepw> <multpw>
MDISK 0312 3390 <start> 750 <vol> MR <readpw> <writepw> <multpw>
MDISK 0313 3390 <start> 750 <vol> MR <readpw> <writepw> <multpw>



Initial SFS Server Setup: BKRSVSFS

- Logoff MAINT620 or MAINT630
- Logon to BKRSVSFS
- Format 191 disk
 - From BKRSVSFS, issue

format 191 a

Create a PROFILE EXEC on the 191 (A) disk, containing

```
/* */
'ACCESS 193 C'
'CP SET EMSG ON'
'CP SET PF11 RETRIEVE FORWARD'
'CP SET PF12 RETRIEVE'
Exit 0
```

Run the PROFILE


profile

16



Define Startup Parameters for SFS Server: BKRSVSFS

• On BKRSVSFS 191 disk, create a file called BKRSVSFS DMSPARMS, containing:



| IBM Software

IBM	_	
	-	

Generate the File Pool BKRSFS

From BKRSVSFS, issue

fileserv generate

 When prompted in \$\$TEMP \$POOLDEF, delete the existing lines and enter the following lines instead

MAXUSERS=4000	
MAXDISKS=500	
DDNAME=CONTROL	VDEV=250
DDNAME=LOG1	VDEV=405
DDNAME=LOG2	VDEV=406
DDNAME=MDK00001	VDEV=260 GROUP=1 BLOCKS=0
DDNAME=MDK00002	VDEV=310 GROUP=2 BLOCKS=0
DDNAME=MDK00003	VDEV=311 GROUP=2 BLOCKS=0
DDNAME=MDK00004	VDEV=312 GROUP=2 BLOCKS=0
DDNAME=MDK00005	VDEV=313 GROUP=2 BLOCKS=0

- Note: when you leave XEDIT in the next step, z/VM will format the minidisks listed above. This may take a long time, depending on their size. Please be patient.
- Enter file on the XEDIT command line

18



Final SFS Server Tasks for BKRSVSFS

- Start the server
 - From BKRSVSFS,
 - Add the following at the end of PROFILE EXEC (before the Exit statement):
 - 'EXEC FILESERV START'
 - Save the changes and exit file
 - Run the PROFILE EXEC profile
 - Leave the server running disconnected #cp disc



Set Up 5697J06B

Create a PROFILE EXEC on the 191 (A) disk, containing

- /* */
- 'CP SET PF11 RETRIEVE FORWARD'
- 'CP SET PF12 RETRIEVE'
- Exit O

Run the PROFILE

profile

19



Authorize Users and Create Directories in SFS

Authorize service machines to space in SFS

- From 5697J06B, issue

enroll user bkradmin bkrsfs (blocks 4000 storgroup 2 enroll user bkrbkup bkrsfs (blocks 4000 storgroup 2 enroll user bkrcatlg bkrsfs (blocks 500000 storgroup 2 enroll user bkrwrk01 bkrsfs (blocks 20000 storgroup 2 enroll user bkrwrk02 bkrsfs (blocks 20000 storgroup 2 enroll user bkrwrk03 bkrsfs (blocks 20000 storgroup 2 enroll user bkrwrk04 bkrsfs (blocks 20000 storgroup 2

Create required SFS directory entries

- From 5697J06B, issue

create directory bkrsfs:bkradmin.workarea create directory bkrsfs:bkradmin.jobdefs create directory bkrsfs:bkrcatlg.workarea create directory bkrsfs:bkrbkup.workarea create directory bkrsfs:bkrwrk01.workarea create directory bkrsfs:bkrwrk02.workarea create directory bkrsfs:bkrwrk03.workarea

 Authorize additional users to create and update backup job templates (e.g. MAINT, MAINT620, MAINT630, and other admin user IDs)

grant auth bkrsfs:bkradmin.jobdefs to <userid> (write newwrite
grant auth * * bkrsfs:bkradmin.jobdefs to <userid> (write

Don't worry if this command results in an error. It just means nothing is in the SFS directory yet.



Authorize Users and Create Directories in SFS

- Authorize service machines to space in SFS
 - From 5697J06B, issue

enroll	user	bkradmin	bk:	rsfs (blocks 4000 storgro [.]	up 2	2
enroll	user	bkrbkup b	٢r	sfs (blocks 4000 storgrou	p 2	
enroll	user	bkrcatlg	эk	It's okay if these user	rour	2
					bup	2
enroll	user	bkrwrk02	эk	IDs don't actually	bup	2
enroll	user	bkrwrk03	эk	exist yet	bup	2
enroll	user	bkrwrk04	ok.		bup	2

- Create required directory entries
 - From 5697J06B, issue

create directory bkrsfs:bkradmin.workarea
create directory bkrsfs:bkrcatlg.workarea
create directory bkrsfs:bkrwrk01.workarea
create directory bkrsfs:bkrwrk02.workarea
create directory bkrsfs:bkrwrk03.workarea



Take a Breath – New SFS Server is Set Up

If you've never set up SFS before, this is the hardest part of the product install

| IBM Software



Prepare for VMSES/E Installation

From MAINT620 or MAINT630

- Mount installation tape at virtual address 181 Or
- Have SERVLINK envelope available on the MAINT620 or MAINT630 500 disk

acc 500 f

- Unpack the VMARC file vmarc unpk <envfilename> vmarc f = = f Or
- Unpack the SERVLINK file deterse <envfilename> servlink f 5697J06B = f
- Access VMSES/E disks

access 5e5 b access 51d d

Load product control files

vmfins install info (nomemo

or

vmfins install info (nomemo env <envfilename>

Obtain planning info

vmfins install ppf 5697J06B BKUPMGR (plan nomemo

or

vmfins install ppf 5697J06B BKUPMGR (plan nomemo env <envfilename>

Review for errors

vmfview install



Create Directory Entries for All Required Users

 Use directory entry samples specifically for z/VM V6.2 and V6.3 provided here:

http://www.ibm.com/support/docview.wss?rs=0&context=SSMR4R&q1=SSI&uid=swg21613686

- Note that list of basic steps to create directory entries and add minidisks is on next 2 pages
- From MAINT620 or MAINT630, follow steps outlined earlier for creating 5697J06B user ID to create directory entries for
 - BKRADMIN BKRWRK01
 - BKRBKUP BKRWRK02
 - BKRCATLG BKRWRK03
 - BKRWRK04
- Add minidisks based on data in table in topic 5.3 of the Program Directory



Create Directory Entry for Single Configuration User

Create directory entry for BKRADMIN

- From MAINT620 or MAINT630
 - Create file: BKRADMIN DIRECT
 - Based on sample, but remove the MDISK statement
 - Create directory entry

DIRM ADD BKRADMIN

DIRM FOR BKRADMIN AMD 191 3390 AUTOG 5 USER MR PW <readpw> <writepw> <multpw>



Create Directory Entries for Multiconfiguration Users

Create directory entries for BKRBKUP, BKRCATLG, BKRWRKnn

- From MAINT620 or MAINT630, define the multiconfiguration user ID:
 - Create the file: <userid> DIRECT
 - Based on sample, but remove the BUILD ON, SUBCONFIG and MDISK statements
 - Create directory entry

DIRM ADD <userid>

- From MAINT620 or MAINT630, define the subconfig entry:

- Create file: <userid-1> DIRECT
 - Add only the SUBCONFIG statement from the sample <userid> DIRECT file
 - Note that the length of "userid-1" can only be 8 chars, so you will have to shorten the user ID name to make room for "-1".

> E.g. use BKRBKP-1 instead of BKRBKUP-1

DIRM ADD <userid-1> BUILD ON <nodeid> IN <userid>

– For example:

DIRM ADD BKRBKP-1 BUILD ON SYSTEM1 IN BKRBKUP

Repeat for each user ID: BKRBKUP, BKRCATLG, BKRWRKnn



Add Minidisks to Multiconfiguration Users

Add a minidisk

- From MAINT620 or MAINT630

DIRM FOR <userid-1> AMD <vaddr> 3390 AUTOG <size> USER MR PW <readpw> <writepw> <multpw>

- Note that <userid-1> is the name of the subconfig entry (such as BKRBKP-1), not the actual userid name (BKRBKUP)
- Repeat for each BKRBKUP, BKRCATLG, and BKRWRKnn minidisk defined in the table in topic 5.3 of the Program Directory

_		
_		
	1.1.1	

Format All Minidisks

From MAINT620 or MAINT630, issue

link BKRADMIN 191 333 MR

format 333 z

release z (det

Repeat for each disk you have added for

- BKRADMIN
- BKRBKUP
- BKRCATLG
- BKRWRKnn



IBM Software

Installing using VMSES/E

© 2013 IBM Corporation

IBM Software

-	

Initial VMSES/E Install

- From 5697J06B
 - Create and run a PROFILE EXEC

```
xedit profile exec a
```

Add the following lines

```
/**/

`ACCESS 5E5 B'

`ACCESS 51D D`

`CP SET PF11 RETRIEVE FORWARD`

`CP SET PF12 RETRIEVE`
```

• Save and run

```
file
profile
```

- Installing from tape
 - Mount product tape at virtual address 181
 - Load the product code to disk and install vmfins install ppf 5697J06B BKUPMGR (nomemo nolink
- Installing from an envelope
 - Access the product code on the MAINT620 or MAINT630 500 disk link maint6n0 500 500 rr acc 500 c
 - Load the product code to disk and install vmfins install ppf 5697J06B BKUPMGR (nomemo nolink env <envfilename>



Initial VMSES/E Install (continued)

- Review for errors
 - vmfview install
- Update Build Status Table
 - vmfins build ppf 5697J06B BKUPMGR (serviced nolink
- Review for errors
 - vmfview install

_	
-	
_	

Initial VMSES/E Install (continued)

- Copy code from installation/test disk to production disk

```
acc 491 e
acc 591 f
vmfcopy * * e = = f (prodid 5697J06B%BKUPMGR olddate replace
acc 492 e
acc 592 f
vmfcopy * * e = = f (prodid 5697J06B%BKUPMGR olddate replace
```

| IBM Software



Initial VMSES/E Install (continued)

 Copy user code from installation disk to Y disk (MAINT620 or MAINT630 19E) – strongly suggested to simplify access to code

Must copy to "f2", not just "f", so that

data will be loaded in CMS saved

system. Same for helps below.

Logon to MAINT620 or MAINT630

link 5697j06b 492 492 rr

```
acc 492 e
```

link maint620 19e 19e mr

or

link maint630 19e 19e mr

acc 19e f

vmfcopy * * e = = f2 (prodid 5697J06B%BKUPMGR olddate replace

 Copy help files from installation disk to system HELP disk (MAINT620 or MAINT630 19D)

```
link 5697j06b 49d 949d rr
acc 949d e
link maint620 19d 19d mr
or
link maint630 19d 19d mr
acc 19d f
vmfcopy * helpabkr e = = f2 (prodid 5697J06B%BKUPMGR olddate replace
vmfcopy abkr helpmenu e = = f2 (prodid 5697J06B%BKUPMGR olddate replace
```



Where Code is Installed for Configuration and Testing

Disk on 5697J06B	Description
2C2	Sample files
491, 591	Service machine executables for -BKRBKUP -BKRCATLG -BKRWRKxx
492, 592 MAINT, MAINT620, or MAINT630 19E	End user and administrator executables
198	Configuration files
SFS directory	Backup job templates and DISKPOOL files (not used during installation so still considered "installing on minidisks"
49D, MAINT, MAINT620, or MAINT630 19D	Help files



VMSES/E Installation is Complete

- All code is installed from tape or envelope
- Standard install commands used by most z/VM products
- This was the easy part



IBM Software

Install All Available Service

© 2013 IBM Corporation

| IBM Software



Install All Available PTFs (COR Service)

- Order/obtain all PTFs available for Backup Manager V1.2
- Place them on MAINT620 or MAINT630 500 disk
- From MAINT620

ACC 500 F

- If each PTF is in tersed format (from IBMLINK), issue:

DETERSE <fn> <ft> F <fn> SERVLINK F

- If each PTF is in VMARC format, issue:

```
VMARC UNPK <fn> <ft> F <fn> SERVLINK F
```

- Follow instructions in Chapter 7 of the Program Directory to install each PTF
 - In 7.2, suggest following steps in Appendix B for installation of all initial service, in case of errors
 - SERVICE EXEC can be used in future when installing just 1 PTF
 - If installing more then one PTF
 - Using Appendix B, in section B.1.1.2, you can repeat the VMFREC command for each PTF before continuing to section B.1.1.3
 - If you are using the SERVICE EXEC, repeat ACC 500 F from above before installing each PTF (the service process releases this disk)
 - **<u>Do not</u>** reload CMS saved system or help segments. We'll do this later.





Verify System Access Privileges for Backup Servers

User ID	Privileges Required and Recommended
BKRADMIN	 OPTION LNKNOPAS (or equivalent, such as RACF OPERATIONS) Privilege Class G Privilege Class B (for CP MSGNOH)
BKRBKUP	 OPTION LNKNOPAS (or equivalent, such as RACF OPERATIONS) Privilege Class G Privilege Class A (for CP FORCE) Privilege Class B (CP MSGNOH) Privilege Class D (CP PURGE)
BKRCATLG	 Privilege Class G Privilege Class B (CP MSGNOH) OPTION LNKNOPAS (or equivalent, such as RACF OPERATIONS) if backing up to disk
BKRWRKxx	 OPTION LNKNOPAS (or equivalent, such as RACF OPERATIONS) Privilege Class G Privilege Class B (for CP MSGNOH) Privilege Class A (if you plan to back up DASD volumes (vs minidisks)) OPTION LNKSTABL (if you want to link disks in STABLE mode during a backup) OPTION DEVMAINT (if you plan to back up DASD volumes (vs minidisks) or if you have minidisks defined with DEVNO or &SYSRES options))



```
PROFILE EXEC for BKRADMIN
```

```
- From 5697J06B
```

```
link bkradmin 191 291 mr
```

```
acc 291 z
```

```
acc 2c2 e
```

```
copy admprof sampexec e profile exec {\rm z}
```

```
xedit profile exec z
```

```
    Take out /* and */ before and after section for MINIDISK-based installations
```

```
• Change
Job_Templates = `199'
to
Job Templates = `BKRSFS:BKRADMIN.JOBDEFS'
```

- Take out /* and */ before and after the statement for work area in SFS (line 79)

```
• Change
Work_Area = 'VMSYS:'USERID()'.WORKAREA'
to
Work_Area = 'BKRSFS:'USERID()'.WORKAREA'
file
rel z (det
```



PROFILE EXEC for BKRCATLG

-From 5697J06B

```
link bkrcatlg 191 292 mr
```

```
acc 292 z
```

```
acc 2c2 e
```

```
copy catprof sampexec e profile exec z
```

```
xedit profile exec z
```

```
• Take out /* and */ before and after section for MINIDISK-based installations
```

```
- Change
Job_Templates = `199'
to
Job_Templates = `BKRSFS:BKRADMIN.JOBDEFS'
```

• Take out /* and */ before and after statement for work area in SFS (line 79)

```
- Change
Work_Area = 'VMSYS:'USERID()'.WORKAREA'
to
Work_Area = 'BKRSFS:'USERID()'.WORKAREA'
file
rel z (det
```



PROFILE EXEC for BKRBKUP

- From 5697J06B

```
link bkrbkup 191 292 mr
```

acc 292 z

acc 2c2 e

```
copy mastprof sampexec e profile exec z
```

```
xedit profile exec z
```

```
• Take out /* and */ before and after section for MINIDISK-based installations
```

```
- Change
Job_Templates = `199'
to
Job_Templates = `BKRSFS:BKRADMIN.JOBDEFS'
```

• Take out /* and */ before and after statement for work area in SFS (line 79)

```
- Change
Work_Area = 'VMSYS:'USERID()'.WORKAREA'
to
Work_Area = 'BKRSFS:'USERID()'.WORKAREA'
file
rel z (det
```



PROFILE EXEC for BKRWRK01

- From 5697J06B

```
link bkrwrk01 191 292 mr
acc 292 z
acc 2c2 e
copy wrkprof sampexec e profile exec z
xedit profile exec z

    Take out /* and */ before and after section for MINIDISK-based installations.

   - Change
     Job_Templates = `199'
     to
     Job_Templates = `BKRSFS:BKRADMIN.JOBDEFS'
  Take out /* and */ before and after statement for work area in SFS (line 76)
     Change
      Work Area = 'VMSYS: 'USERID()'.WORKAREA'
     to
      Work Area = 'BKRSFS:'USERID()'.WORKAREA'
file
```

```
rel z (det
```

Repeat for BKRWRK02, BKRWRK03, and BKRWRK04

- Or send or copy the PROFILE EXEC to the other workers
- No changes needed for each worker



Define Special Users to Backup Manager

From 5697J06B

access 198 z access 2c2 e copy bkrusers namesamp e = names z xedit bkrusers names z

- Authorize additional users as Administrators:
 - BKRBKUP
 - Others as required by your site
 - System programmer user IDs
 - MAINT
 - MAINT620
 - MAINT630
 - Operations Manager servers if you plan to have Operations Manager submitting backup jobs as part of automation
 - > OPMGRM1
 - > OPMGRS1
 - > OPMGRS2
 - > OPMGRS3
 - > OPMGRS4
- Remove extra workers BKRWRK05 and BKRWRK06
 - Scroll to the right to make sure you removed all of BKRWRK06
- File to save changes and exit



Define Special Users to Backup Manager

Copy BKRUSERS NAMES to a shared disk for user and server access

• Recommended

- From MAINT620 or MAINT630

link 5697j06b 198 333 rr

acc 333 e

link maint620 19e 19e mr

<u>or</u>

link maint630 19e 19e mr

```
acc 19e f
```

```
copyfile bkrusers names e = = f2
```

- Note: Copy as filemode number 2.
- <u>Do not</u> reload the CMS saved system. (We'll be putting other things on MAINT620 or MAINT630 19E so we'll reload CMS saved system later.)
- Alternative

45

- From 5697J06B

```
acc 198 e
```

```
acc 592 f
```

```
copyfile bkrusers names e = = f
```



Update the Configuration File: BKRSYSTM CONFIG

From 5697J06B

access 198 z

access 2c2 e

copy bkrsystm confsamp e = config z

xedit bkrsystm config z


| IBM Software

47



Update the Configuration File: BKRSYSTM CONFIG

Choose local options for



Workers_Reserved_For_Backup = 2

Workers_Reserved_For_Restore = 2

Change both values to 0 (all workers can do backups and restores)

48



Update Backup Manager to Work with Tape Manager

- If you are using Tape Manager to manage tapes and tape mounts:
 - Verifty you have done the Tape Manager installation verification steps
 - Chapter 4 of Tape Manager Installation and Administration Guide
 - Note the tape pool defined in Tape Manager for use by Backup Manager is BKRADMIN BKRPOOL
 - Perform configuration steps for Backup Manager to work with Tape Manager
 - See the last section of Chapter 2 of the Backup Manager Administration Guide
 - No need to copy BKRSYSTM CONFIG to MAINT620 or MAINT630 19E
 - Will do that on next page



Make the Configuration File Available

Copy BKRSYSTM CONFIG to a shared disk

- Recommended

From MAINT620 or MAINT630

link 5697j06b 198 333 rr access 333 e link maint620 19e 19e mr

or

link maint630 19e 19e mr
access 19e f
copy bkrsystm config z = = f2

- Note: Copy as filemode number 2.
- Do not reload the CMS saved system. (We'll be putting other things on MAINT620 or MAINT630 19E so we'll reload CMS saved system later.)

- Alternative

49

From 5697J06B

```
access 198 z
access 592 f
copy bkrsystm config z = = f
```

50



Complete SFS Configuration and Authorization

- Give all users access to the catalog for restore requests
 - User access is limited to catalog directories for their own data
 - From 5697J06B, issue

enroll public bkrsfs:



Reload CMS Saved System if Needed

- If you added code to MAINT620 or MAINT630 19E disk (during installation, service, and/or configuration)
 - Verify the filemode number is 2 for each file
 - Already done for any Backup Manager code copied during installation and service
 - Need to verify this for any configuration files you put on 19E
 - Rebuild CMS saved system
 - From MAINT620 or MAINT630 put2prod savecms
 - If you added help files to MAINT620 or MAINT630 19D disk (during installation and/or service)
 - Rebuild CMS HELP logical saved segment (from files on 19D)
 - From MAINT620 or MAINT630 put2prod segments helpseg



Create Backup Job to Test

Use a shipped sample template as a model

- From your system programmer ID or BKRADMIN, issue link 5697J06b 2c2 2c2 rr access 2c2 e access bkrsfs:bkradmin.jobdefs z (forcerw copy sampfull tempsamp e testfull template z xedit testfull template z



Customize the Backup Job: TESTFULL

Choose local options for

CONFIG BKR_JOB_WORKERS = 1

Increase the number of workers based on the number of items to back up

CONFIG BKR_JOB_NAME = SAMPFULL

Change to TESTFULL

CONSOLE * Sample full backup generated

Change "Sample full" to indicate name of backup job TESTFULL

CP_QUIET SPOOL CONSOLE CLOSE NAME SAMPFULL \$\$SDATE\$\$

Change SAMPFULL to TESTFULL

CONFIG BKR_CATALOG_GRANULE_FN = SAMPFULL

- Change GRANULE filename: TESTFULL
- Search for other occurrences of "Sample" or "SAMPFULL" and updated
- Many other options available
 - See job statements and comments in SAMPFULL TEMPSAMP

| IBM Software



Customize the Backup Job: TESTFULL

Determine target location for backup

- Update or replace the following line to specify target location for backup data

Config BKR_Output_Spec = IBMTAPE SCRATCH RW 1

- If writing to tape, leave the line as-is
- To write backup data to disk (instead of tape)
 - Specify

Config BKR_Output_Spec = CMSFILE TESTFULL DISKPOOL *

And add this statement

Config BKR_Job_Tolerate_Diskpool_Depletion = Yes

 Create a new file TESTFULL DISKPOOL on the job templates disk, currently accessed as Z (BKRSFS:BKRADMIN.JOBDEFS), containing the following:

BKUPDISK	300
BKUPDISK	310
BKUPDISK	320

- > Create a CP directory entry for the new user ID BKUPDISK
- > Add the minidisks as specified above. Add more minidisks as desired. (Minidisks must contain enough room for multiple copies of backup data)
- > Format each minidisk
- > This user should never logon



Customize the Backup Job: TESTFULL

Update INCLUDE and EXCLUDE statements

Change the following entry from INCLUDE to EXCLUDE

Include Minidisk * = * * * = * = * = END *

Delete following entries for Linux guests

```
EXCLUDE MINIDISK MACKO* = *
INCLUDE MINIDISK MACKO* = 019*
EXCLUDE MINIDISK R54TUX* = *
INCLUDE MINIDISK R54TUX* = 019*
```

- Do not delete the entry that excludes all minidisks with an end extend of END

END

Exclude Minidisk * = * * * = * = * =

Delete or comment out the following entries

```
EXCLUDE MINIDISK MAINT = 0123
EXCLUDE MINIDISK MAINT = 0124
INCLUDE MINIDISK MAINT = 012*
EXCLUDE MINIDISK RS54QA* = *
INCLUDE MINIDISK RS54QA* = 019*
INCLUDE SFS VMSYSU: * SFS
EXCLUDE SFS VMSYSU: DFSMS* SFS
INCLUDE SFS VMDEVU: * SFS
```



Customize the Backup Job: TESTFULL

Update INCLUDE and EXCLUDE statements

Delete the SFS entries for VMSYSU

Include	SFS	VMSYSU:	*	SFS
Exclude	SFS	VMSYSU:	DFSMS*	SFS
Include	SFS	VMDEVU:	*	SFS

Change the following to reflect BKRSVSFS instead of ROCKSFS

EXCLUDE MINIDISK ROCKSFS* = * INCLUDE MINIDISK ROCKSFS* = 019*

- Add a new entry to back up just your 191 disk or BKRADMIN's 191 disk

Include MINIDISK BKRADMIN = 191 * * = * = * * *

Modify the following to exclude large minidisks

EXCLUDE MINIDISK * = * * * = * = * > 3300 *


FILE to save changes



Configuration is Complete

Now let's see if it actually works!







Start Backup Manager Service Machines

Start and verify BKRCATLG startup

- From MAINT620 or MAINT630, issue
 - cp xautolog bkrcatlg
 - cp smsg bkrcatlg status
- If no response to status command, then view BKRCATLG console using Operations Manager
 - Find and fix the error
 - Force BKRCATLG off the system and repeat above steps

Start and verify BKRBKUP startup

- From MAINT620 or MAINT630, issue
 - cp xautolog bkrbkup
 - cp smsg bkrbkup status
- If no response to status command, then view BKRBKUP console using Operations Manager
 - Find and fix the error
 - Force BKRBKUP off the system and repeat above steps



Start Backup Manager Service Machines

- Starting workers is recommended when product is first installed to verify configuration
 - In normal operations, BKRBKUP will start workers when needed
 - Workers then automatically logged off when idle for 2 minutes
 - From MAINT620 or MAINT630, issue

cp xautolog bkrwrk01

cp smsg bkrwrk01 status

- If no response to status command, then view BKRWRK01 console using Operations Manager
 - Find and fix the error

60

- Force BKRWRK01 off the system and repeat above steps
- Repeat for BKRWRK02, BKRWRK03, BKRWRK04



Submit a Backup Job

- Submit a job for review
 - From BKRADMIN, issue
 - smsg bkrbkup review testfull
 - Review files returned to BKRADMIN's reader
 - TESTFULn JOB
 - One file for each backup worker assigned
 - All configuration statements with (most) variables resolved
 - All DUMPDYN statements for data that would be backed up



Submit a Backup Job

- Submit a job and perform real backup
 - From BKRADMIN (or other user authorized as a Backup Manager admin), issue
 - smsg bkrbkup submit testfull
 - Note the message(s) indicating which worker(s) the job went to
 - Review consoles of BKRWRKxx servers
 - Authorize BKRADMIN to view backup server consoles in Operations Manager
 - Use AUTH statement
 - See Chapter 5 of Operations Manager Administration Guide
 - From BKRADMIN, issue

GOMCMD OPMGRM1 VIEWCON USER(BKRWRKxx)



Backup and Restore Manager is Up and Running



- Major task is SFS setup
 - Especially if you aren't familiar with SFS
- VMSES/E install is straightforward
- Configuration is quick for initial testing
 - Use the defaults for most things
 - Give all options some thought before production use
- Use your in-house procedures to move it to production

IBM Software

_	

References and More Information

Backup and Restore Manager for z/VM Web site

- http://www.ibm.com/software/stormgmt/zvm/backup
 - Publications
 - Pre-requisites
 - Announcements
 - Support
- e-mail: Tracy Dean, tld1@us.ibm.com
- Publications
 - CMS File Pool Planning, Administration, and Operation (SC24-6074)
 - Directory Maintenance Facility Commands Reference (SC24-6133)
 - Backup and Restore Manager for z/VM Program Directory (GI10-8662)
 - Backup and Restore Manager for z/VM Administration Guide (SC18-9346)
 - Backup and Restore Manager for z/VM User Guide (SC18-9523)