




Version 3.4.0



Nokia ASCII Gateway User Guide

16 January 2008

**TIVOLI® NETCOOL® PERFORMANCE MANAGER FOR WIRELESS
NOKIA ASCII GATEWAY USER GUIDE**

Note: Before using this information and the product it supports, read the information in Notices on page 16.

This edition applies to Version 4.1 of IBM® Tivoli® Netcool® Performance Manager for Wireless and to all subsequent releases and modifications until otherwise indicated in new editions.

© Copyright International Business Machines Corporation, 2008. All rights reserved.

US Government Users Restricted Rights - Use, duplication or disclosure restricted by GSA ADP Schedule Contract with IBM Corp.

Table of Contents

1	About this Documentation	1
1.1	Audience	1
1.2	Required Skills and Knowledge	1
2	Overview	2
2.1	The Gateway Framework.....	2
2.2	Nokia ASCII Overview.....	2
2.2.1	Network Details.....	2
2.2.2	Data Types.....	2
2.2.3	Data Version Support	2
2.2.4	Data/File Formats	3
2.2.5	Architectural extensions.....	4
3	Engine Rules and Configuration	4
3.1	NOKIA_ASCII.....	4
3.1.1	PIF Naming	5
3.1.2	Rule Configuration	5
3.2	NOKIA_MML	8
3.2.1	PIF Naming	9
3.2.2	Rule Configuration	9
4	Post Parser Rules and Configuration	12
4.1	CNAME_MANIP	12
4.1.1	Rule Configuration	12
4.1.2	Sample Usage	13
4.2	VALIDATE_AGGREGATE	13
4.2.1	Rule Configuration	13
4.2.2	Sample Usage	14
5	Tech Pack Support	15
6	Hierarchy Information	15
Appendix A	Notices and Trademarks	16

References

Name	Description
Gateway Framework User Guide	This use guide describes in detail the functionality of the Gateway Framework, and the standard suite of tools available.

Glossary

1 About this Documentation

1.1 Audience

The target audience of this document is IBM Performance Manager for Wireless customers. They should be familiar with telecommunication and IT principles and should also have a good understanding of Solaris.

IMPORTANT: Before attempting an installation of Performance Manager for Wireless you are strongly advised to read the release notes and any readme files distributed with your Performance Manager for Wireless software. Readme files and release notes may contain information specific to your installation not contained in this guide. Failure to consult readme files and release notes may result in a corrupt, incomplete or failed installation.

Note: Performance Manager for Wireless Administrators should not, without prior consultation and agreement from IBM, make any changes to the Index Organized tables or database schema. Changes to the Index Organized tables or database schema may result in corruption of data and failure of the Performance Manager for Wireless System. This applies to all releases of Performance Manager for Wireless using all versions of interfaces.

1.2 Required Skills and Knowledge

This guide assumes you are familiar with the following:

- General IT Principles
- Sun Solaris Operating System
- Oracle Database
- Windows operating systems
- Graphical User Interfaces
- Network Operator's OSS and BSS systems architecture

This guide also assumes that you are familiar with your company's network and with procedures for configuring, monitoring, and solving problems on your network.

2 Overview

2.1 The Gateway Framework

The Nokia ASCII uses the Gateway Framework as a container for the execution of its engine and post parser stages. The Gateway Framework and Vendor Gateway are decoupled into two separate installations. The Gateway Framework consists of a library of perl modules that provide functionality such as:

- a container for the execution of the Vendor Engine and Post Parser rules for of data transformation
- Intermediate (PIF) and output data (LIF) storage and management
- logging utilities
- cleanup and crash recovery
- statistics gathering

The Vendor Gateway plugs into the Gateway Framework and extends this functionality to provide the final Gateway that parses the vendor data.

More information on the standard Gateway configuration is contained in the Gateway Framework User Guide.

Only vendor specific configuration details will be described in this document.

2.2 Nokia ASCII Overview

2.2.1 Network Details

This Gateway supports raw performance and hierarchy data from a number of different sources:

- NSS, BSS and SGSN performance data from the Nokia NetAct Performance Management system, using the NOKIA_ASCII.pm engine.
- SGSN configuration data, provided in ASCII MML report format, which is parsed by the NOKIA_MML.pm engine.

2.2.2 Data Types

The types of data supported are:

- For NSS, BSS and SGSN performance data the Gateway supports performance data from the Nokia NetAct Performance Management System. This includes an extensive list of measurement object types within each network type.
- For SGSN configuration data, the MML type output is supported.

2.2.3 Data Version Support

- For NSS, BSS and SGSN performance data. the version supported are T12 and OSS3.1
- For SGSN configuration data, version information is not relevant.

2.2.4 Data/File Formats

2.2.4.1 NSS, BSS and SGSN performance data

For the performance data, the standard performance data format from the Nokia ASCII netact system is supported. The performance data consists of:

- A File Header: The first line in the raw file, the file header is formatted as follows:
`<NE_TYPE><NE_ID>, <meas_type>, <meas time>, <duration>;`

where

NE_TYPE – the type of network element, such as HLR or MSC for NSS data.

NE_ID – The identifier of the network element, a 6 digit number.

Meas type – the type of measurement that follows.

Meas time – starting time of the measurement period.

Duration – length of measurement period in minutes.

The following format is then repeated:

- The Object ID: This identifies the measurement target, which is made up of 0 or more numeric object identifications. The combination of this line and the NE is unique for all elements in the network.
- Counter name, counter value: Each subsequent line, until delimited by a “;” to indicate the end of record consists of a counter name and counter value associated with the object ID.

A sample of the file header and one measurement object:

```
BSC30936, 90, 200403311900, 60;  
36, 11,  
INT_ID, 21,  
PERIOD_START_TIME, 20040331190000,  
PERIOD_STOP_TIME, 20040331200000,  
PERIOD_REAL_STOP_TIME, 20040331200113,  
PERIOD_REAL_START_TIME, 20040331190000,  
PERIOD_DURATION, 60,  
SEGMENT_ID, 36,  
QOS_PRIORITY_CLASS, 11,  
NBR_OF_TBF_ALLOCATIONS, 11,  
TOTAL_NBR_OF_RLC_BLOCKS, 11,  
TOTAL_DURATION_OF_TBFS, 27,  
DROPPED_DL_LLC_PDUS_OVERFLOW, 0,  
DROPPED_DL_LLC_PDUS_LIFETIME, 0,  
AVE_MS_BSSGP_FLOW_RATE_SUM, 0,  
AVE_MS_BSSGP_FLOW_RATE_DEN, 1;
```

2.2.4.1 SGSN Configuration data.

SGSN configuration is in the format of MML report output. The format of the report can be broken into:

- A report header, containing the date and time the report was generated.
- A set of header lines, which identify the hierarchy information for the following configuration entries. These are mapped to header output in the PIF.

3. The secondary hierarchy data, from the hierarchy configuration files is inserted based on the key from the object id line.
4. The counter names and values are mapped to a single row in the output PIF.

3.1.1 PIF Naming

The naming format of the PIF files is configurable. This section describes the standard naming supported by the default configuration. This should be sufficient unless there is a specific requirement to rename the PIF files differently.

The PIF naming consists of:

- the name of the measurement type, derived from a lookup on the object identifier in the configuration file. e.g. P_NBSC_PBCCH_AVAIL.
- The startdate from the file header, e.g. 20040331.
- The NODEID derived from lookup of the hierarchy file.
- The starttime from the file header.
- The network type derived from the file header.
- The object instance derived from the file header.
- The object identifier derived from the file header.

An example of a PIF file name for measurement 90, P_NBSC_QOS.

P_NBSC_QOS-#-20040331-#-TBD0004BSC1-#-19:00-#-BSC-#-30936-#-90-#-I.pif

Significant performance improvement can be achieved by using fewer keys for the file header. This should generate larger PIF files.

3.1.2 Rule Configuration

The configuration of the NOKIA_ASCII rule is split into 2 separate files due to its complexity:

- EngineConfig.pm which as normal describes the main configuration of the rule.
- NOKIA_<Network Type>_Config.pm that contains the configuration of the measurement types handled for a particular Network Type e.g. Nokia_BSS_Config.pm. This configuration is then referenced within the appropriate rule in EngineConfig.pm. The configuration of these measurement objects will be described but in general should not need to be changed during installation.

3.1.2.1 EngineConfig.pm

EngineConfig.pm contains the main configuration of the NOKIA_ASCII rule. In addition to the standard entries, the NOKIA_ASCII rule mandatory entries are:

- **HEADER_LINE_DESCRIPTION**: A regular expression detailing the format of the header line in the input file.

```
HEADER_LINE_DESCRIPTION => '^(BSC) \w+\\, \w+\\, \w+\\, \w+\\; .*$',
```

- **FIELD_DELIMITER**: Describes the delimiter used within the configuration files from which the hierarchy information is read.

```
FIELD_DELIMITER => ', ',
```

- **HEADER_FIELDS**: A list header field names which represents the number of fields in the **HEADER_LINE_DESCRIPTION** separated by **FIELD_DELIMITER**.

```
HEADER_FIELDS => [ qw(ASCII_ID OMTYPE DATE DURATION) ],
```

- **HEADER_PROCESSING**: The names and values of the header counters to be extracted from the line matched in the **HEADER_LINE_DESCRIPTION**.

```
HEADER_PROCESSING => {  
  DATE => {  
    STARTDATE => '^(\\d{8}) .+',  
    STARTTIME => '^(\\d{8})(\\d{4}) ',  
  },  
  ASCII_ID => {  
    OBJECT_INSTANCE => '^([a-zA-Z]+)(\\d+) .*',  
    NETWORK_TYPE => '^([a-zA-Z]+) .*',  
  },  
},
```

- **HEADER_INFO_FOR_PIF_FILENAME**: An array, listing the fields derived from the header line that will be used to create the PIF filename:

```
HEADER_INFO_FOR_PIF_FILENAME => [ qw(STARTDATE NETWORK_TYPE BSCID  
OMTYPE) ],
```

- **OBJECTID_LINE_DESCRIPTION**: At the beginning of each record is an object id description. This configuration describes the valid format of this line that will consist of up to 5 comma separated keys.

```
OBJECTID_LINE_DESCRIPTION      => '^(\\d*\\, *) {0,5} .*',
```

- **RECORD_DELIMITER_DESCRIPTION**: At the end of each record is delimiter. This configuration describes the valid format of this line that will consist of a comma separated values with a semi column at the end.

```
RECORD_DELIMITER_DESCRIPTION  => '^\\w+\\, [\\w\\-]*\\; .*',
```

- **OBJECT_TYPES**: A hash that describes the information associated with each different measurement type. This is quite a large hash as there can be many different objects for each network component. In this section the possible values configured for each are described.

The subroutine and configuration are stored in the module associated with that network type, **NOKIA_BSS_Config.pm**, **NOKIA_NSS_Config.pm** and **NOKIA_SGSN_Config.pm**.

See the next section on the format of these configuration files.

```
OBJECT_TYPES => nokia_nss(),
```

The optional entries are:

- **HEADER_INFO_FOR_DATA_RECORD**: For certain installations, input files can contain measurements for the same om type for several different BSCs etc. This option allows you to configure the header info that you want inserted per record rather than as normal in the header. For example **NODEID**, **BSCID** etc can be inserted in every record to create larger PIFs, which will be faster for post parser rules. It is configured empty by default.

```
HEADER_INFO_FOR_DATA_RECORD => []
```

- **CONFIGURATION_DATA_FOR_HEADER**: The fields, extracted from the lookup in of the hierarchy data that should be inserted into the PIF header.

```
CONFIGURATION_DATA_FOR_HEADER => {
    NODEID => "NODEID",
},
```

- **IGNORE_LINE_IF_NETWORK_CONFIG_DATA_MISSING**: This scalar specifies whether or not to ignore lines for which the hierarchical data cannot be found. If it is set to true, then any data lines for which the lookup of key data fails will be removed from the PIF output. By default it is configured as false.

```
IGNORE_LINE_IF_NETWORK_CONFIG_DATA_MISSING => '0',
```

- **CONFIGURATION_DETAILS**: A complex hash containing details on the network configuration files. Hierarchy data from these files is integrated into PIF output records. There are 4 possible entries:

HIERARCHY, TRXHIER, SGSN and OBJECT.

Each has entry contains the following configuration elements:

- **DIR**: The path name that is pointing to the hierarchy files.
- **FILENAME**: The regular expression of hierarchy filename. These files store the hierarchy data.
- **FIELDS**: An array mapping the fields in the input file to counter names.
- **KEYS**: The sets of simple and complex keys to generate for lookup. These keys are then used while processing the performance files, to insert the relevant hierarchy data into each PIF row.

```
CONFIGURATION_DETAILS => {
    HIERARCHY => {
        DIR      => '../hier/',
        FILENAME => [ '^hierarchy.*\.dat$', ],
        FIELDS   => [qw(BSCID BTSID BSCNAME BTSNAME BSNAME LACID CELLID
DEFTCH DEFCCCH MSCNAME)],
        KEYS     => {
            LAC_CELL_KEY => [qw(LACID CELLID)],
            LAC_KEY      => 'LACID',
        },
    },
    OBJECT => {
        DIR      => '../hier/',
        FILENAME => [ '^objects.*\.dat$', ],
        FIELDS   => [qw(OBJECT_INSTANCE NAME)],
        KEYS     => {
            OBJ_KEY      => 'OBJECT_INSTANCE',
            OBJ_NAME_KEY => 'NAME',
        },
    },
},
```

- **DEFAULT_CONCATENATION_CHAR**: A single character scalar with the string to be used when concatenating values which are being used to create a single counter value in the output PIF.

`DEFAULT_CONCATENATION_CHAR => '/',`

- `USE_PIF_FILENAME_COUNTER`: Is set a unique number will be inserted in the PIF filename to ensure that the output PIFs are unique and do not overwrite each other, especially when large raw files are being used, which have previously been concatenated together.

`USE_PIF_FILENAME_COUNTER => "True",`

- `INPUT_NULL_VALUE`: A scalar with the string for null data value.

`INPUT_NULL_VALUE => '-1',`

3.1.2.2 Network Measurement Object Configuration

As stated above, the Nokia_<XXX>_Config.pm files detail the mapping of each measurement object within each network type. Each file has the same format. A hash detailing the configuration for each network type.

Each element within this hash details the configuration for mapping from the measurement object to the PIF. The hash key is the measurement object value e.g. 160.

The configuration entries for each measurement object are detailed below:

- `NAME`: The actual name that the measurement type maps to. Used in the output PIF filename.

`NAME => 'P_NBSC_TRAFFIC',`

- `OBJECT_ID_NAMES`: An array with the names of the expected entries in the object id line.

`OBJECT_ID_NAMES => [qw(BTSID TRX_TYPE)],`

- `RECORD_KEY`: An array with the names of the keys that are to be used when searching the network configuration information.

`RECORD_KEY => [qw(BSCID BTSID)],`

- `HIERARCHY_KEY_SET`: A scalar referring to the hierarchy key from the hierarchy configuration in the engine which is to be used for lookups for this OM type. This key set must be configured in the hierarchy configuration in CONFIGURATION_DETAILS for the rule.

`HIERARCHY_KEY_SET => 'BSCID_BTSID_KEY',`

- `OUTPUT_COUNTERS`: The `OUTPUT_COUNTERS` is a hash entry whose keys contain the network configuration counter names to be integrated into the current record. The corresponding hash values contain the names of the network configuration column counters or object ID line entries. This may be a single or a list of counter names. In the event of a list of names, the output counter value will be the concatenation of all these.

```
OUTPUT_COUNTERS => {  
    NODEID => 'NAME',  
},
```

3.2 NOKIA_MML

Due to the report format of the MML output files parsed by the NOKIA_MML rule, the parsing of the input files is based upon parsing of a file header and then multiple blocks each of which contains a block header and a list of data blocks.

It may be useful to examine the raw input files that are parsed by this rule while reading the description. They are contained in `example/data/nokia_mml` directory of the release package.

The format of the file consists of:

- a report header line, extracted and mapped to the PIF header and filename.
- a repeating set consisting of:
 - report header lines, which detail hierarchy configuration information. This set of lines maps to the header in the output PIF.
 - Report detail lines, which detail the configuration data. Each line is mapped to a data row in the output PIF.

3.2.1 PIF Naming

The naming of the PIF file is controlled by 2 configuration entries, one detailing the elements extracted from the raw file and the other detailing the block information from the PIF header to be included in the PIF filename.

The PIF filename typically contains hierarchy information and the date and time the MML command was executed to ensure uniqueness.

3.2.2 Rule Configuration

This section details the non-standard entries for the NOKIA_MML rule.

- `OUTPUT_FILENAME_START`: An optional string to prepend to the PIF filename

```
OUTPUT_FILENAME_START      => 'ZFWO',
```

- `BLOCK_NAME`: The name of the block to use in the PIF

```
BLOCK_NAME                 => 'ZFWO_BLOCK',
```

- `FILE_HEADER_DESC`: This is an array of hash elements each of that describes an expected file header line in the input. Each entry consists of a `LINE_DESC`, a RE to match the line on, and `FIELDS` that is an array of counter names to assign the extracted values to.

```
FILE_HEADER_DESC =>
[
  {
    LINE_DESC =>
      'DX\s+\d+\s+([\d\-\-]+)\s+([\d\-\-]+)\s+([\d:]+)',
    FIELDS    => [qw (FILE_BSC MML_DATE MML_TIME)],
  },
],
```

- `FILE_HEADER_INFO_FOR_PIF_FILENAME`: An array containing the names of the counters extracted in `FILE_HEADER_DESC` that are to be used in the PIF filename.

```
FILE_HEADER_INFO_FOR_PIF_FILENAME =>
[qw (FILE_BSC MML_DATE MML_TIME) ]
```

- `BLOCK_INFO_FOR_PIF_FILENAME`: Similar to above this describes the counters, extracted from the report headers that is to be used in the PIF filename.

BLOCK_INFO_FOR_PIF_FILENAME => [qw (NSEI BSCU PCU)],

- **FILE_HEADER_INFO_FOR_PIF_HEADER:** This array contains the list of counters, extracted in the **FILE_HEADER_DESC** that are to be put in the PIF header.

FILE_HEADER_INFO_FOR_PIF_HEADER =>
[qw (FILE_BSC MML_DATE MML_TIME)]

- **BLOCK_INFO_FOR_PIF_HEADER:** The names of the counters, extracted from the report block header to be written to the PIF header.

BLOCK_INFO_FOR_PIF_HEADER => [
qw (NSVCI NSEI BSCU PCU NSVC_NAME)
qw (NSVC_OP_STATE DLCI DLCI_OP_STATE CIR BEARER CHANNEL)
],

- **BLOCK_DESCRIPTION:** This hash describes the core processing of the report details lines in the MML input file.

It contains a number of sub-elements described below:

- **BEGIN_DESCRIPTION:** A scalar RE, describing the RE to match which marks the start of a report block.

BEGIN_DESCRIPTION => 'NSEI-\d+',

- **LINE_DESC:** An array of hash elements, each of which describes a report line to be matched during processing. Any lines that are not matched by one of the RE's in this list are ignored. With each **LINE_DESC** element a number of configuration fields are used:

- **LINE_DESC:** A RE to use to match the line. Once the RE is true for a line the other line configuration is used to control what happens to the line. These options are detailed below. Fields can be extracted from the matched RE either by bracketing them as normal in **LINE_DESC**, or by specifying the **LINE_SEPARATOR** (see below).

LINE_DESC => '^NSEI-(\d+)\s+BCSU-(\d+)\s+PCU-(\d)'

- **LINE_SEPARATOR:**The string used to split the fields in the matched line.

LINE_SEPARATOR => '\s+',

- **FIELDS:** The names of the counters that are extracted from the matched line. In the case ZFWO files multiple name-value pairs exist on a single report line and so one report line can map to multiple rows in the PIF.

FIELDS => [qw(NSEI BSCU PCU)],

- **LINE_TYPE:** This defines the type of report line which has been matched, which can be either **HEADER**, in which case it will be mapped into the PIF header, or **DATA** in which case the value is mapped into the next row written.

LINE_TYPE => 'DATA'

- WRITE_LINE: (Only applies to LINE_TYPE 'DATA') A boolean used to define whether the matched line is to be written out as a line in the PIF. If not, the counter value will be stored to be used in the next rows written to the PIF.

```
WRITE_LINE      => 'TRUE' ,
```

Given the report extract below:

```
NSEI-02750
  PAPU-00
    LAC-00252
      RAC-002
        CI-23382  BVCI-10005 STATE-WO
        CI-25152  BVCI-10018 STATE-WO
        CI-07202  BVCI-10002 STATE-WO
```

The NSEI, LAC, RAC are not written directly to the PIF but are used as counter values in the real data rows, which start with the CI marker.

A line description to match the main report details line above is:

```
{
  LINE_DESC => '^\\s+CI-(\\d+) \\s+BVCI-(\\d+) \\s+STATE-(\\w+)' ,
  FIELDS => [ qw (CI BVCI STATE) ] ,
  LINE_TYPE => 'DATA' ,
  WRITE_LINE => '1' ,
},
```

- NEW_COUNTERS: This is an array containing descriptions of new counters to be derived from the counters extracted from the input report. Each array element contains a hash with the following elements:
 - COUNTER: The name of the counter to be transformed


```
COUNTER      => 'MML_ID' ,
```
 - NEW_COUNTER: The name of the new counter to insert.


```
NEW_COUNTER  => 'BSNAME' ,
```
 - COUNTER_DESC: A RE describing the fields to be extracted from the original counter value. The values to be extracted are bracketed ().


```
COUNTER_DESC => '\\(\\d{4}) (\\d{2}) (\\d{2}) (\\d{1})' ,
```
 - NEW_COUNTER_DESC: A scalar to describe the new format of the counter, using the extracted values above to recreate the counter. The format is the same as the normal format used in REs to match text.


```
NEW_COUNTER_DESC => '$1-$2-$3/$4' ,
```
- CONFIGURATION_DETAILS: Similar to NOKIA_ASCII this consists of the configuration required for the insertion of the hierarchy data into each row of the pif. This hash consists of a series of hash entries, each of which defines a hierarchy file and key mapping.

The fields in each entry are:

- DIR: The name of the path that is pointing to the hierarchy file.
`DIR => '../hierarchy/'`,
- FILENAME: An array of regular expressions of the hierarchy file name. The hierarchy information is stored in those files.
`FILENAME => ['^hierarchy.*\.dat$',]`,
- FIELDS: An array describing the list of fields contained on each row of the file.
`FIELDS => [qw(BSCID BTS_ID BSCNAME BTSNAME BSNAME
LACID CELLID DEFTCH DEFCCCH MSCNAME)]`,
- KEYS: An array describing the keys used to map between the raw data and the hierarchy data.
`KEYS => ['BSNAME']`,
- FIELDS_TO_INSERT: The fields from the hierarchy data to insert into the PIF when the key is matched.
`FIELDS_TO_INSERT => [qw(BTSNAME BSCNAME)]`,

4 Post Parser Rules and Configuration

4.1 CNAME_MANIP

The CNAME_MANIP is used for counter manipulation. Part of the Nokia ASCII requirements is that counter names must be prepended with certain values.

This rule will prepend either a default or custom string, based on the current counter name, to rename the counter in the output PIF.

4.1.1 Rule Configuration

The non-standard configuration entries associated with this rule are:

- DEFAULT_PREPEND_STR: A scalar describing the default string to be used to prepend all *strings* with.

```
'DEFAULT_PREPEND_STR' => "BSC_"
```

- CUSTOM_PREPEND_STR: A hash mapping a counter name to an value to prepend it with.

```
'CUSTOM_PREPEND_STR' => {  
  'PERIOD_START_TIME' => 'PP_',  
  'NOPERIOD_' => 'QS_',  
  'PERIOD_STOP_TIME' => 'PS_',  
}
```

NOTE: Either DEFAULT_PREPEND_STR or CUSTOM_PREPEND_STR must be configured. If both are, DEFAULT_PREPEND_STR takes precedence and all counters will be prepended with that value.

4.1.2 Sample Usage

Given the following input PIF:

```
## Parser Intermediate File
##START|HEADER
Network_FileType|BSCID|NODEID|STARTTIME|OMTYPE|DURATION|NETWORK_TYPE|STARTDATE
BSC|30936|TBD0004BSC1|19:00|90|60|BSC|20040331
##END|HEADER
##START|P_NBSC_QOS
AVE_MS_BSSGP_FLOW_RATE_SUM|INT_ID|SEGMENT_ID
1|3|5
1|7|9
```

each counter name will be prefixed with BSC to produce the following output:

```
## Parser Intermediate File
##START|HEADER
Network_FileType|BSCID|NODEID|STARTTIME|OMTYPE|DURATION|NETWORK_TYPE|STARTDATE
BSC|30936|TBD0004BSC1|19:00|90|60|BSC|20040331
##END|HEADER
##START|P_NBSC_QOS
BSC_AVE_MS_BSSGP_FLOW_RATE_SUM|BSC_INT_ID|BSC_SEGMENT_ID
1|3|5
1|7|9
```

The configuration required to produce this output is below:

```
{
  'RULE_TYPE'          => 'CNAME_MANIP',
  'RULE_DESC'         =>
    'Alternative counter names P_NBSC_LOAD',
  'INPUT_FILE_DESCRIPTION'=>
    ['^P_NBSC_LOAD-#-(\d{8}-#-.*-#\d{2}:\d{2}-#-BSC-#\d+##-\d+)-#-I.pif'],
  'PRODUCE_PIF'       => 'True',
  'PRODUCE_LIF'       => 0,
  'DEFAULT_PREPEND_STR' => "BSC_",
},
```

4.2 VALIDATEAggregate

This rule is used to accumulate configured counters over a number of records within a PIF. It is also configured with validating counters that are used to identify from which PIF data row all other non-accumulated counter values should be taken. In this way as well as combining a number of rows via accumulation, the correct non-accumulated counter values can also be inserted into the output PIF data.

4.2.1 Rule Configuration

The non-standard configuration entries for this rule are:

- COUNTERS_TO_ACCUMULATE: An array list of counters to be accumulated over all records.
COUNTERS_TO_ACCUMULATE => ['LOC_AREAS_IN_USE'],

- **COUNTERS_TO_VALIDATE_ON**: The names of the counters to use within each record to check for nulls, while looking for the valid record.
`COUNTERS_TO_VALIDATE_ON => ['ROAM_DB_OP'],`
- **VALID_NULL_VALUES**: An array describing the values that are to be interpreted as null values within each row.
`'VALID_NULL_VALUES' => [''],`

In this case the counters above would be considered nulls when they are equal to "".

- **COUNTERS_TO_SORT_ON**: If specified the counters in this array will be used to sort the records and a new record will be created in the output pif for each unique key.
`COUNTERS_TO_SORT_ON => ['CELLID']`

NOTE:

1. All counters must be non null for a record to be considered valid.
2. The accumulate counters are accumulated over all matching null and non null records.
3. If no record is found with all **COUNTERS_TO_VALIDATE_ON** with non null values, a warning will be logged. The values in first record read in will be used as the output counters.

4.2.2 Sample Usage

Given the following PIF:

```
## Parser Intermediate File
##START|HEADER
Network_FileType|BSCID|NODEID|STARTTIME|OMTYPE|DURATION|NETWORK_TYPE
BSC|30936|TBD0004BSC1|19:00|90|60|BSC
##END|HEADER
##START|CELLDATA
CELLID|ROAM_DB_OP|LOC_AREAS_IN_USE
333333||10
333333|45|20
333333||80
222222||800
222222|50|200
```

The following output is produced:

```
##START|HEADER
Network_FileType|BSCID|NODEID|STARTTIME|OMTYPE|DURATION|NETWORK_TYPE
BSC|30936|TBD0004BSC1|19:00|90|60|BSC
##END|HEADER
##START|CELL1
CELLID|ROAM_DB_OP|LOC_AREAS_IN_USE
333333|45|100
222222|50|1000
```

The counter **LOC_AREAS_IN_USE** is accumulated for each **CELLID**, and the value of **ROAM_DB_OP** considered valid, in this case any non "" value, is output in the accumulated row.

The following rule configuration would achieve the above

```
{
    'RULE_TYPE'           => 'VALIDATE_AGGREGATE',
    'RULE_DESC'          => 'Validate MSC files',
```

```
'INPUT_FILE_DESCRIPTION' => ['^P_MSC_VLR-#-(\d{8}-#-.*).pif'],
'OUTPUT_BLOCK_NAME'     => 'CELL1',
'PRODUCE_LIF'           => 'TRUE',
'PRODUCE_PIF'           => 'TRUE',
'COUNTERS_TO_VALIDATE_ON' => ['ROAM_DB_OP'],
'VALID_NULL_VALUES'     => [''],
'COUNTERS_TO_ACCUMULATE' => ['LOC_AREAS_IN_USE']
'COUNTERS_TO_SORT_ON'   => ['CELLID']
},
```

NOTE: Using the PERLIZE rule, now included in the Gateway Framework, will be able to fulfil the requirement of DLCI data normalisation (for certain TechPacks).

5 Tech Pack Support

Gateway configurations currently available for the following Tech Packs:

- Nokia BSS S11.5

6 Hierarchy Information

Hierarchy information is produce by customer or vendor using a set of extraction tools. The extraction tools will query the NetAct database to extract the necessary config data. An example of the extraction tool is provided with this vendor gateway.

Appendix A Notices and Trademarks

This appendix contains the following:

- Notices
- Trademarks

Notices

This information was developed for products and services offered in the U.S.A.

IBM may not offer the products, services, or features discussed in this document in other countries. Consult your local IBM representative for information on the products and services currently available in your area. Any reference to an IBM product, program, or service is not intended to state or imply that only that IBM product, program, or service may be used. Any functionally equivalent product, program, or service that does not infringe any IBM intellectual property right may be used instead. However, it is the user's responsibility to evaluate and verify the operation of any non-IBM product, program, or service.

IBM may have patents or pending patent applications covering subject matter described in this document. The furnishing of this document does not grant you any license to these patents. You can send license inquiries, in writing, to:

IBM Director of Licensing
IBM Corporation
North Castle Drive
Armonk NY 10504-1785
U.S.A.

For license inquiries regarding double-byte (DBCS) information, contact the IBM Intellectual Property Department in your country or send inquiries, in writing, to:

IBM World Trade Asia Corporation
Licensing
2-31 Roppongi 3-chome
Minato-ku
Tokyo 106-0032
Japan.

The following paragraph does not apply to the United Kingdom or any other country where such provisions are inconsistent with local law: INTERNATIONAL BUSINESS MACHINES CORPORATION PROVIDES THIS PUBLICATION "AS IS" WITHOUT WARRANTY OF ANY KIND, EITHER EXPRESS OR IMPLIED, INCLUDING, BUT NOT LIMITED TO, THE IMPLIED WARRANTIES OF NON-INFRINGEMENT, MERCHANTABILITY OR FITNESS FOR A PARTICULAR PURPOSE. Some

states do not allow disclaimer of express or implied warranties in certain transactions, therefore, this statement may not apply to you.

This information could include technical inaccuracies or typographical errors. Changes are periodically made to the information herein; these changes will be incorporated in new editions of the publication. IBM may make improvements and/or changes in the product(s) and/or the program(s) described in this publication at any time without notice.

Any references in this information to non-IBM Web sites are provided for convenience only and do not in any manner serve as an endorsement of those Web sites. The materials at those Web sites are not part of the materials for this IBM product and use of those Web sites is at your own risk.

IBM may use or distribute any of the information you supply in any way it believes appropriate without incurring any obligation to you.

Licenses of this program who wish to have information about it for the purpose of enabling: (i) the exchange of information between independently created programs and other programs (including this one) and (ii) the mutual use of the information which has been exchanged, should contact:

IBM Corporation
5300 Cork Airport Business Park
Kinsale Road
Cork
Ireland.

Such information may be available, subject to appropriate terms and conditions, including in some cases, payment of a fee.

The licensed program described in this document and all licensed material available for it are provided by IBM under terms of the IBM Customer Agreement, IBM International Program License Agreement or any equivalent agreement between us.

Information concerning non-IBM products was obtained from the suppliers of those products, their published announcements or other publicly available sources. IBM has not tested those products and cannot confirm the accuracy of performance, compatibility or any other claims related to non-IBM products. Questions on the capabilities of non-IBM products should be addressed to the suppliers of those products.

All statements regarding IBM's future direction or intent are subject to change or withdrawal without notice, and represent goals and objectives only.

This information contains examples of data and reports used in daily business operations. To illustrate them as completely as possible, the examples include the names of individuals, companies, brands, and products. All of these names are fictitious and any similarity to the names and addresses used by an actual business enterprise is entirely coincidental.

If you are viewing this information softcopy, the photographs and color illustrations may not appear.

Trademarks

IBM, IBM logo, Tivoli, and Netcool are trademarks of International Business Machines Corporation in the United States, other countries or both.

UNIX is a registered trademark of The Open Group in the United States and other countries.

Intel and Pentium are trademarks or registered trademarks of Intel Corporation or its subsidiaries in the United States and other countries.

Other company, product or service names may be trademarks or service marks of others.

IBM

© Copyright IBM Corporation 2008

International Business Machines Corporation
5300 Cork Airport
Business Park
Kinsale Road
Cork
Ireland

Printed in the Republic of Ireland
All Rights Reserved
IBM, IBM logo, Tivoli, and Netcool are trademarks
of International Business Machines Corporation in
the United States, other countries or both.

Other company, product and service names may
be trademarks or service marks of others.