

IBM Passport Advantage Software

Virtualization Capacity License Counting Rules

IBM Power Systems (System p and System i) PowerVM Virtualization Environment

NOTE: Please use these rules in conjunction with the **<u>Sub-capacity licensing attachment</u>**



@business on demand software

July 1, 2008

Index

- Summary of Virtualization Capacity Licensing Requirements (page 3)
- ILMT License Counting Definitions, Scenarios, Rules (page 4-12)
 - Definitions (page 4-5)
 - Scenarios (page 6-11)
 - Dedicated LPAR (page 6)
 - Dynamic LPAR (page 7)
 - Single Shared Pool with Capped and Uncapped Partitions (page 8-9)
 - Micro-Partitioning (Fractional cores) with Single Shared Pool, Capped & Uncapped Partitions (page 10)
 - POWER6 Multiple Shared Pool with Capped and Uncapped Partitions (page 11)
 - Licensing Rules (page 12)
- Manual Calculation of Virtualization Capacity if allowed (page 13-15)
 - Eligibility Criteria & Requirements (page 13)
 - Rules (page 14)
 - Worksheet Example (page 15)
- Other
 - Key Web Links (page 16)
 - Special Notices (page 17)

Sub-capacity Licensing Requirements Summary

• Customers must:

- Agree to the terms of the Sub-capacity Attachment, and follow Virtualization Capacity License Counting rules for their Eligible Virtualization Environment(s)
- Use Eligible Sub-capacity Products, with sub-capacity part numbers
- Use Eligible Virtualization Technologies
- Use Eligible Processor Technologies
- Use the IBM License Metric Tool (ILMT) and maintain report documentation
 - Certain ILMT use exceptions may apply

PLEASE NOTE:

• The above is only a summary. For details about sub-capacity licensing requirements, see the Sub-capacity Attachment and other information referred to above, at **Passport Advantage Sub-capacity licensing information**

Customers are responsible for the installation of the IBM License Metric Tool and for the server it runs on.

Definitions

Dedicated partition (LPAR):

- Processors are always allocated in whole increments (no micro-partitioning)
- Resources are only moved between partitions "explicitly" (e.g. by an operator or a scheduled job)

Entitled Capacity (EC)

 The actual processor core capacity available to a partition. May be changed via DLPAR operation after startup. It is a unit of measure for shared processing capacity. One EC accomplishes approximately the same work as one dedicated processor core. Formerly referred to as PrU.

Virtual Processor (VP)

- Defines the maximum number of physical processor cores that the system can access simultaneously to provide the processing capacity of a shared processors partition
- The processing capacity of a partition is evenly distributed across the virtual processors

Online VP

- The actual VPs available to a partition. May be changed via DLPAR operation after startup.
- Shared pool:
 - Pool of processor cores shared by capped and uncapped partitions
 - System automatically moves processor core resources between partitions as needed
 - Processor cores are allocated in increments of 0.01 processor core

Definitions

Shared processors Partition (Also known as Micro-partition LPAR)

- A logical partition that utilizes processor resources from the shared processing pool using Micro-Partitioning technology are referred to as shared processor partitions.
- The processing unit assigned to a shared processors partition is known as processor entitlement, or entitled capacity. A shared processors partition can be defined as "capped" or "uncapped"
- The POWER Hypervisor automatically moves processor core resources among partitions based on each partition's entitled capacity, "capped or uncapped" attributes, and its load

• Capped partition:

 This type of shared processor partition can never be allocated processing capacity that is more than its Entitled Capacity

Uncapped partition:

- This type of shared processor partition can be allocated processing capacity that can exceed its Entitled Capacity. It can access the unused processor cores in the shared pool, when available, up to the Online VP value (VP).

• Micro-partitioning:


- The ability to divide a physical processor's computing power into fractions of a processing unit and share them among multiple logical partitions.
- To obtain the number of license entitlements the customer should acquire, add up the total number of cores per server then round up to the next whole number of processor cores (aggregate and round up, by server)
- Processor units are allocated in increments of 0.01 processor core


Multiple Shared Pools

 A POWER6 capability that allows the physical shared processor pool to be subdivided into multiple virtual pools. LPARs that are part of a shared pool are limited by the number of processor resources in that pool. There is only one level of pool nesting, the virtual shared pools are always a child to the physical shared processor pool. POWER5 systems only have the physical shared processor pool.

License Counting – Dedicated LPAR


- License entitlements required are based on processor core capacity available to the software in the partition
- For the example below:
 - WebSphere Application Server (WAS): PVUs for 10 cores need to be licensed
 - DB2 Enterprise Server Edition (DB2): PVUs for 4 cores need to be licensed





License Counting – Dynamic LPAR

- System i and System p provide the capability to dynamically move processor core resources between partitions
- Customer must acquire PVUs for the highest* number of processor core capacity available to the IBM software



License PVUs for: 10 WAS cores (consistent throughout) + 6 DB2 cores (from simulation peak)

* greater of a) what the partition starts with or b) the result of a DLPAR operation



License Counting – Single Shared Pool with Capped and Uncapped Partitions

Server with 12 processor cores

D	E
Capped	Uncapped
AIX	i5/OS
DB2	WAS
VP = 6	VP = 7
EC = 4.00	EC = 5.00

A i5/OS	B AIX	C Linux			Sha	red Po	ol (9 pr	ocesso	r cores)	
1	1	1	1	2	3	4	5	6	7	8	9

 DB2 cores to license: 4 from EC for capped partition D WAS cores to license: 7 from VP for uncapped 	 License Rules: For Capped Partitions: The highest* level of Entitled Capacity (EC); EC was formerly referred to as Processing Unit (PrU). For Uncapped Partitions: The highest* number of Online VP (Virtual Processors) Shared Pool: the lower of the sum of each partition for a product or the processor capacity of the shared pool
partition E	* The greater of what the partition starts with or the result of a DLPAR operation



License Counting – Single Shared Pool with Capped and Uncapped Partitions

Server with 12 processor cores

	D	E	F	G	Н
DB2 cores to license:	Capped	Capped	Capped	Uncapped	Uncapped
1 from dedicated partition B	i5/OS	AIX	Linux	i5/OS	AIX
4 from EC for capped partitions E			WAS	WAS	WAS
and F 3 from VP for uncapped partition H		DB2	DB2		DB2
8 total	VP = 1	VP = 4	VP = 4	VP = 7	VP = 3
	EC= 1.00	EC = 2.00	EC = 2.00	EC = 3.00	EC = 1.00

Α	В	С									
i5/OS	AIX	Linux			Sha	rod Po	ol (9 pr	ocesso	r coros	、	
	DB2				3114	ileu FU		066330	I COLES)	
1	1	1	1	2	3	4	5	6	7	8	9

WAS cores to license:

2 from EC for capped partition F 10 from VP for uncapped partitions G and H

12 total reduced to 9*

* maximum cores available in shared pool

License Rules:

- For Capped Partitions: The highest* level of Entitled Capacity (EC);
 - EC was formerly referred to as Processing Unit (PrU).
- For Uncapped Partitions: The highest* number of Online VP (Virtual Processors)
- Shared Pool: the lower of the sum of each partition for a product or the processor capacity of the shared pool
 - The greater of what the partition starts with or the result of a DLPAR operation



License Counting - <u>Micro-Partitioning (Fractional cores</u>) with Single Shared Pool, Capped & Uncapped Partitions

Server with 12 processor cores

	D	E	F	G	н
DB2 cores to license:	Capped	Capped	Capped	Uncapped	Uncapped
1.0 from dedicated partition B 2.9 from EC for capped partitions	i5/OS	AIX	Linux	i5/OS	AIX
E and F			WAS	WAS	WAS
3.0 from VP for uncapped partition H		DB2	DB2		DB2
6.9 rounded up to 7.0	VP = 3	VP = 4	VP = 4	VP = 7	VP = 3
7.0 total cores to license	EC = 2.10	EC = 1.60	EC = 1.30	EC = 3.00	EC = 1.00

Α	В	С									
i5/OS	AIX	Linux			Sha	ared Po	ol (9 pr	ocesso	r cores	`	
	DB2				She			066330	I COIES	,	
1	1	1	1	2	3	4	5	6	7	8	9

WAS cores to license:

1.3 from EC for capped partition F

10 for uncapped partitions G and H

11.3 total, rounded up to 12

Reduced to 9, maximum cores

available in shared pool

License Rules:

- For Capped Partitions: The highest* level of Entitled Capacity (EC)
 - EC was formerly referred to as PrU (Processing Units).
- For Uncapped Partitions: The highest* number of Online VP (Virtual Processor Cores)
- Shared Pool Capping Rule: the lower of the sum of each partition for a product or the processor core capacity of the shared pool
- Aggregate fractional processor cores, apply shared pool capping rules, and round up at the server level to the next whole processor core.

* The greater of what the partition starts with or the result of a DLPAR operation



License Counting – POWER6 <u>Multiple</u> <u>Shared Pool</u> with <u>Capped</u> and <u>Uncapped</u> <u>Partitions</u>

<u>Server</u>	with 12	with 12 processor cores			D		E			G		н		
DB2 co	res to li	cense:		Ca	pped	Cap	pped	Cappe	ed	Uncapped	U	ncapped		
		ated partition		i5	/OS	A	AIX		AIX Linux		inux i5/OS			AIX
• 1.7 from EC for capped partition E								WAS	•	WAS		WAS		
 3.0 from VP for uncapped partition H 5.7 rounded up to 6 						D	DB2					DB2		
				VF	P = 2	VP	VP = 4		4	VP = 7		VP = 3		
				EC= 1.80 EC= 1.7		EC = 2	.00	EC = 2.00	E	C = 1.00				
	Α	В	С	V	irtual S	hared po	ared pool #1 Virtual Shared pool #2							
	i5/OS	AIX	Linux		7 proc	essor cor	es	5 processor cores						
		DB2			P	hysica	I Share	d Pool (9 proc	essor c	ores)			
	1	1	1	1	2	3	4	5	6	7	8	9		

WebSphere cores to license:

- 2 from EC for capped partition F
- 7 from VP for uncapped partition G
- 3 from VP for uncapped partition H
- = **12 but reduced to** <u>5</u> (the size of the virtual shared pool #2)

License Rules:

- For Capped Partitions: The highest* level of Entitled Capacity (EC)
 - EC was formerly referred to as PrU (Processing Units).
- For Uncapped Partitions: The highest* number of Online VP (Virtual Processor Cores)
- Shared Pool Capping Rule: the lower of the sum of each partition for a product or the processor core capacity of the shared pool
- Aggregate fractional processor cores, apply shared pool capping rules, and round up at the server level to the next whole processor core.

11

^{*} The greater of what the partition starts with or the result of a DLPAR operation

IBM

ILMT Licensing Counting Rules – for Single Server Environments

License Rules for Partitions, Shared Pools, and Micro-partitioning for each product:

- for a Dedicated LPAR, the highest* number of cores allocated to the LPAR
- for a Capped Partition, the highest* amount of Entitled Capacity (EC)
- for a Uncapped Partitions, the highest* amount of VP (Virtual Processor Cores)
- for a Shared Processor Pool, the lower of the sum of each partition for a product or the processor core capacity of the shared pool
- Aggregate fractional processor cores, apply shared pool capping rules, and round up at the server level to the next whole processor core
 - (lower of the sum of the virtual cores or the server capacity)

* The greater of what the partition starts with or the result of a DLPAR operation

Manual Calculation of Virtualization Capacity

- <u>Eligibility Criteria</u>: Customers must use the IBM License Metric Tool, with the following exceptions
 - ILMT does not support the Eligible Virtualization Environment
 - Customer has fewer than 1000 employees and contractors Tool recommended
 - Customer server Full Capacity licensing for a PVU product is less than 1000 PVUs (on servers with an Eligible Virtualization Environment) - Tool recommended
- <u>Requirements</u>: For the above exceptions, customers must manually manage, track and prepare Audit Reports
 - A separate Audit Report must be prepared for each Eligible Sub-Capacity Product deployed for each Eligible Virtualization Environment
 - Which can be a Single Server or a Group of Servers "Cluster"
 - Audit Reports must be prepared as frequently as is required to maintain a history of increases to Virtualization Capacity and Full Capacity
 - Each Audit Report must be signed and date stamped, at least once per quarter

The above is only a summary. For detailed terms please see the Sub-capacity licensing attachment

13

Manual Calculation of Virtualization Capacity – Rules

For Single Server Environments:

License Rules for a partition, shared pools and micro-partitioning for each product:

- for a Dedicated LPAR, the highest* number of cores allocated to the LPAR
- for a Capped Partition, the highest* amount of Entitled Capacity (EC)
- for a Uncapped Partition, the highest* amount of Online VP (Virtual Processor Cores)

*The greater of what the partition starts with or the result of a DLPAR operation (in whole cores)

The PVU licensing requirement is based on the maximum number of virtual processor cores in the partitions available to a product (lower of the sum of the virtual cores or the server capacity)

If you want to use sub-capacity licensing for any other PowerVM technology, including shared processor pool, you must use the ILMT tool

VIRTUALIZATION ENVIRONMENT - SINGLE SERVER

Manual Calculation of Virtualization Capacity - Worksheet Example

Worksheet has 3 tabs; use the following tabs

- Instructions & Information
- Single Server

Web Link: Worksheet for Manual Calculation of Virtualization Capacity

- This worksheet is for one standalone serve	er for one Software Product
- Enter data for all input fields below (shaded	d area)
Product Name	IBM WEBSPHERE APPLICATION SERVER NETWORK DEPLOYMENT SUBCAPACITY PROCESSOR VALUE UNIT (PVU)
Part Number	D55VGLL
Date	Jul 31, 2008
Server ID / Location	Server ID # F6015; Bldg 1, Room 1, Somers, NY
Server Vendor / Brand	
Virtualization Technology used	· ·
Server Model	x3500
Processor Vendor / Brand	Intel Xeon Quad Core
PVUs per core (A)	
Total Activated Cores on Server	
Full Capacity PVUs for Server	
	DO NOT DELETE ROW
	Cores (B)
	per Partition
VM or Partition ID	or VM User Comments
	1
A	
B	2
U U	2
Sum of Virtual Cores	5
PVUs per core	50
Virtualization Capacity PVUs by Product for Server	250
PVU Licenses required by Product for Server (c)	250
(A) PVU's required for each physical core are listed on the PVU	table (see link below)
http://www-306.ibm.com/software/lotus/passportadvantage/pvi	u licensing for customers.html
(B) For purposes of 'Manual Calculation' of Virtual Capacity. 1 vi	irtual core (or CPU) is equivalent to 1 physical core. Enter values in whole cores.
(C) Lower of Full Capacity or Virtualization Capacity	
Instructions + Information Single Serve	r/ Group of Servers "Cluster" /

Key Web Links

PVU

- PVU table and other information
- Guide to identifying your processor

Sub-capacity

Passport Advantage Sub-capacity licensing Information

Virtualization Capacity License Counting Rules

Sub-capacity licensing attachment

Special Notices – Trademarks

The following terms are registered trademarks of International Business Machines Corporation in the United States and/or other countries: AIX, AIX/L, AIX/L(logo), AIX 6 (logo), AS/400, BladeCenter, DB2, Domino, e business(logo), e(logo)business, e(logo)server, i5/OS, IBM, IBM(logo), ibm.com, IBM Business Partner (logo), Informix, Lotus, Lotus Notes, MQSeries, Net.Data, Netfinity, Notes, NUMA-Q, OpenPower, Operating System/400, OS/400, PartnerWorld, Passport Advantage, POWERparallel, Power PC 603, Power PC 604, PowerPC, PowerPC (logo), pSeries, Rational, RISC System/6000, RS/6000, S/390, Sametime, Scalable POWERparallel Systems, SecureWay, System/390, Tivoli, Tivoli (logo), Tivoli Management Environment, Tivoli Ready(logo), WebSphere, xSeries, z/OS, zSeries.

The following terms are trademarks of International Business Machines Corporation in the United States and/or other countries: Advanced Micro-Partitioning, AIX 5L, AIX PVMe, AS/400e, Cloudscape, DB2 OLAP Server, DB2 Universal Database, DFDSM, DFSORT, DS4000, DS6000, DS8000, e-business(logo), ebusiness on demand, Enterprise Workload Manager, eServer, Express Middleware, Express Portfolio, Express Servers, HACMP, HACMP/6000, IBM TotalStorage Proven, IBMLink, Intelligent Miner, iSeries, Micro-Partitioning, NUMACenter, On Demand Business logo, POWER, PowerExecutive, Power Architecture, Power Everywhere, Power Family, Power PC, PowerPC Architecture, POWER3, POWER4, POWER4+, POWER5, POWER5+, POWER6, POWER6+, Quickr, Redbooks, Sequent (logo), SequentLINK, Service Director, SmoothStart, SP, System i, System i5, System p, System p5, System z, System z9, S/390 Parallel Enterprise Server, Tivoli Enterprise, TME 10, TotalStorage Proven, Virtualization Engine, Workload Partitions Manager, X-Architecture, z/Architecture, z/9.

A full list of U.S. trademarks owned by IBM may be found at: http://www.ibm.com/legal/copytrade.shtml.

The Power Architecture and Power.org wordmarks and the Power and Power.org logos and related marks are trademarks and service marks licensed by Power.org.

UNIX is a registered trademark of The Open Group in the United States, other countries or both.

Linux is a trademark of Linus Torvalds in the United States, other countries or both.

Microsoft, Windows, Windows NT and the Windows logo are registered trademarks of Microsoft Corporation in the United States, other countries or both. Intel, Itanium, Pentium are registered trademarks and Xeon is a trademark of Intel Corporation or its subsidiaries in the United States, other countries or both. AMD Opteron is a trademark of Advanced Micro Devices, Inc.

VMware is a registered trademark of VMware, Inc.

Java and all Java-based trademarks and logos are trademarks of Sun Microsystems, Inc. in the United States, other countries or both.

TPC-C and TPC-H are trademarks of the Transaction Performance Processing Council (TPPC).

SPECint, SPECfp, SPECjbb, SPECweb, SPECjAppServer, SPEC OMP, SPECviewperf, SPECapc, SPEChpc, SPECjvm, SPECmail, SPECimap and SPECsfs are trademarks of the Standard Performance Evaluation Corp (SPEC).

Cell Broadband Engine is a trademark of Sony Computer Entertainment Inc.

InfiniBand, InfiniBand Trade Association and the InfiniBand design marks are trademarks and/or service marks of the InfiniBand Trade Association. Other company, product and service names may be trademarks or service marks of others.

References in this publication to IBM products or services do not imply that IBM intends to make them available in all countries in which IBM operates. Offerings are subject to change, extension or withdrawal without notice. All statements regarding IBM future direction or intent are subject to change or withdrawal without notice and represent goals and objectives only.

Revised September 28, 2007

17