

IBM Software

Getting Started with IBM Backup and Restore Manager for z/VM

VMSES/E Installation, SFS Setup, and Initial Configuration

Tracy Dean, IBM tld1@us.ibm.com May 2009

© 2009 IBM Corporation



Important Disclaimer

- THE INFORMATION CONTAINED IN THIS PRESENTATION IS PROVIDED FOR INFORMATIONAL PURPOSES ONLY.
- WHILE EFFORTS WERE MADE TO VERIFY THE COMPLETENESS AND ACCURACY OF THE INFORMATION CONTAINED IN THIS PRESENTATION, IT IS PROVIDED "AS IS", WITHOUT WARRANTY OF ANY KIND, EXPRESS OR IMPLIED.
- IN ADDITION, THIS INFORMATION IS BASED ON IBM'S CURRENT PRODUCT PLANS AND STRATEGY, WHICH ARE SUBJECT TO CHANGE BY IBM WITHOUT NOTICE.
- IBM SHALL NOT BE RESPONSIBLE FOR ANY DAMAGES ARISING OUT OF THE USE OF, OR OTHERWISE RELATED TO, THIS PRESENTATION OR ANY OTHER DOCUMENTATION.
- NOTHING CONTAINED IN THIS PRESENTATION IS INTENDED TO, OR SHALL HAVE THE EFFECT OF:
 - CREATING ANY WARRANTY OR REPRESENTATION FROM IBM (OR ITS AFFILIATES OR ITS OR THEIR SUPPLIERS AND/OR LICENSORS); OR
 - ALTERING THE TERMS AND CONDITIONS OF THE APPLICABLE LICENSE AGREEMENT GOVERNING THE USE OF IBM SOFTWARE.



Agenda

- Assumptions
- Preparing to install
- Installing using VMSES/E
- Configuring
- Verifying installation and configuration



Assumptions

- DIRMAINT is installed for directory management
 - MAINT is authorized to issue AMDISK commands
 - AUTOG is available for group USER for minidisk definitions
- Shared File System is available
- Installation ID is 5697J06B
 - No PPF overrides
- 3390 DASD
- REXX Library (5695-014) is installed and available
 - Alternatively use free download of REXX Alternate Library at: http://www.ibm.com/software/awdtools/rexx/rexxzseries/altlibrary.html
- Installing from tape (not an envelope file)
- Installing on minidisk (not SFS)
- Operations Manager is running on user ID OPMGRM1
- This is not the only way to perform the install
 - Not all options are discussed
 - See product documentation for full details



IBM Software

Preparing to Install

Create installation ID Create an SFS server Prepare system for VMSES/E installation

© 2009 IBM Corporation



Where do I Start ???



In the Program Directory ??



In the Installation Guide ??



 Because we require SFS, we recommend you start with this presentation

May 2009

© 2009 IBM Corporation



Define the Installation ID: 5697J06B

From MAINT

- Create a file called 5697J06B DIRECT

USER 5697J06B password 64M 256M BG * 5697-J06 - SES install & admin for Backup Mgr V1.2 MACHINE ESA IPL CMS OPTION LNKNOPAS CONSOLE 01F 3215 SPOOL 00C 2540 READER A SPOOL 00D 2540 PUNCH A SPOOL 00E 1403 A LINK MAINT 190 190 RR LINK MAINT 19D 19D R LINK MAINT 19E 19E RR LINK MAINT 51D 51D MR LINK MAINT 555 5E5 RR

Issue the command

DIRM ADD 5697J06B

IBM	Software



Define the Installation ID: 5697J06B

Add required minidisks

– From MAINT, issue

DIRM FOR	5697J06B	AMD	191	3390	AUTOG	10	USEF	r MR
DIRM FOR	5697J06B	AMD	198	3390	AUTOG	2	USER	MR
DIRM FOR	5697J06B	AMD	199	3390	AUTOG	5	USER	MR
DIRM FOR	5697J06B	AMD	2A2	3390	AUTOG	1	USER	MR
DIRM FOR	5697J06B	AMD	2A6	3390	AUTOG	1	USER	MR
DIRM FOR	5697J06B	AMD	2B2	3390	AUTOG	5	USER	MR
DIRM FOR	5697J06B	AMD	2C2	3390	AUTOG	2	USER	MR
DIRM FOR	5697J06B	AMD	2D2	3390	AUTOG	20	USEF	r MR
DIRM FOR	5697J06B	AMD	491	3390	AUTOG	5	USER	MR
DIRM FOR	5697J06B	AMD	492	3390	AUTOG	5	USER	MR
DIRM FOR	5697J06B	AMD	49D	3390	AUTOG	5	USER	MR
DIRM FOR	5697J06B	AMD	591	3390	AUTOG	5	USER	MR
DIRM FOR	5697J06B	AMD	592	3390	AUTOG	5	USER	MR



Resulting Minidisk Statements in Directory Entry for 5697J06B

MDISK 0191	3390	<start></start>	010	<vol></vol>	MR	<readpw></readpw>	<writepw></writepw>	<multpw></multpw>
MDISK 0198	3390	<start></start>	002	<vol></vol>	MR	<readpw></readpw>	<writepw></writepw>	<multpw></multpw>
MDISK 0199	3390	<start></start>	005	<vol></vol>	MR	<readpw></readpw>	<writepw></writepw>	<multpw></multpw>
MDISK 02A2	3390	<start></start>	001	<vol></vol>	MR	<readpw></readpw>	<writepw></writepw>	<multpw></multpw>
MDISK 02A6	3390	<start></start>	001	<vol></vol>	MR	<readpw></readpw>	<writepw></writepw>	<multpw></multpw>
MDISK 02B2	3390	<start></start>	005	<vol></vol>	MR	<readpw></readpw>	<writepw></writepw>	<multpw></multpw>
MDISK 02C2	3390	<start></start>	002	<vol></vol>	MR	<readpw></readpw>	<writepw></writepw>	<multpw></multpw>
MDISK 02D2	3390	<start></start>	020	<vol></vol>	MR	<readpw></readpw>	<writepw></writepw>	<multpw></multpw>
MDISK 0491	3390	<start></start>	005	<vol></vol>	MR	<readpw></readpw>	<writepw></writepw>	<multpw></multpw>
MDISK 0492	3390	<start></start>	005	<vol></vol>	MR	<readpw></readpw>	<writepw></writepw>	<multpw></multpw>
MDISK 049D	3390	<start></start>	005	<vol></vol>	MR	<readpw></readpw>	<writepw></writepw>	<multpw></multpw>
MDISK 0591	3390	<start></start>	005	<vol></vol>	MR	<readpw></readpw>	<writepw></writepw>	<multpw></multpw>
MDISK 0592	3390	<start></start>	005	<vol></vol>	MR	<readpw></readpw>	<writepw></writepw>	<multpw></multpw>



Format All Minidisks

From MAINT, issue

link 5697J06B 191 333 MR

- format 333 z
- release z (det

Repeat for each 5697J06B disk



Create New SFS Server and File Pool

Background

- Backup catalog is stored in SFS
 - Separate file pool dedicated to Backup is recommended
 - Should not use VMSYS: or VMSYSU:
 - We'll use **BKRSFS:** here, with **BKRSVSFS** as the server
- Recommend starting with at least 3000 cylinders
 - Large sites will need more
 - Your mileage may vary

999998

- Need space for service machine work areas also
 - We'll use BKRSFS: for this also
- BKRSVSFS is a repository file pool server
 - Does not perform Coordinated Resource Recovery (CRR)
- Reference: "CMS File Pool Planning, Administration, and Operation" (SC24-6074)



Create New SFS Server: BKRSVSFS

- From MAINT, create and add directory entry for BKRSVSFS, using most of the sample values
 - Same procedure used to create user ID 5679J06B
 - Do not format the disks after you've added them

BKRSVSFS DIRECT

USER BKRSVSFS pas OPTION MAXCONN 20		4M BG APPLMON QUICKDSP SV	MSTAT
SHARE REL 1500			
MACHINE XC	Required	to use data spaces	
IUCV ALLOW			
IUCV *IDENT RESAN	Y GLOBAL		
IPL CMS			
CONSOLE 009 3215	T OPMGRM1	Make Ops Mgr the s	secondary console
SPOOL 00C 2540 RE	ADER *		
SPOOL 00D 2540 PU	NCH A		
SPOOL 00E 1403			
LINK MAINT 190 19	0 RR		
LINK MAINT 193 19	3 RR		
LINK MAINT 19D 191	d rr		
LINK MAINT 19E 19	E RR		



BKRSVSFS Directory Entry (continued)

From MAINT, issue

DIRM FOR BKRSVSFS AMD	191 3390	AUTOG	2 USER W	Work disk	
DIRM FOR BKRSVSFS AMD	250 3390	AUTOG	80 USER R	PW readpw wr	itepw Control disk
DIRM FOR BKRSVSFS MINI	IOPT 250	NOMDC			
DIRM FOR BKRSVSFS AMD	405 3390	AUTOG	10 USER R	PW readpw wr	Itepw Repository log
DIRM FOR BKRSVSFS AMD	406 3390	AUTOG	10 USER R	PW readpw wr	itepw disks
DIRM FOR BKRSVSFS MINI	IOPT 405	NOMDC			
DIRM FOR BKRSVSFS MINI	IOPT 406	NOMDC			
DIRM FOR BKRSVSFS AMD	260 3390	AUTOG	50 USER R	PW readpw wr	itepw Initial catalog disk
DIRM FOR BKRSVSFS AMD	310 3390	AUTOG	750 USER H	R PW readpw wi	ritepw
DIRM FOR BKRSVSFS AMD	311 3390	AUTOG	750 USER B	R PW readpw wi	ritepw User data
DIRM FOR BKRSVSFS AMD	312 3390	AUTOG	750 USER H	R PW readpw wi	ritepw disks
DIRM FOR BKRSVSFS AMD	313 3390	AUTOG	750 USER H	R PW readpw wi	ritepw



Initial SFS Server Setup: BKRSVSFS

Format 191 disk

- From BKRSVSFS, issue
 - format 191 a

Create a PROFILE EXEC on the 191 disk, containing

```
/* */
'ACCESS 193 C'
'CP SET EMSG ON'
Exit 0
```

Run the PROFILE

profile



Define Startup Parameters for SFS Server: BKRSVSFS

On BKRSVSFS 191 disk, create a file called BKRSVSFS DMSPARMS

ADMIN 5697J06B		
ADMIN BKRADMIN		
ADMIN BKRBKUP		
ADMIN BKRCATLG		
ADMIN BKRWRK01		
ADMIN BKRWRK02		
ADMIN BKRWRK03		
ADMIN BKRWRK04		
ADMIN xxxxxxx	Any other user IDs that will be Backup Manager	administrators
NOBACKUP		
FILEPOOLID BKRSF	'S	
NOCRR		
NOLUNAME		
SAVESEGID CMSFII	JES	
USERS 700		



Generate the File Pool BKRSFS

From BKRSVSFS, issue

fileserv generate

When prompted in \$\$TEMP \$POOLDEF, enter

MAXUSERS=4000	
MAXDISKS=500	
DDNAME=CONTROL	VDEV=250
DDNAME=LOG1	VDEV=405
DDNAME=LOG2	VDEV=406
DDNAME=MDK00001	VDEV=260 GROUP=1 BLOCKS=0
DDNAME=MDK00002	VDEV=310 GROUP=2 BLOCKS=0
DDNAME=MDK00003	VDEV=311 GROUP=2 BLOCKS=0
DDNAME=MDK00004	VDEV=312 GROUP=2 BLOCKS=0
DDNAME=MDK00005	VDEV=313 GROUP=2 BLOCKS=0

• Then file

16



Final SFS Server Tasks for BKRSVSFS

Start the server

- From BKRSVSFS,
 - Add the following at the end of PROFILE EXEC (before the Exit statement):
 - 'EXEC FILESERV START'
 - Save the changes and exit file
 - Run the PROFILE EXEC profile
 - Leave the server running disconnected #cp disc



Authorize Users and Create Directories in SFS

Authorize service machines to space in SFS

- From 5697J06B, issue

enroll user bkradmin bkrsfs (blocks 4000 storgroup 2 enroll user bkrbkup bkrsfs (blocks 4000 storgroup 2 enroll user bkrcatlg bkrsfs (blocks 500000 storgroup 2 enroll user bkrwrk01 bkrsfs (blocks 20000 storgroup 2 enroll user bkrwrk02 bkrsfs (blocks 20000 storgroup 2 enroll user bkrwrk03 bkrsfs (blocks 20000 storgroup 2 enroll user bkrwrk04 bkrsfs (blocks 20000 storgroup 2

Create required directory entries

- From 5697J06B, issue

create directory bkrsfs:bkradmin.workarea
create directory bkrsfs:bkrcatlg.workarea
create directory bkrsfs:bkrbkup.workarea
create directory bkrsfs:bkrwrk01.workarea
create directory bkrsfs:bkrwrk03.workarea
create directory bkrsfs:bkrwrk04.workarea



Authorize Users and Create Directories in SFS

- Authorize service machines to space in SFS
 - From 5697J06B, issue



- Create required directory entries
 - From 5697J06B, issue

create	directory	bkrsfs:bkradmin.workarea
create	directory	bkrsfs:bkrcatlg.workarea
create	directory	bkrsfs:bkrbkup.workarea
create	directory	bkrsfs:bkrwrk01.workarea
create	directory	bkrsfs:bkrwrk02.workarea
create	directory	bkrsfs:bkrwrk03.workarea
create	directory	bkrsfs:bkrwrk04.workarea



Take a Breath – New SFS Server is Set Up

If you've never set up SFS before, this is the hardest part of the product install



Prepare for VMSES/E Installation

From 5697J06B

- Mount installation tape at virtual address 181
- Link and access MAINT disks
 - link MAINT 5e5 5e5 rr
 - access 5e5 b
 - link MAINT 51d 51d mr
 - access 51d d
- Load product control files
 - vmfins install info (nomemo
- Obtain planning info
 - vmfins install ppf 5697J06B BKUPMGR (plan nomemo
- Review for errors

```
vmfview install
```



Create Directory Entries for All Required Users

- Use directory entry samples in 5697J06B PLANINFO
 - Located on 5697J06B 191 disk
- Follow steps outlined earlier for creating 5697J06B user ID to create directory entries for
 - BKRADMIN
 - BKRCATLG
 - BKRBKUP
 - BKRWRK01
 - BKRWRK02
 - BKRWRK03
 - BKRWRK04
- For all BKRWRKxx user ID's add to the directory entry:
 - LINK 5697J06B 199 199 RR
- If you plan to back up full volumes (INCLUDE RDEVICE or INCLUDE REDEVVOL), also add the following to the BKRWRKxx directory entries:
 - OPTION DEVMAINT
 - Privilege class A



Format All Minidisks

From 5697J06B, issue

link BKRADMIN 191 333 MR

- format 333 z
- release z (det
- Repeat for each disk

23



IBM Software

Installing using VMSES/E

© 2009 IBM Corporation



Initial VMSES/E Install

- From 5697J06B
 - Create and run a PROFILE EXEC

```
xedit profile exec a
===> input /**/
===> input 'ACC 5E5 B'
===> input 'ACCESS 51D D'
===> input 'CP SET PF12 RETRIEVE'
===> file
profile
```

- Installing from tape
 - Mount product tape at virtual address 181
 - Load the product code to disk and install
 - vmfins install ppf 5697J06B BKUPMGR (nomemo nolink
- Installing from an envelope
 - Unpack the VMARC file
 - vmarc unpk <envfilename> VMARC <envfilemode>
 - Load the product code to disk and install vmfins install ppf 5697J06B BKUPMGR (nomemo nolink env <envfilename>



Review for errors

vmfview install

– Update Build Status Table

vmfins build ppf 5697J06B BKUPMGR (serviced nolink

Review for errors

26

vmfview install




- Copy code from installation/test disk to production disk

```
acc 491 e
acc 591 f
vmfcopy * * e = = f (prodid 5697J06B%BKUPMGR olddate replace
acc 492 e
acc 592 f
vmfcopy * * e = = f (prodid 5697J06B%BKUPMGR olddate replace
```



Copy user code from installation disk to Y disk (MAINT 19E)



Copy help files from installation disk to system HELP disk (MAINT 19D)

```
link 5697j06b 49d 49d rr
acc 49d e
acc 19d f
vmfcopy * helpabkr e = = f2 (prodid 5697J06B%BKUPMGR olddate replace
vmfcopy abkr helpmenu e = = f2 (prodid 5697J06B%BKUPMGR olddate replace
```



- Rebuild CMS saved system (from code on 19E disk)

From MAINT

acc 193 m

sampnss cms

ipl 190 clear parm savesys cms

<hit ENTER>

29

- Rebuild CMS HELP logical saved segment (from files on MAINT 19D)

vmfbld ppf segbld esasegs segblist helpseg (all



Where Code is Installed for Configuration and Testing

Disk on 5697J06B	Description
2C2	Sample files
491, 591	Service machine executables for -BKRBKUP -BKRCATLG -BKRWRKxx
492, 592, MAINT 19E	End user and administrator executables
198	Configuration files
199	Backup job templates and DISKPOOL files
49D, MAINT 19D	Help files



VMSES/E Installation is Complete

- All code is installed from tape
- Standard install commands used by most z/VM products
- This was the easy part



IBM Software

Install All Available Service

© 2009 IBM Corporation



Install All Available PTFs (COR Service)

- Order/obtain all PTFs available for Backup Manager V1.2
- If each PTF is in tersed format (from IBMLINK), issue:

DETERSE <fn> <ft> <fm> <fn> SERVLINK A

If each PTF is in VMARC format, issue:

VMARC UNPK <fn> <ft> <fm> <fn> SERVLINK A

- Follow instructions in Chapter 7 of the Program Directory to install each PTF
 - In 7.2, suggest following steps in Appendix B for installation of all initial service, in case of errors
 - SERVICE EXEC can be used in future when installing just 1 PTF



IBM Software

Configuring



© 2009 IBM Corporation



Verify System Access Privileges for Backup Servers

User ID	Privileges Required and Recommended
BKRADMIN	 OPTION LNKNOPAS (or equivalent, such as RACF OPERATIONS) Privilege Class G Privilege Class B (for CP MSGNOH)
BKRBKUP	 OPTION LNKNOPAS (or equivalent, such as RACF OPERATIONS) Privilege Class G Privilege Class A (for CP FORCE) Privilege Class B (CP MSGNOH) Privilege Class D (CP PURGE)
BKRCATLG	 Privilege Class G Privilege Class B (CP MSGNOH) OPTION LNKNOPAS (or equivalent, such as RACF OPERATIONS) if backing up to disk
BKRWRKxx	 > OPTION LNKNOPAS (or equivalent, such as RACF OPERATIONS) > Privilege Class G > Privilege Class B (for CP MSGNOH) > Privilege Class A (if you plan to back up DASD volumes (vs minidisks)) > OPTION DEVINFO (if you have minidisks defined with DEVNO or &SYSRES options) > OPTION LNKSTABL (if you want to link disks in STABLE mode during a backup) > OPTION DEVMAINT (if you plan to back up DASD volumes (vs minidisks))



Create PROFILE EXECs for Test Service Machines

```
PROFILE EXEC for BKRADMIN
```

```
- From 5697J06B
  link bkradmin 191 291 mr
  acc 291 z
  acc 2c2 e
  copy admprof sampexec e profile exec z
  xedit profile exec z
    - Change
       SFS Pool = 'ROCKSFS1'
    – To
       SFS_Pool = 'BKRSFS'
    - Change
       'ACCESS' SFS Pool': BKRADMIN.CONFIGURATION B/B'
       'ACCESS' SFS Pool': BKRADMIN.RUNTIME C/C'
       ... and ...
       'ACCESS' SFS_Pool': BKRADMIN.JOBDEFS E'
     – To
       'ACCESS 198 B/B'
       'ACCESS 591 C/C'
       'ACCESS 199 E'
```

```
file
```



Create PROFILE EXECs for Test Service Machines

```
PROFILE EXEC for BKRCATLG
```

```
    From 5697J06B

  link bkrcatlg 191 292 mr
  acc 292 z
  acc 2c2 e
  copy catprof sampexec e profile exec z
  xedit profile exec z
     - Change
       SFS Pool = 'ROCKSFS1'
     – To
       SFS_Pool = 'BKRSFS'
     - Change
       'ACCESS' SFS Pool': BKRADMIN.CONFIGURATION B/B'
       'ACCESS' SFS Pool': BKRADMIN.RUNTIME C/C'
     – To
       'ACCESS 198 B/B'
       'ACCESS 591 C/C'
     - Change
       'ACCESS ROCKSFS2:RVBCATLG.WORKAREA D (FORCERW'
     – To
       'ACCESS .WORKAREA D (FORCERW'
```

file



Create PROFILE EXECs for Test Service Machines

```
PROFILE EXEC for BKRBKUP
```

```
- From 5697J06B
  link bkrbkup 191 293 mr
  acc 293 z
  acc 2c2 e
  copy mastprof sampexec e profile exec z
  xedit profile exec z
    - Change
       SFS Pool = 'ROCKSFS1'
    – To
       SFS_Pool = 'BKRSFS'
    - Change
       'ACCESS' SFS Pool': BKRADMIN.CONFIGURATION B/B'
       'ACCESS' SFS Pool': BKRADMIN.RUNTIME C/C'
       ... and ...
       'ACCESS' SFS_Pool':BKRADMIN.JOBDEFS E/E'
     – To
       'ACCESS 198 B/B'
       'ACCESS 591 C/C'
       'ACCESS 199 E/E'
```

file



Create PROFILE EXECs for Test Service Machines

```
PROFILE EXEC for BKRWRK01
```

```
- From 5697J06B
  link bkrwrk01 191 294 mr
  acc 294 z
  acc 2c2 e
  copy wrkprof sampexec e profile exec z
  xedit profile exec z
    - Change
       SFS Pool = 'ROCKSFS1'
    – To
       SFS_Pool = 'BKRSFS'
    - Change
       'ACCESS' SFS Pool': BKRADMIN.CONFIGURATION B/B'
       'ACCESS' SFS Pool': BKRADMIN.RUNTIME C/C'
    – To
       'ACCESS 198 B/B'
       'ACCESS 591 C/C'
       'ACCESS 199 E/E'
  File
```

Repeat for BKRWRK02, BKRWRK03, and BKRWRK04

- Or send the PROFILE EXEC to the other workers
- No changes needed for each worker



Define Special Users to Backup Manager

From 5697J06B

access 198 z

access 2c2 e

copy bkrusers namesamp e = names z

xedit bkrusers names z

- Authorize additional users as Administrators:
 - BKRBKUP
 - Others as required by your site
- Remove extra workers BKRWRK05 and BKRWRK06
 - Scroll to the right to make sure you removed all of BKRWRK06
- Copy BKRUSERS NAMES to a shared disk for user and server access
 - E.g. MAINT 19E (Y disk) or 5697J06B 592
 - Note: If you copy to MAINT 19E, copy as filemode number 2 and make a note to reload the CMS saved system again once all configuration is complete



Update the Configuration File: BKRSYSTM CONFIG

From 5697J06B

- access 198 z
- access 2c2 e
- copy bkrsystm confsamp e = config z
- xedit bkrsystm config z

41



Update the Configuration File: BKRSYSTM CONFIG

```
Choose local options for
```

Local_SVM_Contact = System Administrator - sysadmin@some.corp.com

- Contact name displayed on service machines
- Not used for automated e-mails or messages

```
Template_MDISK_Buffer_Pages = 512
```

Increase this value if you have more than 30,000 minidisks on the system

```
BKR_Allow_EDF_Target_Format = 0
```

Change to 1 if you want Backup Manager to format unformatted minidisks on restore

CatalogPool = RS54QA02

Change to BKRSFS

```
Workers_Reserved_For_Backup = 2
Workers_Reserved_For_Restore = 2
```

• Change both values to 0 (all workers can do backups and restores)



Update the Configuration File: BKRSYSTM CONFIG

Copy BKRSYSTM CONFIG to a shared disk

- E.g. MAINT 19E (Y disk) or 5697J06B 592
 - Note: If you copy to MAINT 19E, copy as filemode number 2 and make a note to reload the CMS saved system again once all configuration is complete



Complete SFS Configuration and Authorization

- Create backup catalog structure in SFS
 - From 5697J06B, issue

acc 591 c

setupcat

- Issue all SFS CREATE DIRECTORY commands displayed by SETUPCAT
 - Note: SETUPCAT will not issue the commands it displays. You must type in (cut 'n paste) each one and issue it. These are in addition to those you entered on Page 18.
- Give all users access to the catalog for restore requests
 - User access is limited to catalog directories for their own data
 - From 5697J06B, issue

enroll public bkrsfs:



Reload CMS Saved System if Needed

If you added code to MAINT 19E disk

- Verify the filemode number is 2 for each file
- Rebuild CMS saved system

• From MAINT

acc 193 m sampnss cms ipl 190 clear parm savesys cms <hit ENTER>

45



Create Backup Job to Test

Use a shipped sample template as a model

- From 5697J06B, issue

access 2c2 e access 199 z copy sampfull tempsamp e testfull template z xedit testfull template z

46



Customize the Backup Job: TESTFULL

Choose local options for

CONFIG BKR_JOB_WORKERS = 1

 Increase the number of workers based on the number of items to backup

CONFIG BKR_JOB_NAME = SAMPFULL

Change to TESTFULL

CONSOLE * Sample full backup generated

Change "Sample full" to indicate name of backup job TESTFULL

CP_QUIET SPOOL CONSOLE CLOSE NAME SAMPFULL \$\$SDATE\$\$

Change SAMPFULL to TESTFULL

Many other options available


- See job statements and comments in SAMPFULL TEMPSAMP



Customize the Backup Job: TESTFULL

Update INCLUDE and EXCLUDE statements

- Delete or replace the following entries for Linux guests



Delete the following entries

EXCLUDE	MINIDISK MAINT = 0123
EXCLUDE	MINIDISK MAINT = 0124
INCLUDE	MINIDISK MAINT = 012*
INCLUDE	SFS VMDEVU: * *

Change the following to reflect BKRSVSFS instead of SAMPSFS

EXCLUDE MINIDISK SAMPSFS* = * INCLUDE MINIDISK SAMPSFS* = 019*

Modify the following to exclude large minidisks

EXCLUDE MINIDISK * = * * * = * = * > 3300

FILE to save changes



Configuration is Complete

Now let's see if it actually works!







Start Backup Manager Service Machines

Start required Backup Manager servers

- From MAINT, issue

cp xautolog bkrcatlg

- cp xautolog bkrbkup
- Starting workers is recommended when product is first installed to verify configuration
 - From MAINT, issue

cp xautolog bkrwrk01

- Repeat for other workers
- Starting workers (BKRWRKxx) is not required in general
 - BKRBKUP will start them when needed

Verify servers are up and running

- From MAINT, issue

cp smsg bkrbkup status

- cp smsg bkrwrk01 status
- Repeat for other workers

Workers automatically logged off when idle timeout expires



Submit a Backup Job

Submit a job for review

- From BKRADMIN, issue

smsg bkrbkup review testfull

Review files returned to BKRADMIN's reader

- TESTFULL LINKFAIL
 - All errors linking to disks included in backup job
- TESTFULn JOB
 - One file for each backup worker assigned
 - All configuration statements with (most) variables resolved
 - All DUMPxxx statements for data that would be backed up
 - > xxx = CKD, EDF, SFS, FBA



Submit a Backup Job

Submit a job and perform real backup

– From BKRADMIN, issue

smsg bkrbkup submit testfull

- Review files returned to BKRADMIN's reader
- Review consoles of BKRWRKxx servers
 - Authorize BKRADMIN to view backup server consoles in Operations Manager
 - Use AUTH statement
 - See Chapter 5 of Operations Manager Administration Guide
 - From BKRADMIN, issue

GOMCMD OPMGRM1 VIEWCON USER(BKRWRKxx)



Backup and Restore Manager is Up and Running



- Major task is SFS setup
 - Especially if you aren't familiar with SFS
- VMSES/E install is straightforward
- Configuration is quick for initial testing
 - Use the defaults for most things
 - Give all options some thought before production use
- Use your in-house procedures to move it to production



References and More Information

Backup and Restore Manager for z/VM Web site

- http://www.ibm.com/software/stormgmt/zvm/backup
 - Publications
 - Pre-requisites
 - Announcements
 - Support
- e-mail: Tracy Dean, tld1@us.ibm.com

Publications

- CMS File Pool Planning, Administration, and Operation (SC24-6074)
- Directory Maintenance Facility Commands Reference (SC24-6133)
- Backup and Restore Manager for z/VM Program Directory (GI10-8662)
- Backup and Restore Manager for z/VM Administration Guide (SC18-9346)
- Backup and Restore Manager for z/VM User Guide (SC18-9523)